# **Table Of Contents**

| Table Of Contents     |  |
|-----------------------|--|
| nstall webmin         |  |
| Configure webmin      |  |
| How do I view webmin? |  |

Install webmin 2/4

# nixCraft: Linux Tips, Hacks, Tutorials, And Ideas In Blog Format <a href="http://www.cyberciti.biz/">http://www.cyberciti.biz/</a>

Home > Faq > FreeBSD

## FreeBSD Install and Configure Webmin Web-based Interface (Control Panel)

Posted by Vivek Gite <vivek@nixcraft.com>

Q. How do I install webmin control panel for my FreeBSD server?



A. Webmin is a web-based interface for system administration for Unix including FreeBSD. Using any browser that supports tables and forms, you can setup user accounts, Apache, DNS, file sharing, firewall and so on. Webmin consists of a simple web server, and a number of CGI programs which directly update system files like /etc/inetd.conf and /etc/master.passwd.

### Install webmin

To install webmin, update your ports, enter:

```
# portsnap fetch update
```

Install webmin from /usr/ports/sysutils/webmin, enter:

```
# cd /usr/ports/sysutils/webmin
```

# make install clean

#### Configure webmin

Now, webmin is installed. Start webmin on startup, enter:

```
# vi /etc/rc.conf
```

#### Append following line:

```
webmin_enable="YES"
```

Save and close the file. You need to run /usr/local/lib/webmin/setup.sh script in order to setup the various config files, enter:

```
# /usr/local/lib/webmin/setup.sh
```

#### Sample output:

Install webmin 3/4

```
Testing Perl ...
Perl seems to be installed ok
******
Operating system name: FreeBSD
Operating system version: 7.0
Webmin uses its own password protected web server to provide access
to the administration programs. The setup script needs to know :
 - What port to run the web server on. There must not be another
  web server already using this port.
 - The login name required to access the web server.
 - The password required to access the web server.
  If the webserver should use SSL (if your system supports it).
 - Whether to start webmin at boot time.
Web server port (default 10000): [Press Enter]
Login name (default admin): [Press Enter]
Login password: [type password]
Password again:
Use SSL (y/n): y
********************
Creating web server config files..
..done
Creating access control file..
..done
Creating start and stop scripts..
..done
Copying config files..
..done
Changing ownership and permissions ..
..done
Running postinstall scripts ..
..done
```

#### How do I view webmin?


Fire a webbrowser and enter url:

https://your-domain.com:10000/

OR

https://your-server-ip:10000/

You should see login html form as follows:



(Fig. 01: - Webmin in action under FreeBSD)

[2]

Install webmin 4/4

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our <u>daily email</u> newsletter or <u>weekly newsletter</u> to make sure you don't miss a single tip/tricks. Alternatively, subscribe via <u>RSS/XML</u> feed.

Article printed from Frequently Asked Questions About Linux / UNIX: http://www.cyberciti.biz/faq/

URL to article: http://www.cyberciti.biz/faq/freebsd-installing-webmin/

URLs in this post:

[1] Image: http://www.cyberciti.biz/faq/faq/category/freebsd/

[2] Image: http://www.cyberciti.biz/faq/wp-content/uploads/2008/07/freebsd-webmin-login-screen.png

Copyright © 2006-2010 <u>nixCraft</u>. All rights reserved. This print / pdf version is for personal non-commercial use only. More details <a href="http://www.cyberciti.biz/tips/copyright">http://www.cyberciti.biz/tips/copyright</a>.