Table Of Contents 1/3

## **Table Of Contents**

Table Of Contents	. 1
Create a firewall reset shell script	2


nixCraft: Linux Tips, Hacks, Tutorials, And Ideas In Blog Format <a href="http://www.cyberciti.biz/">http://www.cyberciti.biz/</a>

## Home > Faq > CentOS

## How To Reset Linux Firewall Automatically While Testing Configuration With Remote Server Over SSH Session

Posted by Vivek Gite <vivek@nixcraft.com>

Q. I'd like to tell my Linux iptables firewall to flush out the current configuration every 5 minutes. This will help when I'm testing a new rules and configuration options. Some time I find myself locked out of my own remote server. How do I reset Linux firewall automatically without issuing hard reboot?



A. You can easily flush out current configuration using iptables command and shell script combo. There is no built in option for this kind of settings. So you need to write a small shell script and call it from crontab file.

[1]

## Create a firewall reset shell script

Create a /root/reset.fw script:

```
#!/bin/bash
# reset.fw - Reset firewall
# set x to 0 - No reset
# set x to 1 - Reset firewall
# Added support for IPV6 Firewall
# Written by Vivek Gite <vivek@nixcraft.com>
# ------
# You can copy / paste / redistribute this script under GPL version 2.0 or above
# set to true if it is CentOS / RHEL / Fedora box
RHEL=false
### no need to edit below ###
IPT=/sbin/iptables
IPT6=/sbin/ip6tables
if [ "$x" == "1" ];
then
 if [ "$RHEL" == "true" ];
 then
       # reset firewall using redhat script
  /etc/init.d/iptables stop
  /etc/init.d/ip6tables stop
 else
  # for all other Linux distro use following rules to reset firewall
  ### reset ipv4 iptales ###
  $IPT -F
  $IPT -X
  $IPT -Z
  for table in $(</proc/net/ip_tables_names)</pre>
  $IPT -t $table -F
   $IPT -t $table -X
   $IPT -t $table -Z
  done
  $IPT -P INPUT ACCEPT
  $IPT -P OUTPUT ACCEPT
  $IPT -P FORWARD ACCEPT
```

```
### reset ipv6 iptales ###
   $IPT6 -F
   $IPT6 -X
   $IPT6 -Z
   for table in $(</proc/net/ip6_tables_names)</pre>
    $IPT6 -t $table -F
    $IPT6 -t $table -X
    $IPT6 -t $table -Z
   $IPT6 -P INPUT ACCEPT
   $IPT6 -P OUTPUT ACCEPT
   $IPT6 -P FORWARD ACCEPT
  fi
 else
 fi
4
Set permissions:
 # chmod +x /root/reset.fw
Create <u>cronjon to reset</u> [2] current configuration every 5 minutes, enter
 # crontab -e
```

OR

```
# vi /etc/crontab
```

```
Append following settings:
```

```
*/5 * * * * root /root/reset.fw >/dev/null 2>&1
```

Please remember to **set x to 0** once a working configuration has been created for your Linux system.

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our <u>daily email</u> newsletter or <u>weekly newsletter</u> to make sure you don't miss a single tip/tricks. Alternatively, subscribe via <u>RSS/XML</u> feed.

Article printed from Frequently Asked Questions About Linux / UNIX: http://www.cyberciti.biz/faq/

URL to article: http://www.cyberciti.biz/faq/linux-iptables-firewall-flushout-configuration-every-5minutes/URLs in this post:

- [1] Image: http://www.cyberciti.biz/faq/faq/category/iptables/
- [2] cronjon to reset: http://www.cyberciti.biz/faq/how-do-i-add-jobs-to-cron-under-linux-or-unix-oses/

Copyright © 2006-2010 <u>nixCraft</u>. All rights reserved. This print / pdf version is for personal non-commercial use only. More details <a href="http://www.cyberciti.biz/tips/copyright">http://www.cyberciti.biz/tips/copyright</a>.