Table Of Contents 1/3

# **Table Of Contents**

Table Of Contents	1
Rpm based distro - Red Hat/CentOS/Fedora Core/Suse Linux	2
deb based distro - Debian or Ubuntu Linux	2

nixCraft: Linux Tips, Hacks, Tutorials, And Ideas In Blog Format <a href="http://www.cyberciti.biz/">http://www.cyberciti.biz/</a>

Home > Faq > Debian / Ubuntu

### How to: Linux delete or remove kernel

Posted by Vivek Gite <vivek@nixcraft.com>

Q. I have multiple versions installed and I need to save disk space. I am using Cent OS Linux. How can I delete or remove a Linux kernel from my Linux distribution?

A. Linux Kernel and related files are stored in following locations:

- => /boot Stores actual kernel and related file such system man and initrd images,
- => /etc or /boot/grub Stores grub.conf file (most distro use /boot/grub these days).
- => /iib/modules/KERNEL-VERSION/\* Linux device drivers (modules)



[1]

If kernel is installed using binary package system such as rpm, yum, up2date, apt-get etc you can remove with following commands:

# Rpm based distro - Red Hat/CentOS/Fedora Core/Suse Linux

First find out all installed kernel version with following command:

```
# rpm -qa | grep kernel-smp
```

or

```
# rpm -qa | grep kernel
```

#### Output:

```
kernel-smp-2.6.9-42.EL
kernel-smp-2.6.9-42.0.3.EL
kernel-smp-2.6.9-42.0.8.EL
```

I've total 3 different kernel installed. To remove kernel-smp-2.6.9-42.EL type command:

```
# rpm -e kernel-smp-2.6.9-42.EL
```

OR

```
# rpm -vv -e kernel-smp-2.6.9-42.EL
```

## .deb based distro - Debian or Ubuntu Linux

Again find out all installed kernel version:

```
$ dpkg --list | grep kernel-image
```

#### Output:

```
ii kernel-image-2.4.27-2-386 2.4.27-10sarge1 Linux kernel image for version kernel-image-2.6.8-2-686 2.6.8-16sarge1 Linux kernel image for version
```

Now remove kernel-image-2.4.27-2-386 with apt-get command itself:

```
# apt-get remove kernel-image-2.4.27-2-386
```

OR

\$ sudo apt-get remove kernel-image-2.4.27-2-386

If you have custom compiled kernel you need to remove following files/dirs:

- /boot/vmlinuz\*KERNEL-VERSION\*
- /boot/initrd\*KERNEL-VERSION\*
- /boot/System-map\*KERNEL-VERSION\*
- /boot/config-\*KERNEL-VERSION\*
- /lib/modules/\*KERNEL-VERSION\*/
- Update grub configuration file /etc/grub.conf or /boot/grub/menu.lst to point to correct kernel version.

Caution: Removing working kernel may result into unstable / non- bootable Linux server system.

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our <u>daily email</u> newsletter or <u>weekly newsletter</u> to make sure you don't miss a single tip/tricks. Alternatively, subscribe via <u>RSS/XML</u> feed.

Article printed from Frequently Asked Questions About Linux / UNIX: http://www.cyberciti.biz/faq/

URL to article: http://www.cyberciti.biz/faq/debian-redhat-linux-delete-kernel-command/

URLs in this post:

[1] Image: http://www.cyberciti.biz/faq/faq/category/linux/

Copyright © 2006-2010 <u>nixCraft</u>. All rights reserved. This print / pdf version is for personal non-commercial use only. More details <a href="http://www.cyberciti.biz/tips/copyright">http://www.cyberciti.biz/tips/copyright</a>.