# **Building the Cross-Compilation Toolchain**

Piptor F

To compile software for the Raspberry Pi, you need a cross-compilation toolchain. It's a collection of files and programs that you can run on your computer, and that produce a binary that can be executed on the Raspberry Pi.

### Docker

I don't like to do a lot of installations on my main Linux box, so I build most of it inside of a Docker container. This has the added benefit that all builds are reproducible, and it's easy to undo the previous step or even start from scratch.

#### Installation

You need Docker and Docker Compose to build the toolchain. You can find detailed installation instructions here:

- <u>DigitalOcean How to Install and Use Docker</u>
- <u>DigitalOcean How to Install Docker Compose</u>

#### **Dockefiles**

The actual Dockerfiles are on my GitHub, I'll briefly go over them on this page

https://github.com/tttapa/RPi-Cpp-Toolchain/tree/master/toolchain/docker

## Crosstool-NG

The toolchain is built using Crosstool-NG

It is installed in a CentOS 7 Docker container, because CentOS 7 was the oldest OS that I had to run the toolchain on. In this context, oldest refers to the Linux kernel version and the glibc version. They are backwards compatible, so you can run software compiled for an old version on a computer with a newer version, but you can't run software compiled for a new version on a computer with an older version.

The following Dockerfile downloads, builds and installs Crosstool-NG to the ~/.local directory of the container.

```
FROM centos:7 as ct-ng
        Install dependencies to build toolchain
      RUN yum -y update && '
            yum install -y epel-release && \
yum install -y autoconf gperf bison file flex texinfo help2man gcc-c++ \
libtool make patch ncurses-devel python36-devel perl-Thread-Queue bzip2 \
 6
 8
            git wget which xz unzip && \
            vum clean all
     # Add a user called `develop` and add him to the sudo group
RUN useradd -m develop && echo "develop:develop" | chpasswd && usermod -aG wheel develop
14
15
      USER develop
      WORKDIR /home/develop
17
18
      ENV CT_NG_VERSION=1.24.0
      RUN git clone -b crosstool-ng-${CT_NG_VERSION} --single-branch --depth 1 \
https://github.com/crosstool-ng/crosstool-ng.git
20
21
      WORKDIR /home/develop/crosstool-ng
      RUN ./bootstrap && \
./configure --prefix=/home/develop/.local && \
23
24
            make -j$(($(nproc) * 2)) &&
           make install && \
cd && rm -rf crosstool-ng
      ENV PATH=/home/develop/.local/bin:$PATH
```

The list of dependencies can be found on Crosstool-NG's GitHub: <a href="https://github.com/crosstool-ng/crosstool-ng/blob/master/testing/docker/centos7/Dockerfile">https://github.com/crosstool-ng/crosstool-ng/crosstool-ng/blob/master/testing/docker/centos7/Dockerfile</a>

## Raspberry Pi 3B+ 64-bit Cross-Compilation Toolchain

The following Dockerfile builds the toolchain for a Raspberry Pi 3B+ running a 64-bit operating system.

```
FROM crosstool-ng:v1 as aarch64-toolchain

WORKDIR /home/develop
RUN mkdir /home/develop/RPi3
WORKDIR /home/develop/RPi3
RUN ct-ng aarch64-rpi3-linux-gnu
RUN sed -i 's/CT_GCC_VERSION=\"[0-9.]*\"/CT_GCC_VERSION="9.1.0"/g' .config && \
sed -i 's/CT_LINUX_VERSION=\"[0-9.]*\"/CT_LINUX_VERSION="4.15"/g' .config && \
sed -i 's/CT_GLIBC_VERSION=\"[0-9.]*\"/CT_GLIBC_VERSION="2.27"/g' .config
RUN ct-ng build && rm -rf .build

ENV TOOLCHAIN_PATH=/home/develop/x-tools/aarch64-rpi3-linux-gnu
ENV PATH=${TOOLCHAIN_PATH}/bin:$PATH
WORKDIR /home/develop
```

The configuration is based on the <a href="mailto:aarch64-rpi3-linux-gnu">aarch64-rpi3-linux-gnu</a> sample that comes with Crosstool-NG: <a href="https://github.com/crosstool-ng/tree/master/samples/aarch64-rpi3-linux-gnu">https://github.com/crosstool-ng/tree/master/samples/aarch64-rpi3-linux-gnu</a>

I changed the GCC version to the latest stable one, and the Linux kernel and glibc versions to match the versions that the Ubuntu Server 18.04 image ships with.

The build took around 25 minutes on a 2018 Dell XPS i7-8750H, and 45 minutes on a 2017 Dell XPS i7-7700HQ.

# Raspberry Pi 3B+ 32-bit Cross-Compilation Toolchain

Even though the Raspberry Pi 3B+ has a 64-bit ARMv8/AArch64 CPU, at the time of writing, the Raspbian distribution is still only 32 bits. To be able to cross-compile software for this platform, you'll need a 32-bit cross-compiler.

```
FROM crosstool-ng:v1 as aarch32-toolchain

WORKDIR /home/develop
RUN sed -i 's/CT_ARCH_FPU=\"neon-vfpv4\"/CT_ARCH_FPU="neon-fp-armv8"/g' \
.local/share/crosstool-ng/samples/armv8-rpi3-linux-gnueabihf/crosstool.config
RUN mkdir /home/develop/RPi3
RUN ct-ng armv8-rpi3-linux-gnueabihf
RUN sed -i 's/CT_GCC_VERSION=\"[0-9.]*\"/CT_GCC_VERSION="9.1.0"/g' .config && \
sed -i 's/CT_LINUX_VERSION=\"[0-9.]*\"/CT_LINUX_VERSION="4.14"/g' .config && \
sed -i 's/CT_GLIBC_VERSION=\"[0-9.]*\"/CT_GLIBC_VERSION="2.24"/g' .config
RUN ct-ng build && rm -rf .build

ENV TOOLCHAIN_PATH=/home/develop/x-tools/armv8-rpi3-linux-gnueabihf
ENV PATH=${TOOLCHAIN_PATH}/bin:$PATH
WORKDIR /home/develop
```

The configuration is based on the armv8-rpi3-linux-gnueabihf sample that comes with Crosstool-NG: <a href="https://github.com/crosstool-ng/crosstool-ng/tree/master/samples/armv8-rpi3-linux-gnueabihf">https://github.com/crosstool-ng/crosstool-ng/crosstool-ng/tree/master/samples/armv8-rpi3-linux-gnueabihf</a>

I changed the GCC version to the latest stable one, and the Linux kernel and glibc versions to match the versions that the Raspbian Stretch image ships with.

Even though the CPU will be running in 32-bit mode, you can still use the ARMv8 NEON instructions, so I changed the compiler's default FPU flag to neon-fp-armv8. I haven't tested if it actually makes any difference.

The build took around 25 minutes on a 2018 Dell XPS i7-8750H, and 45 minutes on a 2017 Dell XPS i7-7700HQ.