# The X Keyboard Extension: Library Specification

Amber J. Benson
Gary Aitken
Erik Fortune, Silicon Graphics, Inc
Donna Converse, X Consortium, Inc
George Sachs, Hewlett-Packard Company
Will Walker, Digital Equipment Corporation

#### The X Keyboard Extension:: Library Specification

by Amber J. Benson, Gary Aitken, Erik Fortune, Donna Converse, George Sachs, and Will Walker

X Version 11, Release 7.7

Copyright © 1995, 1996 X Consortium Inc., Silicon Graphics Inc., Hewlett-Packard Company, Digital Equipment Corporation

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE X CONSORTIUM BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Except as contained in this notice, the names of the X Consortium, Silicon Graphics Inc., Hewlett-Packard Company, and Digital Equipment Corporation shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization.

# **Table of Contents**

Acknowledgement	
1. Overview	
Core X Protocol Support for Keyboards	
Xkb Keyboard Extension Support for Keyboards	
Xkb Extension Components	
Groups and Shift Levels	
Radio Groups	3
Client Types	3
Compatibility With the Core Protocol	
Additional Protocol Errors	4
Extension Library Functions	4
Error Indications	4
2. Initialization and General Programming Information	6
Extension Header Files	6
Extension Name	
Determining Library Compatibility	
Initializing the Keyboard Extension	
Disabling the Keyboard Extension	
Protocol Errors	
Display and Device Specifications in Function Calls	
3. Data Structures	
Allocating Xkb Data Structures	
Adding Data and Editing Data Structures	
Making Changes to the Server's Keyboard Description	
Tracking Keyboard Changes in the Server	
Freeing Data Structures	
4. Xkb Events	
Xkb Event Types	
Xkb Event Data Structures	
Selecting Xkb Events	
Event Masks	
Unified Xkb Event Type	
5. Keyboard State	
Keyboard State Description	
Changing the Keyboard State	
Changing Modifiers	
Changing Groups  Determining Keyboard State	
Tracking Keyboard State	
6. Complete Keyboard Description	
The XkbDescRec Structure	
Obtaining a Keyboard Description from the Server	
Tracking Changes to the Keyboard Description in the Server	
Allocating and Freeing a Keyboard Description	
7. Virtual Modifiers	
Virtual Modifier Names and Masks	
Modifier Definitions	
Binding Virtual Modifiers to Real Modifiers	
Virtual Modifier Key Mapping	
Inactive Modifier Sets	
Conventions	32

Example	32
8. Indicators	34
Indicator Names	34
Indicator Data Structures	34
XkbIndicatorRec	34
XkbIndicatorMapRec	35
Getting Information About Indicators	40
Getting Indicator State	40
Getting Indicator Information by Index	
Getting Indicator Information by Name	
Changing Indicator Maps and State	
Effects of Explicit Changes on Indicators	
Changing Indicator Maps by Index	
Changing Indicator Maps by Name	
The XkbIndicatorChangesRec Structure	
Tracking Changes to Indicator State or Map	
Allocating and Freeing Indicator Maps	
9. Bells	
Bell Names	
Audible Bells	
Bell Functions	
Generating Named Bells	
Generating Named Bell Events	
Forcing a Server-Generated Bell	
Detecting Bells	
10. Keyboard Controls	
Controls that Enable and Disable Other Controls	
The EnabledControls Control	
The AutoReset Control	
Control for Bell Behavior	57
The AudibleBell Control	58
Controls for Repeat Key Behavior	58
The PerKeyRepeat Control	58
The RepeatKeys Control	58
The DetectableAutorepeat Control	. 59
Controls for Keyboard Overlays (Overlay1 and Overlay2 Controls)	60
Controls for Using the Mouse from the Keyboard	
The MouseKeys Control	
The MouseKeysAccel Control	
Controls for Better Keyboard Access by Physically Impaired Persons	
The AccessXKeys Control	
The AccessXTimeout Control	
The AccessXFeedback Control	
AccessXNotify Events	
StickyKeys, RepeatKeys, and MouseKeys Events	
The SlowKeys Control	
The BounceKeys Control	
The StickyKeys Control	
Controls for General Keyboard Mapping	
• • • •	
The GroupsWrap Control	
The IgnoreLockMods Control	
The IgnoreGroupLock Control	
The InternalMods Control	
The XkbControlsRec Structure	1:

	. 76
Querying Controls	
Changing Controls	
The XkbControlsChangesRec Structure	
Tracking Changes to Keyboard Controls	
Allocating and Freeing an XkbControlsRec	
The Miscellaneous Per-client Controls	
11. X Library Controls	
Controls Affecting Keycode-to-String Translation	85
ForceLatin1Lookup	85
ConsumeLookupMods	
AlwaysConsumeShiftAndLock	
Controls Affecting Compose Processing	86
ConsumeKeysOnComposeFail	. 86
ComposeLED	. 87
BeepOnComposeFail	. 87
Controls Effecting Event Delivery	87
IgnoreNewKeyboards	87
Manipulating the Library Controls	. 87
Determining Which Library Controls are Implemented	. 88
Determining the State of the Library Controls	. 88
Changing the State of the Library Controls	88
12. Interpreting Key Events	. 90
Effects of Xkb on the Core X Library	. 90
Effects of Xkb on Event State	. 90
Effects of Xkb on MappingNotify Events	90
X Library Functions Affected by Xkb	90
Xkb Event and Keymap Functions	. 91
13. Keyboard Geometry	. 95
Shapes and Outlines	. 97
Sections	. 98
Rows and Keys	99
Doodads	. 99
Overlay Rows and Overlay Keys	
Drawing a Keyboard Representation	
Geometry Data Structures	100
DoodadRec Structures	107
Getting Keyboard Geometry From the Server	108
Using Keyboard Geometry	
Adding Elements to a Keyboard Geometry	110
Allocating and Freeing Geometry Components	114
14. Xkb Keyboard Mapping	122
Notation and Terminology	122
Core Implementation	123
Xkb Implementation	123
Getting Map Components from the Server	124
Changing Map Components in the Server	
The XkbMapChangesRec Structure	
Tracking Changes to Map Components	
Allocating and Freeing Client and Server Maps	130
Allocating an Empty Client Map	
Freeing a Client Map	
Allocating an Empty Server Map	131
Freeing a Server Map	132

15. Xkb Client Keyboard Mapping	133
The XkbClientMapRec Structure	
Key Types	135
The Canonical Key Types	137
Getting Key Types from the Server	
Changing the Number of Levels in a Key Type	
Copying Key Types	
Key Symbol Map	
Per-Key Key Type Indices	
Per-Key Group Information	
Key Width	
Offset in to the Symbol Map	
Getting the Symbol Map for Keys from the Server	
Changing the Number of Groups and Types Bound to a Key	
Changing the Number of Symbols Bound to a Key	
The Per-Key Modifier Map	
Getting the Per-Key Modifier Map from the Server	
16. Xkb Server Keyboard Mapping	
Key Actions	
The XkbAction Structure	
The XkbAnyAction Structure	
Actions for Changing Modifiers' State	
Actions for Changing Group State	
Actions for Moving the Pointer	
Actions for Simulating Pointer Button Press and Release	
Actions for Changing the Pointer Button Simulated	
Actions for Locking Modifiers and Group	
Actions for Changing the Active Screen	
Actions for Changing Boolean Controls State	
Actions for Generating Messages	
Actions for Generating a Different Keycode	
Actions for Generating DeviceButtonPress and DeviceButtonRelease	
Actions for Simulating Events from Device Valuators	
Obtaining Key Actions for Keys from the Server	
Changing the Number of Actions Bound to a Key	
Key Behavior	
Radio Groups	
The XkbBehavior Structure	
Obtaining Key Behaviors for Keys from the Server	
Explicit Components—Avoiding Automatic Remapping by the Server	
Obtaining Explicit Components for Keys from the Server	
Virtual Modifier Mapping	
Obtaining Virtual Modifier Bindings from the Server	
Obtaining Per-Key Virtual Modifier Mappings from the Server	
17. The Xkb Compatibility Map	
The XkbCompatMap Structure	
Xkb State to Core Protocol State Transformation	
Core Keyboard Mapping to Xkb Keyboard Mapping Transformation	
Xkb Keyboard Mapping to Core Keyboard Mapping Transformations	
Getting Compatibility Map Components From the Server	
Using the Compatibility Map	
Changing the Server's Compatibility Map	
Tracking Changes to the Compatibility Map	
Allocating and Freeing the Compatibility Map	191

#### The X Keyboard Extension:

18. Symbolic Names	193
The XkbNamesRec Structure	193
Symbolic Names Masks	. 195
Getting Symbolic Names From the Server	. 196
Changing Symbolic Names on the Server	. 197
	. 197
Tracking Name Changes	198
Allocating and Freeing Symbolic Names	. 200
19. Replacing a Keyboard "On the Fly"	. 201
20. Server Database of Keyboard Components	. 204
Component Names	205
Listing the Known Keyboard Components	205
Component Hints	207
Building a Keyboard Description Using the Server Database	207
21. Attaching Xkb Actions to X Input Extension Devices	214
XkbDeviceInfoRec	215
Querying Xkb Features for Non-KeyClass Input Extension Devices	217
Allocating, Initializing, and Freeing the XkbDeviceInfoRec Structure	. 219
Setting Xkb Features for Non-KeyClass Input Extension Devices	221
XkbExtensionDeviceNotify Event	. 223
Tracking Changes to Extension Devices	. 224
22. Debugging Aids	226
Glossary	228
Index	. 235

# **List of Figures**

1.1. Overall Xkb Structure	2
5.1. Xkb State	19
10.1. MouseKeys Acceleration	63
13.1. Rotated Keyboard Sections	95
13.2. Keyboard with Four Sections	97
13.3. Rows in a Section	98
13.4. Xkb Geometry Data Structures	101
13.5. Xkb Geometry Data Structures (Doodads)	102
13.6. Xkb Geometry Data Structures (Overlays)	103
13.7. Key Surface, Shape Outlines, and Bounding Box	109
14.1. Shift Levels and Groups	123
15.1. Xkb Client Map	
16.1. Server Map Relationships	149
16.2. Virtual Modifier Relationships	
17.1. Server Interaction with Types of Clients	179
17.2. Server Derivation of State and Keyboard Mapping Components	
17.3. Xkb Compatibility Data Structures	182
20.1. Building a New Keyboard Description from the Server Database	211

#### **List of Tables**

1.1. Function Error Returns Due to Extension Problems	5
2.1. Xkb Protocol Errors	
2.2. BadKeyboard Protocol Error resource_id Values	9
4.1. Xkb Event Types	
4.2. XkbSelectEvents Mask Constants	18
5.1. Real Modifier Masks	. 22
5.2. Symbolic Group Names	
5.3. XkbStateNotify Event Detail Masks	. 25
6.1. XkbDescRec Component References	. 27
6.2. Mask Bits for XkbDescRec	
8.1. XkbIndicatorMapRec flags Field	35
8.2. XkbIndicatorMapRec which_groups and groups, Keyboard Drives Indicator	. 37
8.3. XkbIndicatorMapRec which_groups and groups, Indicator Drives Keyboard	. 37
8.4. XkbIndicatorMapRec which_mods and mods, Keyboard Drives Indicator	. 39
8.5. XkbIndicatorMapRec which_mods and mods, Indicator Drives Keyboard	. 39
9.1. Predefined Bells	. 49
9.2. Bell Sounding and Bell Event Generating	. 50
10.1. Xkb Keyboard Controls	. 55
10.2. MouseKeysAccel Fields	61
10.3. AccessXFeedback Masks	. 66
10.4. AccessXNotify Events	. 67
10.5. AccessXNotify Event Details	
10.6. Xkb Controls	
10.7. Controls Mask Bits	. 76
10.8. GroupsWrap options (groups_wrap field)	. 77
10.9. Access X Enable/Disable Bits (ax_options field)	
11.1. Library Control Masks	
13.1. Doodad Types	
14.1. Xkb Mapping Component Masks and Convenience Functions	
14.2. XkbMapChangesRec Masks	
14.3. XkbAllocClientMap Masks	
14.4. XkbAllocServerMap Masks	
15.1. Example Key Type	
15.2. group_info Range Normalization	
15.3. Group Index Constants	
16.1. Action Types	
16.2. Modifier Action Types	
16.3. Modifier Action Flags	
16.4. Group Action Types	
16.5. Group Action Flags	
16.6. Pointer Action Types	
16.7. Pointer Button Action Types	
16.8. Pointer Button Action Flags	
16.9. Pointer Default Flags	
16.10. ISO Action Flags when XkbSA_ISODfltIsGroup is Set	
16.11. ISO Action Flags when XkbSA_ISODfltIsGroup is Not Set	
16.12. ISO Action Affect Field Values	
16.13. Switch Screen Action Flags	
16.14. Controls Action Types	
16.15. Control Action Flags	
16.16. Message Action Flags	

#### The X Keyboard Extension:

16.17. Device Button Action Types	170
16.18. Device Button Action Flags	170
16.19. Device Valuator v <n>_what High Bits Values</n>	171
16.20. Key Behaviors	174
16.21. Explicit Component Masks	175
17.1. Symbol Interpretation Match Criteria	
17.2. Compatibility Map Component Masks	187
18.1. Symbolic Names Masks	
18.2. XkbNameChanges Fields	198
19.1. XkbNewKeyboardNotifyEvent Details	202
20.1. Server Database Keyboard Components	204
20.2. XkbComponentNameRec Flags Bits	
20.3. Want and Need Mask Bits and Required Names Components	
20.4. XkbDescRec Components Returned for Values of Want & Needs	
21.1. XkbDeviceInfoRec Mask Bits	
22.1. Debug Control Masks	

# **Acknowledgement**

This document is the result of a great deal of hard work by a great many people. Without Erik Fortune's work as Architect of the X Keyboard Extension and the longtime support of Silicon Graphics Inc. there would not be a keyboard extension.

We gratefully thank Will Walker and George Sachs for their help and expertise in providing some of the content for this document, and Digital Equipment Corporation and Hewlett-Packard for allowing them to participate in this project, and we are deeply indebted to IBM for providing the funding to complete this library specification.

Most of all, we thank Gary Aitken and Amber J. Benson for their long hours and late nights as ultimate authors of this specification, and for serving as authors, document editors, and XKB protocol and implementation reviewers. Their commitment to accuracy and completeness, their attention to detail, their keen insight, and their good natures when working under tremendous pressure are in some measure responsible not only for the quality of this document, but for the quality of the Keyboard extension itself.

Matt Landau Manager, X Window System X Consortium Inc.

#### X Version 11, Release 7 addendum

This document is made available to you in modern formats such as HTML and PDF thanks to the efforts of Matt Dew, who converted the original troff sources to DocBook/XML and edited them into shape; Fernando Carrijo, who converted the images to SVG format; Gaetan Nadon, who set up the formatting machinery in the libX11 builds and performed further editing of the DocBook markup; and Alan Coopersmith, who converted the DocBook tags to semantic markup and cleaned up other formatting issues.

# Chapter 1. Overview

The X Keyboard Extension provides capabilities that are lacking or are cumbersome in the core X protocol.

### Core X Protocol Support for Keyboards

The core X protocol specifies the ways that the Shift, Control, and Lock modifiers and the modifiers bound to the Mode\_switch or Num\_Lock keysyms interact to generate keysyms and characters. The core protocol also allows users to specify that a key affects one or more modifiers. This behavior is simple and fairly flexible, but it has a number of limitations that make it difficult or impossible to properly support many common varieties of keyboard behavior. The limitations of core protocol support for keyboards include:

- Use of a single, uniform, four-symbol mapping for all keyboard keys makes it difficult to properly support keyboard overlays, PC-style break keys, or keyboards that comply with ISO9995, or a host of other national and international standards.
- A second keyboard group may be specified using a modifier, but this has side effects that wreak havoc with client grabs and X toolkit translations. Furthermore, this approach limits the number of keyboard groups to two.
- Poorly specified locking key behavior requires X servers to look for a few "magic" keysyms to determine
  that keys should lock when pressed. This leads to incompatibilities between X servers with no way for
  clients to detect implementation differences.
- Poorly specified capitalization and control behavior requires modifications to X library source code to support new character sets or locales and can lead to incompatibilities between system wide and X library capitalization behavior.
- Limited interactions between modifiers specified by the core protocol make many common keyboard behaviors difficult or impossible to implement. For example, there is no reliable way to indicate whether or not the shift modifier should "cancel" the lock modifier.
- The lack of any explicit descriptions for indicators, most modifiers, and other aspects of the keyboard appearance requires clients that wish to clearly describe the keyboard to a user to resort to a mish-mash of prior knowledge and heuristics.

# **Xkb Keyboard Extension Support for Keyboards**

The X Keyboard Extension makes it possible to clearly and explicitly specify most aspects of keyboard behavior on a per-key basis. It adds the notion of a keyboard group to the global keyboard state and provides mechanisms to more closely track the logical and physical state of the keyboard. For keyboard-control clients, Xkb provides descriptions and symbolic names for many aspects of keyboard appearance and behavior.


In addition, the X Keyboard Extension includes additional keyboard controls designed to make keyboards more accessible to people with movement impairments.

#### **Xkb Extension Components**

The Xkb extension is composed of two parts: a server extension, and a client-side X library extension. These consist of a loadable module that may be activated when an X server is started and a modified version of Xlib. Both server and Xlib versions must be at least X11 R6.

Figure 1.1 shows the overall structure of the Xkb extension:

Figure 1.1. Overall Xkb Structure



The server portion of the Xkb extension encompasses a database of named keyboard components, in unspecified format, that may be used to configure a keyboard. Internally, the server maintains a *keyboard description* that includes the keyboard state and configuration (mapping). By "keyboard" we mean the logical keyboard device, which includes not only the physical keys, but also potentially a set of up to 32 indicators (usually LEDs) and bells.

The keyboard description is a composite of several different data structures, each of which may be manipulated separately. When manipulating the server components, the design allows partial components to be transmitted between the server and a client. The individual components are shown in Figure 1.1.

Client Map The key mapping information needed to convert arbitrary keycodes to

symbols.

Server Map The key mapping information categorizing keys by functionality (which keys

are modifiers, how keys behave, and so on).

Controls Client configurable quantities effecting how the keyboard behaves, such as

repeat behavior and modifications for people with movement impairments.

Indicators The mapping of behavior to indicators.

Geometry A complete description of the physical keyboard layout, sufficient to draw a

representation of the keyboard.

Names A mapping of names to various aspects of the keyboard such as individual

virtual modifiers, indicators, and bells.

Compatibility Map The definition of how to map core protocol keyboard state to Xkb keyboard

state.

A client application interrogates and manipulates the keyboard by reading and writing portions of the server description for the keyboard. In a typical sequence a client would fetch the current information it is interested in, modify it, and write it back. If a client wishes to track some portion of the keyboard state, it typically maintains a local copy of the portion of the server keyboard description dealing with the items of interest and updates this local copy from events describing state transitions that are sent by the server.

A client may request the server to reconfigure the keyboard either by sending explicit reconfiguration instructions to it, or by telling it to load a new configuration from its database of named components. Partial reconfiguration and incremental reconfiguration are both supported.

#### **Groups and Shift Levels**

The graphic characters or control functions that may be accessed by one key are logically arranged in groups and levels. See section 14.1 for a complete description of groups and levels.

#### **Radio Groups**

A radio group is a set of keys whose behavior simulates a set of radio buttons. Once a key in a radio group is pressed, it stays logically depressed until another key in the group is pressed, at which point the previously depressed key is logically released. Consequently, at most one key in a radio group can be logically depressed at one time. A radio group is defined by a radio group index, an optional name, and by assigning each key in the radio group XkbKB\_RadioGroup behavior and the radio group index.

#### **Client Types**

This specification differentiates between three different classes of client applications:

Xkb-aware applications

These applications make specific use of Xkb functionality and APIs not present in the core protocol.

Xkb-capable applications

These applications make no use of Xkb extended functionality and Application Programming Interfaces (APIs) directly. However, they are linked with a version of Xlib that includes Xkb and indirectly benefit from some of Xkb's features.

· Xkb-unaware applications

These applications make no use of Xkb extended functionality or APIs and require Xkb's functionality to be mapped to core Xlib functionality to operate properly.

#### **Compatibility With the Core Protocol**

Because the Xkb extension allows a keyboard to be configured in ways not foreseen by the core protocol, and because Xkb-unaware clients are allowed to connect to a server using the Xkb extension, there must be a means of converting between the Xkb domain and the core protocol. The Xkb server extension maintains a compatibility map as part of its keyboard description; this map controls the conversion of Xkb generated events to core protocol events and the results of core protocol requests to appropriate Xkb state and configuration.

#### **Additional Protocol Errors**

The Xkb extension adds a single protocol error, BadKeyboard, to the core protocol error set. See section 2.6 for a discussion of the BadKeyboard protocol error.

#### **Extension Library Functions**

The X Keyboard Extension replaces the core protocol definition of a keyboard with a more comprehensive one. The X Keyboard Extension library interfaces are included in Xlib.<sup>1</sup>

Xlib detects the presence of the X Keyboard server extension and uses Xkb protocol to replace some standard X library functions related to the keyboard. If an application uses only standard X library functions to examine the keyboard or process key events, it should not need to be modified when linked with an X library containing the X keyboard extension. All of the keyboard-related X library functions have been modified to automatically use Xkb protocol when the server extension is present.

The Xkb extension adds library interfaces to allow a client application to directly manipulate the new capabilities.

#### **Error Indications**

Xkb functions that communicate with the X server check to be sure the Xkb extension has been properly initialized prior to doing any other operations. If the extension has not been properly initialized or the application, library, and server versions are incompatible, these functions return an error indication as shown in Table 1.1. Because of this test, BadAccess and BadMatch (due to incompatible versions) protocol errors should normally not be generated.

<sup>&</sup>lt;sup>1</sup> X11R6.1 is the first release by the X Consortium, Inc., that includes the X Keyboard Extension in Xlib. X11R6 included work in progress on this extension as nonstandard additions to the library.

**Table 1.1. Function Error Returns Due to Extension Problems** 

<b>Functions return type</b>	Return value
pointer to a structure	NULL
Bool	False
Status	BadAccess

Many Xkb functions do not actually communicate with the X server; they only require processing in the client-side portion of the library. Furthermore, some applications may never actually need to communicate with the server; they simply use the Xkb library capabilities. The functions that do not communicate with the server return either a pointer to a structure, a Bool, or a Status. These functions check that the application has queried the Xkb library version and return the values shown in Table 1.1 if it has not.

# Chapter 2. Initialization and General Programming Information

#### **Extension Header Files**

The following include files are part of the Xkb standard:

• <X11/XKBlib.h>

XKBlib.h is the main header file for Xkb; it declares constants, types, and functions.

• <X11/extensions/XKBstr.h>

XKBstr.h declares types and constants for Xkb. It is included automatically from <X11/XKBlib.h>; you should never need to reference it directly in your application code.

<X11/extensions/XKB.h>

XKB.h defines constants for Xkb. It is included automatically from <X11/XKBstr.h>; you should never need to reference it directly in your application code.

<X11/extensions/XKBgeom.h>

XKBgeom.h declares types, symbolic constants, and functions for manipulating keyboard geometry descriptions.

#### **Extension Name**

The name of the Xkb extension is given in <X11/extensions/Xkb.h>:

```
#define XkbName "XKEYBOARD"
```

Most extensions to the X protocol are initialized by calling XInitExtension and passing the extension name. However, as explained in section 2.4, Xkb requires a more complex initialization sequence, and a client program should not call XInitExtension directly.

## **Determining Library Compatibility**

If an application is dynamically linked, both the X server and the client-side X library must contain the Xkb extension in order for the client to use the Xkb extension capabilities. Therefore a dynamically linked application must check both the library and the server for compatibility before using Xkb function calls. A properly written program must check for compatibility between the version of the Xkb library that is dynamically loaded and the one used when the application was built. It must then check the server version for compatibility with the version of Xkb in the library.

If your application is statically linked, you must still check for server compatibility and may check library compatibility. (It is possible to compile against one set of header files and link against a different, incompatible, version of the library, although this should not normally occur.)

To determine the compatibility of a library at runtime, call XkbLibraryVersion.

# Initialization and General Programming Information

Bool XkbLibraryVersion(lib\_major\_in\_out, lib\_minor\_in\_out);

lib\_major\_in\_out specifies and returns the major Xkb library version.

lib\_minor\_in\_out specifies and returns the minor Xkb library version.

Pass the symbolic value XkbMajorVersion in <code>lib\_major\_in\_out</code> and XkbMinorVersion in <code>lib\_minor\_in\_out</code>. These arguments represent the version of the library used at compile time. The XkbLibraryVersion function backfills the major and minor version numbers of the library used at run time in <code>lib\_major\_in\_out</code> and <code>lib\_minor\_in\_out</code>. If the versions of the compile time and run time libraries are compatible, XkbLibraryVersion returns True, otherwise, it returns False.

In addition, in order to use the Xkb extension, you must ensure that the extension is present in the server and that the server supports the version of the extension expected by the client. Use XkbQueryExtension to do this, as described in the next section.

#### **Initializing the Keyboard Extension**

Call XkbQueryExtension to check for the presence and compatibility of the extension in the server and to initialize the extension. Because of potential version mismatches, you cannot use the generic extension mechanism functions (XQueryExtension and XInitExtension) for checking for the presence of, and initializing the Xkb extension.

You must call XkbQueryExtension or XkbOpenDisplay before using any other Xkb library interfaces, unless such usage is explicitly allowed in the interface description in this document. The exceptions are: XkbIgnoreExtension, XkbLibraryVersion, and a handful of audible-bell functions. You should not use any other Xkb functions if the extension is not present or is uninitialized. In general, calls to Xkb library functions made prior to initializing the Xkb extension cause BadAccess protocol errors.

XkbQueryExtension both determines whether a compatible Xkb extension is present in the X server and initializes the extension when it is present.

Bool **XkbQueryExtension**(dpy, opcode\_rtrn, event\_rtrn, error\_rtrn, major\_in\_out, minor\_in\_out);

dpy connection to the X server

opcode rtrn backfilled with the major extension opcode

event\_rtrn backfilled with the extension base event code

error\_rtrn backfilled with the extension base error code

major\_in\_out compile time lib major version in, server major version out

minor\_in\_out compile time lib min version in, server minor version out

The XkbQueryExtension function determines whether a compatible version of the X Keyboard Extension is present in the server. If a compatible extension is present, XkbQueryExtension returns True; otherwise, it returns False.

If a compatible version of Xkb is present, XkbQueryExtension initializes the extension. It backfills the major opcode for the keyboard extension in opcode\_rtrn, the base event code in event\_rtrn, the base error code in error\_rtrn, and the major and minor version numbers of the extension in major\_in\_out and minor\_in\_out. The major opcode is reported in the req\_major fields of some Xkb events. For a discussion of the base event code, see section 4.1.

As a convenience, you can use the function XkbOpenDisplay to perform these three tasks at once: open a connection to an X server, check for a compatible version of the Xkb extension in both the library and the server, and initialize the extension for use.

Display \*XkbOpenDisplay(display\_name, event\_rtrn, error\_rtrn,
major\_in\_out, minor\_in\_out, reason\_rtrn);

display\_name hardware display name, which determines the display and

communications domain to be used

event\_rtrn backfilled with the extension base event code

error\_rtrn backfilled with the extension base error code

major\_in\_out compile time lib major version in, server major version out

minor\_in\_out compile time lib minor version in, server minor version out

reason\_rtrn backfilled with a status code

XkbOpenDisplay is a convenience function that opens an X display connection and initializes the X keyboard extension. In all cases, upon return <code>reason\_rtrn</code> contains a status value indicating success or the type of failure. If <code>major\_in\_out</code> and <code>minor\_in\_out</code> are not NULL, <code>XkbOpenDisplay</code> first calls <code>XkbLibraryVersion</code> to determine whether the client library is compatible, <code>passing</code> it the values pointed to by <code>major\_in\_out</code> and <code>minor\_in\_out</code>. If the library is incompatible, <code>XkbOpenDisplay</code> backfills <code>major\_in\_out</code> and <code>minor\_in\_out</code> with the major and minor extension versions of the library being used and returns <code>NULL</code>. If the library is compatible, <code>XkbOpenDisplay</code> next calls <code>XOpenDisplay</code> with the <code>display\_name</code>. If this fails, the function returns <code>NULL</code>. If successful, <code>XkbOpenDisplay</code> calls <code>XkbQueryExtension</code> and backfills the major and minor <code>Xkb</code> server extension version numbers in <code>major\_in\_out</code> and <code>minor\_in\_out</code></code>. If the server extension version is not compatible with the library extension version or if the server extension is not present, <code>XkbOpenDisplay</code> closes the display and returns <code>NULL</code>. When successful, the function returns the display connection.

The possible values for reason\_rtrn are:

- $\bullet \ \ XkbOD\_BadLibraryVersion\ indicates\ XkbLibraryVersion\ returned\ False.$
- XkbOD\_ConnectionRefused indicates the display could not be opened.
- XkbOD\_BadServerVersion indicates the library and the server have incompatible extension versions.
- XkbOD\_NonXkbServer indicates the extension is not present in the X server.
- XkbOD\_Success indicates that the function succeeded.

### Disabling the Keyboard Extension

If a server supports the Xkb extension, the X library normally implements preXkb keyboard functions using the Xkb keyboard description and state. The server Xkb keyboard state may differ from the preXkb keyboard state. This difference does not affect most clients, but there are exceptions. To allow these clients to work properly, you may instruct the extension not to use Xkb functionality.

Call XkbIgnoreExtension to prevent core X library keyboard functions from using the X Keyboard Extension. You must call XkbIgnoreExtension before you open a server connection; Xkb does not provide a way to enable or disable use of the extension once a connection is established.

Bool XkbIgnoreExtension(ignore);

ignore True means ignore the extension

XkbIgnoreExtension tells the X library whether to use the X Keyboard Extension on any subsequently opened X display connections. If ignore is True, the library does not initialize the Xkb extension when it opens a new display. This forces the X server to use compatibility mode and communicate with the client using only core protocol requests and events. If ignore is False, the library treats subsequent calls to XOpenDisplay normally and uses Xkb extension requests, events, and state. Do not explicitly use Xkb on a connection for which it is disabled. XkbIgnoreExtension returns False if it was unable to apply the ignore request.

#### **Protocol Errors**

Many of the Xkb extension library functions described in this document can cause the X server to report an error, referred to in this document as a BadXxx protocol error, where Xxx is some name. These errors are fielded in the normal manner, by the default Xlib error handler or one replacing it. Note that X protocol errors are not necessarily reported immediately because of the buffering of X protocol requests in Xlib and the server.

Table 2.1 lists the protocol errors that can be generated, and their causes.

Table 2.1. Xkb Protocol Errors

Error	Cause
BadAccess	The Xkb extension has not been properly initialized
BadKeyboard	The device specified was not a valid core or input extension device
BadImplementation	Invalid reply from server
BadAlloc	Unable to allocate storage
BadMatch	A compatible version of Xkb was not available in the server or an argument has correct type and range, but is otherwise invalid
BadValue	An argument is out of range
BadAtom	A name is neither a valid Atom or None
BadDevice	Device, Feedback Class, or Feedback ID invalid

The Xkb extension adds a single protocol error, BadKeyboard, to the core protocol error set. This error code will be reported as the <code>error\_rtrn</code> when XkbQueryExtension is called. When a BadKeyboard error is reported in an XErrorEvent, additional information is reported in the <code>resourceid</code> field. The most significant byte of the <code>resource\_id</code> is a further refinement of the error cause, as defined in Table 2.2. The least significant byte will contain the device, class, or feedback ID as indicated in the table.

Table 2.2. BadKeyboard Protocol Error resource id Values

high-order byte	value	meaning	low-order byte
XkbErr_BadDevice	0xff	device not found	device ID
XkbErr_BadClass	0xfe	device found, but it is of the wrong class	class ID
XkbErr_BadId	0xfd	device found, class ok, but device does not contain a feedback with the indicated ID	feedback ID

# Display and Device Specifications in Function Calls

Where a connection to the server is passed as an argument (Display\*) and an XkbDescPtr is also passed as an argument, the Display\* argument must match the dpy field of the XkbDescRec pointed to by the XkbDescPtr argument, or else the dpy field of the XkbDescRec must be NULL. If they don't match or the dpy field is not NULL, a BadMatch error is returned (either in the return value or a backfilled Status variable). Upon successful return, the dpy field of the XkbDescRec always contains the Display\* value passed in.

The Xkb extension can communicate with the X input extension if it is present. Consequently, there can potentially be more than one input device connected to the server. Most Xkb library calls that require communicating with the server involve both a server connection (Display \* dpy) and a device identifier (unsigned int device\_spec). In some cases, the device identifier is implicit and is taken as the device\_spec field of an XkbDescRec structure passed as an argument.

The device identifier can specify any X input extension device with a KeyClass component, or it can specify the constant, XkbUseCoreKbd. The use of XkbUseCoreKbd allows applications to indicate the core keyboard without having to determine its device identifier.

Where an Xkb device identifier is passed as an argument and an XkbDescPtr is also passed as an argument, if either the argument or the XkbDescRec device\_spec field is XkbUseCoreKbd, and if the function returns successfully, the XkbDescPtr device\_spec field will have been converted from XkbUseCoreKbd to a real Xkb device ID. If the function does not complete successfully, the device\_spec field remains unchanged. Subsequently, the device id argument must match the device\_spec field of the XkbDescPtr argument. If they don't match, a BadMatch error is returned (either in the return value or a backfilled Status variable).

When the Xkb extension in the server hands an application a device identifier to use for the keyboard, that ID is the input extension identifier for the device if the server supports the X Input Extension. If the server does not support the input extension, the meaning of the identifier is undefined — the only guarantee is that when you use XkbUseCoreKbd, XkbUseCoreKbd will work and the identifier returned by the server will refer to the core keyboard device.

# **Chapter 3. Data Structures**

An Xkb keyboard description consists of a variety of data structures, each of which describes some aspect of the keyboard. Although each data structure has its own peculiarities, there are a number of features common to nearly all Xkb structures. This chapter describes these common features and techniques for manipulating them.

Many Xkb data structures are interdependent; changing a field in one might require changes to others. As an additional complication, some Xkb library functions allocate related components as a group to reduce fragmentation and allocator overhead. In these cases, simply allocating and freeing fields of Xkb structures might corrupt program memory. Creating and destroying such structures or keeping them properly synchronized during editing is complicated and error prone.

Xkb provides functions and macros to allocate and free all major data structures. You should use them instead of allocating and freeing the structures yourself.

#### Allocating Xkb Data Structures

Xkb provides functions, known as allocators, to create and initialize Xkb data structures. In most situations, the Xkb functions that read a keyboard description from the server call these allocators automatically. As a result, you will seldom have to directly allocate or initialize Xkb data structures.

However, if you need to enlarge an existing structure or construct a keyboard definition from scratch, you may need to allocate and initialize Xkb data structures directly. Each major Xkb data structure has its own unique allocator. The allocator functions share common features: allocator functions for structures with optional components take as an input argument a mask of subcomponents to be allocated. Allocators for data structures containing variable-length data take an argument specifying the initial length of the data.

You may call an allocator to change the size of the space allocated for variable-length data. When you call an allocator with an existing data structure as a parameter, the allocator does not change the data in any of the fields, with one exception: variable-length data might be moved. The allocator resizes the allocated memory if the current size is too small. This normally involves allocating new memory, copying existing data to the newly allocated memory, and freeing the original memory. This possible reallocation is important to note because local variables pointing into Xkb data structures might be invalidated by calls to allocator functions.

#### **Adding Data and Editing Data Structures**

You should edit most data structures via the Xkb-supplied helper functions and macros, although a few data structures can be edited directly. The helper functions and macros make sure everything is initialized and interdependent values are properly updated for those Xkb structures that have interdependencies. As a general rule, if there is a helper function or macro to edit the data structure, use it. For example, increasing the width of a type requires you to resize every key that uses that type. This is complicated and ugly, which is why there's an XkbResizeKeyType function.

Many Xkb data structures have arrays whose size is reported by two fields. The first field, whose name is usually prefixed by  $sz_{-}$ , represents the total number of elements that can be stored in the array. The second field, whose name is usually prefixed by  $num_{-}$ , specifies the number of elements currently stored there. These arrays typically represent data whose total size cannot always be determined when the array is created. In these instances, the usual way to allocate space and add data is as follows:

• Call the allocator function with some arbitrary size, as a hint.

• For those arrays that have an Xkb...Add... function, call it each time you want to add new data to the array. The function expands the array if necessary.

For example, call:

XkbAllocGeomShapes(geom, 4)

to say "I'll need space for four new shapes in this geometry." This makes sure that  $sz\_shapes\_num\_shapes>=4$ , and resizes the shapes array if it isn't. If this function succeeds, you are guaranteed to have space for the number of shapes you need.

When you call an editing function for a structure, you do not need to check for space, because the function automatically checks the  $sz_{-}$  and  $num_{-}$  fields of the array, resizes the array if necessary, adds the entry to the array, and then updates the  $num_{-}$  field.

# Making Changes to the Server's Keyboard Description

In Xkb, as in the core protocol, the client and server have independent copies of the data structures that describe the keyboard. The recommended way to change some aspect of the keyboard mapping in the X server is to edit a local copy of the Xkb keyboard description and then send only the changes to the X server. This method helps eliminate the need to transfer the entire keyboard description or even an entire data structure for only minor changes.

To help you keep track of the changes you make to a local copy of the keyboard description, Xkb provides separate special *changes* data structures for each major Xkb data structure. These data structures do not contain the actual changed values: they only indicate the changes that have been made to the structures that actually describe the keyboard.

When you wish to change the keyboard description in the server, you first modify a local copy of the keyboard description and then flag the modifications in an appropriate changes data structure. When you finish editing the local copy of the keyboard description, you pass your modified version of the keyboard description and the modified changes data structure to an Xkb function. This function uses the modified keyboard description and changes structure to pass only the changed information to the server. Note that modifying the keyboard description but not setting the appropriate flags in the changes data structure causes indeterminate behavior.

#### **Tracking Keyboard Changes in the Server**

The server reports all changes in its keyboard description to any interested clients via special Xkb events. Just as clients use special changes data structures to change the keyboard description in the server, the server uses special changes data structures to tell a client what changed in the server's keyboard description.

Unlike clients, however, the server does not always pass the new values when it reports changes to its copy of the keyboard description. Instead, the server only passes a changes data structure when it reports changes to its keyboard description. This is done for efficiency reasons — some clients do not always need to update their copy of the keyboard description with every report from the server.

When your client application receives a report from the server indicating the keyboard description has changed, you can determine the set of changes by passing the event to an Xkb function that "notes" event information in the corresponding changes data structure. These "note changes" functions are defined for all major Xkb components, and their names have the form XkbNote({Component})Changes),

where *Component* is the name of a major Xkb component such as Map or Names. When you want to copy these changes from the server into a local copy of the keyboard description, use the corresponding XkbGet({Component}Changes) function, passing it the changes structure. The function then retrieves only the changed structures from the server and copies the modified pieces into the local keyboard description.

#### **Freeing Data Structures**

For the same reasons you should not directly use malloc to allocate Xkb data structures, you should not free Xkb data structures or components directly using free or Xfree. Xkb provides functions to free the various data structures and their components. Always use the free functions supplied by Xkb. There is no guarantee that any particular field can be safely freed by free or Xfree.

# Chapter 4. Xkb Events

The primary way the X server communicates with clients is by sending X events to them. Some events are sent to all clients, while others are sent only to clients that have requested them. Some of the events that can be requested are associated with a particular window and are only sent to those clients who have both requested the event and specified the window in which the event occurred.

The Xkb extension uses events to communicate the keyboard status to interested clients. These events are not associated with a particular window. Instead, all Xkb keyboard status events are reported to all interested clients, regardless of which window currently has the keyboard focus and regardless of the grab state of the keyboard.<sup>1</sup>

The X server reports the events defined by the Xkb extension to your client application only if you have requested them. You may request Xkb events by calling either XkbSelectEvents or XkbSelectEventDetails. XkbSelectEvents requests Xkb events by their event type and causes them to be reported to your client application under all circumstances. You can specify a finer granularity for event reporting by using XkbSelectEventDetails; in this case events are reported only when the specific detail conditions you specify have been met.

#### **Xkb Event Types**

The Xkb Extension adds new event types to the X protocol definition. An Xkb event type is defined by two fields in the X event data structure. One is the type field, containing the base event code. This base event code is a value the X server assigns to each X extension at runtime and that identifies the extension that generated the event; thus, the event code in the type field identifies the event as an Xkb extension event, rather than an event from another extension or a core X protocol event. You can obtain the base event code via a call to XkbQueryExtension or XkbOpenDisplay. The second field is the Xkb event type, which contains a value uniquely identifying each different Xkb event type. Possible values are defined by constants declared in the header file <X11/extensions/Xkb.h>.

Table 4.1 lists the categories of events defined by Xkb and their associated event types, as defined in Xkb. h. Each event is described in more detail in the section referenced for that event.

<sup>&</sup>lt;sup>1</sup>The one exception to this rule is the XkbExtensionDeviceNotify event report that is sent when a client attempts to use an unsupported feature of an X Input Extension device (see section 21.4).

Table 4.1. Xkb Event Types

<b>Event Type</b>	Conditions Generating Event	Section	
XkbNewKeyboardNotify	Keyboard geometry; keycode range change	19	
XkbMapNotify	Keyboard mapping change	14.4	
XkbStateNotify	Keyboard state change	5.4	
XkbControlsNotify	Keyboard controls state change	10.11	
XkbIndicatorStateNotify	Keyboard indicators state change	8.5	
XkbIndicatorMapNotify	Keyboard indicators map change	8.5	
XkbNamesNotify	Keyboard name change	18.5	
XkbCompatMapNotify	Keyboard compatibility map change	17.5	
XkbBellNotify	Keyboard bell generated	9.4	
XkbActionMessage	Keyboard action message	16.1.11	
XkbAccessXNotify	AccessX state change	10.6.4	
XkbExtensionDeviceNotify	Extension device change	21.6	

#### **Xkb Event Data Structures**

Xkb reports each event it generates in a unique structure holding the data values needed to describe the conditions the event is reporting. However, all Xkb events have certain things in common. These common features are contained in the same fields at the beginning of all Xkb event structures and are described in the XkbAnyEvent structure:

```
typedef struct {
                                  /* Xkb extension base event code */
    int
                    type;
    unsigned long
                    serial;
                                  /* X server serial number for event */
                                  /* True # synthetically generated */
   Bool
                    send_event;
   Display *
                    display;
                                  /* server connection where event generated */
                                  /* server time when event generated */
   Time
                    time;
                    xkb_type;
                                  /* Xkb minor event code */
    int
                                  /* Xkb device ID, will not be XkbUseCoreKbd */
    unsigned int
                    device;
} XkbAnyEvent;
```

For any Xkb event, the type field is set to the base event code for the Xkb extension, assigned by the server to all Xkb extension events. The serial, send\_event, and display fields are as described for all X11 events. The time field is set to the time when the event was generated and is expressed in milliseconds. The xkb\_type field contains the minor extension event code, which is the extension event type, and is one of the values listed in Table 4.1. The device field contains the keyboard device identifier associated with the event. This is never XkbUseCoreKbd, even if the request that generated the event specified a device of XkbUseCoreKbd. If the request that generated the event specified XkbUseCoreKbd, device contains a value assigned by the server to specify the core keyboard. If the request that generated the event specified an X input extension device, device contains that same identifier.

Other data fields specific to individual Xkb events are described in subsequent chapters where the events are described.

## **Selecting Xkb Events**

Xkb events are selected using an event mask, much the same as normal core X events are selected. However, unlike selecting core X events, where you must specify the selection status (on or off) for all possible event types whenever you wish to change the selection criteria for any one event, Xkb allows you to restrict the specification to only the event types you wish to change. This means that you do not need to remember the event selection values for all possible types each time you want to change one of them.

Many Xkb event types are generated under several different circumstances. When selecting to receive an Xkb event, you may specify either that you want it delivered under all circumstances, or that you want it delivered only for a subset of the possible circumstances.

You can also deselect an event type that was previously selected for, using the same granularity.

Xkb provides two functions to select and deselect delivery of Xkb events. XkbSelectEvents allows you to select or deselect delivery of more than one Xkb event type at once. Events selected using XkbSelectEvents are delivered to your program under all circumstances that generate the events. To restrict delivery of an event to a subset of the conditions under which it occurs, use XkbSelectEventDetails. XkbSelectEventDetails only allows you to change the selection conditions for a single event at a time, but it provides a means of fine-tuning the conditions under which the event is delivered.

To select and / or deselect for delivery of one or more Xkb events and have them delivered under all conditions, use XkbSelectEvents.

Bool **XkbSelectEvents**(display, device\_spec, bits\_to\_change, values\_for\_bits);

display connection to the X server

device\_spec device ID, or XkbUseCoreKbd

bits\_to\_change determines events to be selected / deselected

values\_for\_bits 1#select, 0#deselect; for events in bits\_to\_change

This request changes the Xkb event selection mask for the keyboard specified by device\_spec.

Each Xkb event that can be selected is represented by a bit in the <code>bits\_to\_change</code> and <code>values\_for\_bits</code> masks. Only the event selection bits specified by the <code>bits\_to\_change</code> parameter are affected; any unspecified bits are left unchanged. To turn on event selection for an event, set the bit for the event in the <code>bits\_to\_change</code> parameter and set the corresponding bit in the <code>values\_for\_bits</code> parameter. To turn off event selection for an event, set the bit for the event in the <code>bits\_to\_change</code> parameter and do not set the corresponding bit in the <code>values\_for\_bits</code> parameter. The valid values for both of these parameters are an inclusive bitwise OR of the masks shown in Table 4.2. There is no interface to return your client's current event selection mask. Clients cannot set other clients' event selection masks.

If a bit is not set in the bits\_to\_change parameter, but the corresponding bit is set in the values\_for\_bits parameter, a BadMatch protocol error results. If an undefined bit is set in either the bits\_to\_change or the values\_for\_bits parameter, a BadValue protocol error results.

All event selection bits are initially zero for clients using the Xkb extension. Once you set some bits, they remain set for your client until you clear them via another call to XkbSelectEvents.

XkbSelectEvents returns False if the Xkb extension has not been initialized and True otherwise.

To select or deselect for a specific Xkb event and optionally place conditions on when events of that type are reported to your client, use XkbSelectEventDetails. This allows you to exercise a finer granularity of control over delivery of Xkb events with XkbSelectEvents.

Bool **XkbSelectEventDetails**(display, device\_spec, event\_type, bits\_to\_change, values\_for\_bits);

display connection to the X server

device\_spec device ID, or XkbUseCoreKbd

event\_type Xkb event type of interest

bits\_to\_change event selection details

values\_for\_bits values for bits selected by bits\_to\_change

While XkbSelectEvents allows multiple events to be selected, XkbSelectEventDetails changes the selection criteria for a single type of Xkb event. The interpretation of the bits\_to\_change and values\_for\_bits masks depends on the event type in question.

XkbSelectEventDetails changes the Xkb event selection mask for the keyboard specified by device\_spec and the Xkb event specified by event\_type. To turn on event selection for an event detail, set the bit for the detail in the bits\_to\_change parameter and set the corresponding bit in the values\_for\_bits parameter. To turn off event detail selection for a detail, set the bit for the detail in the bits\_to\_change parameter and do not set the corresponding bit in the values\_for\_bits parameter.

If an invalid event type is specified, a BadValue protocol error results. If a bit is not set in the <code>bits\_to\_change</code> parameter, but the corresponding bit is set in the <code>values\_for\_bits</code> parameter, a BadMatch protocol error results. If an undefined bit is set in either the <code>bits\_to\_change</code> or the <code>values\_for\_bits</code> parameter, a BadValue protocol error results.

For each type of Xkb event, the legal event details that you can specify in the XkbSelectEventDetails request are listed in the chapters that describe each event in detail.

#### **Event Masks**

The X server reports the events defined by Xkb to your client application only if you have requested them via a call to XkbSelectEvents or XkbSelectEventDetails. Specify the event types in which you are interested in a mask, as described in section 4.3.

Table 4.2 lists the event mask constants that can be specified with the XkbSelectEvents request and the circumstances in which the mask should be specified.

Table 4.2. XkbSelectEvents Mask Constants

Event Mask	Value	Notification Wanted
XkbNewKeyboardNotifyMask	(1L<<0)	Keyboard geometry change
XkbMapNotifyMask	(1L<<1)	Keyboard mapping change
XkbStateNotifyMask	(1L<<2)	Keyboard state change
XkbControlsNotifyMask	(1L<<3)	Keyboard control change
XkbIndicatorStateNotifyMask	(1L<<4)	Keyboard indicator state change
XkbIndicatorMapNotifyMask	(1L<<5)	Keyboard indicator map change
XkbNamesNotifyMask	(1L<<6)	Keyboard name change
XkbCompatMapNotifyMask	(1L<<7)	Keyboard compat map change
XkbBellNotifyMask	(1L<<8)	Bell
XkbActionMessageMask	(1L<<9)	Action message
XkbAccessXNotifyMask	(1L<<10)	AccessX features
XkbExtensionDeviceNotifyMask	(1L<<11)	Extension device
XkbAllEventsMask	(0xFFF)	All Xkb events

#### **Unified Xkb Event Type**

The XkbEvent structure is a union of the individual structures declared for each Xkb event type and for the core protocol XEvent type. Given an XkbEvent structure, you may use the type field to determine if the event is an Xkb event (type equals the Xkb base event code; see section 2.4). If the event is an Xkb event, you may then use the any.xkb\_type field to determine the type of Xkb event and thereafter access the event-dependent components using the union member corresponding to the particular Xkb event type.

```
typedef union _XkbEvent {
      int
                                       type;
      XkbAnyEvent
                                      any;
      XkbStateNotifyEvent
                                      state;
      XkbMapNotifyEvent
                                      map;
      XkbControlsNotifyEvent
                                      ctrls;
      XkbIndicatorNotifyEvent
                                      indicators;
                                      bell;
      XkbBellNotifyEvent
      XkbAccessXNotifyEvent
                                      accessx;
      XkbNamesNotifyEvent
                                      names;
      XkbCompatMapNotifyEvent
                                      compat;
      XkbActionMessageEvent
                                      message;
      XkbExtensionDeviceNotifyEvent
                                      device;
      XkbNewKeyboardNotifyEvent
                                      new kbd;
      XEvent
                                      core;
} XkbEvent;
```


This unified Xkb event type includes a normal XEvent as used by the core protocol, so it is straightforward for applications that use Xkb events to call the X library event functions without having to cast every reference. For example, to get the next event, you can simply declare a variable of type XkbEvent and call:

```
XNextEvent(dpy,&xkbev.core);
```

# **Chapter 5. Keyboard State**

Keyboard state encompasses all of the transitory information necessary to map a physical key press or release to an appropriate event. The Xkb keyboard state consists of primitive components and additional derived components that are maintained for efficiency reasons. Figure 5.1 shows the components of Xkb keyboard state and their relationships.

Figure 5.1. Xkb State



## **Keyboard State Description**

The Xkb keyboard state is comprised of the state of all keyboard modifiers, the keyboard group, and the state of the pointer buttons. These are grouped into the following components:

- · The locked group and locked modifiers
- The latched group and latched modifiers
- The base group and base modifiers
- The effective group and effective modifiers
- The state of the core pointer buttons

The *modifiers* are Shift, Lock, Control, and Mod1 – Mod5, as defined by the core protocol. A modifier can be thought of as a toggle that is either set or unset. All modifiers are initially unset. When a modifier is locked, it is set and remains set for all future key events, until it is explicitly unset. A latched modifier is set, but automatically unsets after the next key event that does not change the keyboard state. Locked and latched modifier state can be changed by keyboard activity or via Xkb extension library functions.

The Xkb extension provides support for keysym groups, as defined by ISO9995:

Group A logical state of a keyboard providing access to a collection of characters. A group usually contains a set of characters that logically belong together and that may be arranged on several shift levels within that group.

The Xkb extension supports up to four keysym groups. Groups are named beginning with one and indexed beginning with zero. All group states are indicated using the group index. At any point in time, there is zero or one locked group, zero or one latched group, and one base group. When a group is locked, it supersedes any previous locked group and remains the locked group for all future key events, until a new group is locked. A latched group applies only to the next key event that does not change the keyboard state. The locked and latched group can be changed by keyboard activity or via Xkb extension library functions.

Changing to a different group changes the keyboard state to produce characters from a different group. Groups are typically used to switch between keysyms of different languages and locales.

The *pointer buttons* are Button1 – Button5, as defined by the core protocol.

The *base group* and *base modifiers* represent keys that are physically or logically down. These and the pointer buttons can be changed by keyboard activity and not by Xkb requests. It is possible for a key to be logically down, but not physically down, and neither latched nor locked. <sup>1</sup>

The effective modifiers are the bitwise union of the locked, latched, and the base modifiers.

The *effective group* is the arithmetic sum of the group indices of the latched group, locked group, and base group, which is then normalized by some function. The result is a meaningful group index.

```
\begin{split} n &= number\ of\ keyboard\ groups,\ 1 <= n <= 4\\ 0 &<= any\ of\ locked,\ latched,\ or\ base\ group < n\\ effective\ group &= f(locked\ group + latched\ group + base\ group) \end{split}
```

<sup>&</sup>lt;sup>1</sup> Keys may be logically down when they are physically up because of their electrical properties or because of the keyboard extension in the X server having filtered the key release, for esoteric reasons.

The function f ensures that the effective group is within range. The precise function is specified for the keyboard and can be retrieved through the keyboard description. It may wrap around, clamp down, or default. Few applications will actually examine the effective group, and far fewer still will examine the locked, latched, and base groups.

There are two circumstances under which groups are normalized:

- 1. The global locked or effective group changes. In this case, the changed group is normalized into range according to the settings of the *groups\_wrap* field of the XkbControlsRec structure for the keyboard (see section 10.7.1).
- 2. The Xkb library is interpreting an event with an effective group that is legal for the keyboard as a whole, but not for the key in question. In this case, the group to use for this event only is determined using the group\_info field of the key symbol mapping (XkbSymMapRec) for the event key.

Each nonmodifier key on a keyboard has zero or more symbols, or keysyms, associated with it. These are the logical symbols that the key can generate when it is pressed. The set of all possible keysyms for a keyboard is divided into groups. Each key is associated with zero or more groups; each group contains one or more symbols. When a key is pressed, the determination of which symbol for the key is selected is based on the effective group and the shift level, which is determined by which modifiers are set.

A client that does not explicitly call Xkb functions, but that otherwise makes use of an X library containing the Xkb extension, will have keyboard state represented in bits 0-14 of the state field of events that report modifier and button state. Such a client is said to be Xkb-capable. A client that does explicitly call Xkb functions is an Xkb-aware client. The Xkb keyboard state includes information derived from the effective state and from two server parameters that can be set through the keyboard extension. The following components of keyboard state pertain to Xkb-capable and Xkb-aware clients:

- · lookup state: lookup group and lookup modifiers
- grab state: grab group and grab modifiers

The *lookup modifiers* and *lookup group* are represented in the state field of core X events. The modifier state and keycode of a key event are used to determine the symbols associated with the event. For KeyPress and KeyRelease events, the lookup modifiers are computed as:

```
((base | latched | locked) & ~server_internal_modifiers)
```

Otherwise the lookup modifiers are computed as:

```
(((base | latched | (locked & ~ignore_locks)) & ~server_internal_modifiers)
```

The lookup group is the same as the effective group.

When an Xkb-capable or Xkb-aware client wishes to map a keycode to a keysym, it should use the *lookup* state — the lookup group and the lookup modifiers.

The *grab state* is the state used when matching events to passive grabs. If the event activates a grab, the *grab modifiers* and *grab group* are represented in the state field of core X events; otherwise, the lookup state is used. The grab modifiers are computed as:

```
(((base | latched | (locked & ~ignore locks)) & ~server internal modifiers)
```

If the server's *IgnoreGroupLock* control (see section 10.7.3) is not set, the grab group is the same as the effective group. Otherwise, the grab group is computed from the base group and latched group, ignoring the locked group.

The final three components of Xkb state are applicable to clients that are not linked with an Xlib containing the X keyboard extension library and therefore are not aware of the keyboard extension (*Xkb-unaware* clients):

- The compatibility modifier state
- · The compatibility lookup modifier state
- The compatibility grab modifier state

The X11 protocol interpretation of modifiers does not include direct support for multiple groups. When an Xkb-extended X server connects to an Xkb-unaware client, the compatibility states remap the keyboard group into a core modifier whenever possible. The compatibility state corresponds to the effective modifier and effective group state, with the group remapped to a modifier. The compatibility lookup and grab states correspond to the lookup and grab states, respectively, with the group remapped to a modifier. The compatibility lookup state is reported in events that do not trigger passive grabs; otherwise, the compatibility grab state is reported.

## **Changing the Keyboard State**

#### **Changing Modifiers**

The functions in this section that change the use of modifiers use a mask in the parameter affect. It is a bitwise inclusive OR of the legal modifier masks:

#### Table 5.1. Real Modifier Masks

Mask

ShiftMask

LockMask

ControlMask

Mod1Mask

Mod2Mask

Mod3Mask

Mod4Mask

Mod5Mask

To lock and unlock any of the eight real keyboard modifiers, use XkbLockModifiers:

Bool XkbLockModifiers(display, device\_spec, affect, values);

display connection to the X server

device\_spec device ID, or XkbUseCoreKbd

affect mask of real modifiers whose lock state is to change

values  $1 \rightarrow lock, 0 \rightarrow unlock; only for modifiers selected by affect$ 

XkbLockModifiers sends a request to the server to lock the real modifiers selected by both affect and values and to unlock the real modifiers selected by affect but not selected by values.

XkbLockModifiers does not wait for a reply from the server. It returns True if the request was sent, and False otherwise.

To latch and unlatch any of the eight real keyboard modifiers, use XkbLatchModifiers:

Bool XkbLatchModifiers(display, device\_spec, affect, values);

display connection to the X server

device\_spec device ID, or XkbUseCoreKbd

affect mask of modifiers whose latch state is to change

values  $1 \Rightarrow \text{latch}, 0 \Rightarrow \text{unlatch}; \text{ only for mods selected by affect}$ 

XkbLatchModifiers sends a request to the server to latch the real modifiers selected by both affect and values and to unlatch the real modifiers selected by affect but not selected by values. XkbLatchModifiers does not wait for a reply from the server. It returns True if the request was sent, and False otherwise.

#### **Changing Groups**

Reference the keysym group indices with these symbolic constants:

**Table 5.2. Symbolic Group Names** 

Symbolic Name	Value
XkbGroup1Index	0
XkbGroup2Index	1
XkbGroup3Index	2
XkbGroup4Index	3

To lock the keysym group, use XkbLockGroup.

Bool XkbLockGroup(display, device\_spec, group);

display connection to the X server

device\_spec device ID, or XkbUseCoreKbd

group index of the keysym group to lock

XkbLockGroup sends a request to the server to lock the specified *group* and does not wait for a reply. It returns True if the request was sent and False otherwise.

To latch the keysym group, use XkbLatchGroup.

Bool XkbLatchGroup(display, device\_spec, group);

display connection to the X server

device\_spec device ID, or XkbUseCoreKbd

group index of the keysym group to latch

XkbLatchGroup sends a request to the server to latch the specified group and does not wait for a reply. It returns True if the request was sent and False otherwise.

#### **Determining Keyboard State**

Xkb keyboard state may be represented in an XkbStateRec structure:

```
typedef struct {
    unsigned char
                                                /* effective group index */
                        group;
                                                /* base group index */
    unsigned char
                        base_group;
    unsigned char
                        latched_group;
                                                /* latched group index */
    unsigned char
                        locked_group;
                                                /* locked group index */
                                                /* effective modifiers */
    unsigned char
                        mods;
                                                /* base modifiers */
    unsigned char
                        base_mods;
    unsigned char
                        latched mods;
                                                /* latched modifiers */
    unsigned char
                        locked_mods;
                                                /* locked modifiers */
                                                /* effective group # modifiers */
    unsigned char
                        compat_state;
                                                /* modifiers used for grabs */
    unsigned char
                        grab_mods;
                                                /* mods used for compatibility
    unsigned char
                        compat_grab_mods;
                                                   mode grabs */
    unsigned char
                        lookup_mods;
                                                /* mods used to lookup symbols */
                                                /* mods used for compatibility
    unsigned char
                        compat_lookup_mods;
                                                   lookup */
    unsigned short
                        ptr_buttons;
                                                /* 1 bit # corresponding
                                                   pointer btn is down */
} XkbStateRec, *XkbStatePtr;
To obtain the keyboard state, use XkbGetState.
Status XkbGetState(display, device spec, state return);
display
                           connection to the X server
device spec
                           device ID, or XkbUseCoreKbd
state_return
                           backfilled with Xkb state
```

The XkbGetState function queries the server for the current keyboard state, waits for a reply, and then backfills state\_return with the results.

All group values are expressed as group indices in the range [0..3]. Modifiers and the compatibility modifier state values are expressed as the bitwise union of the core X11 modifier masks. The pointer button state is reported as in the core X11 protocol.

# Tracking Keyboard State

The Xkb extension reports XkbStateNotify events to clients wanting notification whenever the Xkb state changes. The changes reported include changes to any aspect of the keyboard state: when a modifier is set or unset, when the current group changes, or when a pointer button is pressed or released. As with all Xkb events, XkbStateNotify events are reported to all interested clients without regard to the current keyboard input focus or grab state.

There are many different types of Xkb state changes. Xkb defines an event detail mask corresponding to each type of change. The event detail masks are listed in Table 5.3.

Table 5.3. XkbStateNotify Event Detail Masks

Mask	Value
XkbModifierStateMask	(1L << 0)
XkbModifierBaseMask	(1L << 1)
XkbModifierLatchMask	(1L << 2)
XkbModifierLockMask	(1L << 3)
XkbGroupStateMask	(1L << 4)
XkbGroupBaseMask	(1L << 5)
XkbGroupLatchMask	(1L << 6)
XkbGroupLockMask	(1L << 7)
XkbCompatStateMask	(1L << 8)
XkbGrabModsMask	(1L << 9)
XkbCompatGrabModsMask	(1L << 10)
XkbLookupModsMask	(1L << 11)
XkbCompatLookupModsMask	(1L << 12)
XkbPointerButtonMask	(1L << 13)
XkbAllStateComponentsMask	(0x3fff)

To track changes in the keyboard state for a particular device, select to receive XkbStateNotify events by calling either XkbSelectEvents or XkbSelectEventDetails (see section 4.3).

To receive XkbStateNotify events under all possible conditions, use XkbSelectEvents and pass XkbStateNotifyMask in both bits\_to\_change and values\_for\_bits.

To receive XkbStateNotify events only under certain conditions, use XkbSelectEventDetails using XkbStateNotify as the event\_type and specifying the desired state changes in bits\_to\_change and values\_for\_bits using mask bits from Table 5.3.

The structure for XkbStateNotify events is:

```
typedef struct {
                                    /* Xkb extension base event code */
    int
                   type;
   unsigned long serial;
                                    /* X server serial number for event */
                                    /* True # synthetically generated */
   Bool
                   send_event;
                                    /* server connection where event generated */
   Display *
                   display;
   Time
                   time;
                                    /* server time when event generated */
                                    /* XkbStateNotify */
   int
                   xkb_type;
                                    /* Xkb device ID,
    int
                   device;
                                       will not be XkbUseCoreKbd */
                                    /* bits indicating what has changed */
   unsigned int
                   changed;
   int
                   group;
                                    /* group index of effective group */
                                    /* group index of base group */
    int
                   base_group;
    int
                                    /* group index of latched group */
                   latched_group;
                                    /* group index of locked group */
                   locked group;
    int
                                    /* effective modifiers */
   unsigned int
                   mods;
   unsigned int
                   base mods;
                                    /* base modifiers */
                                    /* latched modifiers */
   unsigned int
                   latched mods;
                                    /* locked modifiers */
   unsigned int
                   locked_mods;
```

```
/* computed compatibility state */
    int
                   compat_state;
    unsigned char
                   grab mods;
                                     /* modifiers used for grabs */
                   compat_grab_mods; /* modifiers used for compatibility grabs */
    unsigned char
   unsigned char
                   lookup mods;
                                     /* modifiers used to lookup symbols */
    unsigned char
                   compat_lookup_mods; /* mods used for compatibility look up */
                   ptr buttons;
                                     /* core pointer buttons */
    int
   KeyCode
                   keycode;
                                     /* keycode causing event,
                                        0 if programmatic */
                   event_type;
                                     /* core event if req_major or req_minor
    char
                                        non zero */
                                     /* major request code if program trigger,
    char
                   req_major;
                                        else 0 */
    char
                   req minor;
                                     /* minor request code if program trigger,
                                        else 0 */
} XkbStateNotifyEvent;
```

When you receive an XkbStateNotify event, the *changed* field indicates which elements of keyboard state have changed. This will be the bitwise inclusive OR of one or more of the XkbStateNotify event detail masks shown in Table 5.3. All fields reported in the event are valid, but only those indicated in *changed* have changed values.

The group field is the group index of the effective keysym group. The base\_group, latched\_group, and locked\_group fields are set to a group index value representing the base group, the latched group, and the locked group, respectively. The X server can set the modifier and compatibility state fields to a union of the core modifier mask bits; this union represents the corresponding modifier states. The ptr\_buttons field gives the state of the core pointer buttons as a mask composed of an inclusive OR of zero or more of the core pointer button masks.

Xkb state changes can occur either in response to keyboard activity or under application control. If a key event caused the state change, the <code>keycode</code> field gives the keycode of the key event, and the <code>event\_type</code> field is set to either KeyPress or KeyRelease. If a pointer button event caused the state change, the <code>keycode</code> field is zero, and the <code>event\_type</code> field is set to either ButtonPress or ButtonRelease. Otherwise, the major and minor codes of the request that caused the state change are given in the <code>req\_major</code> and <code>req\_minor</code> fields, and the <code>keycode</code> field is zero. The <code>req\_major</code> value is the same as the major extension opcode.

# Chapter 6. Complete Keyboard Description

The complete Xkb description for a keyboard device is accessed using a single structure containing pointers to major Xkb components. This chapter describes this single structure and provides references to other sections of this document that discuss the major Xkb components in detail.

#### The XkbDescRec Structure

The complete description of an Xkb keyboard is given by an XkbDescRec. The component structures in the XkbDescRec represent the major Xkb components outlined in Figure 1.1.

```
typedef struct {
    struct _XDisplay *
                                         /* connection to X server */
                        display;
                                         /* private to Xkb, do not modify */
    unsigned short
                        flags;
   unsigned short
                                         /* device of interest */
                        device_spec;
                                         /* minimum keycode for device */
   KeyCode
                        min_key_code;
                                         /* maximum keycode for device */
   KeyCode
                        max_key_code;
   XkbControlsPtr
                        ctrls;
                                         /* controls */
                                         /* server keymap */
   XkbServerMapPtr
                        server;
   XkbClientMapPtr
                        map;
                                         /* client keymap */
                                         /* indicator map */
   XkbIndicatorPtr
                        indicators;
                                         /* names for all components */
   XkbNamesPtr
                        names;
                                         /* compatibility map */
   XkbCompatMapPtr
                        compat;
   {\tt XkbGeometryPtr}
                                         /* physical geometry of keyboard */
                        qeom;
} XkbDescRec, *XkbDescPtr;
```

The <code>display</code> field points to an X display structure. The <code>flags</code> field is private to the library: modifying <code>flags</code> may yield unpredictable results. The <code>device\_spec</code> field specifies the device identifier of the keyboard input device, or XkbUseCoreKbd, which specifies the core keyboard device. The <code>min\_key\_code</code> and <code>max\_key\_code</code> fields specify the least and greatest keycode that can be returned by the keyboard.

The other fields specify structure components of the keyboard description and are described in detail in other sections of this document. Table 6.1 identifies the subsequent sections of this document that discuss the individual components of the XkbDescRec.

Table 6.1. XkbDescRec Component References

XkbDescRec Field	For more info
ctrls	Chapter 10, Keyboard Controls
server	Chapter 16, Xkb Server Keyboard Mapping
map	Chapter 15, Xkb Client Keyboard Mapping
indicators	Chapter 8, Indicators
names	Chapter 18, Symbolic Names
compat	Chapter 17, The Xkb Compatibility Map
geom	Chapter 13, Keyboard Geometry

Each structure component has a corresponding mask bit that is used in function calls to indicate that the structure should be manipulated in some manner, such as allocating it or freeing it. These masks and their relationships to the fields in the XkbDescRec are shown in Table 6.2.

Table 6.2. Mask Bits for XkbDescRec

Mask Bit	XkbDescRec Field	Value
XkbControlsMask	ctrls	(1L<<0)
XkbServerMapMask	server	(1L<<1)
XkbIClientMapMask	map	(1L<<2)
XkbIndicatorMapMask	indicators	(1L<<3)
XkbNamesMask	names	(1L<<4)
XkbCompatMapMask	compat	(1L<<5)
XkbGeometryMask	geom	(1L<<6)
XkbAllComponentsMask	All Fields	(0x7f)

# Obtaining a Keyboard Description from the Server

To retrieve one or more components of a keyboard device description, use XkbGetKeyboard (see also XkbGetKeyboardByName).

XkbDescPtr XkbGetKeyboard(display, which, device\_spec);

display connection to X server

which mask indicating components to return

device\_spec device for which to fetch description, or XkbUseCoreKbd

XkbGetKeyboard allocates and returns a pointer to a keyboard description. It queries the server for those components specified in the *which* parameter for device *device\_spec* and copies the results to the XkbDescRec it allocated. The remaining fields in the keyboard description are set to NULL. The valid masks for *which* are those listed in Table 6.2.

XkbGetKeyboard can generate BadAlloc protocol errors.

To free the returned keyboard description, use XkbFreeKeyboard (see section 6.4).

## Tracking Changes to the Keyboard Description in the Server

The server can generate events whenever its copy of the keyboard description for a device changes. Refer to section 14.4 for detailed information on tracking changes to the keyboard description.

## Allocating and Freeing a Keyboard Description

Applications seldom need to directly allocate a keyboard description; calling XkbGetKeyboard usually suffices. In the event you need to create a keyboard description from scratch, however, use XkbAllocKeyboard rather than directly calling malloc or Xmalloc.

```
XkbDescRec *XkbAllocKeyboard();
```

If XkbAllocKeyboard fails to allocate the keyboard description, it returns NULL. Otherwise, it returns a pointer to an empty keyboard description structure. The <code>device\_spec</code> field will have been initialized to XkbUseCoreKbd. You may then either fill in the structure components or use Xkb functions to obtain values for the structure components from a keyboard device.

To destroy either an entire an XkbDescRec or just some of its members, use XkbFreeKeyboard.

void XkbFreeKeyboard(xkb, which, free\_all);

*xkb* keyboard description with components to free

which mask selecting components to free

free\_all True  $\Rightarrow$  free all components and xkb

XkbFreeKeyboard frees the components of xkb specified by which and sets the corresponding values to NULL. If free\_all is True, XkbFreeKeyboard frees every non-NULL component of xkb and then frees the xkb structure itself.

## **Chapter 7. Virtual Modifiers**

The core protocol specifies that certain keysyms, when bound to modifiers, affect the rules of keycode to keysym interpretation for all keys; for example, when the Num\_Lock keysym is bound to some modifier, that modifier is used to select between shifted and unshifted state for the numeric keypad keys. The core protocol does not provide a convenient way to determine the mapping of modifier bits (in particular Mod1 through Mod5) to keysyms such as Num\_Lock and Mode\_switch. Using the core protocol only, a client application must retrieve and search the modifier map to determine the keycodes bound to each modifier, and then retrieve and search the keyboard mapping to determine the keysyms bound to the keycodes. It must repeat this process for all modifiers whenever any part of the modifier mapping is changed.

Xkb alleviates these problems by defining virtual modifiers. In addition to the eight core modifiers, referred to as the *real modifiers*, Xkb provides a set of sixteen named *virtual modifiers*. Each virtual modifier can be bound to any set of the real modifiers (Shift, Lock, Control, and Mod1 – Mod5).

The separation of function from physical modifier bindings makes it easier to specify more clearly the intent of a binding. X servers do not all assign modifiers the same way — for example, Num\_Lock might be bound to Mod2 for one vendor and to Mod4 for another. This makes it cumbersome to automatically remap the keyboard to a desired configuration without some kind of prior knowledge about the keyboard layout and bindings. With XKB, applications can use virtual modifiers to specify the desired behavior, without regard for the actual physical bindings in effect.

#### Virtual Modifier Names and Masks

Virtual modifiers are named by converting their string name to an X Atom and storing the Atom in the names.vmods array in an XkbDescRec structure (see section 6.1). The position of a name Atom in the names.vmods array defines the bit position used to represent the virtual modifier and also the index used when accessing virtual modifier information in arrays: the name in the i-th (0 relative) entry of names.vmods is the i-th virtual modifier, represented by the mask (1<<ii). Throughout Xkb, various functions have a parameter that is a mask representing virtual modifier choices. In each case, the i-th bit (0 relative) of the mask represents the i-th virtual modifier.

To set the name of a virtual modifier, use XkbSetNames, using XkbVirtualModNamesMask in which and the name in the xkb argument; to retrieve indicator names, use XkbGetNames. These functions are discussed in Chapter 18, Symbolic Names.

### **Modifier Definitions**

An Xkb *modifier definition* enumerates a collection of real and virtual modifiers but does not in itself bind those modifiers to any particular key or to each other. Modifier definitions are included in a number of structures in the keyboard description to define the collection of modifiers that affect or are affected by some other entity. A modifier definition is relevant only in the context of some other entity such as an indicator map, a control, or a key type. (See section 8.2.2, section 10.8, and section 15.2.)

An Xkb modifier definition consists of a set of bit masks corresponding to the eight real modifiers (real\_mods); a similar set of bitmasks corresponding to the 16 named virtual modifiers (vmods); and

an effective mask (mask). The effective mask represents the set of all real modifiers that can logically be set either by setting any of the real modifiers or by setting any of the virtual modifiers in the definition. mask is derived from the real and virtual modifiers and should never be explicitly changed — it contains all of the real modifiers specified in the definition (real\_mods) plus any real modifiers that are bound to the virtual modifiers specified in the definition (vmods). The binding of the virtual modifiers to real modifiers is exterior to the modifier definition. Xkb automatically recomputes the mask field of modifier definitions as necessary. Whenever you access a modifier definition that has been retrieved using an Xkb library function, the mask field will be correct for the keyboard mapping of interest.

## **Binding Virtual Modifiers to Real Modifiers**

The binding of virtual modifiers to real modifiers is defined by the *server.vmods* array in an XkbDescRec structure. Each entry contains the real modifier bits that are bound to the virtual modifier corresponding to the entry. The overall relationship of fields dealing with virtual modifiers in the server keyboard description are shown in Figure 16.2.

## Virtual Modifier Key Mapping

Xkb maintains a *virtual modifier mapping*, which lists the virtual modifiers associated with, or bound to, each key. The real modifiers bound to a virtual modifier always include all of the modifiers bound to any of the keys that specify that virtual modifier in their virtual modifier mapping. The server.vmodmap array indicates which virtual modifiers are bound to each key; each entry is a bitmask for the virtual modifier bits. The server.vmodmap array is indexed by keycode.

The *vmodmap* and *vmods* members of the server map are the "master" virtual modifier definitions. Xkb automatically propagates any changes to these fields to all other fields that use virtual modifier mappings (see section 16.4).

For example, if Mod3 is bound to the Num\_Lock key by the core protocol modifier mapping, and the *NumLock* virtual modifier is bound to they Num\_Lock key by the virtual modifier mapping, Mod3 is added to the set of modifiers associated with *NumLock*.

The virtual modifier mapping is normally updated whenever actions are automatically applied to symbols (see section 16.4 for details), and few applications should need to change the virtual modifier mapping explicitly.

Use XkbGetMap (see section 14.2) to get the virtual modifiers from the server or use XkbGetVirtualMods (see section 16.4.1) to update a local copy of the virtual modifiers bindings from the server. To set the binding of a virtual modifier to a real modifier, use XkbSetMap (see section 14.3).

To determine the mapping of virtual modifiers to core X protocol modifiers, use XkbVirtualModsToReal.

Bool **XkbVirtualModsToReal**(xkb, virtual mask, mask rtrn);

xkb keyboard description for input device

virtual mask virtual modifier mask to translate

mask\_rtrn backfilled with real modifiers

If the keyboard description defined by xkb includes bindings for virtual modifiers, XkbVirtualModsToReal uses those bindings to determine the set of real modifiers that correspond to the set of virtual modifiers specified in  $virtual\_mask$ . The  $virtual\_mask$  parameter is a mask

specifying the virtual modifiers to translate; the i-th bit (0 relative) of the mask represents the i-th virtual modifier. If mask\_rtrn is non- NULL, XkbVirtualModsToReal backfills it with the resulting real modifier mask. If the keyboard description in xkb does not include virtual modifier bindings, XkbVirtualModsToReal returns False; otherwise, it returns True.

#### Note

It is possible for a local (client-side) keyboard description (the xkb parameter) to not contain any virtual modifier information (simply because the client has not requested it) while the server's corresponding definition may contain virtual modifier information.

#### **Inactive Modifier Sets**

An unbound virtual modifier is one that is not bound to any real modifier ( server->vmods [virtual\_modifier\_index] is zero).

Some Xkb operations ignore modifier definitions in which the virtual modifiers are unbound. Consider this example:

```
if (state matches {Shift}) Do OneThing;
if (state matches {Shift+NumLock}) Do Another;
```

If the *NumLock* virtual modifier is not bound to any real modifiers, the effective masks for these two cases are identical (that is, contain only Shift). When it is essential to distinguish between *OneThing* and Another, Xkb considers only those modifier definitions for which all virtual modifiers are bound.

#### **Conventions**

The Xkb extension does not require any specific virtual modifier names. However, everyone benefits if the same names are used for common modifiers. The following names are suggested:

NumLock ScrollLock Alt Meta AltGr LevelThree

## **Example**

If the second (0-relative) entry in names.vmods contains the Atom for "NumLock", then 0x4 (1<<2) is the virtual modifier bit for the *NumLock* virtual modifier. If server.vmods [2] contains Mod3Mask, then the *NumLock* virtual modifier is bound to the Mod3 real modifier.

A virtual modifier definition for this example would have:

```
real_mods = 0
vmods = 0x4 (NumLock named virtual modifier)
mask = 0x20 (Mod3Mask)
```

Continuing the example, if the keyboard has a Num\_Lock keysym bound to the key with keycode 14, and the *NumLock* virtual modifier is bound to this key, *server.vmodmap[14]* contains 0x4.

Finally, if the keyboard also used the real Mod1 modifier for numeric lock operations, the modifier definition below would represent the situation where either the key bound to Mod1 or the *NumLock* virtual modifier could be used for this purpose:

```
real_mods = 0x8 (Mod1Mask)
vmods = 0x4 (NumLock named virtual modifier)
mask = 0x28 (Mod1Mask | Mod3Mask)
```

## **Chapter 8. Indicators**

Although the core X implementation supports up to 32 LEDs on an input device, it does not provide any linkage between the state of the LEDs and the logical state of the input device. For example, most keyboards have a CapsLock LED, but X does not provide a mechanism to make the LED automatically follow the logical state of the **CapsLock** key.

Furthermore, the core X implementation does not provide clients with the ability to determine what bits in the <code>led\_mask</code> field of the XKeyboardState map to the particular LEDs on the keyboard. For example, X does not provide a method for a client to determine what bit to set in the <code>led\_mask</code> field to turn on the Scroll Lock LED or whether the keyboard even has a Scroll Lock LED.

Xkb provides indicator names and programmable indicators to help solve these problems. Using Xkb, clients can determine the names of the various indicators, determine and control the way that the individual indicators should be updated to reflect keyboard changes, and determine which of the 32 keyboard indicators reported by the protocol are actually present on the keyboard. Clients may also request immediate notification of changes to the state of any subset of the keyboard indicators, which makes it straightforward to provide an on-screen "virtual" LED panel. This chapter describes Xkb indicators and the functions used for manipulating them.

#### **Indicator Names**

Xkb provides the capability of symbolically naming indicators. Xkb itself doesn't use these symbolic names for anything; they are there only to help make the keyboard description comprehensible to humans. To set the names of specific indicators, use XkbSetNames as discussed in Chapter 18, Symbolic Names. Then set the map using XkbSetMap (see section 14.3) or XkbSetNamedDeviceIndicator (below). To retrieve indicator names, use XkbGetNames (Chapter 18, Symbolic Names).

#### **Indicator Data Structures**

Use the indicator description record, XkbIndicatorRec, and its indicator map, XkbIndicatorMapRec, to inquire about and control most indicator properties and behaviors.

#### **XkbIndicatorRec**

The description for all the Xkb indicators is held in the <code>indicators</code> field of the complete keyboard description (see Chapter 6, Complete Keyboard Description), which is defined as follows:

This structure contains the *phys\_indicators* field, which relates some information about the correspondence between indicators and physical LEDs on the keyboard, and an array of indicator *maps*, one map per indicator.

The phys\_indicators field indicates which indicators are bound to physical LEDs on the keyboard; if a bit is set in phys\_indicators, then the associated indicator has a physical LED associated with it. This field is necessary because some indicators may not have corresponding physical LEDs on the

keyboard. For example, most keyboards have an LED for indicating the state of **CapsLock**, but most keyboards do not have an LED that indicates the current group. Because <code>phys\_indicators</code> describes a physical characteristic of the keyboard, you cannot directly change it under program control. However, if a client program loads a completely new keyboard description via XkbGetKeyboardByName, or if a new keyboard is attached and the X implementation notices, <code>phys\_indicators</code> changes if the indicators for the new keyboard are different.

#### XkbIndicatorMapRec

Each indicator has its own set of attributes that specify whether clients can explicitly set its state and whether it tracks the keyboard state. The attributes of each indicator are held in the *maps* array, which is an array of XkbIndicatorRec structures:

```
typedef struct {
   unsigned char
                                  /* how the indicator can be changed */
                   flags;
                                  /* match criteria for groups */
   unsigned char
                   which groups;
                                  /* which keyboard groups the indicator watches *
   unsigned char
                   groups;
                                  /* match criteria for modifiers */
   unsigned char
                   which mods;
   XkbModsRec
                   mods;
                                  /* which modifiers the indicator watches */
   unsigned int
                                  /* which controls the indicator watches */
                   ctrls;
} XkbIndicatorMapRec, *XkbIndicatorMapPtr;
```

This indicator map specifies for each indicator:

- · The conditions under which the keyboard modifier state affects the indicator
- The conditions under which the keyboard group state affects the indicator
- The conditions under which the state of the boolean controls affects the indicator
- The effect (if any) of attempts to explicitly change the state of the indicator using the functions XkbSetControls or XChangeKeyboardControl

For more information on the effects of explicit changes to indicators and the relationship to the indicator map, see section 8.4.1.

#### XkbIndicatorMapRec flags field

The flags field specifies the conditions under which the indicator can be changed and the effects of changing the indicator. The valid values for flags and their effects are shown in Table 8.1.

Table 8.1. XkbIndicatorMapRec flags Field

Value		Effect
XkbIM_NoExplicit	(1L<<7)	Client applications cannot change the state of the indicator.
XkbIM_NoAutomatic	(1L<<6)	Xkb does not automatically change the value of the indicator based upon a change in the keyboard state, regardless of the values for the other fields of the indicator map.
XkbIM_LEDDrivesKB	(1L<<5)	A client application changing the state of the indicator causes the state of the keyboard to change.

Note that if XkbIM\_NoAutomatic is not set, by default the indicator follows the keyboard state.

If XkbIM\_LEDDrivesKB is set and XkbIM\_NoExplicit is not, and if you call a function which updates the server's image of the indicator map (such as XkbSetIndicatorMap or XkbSetNamedDeviceIndicator), Xkb changes the keyboard state and controls to reflect the other fields of the indicator map, as described in the remainder of this section. If you attempt to explicitly change the value of an indicator for which XkbIM\_LEDDrivesKB is absent or for which XkbIM\_NoExplicit is present, keyboard state or controls are unaffected.

For example, a keyboard designer may want to make the CapsLock LED controllable only by the server, but allow the Scroll Lock LED to be controlled by client applications. To do so, the keyboard designer could set the XkbIM\_NoExplicit flag for the CapsLock LED, but not set it for the Scroll Lock LED. Or the keyboard designer may wish to allow the CapsLock LED to be controlled by both the server and client applications and also have the server to automatically change the *CapsLock* modifier state whenever a client application changes the CapsLock LED. To do so, the keyboard designer would not set the XkbIM\_NoExplicit flag, but would instead set the XkbIM\_LEDDrivesKB flag.

The remaining fields in the indicator map specify the conditions under which Xkb automatically turns an indicator on or off (only if XkbIM\_NoAutomatic is not set). If these conditions match the keyboard state, Xkb turns the indicator on. If the conditions do not match, Xkb turns the indicator off.

#### XkbIndicatorMapRec which\_groups and groups fields

The which\_groups and the groups fields of an indicator map determine how the keyboard group state affects the corresponding indicator. The which\_groups field controls the interpretation of groups and may contain any one of the following values:

The *groups* field specifies what keyboard groups an indicator watches and is the bitwise inclusive OR of the following valid values:

```
#define XkbGroup1Mask (1<<0)
#define XkbGroup2Mask (1<<1)
#define XkbGroup3Mask (1<<2)
#define XkbGroup4Mask (1<<3)
#define XkbAnyGroupMask (1<<7)
#define XkbAllGroupsMask (0xf)
```

If XkbIM\_NoAutomatic is not set (the keyboard drives the indicator), the effect of which\_groups and groups is shown in Table 8.2.

 ${\bf Table~8.2.~XkbIndicatorMapRec~which\_groups~and~groups,~Keyboard~Drives~Indicator}$ 

which_groups	Effect
XkbIM_UseNone	The groups field and the current keyboard group state are ignored.
XkbIM_UseBase	If <i>groups</i> is nonzero, the indicator is lit whenever the base keyboard group is nonzero. If <i>groups</i> is zero, the indicator is lit whenever the base keyboard group is zero.
XkbIM_UseLatched	If <i>groups</i> is nonzero, the indicator is lit whenever the latched keyboard group is nonzero. If <i>groups</i> is zero, the indicator is lit whenever the latched keyboard group is zero.
XkbIM_UseLocked	The <i>groups</i> field is interpreted as a mask. The indicator is lit when the current locked keyboard group matches one of the bits that are set in <i>groups</i> .
XkbIM_UseEffective	The <i>groups</i> field is interpreted as a mask. The indicator is lit when the current effective keyboard group matches one of the bits that are set in <i>groups</i> .

The effect of which\_groups and groups when you change an indicator for which XkbIM\_LEDDrivesKB is set (the indicator drives the keyboard) is shown in Table 8.3. The "New State" column refers to the new state to which you set the indicator.

Table 8.3. XkbIndicatorMapRec which\_groups and groups, Indicator Drives Keyboard

which_groups	New State	Effect on Keyboard Group State
XkbIM_UseNone	On or Off	No effect
XkbIM_UseBase	On or Off	No effect
XkbIM_UseLatched	On	The <i>groups</i> field is treated as a group mask. The keyboard group latch is changed to the lowest numbered group specified in <i>groups</i> ; if <i>groups</i> is empty, the keyboard group latch is changed to zero.
XkbIM_UseLatched	Off	The <i>groups</i> field is treated as a group mask. If the indicator is explicitly extinguished, keyboard group latch is changed to the lowest numbered group not specified in <i>groups</i> ; if <i>groups</i> is zero, the keyboard group latch is set to the index of the highest legal keyboard group.
XkbIM_UseLocked or XkbIM_UseEffective	On	If the <i>groups</i> mask is empty, group is not changed; otherwise, the locked keyboard group is changed to the lowest numbered group specified in <i>groups</i> .
XkbIM_UseLocked or XkbIM_UseEffective	Off	Locked keyboard group is changed to the lowest numbered group that is not specified in the <i>groups</i> mask, or to <i>Group1</i> if the <i>groups</i> mask contains all keyboard groups.

#### XkbIndicatorMapRec which\_mods and mods fields

The mods field specifies what modifiers an indicator watches. The mods field is an Xkb modifier definition, XkbModsRec, as described in section 7.2, which can specify both real and virtual modifiers. The mods field takes effect even if some or all of the virtual indicators specified in mods are unbound. To specify the mods field, in general, assign the modifiers of interest to mods.real\_mods and the virtual modifiers of interest to mods.vmods. You can disregard the mods.mask field unless your application needs to interpret the indicator map directly (that is, to simulate automatic indicator behavior on its own). Relatively few applications need to do so, but if you find it necessary, you can either read the indicator map back from the server after you update it (the server automatically updates the mask field whenever any of the real or virtual modifiers are changed in the modifier definition) or you can use XkbVirtualModsToReal to determine the proper contents for the mask field, assuming that the XkbDescRec contains the virtual modifier definitions.

which\_mods specifies what criteria Xkb uses to determine a match with the corresponding mods field by specifying one or more components of the Xkb keyboard state. If XkbIM\_NoAutomatic is not set (the keyboard drives the indicator), the indicator is lit whenever any of the modifiers specified in the mask field of the mods modifier definition are also set in any of the current keyboard state components specified by which\_mods. Remember that the mask field is comprised of all of the real modifiers specified in the definition plus any real modifiers that are bound to the virtual modifiers specified in the definition. (See Chapter 5, Keyboard State for more information on the keyboard state and Chapter 7, Virtual Modifiers for more information on virtual modifiers.) Use a bitwise inclusive OR of the following values to compose a value for which\_mods:

If XkbIM\_NoAutomatic is not set (the keyboard drives the indicator), the effect of which\_mods and mods is shown in Table 8.4

 ${\bf Table~8.4.~XkbIndicatorMapRec~which\_mods~and~mods,~Keyboard~Drives~Indicator}$ 

which_mods	Effect on Keyboard Modifiers	
XkbIM_UseNone	The mods field and the current keyboard modifier state are ignored.	
XkbIM_UseBase	The indicator is lit when any of the modifiers specified in the <i>mask</i> field of <i>mods</i> are on in the keyboard base state. If both <i>mods.real_mods</i> and <i>mods.vmods</i> are zero, the indicator is lit when the base keyboard state contains no modifiers.	
XkbIM_UseLatched	The indicator is lit when any of the modifiers specified in the <i>mask</i> field of <i>mods</i> are latched. If both <i>mods.real_mods</i> and <i>mods.vmods</i> are zero, the indicator is lit when none of the modifier keys are latched.	
XkbIM_UseLocked	The indicator is lit when any of the modifiers specified in the <i>mask</i> field of <i>mods</i> are locked. If both <i>mods</i> . <i>real_mods</i> and <i>mods</i> . <i>vmods</i> are zero, the indicator is lit when none of the modifier keys are locked.	
XkbIM_UseEffective	The indicator is lit when any of the modifiers specified in the <i>mask</i> field of <i>mods</i> are in the effective keyboard state. If both <i>mods.real_mods</i> and <i>mods.vmods</i> are zero, the indicator is lit when the effective keyboard state contains no modifiers.	
XkbIM_UseCompat	The indicator is lit when any of the modifiers specified in the <i>mask</i> field of <i>mods</i> are in the keyboard compatibility state. If both <i>mods.real_mods</i> and <i>mods.vmods</i> are zero, the indicator is lit when the keyboard compatibility state contains no modifiers.	

The effect on the keyboard modifiers of which\_mods and mods when you change an indicator for which XkbIM\_LEDDrivesKB is set (the indicator drives the keyboard) is shown in Table 8.5. The "New State" column refers to the new state to which you set the indicator.

Table 8.5. XkbIndicatorMapRec which\_mods and mods, Indicator Drives Keyboard

which_mods	New State	Effect on Keyboard Modifiers
XkbIM_UseNone or XkbIM_UseBase	On or Off	No Effect
XkbIM_UseLatched	On	Any modifiers specified in the <i>mask</i> field of <i>mods</i> are added to the latched modifiers.
XkbIM_UseLatched	Off	Any modifiers specified in the <i>mask</i> field of <i>mods</i> are removed from the latched modifiers.
XkbIM_UseLocked, XkbIM_UseCompat, or XkbIM_UseEffective	On	Any modifiers specified in the <i>mask</i> field of <i>mods</i> are added to the locked modifiers.
XkbIM_UseLocked	Off	Any modifiers specified in the <i>mask</i> field of <i>mods</i> are removed from the locked modifiers.
XkbIM_UseCompat or XkbIM_UseEffective	Off	Any modifiers specified in the <i>mask</i> field of <i>mods</i> are removed from both the locked and latched modifiers.

#### XkbIndicatorMapRec ctrls field

The ctrls field specifies what controls (see Chapter 10, Keyboard Controls) the indicator watches and is composed using the bitwise inclusive OR of the following values:

```
(1L << 0)
#define XkbRepeatKeysMask
#define XkbSlowKeysMask
                                     (1L << 1)
                                     (1L << 2)
#define XkbBounceKeysMask
#define XkbStickyKeysMask
                                     (1L << 3)
#define XkbMouseKeysMask
                                     (1L << 4)
#define XkbMouseKeysAccelMask
                                     (1L << 5)
#define XkbAccessXKeysMask
                                     (1L << 6)
#define XkbAccessXTimeoutMask
                                     (1L << 7)
#define XkbAccessXFeedbackMask
                                     (1L << 8)
#define XkbAudibleBellMask
                                     (1L << 9)
#define XkbOverlay1Mask
                                     (1L << 10)
#define XkbOverlay2Mask
                                     (1L << 11)
#define XkbAllBooleanCtrlsMask
                                     (0x00001FFF)
```

Xkb lights the indicator whenever any of the boolean controls specified in ctrls is enabled.

## **Getting Information About Indicators**

Xkb allows applications to obtain information about indicators using two different methods. The first method, which is similar to the core X implementation, uses a mask to specify the indicators. The second method, which is more suitable for applications concerned with interoperability, uses indicator names. The correspondence between the indicator name and the bit position in masks is as follows: one of the parameters returned from XkbGetNamedDeviceIndicator is an index that is the bit position to use in any function call that requires a mask of indicator bits, as well as the indicator's index into the XkbIndicatorRec array of indicator maps.

#### **Getting Indicator State**

Because the state of the indicators is relatively volatile, the keyboard description does not hold the current state of the indicators. To obtain the current state of the keyboard indicators, use XkbGetIndicatorState.

```
Status XkbGetIndicatorState(display, device_spec, state_return);

display connection to the X server

device_spec device ID, or XkbUseCoreKbd

state_return backfilled with a mask of the indicator state
```

XkbGetIndicatorState queries the <code>display</code> for the state of the indicators on the device specified by the <code>device\_spec</code>. For each indicator that is "turned on" on the device, the associated bit is set in <code>state\_return</code>. If a compatible version of the Xkb extension is not available in the server, XkbGetIndicatorState returns a BadMatch error. Otherwise, it sends the request to the X server, places the state of the indicators into <code>state\_return</code>, and returns Success. Thus the value reported by XkbGetIndicatorState is identical to the value reported by the core protocol.

### **Getting Indicator Information by Index**

To get the map for one or more indicators, using a mask to specify the indicators, use XkbGetIndicatorMap.

Status **XkbGetIndicatorMap**(dpy, which, desc);

dpy connection to the X server

which mask of indicators for which maps should be returned

desc keyboard description to be updated

XkbGetIndicatorMap obtains the maps from the server for only those indicators specified by the which mask and copies the values into the keyboard description specified by desc. If the indicators field of the desc parameter is NULL, XkbGetIndicatorMap allocates and initializes it.

XkbGetIndicatorMap can generate BadAlloc, BadLength, BadMatch, and BadImplementation errors.

To free the indicator maps, use XkbFreeIndicatorMaps (see section 8.6).

#### **Getting Indicator Information by Name**

Xkb also allows applications to refer to indicators by name. Use XkbGetNames to get the indicator names (see Chapter 18, Symbolic Names). Using names eliminates the need for hard-coding bitmask values for particular keyboards. For example, instead of using vendor-specific constants such as WSKBLed\_ScrollLock mask on Digital workstations or XLED\_SCROLL\_LOCK on Sun workstations, you can instead use XkbGetNamedDeviceIndicator or XkbGetNamedIndicator to look up information on the indicator named "Scroll Lock."

Use XkbGetNamedDeviceIndicator to look up the indicator map and other information for an indicator by name on a specific device.

Bool **XkbGetNamedDeviceIndicator**(dpy, device\_spec, led\_class, led\_id, name, ndx\_rtrn, state\_rtrn, map\_rtrn, real\_rtrn);

dpy connection to the X server

device\_spec keyboard device ID, or XkbUseCoreKbd

led\_class feedback class, or XkbDfltXIClass

led\_id feedback ID, or XkbDfltXIId

name of the indicator to be retrieved

ndx\_rtrn backfilled with the index of the retrieved indicator

state\_rtrn backfilled with the current state of the retrieved indicator

map\_rtrn backfilled with the mapping for the retrieved indicator

real\_rtrn backfilled with True if the named indicator is real (physical)

If the device specified by device\_spec with feedback specified by led\_class and led\_id has an indicator named name, XkbGetNamedDeviceIndicator returns True and populates the rest of

the parameters with information about the indicator. Otherwise, XkbGetNamedDeviceIndicator returns False.

The  $ndx\_rtrn$  field returns the zero-based index of the named indicator. This index is the bit position to use in any function call that requires a mask of indicator bits, as well as the indicator's index into the XkbIndicatorRec array of indicator maps.  $state\_rtrn$  returns the current state of the named indicator (True = on, False = off).  $map\_rtrn$  returns the indicator map for the named indicator. In addition, if the indicator is mapped to a physical LED, the  $real\_rtrn$  parameter is set to True.

Each of the "\_rtrn" arguments is optional; you can pass NULL for any unneeded "\_rtrn" arguments.

XkbGetNamedDeviceIndicator can generate BadAtom and BadImplementation errors.

As a convenience function, Xkb provides a function to get information about indicators with the default class and identifier on the default device: XkbGetNamedIndicator.

Bool **XkbGetNamedIndicator**(dpy, name, ndx\_rtrn, state\_rtrn, map\_rtrn, real\_rtrn);

dpy connection to the X server

name of the indicator to be retrieved

ndx\_rtrn backfilled with the index of the retrieved indicator

state\_rtrn backfilled with the current state of the retrieved indicator

map\_rtrn backfilled with the mapping for the retrieved indicator

real\_rtrn backfilled with True if the named indicator is real (physical)

XkbGetNamedIndicator calls XkbGetNamedDeviceIndicator with the specified parameters, a device\_spec of XkbUseCoreKbd, a led\_class of XkbDfltXIClass, and a led\_id of XkbDfltXIId, and returns the value which was returned by XkbGetNamedDeviceIndicator.

## **Changing Indicator Maps and State**

Just as you can get the indicator map using a mask or using an indicator name, so you can change it using a mask or a name.

#### Note

You cannot change the *phys\_indicators* field of the indicators structure. The only way to change the *phys\_indicators* field is to change the keyboard map.

There are two ways to make changes to indicator maps and state: either change a local copy of the indicator maps and use XkbSetIndicatorMap or XkbSetNamedDeviceIndicator, or, to reduce network traffic, use an XkbIndicatorChangesRec structure and use XkbChangeIndicators.

#### **Effects of Explicit Changes on Indicators**

This section discusses the effects of explicitly changing indicators depending upon different settings in the indicator map. See Table 8.3 and Table 8.5 for information on the effects of the indicator map fields when explicit changes are made.

If XkbIM\_LEDDrivesKB is set and XkbIM\_NoExplicit is not, and if you call a function that updates the server's image of the indicator map (such as XkbSetIndicatorMap or XkbSetNamedDeviceIndicator), Xkb changes the keyboard state and controls to reflect the other fields of the indicator map. If you attempt to explicitly change the value of an indicator for which XkbIM\_LEDDrivesKB is absent or for which XkbIM\_NoExplicit is present, keyboard state or controls are unaffected.

If neither XkbIM\_NoAutomatic nor XkbIM\_NoExplicit is set in an indicator map, Xkb honors any request to change the state of the indicator, but the new state might be immediately superseded by automatic changes to the indicator state if the keyboard state or controls change.

The effects of changing an indicator that drives the keyboard are cumulative; it is possible for a single change to affect keyboard group, modifiers, and controls simultaneously.

If you change an indicator for which both the XkbIM\_LEDDrivesKB and XkbIM\_NoAutomatic flags are specified, Xkb applies the keyboard changes specified in the other indicator map fields and changes the indicator to reflect the state that was explicitly requested. The indicator remains in the new state until it is explicitly changed again.

If the XkbIM\_NoAutomatic flag is not set and XkbIM\_LEDDrivesKB is set, Xkb applies the changes specified in the other indicator map fields and sets the state of the indicator to the values specified by the indicator map. Note that it is possible in this case for the indicator to end up in a different state than the one that was explicitly requested. For example, Xkb does not extinguish an indicator with which\_mods of XkbIM\_UseBase and mods of Shift if, at the time Xkb processes the request to extinguish the indicator, one of the Shift keys is physically depressed.

If you explicitly light an indicator for which XkbIM\_LEDDrivesKB is set, Xkb enables all of the boolean controls specified in the ctrls field of its indicator map. Explicitly extinguishing such an indicator causes Xkb to disable all of the boolean controls specified in ctrls.

### **Changing Indicator Maps by Index**

To update the maps for one or more indicators, first modify a local copy of the keyboard description, then use XkbSetIndicatorMap to download the changes to the server:

Bool XkbSetIndicatorMap(dpy, which, desc);

dpy connection to the X server

which mask of indicators to change

desc keyboard description from which the maps are taken

For each bit set in the *which* parameter, XkbSetIndicatorMap sends the corresponding indicator map from the *desc* parameter to the server.

#### **Changing Indicator Maps by Name**

XkbSetNamedDeviceIndicator and XkbSetNamedIndicator can do several related things:

- · Name an indicator if it is not already named
- Toggle the state of the indicator
- Set the indicator to a specified state

• Set the indicator map for the indicator

BoolXkbSetNamedDeviceIndicator(dpy, device\_spec, led\_class, led\_id, name, change\_state, state, create\_new, map);

dpy connection to the X server

device spec device ID, or XkbUseCoreKbd

led\_class feedback class, or XkbDfltXIClass

led id feedback ID, or XkbDfltXIId

name of the indicator to change

change\_state whether to change the indicator state or not

state desired new state for the indicator

create\_new whether a new indicator with the specified name should be created

when necessary

map new map for the indicator

If a compatible version of the Xkb extension is not available in the server, XkbSetNamedDeviceIndicator returns False. Otherwise, it sends a request to the X server to change the indicator specified by *name* and returns True.

If change\_state is True, XkbSetNamedDeviceIndicator tells the server to change the state of the named indicator to the value specified by state. If change state is False, state is not used.

If an indicator with the name specified by *name* does not already exist, the *create\_new* parameter tells the server whether it should create a new named indicator. If *create\_new* is True, the server finds the first indicator that doesn't have a name and gives it the name specified by *name*.

If the optional parameter, map, is not NULL, XkbSetNamedDeviceIndicator tells the server to change the indicator's map to the values specified in map.

XkbSetNamedDeviceIndicator can generate BadAtom and BadImplementation errors. In addition, it can also generate XkbIndicatorStateNotify (see section 8.5), XkbIndicatorMapNotify, and XkbNamesNotify events (see section 18.5).

As a convenience function, Xkb provides a function to set information about indicators with the default class and identifier on the default device: XkbSetNamedIndicator.

 $\label{location} {\tt Bool} \textbf{XkbSetNamedIndicator}(\textit{dpy}, \textit{name}, \textit{change\_state}, \textit{state}, \textit{create\_new}, \\ \textit{map});$ 

dpy connection to the X server

name of the indicator to change

change\_state whether to change the indicator state or not

state desired new state for the indicator

create\_new whether a new indicator with the specified name should be created

when necessary

map new map for the indicator

XkbSetNamedIndicator calls XkbSetNamedDeviceIndicator with the specified parameters, a device\_spec of XkbUseCoreKbd, a led\_class of XkbDfltXIClass, and a led\_id of XkbDfltXIId, and returns the value which was returned by XkbSetNamedDeviceIndicator.

#### The XkbIndicatorChangesRec Structure

The XkbIndicatorChangesRec identifies small modifications to the indicator map. Use it with the function XkbChangeIndicators to reduce the amount of traffic sent to the server.

The state\_changes field is a mask that specifies the indicators that have changed state, and map\_changes is a mask that specifies the indicators whose maps have changed.

To change indicator maps or state without passing the entire keyboard description, use XkbChangeIndicators.

```
Bool XkbChangeIndicators(dpy, xkb, changes, state);
```

dpy connection to the X server

*xkb* keyboard description from which names are to be taken.

changes indicators to be updated on the server

state new state of indicators listed in changes->state\_changes

XkbChangeIndicators copies any maps specified by *changes* from the keyboard description, *xkb*, to the server specified by *dpy*. If any bits are set in the *state\_changes* field of *changes*, XkbChangeIndicators also sets the state of those indicators to the values specified in the *state* mask. A 1 bit in *state* turns the corresponding indicator on, a 0 bit turns it off.

XkbChangeIndicators can generate BadAtom and BadImplementation errors. In addition, it can also generate XkbIndicatorStateNotify and XkbIndicatorMapNotify events (see section 8.5).

## Tracking Changes to Indicator State or Map

Whenever an indicator changes state, the server sends XkbIndicatorStateNotify events to all interested clients. Similarly, whenever an indicator's map changes, the server sends XkbIndicatorMapNotify events to all interested clients.

To receive XkbIndicatorStateNotify events, use XkbSelectEvents (see section 4.3) with both the bits\_to\_change and values\_for\_bits parameters containing XkbIndicatorStateNotifyMask. To receive XkbIndicatorMapNotify events, use XkbSelectEvents with XkbIndicatorMapNotifyMask.

To receive events for only specific indicators, use XkbSelectEventDetails. Set the <code>event\_type</code> parameter to XkbIndicatorStateNotify or XkbIndicatorMapNotify, and set both the <code>bits\_to\_change</code> and <code>values\_for\_bits</code> detail parameters to a mask where each bit specifies one indicator, turning on those bits that specify the indicators for which you want to receive events.

Both types of indicator events use the same structure:

```
typedef struct _XkbIndicatorNotify {
                                /* Xkb extension base event code */
                   type;
   unsigned long
                                /* X server serial number for event */
                   serial;
                   send event;
                                /* True # synthetically generated */
   Bool
                                /* server connection where event generated */
   Display *
                   display;
   Time
                   time;
                                /* server time when event generated */
                   xkb_type;
                                /* specifies state or map notify */
    int
                                /* Xkb device ID, will not be XkbUseCoreKbd */
    int
                   device;
   unsigned int
                                /* mask of indicators with new state or map */
                   changed;
                                /* current state of all indicators */
   unsigned int
                   state;
} XkbIndicatorNotifyEvent;
```

*xkb\_type* is either XkbIndicatorStateNotify or XkbIndicatorMapNotify, depending on whether the event is a XkbIndicatorStateNotify event or XkbIndicatorMapNotify, event.

The *changed* parameter is a mask that is the bitwise inclusive OR of the indicators that have changed. If the event is of type XkbIndicatorMapNotify, *changed* reports the maps that changed. If the event is of type XkbIndicatorStateNotify, *changed* reports the indicators that have changed state. *state* is a mask that specifies the current state of all indicators, whether they have changed or not, for both XkbIndicatorStateNotify and XkbIndicatorMapNotify events.

When your client application receives either a XkbIndicatorStateNotify event or XkbIndicatorMapNotify event, you can note the changes in a changes structure by calling XkbNoteIndicatorChanges.

```
void XkbNoteIndicatorChanges(old, new, wanted);
```

New Event from which changes are to be copied wanted which changes are to be noted

The wanted parameter is the bitwise inclusive OR of XkbIndicatorMapMask and XkbIndicatorStateMask. XkbNoteIndicatorChanges copies any changes reported in new and specified in wanted into the changes record specified by old.

To update a local copy of the keyboard description with the actual values, pass the results of one or more calls to XkbNoteIndicatorChanges to XkbGetIndicatorChanges:

```
Status XkbGetIndicatorChanges(dpy, xkb, changes, state);
dpy connection to the X server
```

xkb keyboard description to hold the new values

changes indicator maps/state to be obtained from the server

state backfilled with the state of the indicators

XkbGetIndicatorChanges examines the *changes* parameter, pulls over the necessary information from the server, and copies the results into the *xkb* keyboard description. If any bits are set in the *state\_changes* field of *changes*, XkbGetIndicatorChanges also places the state of those indicators in *state*. If the *indicators* field of *xkb* is NULL, XkbGetIndicatorChanges

allocates and initializes it. To free the *indicators* field, use XkbFreeIndicatorMaps (see section 8.6).

XkbGetIndicatorChanges can generate BadAlloc, BadImplementation, and BadMatch errors.

## Allocating and Freeing Indicator Maps

Most applications do not need to directly allocate the <code>indicators</code> member of the keyboard description record (the keyboard description record is described in Chapter 6, <code>Complete Keyboard Description</code>). If the need arises, however, use <code>XkbAllocIndicatorMaps</code>.

Status **XkbAllocIndicatorMaps**(xkb);

xkb keyboard description structure

The xkb parameter must point to a valid keyboard description. If it doesn't, XkbAllocIndicatorMaps returns a BadMatch error. Otherwise, XkbAllocIndicatorMaps allocates and initializes the *indicators* member of the keyboard description record and returns Success. If XkbAllocIndicatorMaps was unable to allocate the indicators record, it reports a BadAlloc error.

To free memory used by the *indicators* member of an XkbDescRec structure, use XkbFreeIndicatorMaps.

void XkbFreeIndicatorMaps(xkb);

*xkb* keyboard description structure

If the *indicators* member of the keyboard description record pointed to by *xkb* is not NULL, XkbFreeIndicatorMaps frees the memory associated with the *indicators* member of *xkb*.

## Chapter 9. Bells

The core X protocol allows only applications to explicitly sound the system bell with a given duration, pitch, and volume. Xkb extends this capability by allowing clients to attach symbolic names to bells, disable audible bells, and receive an event whenever the keyboard bell is rung. For the purposes of this document, the *audible* bell is defined to be the system bell, or the default keyboard bell, as opposed to any other audible sound generated elsewhere in the system.

You can ask to receive XkbBellNotify events (see section 9.4) when any client rings any one of the following:

- · The default bell
- Any bell on an input device that can be specified by a bell\_class and bell\_id pair
- Any bell specified only by an arbitrary name. (This is, from the server's point of view, merely a name, and not connected with any physical sound-generating device. Some client application must generate the sound, or visual feedback, if any, that is associated with the name.)

You can also ask to receive XkbBellNotify events when the server rings the default bell or if any client has requested events only (without the bell sounding) for any of the bell types previously listed.

You can disable audible bells on a global basis (to set the *AudibleBell* control, see Chapter 10, *Keyboard Controls*). For example, a client that replaces the keyboard bell with some other audible cue might want to turn off the *AudibleBell* control to prevent the server from also generating a sound and avoid cacophony. If you disable audible bells and request to receive XkbBellNotify events, you can generate feedback different from the default bell.

You can, however, override the *AudibleBell* control by calling one of the functions that force the ringing of a bell in spite of the setting of the *AudibleBell* control — XkbForceDeviceBell or XkbForceBell (see section 9.3.3). In this case the server does not generate a bell event.

Just as some keyboards can produce keyclicks to indicate when a key is pressed or repeating, Xkb can provide feedback for the controls by using special beep codes. The *AccessXFeedback* control is used to configure the specific types of operations that generate feedback. See section 10.6.3 for a discussion on *AccessXFeedback* control.

This chapter describes bell names, the functions used to generate named bells, and the events the server generates for bells.

### **Bell Names**

You can associate a name to an act of ringing a bell by converting the name to an Atom and then using this name when you call the functions listed in this chapter. If an event is generated as a result, the name is then passed to all other clients interested in receiving XkbBellNotify events. Note that these are arbitrary names and that there is no binding to any sounds. Any sounds or other effects (such as visual bells on the screen) must be generated by a client application upon receipt of the bell event containing the name. There is no default name for the default keyboard bell. The server does generate some predefined bells for the AccessX controls (see section 10.6.3). These named bells are shown in Table 9.1; the name is included in any bell event sent to clients that have requested to receive XkbBellNotify events.

**Table 9.1. Predefined Bells** 

Action	Named Bell
Indicator turned on	AX_IndicatorOn
Indicator turned off	AX_IndicatorOff
More than one indicator changed state	AX_IndicatorChange
Control turned on	AX_FeatureOn
Control turned off	AX_FeatureOff
More than one control changed state	AX_FeatureChange
SlowKeys and BounceKeys about to be turned on or off	AX_SlowKeysWarning
SlowKeys key pressed	AX_SlowKeyPress
SlowKeys key accepted	AX_SlowKeyAccept
SlowKeys key rejected	AX_SlowKeyReject
Accepted SlowKeys key released	AX_SlowKeyRelease
BounceKeys key rejected	AX_BounceKeyReject
StickyKeys key latched	AX_StickyLatch
StickyKeys key locked	AX_StickyLock
StickyKeys key unlocked	AX_StickyUnlock

#### **Audible Bells**

Using Xkb you can generate bell events that do not necessarily ring the system bell. This is useful if you need to use an audio server instead of the system beep. For example, when an audio client starts, it could disable the audible bell (the system bell) and then listen for XkbBellNotify events (see section 9.4). When it receives a XkbBellNotify event, the audio client could then send a request to an audio server to play a sound.

You can control the audible bells feature by passing the XkbAudibleBellMask to XkbChangeEnabledControls (see section 10.1.1). If you set XkbAudibleBellMask on, the server rings the system bell when a bell event occurs. This is the default. If you set XkbAudibleBellMask off and a bell event occurs, the server does not ring the system bell unless you call XkbForceDeviceBell or XkbForceBell (see section 9.3.3).

Audible bells are also part of the per-client auto-reset controls. For more information on auto-reset controls, see section 10.1.2.

#### **Bell Functions**

Use the functions described in this section to ring bells and to generate bell events.

The input extension has two types of feedbacks that can generate bells — bell feedback and keyboard feedback. Some of the functions in this section have bell\_class and bell\_id parameters; set them as follows: Set bell\_class to BellFeedbackClass or KbdFeedbackClass. A device can have more than one feedback of each type; set bell\_id to the particular bell feedback of bell\_class type.

Table 9.2 shows the conditions that cause a bell to sound or an XkbBellNotifyEvent to be generated when a bell function is called.

Table 9.2. Bell Sounding and Bell Event Generating

<b>Function called</b>	AudibleBell	Server sounds a bell	Server sends an XkbBellNotifyEvent
XkbDeviceBell	On	Yes	Yes
XkbDeviceBell	Off	No	Yes
XkbBell	On	Yes	Yes
XkbBell	Off	No	Yes
XkbDeviceBellEvent	On or Off	No	Yes
XkbBellEvent	On or Off	No	Yes
XkbDeviceForceBell	On or Off	Yes	No
XkbForceBell	On or Off	Yes	No

#### **Generating Named Bells**

name

To ring the bell on an X input extension device or the default keyboard, use XkbDeviceBell.

Bool **XkbDeviceBell**(display, window, device\_spec, bell\_class, bell\_id, percent, name);

displayconnection to the X serverwindowwindow for which the bell is generated, or None $device\_spec$ device ID, or XkbUseCoreKbd $bell\_class$ X input extension bell class of the bell to be rung $bell\_id$ X input extension bell ID of the bell to be rungpercentbell volume, from  $_{-100}$  to 100 inclusive

Set percent to be the volume relative to the base volume for the keyboard as described for XBell.

a name for the bell, or NULL

Note that bell\_class and bell\_id indicate the bell to physically ring. name is simply an arbitrary moniker for the client application's use.

To determine the current feedback settings of an extension input device, use XGetFeedbackControl. See the X input extension documentation for more information on XGetFeedbackControl and related data structures.

If a compatible keyboard extension is not present in the X server, XkbDeviceBell immediately returns False. Otherwise, XkbDeviceBell rings the bell as specified for the display and keyboard device and returns True. If you have disabled the audible bell, the server does not ring the system bell, although it does generate a XkbBellNotify event.

You can call XkbDeviceBell without first initializing the keyboard extension.

As a convenience function, Xkb provides a function to ring the bell on the default keyboard: XkbBell.

Bool XkbBell(display, window, percent, name);

display connection to the X server

window event window, or None

percent relative volume, which can range from \_100 to 100 inclusive

name a bell name, or NULL

If a compatible keyboard extension isn't present in the X server, XkbBell calls XBell with the specified <code>display</code> and <code>percent</code>, and returns False. Otherwise, XkbBell calls XkbDeviceBell with the specified <code>display</code>, <code>window</code>, <code>percent</code>, and <code>name</code>, a <code>device\_spec</code> of XkbUseCoreKbd, a <code>bell\_class</code> of XkbDfltXIClass, and a <code>bell\_id</code> of XkbDfltXIId, and returns True.

If you have disabled the audible bell, the server does not ring the system bell, although it does generate a XkbBellNotify event.

You can call XkbBell without first initializing the keyboard extension.

#### **Generating Named Bell Events**

Using Xkb, you can also generate a named bell event that does not ring any bell. This allows you to do things such as generate events when your application starts.

For example, if an audio client listens for these types of bells, it can produce a "whoosh" sound when it receives a named bell event to indicate a client just started. In this manner, applications can generate start-up feedback and not worry about producing annoying beeps if an audio server is not running.

To cause a bell event for an X input extension device or for the keyboard, without ringing the corresponding bell, use XkbDeviceBellEvent.

Bool **XkbDeviceBellEvent**(display, window, device\_spec, bell\_class, bell\_id, percent, name);

display connection to the X server

window event window, or None

device\_spec device ID, or XkbUseCoreKbd

be 11\_class input extension bell class for the event

bell\_id input extension bell ID for the event

percent volume for the bell, which can range from  $_{-100}$  to 100 inclusive

name a bell name, or NULL

If a compatible keyboard extension isn't present in the X server, XkbDeviceBellEvent immediately returns False. Otherwise, XkbDeviceBellEvent causes an XkbBellNotify event to be sent to all interested clients and returns True. Set percent to be the volume relative to the base volume for the keyboard as described for XBell.

In addition, XkbDeviceBellEvent may generate Atom protocol errors as well as XkbBellNotify events. You can call XkbBell without first initializing the keyboard extension.

As a convenience function, Xkb provides a function to cause a bell event for the keyboard without ringing the bell: XkbBellEvent.

Bool **XkbBellEvent**(display, window, percent, name);

display connection to the X server

window the event window, or None

percent relative volume, which can range from \_100 to 100 inclusive

name a bell name, or NULL

If a compatible keyboard extension isn't present in the X server, XkbBellEvent immediately returns False. Otherwise, XkbBellEvent calls XkbDeviceBellEvent with the specified display, window, percent, and name, a device\_spec of XkbUseCoreKbd, a bell\_class of XkbDfltXIClass, and a bell\_id of XkbDfltXIId, and returns what XkbDeviceBellEvent returns.

XkbBellEvent generates a XkbBellNotify event.

You can call XkbBellEvent without first initializing the keyboard extension.

#### Forcing a Server-Generated Bell

To ring the bell on any keyboard, overriding user preference settings for audible bells, use XkbForceDeviceBell.

Bool **XkbForceDeviceBell**(display, window, device\_spec, bell\_class, bell id, percent);

display connection to the X server

window event window, or None

device\_spec device ID, or XkbUseCoreKbd

bell\_class input extension class of the bell to be rung

bell\_id input extension ID of the bell to be rung

percent relative volume, which can range from \_100 to 100 inclusive

If a compatible keyboard extension isn't present in the X server, XkbForceDeviceBell immediately returns False. Otherwise, XkbForceDeviceBell rings the bell as specified for the display and keyboard device and returns True. Set percent to be the volume relative to the base volume for the keyboard as described for XBell. There is no name parameter because XkbForceDeviceBell does not cause an XkbBellNotify event.

You can call XkbBell without first initializing the keyboard extension.

To ring the bell on the default keyboard, overriding user preference settings for audible bells, use XkbForceBell.

Bool XkbForceBell(display, percent);

display connection to the X server

percent volume for the bell, which can range from  $_{-100}$  to 100 inclusive

If a compatible keyboard extension isn't present in the X server, XkbForceBell calls XBell with the specified *display* and *percent* and returns False. Otherwise, XkbForceBell

calls XkbForceDeviceBell with the specified display and percent, device\_spec = XkbUseCoreKbd, bell\_class = XkbDfltXIClass, bell\_id = XkbDfltXIId, window = None, and name = NULL and returns what XkbForceDeviceBell returns.

XkbForceBell does not cause an XkbBellNotify event.

You can call XkbBell without first initializing the keyboard extension.

## **Detecting Bells**

Xkb generates XkbBellNotify events for all bells except for those resulting from calls to XkbForceDeviceBell and XkbForceBell. To receive XkbBellNotify events under all possible conditions, pass XkbBellNotifyMask in both the bits\_to\_change and values\_for\_bits parameters to XkbSelectEvents (see section 4.3).

The XkbBellNotify event has no event details. It is either selected or it is not. However, you can call XkbSelectEventDetails using XkbBellNotify as the event\_type and specifying XkbAllBellEventsMask in bits\_to\_change and values\_for\_bits. This has the same effect as a call to XkbSelectEvents.

The structure for the XkbBellNotify event type contains:

```
typedef struct _XkbBellNotify {
                                  /* Xkb extension base event code */
    int
                    type;
                                  /* X server serial number for event */
    unsigned long
                    serial;
                                 /* True # synthetically generated */
    Bool
                    send event;
                                  /* server connection where event generated */
   Display *
                    display;
   Time
                    time;
                                  /* server time when event generated */
                                  /* XkbBellNotify */
    int
                    xkb_type;
    unsigned int
                    device;
                                  /* Xkb device ID, will not be XkbUseCoreKbd */
    int
                    percent;
                                  /* requested volume as % of max */
    int
                    pitch;
                                  /* requested pitch in Hz */
    int
                    duration;
                                  /* requested duration in microseconds */
                                 /* X input extension feedback class */
                    bell_class;
    unsigned int
    unsigned int
                    bell_id;
                                  /* X input extension feedback ID */
                                  /* "name" of requested bell */
   Atom
                    name;
    Window
                    window;
                                  /* window associated with event */
                                 /* False # the server did not produce a beep */
    Bool
                    event_only;
} XkbBellNotifyEvent;
```

If your application needs to generate visual bell feedback on the screen when it receives a bell event, use the window ID in the XkbBellNotifyEvent, if present.

## **Chapter 10. Keyboard Controls**

The Xkb extension is composed of two parts: a server extension, and a client-side X library extension. This chapter discusses functions used to modify controls effecting the behavior of the server portion of the Xkb extension. Chapter 11, *X Library Controls* discusses functions used to modify controls that affect only the behavior of the client portion of the extension; those controls are known as Library Controls.

Xkb contains control features that affect the entire keyboard, known as global keyboard controls. Some of the controls may be selectively enabled and disabled; these controls are known as the *Boolean Controls*. Boolean Controls can be turned on or off under program control and can also be automatically set to an on or off condition when a client program exits. The remaining controls, known as the *Non-Boolean Controls*, are always active. The XkbControlsRec structure describes the current state of most of the global controls and the attributes effecting the behavior of each of these Xkb features. This chapter describes the Xkb controls and how to manipulate them.

There are two possible components for each of the Boolean Controls: attributes describing how the control should work, and a state describing whether the behavior as a whole is enabled or disabled. The attributes and state for most of these controls are held in the XkbControlsRec structure (see section 10.8).

You can manipulate the Xkb controls individually, via convenience functions, or as a whole. To treat them as a group, modify an XkbControlsRec structure to describe all of the changes to be made, and then pass that structure and appropriate flags to an Xkb library function, or use a XkbControlsChangesRec (see section 10.10.1) to reduce network traffic. When using a convenience function to manipulate one control individually, you do not use an XkbControlsRec structure directly.

The Xkb controls are grouped as shown in Table 10.1.

Table 10.1. Xkb Keyboard Controls

Type of Control	Control Name	<b>Boolean Control?</b>
Controls for enabling and disabling other controls	EnabledControls	No
	AutoReset	No
Control for bell behavior	AudibleBell	Boolean
Controls for repeat key behavior	PerKeyRepeat	No
	RepeatKeys	Boolean
	DetectableAutorepeat	Boolean
Controls for keyboard overlays	Overlay1	Boolean
	Overlay2	Boolean
Controls for using the mouse from the keyboard	MouseKeys	Boolean
	MouseKeysAccel	Boolean
Controls for better keyboard access by	AccessXFeedback	Boolean
physically impaired persons	AccessXKeys	Boolean
	AccessXTimeout	Boolean
	BounceKeys	Boolean
	SlowKeys	Boolean
	StickyKeys	Boolean
Controls for general keyboard mapping	GroupsWrap	No
	IgnoreGroupLock	Boolean
	IgnoreLockMods	No
	InternalMods	No
Miscellaneous per-client controls	GrabsUseXKBState	Boolean
	LookupStateWhenGrabbed	Boolean
	SendEventUsesXKBState	Boolean

The individual categories and controls are described first, together with functions for manipulating them. A description of the XkbControlsRec structure and the general functions for dealing with all of the controls at once follow at the end of the chapter.

# **Controls that Enable and Disable Other Controls**

Enable and disable the boolean controls under program control by using the *EnabledControls* control; enable and disable them upon program exit by configuring the *AutoReset* control.

#### The EnabledControls Control

The *EnabledControls* control is a bit mask where each bit that is turned on means the corresponding control is enabled, and when turned off, disabled. It corresponds to the *enabled\_ctrls* field of an

XkbControlsRec structure (see section 10.8). The bits describing which controls are turned on or off are defined in Table 10.7.

Use XkbChangeEnabledControls to manipulate the *EnabledControls* control.

Bool **XkbChangeEnabledControls**(dpy, device\_spec, mask, values);

dpy connection to X server

device\_spec keyboard device to modify

mask 1 bit  $\rightarrow$  controls to enable / disable

values 1 bit  $\Rightarrow$  enable, 0 bit  $\Rightarrow$  disable

The *mask* parameter specifies the boolean controls to be enabled or disabled, and the *values* mask specifies the new state for those controls. Valid values for both of these masks are composed of a bitwise inclusive OR of bits taken from the set of mask bits in Table 10.7, using only those masks with "ok" in the *enabled ctrls* column.

If the X server does not support a compatible version of Xkb or the Xkb extension has not been properly initialized, XkbChangeEnabledControls returns False; otherwise, it sends the request to the X server and returns True.

Note that the *EnabledControls* control only enables and disables controls; it does not configure them. Some controls, such as the *AudibleBell* control, have no configuration attributes and are therefore manipulated solely by enabling and disabling them. Others, however, have additional attributes to configure their behavior. For example, the *RepeatControl* control uses  $repeat\_delay$  and  $repeat\_interval$  fields to describe the timing behavior of keys that repeat. The *RepeatControl* behavior is turned on or off depending on the value of the XkbRepeatKeysMask bit, but you must use other means, as described in this chapter, to configure its behavior in detail.

#### The AutoReset Control

You can configure the boolean controls to automatically be enabled or disabled when a program exits. This capability is controlled via two masks maintained in the X server on a per-client basis. There is no client-side Xkb data structure corresponding to these masks. Whenever the client exits for any reason, any boolean controls specified in the *auto-reset mask* are set to the corresponding value from the *auto-reset values* mask. This makes it possible for clients to "clean up after themselves" automatically, even if abnormally terminated. The bits used in the masks correspond to the *EnabledControls* control bits.

For example, a client that replaces the keyboard bell with some other audible cue might want to turn off the *AudibleBell* control to prevent the server from also generating a sound and avoid cacophony. If the client were to exit without resetting the *AudibleBell* control, the user would be left without any feedback at all. Setting *AudibleBell* in both the auto-reset mask and auto-reset values guarantees that the audible bell will be turned back on when the client exits.

To get the current values of the auto-reset controls, use XkbGetAutoResetControls.

Bool XkbGetAutoResetControls(dpy, auto\_ctrls, auto\_values);

dpy connection to X server

auto\_ctrls specifies which bits in auto\_values are relevant

auto\_values 1 bit \_ corresponding control has auto-reset on

XkbGetAutoResetControls backfills auto\_ctrls and auto\_values with the AutoReset control attributes for this particular client. It returns True if successful, and False otherwise.

To change the current values of the *AutoReset* control attributes, use XkbSetAutoResetControls.

Bool XkbSetAutoResetControls(dpy, changes, auto\_ctrls, auto\_values);

dpy connection to X server

changes controls for which to change auto-reset values

auto\_ctrls controls from changes that should auto reset

auto\_values 1 bit  $\Rightarrow$  auto-reset on

XkbSetAutoResetControls changes the auto-reset status and associated auto-reset values for the controls selected by *changes*. For any control selected by *changes*, if the corresponding bit is set in <code>auto\_ctrls</code>, the control is configured to auto-reset when the client exits. If the corresponding bit in <code>auto\_values</code> is on, the control is turned on when the client exits; if zero, the control is turned off when the client exits. For any control selected by <code>changes</code>, if the corresponding bit is not set in <code>auto\_ctrls</code>, the control is configured to not reset when the client exits. For example:

To leave the auto-reset controls for StickyKeys the way they are:

```
ok = XkbSetAutoResetControls(dpy, 0, 0, 0);
```

To change the auto-reset controls so that StickyKeys are unaffected when the client exits:

```
ok = XkbSetAutoResetControls(dpy, XkbStickyKeysMask, 0, 0);
```

To change the auto-reset controls so that StickyKeys are turned off when the client exits:

```
ok = XkbSetAutoResetControls(dpy, XkbStickyKeysMask, XkbStickyKeysMask, 0);
```

To change the auto-reset controls so that StickyKeys are turned on when the client exits:

```
ok = XkbSetAutoResetControls(dpy, XkbStickyKeysMask, XkbStickyKeysMask);
```

XkbSetAutoResetControls backfills auto\_ctrls and auto\_values with the auto-reset controls for this particular client. Note that all of the bits are valid in the returned values, not just the ones selected in the changes mask.

#### Control for Bell Behavior

The X server's generation of sounds is controlled by the *AudibleBell* control. Configuration of different bell sounds is discussed in Chapter 9, *Bells*.

#### The AudibleBell Control

The *AudibleBell* control is a boolean control that has no attributes. As such, you may enable and disable it using either the *EnabledControls* control or the *AutoReset* control discussed in section 10.1.1. When enabled, protocol requests to generate a sound result in the X server actually producing a real sound; when disabled, requests to the server to generate a sound are ignored unless the sound is forced. See section 9.2.

## **Controls for Repeat Key Behavior**

The repeating behavior of keyboard keys is governed by three controls, the *PerKeyRepeat* control, which is always active, and the *RepeatKeys* and *DetectableAutorepeat* controls, which are boolean controls that may be enabled and disabled. *PerKeyRepeat* determines which keys are allowed to repeat. *RepeatKeys* governs the behavior of an individual key when it is repeating. *DetectableAutorepeat* allows a client to detect when a key is repeating as a result of being held down.

#### The PerKeyRepeat Control

The *PerKeyRepeat* control is a bitmask long enough to contain a bit for each key on the device; it determines which individual keys are allowed to repeat. The Xkb *PerKeyRepeat* control provides no functionality different from that available via the core X protocol. There are no convenience functions in Xkb for manipulating this control. The *PerKeyRepeat* control settings are carried in the *per\_key\_repeat* field of an XkbControlsRec structure, discussed in section 10.8.

### The RepeatKeys Control

The core protocol allows only control over whether or not the entire keyboard or individual keys should auto-repeat when held down. *RepeatKeys* is a boolean control that extends this capability by adding control over the delay until a key begins to repeat and the rate at which it repeats. *RepeatKeys* is coupled with the core auto-repeat control: when *RepeatKeys* is enabled or disabled, the core auto-repeat is enabled or disabled and vice versa.

Auto-repeating keys are controlled by two attributes. The first, *timeout*, is the delay after the initial press of an auto-repeating key and the first generated repeat event. The second, *interval*, is the delay between all subsequent generated repeat events. As with all boolean controls, configuring the attributes that determine how the control operates does not automatically enable the control as a whole; see section 10.1.

To get the current attributes of the *RepeatKeys* control for a keyboard device, use XkbGetAutoRepeatRate.

Bool **XkbGetAutoRepeatRate**(display, device\_spec, timeout\_rtrn, interval\_rtrn);

display connection to X server

device\_spec desired device ID, or XkbUseCoreKbd

timeout\_rtrn backfilled with initial repeat delay, ms

interval\_rtrn backfilled with subsequent repeat delay, ms

XkbGetAutoRepeatRate queries the server for the current values of the *RepeatControls* control attributes, backfills timeout\_rtrn and interval\_rtrn with them, and returns True. If a compatible version of the Xkb extension is not available in the server XkbGetAutoRepeatRate returns False.

To set the attributes of the RepeatKeys control for a keyboard device, use XkbSetAutoRepeatRate.

Bool XkbSetAutoRepeatRate(display, device\_spec, timeout, interval);

display connection to X server

device\_spec device to configure, or XkbUseCoreKbd

timeout initial delay, ms

interval delay between repeats, ms

XkbSetAutoRepeatRate sends a request to the X server to configure the AutoRepeat control attributes to the values specified in timeout and interval.

XkbSetAutoRepeatRate does not wait for a reply; it normally returns True. Specifying a zero value for either timeout or interval causes the server to generate a BadValue protocol error. If a compatible version of the Xkb extension is not available in the server, XkbSetAutoRepeatRate returns False.

#### The DetectableAutorepeat Control

Auto-repeat is the generation of multiple key events by a keyboard when the user presses a key and holds it down. Keyboard hardware and device-dependent X server software often implement auto-repeat by generating multiple KeyPress events with no intervening KeyRelease event. The standard behavior of the X server is to generate a KeyRelease event for every KeyPress event. If the keyboard hardware and device-dependent software of the X server implement auto-repeat by generating multiple KeyPress events, the device-independent part of the X server by default synthetically generates a KeyRelease event after each KeyPress event. This provides predictable behavior for X clients, but does not allow those clients to detect the fact that a key is auto-repeating.

Xkb allows clients to request *detectable auto-repeat*. If a client requests and the server supports *DetectableAutorepeat*, Xkb generates KeyRelease events only when the key is physically released. If *DetectableAutorepeat* is not supported or has not been requested, the server synthesizes a KeyRelease event for each repeating KeyPress event it generates.

DetectableAutorepeat, unlike the other controls in this chapter, is not contained in the XkbControlsRec structure, nor can it be enabled or disabled via the *EnabledControls* control. Instead, query and set *DetectableAutorepeat* using XkbGetDetectableAutorepeat and XkbSetDetectableAutorepeat.

DetectableAutorepeat is a condition that applies to all keyboard devices for a client's connection to a given X server; it cannot be selectively set for some devices and not for others. For this reason, none of the Xkb library functions involving DetectableAutorepeat involve a device specifier.

To determine whether or not the server supports *DetectableAutorepeat*, use XkbGetDetectableAutorepeat.

Bool XkbGetDetectableAutorepeat(display, supported\_rtrn);

display connection to X server

supported\_rtrn backfilled True if DetectableAutorepeat supported

XkbGetDetectableAutorepeat queries the server for the current state of *DetectableAutorepeat* and waits for a reply. If <code>supported\_rtrn</code> is not NULL, it backfills supported\_rtrn with True if the server

supports *DetectableAutorepeat*, and False otherwise. XkbGetDetectableAutorepeat returns the current state of *DetectableAutorepeat* for the requesting client: True if *DetectableAutorepeat* is set, and False otherwise.

To set *DetectableAutorepeat*, use XkbSetDetectableAutorepeat. This request affects all keyboard activity for the requesting client only; other clients still see the expected nondetectable auto-repeat behavior, unless they have requested otherwise.

Bool XkbSetDetectableAutorepeat(display, detectable, supported\_rtrn);

display connection to X server

detectable True  $\rightarrow$  set DetectableAutorepeat

supported rtrn backfilled True if DetectableAutorepeat supported

XkbSetDetectableAutorepeat sends a request to the server to set *DetectableAutorepeat* on for the current client if *detectable* is True, and off it *detectable* is False; it then waits for a reply. If *supported\_rtrn* is not NULL, XkbSetDetectableAutorepeat backfills *supported\_rtrn* with True if the server supports *DetectableAutorepeat*, and False if it does not. XkbSetDetectableAutorepeat returns the current state of *DetectableAutorepeat* for the requesting client: True if *DetectableAutorepeat* is set, and False otherwise.

# Controls for Keyboard Overlays (Overlay1 and Overlay2 Controls)

A keyboard overlay allows some subset of the keyboard to report alternate keycodes when the overlay is enabled. For example, a keyboard overlay can be used to simulate a numeric or editing keypad on a keyboard that does not actually have one by reusing some portion of the keyboard as an overlay. This technique is very common on portable computers and embedded systems with small keyboards.

Xkb includes direct support for two keyboard overlays, using the *Overlay1* and *Overlay2* controls. When *Overlay1* is enabled, all of the keys that are members of the first keyboard overlay generate an alternate keycode. When *Overlay2* is enabled, all of the keys that are members of the second keyboard overlay generate an alternate keycode. The two overlays are mutually exclusive; any particular key may be in at most one overlay. *Overlay1* and *Overlay2* are boolean controls. As such, you may enable and disable them using either the *EnabledControls* control or the *AutoReset* control discussed in section 10.1.1.

To specify the overlay to which a key belongs and the alternate keycode it should generate when that overlay is enabled, assign it either the XkbKB\_Overlay1 or XkbKB\_Overlay2 key behaviors, as described in section 16.2.

## Controls for Using the Mouse from the Keyboard

Using Xkb, it is possible to configure the keyboard to allow simulation of the X pointer device. This simulation includes both movement of the pointer itself and press and release events associated with the buttons on the pointer. Two controls affect this behavior: the *MouseKeys* control determines whether or not simulation of the pointer device is active, as well as configuring the default button; the *MouseKeysAccel* control determines the movement characteristics of the pointer when simulated via the keyboard. Both of

them are boolean controls; as such, you may enable and disable them using either the *EnabledControls* control or the *AutoReset* control discussed in section 10.1.1. The individual keys that simulate different aspects of the pointer device are determined by the keyboard mapping, discussed in Chapter 16, *Xkb Server Keyboard Mapping*.

#### The MouseKeys Control

The *MouseKeys* control allows a user to control all the mouse functions from the keyboard. When *MouseKeys* are enabled, all keys with *MouseKeys* actions bound to them generate core pointer events instead of normal KeyPress and KeyRelease events.

The *MouseKeys* control has a single attribute,  $mk\_dflt\_btn$  that specifies the core button number to be used by mouse keys actions that do not explicitly specify a button. There is no convenience function for getting or setting the attribute; instead use XkbGetControls and XkbSetControls (see section 10.9 and section 10.10).

#### Note

*MouseKeys* can also be turned on and off by pressing the key combination necessary to produce an XK\_Pointer\_EnableKeys keysym. The de facto default standard for this is **Shift+Alt+NumLock**, but this may vary depending on the keymap.

### The MouseKeysAccel Control

When the *MouseKeysAccel* control is enabled, the effect of a key-activated pointer motion action changes as a key is held down. If the control is disabled, pressing a mouse-pointer key yields one mouse event. When *MouseKeysAccel* is enabled, mouse movement is defined by an initial distance specified in the XkbSA\_MovePtr action and the following fields in the XkbControlsRec structure (see section 10.8).

Table 10.2. MouseKeysAccel Fields

Field	Function
mk_delay	Time (ms) between the initial key press and the first repeated motion event
mk_interval	Time (ms) between repeated motion events
mk_time_to_max	Number of events (count) before the pointer reaches maximum speed
mk_max_speed	The maximum speed (in pixels per event) the pointer reaches
mk_curve	The ramp used to reach maximum pointer speed

There are no convenience functions to query or change the attributes of the *MouseKeysAccel* control; instead use XkbGetControls and XkbSetControls (see section 10.9 and section 10.10).

The effects of the attributes of the *MouseKeysAccel* control depend on whether the XkbSA\_MovePtr action (see section 16.1) specifies relative or absolute pointer motion.

#### **Absolute Pointer Motion**

If an XkbSA\_MovePtr action specifies an absolute position for one of the coordinates but still allows acceleration, all repeated events contain any absolute coordinates specified in the action. For example, if

the XkbSA\_MovePtr action specifies an absolute position for the X direction, but a relative motion for the Y direction, the pointer accelerates in the Y direction, but stays at the same X position.

#### **Relative Pointer Motion**

If the XkbSA\_MovePtr action specifies relative motion, the initial event always moves the cursor the distance specified in the action. After  $mk\_delay$  milliseconds, a second motion event is generated, and another occurs every  $mk\_interval$  milliseconds until the user releases the key.

Between the time of the second motion event and  $mk\_time\_to\_max$  intervals, the change in pointer distance per interval increases with each interval. After  $mk\_time\_to\_max$  intervals have elapsed, the change in pointer distance per interval remains the same and is calculated by multiplying the original distance specified in the action by  $mk\_max\_speed$ .

For example, if the XkbSA\_MovePtr action specifies a relative motion in the X direction of 5,  $mk\_delay = 160$ ,  $mk\_interval = 40$ ,  $mk\_time\_to\_max = 30$ , and  $mk\_max\_speed = 30$ , the following happens when the user presses the key:

- The pointer immediately moves 5 pixels in the X direction when the key is pressed.
- After 160 milliseconds (mk\_delay), and every 40 milliseconds thereafter (mk\_interval), the pointer moves in the X direction.
- The distance in the X direction increases with each interval until 30 intervals ( mk\_time\_to\_max) have elapsed.
- After 30 intervals, the pointer stops accelerating, and moves 150 pixels (mk\_max\_speed \* the original distance) every interval thereafter, until the key is released.

The increase in pointer difference for each interval is a function of *mk\_curve*. Events after the first but before maximum acceleration has been achieved are accelerated according to the formula:

$$d(step) = action\_delta \times \left(\frac{max\_accel}{steps\_to\_max \ ^{curveFactor}}\right) \times step \ ^{curveFactor}$$

Where action\_delta is the relative motion specified by the XkbSA\_MovePtr action, mk\_max\_speed and mk\_time\_to\_max are parameters to the MouseKeysAccel control, and the curveFactor is computed using the MouseKeysAccel mk\_curve parameter as follows:

$$curveFactor(curve) = 1 + \frac{curve}{1000}$$


With the result that a mk\_curve of zero causes the distance moved to increase linearly from action\_delta to

$$(mk\_max\_speed \times action\_delta)$$

. A negative  $mk\_curve$  causes an initial sharp increase in acceleration that tapers off, and a positive curve yields a slower initial increase in acceleration followed by a sharp increase as the number of pointer events generated by the action approaches  $mk\_time\_to\_max$ . The legal values for  $mk\_curve$  are between  $_{-1000}$  and  $_{1000}$ .

A distance vs. time graph of the pointer motion is shown in Figure 10.1.

Figure 10.1. MouseKeys Acceleration



# Controls for Better Keyboard Access by Physically Impaired Persons

The Xkb extension includes several controls specifically aimed at making keyboard use more effective for physically impaired people. All of these controls are boolean controls and may be individually enabled

and disabled, as well as configured to tune their specific behavior. The behavior of these controls is based on the AccessDOS package <sup>1</sup>.

## The AccessXKeys Control

Enabling or disabling the keyboard controls through a graphical user interface may be impossible for people who need to use the controls. For example, a user who needs *SlowKeys* (see section 10.6.6) may not even be able to start the graphical application, let alone use it, if *SlowKeys* is not enabled. To allow easier access to some of the controls, the *AccessXKeys* control provides a set of special key sequences similar to those available in AccessDOS.

When the *AccessXKeys* control is enabled, the user can turn controls on or off from the keyboard by entering the following standard key sequences:

- Holding down a **Shift** key by itself for eight seconds toggles the *SlowKeys* control.
- Pressing and releasing the left or right Shift key five times in a row, without any intervening key events
  and with less than 30 seconds delay between consecutive presses, toggles the state of the StickyKeys
  control.
- Simultaneously operating two or more modifier keys deactivates the *StickyKeys* control.

When the AccessXKeys control is disabled, Xkb does not look for the above special key sequences.

Some of these key sequences optionally generate audible feedback of the change in state, as described in section 10.6.3, or XkbControlsNotify events, described in section 10.11.

#### The AccessXTimeout Control

In environments where computers are shared, features such as *SlowKeys* present a problem: if *SlowKeys* is on, the keyboard can appear to be unresponsive because keys are not accepted until they are held for a certain period of time. To help solve this problem, Xkb provides an *AccessXTimeout* control to automatically change the enabled/disabled state of any boolean controls and to change the value of the *AccessXKeys* and *AccessXFeedback* control attributes if the keyboard is idle for a specified period of time.

When a timeout as specified by *AccessXTimeout* occurs and a control is consequently modified, Xkb generates an XkbControlsNotify event. For more information on XkbControlsNotify events, refer to section 10.11.

Use XkbGetAccessXTimeout to query the current AccessXTimeout options for a keyboard device.

```
Bool XkbGetAccessXTimeout(display, device_spec, timeout_rtrn, ctrls_mask_rtrn, ctrls_values_rtrn, opts_mask_rtrn, opts_values_rtrn);

display connection to X server

device_spec device to query, or XkbUseCoreKbd

timeout_rtrn delay until AccessXTimeout, seconds

ctrls_mask_rtrn backfilled with controls to modify
```

<sup>&</sup>lt;sup>1</sup> AccessDOS provides access to the DOS operating system for people with physical impairments and was developed by the Trace R&D Center at the University of Wisconsin. For more information on AccessDOS, contact the Trace R&D Center, Waisman Center and Department of Industrial Engineering, University of Wisconsin-Madison WI 53705-2280. Phone: 608-262-6966. e-mail: info@trace.wisc.edu.

ctrls\_values\_rtrn backfilled with on/off status for controls

opts\_mask\_rtrn backfilled with ax\_options to modify

opts\_values\_rtrn backfilled with values for ax\_options

XkbGetAccessXTimeout sends a request to the X server to obtain the current values for the *AccessXTimeout* attributes, waits for a reply, and backfills the values into the appropriate arguments. The parameters opts\_mask\_rtrn and opts\_values\_rtrn are backfilled with the options to modify and the values for ax\_options, which is a field in the XkbControlsRec structure (see section 10.8). XkbGetAccessXTimeout returns True if successful; if a compatible version of the Xkb extension is not available in the server, XkbGetAccessXTimeout returns False.

To configure the AccessXTimeout options for a keyboard device, use XkbSetAccessXTimeout.

Bool **XkbSetAccessXTimeout**(display, device\_spec, timeout, ctrls\_mask, ctrls\_values, opts\_mask, opts\_values);

display connection to X server

device\_spec device to configure, or XkbUseCoreKbd

timeout seconds idle until AccessXTimeout occurs

ctrls\_mask boolean controls to modify

ctrls\_values new bits for controls selected by ctrls\_mask

opts\_mask ax\_options to change

opts\_values new bits for ax\_options selected by opts\_mask

timeout specifies the number of seconds the keyboard must be idle before the controls are modified. ctrls\_mask specifies what controls are to be enabled or disabled, and ctrls\_values specifies whether those controls are to be enabled or disabled. The bit values correspond to those for enabling and disabling boolean controls (see section 10.1.1). The opts\_mask field specifies which attributes of the AccessXKeys and AccessXFeedback controls are to be changed, and opts\_values specifies the new values for those options. The bit values correspond to those for the ax\_options field of an XkbDescRec (see section 10.8).

XkbSetAccessXTimeout sends a request to configure the *AccessXTimeout* control to the server. It does not wait for a reply, and normally returns True. If a compatible version of the Xkb extension is not available in the server, XkbSetAccessXTimeout returns False.

#### The AccessXFeedback Control

Just as some keyboards can produce keyclicks to indicate when a key is pressed or repeating, Xkb can provide feedback for the controls by using special beep codes. Use the *AccessXFeedback* control to configure the specific types of operations that generate feedback.

There is no convenience function for modifying the AccessXFeedback control, although the feedback as a whole can be enabled or disabled just as other boolean controls are (see section 10.1). Individual beep codes are turned on or off by modifying the following bits in the  $ax\_options$  field of an XkbControlsRec structure and using XkbSetControls (see section 10.10):

Table 10.3. AccessXFeedback Masks

Action	Beep Code	ax_options bit
LED turned on	High-pitched beep	XkbAX_IndicatorFBMask
LED turned off	Low-pitched beep	XkbAX_IndicatorFBMask
More than one LED changed state	Two high-pitched beeps	XkbAX_IndicatorFBMask
Control turned on	Rising tone	XkbAX_FeatureFBMask
Control turned off	Falling tone	XkbAX_FeatureFBMask
More than one control changed state	Two high-pitched beeps	XkbAX_FeatureFBMask
SlowKeys and BounceKeys about to be turned on or off	Three high-pitched beeps	XkbAX_SlowWarnFBMask
SlowKeys key pressed	Medium-pitched beep	XkbAX_SKPressFBMask
SlowKeys key accepted	Medium-pitched beep	XkbAX_SKAcceptFBMask
SlowKeys key rejected	Low-pitched beep	XkbAX_SKRejectFBMask
Accepted SlowKeys key released	Medium-pitched beep	XkbAX_SKReleaseFBMask
BounceKeys key rejected	Low-pitched beep	XkbAX_BKRejectFBMask
StickyKeys key latched	Low-pitched beep followed by high-pitched beep	XkbAX_StickyKeysFBMask
StickyKeys key locked	High-pitched beep	XkbAX_StickyKeysFBMask
StickyKeys key unlocked	Low-pitched beep	XkbAX_StickyKeysFBMask

Implementations that cannot generate continuous tones may generate multiple beeps instead of falling and rising tones; for example, they can generate a high-pitched beep followed by a low-pitched beep instead of a continuous falling tone. Other implementations can only ring the bell with one fixed pitch. In these cases, use the XkbAX\_DumbBellFBMask bit of ax\_options to indicate that the bell can only ring with a fixed pitch.

When any of the above feedbacks occur, Xkb may generate a XkbBellNotify event (see section 9.4).

## **AccessXNotify Events**

The server can generate XkbAccessXNotify events for some of the global keyboard controls. The structure for the XkbAccessXNotify event type is as follows:

```
typedef struct {
                                     /* Xkb extension base event code */
   int
                    type;
                                     /* X server serial number for event */
   unsigned long
                    serial;
                                     /* True # synthetically generated */
   Bool
                    send event;
   Display *
                    display;
                                     /* server connection where event generated */
   Time
                    time;
                                     /* server time when event generated */
    int
                    xkb_type;
                                     /* XkbAccessXNotify */
    int
                    device;
                                     /* Xkb device ID, will not be XkbUseCoreKbd *
                    detail;
                                     /* XkbAXN_* */
   int
   KeyCode
                    keycode;
                                     /* key of event */
                                     /* current SlowKeys delay */
   int
                    slowKeysDelay;
                                     /* current debounce delay */
    int
                    debounceDelay;
```

} XkbAccessXNotifyEvent;

The detail field describes what AccessX event just occurred and can be any of the values in Table 10.4.

Table 10.4. AccessXNotify Events

detail	Reason
XkbAXN_SKPress	A key was pressed when SlowKeys was enabled.
XkbAXN_SKAccept	A key was accepted (held longer than the SlowKeys delay).
XkbAXN_SKRelease	An accepted SlowKeys key was released.
XkbAXN_SKReject	A key was rejected (released before the SlowKeys delay expired).
XkbAXN_BKAccept	A key was accepted by BounceKeys.
XkbAXN_BKReject	A key was rejected (pressed before the BounceKeys delay expired).
XkbAXN_AXKWarning	AccessXKeys is about to turn on/off StickyKeys or BounceKeys.

The keycode field reports the keycode of the key for which the event occurred. If the action is related to SlowKeys, the slowKeysDelay field contains the current SlowKeys acceptance delay. If the action is related to BounceKeys, the debounceDelay field contains the current BounceKeys debounce delay.

#### **Selecting for AccessX Events**

To receive XkbAccessXNotify events under all possible conditions, use XkbSelectEvents (see section 4.3) and pass XkbAccessXNotifyMask in both bits\_to\_change and values\_for\_bits.

To receive XkbStateNotify events only under certain conditions, use XkbSelectEventDetails using XkbAccessXNotify as the event\_type and specifying the desired state changes in bits\_to\_change and values\_for\_bits using mask bits from Table 10.5.

Table 10.5. AccessXNotify Event Details

XkbAccessXNotify Event Details	Value	Circumstances
XkbAXN_SKPressMask	(1<<0)	Slow key press notification wanted
XkbAXN_SKAcceptMask	(1<<1)	Slow key accept notification wanted
XkbAXN_SKRejectMask	(1<<2)	Slow key reject notification wanted
XkbAXN_SKReleaseMask	(1<<3)	Slow key release notification wanted
XkbAXN_BKAcceptMask	(1<<4)	Bounce key accept notification wanted
XkbAXN_BKRejectMask	(1<<5)	Bounce key reject notification wanted
XkbAXN_AXKWarningMask	(1<<6)	AccessX warning notification wanted
XkbAXN_AllEventsMask	(0x7f)	All AccessX features notifications wanted

### StickyKeys, RepeatKeys, and MouseKeys Events

The *StickyKeys*, *RepeatKeys*, and *MouseKeys* controls do not generate specific events. Instead, the latching, unlatching, locking, or unlocking of modifiers using *StickyKeys* generates XkbStateNotify events as described in section 5.4. Repeating keys generate normal KeyPress and KeyRelease events, though the auto-repeat can be detected using *DetectableAutorepeat* (see section 10.3.3). Finally, *MouseKeys* generates pointer events identical to those of the core pointer device.

## The SlowKeys Control

Some users may accidentally bump keys while moving a hand or typing stick toward the key they want. Usually, the keys that are accidentally bumped are just hit for a very short period of time. The *SlowKeys* control helps filter these accidental bumps by telling the server to wait a specified period, called the *SlowKeys acceptance delay*, before delivering key events. If the key is released before this period elapses, no key events are generated. Users can then bump any number of keys on their way to the one they want without accidentally getting those characters. Once they have reached the key they want, they can then hold the desired key long enough for the computer to accept it. *SlowKeys* is a boolean control with one configurable attribute.

When the *SlowKeys* control is active, the server reports the initial key press, subsequent acceptance or rejection, and release of any key to interested clients by sending an appropriate *AccessXNotify* event (see section 10.6.4).

To get the SlowKeys acceptance delay for a keyboard device, use XkbGetSlowKeysDelay.

Bool **XkbGetSlowKeysDelay**(display, device\_spec, delay\_rtrn);

display connection to X server

device\_spec device ID, or XkbUseCoreKbd

delay\_rtrn backfilled with SlowKeys delay, ms

XkbGetSlowKeysDelay requests the attributes of the *SlowKeys* control from the server, waits for a reply and backfills *delay\_rtrn* with the *SlowKeys* delay attribute. XkbGetSlowKeysDelay returns True if successful; if a compatible version of the Xkb extension is not available in the server, XkbGetSlowKeysDelay returns False.

To set the SlowKeys acceptance delay for a keyboard device, use XkbSetSlowKeysDelay.

Bool XkbSetSlowKeysDelay(display, device\_spec, delay);

display connection to X server

device\_spec device to configure, or XkbUseCoreKbd

delay SlowKeys delay, ms

XkbSetSlowKeysDelay sends a request to configure the *SlowKeys* control to the server. It does not wait for a reply, and normally returns True. Specifying a value of 0 for the *delay* parameter causes XkbSetSlowKeysDelay to generate a BadValue protocol error. If a compatible version of the Xkb extension is not available in the server XkbSetSlowKeysDelay returns False.

## The BounceKeys Control

Some users may accidentally "bounce" on a key when they release it. They press it once, then accidentally press it again after they release it. The *BounceKeys* control temporarily disables a key after it has been pressed, effectively "debouncing" the keyboard. The period of time the key is disabled after it is released is known as the *BounceKeys delay*. *BounceKeys* is a boolean control.

When the *BounceKeys* control is active, the server reports acceptance or rejection of any key to interested clients by sending an appropriate *AccessXNotify* event (see section 10.6.4).

Use XkbGetBounceKeysDelay to query the current BounceKeys delay for a keyboard device.

Bool XkbGetBounceKeysDelay(display, device\_spec, delay\_rtrn);

display connection to X server

device\_spec device ID, or XkbUseCoreKbd

delay\_rtrn backfilled with bounce keys delay, ms

XkbGetBounceKeysDelay requests the attributes of the *BounceKeys* control from the server, waits for a reply, and backfills *delay\_rtrn* with the *BounceKeys* delay attribute. XkbGetBounceKeysDelay returns True if successful; if a compatible version of the Xkb extension is not available in the server XkbGetSlowKeysDelay returns False.

To set the *BounceKeys* delay for a keyboard device, use XkbSetBounceKeysDelay.

Bool XkbSetBounceKeysDelay(display, device\_spec, delay);

display connection to X server

device\_spec device to configure, or XkbUseCoreKbd

delay bounce keys delay, ms

XkbSetBounceKeysDelay sends a request to configure the *BounceKeys* control to the server. It does not wait for a reply and normally returns True. Specifying a value of *zero* for the *delay* parameter causes XkbSetBounceKeysDelay to generate a BadValue protocol error. If a compatible version of the Xkb extension is not available in the server, XkbSetBounceKeysDelay returns False.

## The StickyKeys Control

Some people find it difficult or even impossible to press two keys at once. For example, a one-fingered typist or someone using a mouth stick cannot press the **Shift** and **1** keys at the same time. The *StickyKeys* control solves this problem by changing the behavior of the modifier keys. With *StickyKeys*, the user can first press a modifier, release it, then press another key. For example, to get an exclamation point on a PC-style keyboard, the user can press the **Shift** key, release it, and then press the **1** key.

StickyKeys also allows users to lock modifier keys without requiring special locking keys. When StickyKeys is enabled, a modifier is latched when the user presses it just once. The user can press a modifier twice in a row to lock it, and then unlock it by pressing it one more time.

When a modifier is latched, it becomes unlatched when the user presses a nonmodifier key or a pointer button. For instance, to enter the sequence **Shift+Control+Z** the user could press and release the **Shift** key to latch it, then press and release the **Control** key to latch it, and finally press and release the **Z** key. Because the **Control** key is a modifier key, pressing it does not unlatch the **Shift** key. Thus, after the user presses the **Control** key, both the Shift and Control modifiers are latched. When the user presses the **Z** key, the effect is as though the user had pressed **Shift+Control+Z**. In addition, because the **Z** key is not a modifier key, the Shift and Control modifiers are unlatched.

Locking a modifier key means that the modifier affects any key or pointer button the user presses until the user unlocks it or it is unlocked programmatically. For example, to enter the sequence ("XKB") on a keyboard where '(' is a shifted '9', ')' is a shifted '0', and '"' is a shifted single quote, the user could press and release the **Shift** key twice to lock the Shift modifier. Then, when the user presses the **9**, ', **x**, **k**, **b**, ', and **0** keys in sequence, it generates ("XKB"). To unlock the Shift modifier, the user can press and release the **Shift** key.

*StickyKeys* is a boolean control with two separate attributes that may be individually configured: one to automatically disable it, and one to control the latching behavior of modifier keys.

#### **StickyKeys Options**

The *StickyKeys* control has two options that can be accessed via the <code>ax\_options</code> of an XkbControlsRec structure (see section 10.8). The first option, *TwoKeys*, specifies whether *StickyKeys* should automatically turn off when two keys are pressed at the same time. This feature is useful for shared computers so people who do not want them do not need to turn *StickyKeys* off if a previous user left *StickyKeys* on. The second option, *LatchToLock*, specifies whether or not *StickyKeys* locks a modifier when pressed twice in a row.

Use XkbGetStickyKeysOptions to query the current StickyKeys attributes for a keyboard device.

Bool XkbGetStickyKeysOptions(display, device\_spec, options\_rtrn);

display connection to X server

device spec device ID, or XkbUseCoreKbd

options rtrn backfilled with StickyKeys option mask

XkbGetStickyKeysOptions requests the attributes of the *StickyKeys* control from the server, waits for a reply, and backfills *options\_rtrn* with a mask indicating whether the individual *StickyKeys* options are on or off. Valid bits in *options\_rtrn* are:

XkbAX\_TwoKeysMask XkbAX\_LatchToLockMask

XkbGetStickyKeysOptions returns True if successful; if a compatible version of the Xkb extension is not available in the server XkbGetStickyKeysOptions returns False.

To set the *StickyKeys* attributes for a keyboard device, use XkbSetStickyKeysOptions.

Bool XkbSetStickyKeysOptions(display, device\_spec, mask, values);

display connection to X server

device\_spec device to configure, or XkbUseCoreKbd

mask selects StickyKeys attributes to modify

values values for selected attributes

XkbSetStickyKeysOptions sends a request to configure the *StickyKeys* control to the server. It does not wait for a reply and normally returns True. The valid bits to use for both the *mask* and *values* parameters are:

XkbAX\_TwoKeysMask XkbAX\_LatchToLockMask

If a compatible version of the Xkb extension is not available in the server, XkbSetStickyKeysOptions returns False.

## **Controls for General Keyboard Mapping**

There are several controls that apply to the keyboard mapping in general. They control handling of outof-range group indices and how modifiers are processed and consumed in the server. These are:

GroupsWrap IgnoreGroupLock IgnoreLockMods

#### InternalMods

*IgnoreGroupLock* is a boolean control; the rest are always active.

Without the modifier processing options provided by Xkb, passive grabs set via translations in a client (for example, Alt < KeyPress > space) do not trigger if any modifiers other than those specified by the translation are set. This results in problems in the user interface when either NumLock or a secondary keyboard group is active. The IgnoreLockMods and IgnoreGroupLock controls make it possible to avoid this behavior without exhaustively specifying a grab for every possible modifier combination.

#### The GroupsWrap Control

The *GroupsWrap* control determines how illegal groups are handled on a global basis. There are a number of valid keyboard sequences that can cause the effective group number to go out of range. When this happens, the group must be normalized back to a valid number. The *GroupsWrap* control specifies how this is done.

When dealing with group numbers, all computations are done using the group index, which is the group number minus one. There are three different algorithms; the *GroupsWrap* control specifies which one is used:

#### XkbRedirectIntoRange

All invalid group numbers are converted to a valid group number by taking the last four bits of the *GroupsWrap* control and using them as the group index. If the result is still out of range, Group one is used.

#### XkbClampIntoRange

All invalid group numbers are converted to the nearest valid group number. Group numbers larger than the highest supported group number are mapped to the highest supported group; those less than one are mapped to group one.

#### XkbWrapIntoRange

All invalid group numbers are converted to a valid group number using integer modulus applied to the group index.

There are no convenience functions for manipulating the *GroupsWrap* control. Manipulate the *GroupsWrap* control via the *groups\_wrap* field in the XkbControlsRec structure, then use XkbSetControls and XkbGetControls (see section 10.9 and section 10.10) to query and change this control.

#### Note

See also section 15.3.2 or a discussion of the related field, group\_info, which also normalizes a group under certain circumstances.

#### The IgnoreLockMods Control

The core protocol does not provide a way to exclude specific modifiers from grab calculations, with the result that locking modifiers sometimes have unanticipated side effects.

The *IgnoreLockMods* control specifies modifiers that should be excluded from grab calculations. These modifiers are also not reported in any core events except KeyPress and KeyRelease events that do not activate a passive grab and that do not occur while a grab is active.

Manipulate the *IgnoreLockMods* control via the *ignore\_lock* field in the XkbControlsRec structure, then use XkbSetControls and XkbGetControls (see section 10.9 and section 10.10) to query and change this control. Alternatively, use XkbSetIgnoreLockMods.

To set the modifiers that, if locked, are not to be reported in matching events to passive grabs, use XkbSetIgnoreLockMods.

Bool **XkbSetIgnoreLockMods**(display, device\_spec, affect\_real, real\_values, affect\_virtual, virtual\_values);

display connection to the X server

device\_spec device ID, or XkbUseCoreKbd

affect\_real mask of real modifiers affected by this call

real\_values values values for affected real modifiers (1#set, 0#unset)

affect\_virtual mask of virtual modifiers affected by this call

virtual\_values values for affected virtual modifiers (1#set, 0#unset)

XkbSetIgnoreLockMods sends a request to the server to change the server's <code>IgnoreLockMods</code> control. <code>affect\_real</code> and <code>real\_values</code> are masks of real modifier bits indicating which real modifiers are to be added and removed from the server's <code>IgnoreLockMods</code> control. Modifiers selected by both <code>affect\_real</code> and <code>real\_values</code> are added to the server's <code>IgnoreLockMods</code> control; those selected by <code>affect\_real</code> but not by <code>real\_values</code> are removed from the server's <code>IgnoreLockMods</code> control. Valid values for <code>affect\_real</code> and <code>real\_values</code> consist of any combination of the eight core modifier bits: ShiftMask, LockMask, ControlMask, ModlMask – Mod5Mask. <code>affect\_virtual</code> and <code>virtual\_values</code> are masks of virtual modifier bits indicating which virtual modifiers are to be added and removed from the server's <code>IgnoreLockMods</code> control. Modifiers selected by both <code>affect\_virtual</code> and <code>virtual\_values</code> are added to the server's <code>IgnoreLockMods</code> control; those selected by <code>affect\_virtual</code> but not by <code>virtual\_values</code> are removed from the server's <code>IgnoreLockMods</code> control. See section 7.1 for a discussion of virtual modifier masks to use in <code>affect\_virtual</code> and <code>virtual\_values</code>. XkbSetIgnoreLockMods does not wait for a reply from the server. It returns True if the request was sent, and False otherwise.

### The IgnoreGroupLock Control

The *IgnoreGroupLock* control is a boolean control with no attributes. If enabled, it specifies that the locked state of the keyboard group should not be considered when activating passive grabs.

Because *IgnoreGroupLock* is a boolean control with no attributes, use the general boolean controls functions (see section 10.1) to change its state.

#### The Internal Mods Control

The core protocol does not provide any means to prevent a modifier from being reported in events sent to clients; Xkb, however makes this possible via the *InternalMods* control. It specifies modifiers that should be consumed by the server and not reported to clients. When a key is pressed and a modifier that has its bit set in the *InternalMods* control is reported to the server, the server uses the modifier when determining the actions to apply for the key. The server then clears the bit, so it is not actually reported to the client. In addition, modifiers specified in the *InternalMods* control are not used to determine grabs and are not used to calculate core protocol compatibility state.

Manipulate the *InternalMods* control via the *internal* field in the XkbControlsRec structure, using XkbSetControls and XkbGetControls (see section 10.9 and section 10.10). Alternatively, use XkbSetServerInternalMods.

To set the modifiers that are consumed by the server before events are delivered to the client, use XkbSetServerInternalMods.

```
Bool
        XkbSetServerInternalMods(display,
                                                       device spec,
                                                                          affect real,
real_values, affect_virtual, virtual_values);
                                connection to the X server
display
                                 'device ID. or XkbUseCoreKbd
device spec
                                mask of real modifiers affected by this call
affect_real
real_values
                                values for affected real modifiers (1#set, 0#unset)
affect virtual
                                mask of virtual modifiers affected by this call
virtual values
                                values for affected virtual modifiers (1#set, 0#unset)
```

XkbSetServerInternalMods sends a request to the server to change the internal modifiers consumed by the server. <code>affect\_real</code> and <code>real\_values</code> are masks of real modifier bits indicating which real modifiers are to be added and removed from the server's internal modifiers control. Modifiers selected by both <code>affect\_real</code> and <code>real\_values</code> are added to the server's internal modifiers control; those selected by <code>affect\_real</code> but not by <code>real\_values</code> are removed from the server's internal modifiers mask. Valid values for <code>affect\_real</code> and <code>real\_values</code> consist of any combination of the eight core modifier bits: ShiftMask, LockMask, ControlMask, Mod1Mask – Mod5Mask. <code>affect\_virtual</code> and <code>virtual\_values</code> are masks of virtual modifiers bits indicating which virtual modifiers are to be added and removed from the server's internal modifiers control. Modifiers selected by both <code>affect\_virtual</code> and <code>virtual\_values</code> are added to the server's internal modifiers control; those selected by <code>affect\_virtual</code> but not by <code>virtual\_values</code> are removed from the server's internal modifiers control. See section 7.1 for a discussion of virtual modifier masks to use in <code>affect\_virtual</code> and <code>virtual\_values</code>. XkbSetServerInternalMods does not wait for a reply from the server. It returns True if the request was sent and False otherwise.

#### The XkbControlsRec Structure

Many of the individual controls described in sections 10.1 through 10.7 may be manipulated via convenience functions discussed in those sections. Some of them, however, have no convenience functions. The XkbControlsRec structure allows the manipulation of one or more of the controls in a single operation and to track changes to any of them in conjunction with the XkbGetControls and XkbSetControls functions. This is the only way to manipulate those controls that have no convenience functions.

The XkbControlsRec structure is defined as follows:

```
#define
             XkbMaxLegalKeyCode
                                       255
#define
             XkbPerKeyBitArraySize
                                       ((XkbMaxLegalKeyCode+1)/8)
typedef struct {
                                          /* default button for
    unsigned char
                      mk dflt btn;
                                              keyboard driven mouse */
    unsigned char
                      num groups;
                                          /* number of keyboard groups */
                                          /* how to wrap out-of-bounds groups */
    unsigned char
                      groups wrap;
    XkbModsRec
                                          /* defines server internal modifiers */
                      internal;
```

```
XkbModsRec
                      ignore_lock;
                                          /* modifiers to ignore when
                                              checking for grab */
    unsigned int
                      enabled_ctrls;
                                          /* 1 bit # corresponding
                                              boolean control enabled */
    unsigned short
                      repeat_delay;
                                          /* ms delay until first repeat */
    unsigned short
                      repeat_interval;
                                          /* ms delay between repeats */
    unsigned short
                      slow_keys_delay;
                                          /* ms minimum time key must be
                                              down to be ok */
                                          /* ms delay before key reactivated */
    unsigned short
                      debounce_delay;
                                          /* ms delay to second mouse
    unsigned short
                      mk delay;
                                              motion event */
    unsigned short
                      mk_interval;
                                          /* ms delay between repeat mouse
                                              events */
    unsigned short
                                          /* # intervals until constant
                      mk_time_to_max;
                                              mouse move */
    unsigned short
                                          /* multiplier for maximum mouse speed */
                      mk_max_speed;
    short
                      mk curve;
                                          /* determines mouse move curve type */
    unsigned short
                                          /* 1 bit # Access X option enabled */
                      ax_options;
    unsigned short
                                          /* seconds until Access X disabled */
                      ax timeout;
    unsigned short
                                          /* 1 bit # options to reset
                      axt_opts_mask;
                                              on Access X timeout */
    unsigned short
                      axt_opts_values;
                                          /* 1 bit # turn option on, 0# off */
    unsigned int
                      axt_ctrls_mask;
                                          /* which bits in enabled_ctrls
                                              to modify */
    unsigned int
                                          /* values for new bits in
                      axt_ctrls_values;
                                              enabled ctrls */
    unsigned char
                      per_key_repeat[XkbPerKeyBitArraySize];
                                          /* per key auto repeat */
} XkbControlsRec, *XkbControlsPtr;
```

The general-purpose functions that work with the XkbControlsRec structure use a mask to specify which controls are to be manipulated. Table 10.6 lists these controls, the masks used to select them in the general function calls (which parameter), and the data fields in the XkbControlsRec structure that comprise each of the individual controls. Also listed are the bit used to turn boolean controls on and off and the section where each control is described in more detail.

Table 10.6. Xkb Controls

Control	Control Selection Mask (which parameter)	Relevant XkbControlsRec Data Fields	Boolean Control enabled_ctrls bit	Section
AccessXFeedback	XkbAccessXFeedbackMask	ax_options: XkbAX_*FBMask	XkbAccessXFeedback- Mask	10.6.3
AccessXKeys			XkbAccessXKeysMask	10.6.1
AccessXTimeout	XkbAccessXTimeoutMask	ax_timeout axt_opts_mask	XkbAccessXTimeout- Mask	10.6.2
		axt_opts_values		
		axt_ctrls_mask		
		axt_ctrls_values		

Control	Control Selection Mask (which parameter)	Relevant XkbControlsRec Data Fields	Boolean Control enabled_ctrls bit	Section
AudibleBell			XkbAudibleBellMask	9.2
AutoReset				10.1.2
BounceKeys	XkbBounceKeysMask	debounce_delay	XkbBounceKeysMask	10.6.7
Detectable- Autorepeat				10.3.3
EnabledControls	Xkb Controls Enabled Mask	enabled_ctrls	Non-Boolean Control	10.1.1
GroupsWrap	Xkb Groups Wrap Mask	groups_wrap	Non-Boolean Control	10.7.1
IgnoreGroupLock			XkbIgnoreGroupLock- Mask	10.7.3
IgnoreLockMods	XkbIgnoreLockModsMask	ignore_lock	Non-Boolean Control	5.1
InternalMods	XkbInternal Mods Mask	internal	Non-Boolean Control	5.1
MouseKeys	XkbMouseKeysMask	mk_dflt_btn	Xkb Mouse Keys Mask	10.5.1
MouseKeysAccel	Xkb Mouse Keys Accel Mask	mk_delay	XkbMouseKeysAccel-	10.5.2
		mk_interval	Mask	
		mk_time_to_max		
		mk_max_speed		
		mk_curve		
Overlay1			XkbOverlay1Mask	10.4
Overlay2			XkbOverlay2Mask	10.4
PerKeyRepeat	XkbPerKeyRepeatMask	per_key_repeat	Non-Boolean Control	10.3.1
RepeatKeys	XkbRepeatKeysMask	repeat_delay	XkbRepeatKeysMask	10.3
		repeat_interval		
SlowKeys	XkbSlowKeysMask	slow_keys_delay	XkbSlowKeysMask	10.6.6
StickyKeys	XkbStickyKeysMask	ax_options:	XkbStickyKeysMask	10.6.8
		XkbAX_Two- KeysMask		
		XkbAX_Latch- ToLockMask		

Table 10.7 shows the actual values for the individual mask bits used to select controls for modification and to enable and disable the control. Note that the same mask bit is used to specify general modifications to the parameters used to configure the control (which), and to enable and disable the control (enabled\_ctrls). The anomalies in the table (no "ok" in column) are for controls that have no configurable attributes; and for controls that are not boolean controls and therefore cannot be enabled or disabled.

**Table 10.7. Controls Mask Bits** 

Mask Bit	which or changed_ctrls	enabled_ctrls	Value
XkbRepeatKeysMask	ok	ok	(1L<<0)
XkbSlowKeysMask	ok	ok	(1L<<1)
XkbBounceKeysMask	ok	ok	(1L<<2)
XkbStickyKeysMask	ok	ok	(1L<<3)
XkbMouseKeysMask	ok	ok	(1L<<4)
XkbMouseKeysAccelMask	ok	ok	(1L<<5)
XkbAccessXKeysMask	ok	ok	(1L<<6)
XkbAccessXTimeoutMask	ok	ok	(1L<<7)
XkbAccessXFeedbackMask	ok	ok	(1L<<8)
XkbAudibleBellMask		ok	(1L<<9)
XkbOverlay1Mask		ok	(1L<<10)
XkbOverlay2Mask		ok	(1L<<11)
XkbIgnoreGroupLockMask		ok	(1L<<12)
XkbGroupsWrapMask	ok		(1L<<27)
XkbInternalModsMask	ok		(1L<<28)
XkbIgnoreLockModsMask	ok		(1L<<29)
XkbPerKeyRepeatMask	ok		(1L<<30)
XkbControlsEnabledMask	ok		(1L<<31)
XkbAccessXOptionsMask	ok	ok	(XkbStickyKeysMask   XkbAccessXFeedbackMask)
XkbAllBooleanCtrlsMask		ok	(0x00001FFF)
XkbAllControlsMask	ok		(0xF8001FFF)

The individual fields of the XkbControlsRec structure are defined as follows.

#### mk\_dflt\_btn

*mk\_dflt\_btn* is an attribute of the *MouseKeys* control (see section 10.5). It specifies the mouse button number to use for keyboard simulated mouse button operations. Its value should be one of the core symbols Button1 – Button5.

#### num\_groups

num\_groups is not a part of any control, but is reported in the XkbControlsRec structure whenever any of its components are fetched from the server. It reports the number of groups the particular keyboard configuration uses and is computed automatically by the server whenever the keyboard mapping changes.

#### groups\_wrap

groups\_wrap is an attribute of the *GroupsWrap* control (see section 10.7.1). It specifies the handling of illegal groups on a global basis. Valid values for groups\_wrap are shown in Table 10.8.

Table 10.8. GroupsWrap options (groups\_wrap field)

groups_wrap symbolic name	value	
XkbWrapIntoRange	(0x00)	
XkbClampIntoRange	(0x40)	
XkbRedirectIntoRange	(0x80)	

When groups\_wrap is set to XkbRedirectIntoRange, its four low-order bits specify the index of the group to use.

#### internal

*internal* is an attribute of the *InternalMods* control (see section 10.7.4). It specifies modifiers to be consumed in the server and not passed on to clients when events are reported. Valid values consist of any combination of the eight core modifier bits: ShiftMask, LockMask, ControlMask, Mod1Mask – Mod5Mask.

#### ignore\_lock

*ignore\_lock* is an attribute of the *IgnoreLockMods* control (see section 10.7.2). It specifies modifiers to be ignored in grab calculations. Valid values consist of any combination of the eight core modifier bits: ShiftMask, LockMask, ControlMask, Mod1Mask – Mod5Mask.

#### enabled\_ctrls

enabled\_ctrls is an attribute of the EnabledControls control (see section 10.1.1). It contains one bit per boolean control. Each bit determines whether the corresponding control is enabled or disabled; a one bit means the control is enabled. The mask bits used to enable these controls are listed in Table 10.7, using only those masks with "ok" in the enabled\_ctrls column.

#### repeat\_delay and repeat\_interval

repeat\_delay and repeat\_interval are attributes of the RepeatKeys control (see section 10.3.2). repeat\_delay is the initial delay before a key begins repeating, in milliseconds; repeat\_interval is the delay between subsequent key events, in milliseconds.

#### slow\_keys\_delay

slow\_keys\_delay is an attribute of the SlowKeys control (see section 10.6.6). Its value specifies the SlowKeys acceptance delay period in milliseconds before a key press is accepted by the server.

#### debounce\_delay

debounce\_delay is an attribute of the *BounceKeys* control (see section 10.6.7). Its value specifies the *BounceKeys* delay period in milliseconds for which the key is disabled after having been pressed before another press of the same key is accepted by the server.

# mk\_delay, mk\_interval, mk\_time\_to\_max, mk\_max\_speed, and mk\_curve

mk\_delay, mk\_interval, mk\_time\_to\_max, mk\_max\_speed, and mk\_curve are attributes of the *MouseKeysAccel* control. Refer to section 10.5.2 for a description of these fields and the units involved.

#### ax\_options

The ax\_options field contains attributes used to configure two different controls, the *StickyKeys* control (see section 10.6.8) and the *AccessXFeedback* control (see section 10.6.3). The ax\_options field is a bitmask and may include any combination of the bits defined in Table 10.9.

Table 10.9. Access X Enable/Disable Bits (ax\_options field)

Access X Control	ax_options bit	value
AccessXFeedback	XkbAX_SKPressFBMask	(1L<<0)
	XkbAX_SKAcceptFBMask	(1L << 1)
	XkbAX_FeatureFBMask	(1L << 2)
	XkbAX_SlowWarnFBMask	(1L << 3)
	XkbAX_IndicatorFBMask	(1L << 4)
	XkbAX_StickyKeysFBMask	(1L << 5)
	XkbAX_SKReleaseFBMask	(1L << 8)
	XkbAX_SKRejectFBMask	(1L << 9)
	XkbAX_BKRejectFBMask	(1L << 10)
	XkbAX_DumbBellFBMask	(1L << 11)
StickyKeys	XkbAX_TwoKeysMask	(1L << 6)
	XkbAX_LatchToLockMask	(1L << 7)
	XkbAX_AllOptionsMask	(0xFFF)

The fields pertaining to each control are relevant only when the control is enabled (XkbAccessXFeedbackMask or XkbStickyKeysMask bit is turned on in the enabled\_ctrls field).

Xkb provides a set of convenience macros for working with the ax\_options field of an XkbControlsRec structure:

```
#define XkbAX_NeedOption(c,w) ((c)->ax_options & (w))
```

The XkbAX\_NeedOption macro is useful for determining whether a particular AccessX option is enabled or not. It accepts a pointer to an XkbControlsRec structure and a valid mask bit from Table 10.9. If the specified mask bit in the <code>ax\_options</code> field of the controls structure is set, the macro returns the mask bit. Otherwise, it returns zero. Thus,

```
XkbAX_NeedOption(ctlrec, XkbAX_LatchToLockMask)
```

is nonzero if the latch to lock transition for latching keys is enabled, and zero if it is disabled. Note that XkbAX\_NeedOption only determines whether or not the particular capability is configured to operate; the XkbAccessXFeedbackMask bit must also be turned on in enabled\_ctrls for the capability to actually be functioning.

The XkbAX\_AnyFeedback macro accepts a pointer to an XkbControlsRec structure and tells whether the *AccessXFeedback* control is enabled or not. If the *AccessXFeedback* control is enabled, the macro returns XkbAccessXFeedbackMask. Otherwise, it returns zero.

The XkbAX\_NeedFeedback macro is useful for determining if both the *AccessXFeedback* control and a particular AccessX feedback option are enabled. The macro accepts a pointer to an XkbControlsRec structure and a feedback option from the table above. If both the *AccessXFeedback* control and the specified feedback option are enabled, the macro returns True. Otherwise it returns False.

# ax\_timeout, axt\_opts\_mask, axt\_opts\_values, axt\_ctrls\_mask, and axt\_ctrls\_values

ax\_timeout, axt\_opts\_mask, axt\_opts\_values, axt\_ctrls\_mask, and axt\_ctrls\_values are attributes of the *AccessXTimeout* control. Refer to section 10.6.2 for a description of these fields and the units involved.

#### per\_key\_repeat

The per\_key\_repeat field mirrors the auto\_repeats field of the core protocol XKeyboardState structure: changing the auto\_repeats field automatically changes per\_key\_repeat and vice versa. It is provided for convenience and to reduce protocol traffic. For example, to obtain the individual repeat key behavior as well as the repeat delay and rate, use XkbGetControls. If the per\_key\_repeat were not in this structure, you would have to call both XGetKeyboardControl and XkbGetControls to get this information. The bits correspond to keycodes. The first seven keys (keycodes 1–7) are indicated in per\_key\_repeat[0], with bit position 0 (low order) corresponding to the fictitious keycode 0. Following array elements correspond to 8 keycodes per element. A 1 bit indicates that the key is a repeating key.

## **Querying Controls**

Use XkbGetControls to find the current state of Xkb server controls.

Status **XkbGetControls**(display, which, xkb);

display connection to X server

which mask of controls requested

xkb keyboard description for controls information

XkbGetControls queries the server for the requested control information, waits for a reply, and then copies the server's values for the requested information into the ctrls structure of the xkb argument. Only those components specified by the which parameter are copied. Valid values for which are any combination of the masks listed in Table 10.7 that have "ok" in the which column.

If xkb->ctrls is NULL, XkbGetControls allocates and initializes it before obtaining the values specified by which. If xkb->ctrls is not NULL, XkbGetControls modifies only those portions of xkb->ctrls corresponding to the values specified by which.

XkbGetControls returns Success if successful; otherwise, it returns BadAlloc if it cannot obtain sufficient storage, BadMatch if xkb is NULL or which is empty, or BadImplementation.

To free the ctrls member of a keyboard description, use XkbFreeControls (see section 10.12)

The num\_groups field in the ctrls structure is always filled in by XkbGetControls, regardless of which bits are selected by which.

## **Changing Controls**

There are two ways to make changes to controls: either change a local copy keyboard description and call XkbSetControls, or, to reduce network traffic, use an XkbControlsChangesRec structure and call XkbChangeControls.

To change the state of one or more controls, first modify the *ctrls* structure in a local copy of the keyboard description and then use XkbSetControls to copy those changes to the X server.

```
Bool XkbSetControls(display, which, xkb);
display connection to X server
which mask of controls to change
xkb ctrls field contains new values to be set
```

For each bit that is set in the *which* parameter, XkbSetControls sends the corresponding values from the *xkb->ctrls* field to the server. Valid values for *which* are any combination of the masks listed in Table 10.7 that have "ok" in the *which* column.

If xkb->ctrls is NULL, the server does not support a compatible version of Xkb, or the Xkb extension has not been properly initialized, XkbSetControls returns False. Otherwise, it sends the request to the X server and returns True.

Note that changes to attributes of controls in the XkbControlsRec structure are apparent only when the associated control is enabled, although the corresponding values are still updated in the X server. For example, the  $repeat\_delay$  and  $repeat\_interval$  fields are ignored unless the RepeatKeys control is enabled (that is, the X server's equivalent of xkb->ctrls has XkbRepeatKeysMask set in  $enabled\_ctrls$ ). It is permissible to modify the attributes of a control in one call to XkbSetControls and enable the control in a subsequent call. See section 10.1.1 for more information on enabling and disabling controls.

Note that the <code>enabled\_ctrls</code> field is itself a control — the <code>EnabledControls</code> control. As such, to set a specific configuration of enabled and disabled boolean controls, you must set <code>enabled\_ctrls</code> to the appropriate bits to enable only the controls you want and disable all others, then specify the <code>XkbControlsEnabledMask</code> in a call to <code>XkbSetControls</code>. Because this is somewhat awkward if all you want to do is enable and disable controls, and not modify any of their attributes, a convenience function is also provided for this purpose (<code>XkbChangeEnabledControls</code>, section 10.1.1).

## The XkbControlsChangesRec Structure

The XkbControlsChangesRec structure allows applications to track modifications to an XkbControlsRec structure and thereby reduce the amount of traffic sent to the server. The same XkbControlsChangesRec structure may be used in several successive modifications to the same XkbControlsRec structure, then subsequently used to cause all of the changes, and only the changes, to be propagated to the server. The XkbControlsChangesRec structure is defined as follows:

The <code>changed\_ctrls</code> field is a mask specifying which logical sets of data in the controls structure have been modified. In this context, modified means <code>set</code>, that is, if a value is set to the same value it previously contained, it has still been modified, and is noted as changed. Valid values for <code>changed\_ctrls</code> are any combination of the masks listed in Table 10.7 that have "ok" in the <code>changed\_ctrls</code> column. Setting a bit implies the corresponding data fields from the "Relevant XkbControlsRec Data Fields" column in Table 10.6 have been modified. The <code>enabled\_ctrls\_changes</code> field specifies which bits in the <code>enabled\_ctrls</code> field have changed. If the number of keyboard groups has changed, the <code>num\_groups\_changed</code> field is set to True.

If you have an Xkb description with controls that have been modified and an XkbControlsChangesRec that describes the changes that have been made, the XkbChangeControls function provides a flexible method for updating the controls in a server to match those in the changed keyboard description.

```
Bool XkbChangeControls(dpy, xkb, changes);

dpy connection to X server

xkb keyboard description with changed xkb->ctrls

changes which parts of xkb->ctrls have changed
```

XkbChangeControls copies any controls fields specified by *changes* from the keyboard description controls structure, *xkb->ctrls*, to the server specified by *dpy*.

## **Tracking Changes to Keyboard Controls**

Whenever a field in the controls structure changes in the server's keyboard description, the server sends an XkbControlsNotify event to all interested clients. To receive XkbControlsNotify events under all possible conditions, use XkbSelectEvents (see section 4.3) and pass XkbControlsNotifyMask in both bits\_to\_change and values\_for\_bits.

To receive XkbControlsNotify events only under certain conditions, use XkbSelectEventDetails using XkbControlsNotify as the event\_type and specifying the desired state changes in bits\_to\_change and values\_for\_bits using mask bits from Table 10.7.

The structure for the XkbControlsNotify event is defined as follows:

```
typedef struct {
                                   /* Xkb extension base event code */
    int
                   type;
                                   /* X server serial number for event */
    unsigned long
                   serial;
   Bool
                   send event;
                                   /* True # synthetically generated */
   Display *
                   display;
                                   /* server connection where event generated */
   Time
                   time;
                                   /* server time when event generated */
                                   /* XkbCompatMapNotify */
    int
                   xkb type;
                                   /* Xkb device ID,
    int
                   device;
                                      will not be XkbUseCoreKbd */
                   changed ctrls; /* bits indicating which controls
    unsigned int
                                      data have changed */
```

```
unsigned int
                   enabled_ctrls; /* controls currently enabled in server */
   unsigned int
                   enabled ctrl changes; /* bits indicating
                                             enabled/disabled controls */
    int
                   num groups;
                                  /* current number of keyboard groups */
                   keycode;
                                  /* != 0 # keycode of key causing change */
   KeyCode
    char
                   event_type;
                                  /* Type of event causing change */
                                  /* major event code of event causing change */
    char
                   req_major;
                   req minor;
                                  /* minor event code of event causing change */
    char
} XkbControlsNotifyEvent;
```

The *changed\_ctrls* field specifies the controls components that have changed and consists of bits taken from the masks defined in Table 10.7 with "ok" in the *changed\_ctrls* column.

The controls currently enabled in the server are reported in the <code>enabled\_ctrls</code> field. If any controls were just enabled or disabled (that is, the contents of the <code>enabled\_ctrls</code> field changed), they are flagged in the <code>enabled\_ctrl\_changes</code> field. The valid bits for these fields are the masks listed in Table 10.7 with "ok" in the <code>enabled\_ctrls</code> column. The <code>num\_groups</code> field reports the number of groups bound to the key belonging to the most number of groups and is automatically updated when the keyboard mapping changes.

If the change was caused by a request from a client, the <code>keycode</code> and <code>event\_type</code> fields are set to <code>zero</code> and the <code>req\_major</code> and <code>req\_minor</code> fields identify the request. The <code>req\_major</code> value is the same as the major extension opcode. Otherwise, <code>event\_type</code> is set to the type of event that caused the change (one of KeyPress, KeyRelease, DeviceKeyPress, DeviceKeyRelease, ButtonPress or ButtonRelease), and <code>req\_major</code> and <code>req\_minor</code> are undefined. If <code>event\_type</code> is KeyPress, KeyRelease, DeviceKeyPress, or DeviceKeyRelease, the <code>keycode</code> field is set to the key that caused the change. If <code>event\_type</code> is ButtonPress or ButtonRelease, <code>keycode</code> contains the button number.

When a client receives an XkbControlsNotify event, it can note the changes in a changes structure using XkbNoteControlsChanges.

```
void XkbNoteControlsChanges (changes, new, wanted);

changes records changes indicated by new

new tells which things have changed

wanted tells which parts of new to record in changes
```

The wanted parameter is a bitwise inclusive OR of bits taken from the set of masks specified in Table 10.7 with "ok" in the changed\_ctrls column. XkbNoteControlsChanges copies any changes reported in new and specified in wanted into the changes record specified by changes.

Use XkbGetControlsChanges to update a local copy of a keyboard description with the changes previously noted by one or more calls to XkbNoteControlsChanges.

```
Status XkbGetControlsChanges(dpy, xkb, changes);

dpy connection to X server

xkb xkb->ctrls will be updated

changes indicates which parts of xkb->ctrls to update
```

XkbGetControlsChanges examines the *changes* parameter, queries the server for the necessary information, and copies the results into the *xkb->ctrls* keyboard description. If the *ctrls* field of

xkb is NULL, XkbGetControlsChanges allocates and initializes it. To free the ctrls field, use XkbFreeControls (see section 10.12).

XkbGetControlsChanges returns Success if successful and can generate BadAlloc, BadImplementation, and BadMatch errors.

## Allocating and Freeing an XkbControlsRec

The need to allocate an XkbControlsRec structure seldom arises; Xkb creates one when an application calls XkbGetControls or a related function. For those situations where there is not an XkbControlsRec structure allocated in the XkbDescRec, allocate one by calling XkbAllocControls.

Status **XkbAllocControls**(xkb, which);

xkb Xkb description in which to allocate ctrls rec

which mask of components of ctrls to allocate

XkbAllocControls allocates the <code>ctrls</code> field of the <code>xkb</code> parameter, initializes all fields to zero, and returns Success. If the <code>ctrls</code> field is not NULL, XkbAllocControls simply returns Success. If <code>xkb</code> is NULL, XkbAllocControls reports a BadMatch error. If the <code>ctrls</code> field could not be allocated, it reports a BadAlloc error.

The *which* mask specifies the individual fields of the *ctrls* structure to be allocated and can contain any of the valid masks defined in Table 10.7. Because none of the currently existing controls have any structures associated with them, which is currently of little practical value in this call.

To free memory used by the ctrls member of an XkbDescRec structure, use XkbFreeControls:

```
void XkbFreeControls(xkb, which, free_all);
```

xkb Xkb description in which to free controls components

which mask of components of ctrls to free

free\_all True \_ free everything + ctrls itself

XkbFreeControls frees the specified components of the ctrls field in the xkb keyboard description and sets the corresponding structure component values to NULL or zero. The which mask specifies the fields of ctrls to be freed and can contain any of the controls components specified in Table 10.7.

If free\_all is True, XkbFreeControls frees every non-NULL structure component in the controls, frees the XkbControlsRec structure referenced by the ctrls member of xkb, and sets ctrls to NULL.

### The Miscellaneous Per-client Controls

You can configure the boolean per-client controls which affect the state reported in button and key events. See section 12.1.1, 12.3, 12.5, and 16.3.11 of the *XKB Protocol specification* for more details.

To get the current values of the *per-client* controls, use XkbGetPerClientControls.

```
Bool XkbGetPerClientControls(dpy, ctrls);
```

dpy connection to X server

ctrls 1 bit  $\rightarrow$  corresponding control is on

XkbGetPerClientControls backfills <code>ctrls</code> with the <code>per-client</code> control attributes for this particular client. It returns True if successful, and False otherwise.

To change the current values of the *per-client* control attributes, use XkbSetPerClientControls.

Bool **XkbSetPerClientControls**(dpy, change, value);

dpy connection to X server

change 1 bit  $\Rightarrow$  change control

value 1 bit  $\Rightarrow$  control on

XkbSetPerClientControls changes the per-client values for the controls selected by *change* to the corresponding value in *value*. Legal values for *change* and *value* are: XkbPCF\_GrabsUseXKBStateMask, XkbPCF\_LookupStateWhenGrabbed, and XkbPCF\_SendEventUsesXKBState. More than one control may be changed at one time by OR-ing the values together. XkbSetPerClientControls backfills value with the *per-client* control attributes for this particular client. It returns True if successful, and False otherwise.

## **Chapter 11. X Library Controls**

The Xkb extension is composed of two parts: a server extension, and a client-side X library extension. Chapter 10, *Keyboard Controls* discusses functions used to modify controls affecting the behavior of the server portion of the Xkb extension. This chapter discusses functions used to modify controls that affect only the behavior of the client portion of the extension; these controls are known as *Library Controls*.

All of the Library Controls are boolean flags that may be enabled and disabled. The controls can be divided into several categories:

- · Controls affecting general string lookups
- Controls affecting compose processing
- Controls affecting event delivery

There are two types of string lookups performed by XLookupString. The first type involves translating a single keycode into a string; the controls in the first category affect this type of lookup. The second type involves translating a series of keysyms into a string; the controls in the second category affect this type of lookup.

An Xkb implementation is required to support the programming interface for all of the controls. However, an implementation may choose not to support the semantics associated with the controls that deal with compose processing. In this case, a program that accesses these controls should still function normally; however, the feedback that would normally occur with the controls enabled may be missing.

# Controls Affecting Keycode-to-String Translation

The first type of string lookups, which are here called *simple string lookups*, involves translating a single keycode into a string. Because these simple lookups involve only a single keycode, all of the information needed to do the translation is contained in the keyboard state in a single event. The controls affecting simple string lookups are:

ForceLatin1Lookup ConsumeLookupMods LevelOneUsesShiftAndLock

## ForceLatin1Lookup

If the *ForceLatin1Lookup* control is enabled, XLookupString only returns strings using the Latin1 character set. If *ForceLatin1Lookup* is not enabled, XLookupString can return characters that are not in the Latin1 set. By default, this control is disabled, allowing characters outside of the Latin1 set to be returned.

#### ConsumeLookupMods

Simple string lookups in XLookupString involve two different translation phases. The first phase translates raw device keycodes to individual keysyms. The second phase attempts to map the resulting keysym into a string of one or more characters. In the first phase, some of the modifiers are normally used to determine the appropriate shift level for a key.

The *ConsumeLookupMods* control determines whether or not XLookupString *consumes* the modifiers it uses during the first phase of processing (mapping a keycode to a keysym). When a modifier is consumed, it is effectively removed from the working copy of the keyboard state information XLookupString is using and appears to be unset for the remainder of the processing.

If the *ConsumeLookupMods* control is enabled, XLookupString does not use the modifiers used to translate the keycode of the event to a keysym when it is determining the string associated with a keysym. For example, assume the keymap for the 'A' key only contains the shift modifier and the *ConsumeLookupMods* control is enabled. If a user presses the **Shift** key and the **A** key while the **Num\_Lock** key is locked, XLookupString uses the Shift modifier when mapping the keycode for the 'a' key to the keysym for 'A'; subsequently, it only uses the *NumLock* modifier when determining the string associated with the keysym 'A'.

If the *ConsumeLookupMods* control is not enabled, XLookupString uses all of the event modifiers to determine the string associated with a keysym. This behavior mirrors the behavior of XLookupString in the core implementation.

The *ConsumeLookupMods* control is unset by default. For more information on modifier consumption, refer to Chapter 12, *Interpreting Key Events*.

## AlwaysConsumeShiftAndLock

The Always Consume Shift And Lock control, if enabled, forces XLookupString to consume the Shift and Lock modifiers when processing all keys, even if the definition for the key type does not specify these modifiers. The Always Consume Shift And Lock control is unset by default. See section 15.2 for a discussion of key types.

## **Controls Affecting Compose Processing**

The second type of string lookup performed by XLookupString involves translating a series of keysyms into a string. Because these lookups can involve more than one key event, they require XLookupString to retain some state information between successive calls. The process of mapping a series of keysyms to a string is known as *compose processing*. The controls affecting compose processing are:

ConsumeKeysOnComposeFail ComposeLED BeepOnComposeFail

Because different vendors have historically used different algorithms to implement compose processing, and these algorithms may be incompatible with the semantics required by the Xkb compose processing controls, implementation of the compose processing controls is optional in an Xkb implementation.

#### ConsumeKeysOnComposeFail

Some compose processing algorithms signal the start of a compose sequence by a key event meaning "start compose". <sup>1</sup> The subsequent key events should normally result in a valid composition yielding a valid translation to a string. If the subsequent key events do not have a valid translation, some decision must be made about what to do with the key events that were processed while attempting the compose. The *ConsumeKeysOnComposeFail* control allows a client to specify what happens with the key events XLookupString has been considering when it reaches a dead end in a compose sequence.

<sup>&</sup>lt;sup>1</sup> Another possibility is to have the compose processing simply be the result of a finite state acceptor; a compose sequence would never fail for a properly written finite state acceptor.

If the *ConsumeKeysOnComposeFail* control is set, all keys associated with a failed compose sequence should be consumed (discarded). If the *ConsumeKeysOnComposeFail* control is not set, the key events associated with a failed compose sequence should be processed as a normal sequence of key events.

The *ConsumeKeysOnComposeFail* control is disabled by default.

## **ComposeLED**

The *ComposeLED* control allows a client to specify whether or not an indicator should be set and cleared to provide feedback when compose processing is in progress. The control does not specify which indicator should be used; the mapping for this is up to the individual implementation. If the *ComposeLED* control is enabled, it specifies that an indicator should be set when a compose sequence is in progress and cleared when one is not in progress. The *ComposeLED* control is disabled by default.

While the Xkb extension does not specify the type of type of indicator to be used when the *ComposeLED* control is implemented, a consistent convention between implementations is to everyone's benefit. If a named indicator is used for this purpose, the recommended name is "Compose". Note that some implementations may use an unnamed, custom hardware LED for this purpose.

## **BeepOnComposeFail**

The *BeepOnComposeFail* control allows a client to specify whether or not a bell should be activated to provide feedback when a compose sequence fails. The control does not specify the type of bell that should be used; the mapping for this is up to the individual implementation. If the *BeepOnComposeFail* control is enabled, it specifies that a bell should be activated when a compose sequence fails. The *BeepOnComposeFail* control is disabled by default. If implemented, the bell should be activated using XkbBell or XkbDeviceBell.

While the Xkb extension does not specify the type of bell to be used when the *BeepOnComposeFail* control is implemented, a consistent convention between implementations is to everyone's benefit. If a named bell is used for this purpose, the recommended name is "ComposeFail".

## **Controls Effecting Event Delivery**

#### **IgnoreNewKeyboards**

When Xkb is initialized, it implicitly forces requests for NewKeyboardNotify events. These events may be used by the Xkb library extension internally; they are normally translated into core protocol MappingNotify events before being passed to the client. While delivering the event to the client is appropriate in most cases, it is not appropriate for some clients that maintain per-key data structures. This is because once the server has sent a NewKeyboardNotify event, it is free to send the client events for all keys in the new range and that range may be outside of the per-key data structures the client is maintaining.

The *IgnoreNewKeyboards* control, if enabled, prevents Xkb from mapping NewKeyboardNotify events to core MappingNotify events and passing them to the client. The control is initially disabled.

## **Manipulating the Library Controls**

The Library Controls are manipulated using functions that deal with bitmasks to indicate which controls to manipulate. The controls are identified by the masks defined in Table 11.1.

**Table 11.1. Library Control Masks** 

Library Control Mask	Value
XkbLC_ForceLatin1Lookup	(1 << 0)
$XkbLC\_ConsumeLookupMods$	(1 << 1)
XkbLC_AlwaysConsumeShiftAndLock	(1 << 2)
XkbLC_IgnoreNewKeyboards	(1 << 3)
XkbLC_ConsumeKeysOnComposeFail	(1 << 29)
XkbLC_ComposeLED	(1 << 30)
XkbLC_BeepOnComposeFail	(1 << 31)
XkbLC_AllControls	(0xc0000007)

## **Determining Which Library Controls are Implemented**

To determine which Library Controls are actually implemented, use XkbXlibControlsImplemented.

 $\verb"unsigned" int {\tt XkbXlibControlsImplemented"} (display);$ 

display connection to X server

XkbXlibControlsImplemented returns a bitmask indicating the controls actually implemented in the Xkb library and is composed of an inclusive OR of bits from Table 11.1.

## **Determining the State of the Library Controls**

To determine the current state of the Library Controls, use  ${\tt XkbGetXlibControls}$ .

XkbGetXlibControls returns the current state of the Library Controls as a bit mask that is an inclusive OR of the control masks from Table 11.1 for the controls that are enabled. For the optional compose processing controls, the fact that a control is enabled does not imply that it is actually implemented.

## Changing the State of the Library Controls

To change the state of the Library Controls, use XkbSetXlibControls.

Bool XkbSetXlibControls(display, bits\_to\_change, values\_for\_bits);

display connection to X server

bits to change selects controls to be modified

values\_for\_bits turns selected controls on (1) or off (0)

XkbSetXlibControls modifies the state of the controls selected by bits\_to\_change; only the controls selected by bits\_to\_change are modified. If the bit corresponding to a control is on in bits\_to\_change and also on in values\_for\_bits, the control is enabled. If the bit corresponding



## **Chapter 12. Interpreting Key Events**

Xkb provides functions to help developers interpret key events without having to directly interpret Xkb data structures. Xkb also modifies the behavior of several core X library functions.

## Effects of Xkb on the Core X Library

When support for Xkb is built into the X library, the XOpenDisplay function looks for a compatible version of Xkb on the server. If it finds a compatible version, it initializes the extension and enables *implicit support* for Xkb in a number of X library functions. This makes it possible for clients to take advantage of nearly all Xkb features without having to be rewritten or even recompiled, if they are built with shared libraries. This implicit support is invisible to most clients, but it can have side effects, so the extension includes ways to control or disable it.

#### Effects of Xkb on Event State

Because XOpenDisplay initializes Xkb, some events contain an Xkb description of the keyboard state instead of that normally used by the core protocol. See section 17.1.1 for more information about the differences between Xkb keyboard state and that reported by the core protocol.

#### Effects of Xkb on MappingNotify Events

When Xkb is missing or disabled, the X library tracks changes to the keyboard mapping using MappingNotify events. Whenever the keyboard mapping is changed, the server sends all clients a MappingNotify event to report the change. When a client receives a MappingNotify event, it is supposed to call XRefreshKeyboardMapping to update the keyboard description used internally by the X library.

The X Keyboard Extension uses XkbMapNotify and XkbNewKeyboardNotify events to track changes to the keyboard mapping. When an Xkb-aware client receives either event, it should call XkbRefreshKeyboardMapping to update the keyboard description used internally by the X library. To avoid duplicate events, the X server does not send core protocol MappingNotify events to a client that has selected for XkbMapNotify events.

The implicit support for Xkb selects for XkbMapNotify events. This means that clients that do not explicitly use Xkb but that are using a version of the X library that has implicit support for Xkb do not receive MappingNotify events over the wire. Clients that were not written with Xkb in mind do not recognize or properly handle the new Xkb events, so the implicit support converts them to MappingNotify events that report approximately the same information, unless the client has explicitly selected for the Xkb version of the event.

An Xkb-capable X server does not send events from keys that fall outside the legal range of keycodes expected by that client. Once the server sends a client an XkbNewKeyboardNotify event, it reports events from all keys because it assumes that any client that has received an XkbNewKeyboardNotify event expects key events from the new range of keycodes. The implicit support for Xkb asks for XkbNewKeyboardNotify events, so the range of keycodes reported to the client might vary without the client's knowledge. Most clients don't really care about the range of legal keycodes, but some clients maintain information about each key and might have problems with events that come from unexpected keys. Such clients can set the XkbLC\_IgnoreNewKeyboards library control (see section 11.3.1) to prevent the implicit support from requesting notification of changes to the legal range of keycodes.

### X Library Functions Affected by Xkb

The following X library functions are modified by Xkb:

XKeycodeToKeysym XKeysymToKeycode XLookupKeysym XLookupString XRefreshKeyboardMapping XRebindKeysym

The implicit support for Xkb replaces a number of X library functions with versions that understand and use the X Keyboard Extension. In most cases, the semantics of the new versions are identical to those of the old, but there are occasional visible differences. This section lists all of the functions that are affected and the differences in behavior, if any, that are visible to clients.

The XKeycodeToKeysym function reports the keysym associated with a particular index for a single key. The index specifies a column of symbols in the core keyboard mapping (that is, as reported by the core protocol GetKeyboardMapping request). The order of the symbols in the core mapping does not necessarily correspond to the order of the symbols used by Xkb; section 17.1.3 describes the differences.

The XKeysymToKeycode function reports a keycode to which a particular keysym is bound. When Xkb is missing or disabled, this function looks in each column of the core keyboard mapping in turn and returns the lowest numbered key that matches in the lowest numbered group. When Xkb is present, this function uses the Xkb ordering for symbols instead.

The XLookupKeysym function reports the symbol in a specific column of the key associated with an event. Whether or not Xkb is present, the column specifies an index into the core symbol mapping.

The XLookupString function reports the symbol and string associated with a key event, taking into account the keycode and keyboard state as reported in the event. When Xkb is disabled or missing, XLookupString uses the rules specified by the core protocol and reports only ISO Latin-1 characters. When Xkb is present, XLookupString uses the explicit keyboard group, key types, and rules specified by Xkb. When Xkb is present, XLookupString is allowed, but not required, to return strings in character sets other than ISO Latin-1, depending on the current locale. If any key bindings are defined, XLookupString does not use any consumed modifiers (see section 11.1.2 and section 15.2) to determine matching bindings.

The XRefreshKeyboardMapping function updates the X library's internal representation of the keyboard to reflect changes reported via MappingNotify events. When Xkb is missing or disabled, this function reloads the entire modifier map or keyboard mapping. When Xkb is present, the implicit Xkb support keeps track of the changed components reported by each XkbMapNotify event and updates only those pieces of the keyboard description that have changed. If the implicit support has not noted any keyboard mapping changes, XRefreshKeyboardMapping updates the entire keyboard description.

The XRebindKeysym function associates a string with a keysym and a set of modifiers. Xkb does not directly change this function, but it does affect the way that the state reported in the event is compared to the state specified to XRebindKeysym. When Xkb is missing or disabled, XLookupString returns the specified string if the modifiers in the event exactly match the modifiers from this call. When Xkb is present, any modifiers used to determine the keysym are consumed and are not used to look up the string.

## **Xkb Event and Keymap Functions**

dpy

To find the keysym bound to a particular key at a specified group and shift level, use XkbKeycodeToKeysym.

```
KeySym XkbKeycodeToKeysym(dpy, kc, group, level);
```

connection to X server

kc key of interest

group group of interest

level shift level of interest

XkbKeycodeToKeysym returns the keysym bound to a particular group and shift level for a particular key on the core keyboard. If kc is not a legal keycode for the core keyboard, or if group or level are out of range for the specified key, XkbKeycodeToKeysym returns NoSymbol.

To find the set of modifiers bound to a particular keysym on the core keyboard, use XkbKeysymToModifiers.

unsigned int **XkbKeysymToModifiers**(dpy, ks);

dpy connection to X server

ks keysym of interest

XkbKeysymToModifiers finds the set of modifiers currently bound to the keysym ks on the core keyboard. The value returned is the mask of modifiers bound to the keysym ks. If no modifiers are bound to the keysym, XkbKeysymToModifiers returns zero; otherwise, it returns the inclusive OR of zero or more of the following: ShiftMask, ControlMask, LockMask, Mod1Mask, Mod2Mask, Mod3Mask, Mod4Mask, and Mod5Mask.

Use XkbLookupKeySym to find the symbol associated with a key for a particular state.

Bool **XkbLookupKeySym**(dpy, key, state, mods\_rtrn, sym\_rtrn);

dpy connection to X server

key key for which symbols are to be found

state state for which symbol should be found

mods\_rtrn backfilled with consumed modifiers

sym\_rtrn backfilled with symbol associated with key + state

XkbLookupKeySym is the equivalent of the core XLookupKeySym function. For the core keyboard, given a keycode key and an Xkb state state, XkbLookupKeySym returns the symbol associated with the key in sym\_rtrn and the list of modifiers that should still be applied in mods\_rtrn. The state parameter is the state from a KeyPress or KeyRelease event. XkbLookupKeySym returns True if it succeeds.

Use XkbLookupKeyBinding to find the string bound to a key by XRebindKeysym. XkbLookupKeyBinding is the equivalent of the core XLookupString function.

int XkbLookupKeyBinding(dpy, sym, state, buf, nbytes, extra\_rtrn);

dpy connection to server

sym symbol to be looked up

state state for which string is to be looked up

buff buffer into which returned string is written

nbytes size of buffer in bytes

extra\_rtrn backfilled with number bytes overflow

XRebindKeysym binds an ASCII string to a specified keysym, so that the string and keysym are returned when the key is pressed and a specified list of modifiers are also being held down. XkbLookupKeyBinding returns in buf the string associated with the keysym sym and modifier state state. buf is NULL terminated unless there's an overflow. If the string returned is larger than nbytes, a count of bytes that does not fit into the buffer is returned in extra\_rtrn. XkbTranslateKeySym returns the number of bytes that it placed into buf.

To find the string and symbol associated with a keysym for a given keyboard state, use XkbTranslateKeySym.

int XkbTranslateKeySym(dpy, sym\_inout, mods, buf, nbytes, extra\_rtrn);

dpy connection to X server

sym\_inout symbol to be translated; result of translation

mods modifiers to apply to sym\_inout

buf buffer into which returned string is written

nbytes size of buffer in bytes

extra\_rtrn number of bytes overflow

XkbTranslateKeySym applies the transformations specified in *mods* to the symbol specified by  $sym\_inout$ . It returns in *buf* the string, if any, associated with the keysym for the current locale. If the transformations in *mods* changes the keysym,  $sym\_inout$  is updated accordingly. If the string returned is larger than *nbytes*, a count of bytes that does not fit into the buffer is returned in extra\_rtrn. XkbTranslateKeySym returns the number of bytes it placed into *buf*.

To update the keyboard description that is internal to the X library, use XkbRefreshKeyboardMapping.

Status **XkbRefreshKeyboardMapping**(event);

event initiating remapping

XkbRefreshKeyboardMapping is the Xkb equivalent of the core XRefreshKeyboardMapping function. It requests that the X server send the current key mapping information to this client. A client usually invokes XkbRefreshKeyboardMapping after receiving an XkbMapNotify event. XkbRefreshKeyboardMapping returns Success if it succeeds and BadMatch if the event is not an Xkb event.

The XkbMapNotify event can be generated when some client calls XkbSetMap, XkbChangeMap, XkbGetKeyboardByName, or any of the standard X library functions that change the keyboard mapping or modifier mapping.

To translate a keycode to a key symbol and modifiers, use XkbTranslateKeyCode.

Bool **XkbTranslateKeyCode**(xkb, key, mods, mods\_rtrn, keysym\_rtrn);

xkb keyboard description to use for translation

key keycode to translate

#### **Interpreting Key Events**

mods modifiers to apply when translating key

mods\_rtrn backfilled with consumed modifiers

keysym\_rtrn keysym resulting from translation

<code>mods\_rtrn</code> is backfilled with the modifiers consumed by the translation process. <code>mods</code> is a bitwise inclusive OR of the legal modifier masks: ShiftMask, LockMask, ControlMask, Mod1Mask, Mod2Mask, Mod3Mask, Mod4Mask, Mod5Mask. The <code>AlwaysConsumeShiftAndLock</code> library control (see section 11.1.3), if enabled, causes <code>XkbTranslateKeyCode</code> to consume shift and lock. <code>XkbTranslateKeyCode</code> returns True if the translation resulted in a keysym, and False if it resulted in NoSymbol.


# **Chapter 13. Keyboard Geometry**

The Xkb description of a keyboard includes an optional keyboard geometry that describes the physical appearance of the keyboard. Keyboard geometry describes the shape, location, and color of all keyboard keys or other visible keyboard components such as indicators. The information contained in a keyboard geometry is sufficient to allow a client program to draw an accurate two-dimensional image of the keyboard.

You can retrieve a keyboard geometry from an X server that supports Xkb, or you can allocate it from scratch and initialize it in a client program. The keyboard geometry need not have any correspondence with the physical keyboard that is connected to the X server.

Geometry measurements are specified in mm/10 units. The origin (0,0) is in the top left corner of the keyboard image. A component's own origin is also its upper left corner. In some cases a component needs to be drawn rotated. For example, a special keyboard may have a section of keys arranged in rows in a rectangular area, but the entire rectangle may not be in alignment with the rest of the keyboard, and instead, it is rotated from horizontal by 30°. Rotation for a geometry object is specified in 1/10° increments about its origin. An example of a keyboard with rotated sections is shown in Figure 13.1.

Figure 13.1. Rotated Keyboard Sections



Some geometry components include a priority, which indicates the order in which overlapping objects should be drawn. Objects should be drawn in order from highest priority (0) to lowest (255).

The keyboard geometry's top-level description is stored in a XkbGeometryRec structure. This structure contains three types of information:

- 1. Lists of items, not used to draw the basic keyboard, but indexed by the geometry descriptions that comprise the entire keyboard geometry (colors, geometry properties, key aliases, shapes)
- 2. A number of singleton items that describe the keyboard as a whole (keyboard name, width and height, a color for the keyboard as a whole, and a color for keyboard key labels)
- 3. A list of the keyboard's sections and nonkey doodads

The top-level geometry is described in more detail in the following.

The lists of items used by components of the keyboard geometry description is as follows:

- The top-level keyboard geometry description includes a list of up to XkbGeomMaxColors (32) color names. A color name is a string whose interpretation is not specified by Xkb. The XkbColorRec structure provides a field for this name as well as a pixel field. The pixel field is a convenient place for an application to store a pixel value or color definition, if it needs to. All other geometry data structures refer to colors using their indices in this global list.
- The top-level keyboard geometry description includes a list of *geometry properties*. A geometry property associates an arbitrary string with an equally arbitrary name. Geometry properties can be used to provide hints to programs that display images of keyboards, but they are not interpreted by Xkb. No other geometry structures refer to geometry properties. As an example of a possible use of *properties*, consider the pause/break key on most PC keyboards: the "break" symbol is usually on the front of the key and is often a different color. A program might set a property to:

LBL\_PAUS = "{Pause/top/black,Break/front/red}"

and use the property information to draw the key with a front label as well as a top label.

• The top-level keyboard geometry description includes a list of *key aliases* (see Chapter 18, *Symbolic Names*). Key aliases allow the keyboard layout designer to assign multiple key names to a single key.

#### Note

Key aliases defined in the geometry component of a keyboard mapping override those defined in the keycodes component of the server database, which are stored in the XkbNamesRec (xkb->names). Therefore, consider the key aliases defined by the geometry before considering key aliases supplied by the keycodes.


• The top-level keyboard geometry description includes a list of <code>shapes</code>; other keyboard components refer to shapes by their index in this list. A shape consists of an arbitrary name of type Atom and one or more closed-polygon <code>outlines</code>. All points in an outline are specified relative to the origin of its enclosing shape, that is, whichever shape that contains this outline in its list of outlines. One outline is the primary outline. The primary outline is by default the first outline, or it can be optionally specified by the <code>primary</code> field in the XkbShapeRec structure. A keyboard display application can generate a simpler but still accurate keyboard image by displaying only the primary outlines for each shape. Nonrectangular keys must include a rectangular <code>approximation</code> as one of the outlines associated with the shape. The approximation is not normally displayed but can be used by very simple keyboard display applications to generate a recognizable but degraded image of the keyboard.

The XkbGeometryRec top-level geometry description contains the following information that pertains to the keyboard as a whole:

- A keyboard symbolic name of type Atom to help users identify the keyboard.
- The width and height of the keyboard, in mm/10. For nonrectangular keyboards, the width and height describe the smallest bounding box that encloses the outline of the keyboard.
- The *base color* of the keyboard is the predominant color on the keyboard and is used as the default color for any components whose color is not explicitly specified.
- The *label color* is the color used to draw the labels on most of the keyboard keys.
- The *label font* is a string that describes the font used to draw labels on most keys; label fonts are arbitrary strings, because Xkb does not specify the format or name space for font names.

The keyboard is subdivided into named <code>sections</code> of related keys and doodads. The sections and doodads on the keyboard are listed in the XkbGeometryRec top-level keyboard geometry description. A section is composed of keys that are physically together and logically related. Figure 13.2 shows a keyboard that is divided into four sections. A <code>doodad</code> describes some visible aspect of the keyboard that is not a key and is not a section.

Figure 13.2. Keyboard with Four Sections



## **Shapes and Outlines**

A shape, used to draw keyboard components and stored in a XkbShapeRec structure, has:

- An arbitrary name of type Atom.
- Bounds (two x and y coordinates) that describe the corners of a rectangle containing the shape's top surface outline.
- A list of one or more outlines (described below).
- Optional pointers to a primary and an approximation outline (described below). If either of these pointers is NULL, the default primary/approximation outline is the first one in the list of outlines for the shape.

An *outline*, stored in a XkbOutlineRec structure, is a list of one or more points that describes a single closed-polygon, as follows:

- A list with a single point describes a rectangle with one corner at the origin of the shape (0,0) and the opposite corner at the specified point.
- A list of two points describes a rectangle with one corner at the position specified by the first point and the opposite corner at the position specified by the second point.
- A list of three or more points describes an arbitrary polygon. If necessary, the polygon is automatically closed by connecting the last point in the list with the first.

• A nonzero value for the *corner\_radius* field specifies that the corners of the polygon should be drawn as circles with the specified radius.

All points in an outline are specified relative to the origin of the enclosing shape. Points in an outline may have negative values for the X and Y coordinate.


One outline is the primary outline; a keyboard display application can generate a simple but still accurate keyboard image by displaying only the primary outlines for each shape. The default primary outline is the first in a shape's list of outlines. If the primary field of the XkbShapeRec structure is not NULL, it points to the primary outline. A rectangular approximation must be included for nonrectangular keys as one of the outlines associated with the shape; the approximation is not normally displayed but can be used by very simple keyboard display applications to generate a recognizable but degraded image of the keyboard.

#### **Sections**

As previously noted, a keyboard is subdivided into sections of related keys. Each section has its own coordinate system — if a section is rotated, the coordinates of any components within the section are interpreted relative to the edges that were on the top and left before rotation. The components that make up a section, stored in a XkbSectionRec, include:

- An arbitrary name of type Atom.
- A priority, to indicate drawing order. 0 is the highest priority, 255 the lowest.
- Origin of the section, relative to the origin of the keyboard.
- The width and height and the angle of rotation.
- A list of *rows*. A row is a list of horizontally or vertically adjacent keys. Horizontal rows parallel the (prerotation) top of the section, and vertical rows parallel the (prerotation) left of the section. All keys in a horizontal row share a common top coordinate; all keys in a vertical row share a left coordinate. Figure 13.3 shows the alpha section from the keyboard shown in Figure 13.2, divided into rows. Rows and keys are defined below.

Figure 13.3. Rows in a Section



- An optional list of *doodads*; any type of doodad can be enclosed within a section. Position and angle of rotation are relative to the origin and angle of rotation of the sections that contain them. Priority for doodads in a section is relative to the other components of the section, not to the keyboard as a whole.
- An optional *overlay* with a name of type Atom and a list of overlay rows (described below).
- Bounds (two x and y coordinates) that describe the corners of a rectangle containing the entire section.

# **Rows and Keys**

A row description (XkbRowRec) consists of the coordinates of its origin relative to its enclosing section, a flag indicating whether the row is horizontal or vertical, and a list of keys in the row.

A key description (XkbKeyRec) consists of a key name, a shape, a key color, and a gap. The key name should correspond to one of the keys named in the keyboard names description, the shape specifies the appearance of the key, and the key color specifies the color of the key (not the label on the key; the label color is stored in the XkbGeometryRec). Keys are normally drawn immediately adjacent to one another from left to right (or top to bottom) within a row. The gap field specifies the distance between a key and its predecessor.

#### **Doodads**

Doodads can be global to the keyboard or part of a section. Doodads have symbolic names of arbitrary length. The only doodad name whose interpretation is specified by Xkb is "Edges", which, if present, describes the outline of the entire keyboard.

Each doodad's origin is stored in fields named *left* and *top*, which are the coordinates of the doodad's origin relative to its enclosing object, whether it be a section or the top-level keyboard. The priority for doodads that are listed in the top-level geometry is relative to the other doodads listed in the top-level geometry and the sections listed in the top-level geometry. The priority for doodads listed in a section are relative to the other components of the section. Each doodad is stored in a structure with a *type* field, which specifies the type of doodad.

Xkb supports five types of doodads:

- An *indicator doodad* describes one of the physical keyboard indicators. Indicator doodads specify the shape of the indicator, the indicator color when it is lit (*on\_color*) and the indicator color when it is dark (*off color*).
- An *outline doodad* describes some aspect of the keyboard to be drawn as one or more hollow, closed polygons. Outline doodads specify the shape, color, and angle of rotation about the doodad origin at which they should be drawn.
- A solid doodad describes some aspect of the keyboard to be drawn as one or more filled polygons. Solid
  doodads specify the shape, color, and angle of rotation about the doodad origin at which they should
  be drawn.
- A *text doodad* describes a text label somewhere on the keyboard. Text doodads specify the label string, the font and color to use when drawing the label, and the angle of rotation of the doodad about its origin.
- A *logo doodad* is a catch-all, which describes some other visible element of the keyboard. A logo doodad is essentially an outline doodad with an additional symbolic name that describes the element to be drawn.

If a keyboard display program recognizes the symbolic name, it can draw something appropriate within the bounding region of the shape specified in the doodad. If the symbolic name does not describe a recognizable image, it should draw an outline using the specified shape, outline, and angle of rotation. The Xkb extension does not specify the interpretation of logo names.

The structures these doodads are stored in and the values of the type fields are shown in Table 13.1.

Table 13.1. Doodad Types

Doodad	Structure	Туре
indicator doodad	XkbIndicatorDoodadRec	XkbIndicatorDoodad
outline doodad	XkbShapeDoodadRec	XkbOutlineDoodad
solid doodad	XkbShapeDoodadRec	XkbSolidDoodad
text doodad	XkbTextDoodadRec	XkbTextDoodad
logo doodad	XkbLogoDoodadRec	XkbLogoDoodad

# **Overlay Rows and Overlay Keys**

An overlay row (XkbOverlayRowRec) contains a pointer to the row it overlays and a list of overlay keys.

Each overlay key definition (XkbOverlayKeyRec) indicates a key that can yield multiple keycodes and consists of a field named *under*, which specifies the primary name of the key and a field named *over*, which specifies the name for the key when the overlay keycode is selected. The key specified in *under* must be a member of the section that contains the overlay key definition, while the key specified in over must not be.

# **Drawing a Keyboard Representation**

To draw a representation of the keyboard, draw in the following order:

```
Draw the top-level keyboard as a rectangle, using its width and height.

For each component (section or doodad) of the top-level geometry, in priority

If component is a section

For each row, in the order it appears in the section

Draw keys in the order they appear in the row

Draw doodads within the section in priority order.
```

# **Geometry Data Structures**

Else draw doodad

In the following figures, a solid arrow denotes a pointer to an array of structures or a singleton structure. A dotted arrow denotes an index or a pointer into the array.

label\_color XkbPropertyRec(s) (array) base\_color properties XkbColorRec(s) (array) colors shapes outlines sections approx doodads primary XkbOutlineRec(s) key\_aliases (array) bounds XkbGeometryRec XkbShapeRec(s) (array) XkbBoundsRec XkbKeyAliasRec(s) (array) (See Figure 13.5) . . . rows doodads(s) keys (array) shape\_ndx doodads bounds color\_ndx bounds XkbRowRec(s) overlays (array) XkbKeyRec(s) (array) XkbSectionRec(s) (array) (See Figure 13.5) XkbBoundsRec (See Figure 13.6) doodads(s) (array) overlays(s) (array)

Figure 13.4. Xkb Geometry Data Structures

XkbBoundsRec





Figure 13.6. Xkb Geometry Data Structures (Overlays)



```
XkbColorPtr
                      label_color;
                                       /* color for key labels
                                          - pointer into colors array */
                                       /* color for basic keyboard
   XkbColorPtr
                     base color;
                                          - pointer into colors array */
   unsigned short
                      sz_properties;
                                       /* size of properties array */
                                       /* size of colors array */
   unsigned short
                      sz_colors;
   unsigned short
                                       /* size of shapes array */
                     sz_shapes;
   unsigned short
                     sz sections;
                                      /* size of sections array */
                                       /* size of doodads array */
   unsigned short
                     sz doodads;
   unsigned short
                     sz_key_aliases;
                                       /* size of key aliases array */
   unsigned short
                                      /* number of properties in the
                     num_properties;
                                           properties array */
                     num colors;
                                       /* number of colors in the
   unsigned short
                                           colors array */
                                       /* number of shapes in the
   unsigned short
                     num shapes;
                                           shapes array */
                                       /* number of sections in the
   unsigned short
                     num sections;
                                           sections array */
   unsigned short
                     num doodads;
                                       /* number of doodads in the
                                           doodads array */
                     num_key_aliases; /* number of key aliases in the
   unsigned short
                                           key_aliases array */
   XkbPropertyPtr
                     properties;
                                       /* properties array */
                                       /* colors array */
   XkbColorPtr
                     colors;
   XkbShapePtr
                     shapes;
                                       /* shapes array */
                                      /* sections array */
   XkbSectionPtr
                      sections;
   XkbDoodadPtr
                     doodads;
                                       /* doodads array */
   XkbKeyAliasPtr
                     key aliases;
                                       /* key aliases array */
} XkbGeometryRec, *XkbGeometryPtr;
```

The doodads array is only for doodads not contained in any of the sections that has its own doodads. The key aliases contained in the key\_aliases array take precedence over any defined in the keycodes component of the keyboard description.

```
typedef struct _XkbProperty {
    char *
               name;
                                         /* property name */
    char *
                                         /* property value */
               value;
} XkbPropertyRec, *XkbPropertyPtr;
typedef struct _XkbColor {
                                        /* color */
   unsigned int
                      pixel;
                                        /* color name */
                      spec;
} XkbColorRec, *XkbColorPtr;
typedef struct _XkbKeyAliasRec {
             real[XkbKeyNameLength];
                                        /* real name of the key */
    char
              alias[XkbKeyNameLength];
                                        /* alias for the key */
} XkbKeyAliasRec, *XkbKeyAliasPtr;
typedef struct _XkbPoint {
                                        /* x, y coordinates */
    short
              x;
```

```
short
               у;
} XkbPointRec, *XkbPointPtr;
typedef struct _XkbOutline {
                                          /* number of points in the outline */
    unsigned short
                         num_points;
    unsigned short
                         sz_points;
                                          /* size of the points array */
                                          /* draw corners as circles
    unsigned short
                         corner_radius;
                                             with this radius */
    XkbPointPtr
                                          /* array of points defining
                         points;
                                             the outline */
} XkbOutlineRec, *XkbOutlinePtr;
typedef struct _XkbBounds {
                              /* upper left corner of the bounds, in ^{mm}/_{10} */
    short
               x1, y1;
                             /* lower right corner of the bounds, in ^{mm}/_{10} */
    short
               x2, y2;
} XkbBoundsRec, *XkbBoundsPtr;
typedef struct _XkbShape {
    Atom
                                          /* shape's name */
                       name;
    unsigned short
                       num outlines;
                                          /* number of outlines for the shape */
                                          /* size of the outlines array */
    unsigned short
                       sz_outlines;
    XkbOutlinePtr
                       outlines;
                                          /* array of outlines for the shape */
    XkbOutlinePtr
                                          /* pointer into the array to the
                       approx;
                                             approximating outline */
                                          /* pointer into the array to the
    XkbOutlinePtr
                       primary;
                                             primary outline */
    XkbBoundsRec
                       bounds;
                                          /* bounding box for the shape;
                                             encompasses all outlines */
} XkbShapeRec, *XkbShapePtr;
If approx and/or primary is NULL, the default value is used. The default primary outline is the first
element in the outlines array, as is the default approximating outline.
typedef struct _XkbKey {
                                     /* key in a row */
    XkbKeyNameRec
                                     /* key name */
                      name;
                                     /* gap in ^{mm}/_{10} from previous key in row */
    short
                      qap;
                                    /* index of shape for key */
    unsigned char
                      shape_ndx;
    unsigned char
                      color ndx;
                                    /* index of color for key body */
} XkbKeyRec, *XkbKeyPtr;
typedef struct _XkbRow {
                                     /* row in a section */
                                     /* top coordinate of row origin,
    short
                         top;
                                        relative to section's origin */
    short
                         left;
                                     /* left coordinate of row origin,
                                        relative to section's origin */
                         num_keys;
    unsigned short
                                    /* number of keys in the keys array */
    unsigned short
                                     /* size of the keys array */
                         sz_keys;
    int
                         vertical;
                                    /* True #vertical row,
                                        False #horizontal row */
                                     /* array of keys in the row */
    XkbKeyPtr
                         keys;
```

```
XkbBoundsRec
                        bounds;
                                    /* bounding box for the row */
} XkbRowRec, *XkbRowPtr;
top and left are in ^{mm}/_{10}.
typedef struct _XkbOverlayRec {
    Atom
                      name;
                                       /* overlay name */
   XkbSectionPtr
                      section_under; /* the section under this overlay */
                                      /* number of rows in the rows array */
    unsigned short
                      num_rows;
   unsigned short
                                      /* size of the rows array */
                      sz_rows;
   XkbOverlayRowPtr
                      rows;
                                       /* array of rows in the overlay */
                                       /* bounding box for the overlay */
   XkbBoundsPtr
                      bounds;
} XkbOverlayRec, *XkbOverlayPtr;
typedef struct _XkbOverlayRow {
   unsigned short
                                       /* index into the row under this
                        row_under;
                                          overlay row */
   unsigned short
                        num_keys;
                                       /* number of keys in the keys array */
    unsigned short
                        sz keys;
                                       /* size of the keys array */
   XkbOverlayKeyPtr
                        keys;
                                       /* array of keys in the overlay row */
} XkbOverlayRowRec, *XkbOverlayRowPtr;
row_under is an index into the array of rows in the section under this overlay. The section under this
overlay row is the one pointed to by section_under in this overlay row's XkbOverlayRec.
typedef struct XkbOverlayKey {
   XkbKeyNameRec
                       over;
                                   /* name of this overlay key */
    XkbKeyNameRec
                       under;
                                   /* name of the key under this overlay key */
} XkbOverlayKeyRec, *XkbOverlayKeyPtr;
typedef struct _XkbSection {
                                    /* section name */
                    name;
                                    /* drawing priority, 0#highest, 255#lowest */
   unsigned char
                    priority;
    short
                    top;
                                    /* top coordinate of section origin */
    short
                    left;
                                    /* left coordinate of row origin */
                                    /* section width, in ^{mm}/_{10} */
    unsigned short width;
                                    /* section height, in ^{mm}/_{10} */
   unsigned short height;
                                    /* angle of section rotation,
    short
                    angle;
                                       counterclockwise */
                                    /* number of rows in the rows array */
   unsigned short num_rows;
   unsigned short num_doodads;
                                   /* number of doodads in the doodads array */
   unsigned short num_overlays; /* number of overlays in the overlays array */
   unsigned short sz_rows;
                                    /* size of the rows array */
   unsigned short sz_doodads;
                                    /* size of the doodads array */
    unsigned short sz overlays;
                                   /* size of the overlays array */
   XkbRowPtr
                                    /* section rows array */
                    rows;
    XkbDoodadPtr
                    doodads;
                                    /* section doodads array */
   XkbBoundsRec
                                    /* bounding box for the section,
                    bounds;
                                       before rotation */
                                    /* section overlays array */
   XkbOverlayPtr
                    overlays;
} XkbSectionRec, *XkbSectionPtr;
```

top and left are the origin of the section, relative to the origin of the keyboard, in  $^{mm}/_{10}$ . angle is in  $^{1}/_{10}$  degrees.

#### **DoodadRec Structures**

The doodad arrays in the XkbGeometryRec and the XkbSectionRec may contain any of the doodad structures and types shown in Table 13.1.

The doodad structures form a union:

```
typedef union _XkbDoodad {
     XkbAnyDoodadRec any;
     XkbShapeDoodadRec shape;
     XkbTextDoodadRec text;
     XkbIndicatorDoodadRec indicator;
     XkbLogoDoodadRec logo;
} XkbDoodadRec, *XkbDoodadPtr;
```

The <code>top</code> and <code>left</code> coordinates of each doodad are the coordinates of the origin of the doodad relative to the keyboard's origin if the doodad is in the XkbGeometryRec doodad array, and with respect to the section's origin if the doodad is in a XkbSectionRec doodad array. The <code>color\_ndx</code> or <code>on\_color\_ndx</code> and <code>off\_color\_ndx</code> fields are color indices into the XkbGeometryRec's color array and are the colors to draw the doodads with. Similarly, the <code>shape\_ndx</code> fields are indices into the XkbGeometryRec's shape array.

```
typedef struct _XkbShapeDoodad {
                                       /* doodad name */
                       name;
    unsigned char
                       type;
                                       /* XkbOutlineDoodad
                                          or XkbSolidDoodad */
    unsigned char
                                       /* drawing priority,
                       priority;
                                           O#highest, 255#lowest */
                                       /* top coordinate, in ^{mm}/_{10} */
    short
                       top;
                                       /* left coordinate, in ^{mm}/_{10} */
    short
                       left;
                                       /* angle of rotation, clockwise,
    short
                       angle;
                                          in ^{1}/_{10} degrees */
    unsigned short
                       color ndx;
                                       /* doodad color */
    unsigned short
                                       /* doodad shape */
                       shape ndx;
} XkbShapeDoodadRec, *XkbShapeDoodadPtr;
typedef struct _XkbTextDoodad {
                                       /* doodad name */
    Atom
                       name;
    unsigned char
                                       /* XkbTextDoodad */
                       type;
                                       /* drawing priority,
    unsigned char
                       priority;
                                         O#highest, 255#lowest */
                                       /* top coordinate, in ^{mm}/_{10} */
    short
                       top;
                                       /* left coordinate, in ^{mm}/_{10} */
                       left;
    short
    short
                       angle;
                                       /* angle of rotation, clockwise,
                                          in ^{1}/_{10} degrees */
                                       /* width in ^{mm}/_{10} */
    short
                       width;
                                      /* height in ^{mm}/_{10} */
    short
                       height;
    unsigned short
                                       /* doodad color */
                       color_ndx;
```

```
/* doodad text */
    char *
                      text;
    char *
                      font;
                                     /* arbitrary font name for doodad text */
} XkbTextDoodadRec, *XkbTextDoodadPtr;
typedef struct _XkbIndicatorDoodad {
                                     /* doodad name */
    Atom
                      name;
                                     /* XkbIndicatorDoodad */
    unsigned char
                      type;
    unsigned char
                                     /* drawing priority, 0#highest, 255#lowest */
                      priority;
                                     /* top coordinate, in ^{mm}/_{10} */
    short
                      top;
                                     /* left coordinate, in ^{mm}/_{10} */
                      left;
    short
                                     /* angle of rotation, clockwise,
    short
                      angle;
                                        in ^{1}/_{10} degrees */
    unsigned short
                      shape_ndx;
                                     /* doodad shape */
                      on_color_ndx; /* color for doodad if indicator is on */
    unsigned short
    unsigned short
                      off color ndx;/* color for doodad if indicator is off */
} XkbIndicatorDoodadRec, *XkbIndicatorDoodadPtr;
typedef struct _XkbLogoDoodad {
                                     /* doodad name */
    Atom
                      name;
                                     /* XkbLogoDoodad */
    unsigned char
                      type;
    unsigned char
                                     /* drawing priority, 0#highest, 255#lowest */
                      priority;
                                     /* top coordinate, in ^{mm}/_{10} */
    short
                      top;
                                     /* left coordinate, in ^{mm}/_{10} */
    short
                      left;
    short
                      angle;
                                     /* angle of rotation, clockwise,
                                        in ^{1}/_{10} degrees */
                                     /* doodad color */
    unsigned short
                      color_ndx;
    unsigned short
                      shape_ndx;
                                     /* doodad shape */
                                     /* text for logo */
    char *
                      logo_name;
} XkbLogoDoodadRec, *XkbLogoDoodadPtr
```

# **Getting Keyboard Geometry From the Server**

You can load a keyboard geometry as part of the keyboard description returned by XkbGetKeyboard. However, if a keyboard description has been previously loaded, you can instead obtain the geometry by calling the XkbGetGeometry. In this case, the geometry returned is the one associated with the keyboard whose device ID is contained in the keyboard description.

To load a keyboard geometry if you already have the keyboard description, use XkbGetGeometry.

```
Status xkbGetGeometry(dpy, xkb);

dpy connection to the X server

xkb keyboard description that contains the ID for the keyboard and into which the geometry should be loaded
```

XkbGetGeometry can return BadValue, BadImplementation, BadName, BadAlloc, or BadLength errors or Success if it succeeds.

It is also possible to load a keyboard geometry by name. The X server maintains a database of keyboard components (see Chapter 20, *Server Database of Keyboard Components*). To load a keyboard geometry description from this database by name, use XkbGetNamedGeometry.

Status **XkbGetNamedGeometry**(dpy, xkb, name);

dpy connection to the X server

xkb keyboard description into which the geometry should be loaded

name of the geometry to be loaded


XkbGetNamedGeometry can return BadName if the name cannot be found.

# **Using Keyboard Geometry**

Xkb provides a number of convenience functions to help use a keyboard geometry. These include functions to return the bounding box of a shape's top surface and to update the bounding box of a shape row or section.

A shape is made up of a number of outlines. Each outline is a polygon made up of a number of points. The bounding box of a shape is a rectangle that contains all the outlines of that shape.

Figure 13.7. Key Surface, Shape Outlines, and Bounding Box



To determine the bounding box of the top surface of a shape, use XkbComputeShapeTop.

Bool **XkbComputeShapeTop**(shape, bounds\_rtrn);

shape shape to be examined

bounds\_rtrn backfilled with the bounding box for the shape

XkbComputeShapeTop returns a BoundsRec that contains two x and y coordinates. These coordinates describe the corners of a rectangle that contains the outline that describes the top surface of the shape. The top surface is defined to be the approximating outline if the approx field of shape is not NULL. If approx is NULL, the top surface is defined as the last outline in the shape's array of outlines. XkbComputeShapeTop returns False if shape is NULL or if there are no outlines for the shape; otherwise, it returns True.

A ShapeRec contains a BoundsRec that describes the bounds of the shape. If you add or delete an outline to or from a shape, the bounding box must be updated. To update the bounding box of a shape, use XkbComputeShapeBounds.

Bool XkbComputeShapeBounds(shape);

shape shape to be examined

XkbComputeShapeBounds updates the BoundsRec contained in the *shape* by examining all the outlines of the shape and setting the BoundsRec to the minimum x and minimum y, and maximum x and maximum y values found in those outlines. XkbComputeShapeBounds returns False if *shape* is NULL or if there are no outlines for the shape; otherwise, it returns True.

If you add or delete a key to or from a row, or if you update the shape of one of the keys in that row, you may need to update the bounding box of that row. To update the bounding box of a row, use XkbComputeRowBounds.

Bool XkbComputeRowBounds(geom, section, row);

geometry that contains the section

section section that contains the row

row row to be examined and updated

XkbComputeRowBounds checks the bounds of all keys in the row and updates the bounding box of the row if necessary. XkbComputeRowBounds returns False if any of the arguments is NULL; otherwise, it returns True.

If you add or delete a row to or from a section, or if you change the geometry of any of the rows in that section, you may need to update the bounding box for that section. To update the bounding box of a section, use XkbComputeSectionBounds.

```
Bool XkbComputeSectionBounds(geom, section);
```

geometry that contains the section

section section to be examined and updated

XkbComputeSectionBounds examines all the rows of the section and updates the bounding box of that section so that it contains all rows. XkbComputeSectionBounds returns False if any of the arguments is NULL; otherwise, it returns True.

Keys that can generate multiple keycodes may be associated with multiple names. Such keys have a primary name and an alternate name. To find the alternate name by using the primary name for a key that is part of an overlay, use XkbFindOverlayForKey.

```
char *XkbFindOverlayForKey(geom, section, under);
```

geometry that contains the section

section section to be searched for matching keys

under .primary name of the key to be considered

XkbFindOverlayForKey uses the primary name of the key, *under*, to look up the alternate name, which it returns.

## Adding Elements to a Keyboard Geometry

Xkb provides functions to add a single new element to the top-level keyboard geometry. In each case the  $num_*$  fields of the corresponding structure is incremented by 1. These functions do not change  $sz_*$ 

unless there is no more room in the array. Some of these functions fill in the values of the element's structure from the arguments. For other functions, you must explicitly write code to fill the structure's elements.

The top-level geometry description includes a list of *geometry properties*. A geometry property associates an arbitrary string with an equally arbitrary name. Programs that display images of keyboards can use geometry properties as hints, but they are not interpreted by Xkb. No other geometry structures refer to geometry properties.

To add one property to an existing keyboard geometry description, use XkbAddGeomProperty.

XkbPropertyPtr XkbAddGeomProperty(geom, name, value);

geometry to be updated

name of the new property

value value for the new property

XkbAddGeomProperty adds one property with the specified name and value to the keyboard geometry specified by geom. XkbAddGeomProperty returns NULL if any of the parameters is empty or if it was not able to allocate space for the property. To allocate space for an arbitrary number of properties, use the XkbAllocGeomProps function.

To add one key alias to an existing keyboard geometry description, use XkbAddGeomKeyAlias.

XkbKeyAliasPtr XkbAddGeomKeyAlias(geom, alias, real);

geometry to be updated

alias alias to be added

real name to be bound to the new alias

XkbAddGeomKeyAlias adds one key alias with the value alias to the geometry geom, and associates it with the key whose real name is real. XkbAddGeomKeyAlias returns NULL if any of the parameters is empty or if it was not able to allocate space for the alias. To allocate space for an arbitrary number of aliases, use the XkbAllocGeomKeyAliases function.

To add one color name to an existing keyboard geometry description, use XkbAddGeomColor.

XkbColorPtr XkbAddGeomColor(geom, spec, pixel);

geometry to be updated

spec color to be added

pixel color to be added

XkbAddGeomColor adds the specified color name and pixel to the specified geometry geom. The top-level geometry description includes a list of up to MaxColors (32) color names. A color name is a string whose interpretation is not specified by Xkb and neither is the pixel value's interpretation. All other geometry data structures refer to colors using their indices in this global list or pointers to colors in this list. XkbAddGeomColor returns NULL if any of the parameters is empty or if it was not able to allocate space for the color. To allocate space for an arbitrary number of colors to a geometry, use the XkbAllocGeomColors function.

To add one outline to an existing shape, use XkbAddGeomOutline.

XkbOutlinePtr XkbAddGeomOutline(shape, sz\_points);

shape shape to be updated

sz\_points number of points to be reserved

An outline consists of an arbitrary number of points. XkbAddGeomOutline adds an outline to the specified *shape* by reserving *sz\_points* points for it. The new outline is allocated and zeroed. XkbAddGeomOutline returns NULL if any of the parameters is empty or if it was not able to allocate space. To allocate space for an arbitrary number of outlines to a shape, use XkbAllocGeomOutlines.

To add a shape to a keyboard geometry, use XkbAddGeomShape.

XkbShapePtr XkbAddGeomShape(geom, name, sz\_outlines);

geometry to be updated

name of the new shape

sz\_outlines number of outlines to be reserved

A geometry contains an arbitrary number of shapes, each of which is made up of an arbitrary number of outlines. XkbAddGeomShape adds a shape to a geometry <code>geom</code> by allocating space for <code>sz\_outlines</code> outlines for it and giving it the name specified by name. If a shape with name <code>name</code> already exists in the geometry, a pointer to the existing shape is returned. XkbAddGeomShape returns NULL if any of the parameters is empty or if it was not able to allocate space. To allocate space for an arbitrary number of geometry shapes, use XkbAllocGeomShapes.

To add one key at the end of an existing row of keys, use XkbAddGeomKey.

```
XkbKeyPtr XkbAddGeomKey(row);
row row to be updated
```

Keys are grouped into rows. XkbAddGeomKey adds one key to the end of the specified row. The key is allocated and zeroed. XkbAddGeomKey returns NULL if row is empty or if it was not able to allocate space for the key. To allocate space for an arbitrary number of keys to a row, use XkbAllocGeomKeys.

To add one section to an existing keyboard geometry, use XkbAddGeomSection.

```
XkbSectionPtr XkbAddGeomSection(geom, name, sz_rows, sz_doodads,
sz_overlays);
```

geometry to be updated

name of the new section

sz\_rows number of rows to reserve in the section

sz\_doodads number of doodads to reserve in the section

sz\_overlays number of overlays to reserve in the section

A keyboard geometry contains an arbitrary number of sections. XkbAddGeomSection adds one section to an existing keyboard geometry geom. The new section contains space for the number of rows, doodads, and overlays specified by  $sz\_rows$ ,  $sz\_doodads$ , and  $sz\_overlays$ . The new section is allocated and zeroed and given the name specified by name. If a section with name name already exists in the geometry, a pointer to the existing section is returned. XkbAddGeomSection returns NULL if any of

the parameters is empty or if it was not able to allocate space for the section. To allocate space for an arbitrary number of sections to a geometry, use XkbAllocGeomSections.

To add a row to a section, use XkbAddGeomRow.

XkbRowPtr XkbAddGeomRow(section, sz keys);

section section to be updated

sz\_keys number of keys to be reserved

One of the components of a keyboard geometry section is one or more rows of keys. XkbAddGeomRow adds one row to the specified <code>section</code>. The newly created row contains space for the number of keys specified in <code>sz\_keys</code>. They are allocated and zeroed, but otherwise uninitialized. XkbAddGeomRow returns NULL if any of the parameters is empty or if it was not able to allocate space for the row. To allocate space for an arbitrary number of rows to a section, use the XkbAllocGeomRows function.

To add one doodad to a section of a keyboard geometry or to the top-level geometry, use XkbAddGeomDoodad.

XkbDoodadPtr XkbAddGeomDoodad(geom, section, name);

geometry to which the doodad is added

section section, if any, to which the doodad is added

name of the new doodad

A doodad describes some visible aspect of the keyboard that is not a key and is not a section. XkbAddGeomDoodad adds a doodad with name specified by name to the geometry geom if section is NULL or to the section of the geometry specified by section if section is not NULL. XkbAddGeomDoodad returns NULL if any of the parameters is empty or if it was not able to allocate space for the doodad. If there is already a doodad with the name name in the doodad array for the geometry (if section is NULL) or the section (if section is non-NULL), a pointer to that doodad is returned. To allocate space for an arbitrary number of doodads to a section, use the XkbAllocGeomSectionDoodads function. To allocate space for an arbitrary number of doodads to a keyboard geometry, use the XkbAllocGeomDoodads function.

To add one overlay to a section, use XkbAddGeomOverlay.

```
XkbOverlayPtr XkbAddGeomOverlay(section, name, sz_rows);
```

section section to which an overlay will be added

name of the overlay

sz\_rows number of rows to reserve in the overlay

XkbAddGeomOverlay adds an overlay with the specified name to the specified <code>section</code>. The new overlay is created with space allocated for <code>sz\_rows</code> rows. If an overlay with name <code>name</code> already exists in the section, a pointer to the existing overlay is returned. XkbAddGeomOverlay returns NULL if any of the parameters is empty or if it was not able to allocate space for the overlay. To allocate space for an arbitrary number of overlays to a section, use the XkbAllocGeomOverlay function.

To add a row to an existing overlay, use XkbAddGeomOverlayRow.

```
XkbOverlayRowPtr XkbAddGeomOverlayRow(overlay, row_under, sz_keys);
```

overlay overlay to be updated

row\_under row to be overlaid in the section overlay overlays

sz\_keys number of keys to reserve in the row

XkbAddGeomOverlayRow adds one row to the *overlay*. The new row contains space for *sz\_keys* keys. If *row\_under* specifies a row that doesn't exist on the underlying section, XkbAddGeomOverlayRow returns NULL and doesn't change the overlay. XkbAddGeomOverlayRow returns NULL if any of the parameters is empty or if it was not able to allocate space for the overlay.

To add a key to an existing overlay row, use XkbAddGeomOverlayKey.

XkbOverlayKeyPtr XkbAddGeomOverlayKey(overlay, row, under);

overlay overlay to be updated

row in overlay to be updated

under primary name of the key to be considered

XkbAddGeomOverlayKey adds one key to the row in the overlay. If there is no key named under in the row of the underlying section, XkbAddGeomOverlayKey returns NULL.

# **Allocating and Freeing Geometry Components**

Xkb provides a number of functions to allocate and free subcomponents of a keyboard geometry. Use these functions to create or modify keyboard geometries. Note that these functions merely allocate space for the new element(s), and it is up to you to fill in the values explicitly in your code. These allocation functions increase  $sz_*$  but never touch  $num_*$  (unless there is an allocation failure, in which case they reset both  $sz_*$  and  $num_*$  to zero). These functions return Success if they succeed, BadAlloc if they are not able to allocate space, or BadValue if a parameter is not as expected.

To allocate space for an arbitrary number of outlines to a shape, use XkbAllocGeomOutlines.

Status XkbAllocGeomOutlines(shape, num\_needed);

shape shape for which outlines should be allocated

num\_needed number of new outlines required

XkbAllocGeomOutlines allocates space for num\_needed outlines in the specified shape. The outlines are not initialized.

To free geometry outlines, use XkbFreeGeomOutlines.

void XkbFreeGeomOutlines(shape, first, count, free\_all);

shape shape in which outlines should be freed

first outline to be freed

count number of outlines to be freed

 $free\_all$  True  $\Rightarrow$  all outlines are freed

If free\_all is True, all outlines are freed regardless of the value of first or count. Otherwise, count outlines are freed beginning with the one specified by first.

To allocate space for an arbitrary number of keys to a row, use XkbAllocGeomKeys.

Status XkbAllocGeomKeys(row, num\_needed);

row row to which keys should be allocated

num\_needed number of new keys required

XkbAllocGeomKeys allocates num\_needed keys and adds them to the row. No initialization of the keys is done.

To free geometry keys, use XkbFreeGeomKeys.

```
void XkbFreeGeomKeys(row, first, count, free_all);
```

row in which keys should be freed

first key to be freed

count number of keys to be freed

free\_all True  $\rightarrow$  all keys are freed

If free\_all is True, all keys are freed regardless of the value of first or count. Otherwise, count keys are freed beginning with the one specified by first.

To allocate geometry properties, use XkbAllocGeomProps.

```
Status XkbAllocGeomProps(geom, num_needed);
```

geometry for which properties should be allocated

num\_needed number of new properties required

XkbAllocGeomProps allocates space for num\_needed properties and adds them to the specified geometry geom. No initialization of the properties is done. A geometry property associates an arbitrary string with an equally arbitrary name. Geometry properties can be used to provide hints to programs that display images of keyboards, but they are not interpreted by Xkb. No other geometry structures refer to geometry properties.

To free geometry properties, use XkbFreeGeomProperties.

```
void XkbFreeGeomProperties(geom, first, count, free_all);
```

geometry in which properties should be freed

first property to be freed

count number of properties to be freed

free\_all True \_ all properties are freed

If free\_all is True, all properties are freed regardless of the value of first or count. Otherwise, count properties are freed beginning with the one specified by first.

To allocate geometry key aliases, use XkbAllocGeomKeyAliases.

Status XkbAllocGeomKeyAliases(geom, num\_needed);

geometry for which key aliases should be allocated

num\_needed number of new key aliases required

XkbAllocGeomKeyAliases allocates space for num\_needed key aliases and adds them to the specified geometry *geom*. A key alias is a pair of strings that associates an alternate name for a key with the real name for that key.

To free geometry key aliases, use XkbFreeGeomKeyAliases.

void XkbFreeGeomKeyAliases(geom, first, count, free\_all);

geometry in which key aliases should be freed

first key alias to be freed

count number of key aliases to be freed

free\_all True \_ all key aliases are freed

If free\_all is True, all aliases in the top level of the specified geometry geom are freed regardless of the value of first or count. Otherwise, count aliases in geom are freed beginning with the one specified by first.

To allocate geometry colors, use XkbAllocGeomColors.

Status XkbAllocGeomColors(geom, num\_needed);

geometry for which colors should be allocated

num\_needed number of new colors required.

XkbAllocGeomColors allocates space for num\_needed colors and adds them to the specified geometry geom. A color name is a string whose interpretation is not specified by Xkb. All other geometry data structures refer to colors using their indices in this global list or pointers to colors in this list.

To free geometry colors, use XkbFreeGeomColors.

void XkbFreeGeomColors(geom, first, count, free\_all);

geometry in which colors should be freed

first color to be freed

count number of colors to be freed

free\_all True  $\rightarrow$  all colors are freed

If free\_all is True, all colors are freed regardless of the value of first or count. Otherwise, count colors are freed beginning with the one specified by first.

To allocate points in an outline, use XkbAllocGeomPoints.

Status **XkbAllocGeomPoints**(outline, num\_needed);

outline outline for which points should be allocated

num\_needed number of new points required

XkbAllocGeomPoints allocates space for num\_needed points in the specified outline. The points are not initialized.

To free points in a outline, use XkbFreeGeomPoints.

void XkbFreeGeomPoints(outline, first, count, free\_all);

outline outline in which points should be freed

first point to be freed.

count number of points to be freed

free\_all True \( \to \) all points are freed

If free\_all is True, all points are freed regardless of the value of first and count. Otherwise, the number of points specified by count are freed, beginning with the point specified by first in the specified outline.

To allocate space for an arbitrary number of geometry shapes, use XkbAllocGeomShapes.

Status XkbAllocGeomShapes(geom, num\_needed);

geom geometry for which shapes should be allocated

num\_needed number of new shapes required

XkbAllocGeomShapes allocates space for num\_needed shapes in the specified geometry geom. The shapes are not initialized.

To free geometry shapes, use XkbFreeGeomShapes.

void XkbFreeGeomShapes(geom, first, count, free\_all);

geometry in which shapes should be freed

first shape to be freed

count number of shapes to be freed

free\_all True  $\rightarrow$  all shapes are freed

If free\_all is True, all shapes in the geometry are freed regardless of the values of first and count. Otherwise, count shapes are freed, beginning with the shape specified by first.

To allocate geometry sections, use XkbAllocGeomSections.

Status XkbAllocGeomSections(geom, num needed);

geometry for which sections should be allocated

num\_needed number of new sections required

XkbAllocGeomSections allocates num\_needed sections and adds them to the geometry geom. No initialization of the sections is done.

To free geometry sections, use XkbFreeGeomSections.

void XkbFreeGeomSections(geom, first, count, free\_all);

geometry in which sections should be freed

first section to be freed.

count number of sections to be freed

free\_all True  $\rightarrow$  all sections are freed

If free\_all is True, all sections are freed regardless of the value of first and count. Otherwise, the number of sections specified by count are freed, beginning with the section specified by first in the specified geometry.

To allocate rows in a section, use XkbAllocGeomRows.

Status XkbAllocGeomRows(section, num\_needed);

section section section for which rows should be allocated

num\_needed number of new rows required

XkbAllocGeomRows allocates num\_needed rows and adds them to the section. No initialization of the rows is done.

To free rows in a section, use XkbFreeGeomRows.

void XkbFreeGeomRows(section, first, count, free\_all);

section section in which rows should be freed

first row to be freed.

count number of rows to be freed

free\_all True  $\Rightarrow$  all rows are freed

If free\_all is True, all rows are freed regardless of the value of first and count. Otherwise, the number of rows specified by count are freed, beginning with the row specified by first in the specified section.

To allocate overlays in a section, use XkbAllocGeomOverlays.

Status XkbAllocGeomOverlays(section, num\_needed);

section section for which overlays should be allocated

num\_needed number of new overlays required

XkbAllocGeomOverlays allocates num\_needed overlays and adds them to the section. No initialization of the overlays is done.

To free rows in an section, use XkbFreeGeomOverlays.

void XkbFreeGeomOverlays(section, first, count, free\_all);

section section in which overlays should be freed

first overlay to be freed.

count number of overlays to be freed

free\_all True \_ all overlays are freed

If free\_all is True, all overlays are freed regardless of the value of first and count. Otherwise, the number of overlays specified by count are freed, beginning with the overlay specified by first in the specified section.

To allocate rows in a overlay, use XkbAllocGeomOverlayRows.

Status XkbAllocGeomOverlayRows(overlay, num\_needed);

overlay overlay for which rows should be allocated

num\_needed number of new rows required

XkbAllocGeomOverlayRows allocates num\_needed rows and adds them to the overlay. No initialization of the rows is done.

To free rows in an overlay, use XkbFreeGeomOverlayRows.

void XkbFreeGeomOverlayRows(overlay, first, count, free\_all);

overlay section in which rows should be freed

first row to be freed.

count number of rows to be freed

free\_all True  $\rightarrow$  all rows are freed

If free\_all is True, all rows are freed regardless of the value of first and count. Otherwise, the number of rows specified by count are freed, beginning with the row specified by first in the specified overlay.

To allocate keys in an overlay row, use XkbAllocGeomOverlayKeys.

Status XkbAllocGeomOverlayKeys(row, num\_needed);

row row for which keys should be allocated

num\_needed number of new rows required

XkbAllocGeomOverlayKeys allocates num\_needed keys and adds them to the row. No initialization of the keys is done.

To free keys in an overlay row, use XkbFreeGeomOverlayKeys.

void XkbFreeGeomOverlayKeys(row, first, count, free\_all);

row in which keys should be freed

first key to be freed.

count number of keys to be freed

 $free\_all$  True  $\Rightarrow$  all keys are freed

If free\_all is True, all keys are freed regardless of the value of first and count. Otherwise, the number of keys specified by count are freed, beginning with the key specified by first in the specified row.

To allocate doodads that are global to a keyboard geometry, use XkbAllocGeomDoodads.

Status XkbAllocGeomDoodads(geom, num\_needed);

geometry for which doodads should be allocated

num\_needed number of new doodads required

XkbAllocGeomDoodads allocates num\_needed doodads and adds them to the specified geometry geom. No initialization of the doodads is done.

To allocate doodads that are specific to a section, use XkbAllocGeomSectionDoodads.

Status XkbAllocGeomSectionDoodads(section, num needed);

section section for which doodads should be allocated

num\_needed number of new doodads required

XkbAllocGeomSectionDoodads allocates num\_needed doodads and adds them to the specified section. No initialization of the doodads is done.

To free geometry doodads, use XkbFreeGeomDoodads.

void XkbFreeGeomDoodads(doodads, count, free\_all);

doodads doodads to be freed

count number of doodads to be freed

free\_all True  $\Rightarrow$  all doodads are freed

If free\_all is True, all doodads in the array are freed, regardless of the value of count. Otherwise, count doodads are freed.

To allocate an entire geometry, use XkbAllocGeometry.

Status **XkbAllocGeometry**(xkb, sizes);

*xkb* keyboard description for which geometry is to be allocated

sizes initial sizes for all geometry components

XkbAllocGeometry allocates a keyboard geometry and adds it to the keyboard description specified by xkb. The keyboard description should be obtained via the XkbGetKeyboard or XkbAllockeyboard functions. The sizes parameter specifies the number of elements to be reserved for the subcomponents of the keyboard geometry and can be zero or more. These subcomponents include the properties, colors, shapes, sections, and doodads.

To free an entire geometry, use XkbFreeGeometry.

void XkbFreeGeometry(geom, which, free\_all);

geometry to be freed

which mask of geometry components to be freed

 $free\_all$  True  $\Rightarrow$  the entire geometry is freed.

The values of which and free\_all determine how much of the specified geometry is freed. The valid values for which are:

#define	XkbGeomPropertiesMask	(1<<0)
#define	XkbGeomColorsMask	(1<<1)
#define	XkbGeomShapesMask	(1<<2)
#define	XkbGeomSectionsMask	(1<<3)
#define	XkbGeomDoodadsMask	(1 << 4)
#define	XkbGeomAllMask	(0x1f)

If free\_all is True, the entire geometry is freed regardless of the value of which. Otherwise, the portions of the geometry specified by which are freed.

# Chapter 14. Xkb Keyboard Mapping

The Xkb keyboard mapping contains all the information the server and clients need to interpret key events. This chapter provides an overview of the terminology used to describe an Xkb keyboard mapping and introduces common utilities for manipulating the keyboard mapping.

The mapping consists of two components, a server map and a client map. The *client map* is the collection of information a client needs to interpret key events from the keyboard. It contains a global list of key types and an array of key symbol maps, each of which describes the symbols bound to a key and the rules to be used to interpret those symbols. The *server map* contains the information the server needs to interpret key events. This includes actions and behaviors for each key, explicit components for a key, and the virtual modifiers and the per-key virtual modifier mapping.

For detailed information on particular components of the keyboard map, refer to Chapter 15, Xkb Client Keyboard Mapping, and Chapter 16, Xkb Server Keyboard Mapping.

# **Notation and Terminology**

The graphic characters or control functions that may be accessed by one key are logically arranged in groups and levels, where *group* and *level* are defined as in the ISO9995 standard:

Group: A logical state of a keyboard providing access to a collection of graphic characters. Usually

these graphic characters logically belong together and may be arranged on several levels within

a group.

Level: One of several states (normally 2 or 3) governing which graphic character is produced when a

graphic key is actuated. In certain cases the level may also affect function keys.

These definitions, taken from the ISO standard, refer to graphic keys and characters. In the context of Xkb, Group and Level are not constrained to graphic keys and characters; they may be used with any key to access any character the key is capable of generating.


Level is often referred to as "Shift Level". Levels are numbered sequentially starting at one.

#### Note

Shift level is derived from the modifier state, but not necessarily in the same way for all keys. For example, the Shift modifier selects shift level 2 on most keys, but for keypad keys the modifier bound to Num\_Lock (that is, the *NumLock* virtual modifier) also selects shift level 2.

For example, consider the following key (the gray characters indicate symbols that are implied or expected but are not actually engraved on the key):

Figure 14.1. Shift Levels and Groups



L1

Xkb Svmb

This key has two groups, indicated by the columns, and each group has two shift levels. For the first group (Group1), the symbol shift level one is a, and the symbol for shift level two is A. For the second group, the symbol for shift level one is æ, and the symbol for shift level two is Æ.

#### **Core Implementation**

The standard interpretation rules for the core X keymap only allow clients to access keys such as the one shown in Figure 14.1. That is, clients using the standard interpretation rules can only access one of four keysyms for any given KeyPress event — two different symbols in two different groups.

In general, the Shift modifier, the Lock modifier, and the modifier bound to the Num\_Lock key are used to change between shift level 1 and shift level 2. To switch between groups, the core implementation uses the modifier bound to the Mode\_switch key. When the Mode\_switch modifier is set, the keyboard is logically in Group 2. When the Mode\_switch modifier is not set, the keyboard is logically in Group 1.

The core implementation does not clearly specify the behavior of keys. For example, the locking behavior of the *CapsLock* and Num\_Lock keys depends on the vendor.

## **Xkb Implementation**

Xkb extends the core implementation by providing access to up to four keyboard groups with up to 63 shift levels per key <sup>1</sup>. In addition, Xkb provides precise specifications regarding the behavior of keys. In Xkb, modifier state and the current group are independent (with the exception of compatibility mapping, discussed in Chapter 17, *The Xkb Compatibility Map*).

Xkb handles switching between groups via key actions, independent of any modifier state information. Key actions are in the server map component and are described in detail in section 16.1.4.

Xkb handles shift levels by associating a key type with each group on each key. Each key type defines the shift levels available for the groups on keys of its type and specifies the modifier combinations necessary to access each level.

For example, Xkb allows key types where the Control modifier can be used to access the shift level two of a key. Key types are in the client map component and are described in detail in section 15.2.

Xkb provides precise specification of the behavior of a key using key behaviors. Key behaviors are in the server map component and are described in detail in section 16.2.

<sup>&</sup>lt;sup>1</sup> The core implementation restricts the number of symbols per key to 255. With four groups, this allows for up to 63 symbols (or shift levels) per group. Most keys will only have a few shift levels.

# **Getting Map Components from the Server**

Xkb provides two functions to obtain the keyboard mapping components from the server. The first function, XkbGetMap, allocates an XkbDescRec structure, retrieves mapping components from the server, and stores them in the XkbDescRec structure it just allocated. The second function, XkbGetUpdatedMap, retrieves mapping components from the server and stores them in an XkbDescRec structure that has previously been allocated.

To allocate an XkbDescRec structure and populate it with the server's keyboard client map and server map, use XkbGetMap. XkbGetMap is similar to XkbGetKeyboard (see section 6.2), but is used only for obtaining the address of an XkbDescRec structure that is populated with keyboard mapping components. It allows finer control over which substructures of the keyboard mapping components are to be populated. XkbGetKeyboard always returns fully populated components, while XkbGetMap can be instructed to return a partially populated component.

XkbDescPtr XkbGetMap(display, which, device\_spec);

display connection to X server

which mask selecting subcomponents to populate

device\_spec device\_id, or XkbUseCoreKbd

The which mask is a bitwise inclusive OR of the masks defined in Table 14.1. Only those portions of the keyboard server map and the keyboard client maps that are specified in which are allocated and populated.

In addition to allocating and obtaining the server map and the client map, XkbGetMap also sets the device\_spec, the min\_key\_code, and max\_key\_code fields of the keyboard description.

XkbGetMap is synchronous; it queries the server for the desired information, waits for a reply, and then returns. If successful, XkbGetMap returns a pointer to the XkbDescRec structure it allocated. If unsuccessful, XkbGetMap returns NULL. When unsuccessful, one of the following protocol errors is also generated: BadAlloc (unable to allocate the XkbDescRec structure), BadValue (some mask bits in which are undefined), or BadImplementation (a compatible version of the Xkb extension is not available in the server). To free the returned data, use XkbFreeClientMap.

Xkb also provides convenience functions to get partial component definitions from the server. These functions are specified in the "convenience functions" column in Table 14.1. Refer to the sections listed in the table for more information on these functions.

**Table 14.1. Xkb Mapping Component Masks and Convenience Functions** 

Mask	Value	Map	Fields	Convenience Section Functions
XkbKeyTypesMask	(1<<0)	client	types	XkbGetKeyTypes 15.2
			size_types	XkbResizeKeyType
			num_types	XkbCopyKeyType
				XkbCopyKeyTypes
XkbKeySymsMask	(1<<1)	client	syms	XkbGetKeySyms 15.3
			size_syms	XkbResizeKeySyms
			num_syms	XkbChangeTypes-
			key_sym_map	OfKey
XkbModifierMapMask	(1<<2)	client	modmap	XkbGetKeyModifielb.4 Map
XkbExplicitComponentsMask	(1<<3)	server	explicit	XkbGetKeyExplicilt6-3 Components
XkbKeyActionsMask	(1<<4)	server	key_acts	XkbGetKeyActions16.1
			acts	XkbResizeKey- Actions
			num_acts	ACCIONS
			size_acts	
XkbKeyBehaviorsMask	(1<<5)	server	behaviors	XkbGetKey- 16.2 Behaviors
XkbVirtualModsMask	(1<<6)	server	vmods	XkbGetVirtualModk6.4
XkbVirtualModMapMask	(1<<7)	server	vmodmap	XkbGetVirtualModH6.4 Map

Xkb defines combinations of these masks for convenience:

#define	XkbResizableInfoMask	(XkbKeyTypesMask)
#define	XkbAllClientInfoMask	(XkbKeyTypesMask   XkbKeySymsMask
		<pre>XkbModifierMapMask)</pre>
#define	XkbAllServerInfoMask	(XkbExplicitComponentsMask
		XkbKeyActionsMask   XkbKeyBehaviorsMask
		<pre>XkbVirtualModsMask   XkbVirtualModMapMask)</pre>
#define	XkbAllMapComponentsMask	(XkbAllClientInfoMask XkbAllServerInfoMask)

Key types, symbol maps, and actions are all interrelated: changes in one require changes in the others. The convenience functions make it easier to edit these components and handle the interdependencies.

To update the client or server map information in an existing keyboard description, use XkbGetUpdatedMap.

Status **XkbGetUpdatedMap**(display, which, xkb);

display connection to X server

which mask selecting subcomponents to populate

xkb keyboard description to be updated

The which parameter is a bitwise inclusive OR of the masks in Table 14.1. If the needed components of the xkb structure are not already allocated, XkbGetUpdatedMap allocates them. XkbGetUpdatedMap fetches the requested information for the device specified in the XkbDescRec passed in the xkb parameter.

XkbGetUpdatedMap is synchronous; it queries the server for the desired information, waits for a reply, and then returns. If successful, XkbGetUpdatedMap returns Success. If unsuccessful, XkbGetUpdatedMap returns one of the following: BadAlloc (unable to allocate a component in the XkbDescRec structure), BadValue (some mask bits in which are undefined), BadImplementation (a compatible version of the Xkb extension is not available in the server or the reply from the server was invalid).

# **Changing Map Components in the Server**

There are two ways to make changes to map components: either change a local copy of the keyboard map and call XkbSetMap to send the modified map to the server, or, to reduce network traffic, use an XkbMapChangesRec structure and call XkbChangeMap.

Bool **XkbSetMap**(dpy, which, xkb);

dpy connection to X server

which mask selecting subcomponents to update

xkb description from which new values are taken

Use XkbSetMap to send a complete new set of values for entire components (for example, all symbols, all actions, and so on) to the server. The which parameter specifies the components to be sent to the server, and is a bitwise inclusive OR of the masks listed in Table 14.1. The xkb parameter is a pointer to an XkbDescRec structure and contains the information to be copied to the server. For each bit set in the which parameter, XkbSetMap takes the corresponding structure values from the xkb parameter and sends it to the server specified by dpy.

If any components specified by which are not present in the xkb parameter, XkbSetMap returns False. Otherwise, it sends the update request to the server and returns True. XkbSetMap can generate BadAlloc, BadLength, and BadValue protocol errors.

Key types, symbol maps, and actions are all interrelated; changes in one require changes in the others. Xkb provides functions to make it easier to edit these components and handle the interdependencies. Table 14.1 lists these helper functions and provides a pointer to where they are defined.

## The XkbMapChangesRec Structure

Use the XkbMapChangesRec structure to identify and track partial modifications to the mapping components and to reduce the amount of traffic between the server and clients.

```
typedef struct _XkbMapChanges {
```

```
/* identifies valid components
   unsigned short
                      changed;
                                                in structure */
                      min_key_code;
                                             /* lowest numbered keycode for
   KeyCode
                                                device */
   KeyCode
                      max_key_code;
                                             /* highest numbered keycode for
                                                device */
   unsigned char
                      first_type;
                                             /* index of first key type
                                                modified */
                                             /* # types modified */
   unsigned char
                      num_types;
   KeyCode
                      first_key_sym;
                                             /* first key whose key_sym_map
                                                changed */
   unsigned char
                      num_key_syms;
                                             entries changed */
                      first_key_act;
                                             /* first key whose key_acts
   KeyCode
                                                entry changed */
   unsigned char
                      num_key_acts;
                                             /* # key_acts
                                                entries changed */
   KeyCode
                      first_key_behavior;
                                             /* first key whose behaviors
                                                changed */
                                             /* # behaviors
   unsigned char
                      num_key_behaviors;
                                                entries changed */
   KeyCode
                      first_key_explicit;
                                             /* first key whose explicit
                                                entry changed */
   unsigned char
                      num_key_explicit;
                                             /* # explicit
                                                entries changed */
   KeyCode
                      first_modmap_key;
                                             /* first key whose modmap
                                                entry changed */
   unsigned char
                      num_modmap_keys;
                                             /* # modmap
                                                entries changed */
   KeyCode
                      first vmodmap key;
                                             /* first key whose vmodmap
                                                changed */
   unsigned char
                      num_vmodmap_keys;
                                             /* # vmodmap
                                                entries changed */
   unsigned char
                                             /* reserved */
                      pad1;
                                             /* mask indicating which vmods
   unsigned short
                      vmods;
                                                changed */
} XkbMapChangesRec, *XkbMapChangesPtr;
```

The *changed* field identifies the map components that have changed in an XkbDescRec structure and may contain any of the bits in Table 14.1, which are also shown in Table 14.2. Every 1 bit in *changed* also identifies which other fields in the XkbMapChangesRec structure contain valid values, as indicated in Table 14.2. The *min\_key\_code* and *max\_key\_code* fields are for reference only; they are ignored on any requests sent to the server and are always updated by the server whenever it returns the data for an XkbMapChangesRec.

Table 14.2. XkbMapChangesRec Masks

Mask	Valid XkbMapChangesRec Fields	XkbDescRec Field Containing Changed Data
XkbKeyTypesMask	first_type, num_types	<pre>map-&gt;type[first_type] map-&gt;type[first_type + num_types - 1]</pre>
XkbKeySymsMask	first_key_sym, num_key_syms	<pre>map- &gt;key_sym_map[first_key_symmap- &gt;key_sym_map[first_key_sym + num_key_syms - 1]</pre>
XkbModifierMapMask	<pre>first_modmap_key, num_modmap_keys</pre>	<pre>map- &gt;modmap[first_modmap_key]map- &gt;modmap[first_modmap_key + num_modmap_keys - 1]</pre>
XkbExplicitComponentsMask	<pre>first_key_explicit, num_key_explicit</pre>	<pre>server- &gt;explicit[first_key_explicserver- &gt;explicit[first_key_explic + num_key_explicit - 1]</pre>
XkbKeyActionsMask	first_key_act, num_key_acts	server- >key_acts[first_key_act]server- >key_acts[first_key_act + num_key_acts - 1]
XkbKeyBehaviorsMask	<pre>first_key_behavior, num_key_behaviors</pre>	
XkbVirtualModsMask	vmods	server->vmods[*]
XkbVirtualModMapMask	<pre>first_vmodmap_key, num_vmodmap_keys</pre>	<pre>server- &gt;vmodmap[first_vmodmap_keyserver- &gt;vmodmap[first_vmodmap_key + num_vmodmap_keys - 1]</pre>

To update only partial components of a keyboard description, modify the appropriate fields in the server and map components of a local copy of the keyboard description, then call XkbChangeMap with an XkbMapChangesRec structure indicating which components have changed.

```
Bool XkbChangeMap(dpy, xkb, changes);
dpy \qquad \qquad \text{connection to X server}
xkb \qquad \qquad \text{description from which new values are taken}
```

changes identifies component parts to update

XkbChangeMap copies any components specified by the *changes* structure from the keyboard description, *xkb*, to the X server specified by *dpy*.

If any components specified by *changes* are not present in the *xkb* parameter, XkbChangeMap returns False. Otherwise, it sends a request to the server and returns True.

XkbChangeMap can generate BadAlloc, BadLength, and BadValue protocol errors.

# **Tracking Changes to Map Components**

The Xkb extension reports XkbMapNotify events to clients wanting notification whenever a map component of the Xkb description for a device changes. There are many different types of Xkb keyboard map changes. Xkb uses an event detail mask to identify each type of change. The event detail masks are identical to the masks listed in Table 14.1.

To receive XkbMapNotify events under all possible conditions, use XkbSelectEvents (see section 4.3) and pass XkbMapNotifyMask in both bits\_to\_change and values\_for\_bits.

To receive XkbMapNotify events only under certain conditions, use XkbSelectEventDetails using XkbMapNotify as the event\_type and specifying the desired map changes in bits\_to\_change and values\_for\_bits using mask bits from Table 14.1.

The structure for XkbMapNotify events is:

```
typedef struct {
                                 /* Xkb extension base event code */
    int
                   type;
                                 /* X server serial number for event */
   unsigned long
                   serial;
                                 /* True # synthetically generated */
   Bool
                   send event;
   Display *
                   display;
                                 /* server connection where event generated */
                                 /* server time when event generated */
   Time
                   time;
                   xkb_type;
   int
                                 /* XkbMapNotify */
                                 /* Xkb device ID, will not be XkbUseCoreKbd */
    int
                   device;
                                 /* identifies valid fields in rest of event */
   unsigned int
                   changed;
   unsigned int
                   resized;
                                 /* reserved */
   int
                   first_type;
                                 /* index of first key type modified */
    int
                                 /* # types modified */
                   num_types
                   min_key_code; /* minimum keycode for device */
   KeyCode
                   max key code; /* maximum keycode for device */
   KeyCode
                   first_key_sym; /* first key whose key_sym_map changed */
   KeyCode
   KeyCode
                   first_key_act; /* first key whose key_acts entry changed */
                   first_key_behavior; /* first key whose behaviors changed */
   KeyCode
                   first_key_explicit; /* first key whose explicit entry changed *
   KeyCode
   KeyCode
                   first modmap key;
                                       /* first key whose modmap entry changed */
   KeyCode
                   first_vmodmap_key; /* first key whose vmodmap entry changed */
    int
                   num key syms;
                                       /* # key sym map entries changed */
                                       /* # key_acts entries changed */
                   num_key_acts;
    int
                   num_key_behaviors; /* # behaviors entries changed */
    int
                   num_key_explicit;
                                       /* # explicit entries changed */
    int
    int
                   num modmap keys;
                                      /* # modmap entries changed */
                   num vmodmap keys;
                                       /* # vmodmap entries changed */
    int
   unsigned int
                   vmods;
                                       /* mask indicating which vmods changed */
```

#### } XkbMapNotifyEvent;

The *changed* field specifies the map components that have changed and is the bitwise inclusive OR of the mask bits defined in Table 14.1. The other fields in this event are interpreted as the like-named fields in an XkbMapChangesRec (see section 14.3.1). The XkbMapNotifyEvent structure also has an additional resized field that is reserved for future use.

# **Allocating and Freeing Client and Server Maps**

Calling XkbGetMap (see section 14.2) should be sufficient for most applications to get client and server maps. As a result, most applications do not need to directly allocate client and server maps.

If you change the number of key types or construct map components without loading the necessary components from the X server, do not allocate any map components directly using malloc or Xmalloc. Instead, use the Xkb allocators, XkbAllocClientMap, and XkbAllocServerMap.

Similarly, use the Xkb destructors, XkbFreeClientMap, and XkbFreeServerMap instead of free or Xfree.

### **Allocating an Empty Client Map**

To allocate and initialize an empty client map description record, use XkbAllocClientMap.

Status XkbAllocClientMap(xkb, which, type\_count);

xkb keyboard description in which to allocate client map
which mask selecting map components to allocate

type\_count value of num\_types field in map to be allocated

XkbAllocClientMap allocates and initializes an empty client map in the *map* field of the keyboard description specified by xkb. The which parameter specifies the particular components of the client map structure to allocate and is a mask composed by a bitwise inclusive OR of one or more of the masks shown in Table 14.3.

Table 14.3. XkbAllocClientMap Masks

Mask	Effect
XkbKeyTypesMask	The type_count field specifies the number of entries to preallocate for the types field of the client map. If the type_count field is less than XkbNumRequiredTypes (see section 15.2.1), returns BadValue.
XkbKeySymsMask	The min_key_code and max_key_code fields of the xkb parameter are used to allocate the syms and key_sym_map fields of the client map. The fields are allocated to contain the maximum number of entries necessary for max_key_code _ min_key_code + 1 keys.
XkbModifierMapMask	The min_key_code and max_key_code fields of the xkb parameter are used to allocate the modmap field of the client map. The field is allocated to contain the maximum number of entries necessary for max_key_code _ min_key_code + 1 keys.

#### Note

The min\_key\_code and max\_key\_code fields of the xkb parameter must be legal values if the XkbKeySymsMask or XkbModifierMapMask masks are set in the which parameter. If they are not valid, XkbAllocClientMap returns BadValue.

If the client map of the keyboard description is not NULL, and any fields are already allocated in the client map, XkbAllocClientMap does not overwrite the existing values; it simply ignores that part of the request. The only exception is the types array. If type\_count is greater than the current num\_types field of the client map, XkbAllocClientMap resizes the types array and resets the num\_types field accordingly.

If XkbAllocClientMap is successful, it returns Success. Otherwise, it can return either BadMatch, BadAlloc, or BadValue errors.

## Freeing a Client Map

To free memory used by the client map member of an XkbDescRec structure, use XkbFreeClientMap.

void XkbFreeClientMap(xkb, which, free\_all);

xkb keyboard description containing client map to free

which mask identifying components of map to free

free\_all True \_ free all client components and map itself

XkbFreeClientMap frees the components of client map specified by which in the XkbDescRec structure specified by the xkb parameter and sets the corresponding structure component values to NULL. The which parameter specifies a combination of the client map masks shown in Table 14.3.

If free\_all is True, which is ignored; XkbFreeClientMap frees every non- NULL structure component in the client map, frees the XkbClientMapRec structure referenced by the map member of the xkb parameter, and sets the map member to NULL.

### Allocating an Empty Server Map

To allocate and initialize an empty server map description record, use XkbAllocServerMap.

Status **XkbAllocServerMap**(xkb, which, count\_acts);

xkb keyboard description in which to allocate server map

which mask selecting map components to allocate

count\_acts value of num\_acts field in map to be allocated

XkbAllocServerMap allocates and initializes an empty server map in the *server* field of the keyboard description specified by *xkb*. The *which* parameter specifies the particular components of the server map structure to allocate, as specified in Table 14.4.

Table 14.4. XkbAllocServerMap Masks

Mask	Effect
XkbExplicitComponentsMask	The min_key_code and max_key_code fields of the xkb parameter are used to allocate the explicit field of the server map.
XkbKeyActionsMask	The min_key_code and max_key_code fields of the xkb parameter are used to allocate the key_acts field of the server map. The count_acts parameter is used to allocate the acts field of the server map.
XkbKeyBehaviorsMask	The min_key_code and max_key_code fields of the xkb parameter are used to allocate the behaviors field of the server map.
XkbVirtualModMapMask	The min_key_code and max_key_code fields of the xkb parameter are used to allocate the vmodmap field of the server map.

#### Note

The min\_key\_code and max\_key\_code fields of the xkb parameter must be legal values. If they are not valid, XkbAllocServerMap returns BadValue.

If the server map of the keyboard description is not NULL and any fields are already allocated in the server map, XkbAllocServerMap does not overwrite the existing values. The only exception is with the acts array. If the count\_acts parameter is greater than the current num\_acts field of the server map, XkbAllocServerMap resizes the acts array and resets the num\_acts field accordingly.

If XkbAllocServerMap is successful, it returns Success. Otherwise, it can return either BadMatch or BadAlloc errors.

#### Freeing a Server Map

To free memory used by the server member of an XkbDescRec structure, use XkbFreeServerMap.

void XkbFreeServerMap(xkb, which, free\_all);

keyboard description containing server map to free
 which mask identifying components of map to free
 free\_all True → free all server map components and server itself

The XkbFreeServerMap function frees the specified components of server map in the XkbDescRec structure specified by the xkb parameter and sets the corresponding structure component values to NULL. The which parameter specifies a combination of the server map masks and is a bitwise inclusive OR of the masks listed in Table 14.4. If free\_all is True, which is ignored and XkbFreeServerMap frees every non- NULL structure component in the server map, frees the XkbServerMapRec structure referenced by the server member of the xkb parameter, and sets the server member to NULL.

# **Chapter 15. Xkb Client Keyboard Mapping**

The Xkb client map for a keyboard is the collection of information a client needs to interpret key events from the keyboard. It contains a global list of key types and an array of key symbol maps, each of which describes the symbols bound to a key and the rules to be used to interpret those symbols.

Figure 15.1 shows the relationships between elements in the client map:




Figure 15.1. Xkb Client Map

# The XkbClientMapRec Structure

The map field of the complete Xkb keyboard description (see section 6.1) is a pointer to the Xkb client map, which is of type XkbClientMapRec:

```
/* # occupied entries in types */
   unsigned char
                    size_types;
   unsigned char
                    num types;
                                   /* # entries in types */
   XkbKeyTypePtr
                                   /* vector of key types used by this keymap */
                    types;
   unsigned short size syms;
                                   /* length of the syms array */
   unsigned short num_syms;
                                   /* # entries in syms */
                                   /* linear 2d tables of keysyms, 1 per key */
   KeySym *
                    syms;
   XkbSymMapPtr
                    key_sym_map;
                                   /* 1 per keycode, maps keycode to syms */
   unsigned char * modmap;
                                   /* 1 per keycode, real mods bound to key */
} XkbClientMapRec, *XkbClientMapPtr;
```

The following sections describe each of the elements of the XkbClientMapRec structure in more detail.

# **Key Types**

Key types are used to determine the shift level of a key given the current state of the keyboard. The set of all possible key types for the Xkb keyboard description are held in the types field of the client map, whose total size is stored in size\_types, and whose total number of valid entries is stored in num\_types. Key types are defined using the following structures:

```
/* Key Type */
typedef struct {
   XkbModsRec
                      mods;
                                      /* modifiers used to compute shift level */
                                      /* total # shift levels, do not
    unsigned char
                      num_levels;
                                         modify directly */
                                      /* # entries in map, preserve
    unsigned char
                      map_count;
                                         (if non-NULL) */
   XkbKTMapEntryPtr
                                      /* vector of modifiers for each
                                         shift level */
                                      /* mods to preserve for
   XkbModsPtr
                      preserve;
                                         corresponding map entry */
   Atom
                      name;
                                      /* name of key type */
    Atom *
                      level_names;
                                      /* array of names of each shift level */
} XkbKeyTypeRec, *XkbKeyTypePtr;
typedef struct {
                                      /* Modifiers for a key type */
    Bool
                                      /* True # entry active when
                      active;
                                         determining shift level */
    unsigned char
                                      /* shift level if modifiers match mods */
                      level;
   XkbModsRec
                                      /* mods needed for this level to be
                      mods;
                                         selected */
} XkbKTMapEntryRec, *XkbKTMapEntryPtr;
```

The *mods* field of a key type is an XkbModsRec (see section 7.2) specifying the modifiers the key type uses when calculating the shift level, and can be composed of both the core modifiers and virtual modifiers. To set the modifiers associated with a key type, modify the  $real\_mods$  and vmods fields of the mods XkbModsRec accordingly. The mask field of the XkbModsRec is reserved for use by Xkb and is calculated from the  $real\_mods$  and vmods fields.

The num\_levels field holds the total number of shift levels for the key type. Xkb uses num\_levels to ensure the array of symbols bound to a key is large enough. Do not modify num\_levels directly to change the number if shift levels for a key type. Instead, use XkbResizeKeyType (see section 15.2.3).

The map field is a vector of XkbKTMapEntryRec structures, with map\_count entries, that specify the modifier combinations for each possible shift level. Each map entry contains an active field, a mods

field, and a *level* field. The *active* field determines whether the modifier combination listed in the *mods* field should be considered when determining shift level. If *active* is False, this *map* entry is ignored. If *active* is True, the *level* field of the *map* entry specifies the shift level to use when the current modifier combination matches the combination specified in the *mods* field of the *map* entry.

Any combination of modifiers not explicitly listed somewhere in the map yields shift level one. In addition, map entries specifying unbound virtual modifiers are not considered.

Any modifiers specified in *mods* are normally *consumed* by XkbTranslateKeyCode (see section 12.1.3). For those rare occasions a modifier *should* be considered despite having been used to look up a symbol, key types include an optional *preserve* field. If a *preserve* member of a key type is not NULL, it represents a list of modifiers where each entry corresponds directly to one of the key type's *map*. Each entry lists the modifiers that should *not* be consumed if the matching map entry is used to determine shift level.

Each shift level has a name and these names are held in the <code>level\_names</code> array, whose length is <code>num\_levels</code>. The type itself also has a name, which is held in the <code>name</code> field.

For example, consider how the server handles the following possible symbolic description of a possible key type (note that the format used to specify keyboard mappings in the server database is not specified by the Xkb extension, although this format is one possible example):

Table 15.1. Example Key Type

Symbolic Description	Key Type Data Structure
type "ALPHATHREE" {	Xkb->map->types[i].name
modifiers = Shift+Lock+LevelThree;	Xkb->map->types[i].mods
map[None]= Level1;	Xkb->map->types[i].map[0]
map[Lock] = Level1;	Xkb->map->types[i].map[1]
map[Shift]= Level2;	Xkb->map->types[i].map[2]
map[LevelThree]= Level3;	Xkb->map->types[i].map[3]
map[Shift+LevelThree]= Level3;	Xkb->map->types[i].map[4]
<pre>preserve[None]= None;</pre>	Xkb->map->types[i].preserve[0]
<pre>preserve[Lock]= Lock;</pre>	Xkb->map->types[i].preserve[1]
<pre>preserve[Shift]= None;</pre>	Xkb->map->types[i].preserve[2]
<pre>preserve[LevelThree]= None;</pre>	Xkb->map->types[i].preserve[3]
<pre>preserve[Shift+Level3]= None;</pre>	Xkb->map->types[i].preserve[4]
<pre>level_name[Level1]= "Base";</pre>	Xkb->map->types[i].level_names[0]
level_name[Level2]= "Caps";	Xkb->map->types[i].level_names[1]
level_name[Level3]= "Level3";	Xkb->map->types[i].level_names[2]
<b>}</b> ;	

The *name* of the example key type is "ALPHATHREE," and the modifiers it pays attention to are Shift, Lock, and the virtual modifier *LevelThree*. There are three shift levels. The name of shift level one is "Base," the name of shift level two is "Caps," and the name of shift level three is "Level3."

Given the combination of the map and preserve specifications, there are five map entries. The first map entry specifies that shift level one is to be used if no modifiers are set. The second entry specifies the Lock modifier alone also yields shift level one. The third entry specifies the Shift modifier alone yields shift

level two. The fourth and fifth entries specify that the virtual *LevelThree* modifier alone, or in combination with the Shift modifier, yields shift level three.

#### Note

Shift level three can be reached only if the virtual modifier *LevelThree* is bound to a real modifier (see section 16.4). If *LevelThree* is not bound to a real modifier, the *map* entries associated with it are ignored.

Because the Lock modifier is to be preserved for further event processing, the preserve list is not NULL and parallels the map list. All preserve entries, except for the one corresponding to the map entry that specifies the Lock modifier, do not list any modifiers. For the map entry that specifies the Lock modifier, the corresponding preserve list entry lists the Lock modifier, meaning do not consume the Lock modifier. In this particular case, the preserved modifier is passed to Xlib translation functions and causes them to notice that the Lock modifier is set; consequently, the Xlib functions apply the appropriate capitalization rules to the symbol. Because this preserve entry is set only for a modifier that yields shift level one, the capitalization occurs only for level-one symbols.

#### The Canonical Key Types

Xkb allows up to XkbMaxKeyTypes (255) key types to be defined, but requires at least XkbNumRequiredTypes (4) predefined types to be in a key map. These predefined key types are referred to as the canonical key types and describe the types of keys available on most keyboards. The definitions for the canonical key types are held in the first XkbNumRequiredTypes entries of the types field of the client map and are indexed using the following constants:

XkbOneLevelIndex XkbTwoLevelIndex XkbAlphabeticIndex XkbKeypadIndex

#### ONE\_LEVEL

The ONE\_LEVEL key type describes groups that have only one symbol. The default ONE\_LEVEL key type has no map entries and does not pay attention to any modifiers. A symbolic representation of this key type could look like the following:

```
type "ONE_LEVEL" {
    modifiers = None;
    map[None]= Level1;
    level_name[Level1]= "Any";
};
```

The description of the ONE\_LEVEL key type is stored in the *types* [ XkbOneLevelIndex ] entry of the client key map.

#### TWO\_LEVEL

The TWO\_LEVEL key type describes groups that consist of two symbols but are neither alphabetic nor numeric keypad keys. The default TWO\_LEVEL type uses only the Shift modifier. It returns shift level two if Shift is set, and level one if it is not. A symbolic representation of this key type could look like the following:

```
type "TWO_LEVEL" {
    modifiers = Shift;
    map[Shift]= Level2;
    level_name[Level1]= "Base";
    level_name[Level2]= "Shift";
};
```

The description of the TWO\_LEVEL key type is stored in the types [ XkbTwoLevelIndex ] entry of the client key map.

#### **ALPHABETIC**

The ALPHABETIC key type describes groups consisting of two symbols: the lowercase form of a symbol followed by the uppercase form of the same symbol. The default ALPHABETIC type implements localesensitive "Shift cancels CapsLock" behavior using both the Shift and Lock modifiers as follows:

- If Shift and Lock are both set, the default ALPHABETIC type yields level one.
- If Shift alone is set, it yields level two.
- If Lock alone is set, it yields level one, but preserves the Lock modifier so Xlib notices and applies the
  appropriate capitalization rules. The Xlib functions are locale-sensitive and apply different capitalization
  rules for different locales.
- If neither Shift nor Lock is set, it yields level one.

A symbolic representation of this key type could look like the following:

```
type "ALPHABETIC" {
    modifiers = Shift+Lock;
    map[Shift]= Level2;
    preserve[Lock]= Lock;
    level_name[Level1]= "Base";
    level_name[Level2]= "Caps";
};
```

The description of the ALPHABETIC key type is stored in the types [ XkbAlphabeticIndex ] entry of the client key map.

#### **KEYPAD**

The KEYPAD key type describes groups that consist of two symbols, at least one of which is a numeric keypad symbol. The numeric keypad symbol is assumed to reside at level two. The default KEYPAD key type implements "Shift cancels NumLock" behavior using the Shift modifier and the real modifier bound to the virtual modifier named "NumLock", known as the *NumLock* modifier, as follows:

- If Shift and *NumLock* are both set, the default KEYPAD type yields level one.
- If Shift alone is set, it yields level two.
- If NumLock alone is set, it yields level two.
- If neither Shift nor *NumLock* is set, it yields level one.

A symbolic representation of this key type could look like the following:

```
type "KEYPAD" {
    modifiers = Shift+NumLock;
    map[None]= Level1;
    map[Shift]= Level2;
    map[NumLock]= Level2;
    map[Shift+NumLock]= Level1;
    level_name[Level1]= "Base";
    level_name[Level2]= "Caps";
};
```

The description of the KEYPAD key type is stored in the types [ XkbKeypadIndex ] entry of the client key map.

#### Initializing the Canonical Key Types in a New Client Map

To set the definitions of the canonical key types in a client map to their default values, use XkbInitCanonicalKeyTypes.

```
Status XkbInitCanonicalKeyTypes(xkb, which, keypadVMod);
```

xkb keyboard description containing client map to initialize

which mask of types to initialize

keypadVMod index of NumLock virtual modifier

XkbInitCanonicalKeyTypes initializes the first XkbNumRequiredTypes key types of the keyboard specified by the xkb parameter to their default values. The which parameter specifies what canonical key types to initialize and is a bitwise inclusive OR of the following masks: XkbOneLevelMask, XkbTwoLevelMask, XkbAlphabeticMask, and XkbKeypadMask. Only those canonical types specified by the which mask are initialized.

If XkbKeypadMask is set in the which parameter, XkbInitCanonicalKeyTypes looks up the NumLock named virtual modifier to determine which virtual modifier to use when initializing the KEYPAD key type. If the NumLock virtual modifier does not exist, XkbInitCanonicalKeyTypes creates it.

XkbInitCanonicalKeyTypes normally returns Success. It returns BadAccess if the Xkb extension has not been properly initialized, and BadAccess if the xkb parameter is not valid.

#### **Getting Key Types from the Server**

To obtain the list of available key types in the server's keyboard mapping, use XkbGetKeyTypes.

```
Status XkbGetKeyTypes(dpy, first, num, xkb);

dpy connection to X server

first index to first type to get, 0 \Rightarrow 1st type

num number of key types to be returned

xkb keyboard description containing client map to update
```

#### Note

XkbGetKeyTypes is used to obtain descriptions of the key types themselves, not the key types bound to individual keys. To obtain the key types bound to an individual key, refer to the key\_sym\_map field of the client map (see section 15.3.1).

XkbGetKeyTypes queries the server for the desired types, waits for a reply, and returns the desired types in the xkb->map->types. If successful, it returns Success.

XkbGetKeyTypes returns BadAccess if the Xkb extension has not been properly initialized and BadValue if the combination of first and num results in numbers out of valid range.

#### Changing the Number of Levels in a Key Type

To change the number of levels in a key type, use XkbResizeKeyType.

```
Status XkbResizeKeyType(xkb, type_ndx, map_count, want_preserve, new_num_lvls);
```

xkb keyboard description containing client map to update

type\_ndx index in xkb->map->types of type to change

map\_count total # of map entries needed for the type

want\_preserve True \_ list of preserved modifiers is necessary

new\_num\_lvls new max # of levels for type

XkbResizeKeyType changes the type specified by xkb->map->types [ type\_ndx ], and reallocates the symbols and actions bound to all keys that use the type, if necessary. XkbResizeKeyType updates only the local copy of the types in xkb; to update the server's copy for the physical device, use XkbSetMap or XkbChangeMap after calling XkbResizeKeyType.

The map\_count parameter specifies the total number of map entries needed for the type, and can be zero or greater. If map\_count is zero, XkbResizeKeyType frees the existing map and preserve entries for the type if they exist and sets them to NULL.

The want\_preserve parameter specifies whether a preserve list for the key should be created. If want\_preserve is True, the preserve list with map\_count entries is allocated or reallocated if it already exists. Otherwise, if want\_preserve is False, the preserve field is freed if necessary and set to NULL.

The new\_num\_lvls parameter specifies the new maximum number of shift levels for the type and is used to calculate and resize the symbols and actions bound to all keys that use the type.

If type\_ndx does not specify a legal type, new\_num\_lvls is less than 1, or the map\_count is less than zero, XkbResizeKeyType returns BadValue. If XkbResizeKeyType encounters any problems with allocation, it returns BadAlloc. Otherwise, it returns Success.

# **Copying Key Types**

Use XkbCopyKeyType and XkbCopyKeyTypes to copy one or more XkbKeyTypeRec structures.

```
Status XkbCopyKeyType(from, into);
```

from	pointer to XkbKeyTypeRec to be copied
into	pointer to XkbKeyTypeRec to be changed

XkbCopyKeyType copies the key type specified by from to the key type specified by into. Both must point to legal XkbKeyTypeRec structures. Xkb assumes from and into point to different places. As a result, overlaps can be fatal. XkbCopyKeyType frees any existing map, preserve, and level\_names in into prior to copying. If any allocation errors occur while copying from to into, XkbCopyKeyType returns BadAlloc. Otherwise, XkbCopyKeyType copies from to into and returns Success.

```
Status XkbCopyKeyTypes(from, into, num_types);

from pointer to array of XkbKeyTypeRecs to copy

into pointer to array of XkbKeyTypeRecs to change

num_types number of types to copy
```

XkbCopyKeyTypes copies num\_types XkbKeyTypeRec structures from the array specified by from into the array specified by into. It is intended for copying between, rather than within, keyboard descriptions, so it doesn't check for overlaps. The same rules that apply to the from and into parameters in XkbCopyKeyType apply to each entry of the from and into arrays of XkbCopyKeyTypes. If any allocation errors occur while copying from to into, XkbCopyKeyTypes returns BadAlloc. Otherwise, XkbCopyKeyTypes copies from to into and returns Success.

# **Key Symbol Map**

The entire list of key symbols for the keyboard mapping is held in the *syms* field of the client map. Whereas the core keyboard mapping is a two-dimensional array of KeySyms whose rows are indexed by keycode, the *syms* field of Xkb is a linear list of KeySyms that needs to be indexed uniquely for each key. This section describes the key symbol map and the methods for determining the symbols bound to a key.

The reason the *syms* field is a linear list of KeySyms is to reduce the memory consumption associated with a keymap; because Xkb allows individual keys to have multiple shift levels and a different number of groups per key, a single two-dimensional array of KeySyms would potentially be very large and sparse. Instead, Xkb provides a small two-dimensional array of KeySyms for each key. To store all of these individual arrays, Xkb concatenates each array together in the *syms* field of the client map.

In order to determine which KeySyms in the <code>syms</code> field are associated with each keycode, the client map contains an array of key symbol mappings, held in the <code>key\_sym\_map</code> field. The <code>key\_sym\_map</code> field is an array of XkbSymMapRec structures indexed by keycode. The <code>key\_sym\_map</code> array has <code>min\_key\_code</code> unused entries at the start to allow direct indexing using a keycode. All keycodes falling between the minimum and maximum legal keycodes, inclusive, have <code>key\_sym\_map</code> arrays, whether or not any key actually yields that code. The KeySymMapRec structure is defined as follows:

These fields are described in detail in the following sections.

#### Per-Key Key Type Indices

The kt\_index array of the XkbSymMapRec structure contains the indices of the key types (see section 15.2) for each possible group of symbols associated with the key. To obtain the index of a key type or the pointer to a key type, Xkb provides the following macros, to access the key types:

#### Note

The array of key types is of fixed width and is large enough to hold key types for the maximum legal number of groups (XkbNumKbdGroups, currently four); if a key has fewer than XkbNumKbdGroups groups, the extra key types are reported but ignored.

```
int XkbKeyTypeIndex(xkb, keycode, group);
xkb
Xkb description of interest
```

keycode keycode of interest

group group index

XkbKeyTypeIndex computes an index into the *types* vector of the client map in *xkb* from the given *keycode* and *group* index.

```
XkbKeyTypePtr XkbKeyType(xkb, keycode, group);
```

xkb Xkb description of interest

keycode keycode of interest

group group index

XkbKeyType returns a pointer to the key type in the *types* vector of the client map in *xkb* corresponding to the given *keycode* and *group* index.

#### **Per-Key Group Information**

The <code>group\_info</code> field of an XkbSymMapRec is an encoded value containing the number of groups of symbols bound to the key as well as the specification of the treatment of out-of-range groups. It is legal for a key to have zero groups, in which case it also has zero symbols and all events from that key yield NoSymbol. To obtain the number of groups of symbols bound to the key, use XkbKeyNumGroups. To change the number of groups bound to a key, use XkbChangeTypesOfKey (see section 15.3.6). To obtain a mask that determines the treatment of out-of-range groups, use XkbKeyGroupInfo and XkbOutOfRangeGroupInfo.

The keyboard controls (see Chapter 10, Keyboard Controls) contain a groups\_wrap field specifying the handling of illegal groups on a global basis. That is, when the user performs an action causing the effective group to go out of the legal range, the groups\_wrap field specifies how to normalize the effective keyboard group to a group that is legal for the keyboard as a whole, but there is no guarantee

that the normalized group will be within the range of legal groups for any individual key. The per-key  $group\_info$  field specifies how a key treats a legal effective group if the key does not have a type specified for the group of concern. For example, the **Enter** key usually has just one group defined. If the user performs an action causing the global keyboard group to change to Group2, the  $group\_info$  field for the **Enter** key describes how to handle this situation.

Out-of-range groups for individual keys are mapped to a legal group using the same options as are used for the overall keyboard group. The particular type of mapping used is controlled by the bits set in the group\_info flag, as shown in Table 15.2. See section 10.7.1 for more details on the normalization methods in this table.

Table 15.2. group\_info Range Normalization

Bits set in group_info	Normalization method
XkbRedirectIntoRange	XkbRedirectIntoRange
XkbClampIntoRange	XkbClampIntoRange
none of the above	XkbWrapIntoRange

Xkb provides the following macros to access group information:

int XkbKeyNumGroups(xkb, keycode);

xkb Xkb description of interest

keycode keycode of interest

XkbKeyNumGroups returns the number of groups of symbols bound to the key corresponding to keycode.

unsigned char **XkbKeyGroupInfo**(xkb, keycode);

xkb Xkb description of interest

keycode keycode of interest

XkbKeyGroupInfo returns the *group\_info* field from the XkbSymMapRec structure associated with the key corresponding to *keycode*.

unsigned char XkbOutOfRangeGroupInfo(grp\_inf);

grp\_inf group\_info field of XkbSymMapRec

 ${\tt XkbOutOfRangeGroupInfo\ returns\ only\ the\ out-of-range\ processing\ information\ from\ the\ group\_info\ field\ of\ an\ XkbSymMapRec\ structure.}$ 

 $\verb"unsigned" char {\tt XkbOutOfRangeGroupNumber} (grp\_inf);$ 

grp\_inf group\_info field of XkbSymMapRec

XkbOutOfRangeGroupNumber returns the out-of-range group number, represented as a group index, from the *group\_info* field of an XkbSymMapRec structure.

#### **Key Width**

The maximum number of shift levels for a type is also referred to as the width of a key type. The width field of the key\_sym\_map entry for a key contains the width of the widest type associated with the key.

The width field cannot be explicitly changed; it is updated automatically whenever the symbols or set of types bound to a key are changed.

#### Offset in to the Symbol Map

The key width and number of groups associated with a key are used to form a small two-dimensional array of KeySyms for a key. This array may be different sizes for different keys. The array for a single key is stored as a linear list, in row-major order. The arrays for all of the keys are stored in the syms field of the client map. There is one row for each group associated with a key and one column for each level. The index corresponding to a given group and shift level is computed as:

```
idx = group_index * key_width + shift_level
```

The offset field of the key\_sym\_map entry for a key is used to access the beginning of the array.

Xkb provides the following macros for accessing the width and offset for individual keys, as well as macros for accessing the two-dimensional array of symbols bound to the key:

```
int XkbKeyGroupsWidth(xkb, keycode);
```

xkb Xkb description of interest

keycode keycode of interest

XkbKeyGroupsWidth computes the maximum width associated with the key corresponding to keycode.

```
int XkbKeyGroupWidth(xkb, keycode, grp);
```

xkb Xkb description of interest

keycode keycode of interest

grp group of interest

XkbKeyGroupWidth computes the width of the type associated with the group grp for the key corresponding to keycode.

```
int XkbKeySymsOffset(xkb, keycode);
```

xkb Xkb description of interest

keycode keycode of interest

XkbKeySymsOffset returns the offset of the two-dimensional array of keysyms for the key corresponding to keycode.

```
int XkbKeyNumSyms(xkb, keycode);
```

xkb Xkb description of interest

keycode keycode of interest

XkbKeyNumSyms returns the total number of keysyms for the key corresponding to keycode.

```
KeySym *XkbKeySymsPtr(xkb, keycode);
```

xkb Xkb description of interest

keycode keycode of interest

XkbKeySymsPtr returns the pointer to the two-dimensional array of keysyms for the key corresponding to keycode.

KeySym XkbKeySymEntry(xkb, keycode, shift, grp);

xkb Xkb description of interest

keycode keycode of interest

shift shift level of interest

grp group of interest

XkbKeySymEntry returns the KeySym corresponding to shift level *shift* and group *grp* from the two-dimensional array of keysyms for the key corresponding to *keycode* 

### Getting the Symbol Map for Keys from the Server

To obtain the symbols for a subset of the keys in a keyboard description, use XkbGetKeySyms:

Status **XkbGetKeySyms**(dpy, first, num, xkb);

dpy connection to X server

first key to get

num number of keycodes for which syms desired

xkb Xkb description to be updated

XkbGetKeySyms sends a request to the server to obtain the set of keysyms bound to *num* keys starting with the key whose keycode is *first*. It waits for a reply and returns the keysyms in the *map.syms* field of *xkb*. If successful, XkbGetKeySyms returns Success. The *xkb* parameter must be a pointer to a valid Xkb keyboard description.

If the client map in the xkb parameter has not been allocated, XkbGetKeySyms allocates and initializes it before obtaining the symbols.

If a compatible version of Xkb is not available in the server or the Xkb extension has not been properly initialized, XkbGetKeySyms returns BadAccess. If num is less than 1 or greater than XkbMaxKeyCount, XkbGetKeySyms returns BadValue. If any allocation errors occur, XkbGetKeySyms returns BadAlloc.

# Changing the Number of Groups and Types Bound to a Key

To change the number of groups and the types bound to a key, use XkbChangeTypesOfKey.

Status **XkbChangeTypesOfKey**(xkb, key, n\_groups, groups, new\_types\_in, p\_changes);

*xkb* keyboard description to be changed

key	keycode for key of interest
n_groups	new number of groups for key
groups	mask indicating groups to change
new_types_in	indices for new groups specified in groups
p_changes	notes changes made to xkb

XkbChangeTypesOfKey reallocates the symbols and actions bound to the key, if necessary, and initializes any new symbols or actions to NoSymbol or *NoAction*, as appropriate. If the *p\_changes* parameter is not NULL, XkbChangeTypesOfKey adds the XkbKeySymsMask to the *changes* field of *p\_changes* and modifies the *first\_key\_sym* and *num\_key\_syms* fields of *p\_changes* to include the *key* that was changed. See section 14.3.1 for more information on the XkbMapChangesPtr structure. If successful, XkbChangeTypesOfKey returns Success.

The *n\_groups* parameter specifies the new number of groups for the key. The *groups* parameter is a mask specifying the groups for which new types are supplied and is a bitwise inclusive OR of the following masks: XkbGroup1Mask, XkbGroup2Mask, XkbGroup3Mask, and XkbGroup4Mask.

The new\_types\_in parameter is an integer array of length n\_groups. Each entry represents the type to use for the associated group and is an index into xkb->map->types. The new\_types\_in array is indexed by group index; if n\_groups is four and groups only has XkbGroup1Mask and XkbGroup3Mask set, new\_types\_in looks like this:

```
new_types_in[0] = type for Group1
new_types_in[1] = ignored
new_types_in[2] = type for Group3
new_types_in[3] = ignored
```

For convenience, Xkb provides the following constants to use as indices to the groups:

**Table 15.3. Group Index Constants** 

Constant Name	Value
XkbGroup1Index	0
XkbGroup2Index	1
XkbGroup3Index	2
XkbGroup4Index	3

If the Xkb extension has not been properly initialized, XkbChangeTypesOfKey returns BadAccess. If the xkb parameter it not valid (that is, it is NULL or it does not contain a valid client map), XkbChangeTypesOfKey returns BadMatch. If the key is not a valid keycode, n\_groups is greater than XkbNumKbdGroups, or the groups mask does not contain any of the valid group mask bits, XkbChangeTypesOfKey returns BadValue. If it is necessary to resize the key symbols or key actions arrays and any allocation errors occur, XkbChangeTypesOfKey returns BadAlloc.

#### Changing the Number of Symbols Bound to a Key

To change the number of symbols bound to a key, use XkbResizeKeySyms.

```
KeySym *XkbResizeKeySyms(xkb, key, needed);
```

*xkb* keyboard description to be changed

key keycode for key to modify

needed new number of keysyms required for key

XkbResizeKeySyms reserves the space needed for needed keysyms and returns a pointer to the beginning of the new array that holds the keysyms. It adjusts the offset field of the key\_sym\_map entry for the key if necessary and can also change the syms, num\_syms, and size\_syms fields of xkb->map if it is necessary to reallocate the syms array. XkbResizeKeySyms does not modify either the width or number of groups associated with the key.

If needed is greater than the current number of keysyms for the key, XkbResizeKeySyms initializes all new keysyms in the array to NoSymbol.

Because the number of symbols needed by a key is normally computed as width \* number of groups, and XkbResizeKeySyms does not modify either the width or number of groups for the key, a discrepancy exists upon return from XkbResizeKeySyms between the space allocated for the keysyms and the number required. The unused entries in the list of symbols returned by XkbResizeKeySyms are not preserved across future calls to any of the map editing functions, so you must update the key symbol mapping (which updates the width and number of groups for the key) before calling another allocator function. A call to XkbChangeTypesOfKey will update the mapping.

If any allocation errors occur while resizing the number of symbols bound to the key, XkbResizeKeySyms returns NULL.

#### Note

A change to the number of symbols bound to a key should be accompanied by a change in the number of actions bound to a key. Refer to section 16.1.16 for more information on changing the number of actions bound to a key.

# The Per-Key Modifier Map

The *modmap* entry of the client map is an array, indexed by keycode, specifying the real modifiers bound to a key. Each entry is a mask composed of a bitwise inclusive OR of the legal real modifiers: ShiftMask, LockMask, ControlMask, Mod1Mask, Mod2Mask, Mod3Mask, Mod4Mask, and Mod5Mask. If a bit is set in a *modmap* entry, the corresponding key is bound to that modifier.

Pressing or releasing the key bound to a modifier changes the modifier set and unset state. The particular manner in which the modifier set and unset state changes is determined by the behavior and actions assigned to the key (see Chapter 16, Xkb Server Keyboard Mapping).

#### Getting the Per-Key Modifier Map from the Server

To update the modifier map for one or more of the keys in a keyboard description, use XkbGetKeyModifierMap.

Status **XkbGetKeyModifierMap**(dpy, first, num, xkb);

dpy connection to X server

first key to get

num number of keys for which information is desired

#### xkb keyboard description to update

XkbGetKeyModifierMap sends a request to the server for the modifier mappings for *num* keys starting with the key whose keycode is *first*. It waits for a reply and places the results in the *xkb*->map->modmap array. If successful, XkbGetKeyModifierMap returns Success.

If the map component of the xkb parameter has not been allocated, XkbGetKeyModifierMap allocates and initializes it.


If a compatible version of Xkb is not available in the server or the Xkb extension has not been properly initialized, XkbGetKeySyms returns BadAccess. If any allocation errors occur while obtaining the modifier map, XkbGetKeyModifierMap returns BadAlloc.

# **Chapter 16. Xkb Server Keyboard Mapping**

The *server* field of the complete Xkb keyboard description (see section 6.1) is a pointer to the Xkb server map.

Figure 16.1 shows the relationships between elements in the server map:

Figure 16.1. Server Map Relationships



The Xkb server map contains the information the server needs to interpret key events and is of type XkbServerMapRec:

```
/* # of entries in acts */
   unsigned short
                       size_acts;
   XkbAction *
                       acts;
                                        /* linear 2d tables of key actions,
                                           1 per keycode */
   XkbBehavior *
                       behaviors;
                                        /* key behaviors, 1 per keycode */
   unsigned short *
                       key_acts;
                                        /* index into acts, 1 per keycode */
    unsigned char *
                       explicit;
                                        /* explicit overrides of core
                                           remapping, 1 per key */
    unsigned char
                       vmods[XkbNumVirtualMods]; /* real mods bound
                                                      to virtual mods */
    unsigned short *
                       vmodmap;
                                        /* virtual mods bound to key,
                                           1 per keycode */
} XkbServerMapRec, *XkbServerMapPtr;
```

The num\_acts, size\_acts, acts, and key\_acts fields specify the key actions, defined in section 16.1. The behaviors field describes the behavior for each key and is defined in section 16.2. The explicit field describes the explicit components for a key and is defined in section 16.3. The vmods and the vmodmap fields describe the virtual modifiers and the per-key virtual modifier mapping and are defined in section 16.4.

# **Key Actions**

A key action defines the effect key presses and releases have on the internal state of the server. For example, the expected key action associated with pressing the Shift key is to set the Shift modifier. There is zero or one key action associated with each keysym bound to each key.

Just as the entire list of key symbols for the keyboard mapping is held in the *syms* field of the client map, the entire list of key actions for the keyboard mapping is held in the *acts* array of the server map. The total size of *acts* is specified by *size\_acts*, and the number of entries is specified by *num\_acts*.

The  $key\_acts$  array, indexed by keycode, describes the actions associated with a key. The  $key\_acts$  array has  $min\_key\_code$  unused entries at the start to allow direct indexing using a keycode. If a  $key\_acts$  entry is zero, it means the key does not have any actions associated with it. If an entry is not zero, the entry represents an index into the acts field of the server map, much as the offset field of a KeySymMapRec structure is an index into the syms field of the client map.

The reason the acts field is a linear list of XkbActions is to reduce the memory consumption associated with a keymap. Because Xkb allows individual keys to have multiple shift levels and a different number of groups per key, a single two-dimensional array of KeySyms would potentially be very large and sparse. Instead, Xkb provides a small two-dimensional array of XkbActions for each key. To store all of these individual arrays, Xkb concatenates each array together in the acts field of the server map.

The key action structures consist only of fields of type char or unsigned char. This is done to optimize data transfer when the server sends bytes over the wire. If the fields are anything but bytes, the server has to sift through all of the actions and swap any nonbyte fields. Because they consist of nothing but bytes, it can just copy them out.

Xkb provides the following macros, to simplify accessing information pertaining to key actions:

```
Bool XkbKeyHasActions(xkb, keycode);

xkb Xkb description of interest

keycode keycode of interest
```

XkbKeyHasActions returns True if the key corresponding to *keycode* has any actions associated with it; otherwise, it returns False.

int XkbKeyNumActions(xkb, keycode);

xkb Xkb description of interest

keycode keycode of interest

XkbKeyNumActions computes the number of actions associated with the key corresponding to keycode. This should be the same value as the result of XkbKeyNumSyms (see section 15.3.3).

XkbKeyActionPtr XkbKeyActionsPtr(xkb, keycode);

xkb Xkb description of interest

keycode keycode of interest

XkbKeyActionsPtr returns a pointer to the two-dimensional array of key actions associated with the key corresponding to *keycode*. Use XkbKeyActionsPtr only if the key actually has some actions associated with it, that is, XkbKeyNumActions (xkb, keycode) returns something greater than zero.

XkbAction XkbKeyAction(xkb, keycode, idx);

xkb Xkb description of interest

keycode keycode of interest

idx index for group and shift level

XkbKeyAction returns the key action indexed by *idx* in the two-dimensional array of key actions associated with the key corresponding to *keycode*. *idx* may be computed from the group and shift level of interest as follows:

```
idx = group_index * key_width + shift_level
```

XkbAction XkbKeyActionEntry(xkb, keycode, shift, grp);

xkb Xkb description of interest

keycode keycode of interest

shift shift level within group

group index for group of interest

XkbKeyActionEntry returns the key action corresponding to group grp and shift level shift from the two-dimensional table of key actions associated with the key corresponding to keycode.

#### The XkbAction Structure

The description for an action is held in an XkbAction structure, which is a union of all possible Xkb action types:

```
typedef union _XkbAction {
   XkbAnyAction
                               any;
   XkbModAction
                               mods;
   XkbGroupAction
                               group;
   XkbISOAction
                               iso;
   XkbPtrAction
                               ptr;
   XkbPtrBtnAction
                               btn;
   XkbPtrDfltAction
                               dflt;
   XkbSwitchScreenAction
                               screen;
   XkbCtrlsAction
                               ctrls;
   XkbMessageAction
                               msg;
   XkbRedirectKeyAction
                               redirect;
   XkbDeviceBtnAction
                               devbtn;
   XkbDeviceValuatorAction
                               devval;
    unsigned char
                               type;
} XkbAction;
```

The *type* field is provided for convenience and is the same as the type field in the individual structures. The following sections describe the individual structures for each action in detail.

#### The XkbAnyAction Structure

The XkbAnyAction structure is a convenience structure that refers to any of the actions:

```
#define XkbAnyActionDataSize 7

typedef struct _XkbAnyAction {
   unsigned char type; /* type of action; determines interpretation
   unsigned char data[XkbAnyActionDataSize];
} XkbAnyAction;
```

The data field represents a structure for an action, and its interpretation depends on the type field. The valid values for the type field, and the data structures associated with them are shown in Table 16.1:

**Table 16.1. Action Types** 

Туре	Structure for Data	XkbAction Union Member	Section
XkbSA_NoAction	XkbSA_NoAction means the server does not perform an action for the key; this action does not have an associated data structure.	any	
XkbSA_SetMods	XkbModAction	mods	16.1.3
XkbSA_LatchMods			
XkbSA_LockMods			
XkbSA_SetGroup	XkbGroupAction	group	16.1.4
XkbSA_LatchGroup			
XkbSA_LockGroup			
XkbSA_MovePtr	XkbPtrAction	ptr	16.1.5
XkbSA_PtrBtn	XkbPtrBtnAction	btn	16.1.6
XkbSA_LockPtrBtn			
XkbSA_SetPtrDflt	XkbPtrDfltAction	dflt	16.1.7
XkbSA_ISOLock	XkbISOAction	iso	16.1.8
XkbSA_SwitchScreen	XkbSwitchScreenAction	screen	16.1.9
XkbSA_SetControls	XkbCtrlsAction	ctrls	16.1.10
XkbSA_LockControls			
XkbSA_ActionMessage	XkbMessageAction	msg	16.1.11
XkbSA_RedirectKey	XkbRedirectKeyAction	redirect	16.1.12
XkbSA_DeviceBtn	XkbDeviceBtnAction	devbtn	16.1.13
XkbSA_LockDeviceBtn			
XkbSA_DeviceValuator	XkbDeviceValuatorAction	devval	16.1.14

# **Actions for Changing Modifiers' State**

Actions associated with the XkbModAction structure change the state of the modifiers when keys are pressed and released (see Chapter 7, *Virtual Modifiers* for a discussion of modifiers):

```
typedef struct _XkbModAction {
   unsigned char
                                    /* XkbSA_{Set|Latch|Lock}Mods */
                      type;
                                    /* with type, controls the effect
   unsigned char
                      flags;
                                       on modifiers */
   unsigned char
                                    /* same as mask field of
                      mask;
                                       a modifier description */
   unsigned char
                      real_mods;
                                    /* same as real_mods field of
                                       a modifier description */
```

In the following description, the term *action modifiers* means the real modifier bits associated with this action. Depending on the value of *flags* (see Table 16.3), these are designated either in the *mask* field of the XkbModAction structure itself or the real modifiers bound to the key for which the action is being used. In the latter case, this is the client *map->modmap* [ *keycode* ] field.

The type field can have any of the values shown in Table 16.2.

**Table 16.2. Modifier Action Types** 

Туре	Effect
XkbSA_SetMods	<ul> <li>A key press adds any action modifiers to the keyboard's base modifiers.</li> </ul>
	<ul> <li>A key release clears any action modifiers in the keyboard's base modifiers, provided no other key affecting the same modifiers is logically down.</li> </ul>
	<ul> <li>If no other keys are physically depressed when this key is released, and XkbSA_ClearLocks is set in the flags field, the key release unlocks any action modifiers.</li> </ul>
XkbSA_LatchMods	<ul> <li>Key press and key release events have the same effect as for XkbSA_SetMods; if no keys are physically depressed when this key is released, key release events have the following additional effects:</li> </ul>
	<ul> <li>Modifiers unlocked due to XkbSA_ClearLocks have no further effect.</li> </ul>
	• If XkbSA_LatchToLock is set in the <i>flags</i> field, a key release locks and then unlatches any remaining action modifiers that are already latched.
	<ul> <li>A key release latches any action modifiers not used by the XkbSA_ClearLocks and XkbSA_LatchToLock flags.</li> </ul>
XkbSA_LockMods	<ul> <li>A key press sets the base state of any action modifiers. If XkbSA_LockNoLock is set in the flags field, a key press also sets the locked state of any action modifiers.</li> </ul>
	<ul> <li>A key release clears any action modifiers in the keyboard's base modifiers, provided no other key that affects the same modifiers is down. If XkbSA_LockNoUnlock is not set in the flags field, and any of the action modifiers were locked before the corresponding key press occurred, a key release unlocks them.</li> </ul>

The *flags* field is composed of the bitwise inclusive OR of the masks shown in Table 16.3. A general meaning is given in the table, but the exact meaning depends on the action *type*.

**Table 16.3. Modifier Action Flags** 

Flag	Meaning
XkbSA_UseModMapMods	If set, the action modifiers are determined by the modifiers bound by the modifier mapping of the key. Otherwise, the action modifiers are set to the modifiers specified by the mask, real_mods, vmods1, and vmods2 fields.
XkbSA_ClearLocks	If set and no keys are physically depressed when this key transition occurs, the server unlocks any action modifiers.
XkbSA_LatchToLock	If set, and the action type is XkbSA_LatchMods, the server locks the action modifiers if they are already latched.
XkbSA_LockNoLock	If set, and the action type is XkbSA_LockMods, the server only unlocks the action modifiers.
XkbSA_LockNoUnlock	If set, and the action is XkbSA_LockMods, the server only locks the action modifiers.

If XkbSA\_UseModMapMods is not set in the *flags* field, the *mask*, *real\_mods*, *vmods1*, and *vmods2* fields are used to determine the action modifiers. Otherwise they are ignored and the modifiers bound to the key (client *map->modmap* [ *keycode* ]) are used instead.

The mask, real\_mods, vmods1, and vmods2 fields represent the components of an Xkb modifier description (see section 7.2). While the mask and real\_mods fields correspond directly to the mask and real\_mods fields of an Xkb modifier description, the vmods1 and vmods2 fields are combined to correspond to the vmods field of an Xkb modifier description. Xkb provides the following macros, to convert between the two formats:

```
unsigned short XkbModActionVMods(act);

act action from which to extract virtual mods
```

XkbModActionVMods returns the *vmods1* and *vmods2* fields of act converted to the *vmods* format of an Xkb modifier description.

```
void XkbSetModActionVMods(act, vmods);

act action in which to set vmods

vmods virtual mods to set
```

XkbSetModActionVMods sets the *vmods1* and *vmods2* fields of act using the *vmods* format of an Xkb modifier description.

#### Note

Despite the fact that the first parameter of these two macros is of type XkbAction, these macros may be used only with Actions of type XkbModAction and XkbISOAction.

## **Actions for Changing Group State**

Actions associated with the XkbGroupAction structure change the current group state when keys are pressed and released (see Chapter 5, *Keyboard State* for a description of groups and keyboard state):

```
typedef struct _XkbGroupAction {
```

```
unsigned char type;  /* XkbSA_{Set|Latch|Lock}Group */
unsigned char flags;  /* with type , controls the effect on groups */
char group_XXX; /* represents a group index or delta */
} XkbGroupAction;
```

The type field can have any of the following values:

**Table 16.4. Group Action Types** 

Туре	Effect
XkbSA_SetGroup	• If the XkbSA_GroupAbsolute bit is set in the <i>flags</i> field, key press events change the base keyboard group to the group specified by the <i>group_XXX</i> field. Otherwise, key press events change the base keyboard group by adding the <i>group_XXX</i> field to the base keyboard group. In either case, the resulting effective keyboard group is brought back into range depending on the value of the <i>groups_wrap</i> field of the controls structure (see section 10.7.1).
	<ul> <li>If a key with an XkbSA_ISOLock action (see section 16.1.8) is pressed while this key is down, the key release of this key has no effect. Otherwise, the key release cancels the effects of the key press.</li> </ul>
	• If the XkbSA_ClearLocks bit is set in the flags field, and no keys are physically depressed when this key is released, the key release also sets the locked keyboard group to <i>Group1</i> .
XkbSA_LatchGroup	<ul> <li>Key press and key release events have the same effect as for XkbSA_SetGroup; if no keys are physically depressed when this key is released, key release events have the following additional effects.</li> </ul>
	• If the XkbSA_LatchToLock bit is set in the <i>flags</i> field and the latched keyboard group index is nonzero, the key release adds the delta applied by the corresponding key press to the locked keyboard group and subtracts it from the latched keyboard group. The locked and effective keyboard group are brought back into range according to the value of the <i>groups_wrap</i> field of the controls structure.
	<ul> <li>Otherwise, the key press adds the key press delta to the latched keyboard group.</li> </ul>
XkbSA_LockGroup	• If the XkbSA_GroupAbsolute is set in the <i>flags</i> field, key press events set the locked keyboard group to the group specified by the <i>group_XXX</i> field. Otherwise, key press events add the group specified by the <i>group_XXX</i> field to the locked keyboard group. In either case, the resulting locked and effective keyboard groups are brought back into range depending on the value of the <i>groups_wrap</i> field of the controls structure.
	A key release has no effect.

The flags field is composed of the bitwise inclusive OR of the masks shown in Table 16.5. A general meaning is given in the table, but the exact meaning depends on the action type.

**Table 16.5. Group Action Flags** 

Flag	Meaning
XkbSA_ClearLocks	If set and no keys are physically depressed when this key transition occurs, the server sets the locked keyboard group to <i>Group1</i> on a key release.
XkbSA_LatchToLock	If set, and the action type is XkbSA_LatchGroup, the server locks the action group if it is already latched.
XkbSA_GroupAbsolute	If set, the <code>group_XXX</code> field represents an absolute group number. Otherwise, it represents a group delta to be added to the current group to determine the new group number.

The group\_XXX field represents a signed character. Xkb provides the following macros to convert between a signed integer value and a signed character:

XkbSASetGroup sets the group\_XXX field of act from the group index grp.

#### **Note**

Despite the fact that the first parameter of these two macros is of type XkbAction, these macros may only be used with Actions of type XkbGroupAction and XkbISOAction.

# **Actions for Moving the Pointer**

Actions associated with the XkbPtrAction structure move the pointer when keys are pressed and released:

```
typedef struct _XkbPtrAction {
   unsigned char
                                  /* XkbSA_MovePtr */
                      type;
   unsigned char
                      flags;
                                  /* determines type of pointer motion */
                      high XXX; /* x coordinate, high bits */
   unsigned char
   unsigned char
                      low XXX;
                                  /* y coordinate, low bits */
   unsigned char
                                  /* x coordinate, high bits */
                      high_YYY;
   unsigned char
                       low YYY;
                                  /* y coordinate, low bits */
} XkbPtrAction;
```

If the *MouseKeys* control is not enabled (see section 10.5.1), KeyPress and KeyRelease events are treated as though the action is XkbSA\_NoAction.

If the *MouseKeys* control is enabled, a server action of type XkbSA\_MovePtr instructs the server to generate core pointer MotionNotify events rather than the usual KeyPress event, and the corresponding

KeyRelease event disables any mouse keys timers that were created as a result of handling the XkbSA MovePtr action.

The type field of the XkbPtrAction structure is always XkbSA\_MovePtr.

The *flags* field is a bitwise inclusive OR of the masks shown in Table 16.6.

**Table 16.6. Pointer Action Types** 

act

<b>Action Type</b>	Meaning
XkbSA_NoAcceleration	If not set, and the <i>MouseKeysAccel</i> control is enabled (see section 10.5.2), the KeyPress initiates a mouse keys timer for this key; every time the timer expires, the cursor moves.
XkbSA_MoveAbsoluteX	If set, the X portion of the structure specifies the new pointer X coordinate. Otherwise, the X portion is added to the current pointer X coordinate to determine the new pointer X coordinate.
XkbSA_MoveAbsoluteY	If set, the Y portion of the structure specifies the new pointer Y coordinate. Otherwise, the Y portion is added to the current pointer Y coordinate to determine the new pointer Y coordinate.

Each of the X and Y coordinates of the XkbPtrAction structure is composed of two signed 16-bit values, that is, the X coordinate is composed of  $high\_XXX$  and  $low\_XXX$ , and similarly for the Y coordinate. Xkb provides the following macros, to convert between a signed integer and two signed 16-bit values in XkbPtrAction structures:

```
act action from which to extract X

XkbPtrActionX returns the high_XXX and low_XXX fields of act converted to a signed int.

int XkbPtrActionY(act);

act action from which to extract Y

XkbPtrActionY returns the high_YYY and low_YYY fields of act converted to a signed int.

void XkbSetPtrActionX(act, x);

act action in which to set X

x new value to set

XkbSetPtrActionX sets the high_XXX and low_XXX fields of act from the signed integer value x.

void XkbSetPtrActionY(act, y);
```

XkbSetPtrActionX sets the high\_YYY and low\_YYY fields of act from the signed integer value y.

#### **Actions for Simulating Pointer Button Press and Release**

action in which to set Y

new value to set

Actions associated with the XkbPtrBtnAction structure simulate the press and release of pointer buttons when keys are pressed and released:

```
typedef struct _XkbPtrBtnAction {
   unsigned char
                              /* XkbSA_PtrBtn, XkbSA_LockPtrBtn */
                    type;
   unsigned char
                    flags;
                              /* with type, controls the effect
                                 on pointer buttons */
   unsigned char
                    count;
                              /* controls number of ButtonPress and
                                 ButtonRelease events */
   unsigned char
                              /* pointer button to simulate */
                    button;
} XkbPtrBtnAction;
```

If the *MouseKeys* (see section 10.5.1) control is not enabled, KeyPress and KeyRelease events are treated as though the action is XkbSA\_NoAction.

The type field can have any one of the values shown in Table 16.7.

**Table 16.7. Pointer Button Action Types** 

Type	Effect
XkbSA_PtrBtn	• If XkbSA_UseDfltButton is set in the flags field, the event is generated for the pointer button specified by the mk_dflt_btn attribute of the MouseKeys control (see section 10.5.1). Otherwise, the event is generated for the button specified by the button field.
	• If the mouse button specified for this action is logically down, the key press and corresponding key release are ignored and have no effect. Otherwise, a key press causes one or more core pointer button events instead of the usual KeyPress event. If count is zero, a key press generates a single ButtonPress event; if count is greater than zero, a key press generates count pairs of ButtonPress and ButtonRelease events.
	• If count is zero, a key release generates a core pointer ButtonRelease that matches the event generated by the corresponding KeyPress; if count is nonzero, a key release does not cause a ButtonRelease event. A key release never generates a key KeyRelease event.
XkbSA_LockPtrBtn	• If the button specified by the <i>MouseKeys</i> default button or button is not locked, a key press causes a ButtonPress event instead of a KeyPress event and locks the button. If the button is already locked or if XkbSA_LockNoUnlock is set in the flags field, a key press is ignored and has no effect.
	• If the corresponding key press was ignored, and if XkbSA_LockNoLock is not set in the flags field, a key release generates a ButtonRelease event instead of a KeyRelease event and unlocks the specified button. If the corresponding key press locked a button, the key release is ignored and has no effect.

The *flags* field is composed of the bitwise inclusive OR of the masks shown in Table 16.8. A general meaning is given in the table, but the exact meaning depends on the action *type*:

**Table 16.8. Pointer Button Action Flags** 

Flag	Meaning
XkbSA_UseDfltButton	If set, the action uses the pointer button specified by the $mk\_dflt\_btn$ attribute of the $MouseKeys$ control (see section 10.5.1). Otherwise, the action uses the pointer button specified by the $button$ field.
XkbSA_LockNoLock	If set, and the action type is XkbSA_LockPtrBtn, the server only unlocks the pointer button.
XkbSA_LockNoUnlock	If set, and the action type is XkbSA_LockPtrBtn, the server only locks the pointer button.

#### **Actions for Changing the Pointer Button Simulated**

Actions associated with the XkbPtrDfltAction structure change the *mk\_dflt\_btn* attribute of the *MouseKeys* control (see section 10.5.1):

If the *MouseKeys* control is not enabled, KeyPress and KeyRelease events are treated as though the action is XkbSA\_NoAction. Otherwise, this action changes the *mk\_dflt\_btn* attribute of the *MouseKeys* control.

The type field of the XkbPtrDfltAction structure should always be XkbSA SetPtrDflt.

The *flags* field is composed of the bitwise inclusive OR of the values shown in Table 16.9 (currently there is only one value defined).

**Table 16.9. Pointer Default Flags** 

Flag	Meaning
XkbSA_DfltBtnAbsolute	If set, the <i>value</i> field represents an absolute pointer button. Otherwise, the <i>value</i> field represents the amount to be added to the current default button.

The affect field specifies what changes as a result of this action. The only valid value for the affect field is XkbSA AffectDfltBtn.

The *valueXXX* field is a signed character that represents the new button value for the *mk\_dflt\_btn* attribute of the *MouseKeys* control (see section 10.5.1). If XkbSA\_DfltBtnAbsolute is set in *flags*, *valueXXX* specifies the button to be used; otherwise, *valueXXX* specifies the amount to be added to the current default button. In either case, illegal button choices are wrapped back around into range. Xkb provides the following macros, to convert between the integer and signed character values in XkbPtrDfltAction structures:

```
int XkbSAPtrDfltValue(act);
act action from which to extract group
```

XkbSAPtrDfltValue returns the valueXXX field of act converted to a signed int.

```
void XkbSASetPtrDfltValue(act, val);

act action in which to set valueXXX

val value to set in valueXXX
```

XkbSASetPtrDfltValue sets the valueXXX field of act from val.

#### **Actions for Locking Modifiers and Group**

Actions associated with the XkbISOAction structure lock modifiers and the group according to the ISO9995 specification.

Operated by itself, the XkbISOAction is just a caps lock. Operated simultaneously with another modifier key, it transforms the other key into a locking key. For example, press ISO\_Lock, press and release Control\_L, release ISO\_Lock ends up locking the Control modifier.

The default behavior is to convert:

```
{Set,Latch}Mods to: LockMods
{Set,Latch}Group to: LockGroup
SetPtrBtn to: LockPtrBtn
SetControls to: LockControls
```

The *affects* field allows you to turn those effects on or off individually. Set XkbSA\_ISONoAffectMods to disable the first, XkbSA\_ISONoAffectGroup to disable the second, and so forth.

```
typedef struct _XkbISOAction {
    unsigned char
                    type;
                                  /* XkbSA ISOLock */
    unsigned char
                    flags;
                                  /* controls changes to group or
                                     modifier state */
    unsigned char
                    mask;
                                  /* same as mask field of
                                     a modifier description */
    unsigned char
                    real mods;
                                  /* same as real mods field of
                                     a modifier description */
                                  /* group index or delta group */
    char
                    group_XXX;
                                  /* specifies whether to affect
    unsigned char
                    affect;
                                     mods, group, ptrbtn, or controls */
    unsigned char
                    vmods1;
                                  /* derived from vmods field of
                                     a modifier description */
    unsigned char
                    vmods2;
                                  /* derived from vmods field of
                                     a modifier description */
} XkbISOAction;
```

The type field of the XkbISOAction structure should always be XkbSA\_ISOLock.

The interpretation of the flags field depends on whether the XkbSA\_ISODfltIsGroup is set in the flags field or not.

If the XkbSA\_ISODfltIsGroup is set in the *flags* field, the action is used to change the group state. The remaining valid bits of the *flags* field are composed of a bitwise inclusive OR using the masks shown in Table 16.10.

Table 16.10. ISO Action Flags when XkbSA\_ISODfltIsGroup is Set

Flag	Meaning
XkbSA_ISODfltIsGroup	If set, the action is used to change the base group state. Must be set for the remaining bits in this table to carry their interpretations.
	A key press sets the base group as specified by the <code>group_XXX</code> field and the XkbSA_GroupAbsolute bit of the <code>flags</code> field (see section Note). If no other actions are transformed by the XkbSA_ISOLock action, a key release locks the group. Otherwise, a key release clears group set by the key press.
XkbSA_GroupAbsolute	If set, the <i>group_XXX</i> field represents an absolute group number. Otherwise, it represents a group delta to be added to the current group to determine the new group number.
XkbSA_ISONoAffectMods	If not set, any XkbSA_SetMods or XkbSA_LatchMods actions that occur simultaneously with the XkbSA_ISOLock action are treated as XkbSA_LockMods actions instead.
XkbSA_ISONoAffectGroup	If not set, any XkbSA_SetGroup or XkbSA_LatchGroup actions that occur simultaneously with the XkbSA_ISOLock action are treated as XkbSA_LockGroup actions instead.
XkbSA_ISONoAffectPtr	If not set, any XkbSA_PtrBtn actions that occur simultaneously with the XkbSA_ISOLock action are treated as XkbSA_LockPtrBtn actions instead.
XkbSA_ISONoAffectCtrls	If not set, any XkbSA_SetControls actions that occur simultaneously with the XkbSA_ISOLock action are treated as XkbSA_LockControls actions instead.

If the XkbSA\_ISODfltIsGroup is not set in the *flags* field, the action is used to change the modifier state and the remaining valid bits of the *flags* field are composed of a bitwise inclusive OR using the masks shown in Table 16.11.

Table 16.11. ISO Action Flags when XkbSA\_ISODfltIsGroup is Not Set

Flag	Meaning
XkbSA_ISODfltIsGroup	If not set, action is used to change the base modifier state.  Must not be set for the remaining bits in this table to carry their interpretations.
	A key press sets the action modifiers in the keyboard's base modifiers using the mask, real_mods, vmods1, and vmods2 fields (see section 16.1.3). If no other actions are transformed by the XkbSA_ISOLock action, a key release locks the action modifiers. Otherwise, a key release clears the base modifiers set by the key press.
XkbSA_UseModMapMods	If set, the action modifiers are determined by the modifiers bound by the modifier mapping of the key. Otherwise, the action modifiers are set to the modifiers specified by the mask, real_mods, vmods1, and vmods2 fields.
XkbSA_LockNoLock	If set, the server only unlocks the action modifiers.
XkbSA_LockNoUnlock	If set, the server only locks the action modifiers.
XkbSA_ISONoAffectMods	If not set, any XkbSA_SetMods or XkbSA_LatchMods actions that occur simultaneously with the XkbSA_ISOLock action are treated as XkbSA_LockMods actions instead.
XkbSA_ISONoAffectGroup	If not set, any XkbSA_SetGroup or XkbSA_LatchGroup actions that occur simultaneously with the XkbSA_ISOLock action are treated as XkbSA_LockGroup actions instead.
XkbSA_ISONoAffectPtr	If not set, any XkbSA_PtrBtn actions that occur simultaneously with the XkbSA_ISOLock action are treated as XkbSA_LockPtrBtn actions instead.
XkbSA_ISONoAffectCtrls	If not set, any XkbSA_SetControls actions that occur simultaneously with the XkbSA_ISOLock action are treated as XkbSA_LockControls actions instead.

The group\_XXX field represents a signed character. Xkb provides macros to convert between a signed integer value and a signed character as shown in section Note.

The mask, real\_mods, vmods1, and vmods2 fields represent the components of an Xkb modifier description (see section 7.2). While the mask and real\_mods fields correspond directly to the mask and real\_mods fields of an Xkb modifier description, the vmods1 and vmods2 fields are combined to correspond to the vmods field of an Xkb modifier description. Xkb provides macros to convert between the two formats as shown in section 16.1.3.

The affect field is composed of a bitwise inclusive OR using the masks shown in Table 16.11.

**Table 16.12. ISO Action Affect Field Values** 

Affect	Meaning
XkbSA_ISONoAffectMods	If XkbSA_ISONoAffectMods is not set, any SA_SetMods or SA_LatchMods actions occurring simultaneously with the XkbISOAction are treated as SA_LockMods instead.
XkbSA_ISONoAffectGroup	If XkbSA_ISONoAffectGroup is not set, any <i>SA_SetGroup</i> or <i>SA_LatchGroup</i> actions occurring simultaneously with the XkbISOAction are treated as <i>SA_LockGroup</i> instead.
XkbSA_ISONoAffectPtr	If XkbSA_ISONoAffectPtr is not set, any <i>SA_PtrBtn</i> actions occurring simultaneously with the XkbISOAction are treated as <i>SA_LockPtrBtn</i> instead.
XkbSA_ISONoAffectCtrls	If XkbSA_ISONoAffectCtrls is not set, any <i>SA_SetControls</i> actions occurring simultaneously with the XkbISOAction are treated as <i>SA_LockControls</i> instead.

#### **Actions for Changing the Active Screen**

Actions associated with the XkbSwitchScreenAction action structure change the active screen on a multiscreen display:

#### Note

This action is optional. Servers are free to ignore the action or any of its flags if they do not support the requested behavior. If the action is ignored, it behaves like XkbSA\_NoAction. Otherwise, key press and key release events do not generate an event.

The type field of the XkbSwitchScreenAction structure should always be XkbSA SwitchScreen.

The flags field is composed of the bitwise inclusive OR of the masks shown in Table 16.13.

**Table 16.13. Switch Screen Action Flags** 

Flag	Meaning
XkbSA_SwitchAbsolute	If set, the <i>screenXXX</i> field represents the index of the new screen. Otherwise, it represents an offset from the current screen to the new screen.
XkbSA_SwitchApplication	If not set, the action should switch to another screen on the same server. Otherwise, it should switch to another X server or application that shares the same physical display.

The screenXXX field is a signed character value that represents either the relative or absolute screen index, depending on the state of the XkbSA\_SwitchAbsolute bit in the flags field. Xkb provides the following macros to convert between the integer and signed character value for screen numbers in XkbSwitchScreenAction structures:

```
int XkbSAScreen(act);
```

act action from which to extract screen

XkbSAScreen returns the screenXXX field of act converted to a signed int.

void XkbSASetScreen(act, s);

act action in which to set screenXXX

s value to set in screenXXX

XkbSASetScreen sets the screenXXX field of act from s.

#### **Actions for Changing Boolean Controls State**

Actions associated with the XkbCtrlsAction structure change the state of the boolean controls (see section 10.1):

```
typedef struct _XkbCtrlsAction {
    unsigned char
                                    /* XkbSA_SetControls,
                      type;
                                      XkbSA_LockControls */
   unsigned char
                      flags;
                                    /* with type, controls enabling
                                      and disabling of controls */
   unsigned char
                      ctrls3;
                                    /* ctrls0 through ctrls3
                                      represent the boolean controls */
   unsigned char
                      ctrls2;
                                    /* ctrls0 through ctrls3
                                      represent the boolean controls */
    unsigned char
                      ctrls1;
                                    /* ctrls0 through ctrls3
                                      represent the boolean controls */
    unsigned char
                      ctrls0;
                                    /* ctrls0 through ctrls3
                                       represent the boolean controls */
} XkbCtrlsAction;
```

The type field can have any one of the values shown in Table 16.14.

**Table 16.14. Controls Action Types** 

Туре	Effect
XkbSA_SetControls	• A key press enables any boolean controls specified in the ctrls fields that were not already enabled at the time of the key press.
	• A key release disables any controls enabled by the key press.
	<ul> <li>This action can cause XkbControlsNotify events (see section 10.1).</li> </ul>
XkbSA_LockControls	• If the XkbSA_LockNoLock bit is not set in the <i>flags</i> field, a key press enables any controls specified in the <i>ctrls</i> fields that were not already enabled at the time of the key press.
	• If the XkbSA_LockNoUnlock bit is not set in the <i>flags</i> field, a key release disables any controls specified in the <i>ctrls</i> fields that were not already disabled at the time of the key press.
	<ul> <li>This action can cause XkbControlsNotify events (see section 10.1).</li> </ul>

The flags field is composed of the bitwise inclusive OR of the masks shown in Table 16.15.

**Table 16.15. Control Action Flags** 

Flag	Meaning
XkbSA_LockNoLock	If set, and the action type is XkbSA_LockControls, the server only disables controls.
XkbSA_LockNoUnlock	If set, and the action type is XkbSA_LockControls, the server only enables controls.

The XkbSA\_SetControls action implements a key that enables a boolean control when pressed and disables it when released. The XkbSA\_LockControls action is used to implement a key that toggles the state of a boolean control each time it is pressed and released. The XkbSA\_LockNoLock and XkbSA\_LockNoUnlock flags allow modifying the toggling behavior to only unlock or only lock the boolean control.

The ctrls0, ctrls1, ctrls2, and ctrls3 fields represent the boolean controls in the enabled\_ctrls field of the controls structure (see section 10.1). Xkb provides the following macros, to convert between the two formats:

```
unsigned int XkbActionCtrls(act);

act action from which to extract controls

XkbActionCtrls returns the ctrls fields of act converted to an unsigned int.

void XkbSAActionSetCtrls(act, ctrls);

act action in which to set ctrls0-ctrls3
```

value to set in ctrls0-ctrls3

XkbSAActionSetCtrls sets the ctrls0 through ctrls3 fields of act from ctrls.

#### **Actions for Generating Messages**

ctrls

Actions associated with the XkbMessageAction structure generate XkbActionMessage events:

The type field of the XkbMessageAction structure should always be XkbSA\_ActionMessage.

The flags field is composed of the bitwise inclusive OR of the masks shown in Table 16.16.

**Table 16.16. Message Action Flags** 

Flag	Meaning
XkbSA_MessageOnPress	If set, key press events generate an XkbActionMessage event that reports the keycode, event type, and contents of the message field.
XkbSA_MessageOnRelease	If set, key release events generate an XkbActionMessage event that reports the keycode, event type, and contents of the message field.
XkbSA_MessageGenKeyEvent	If set, key press and key release events generate KeyPress and KeyRelease events, regardless of whether they generate XkbActionMessage events.

The message field is an array of XkbActionMessageLength unsigned characters and may be set to anything the keymap designer wishes.

#### **Detecting Key Action Messages**

To receive XkbActionMessage events by calling either XkbSelectEvents or XkbSelectEventDetails (see section 4.3).

To receive XkbActionMessage events under all possible conditions, use XkbSelectEvents and pass XkbActionMessageMask in both bits\_to\_change and values\_for\_bits.

The XkbActionMessage event has no event details. However, you can call XkbSelectEventDetails using XkbActionMessage as the event\_type and specifying XkbAllActionMessagesMask in bits\_to\_change and values\_for\_bits. This has the same effect as a call to XkbSelectEvents.

The structure for the XkbActionMessage event is defined as follows:

```
typedef struct _XkbActionMessage {
                                      /* Xkb extension base event code */
                   type;
   unsigned long serial;
                                      /* X server serial number for event */
                                     /* True # synthetically generated */
   Bool
                   send_event;
   Display *
                   display;
                                     /* server connection where event generated */
                                     /* server time when event generated */
   Time
                   time;
    int
                                     /* XkbActionMessage */
                   xkb_type;
    int
                   device;
                                     /* Xkb device ID,
                                        will not be XkbUseCoreKbd */
   KeyCode
                   keycode;
                                      /* keycode of key triggering event */
                                      /* True # key press,
   Bool
                   press;
                                        False # release */
   Bool
                   key_event_follows;/* True # KeyPress/KeyRelease follows */
                   message[XkbActionMessageLength+1]; /* message text */
    char
} XkbActionMessageEvent;
```

The *keycode* is the keycode of the key that was pressed or released. The *press* field specifies whether the event was the result of a key press or key release.

The <code>key\_event\_follows</code> specifies whether a KeyPress (if <code>press</code> is True) or KeyRelease (if <code>press</code> is False) event is also sent to the client. As with all other Xkb events, XkbActionMessageEvents are delivered to all clients requesting them, regardless of the current keyboard focus. However, the KeyPress or KeyRelease event that conditionally follows an XkbActionMessageEvent is sent only to the client selected

by the current keyboard focus.  $key\_event\_follows$  is True only for the client that is actually sent the following KeyPress or KeyRelease event.

The message field is set to the message specified in the action and is guaranteed to be NULL-terminated; the Xkb extension forces a NULL into message [XkbActionMessageLength].

### **Actions for Generating a Different Keycode**

Actions associated with the XkbRedirectKeyAction structure generate KeyPress and KeyRelease events containing a keycode different from the key that was pressed or released:

```
typedef struct
                    XkbRedirectKeyAction {
   unsigned char
                                      /* XkbSA_RedirectKey */
                       type;
   unsigned char
                       new_key;
                                      /* keycode to be put in event */
   unsigned char
                                      /* mask of real mods to be reset */
                       mods mask;
   unsigned char
                                      /* mask of real mods to take values from */
                       mods;
   unsigned char
                       vmods mask0;
                                      /* first half of mask of virtual mods
                                         to be reset */
   unsigned char
                       vmods_mask1;
                                       /* other half of mask of virtual mods
                                         to be reset */
                                       /* first half of mask of virtual mods
   unsigned char
                       vmods0;
                                         to take values from */
   unsigned char
                       vmods1;
                                       /* other half of mask of virtual mods
                                         to take values from */
} XkbRedirectKeyAction;
```

The type field for the XkbRedirectKeyAction structure should always be XkbSA\_RedirectKey.

Key presses cause a KeyPress event for the key specified by the <code>new\_key</code> field instead of the actual key. The state reported in this event reports the current effective modifiers changed as follows: any real modifiers selected by the <code>mods\_mask</code> field are set to corresponding values from the <code>mods</code> field. Any real modifiers bound to the virtual modifiers specified by the <code>vmods\_mask0</code> and <code>vmods\_mask1</code> fields are either set or cleared, depending on the corresponding values in the <code>vmods0</code> and <code>vmods1</code> fields. If the real and virtual modifier definitions specify conflicting values for a single modifier, the real modifier definition has priority.

Key releases cause a KeyRelease event for the key specified by the new\_key field instead of the actual key. The state for this event consists of the effective keyboard modifiers at the time of the release, changed as described previously.

The XkbSA\_RedirectKey action normally redirects to another key on the same device as the key that caused the event, unless that device does not belong to the input extension KeyClass, in which case this action causes an event on the core keyboard device. (The input extension categorizes devices by breaking them into classes. Keyboards, and other input devices with keys, are classified as KeyClass devices by the input extension.)

The *vmods\_mask0* and *vmods\_mask1* fields actually represent one *vmods\_mask* value, as described in Chapter 7, *Virtual Modifiers*. Xkb provides the following macros, to convert between the two formats:

```
unsigned int XkbSARedirectVModsMask(act);

act action from which to extract vmods
```

XkbSARedirectVModsMask returns the *vmods\_mask0* and *vmods\_mask1* fields of act converted to an unsigned int.

```
void XkbSARedirectSetVModsMask(act, vm);
act
                     action in which to set vmods
                      new value for virtual modifier mask
vm
XkbSARedirectSetVModsMask sets the vmods mask0 and vmods mask1 fields of act from
vm.
Similarly, the vmods0 and vmods1 fields actually represent one vmods value, as described in Chapter 7,
Virtual Modifiers. To convert between the two formats, Xkb provides the following convenience macros:
unsigned int XkbSARedirectVMods(act);
                      action from which to extract ymods
act
XkbSARedirectVModsMask returns the vmods0 and vmods1 fields of act converted to an unsigned
void XkbSARedirectSetVMods(act, v);
                      action in which to set vmods
act
                     new value for virtual modifiers
```

XkbSARedirectSetVModsMask sets the vmods0 and vmods1 of act from v.

# Actions for Generating DeviceButtonPress and DeviceButtonRelease

Actions associated with XkbDeviceBtnAction structures generate DeviceButtonPress and DeviceButtonRelease events instead of normal KeyPress and KeyRelease events:

```
typedef struct _XkbDeviceBtnAction {
                                /* XkbSA_DeviceBtn, XkbSA_LockDeviceBtn */
   unsigned char
                     type;
                                /* with type, specifies locking or unlocking */
   unsigned char
                     flags;
   unsigned char
                                /* controls number of DeviceButtonPress
                     count;
                                   and Release events */
   unsigned char
                                /* index of button on device */
                     button;
   unsigned char
                     device;
                                /* device ID of an X input extension device */
} XkbDeviceBtnAction;
```

The type field can have any one of the values shown in Table 16.17.

**Table 16.17. Device Button Action Types** 

Type	Effect			
XkbSA_DeviceBtn	• If the button specified by this action is logically down, the key press and corresponding release are ignored and have no effect. If the device or button specified by this action are illegal, this action behaves like XkbSA_NoAction.			
	<ul> <li>Otherwise, key presses cause one or more input extension device events instead of the usual key press event. If the count field is zero, a key press generates a single DeviceButtonPress event. If count is greater than zero, a key press event generates count pairs of DeviceButtonPress and DeviceButtonRelease events.</li> </ul>			
	• If count is zero, a key release generates an input extension DeviceButtonRelease event that matches the event generated by the corresponding key press. If count is nonzero, a key release does not cause a DeviceButtonRelease event. Key releases never cause KeyRelease events.			
XkbSA_LockDeviceBtn	• If the device or button specified by this action are illegal, this action behaves like XkbSA_NoAction.			
	• Otherwise, if the specified button is not locked and the XkbSA_LockNoLock bit is not set in the flags field, a key press generates an input extension DeviceButtonPress event instead of a KeyPress event and locks the button. If the button is already locked or if XkbSA_LockNoLock bit is set in the flags field, the key press is ignored and has no effect.			
	• If the corresponding key press was ignored, and if the XkbSA_LockNoUnlock bit is not set in the flags field, a key release generates an input extension DeviceButtonRelease event instead of a KeyRelease event and unlocks the button. If the corresponding key press locked a button, the key release is ignored and has no effect.			

The flags field is composed of the bitwise inclusive OR of the masks shown in Table 16.18.

**Table 16.18. Device Button Action Flags** 

Flag	Meaning
XkbSA_LockNoLock	If set, and the action type is XkbSA_LockDeviceBtn, the server only unlocks the button.
XkbSA_LockNoUnlock	If set, and the action type is XkbSA_LockDeviceBtn, the server only locks the button.

### **Actions for Simulating Events from Device Valuators**

A *valuator* manipulates a range of values for some entity, like a mouse axis, a slider or a dial. Actions associated with XkbDeviceValuatorAction structures are used to simulate events from one or two input extension device valuators.

```
typedef struct _XkbDeviceValuatorAction {
   unsigned char
                     type;
                                  /* XkbSA DeviceValuator */
   unsigned char
                                  /* device ID */
                     device;
   unsigned char
                     v1 what;
                                  /* determines how valuator is
                                     to behave for valuator 1 */
   unsigned char
                     v1 ndx;
                                  /* specifies a real valuator */
                                  /* the value for valuator 1 */
   unsigned char
                     v1_value;
   unsigned char
                                  /* determines how valuator is
                     v2 what;
                                     to behave for valuator 2 */
                                  /* specifies a real valuator */
   unsigned char
                     v2 ndx;
   unsigned char
                                  /* the value for valuator 1 */
                     v2_value;
} XkbDeviceValuatorAction;
```

If device is illegal or if neither v1\_ndx nor v2\_ndx specifies a legal valuator, this action behaves like XkbSA NoAction.

The low four bits of  $v1\_what$  and  $v2\_what$  specify the corresponding scale value (denoted val < n > Scale in Table 16.17), if needed. The high four bits of  $v1\_what$  and  $v2\_what$  specify the operation to perform to set the values. The high four bits of  $v1\_what$  and  $v2\_what$  can have the values shown in Table 16.17; the use of val < n > Scale is shown in that table also.

Table 16.19. Device Valuator v<n>\_what High Bits Values

Value of high bits	Effect	
XkbSA_IgnoreVal	No action	
XkbSA_SetValMin	v <n>_value is set to its minimum legal value.</n>	
XkbSA_SetValCenter	v <n>_valueis centered (to (max-min)/2).</n>	
XkbSA_SetValMax	v <n>_value is set to its maximum legal value.</n>	
XkbSA_SetValRelative	v <n>_value * (2 val<n>Scale) is added to v<n>_value.</n></n></n>	
XkbSA_SetValAbsolute	v <n>_value is set to (2 val<n>Scale).</n></n>	

Illegal values for XkbSA\_SetValRelative or XkbSA\_SetValAbsolute are clamped into range. Note that all of these possibilities are legal for absolute valuators. For relative valuators, only XkbSA\_SetValRelative is permitted. Part of the input extension description of a device is the range of legal values for all absolute valuators, whence the maximum and minimum legal values shown in Table 16.17.

The following two masks are provided as a convenience to select either portion of v1\_what or v2\_what:

```
#define XkbSA_ValOpMask (0x70)
#define XkbSA_ValScaleMask (0x07)
```

v1\_ndx and v2\_ndx specify valuators that actually exists. For example, most mice have two valuators (x and y axes) so the only legal values for a mouse would be 0 and 1. For a dial box with eight dials, any value in the range 0..7 would be correct.

### Obtaining Key Actions for Keys from the Server

To update the actions (the *key\_acts* array) for a subset of the keys in a keyboard description, use XkbGetKeyActions.

```
Status XkbGetKeyActions(dpy, first, num, xkb);
```

dpy connection to X server

first key of interest

num number of keys desired

xkb pointer to keyboard description where result is stored

XkbGetKeyActions sends a request to the server to obtain the actions for *num* keys on the keyboard starting with key *first*. It waits for a reply and returns the actions in the *server->key\_acts* field of *xkb*. If successful, XkbGetKeyActions returns Success. The *xkb* parameter must be a pointer to a valid Xkb keyboard description.

If the server map in the xkb parameter has not been allocated, XkbGetKeyActions allocates and initializes it before obtaining the actions.

If the server does not have a compatible version of Xkb, or the Xkb extension has not been properly initialized, XkbGetKeyActions returns BadAccess. If *num* is less than 1 or greater than XkbMaxKeyCount, XkbGetKeyActions returns BadValue. If any allocation errors occur, XkbGetKeyActions returns BadAlloc.

### Changing the Number of Actions Bound to a Key

To change the number of actions bound to a key, use XkbResizeKeyActions.

XkbAction \*XkbResizeKeyActions(xkb, key, needed);

xkb keyboard description to change

key keycode of key to change

needed new number of actions required

The xkb parameter points to the keyboard description containing the key whose number of actions is to be changed. The key parameter is the keycode of the key to change, and needed specifies the new number of actions required for the key.

XkbResizeKeyActions reserves the space needed for the actions and returns a pointer to the beginning of the new array that holds the actions. It can change the acts, num\_acts, and size\_acts fields of xkb->server if it is necessary to reallocate the acts array.

If *needed* is greater than the current number of keysyms for the key, XkbResizeKeyActions initializes all new actions in the array to *NoAction*.

Because the number of actions needed by a key is normally computed as width \* number of groups, and XkbResizeKeyActions does not modify either the width or number of groups for the key, a discrepancy exists on return from XkbResizeKeyActions between the space allocated for the actions and the number required. The unused entries in the list of actions returned by XkbResizeKeyActions are not preserved across future calls to any of the map editing functions, so you must update the key actions (which updates the width and number of groups for the key) before calling another allocator function. A call to XkbChangeTypesOfKey updates these.

If any allocation errors occur while resizing the number of actions bound to the key, XkbResizeKeyActions returns NULL.

### Note

A change to the number of actions bound to a key should be accompanied by a change in the number of symbols bound to a key. Refer to section 15.3.7 for more information on changing the number of symbols bound to a key.

### **Key Behavior**

Key behavior refers to the demeanor of a key. For example, the expected behavior of the **CapsLock** key is that it logically locks when pressed, and then logically unlocks when pressed again.

### **Radio Groups**

Keys that belong to the same radio group have the XkbKB\_RadioGroup type in the type field and the radio group index specified in the data field in the XkbBehavior structure. If the radio group has a name in the XkbNamesRec structure, the radio group index is the index into the radio\_group array in the XkbNamesRec structure. A radio group key when pressed stays logically down until another key in the radio group is pressed, when the first key becomes logically up and the new key becomes logically down. Setting the XkbKB\_RGAllowNone bit in the behavior for all of the keys of the radio group means that pressing the logically down member of the radio group causes it to logically release, in which case none of the keys of the radio group would be logically down. If XkbKB\_RGAllowNone is not set, there is no way to release the logically down member of the group.

The low five bits of the data field of the XkbBehavior structure are the group number, the high three bits are flags. The only flag currently defined is:

#define XkbKB RGAllowNone 0x80

### The XkbBehavior Structure

The behaviors field of the server map is an array of XkbBehavior structures, indexed by keycode, and contains the behavior for each key. The XkbBehavior structure is defined as follows:

The type field specifies the Xkb behavior, and the value of the data field depends on the type. Xkb supports the key behaviors shown in Table 16.20.

Table 16.20. Key Behaviors

Type	Effect		
XkbKB_Default	Press and release events are processed normally. The data field is unused.		
XkbKB_Lock	If a key is logically up (that is, the corresponding bit of the core key map is cleared) when it is pressed, the key press is processed normally and the corresponding release is ignored. If the key is logically down when pressed, the key press is ignored but the corresponding release is processed normally. The data field is unused.		
XkbKB_RadioGroup	If another member of the radio group is logically down (all members of the radio group have the same index, specified in <i>data</i> ) when a key is pressed, the server synthesizes a key release for the member that is logically down and then processes the new key press event normally.		
	If the key itself is logically down when pressed, the key press event is ignored, but the processing of the corresponding key release depends on the value of the XkbKB_RGAllowNone bit in flags. If it is set, the key release is processed normally; otherwise, the key release is also ignored.		
	All other key release events are ignored.		
XkbKB_Overlay1	If the <i>Overlay1</i> control is enabled (see section 10.4), <i>data</i> is interpreted as a keycode, and events from this key are reported as if they came from <i>data</i> 's keycode. Otherwise, press and release events are processed normally.		
XkbKB_Overlay2	If the <i>Overlay2</i> control is enabled (see section 10.4), <i>data</i> is interpreted as a keycode, and events from this key are reported as if they came from <i>data</i> 's keycode. Otherwise, press and release events are processed normally.		

Xkb also provides the mask, XkbKB\_Permanent to specify whether the key behavior type should be simulated by Xkb or whether the key behavior describes an unalterable physical, electrical, or software aspect of the keyboard. If the XkbKB\_Permanent bit is not set in the *type* field, Xkb simulates the behavior in software. Otherwise, Xkb relies upon the keyboard to implement the behavior.

### **Obtaining Key Behaviors for Keys from the Server**

To obtain the behaviors (the *behaviors* array) for a subset of the keys in a keyboard description from the server, use XkbGetKeyBehaviors:

Status	<b>XkbGetKeyBehaviors</b> (dpy, first, num, xkb);
dpy	connection to server
first	keycode of first key to get
num	number of keys for which behaviors are desired
xkb	Xkb description to contain the result

XkbGetKeyBehaviors sends a request to the server to obtain the behaviors for *num* keys on the keyboard starting with the key whose keycode is *first*. It waits for a reply and returns the behaviors in the *server->behaviors* field of *xkb*. If successful, XkbGetKeyBehaviors returns Success.

If the server map in the xkb parameter has not been allocated, XkbGetKeyBehaviors allocates and initializes it before obtaining the actions.

If the server does not have a compatible version of Xkb, or the Xkb extension has not been properly initialized, XkbGetKeyBehaviors returns BadAccess. If *num* is less than 1 or greater than XkbMaxKeyCount, XkbGetKeyBehaviors returns BadValue. If any allocation errors occur, XkbGetKeyBehaviors returns BadAlloc.

## Explicit Components—Avoiding Automatic Remapping by the Server

Whenever a client remaps the keyboard using core protocol requests, Xkb examines the map to determine likely default values for the components that cannot be specified using the core protocol (see section 17.1.2 for more information on how Xkb chooses the default values).

This automatic remapping might replace definitions explicitly requested by an application, so the Xkb keyboard description defines an explicit components mask for each key. Any aspects of the automatic remapping listed in the explicit components mask for a key are not changed by the automatic keyboard mapping.

The explicit components masks are held in the *explicit* field of the server map, which is an array indexed by keycode. Each entry in this array is a mask that is a bitwise inclusive OR of the values shown in Table 16.21.

**Table 16.21. Explicit Component Masks** 

Bit in Explicit Mask	Value	Protects Against	
ExplicitKeyType1	(1<<0)	Automatic determination of the key type associated with <i>Group1</i> .	
ExplicitKeyType2	(1<<1)	Automatic determination of the key type associated with <i>Group2</i> .	
ExplicitKeyType3	(1<<2)	Automatic determination of the key type associated with <i>Group3</i> .	
ExplicitKeyType4	(1<<3)	Automatic determination of the key type associated with <i>Group4</i> .	
ExplicitInterpret	(1<<4)	Application of any of the fields of a symbol interpretation to the key in question.	
ExplicitAutoRepeat	(1<<5)	Automatic determination of auto-repeat status for the key, as specified in a symbol interpretation.	
ExplicitBehavior	(1<<6)	Automatic assignment of the XkbKB_Lock behavior to the key, if the XkbSI_LockingKey flag is set in a symbol interpretation.	
ExplicitVModMap	(1<<7)	Automatic determination of the virtual modifier map for the key based on the actions assigned to the key and the symbol interpretations that match the key.	

### **Obtaining Explicit Components for Keys from the Server**

To obtain the explicit components (the explicit array) for a subset of the keys in a keyboard description, use XkbGetKeyExplicitComponents.

Status **XkbGetKeyExplicitComponents**(dpy, first, num, xkb);

dpy connection to server

first keycode of first key to fetch

num number of keys for which to get explicit info

xkb Xkb description in which to put results

XkbGetKeyExplicitComponents sends a request to the server to obtain the explicit components for num keys on the keyboard starting with key first. It waits for a reply and returns the explicit components in the server->explicit array of xkb. If successful, XkbGetKeyExplicitComponents returns Success. The xkb parameter must be a pointer to a valid Xkb keyboard description.

If the *server* map in the *xkb* parameter has not been allocated, XkbGetKeyExplicitComponents allocates and initializes it before obtaining the actions.

If the server does not have a compatible version of Xkb, or the Xkb extension has not been properly initialized, XkbGetKeyExplicitComponents returns BadMatch. If numis less than 1 or greater than XkbMaxKeyCount, XkbGetKeyExplicitComponents returns BadValue. If any allocation errors occur, XkbGetKeyExplicitComponents returns BadAlloc.

## **Virtual Modifier Mapping**

The *vmods* member of the server map is a fixed-length array containing XkbNumVirtualMods entries. Each entry corresponds to a virtual modifier and provides the binding of the virtual modifier to the real modifier bits. Each entry in the *vmods* array is a bitwise inclusive OR of the legal modifier masks:

ShiftMask

LockMask

ControlMask

Mod1Mask

Mod2Mask

Mod3Mask

Mod4Mask Mod5Mask


The *vmodmap* member of the server map is similar to the *modmap* array of the client map (see section 15.4), but is used to define the virtual modifier mapping for each key. Like the *modmap* member, it is indexed by keycode, and each entry is a mask representing the virtual modifiers bound to the corresponding key:

- Each of the bits in a *vmodmap* entry represents an index into the *vmods* member. That is, bit 0 of a *vmodmap* entry refers to index 0 of the *vmods* array, bit 1 refers to index 1, and so on.
- If a bit is set in the *vmodmap* entry for a key, that key is bound to the corresponding virtual modifier in the *vmods* array.

The *vmodmap* and *vmods* members of the server map are the "master" virtual modifier definitions. Xkb automatically propagates any changes to these fields to all other fields that use virtual modifier mappings.

The overall relationship of fields dealing with virtual modifiers in an Xkb keyboard description are shown in Figure 16.2.

Figure 16.2. Virtual Modifier Relationships



### **Obtaining Virtual Modifier Bindings from the Server**

To obtain a subset of the virtual modifier bindings (the *vmods* array) in a keyboard description, use XkbGetVirtualMods:

Status **XkbGetVirtualMods**(dpy, which, xkb);

dpy connection to server

which mask indicating virtual modifier bindings to get

xkb Xkb description where results will be placed

XkbGetVirtualMods sends a request to the server to obtain the *vmods* entries for the virtual modifiers specified in the mask, *which*, and waits for a reply. See section 7.1 for a description of how to determine the virtual modifier mask. For each bit set in *which*, XkbGetVirtualMods updates the corresponding virtual modifier definition in the *server->vmods* array of *xkb*. The *xkb* parameter must be a pointer to a valid Xkb keyboard description. If successful, XkbGetVirtualMods returns Success.

If the *server* map has not been allocated in the *xkb* parameter, XkbGetVirtualMods allocates and initializes it before obtaining the virtual modifier bindings.

If the server does not have a compatible version of Xkb, or the Xkb extension has not been properly initialized, XkbGetVirtualMods returns BadMatch. Any errors in allocation cause XkbGetVirtualMods to return BadAlloc.

## **Obtaining Per-Key Virtual Modifier Mappings from the Server**

To obtain the virtual modifier map (the *vmodmap* array) for a subset of the keys in a keyboard description, use XkbGetKeyVirtualModMap:

Status **XkbGetKeyVirtualModMap**(dpy, first, num, xkb);

dpy connection to server

first keycode of first key to fetch

num # keys for which virtual mod maps are desired

xkb Xkb description where results will be placed

XkbGetKeyVirtualModmap sends a request to the server to obtain the virtual modifier mappings for num keys on the keyboard starting with key first. It waits for a reply and returns the virtual modifier mappings in the server->vmodmap array of xkb. If successful, XkbGetKeyVirtualModMap returns Success. The xkb parameter must be a pointer to a valid Xkb keyboard description


If the server map in the xkb parameter has not been allocated, XkbGetKeyVirtualModMap allocates and initializes it before obtaining the virtual modifier mappings.

If the server does not have a compatible version of Xkb, or the Xkb extension has not been properly initialized, XkbGetKeyVirtualModMap returns BadMatch. If *num* is less than 1 or greater than XkbMaxKeyCount, XkbGetKeyVirtualModMap returns BadValue. If any allocation errors occur, XkbGetKeyVirtualModMap returns BadAlloc.

## Chapter 17. The Xkb Compatibility Map

As shown in Figure 17.1, the X server is normally dealing with more than one client, each of which may be receiving events from the keyboard, and each of which may issue requests to modify the keyboard in some manner. Each client may be either Xkb-unaware, Xkb-capable, or Xkb-aware. The server itself may be either Xkb-aware or Xkb-unaware. If the server is Xkb-unaware, Xkb state and keyboard mappings are not involved in any manner, and Xkb-aware clients may not issue Xkb requests to the server. If the server is Xkb-aware, the server must be able to deliver events and accept requests in which the keyboard state and mapping are compatible with the mode in which the client is operating. Consequently, for some situations, conversions must be made between Xkb state / keyboard mappings and core protocol state / keyboard mappings, and vice versa.

Figure 17.1. Server Interaction with Types of Clients



In addition to these situations involving a single server, there are cases where a client that deals with multiple servers may need to configure keyboards on different servers to be similar and the different servers


may not all be Xkb-aware. Finally, a client may be dealing with descriptions of keyboards (files, and so on) that are based on core protocol and therefore may need to be able to map these descriptions to Xkb descriptions.

An Xkb-aware server maintains keyboard state and mapping as an Xkb keyboard state and an Xkb keyboard mapping plus a compatibility map used to convert from Xkb components to core components and vice versa. In addition, the server also maintains a core keyboard mapping that approximates the Xkb keyboard mapping. The core keyboard mapping may be updated piecemeal, on a per-key basis. When the server receives a core protocol ChangeKeyboardMapping or SetModifierMapping request, it updates its core keyboard mapping, then uses the compatibility map to update its Xkb keyboard mapping. When the server receives an XkbSetMap request, it updates those portions of its Xkb keyboard mapping specified by the request, then uses its compatibility map to update the corresponding parts of its core keyboard map. Consequently, the server's Xkb keyboard map and also its core keyboard map may contain components that were set directly and others that were computed. Figure 17.2 illustrates these relationships.

#### Note

The core keyboard map is contained only in the server, not in any client-side data structures.

Figure 17.2. Server Derivation of State and Keyboard Mapping Components



There are three kinds of compatibility transformations made by the server:

#### 1. Xkb State to Core State

Keyboard state information reported to a client in the state field of various core events may be translated from the Xkb keyboard state maintained by the server, which includes a group number, to core protocol state, which does not.

In addition, whenever the Xkb state is retrieved, the <code>compat\_state</code>, <code>compat\_grab\_mods</code>, and <code>compat\_lookup\_mods</code> fields of the XkbStateRec returned indicate the result of applying the compatibility map to the current Xkb state in the server.

### 2. Core Keyboard Mapping to Xkb Keyboard Mapping

After core protocol requests received by the server to change the keyboard mapping (ChangeKeyboardMapping and SetModifierMapping) have been applied to the server's core keyboard map, the results must be transformed to achieve an equivalent change of the Xkb keyboard mapping maintained by the server.

#### 3. Xkb Keyboard Mapping to Core Keyboard Mapping

After Xkb protocol requests received by the server to change the keyboard mapping (XkbSetMap) have been applied to the server's Xkb keyboard map, the results are transformed to achieve an approximately equivalent change to the core keyboard mapping maintained by the server.

This chapter discusses how a client may modify the compatibility map so that subsequent transformations have a particular result.

### The XkbCompatMap Structure

All configurable aspects of mapping Xkb state and configuration to and from core protocol state and configuration are defined by a compatibility map, contained in an XkbCompatMapRec structure; plus a set of explicit override controls used to prevent particular components of type 2 (core-to-Xkb keyboard mapping) transformations from automatically occurring. These explicit override controls are maintained in a separate data structure discussed in section 16.3.

The compat member of an Xkb keyboard description (XkbDescRec) points to the XkbCompatMapRec structure:

compat sym\_interpret groups[0] Group compatibility 0 groups[1] maps groups[2] XkbDescRec groups[3] num\_si - 1 num\_si size\_si size si - 1 XkbCompMapRec XkbSymInterpre

Figure 17.3. Xkb Compatibility Data Structures

The subsections that follow discuss how the compatibility map and explicit override controls are used in each of the three cases where compatibility transformations are made.

### **Xkb State to Core Protocol State Transformation**

As shown in Figure 17.3, there are four *group compatibility maps* (contained in *groups* [0..3]) in the XkbCompatMapRec structure, one per possible Xkb group. Each group compatibility map is a modifier definition (see section 7.2 for a description of modifier definitions). The *mask* component of the definition specifies which real modifiers should be set in the core protocol state field when the corresponding group is active. Because only one group is active at any one time, only one of the four possible transformations is ever applied at any one point in time. If the device described by the XkbDescRec does not support four groups, the extra groups fields are present, but undefined.

Normally, the Xkb-aware server reports keyboard state in the state member of events such as a KeyPress event and ButtonPress event, encoded as follows:

bits	meaning
15	0
13–14	Group index
8–12	Pointer Buttons
0–7	Modifiers

For Xkb-unaware clients, only core protocol keyboard information may be reported. Because core protocol does not define the group index, the group index is mapped to modifier bits as specified by the *groups* 

[group index] field of the compatibility map (the bits set in the compatibility map are ORed into bits 0–7 of the state), and bits 13–14 are reported in the event as zero.

### Core Keyboard Mapping to Xkb Keyboard Mapping Transformation

When a core protocol keyboard mapping request is received by the server, the server's core keyboard map is updated, and then the Xkb map maintained by the server is updated. Because a client may have explicitly configured some of the Xkb keyboard mapping in the server, this automatic regeneration of the Xkb keyboard mapping from the core protocol keyboard mapping should not modify any components of the Xkb keyboard mapping that were explicitly set by a client. The client must set explicit override controls to prevent this from happening (see section 16.3). The core-to-Xkb mapping is done as follows:

- 1. Map the symbols from the keys in the core keyboard map to groups and symbols on keys in the Xkb keyboard map. The core keyboard mapping is of fixed width, so each key in the core mapping has the same number of symbols associated with it. The Xkb mapping allows a different number of symbols to be associated with each key; those symbols may be divided into a different number of groups (1-4) for each key. For each key, this process therefore involves partitioning the fixed number of symbols from the core mapping into a set of variable-length groups with a variable number of symbols in each group. For example, if the core protocol map is of width five, the partition for one key might result in one group with two symbols and another with three symbols. A different key might result in two groups with two symbols plus a third group with one symbol. The core protocol map requires at least two symbols in each of the first two groups.
  - a. For each changed key, determine the number of groups represented in the new core keyboard map. This results in a tentative group count for each key in the Xkb map.
  - b. For each changed key, determine the number of symbols in each of the groups found in step 1a. There is one explicit override control associated with each of the four possible groups for each Xkb key, *ExplicitKeyType1* through *ExplicitKeyType4*. If no explicit override control is set for a group, the number of symbols used for that group from the core map is two. If the explicit override control is set for a group on the key, the number of symbols used for that Xkb group from the core map is the width of the Xkb group with one exception: because of the core protocol requirement for at least two symbols in each of groups one and two, the number of symbols used for groups one and two is the maximum of 2 or the width of the Xkb group.
  - c. For each changed key, assign the symbols in the core map to the appropriate group on the key. If the total number of symbols required by the Xkb map for a particular key needs more symbols than the core protocol map contains, the additional symbols are taken to be NoSymbol keysyms appended to the end of the core set. If the core map contains more symbols than are needed by the Xkb map, trailing symbols in the core map are discarded. In the absence of an explicit override for group one or two, symbols are assigned in order by group; the first symbols in the core map are assigned to group one, in order, followed by group two, and so on. For example, if the core map contained eight symbols per key, and a particular Xkb map contained 2 symbols for G1 and G2 and three for G3, the symbols would be assigned as (G is group, L is shift level):

### G1L1 G1L2 G2L1 G2L2 G3L1 G3L2 G3L3

If an explicit override control is set for group one or two, the symbols are taken from the core set in a somewhat different order. The first four symbols from the core set are assigned to G1L1, G1L2, G2L1, G2L2, respectively. If group one requires more symbols, they are taken next, and then any additional symbols needed by group two. Group three and four symbols are taken in complete

sequence after group two. For example, a key with four groups and three symbols in each group would take symbols from the core set in the following order:

#### G1L1 G1L2 G2L1 G2L2 G1L3 G2L3 G3L1 G3L2 G3L3 G4L1 G4L2 G4L3

As previously noted, the core protocol map requires at lease two symbols in groups one and two. Because of this, if an explicit override control for an Xkb key is set and group one and / or group two is of width one, it is not possible to generate the symbols taken from the core protocol set and assigned to position G1L2 and / or G2L2.

- d. For each group on each changed key, assign a key type appropriate for the symbols in the group.
- e. For each changed key, remove any empty or redundant groups.
- 2. At this point, the groups and their associated symbols have been assigned to the corresponding key definitions in the Xkb map.
- 3. Apply symbol interpretations to modify key operation. This phase is completely skipped if the *ExplicitInterpret* override control bit is set in the explicit controls mask for the Xkb key (see section 16.3).
  - a. For each symbol on each changed key, attempt to match the symbol and modifiers from the Xkb map to a symbol interpretation describing how to generate the symbol.
  - b. When a match is found in step 2a, apply the symbol interpretation to change the semantics associated with the symbol in the Xkb key map. If no match is found, apply a default interpretation.

The symbol interpretations used in step 2 are configurable and may be specified using XkbSymInterpretRec structures referenced by the *sym\_interpret* field of an XkbCompatMapRec (see Figure 17.3).

### Symbol Interpretations — the XkbSymInterpretRec Structure

Symbol interpretations are used to guide the X server when it modifies the Xkb keymap in step 2. An initial set of symbol interpretations is loaded by the server when it starts. A client may add new ones using XkbSetCompatMap (see section 17.4).

Symbol interpretations result in key semantics being set. When a symbol interpretation is applied, the following components of server key event processing may be modified for the particular key involved:

```
Virtual modifier map
Auto repeat
Key behavior (may be set to XkbKB_Lock)
Key action (see section 16.1)
```

The XkbSymInterpretRec structure specifies a symbol interpretation:

```
typedef struct {
                                  /* keysym of interest or NULL */
   KeySym
                    sym;
                                  /* XkbSI_AutoRepeat, XkbSI_LockingKey */
   unsigned char
                   flags;
                                  /* specifies how mods is interpreted */
   unsigned char
                   match;
   unsigned char
                                  /* modifier bits, correspond to
                   mods;
                                     eight real modifiers */
                                  /* 1 modifier to add to key virtual mod map */
   unsigned char
                   virtual_mod;
```

If sym is not NULL, it limits the symbol interpretation to keys on which that particular keysym is selected by the modifiers matching the criteria specified by mods and match. If sym is NULL, the interpretation may be applied to any symbol selected on a key when the modifiers match the criteria specified by mods and match.

match must be one of the values shown in Table 17.1 and specifies how the real modifiers specified in mods are to be interpreted.

**Table 17.1. Symbol Interpretation Match Criteria** 

Match Criteria	Value	Effect	
XkbSI_NoneOf	(0)	None of the bits that are on in <i>mods</i> can be set, but other bits can be.	
XkbSI_AnyOfOrNone	(1)	Zero or more of the bits that are on in <i>mods</i> can be set, as well as others.	
XkbSI_AnyOf	(2)	One or more of the bits that are on in <i>mods</i> can be set, as well as any others.	
XkbSI_AllOf	(3)	All of the bits that are on in <i>mods</i> must be set, but others may be set as well.	
XkbSI_Exactly	(4)	All of the bits that are on in <i>mods</i> must be set, and no other bits may be set.	

In addition to the above bits, match may contain the XkbSI\_LevelOneOnly bit, in which case the modifier match criteria specified by mods and match applies only if sym is in level one of its group; otherwise, mods and match are ignored and the symbol matches a condition where no modifiers are set.

```
#define XkbSI_LevelOneOnly (0x80)
/* use mods + match only if sym is level 1 */
```

If no matching symbol interpretation is found, the server uses a default interpretation where:

```
sym = 0
flags = XkbSI_AutoRepeat
match = XkbSI_AnyOfOrNone
mods = 0
virtual_mod = XkbNoModifier
act = SA_NoAction
```

When a matching symbol interpretation is found in step 2a, the interpretation is applied to modify the Xkb map as follows.

The act field specifies a single action to be bound to the symbol position; any key event that selects the symbol causes the action to be taken. Valid actions are defined in section 16.1.

If the Xkb keyboard map for the key does not have its *ExplicitVModMap* control set, the XkbSI\_LevelOneOnly bit and symbol position are examined. If the XkbSI\_LevelOneOnly bit is not set in *match* or the symbol is in position G1L1, the *virtual\_mod* field is examined. If *virtual\_mod* is

not XkbNoModifier, virtual\_mod specifies a single virtual modifier to be added to the virtual modifier map for the key. virtual\_mod is specified as an index in the range [0..15].

If the matching symbol is in position G1L1 of the key, two bits in the flags field potentially specify additional behavior modifications:

If the Xkb keyboard map for the key does not have its *ExplicitAutoRepeat* control set, its auto repeat behavior is set based on the value of the XkbSI\_AutoRepeat bit. If the XkbSI\_AutoRepeat bit is set, the auto-repeat behavior of the key is turned on; otherwise, it is turned off.

If the Xkb keyboard map for the key does not have its *ExplicitBehavior* control set, its locking behavior is set based on the value of the XkbSI\_LockingKey bit. If XkbSI\_LockingKey is set, the key behavior is set to *KB\_Lock*; otherwise, it is turned off (see section 16.3).

## **Xkb Keyboard Mapping to Core Keyboard Mapping Transformations**

Whenever the server processes Xkb requests to change the keyboard mapping, it discards the affected portion of its core keyboard mapping and regenerates it based on the new Xkb mapping.

When the Xkb mapping for a key is transformed to a core protocol mapping, the symbols for the core map are taken in the following order from the Xkb map:

```
G1L1 G1L2 G2L1 G2L2 G1L3-n G2L3-n G3L1-n G4L1-n
```

If group one is of width one in the Xkb map, G1L2 is taken to be NoSymbol; similarly, if group two is of width one in the Xkb map, G2L2 is taken to be NoSymbol.

If the Xkb key map for a particular key has fewer groups than the core keyboard, the symbols for group one are repeated to fill in the missing core components. For example, an Xkb key with a single width-three group would be mapped to a core mapping counting three groups as:

```
G1L1 G1L2 G1L1 G1L2 G1L3 G1L3 G1L1 G1L2 G1L3
```

When a core keyboard map entry is generated from an Xkb keyboard map entry, a modifier mapping is generated as well. The modifier mapping contains all of the modifiers affected by any of the actions associated with the key combined with all of the real modifiers associated with any of the virtual modifiers bound to the key. In addition, if any of the actions associated with the key affect any component of the keyboard group, all of the modifiers in the *mask* field of all of the group compatibility maps are added to the modifier mapping as well. While an XkbSA\_ISOLock action can theoretically affect any modifier, if the Xkb mapping for a key specifies an XkbSA\_ISOLock action, only the modifiers or group that are set by default are added to the modifier mapping.

## **Getting Compatibility Map Components From the Server**

Use XkbGetCompatMap to fetch any combination of the current compatibility map components from the server. When another client modifies the compatibility map, you are notified if you have selected for

XkbCompatMapNotify events (see section 17.5). XkbGetCompatMap is particularly useful when you receive an event of this type, as it allows you to update your program's version of the compatibility map to match the modified version now in the server. If your program is dealing with multiple servers and needs to configure them all in a similar manner, the updated compatibility map may be used to reconfigure other servers.

### Note

To make a complete matching configuration you must also update the explicit override components of the server state.

Status **XkbGetCompatMap**(display, which, xkb);

display connection to server

which mask of compatibility map components to fetch

xkb keyboard description where results placed

XkbGetCompatMap fetches the components of the compatibility map specified in which from the server specified by display and places them in the compat structure of the keyboard description xkb. Valid values for which are an inclusive OR of the values shown in Table 17.2.

Table 17.2. Compatibility Map Component Masks

Mask	Value	Affecting
XkbSymInterpMask	(1<<0)	Symbol interpretations
XkbGroupCompatMask	(1<<1)	Group maps
XkbAllCompatMask	(0x3)	All compatibility map components

If no compatibility map structure is allocated in xkb upon entry, XkbGetCompatMap allocates one. If one already exists, its contents are overwritten with the returned results.

XkbGetCompatMap fetches compatibility map information for the device specified by the device\_spec field of xkb. Unless you have specifically modified this field, it is the default keyboard device. XkbGetCompatMap returns Success if successful, BadAlloc if it is unable to obtain necessary storage for either the return values or work space, BadMatch if the dpy field of the xkb argument is non-NULL and does not match the display argument, and BadLength under certain conditions caused by server or Xkb implementation errors.

## **Using the Compatibility Map**

Xkb provides several functions that make it easier to apply the compatibility map to configure a client-side Xkb keyboard mapping, given a core protocol representation of part or all of a keyboard mapping. Obtain a core protocol representation of a keyboard mapping from an actual server (by using XGetKeyboardMapping, for example), a data file, or some other source.

To update a local Xkb keyboard map to reflect the mapping expressed by a core format mapping by calling the function XkbUpdateMapFromCore.

Bool **XkbUpdateMapFromCore**(xkb, first\_key, num\_keys, map\_width, core\_keysyms, changes);

xkb keyboard description to update

first\_key keycode of first key description to update

num\_keys number of key descriptions to update

map\_width width of core protocol keymap

core\_keysyms symbols in core protocol keymap

changes backfilled with changes made to Xkb

XkbUpdateMapFromCore interprets input argument information representing a keyboard map in core format to update the Xkb keyboard description passed in xkb. Only a portion of the Xkb map is updated — the portion corresponding to keys with keycodes in the range first\_key through first\_key + num\_keys - 1. If XkbUpdateMapFromCore is being called in response to a MappingNotify event, first\_key and num\_keys are reported in the MappingNotify event. core\_keysyms contains the keysyms corresponding to the keycode range being updated, in core keyboard description order. map\_width is the number of keysyms per key in core\_keysyms. Thus, the first map\_width entries in core\_keysyms are for the key with keycode first\_key, the next map\_width entries are for key first\_key + 1, and so on.

In addition to modifying the Xkb keyboard mapping in xkb, XkbUpdateMapFromCore backfills the changes structure whose address is passed in changes to indicate the modifications that were made. You may then use changes in subsequent calls such as XkbSetMap, to propagate the local modifications to a server.

When dealing with core keyboard mappings or descriptions, it is sometimes necessary to determine the Xkb key types appropriate for the symbols bound to a key in a core keyboard mapping. Use XkbKeyTypesForCoreSymbols for this purpose:

int XkbKeyTypesForCoreSymbols(xkb, map\_width, core\_syms, protected, types inout, xkb syms rtrn);

*xkb* keyboard description in which to place symbols

map\_width width of core protocol keymap in xkb\_syms\_rtrn

core\_syms core protocol format array of KeySyms

protected explicit key types

types\_inout backfilled with the canonical types bound to groups one and two

for the key

xkb\_syms\_rtrn backfilled with symbols bound to the key in the Xkb mapping

XkbKeyTypesForCoreSymbols expands the symbols in *core\_syms* and types in *types\_inout* according to the rules specified in section 12 of the core protocol, then chooses canonical key types (canonical key types are defined in section 15.2.1) for groups 1 and 2 using the rules specified by the Xkb protocol and places them in *xkb\_syms\_rtrn*, which will be non-NULL.

A core keymap is a two-dimensional array of keysyms. It has  $map\_width$  columns and  $max\_key\_code$  rows. XkbKeyTypesForCoreSymbols takes a single row from a core keymap, determines the number of groups associated with it, the type of each group, and the symbols bound to each group. The return value is the number of groups,  $types\_inout$  has the types for each group, and  $xkb\_syms\_rtrn$  has the symbols in Xkb order (that is, groups are contiguous, regardless of size).

protected contains the explicitly protected key types. There is one explicit override control associated with each of the four possible groups for each Xkb key, ExplicitKeyType1 through ExplicitKeyType4;

protected is an inclusive OR of these controls. map\_width is the width of the core keymap and is not dependent on any Xkb definitions. types\_inout is an array of four type indices. On input, types\_inout contains the indices of any types already assigned to the key, in case they are explicitly protected from change.

Upon return, types\_inout contains any automatically selected (that is, canonical) types plus any protected types. Canonical types are assigned to all four groups if there are enough symbols to do so. The four entries in types inout correspond to the four groups for the key in question.

If the groups mapping does not change, but the symbols assigned to an Xkb keyboard compatibility map do change, the semantics of the key may be modified. To apply the new compatibility mapping to an individual key to get its semantics updated, use XkbApplyCompatMapToKey.

Bool **XkbApplyCompatMapToKey**(xkb, key, changes);

xkb keyboard description to be updated

key key to be updated

changes notes changes to the Xkb keyboard description

XkbApplyCompatMapToKey essentially performs the operation described in section 17.1.2 to a specific key. This updates the behavior, actions, repeat status, and virtual modifier bindings of the key.

### Changing the Server's Compatibility Map

To modify the server's compatibility map, first modify a local copy of the Xkb compatibility map, then call XkbSetCompatMap. You may allocate a new compatibility map for this purpose using XkbAllocCompatMap (see section 17.6). You may also use a compatibility map from another server, although you need to adjust the <code>device\_spec</code> field in the XkbDescRec accordingly. Note that symbol interpretations in a compatibility map (<code>sym\_interpret</code>, the vector of XkbSymInterpretRec structures) are also allocated using this same function.

Bool XkbSetCompatMap(display, which, xkb, update\_actions);

display connection to server

which mask of compat map components to set

xkb source for compat map components

update\_actions True → apply to server's keyboard map

XkbSetCompatMap copies compatibility map information from the keyboard description in xkb to the server specified in display's compatibility map for the device specified by the device\_spec field of xkb. Unless you have specifically modified this field, it is the default keyboard device. which specifies the compatibility map components to be set, and is an inclusive OR of the bits shown in Table 17.2.

After updating its compatibility map for the specified device, if update\_actions is True, the server applies the new compatibility map to its entire keyboard for the device to generate a new set of key semantics, compatibility state, and a new core keyboard map. If update\_actions is False, the new compatibility map is not used to generate any modifications to the current device semantics, state, or core keyboard map. One reason for not applying the compatibility map immediately would be if one server was being configured to match another on a piecemeal basis; the map should not be applied until everything is updated. To force an update at a later time, use XkbSetCompatMap specifying which as zero and update\_actions as True.

XkbSetCompatMap returns True if successful and False if unsuccessful. The server may report problems it encounters when processing the request subsequently via protocol errors.

To add a symbol interpretation to the list of symbol interpretations in an XkbCompatRec, use XkbAddSymInterpret.

```
      XkbSymInterpretPtr
      XkbAddSymInterpret(xkb, si, updateMap, changes);

      xkb
      keyboard description to be updated

      si
      symbol interpretation to be added

      updateMap
      True#apply compatibility map to keys

      changes
      changes are put here
```

XkbAddSymInterpret adds si to the list of symbol interpretations in xkb. If updateMap is True, it (re)applies the compatibility map to all of the keys on the keyboard. If changes is non- NULL, it reports the parts of the keyboard that were affected (unless updateMap is True, not much changes). XkbAddSymInterpret returns a pointer to the actual new symbol interpretation in the list or NULL if it failed.

## Tracking Changes to the Compatibility Map

The server automatically generates MappingNotify events when the keyboard mapping changes. If you wish to be notified of changes to the compatibility map, you should select for XkbCompatMapNotify events. If you select for XkbMapNotify events, you no longer receive the automatically generated MappingNotify events. If you subsequently deselect XkbMapNotifyEvent delivery, you again receive MappingNotify events.

To receive XkbCompatMapNotify events under all possible conditions, use XkbSelectEvents (see section 4.3) and pass XkbCompatMapNotifyMask in both bits\_to\_change and values\_for\_bits.

To receive XkbCompatMapNotify events only under certain conditions, use XkbSelectEventDetails using XkbCompatMapNotify as the event\_type and specifying the desired map changes in bits\_to\_change and values\_for\_bits using mask bits from Table 17.2.

Note that you are notified of changes you make yourself, as well as changes made by other clients.

The structure for the XkbCompatMapNotifyEvent is:

```
typedef struct {
                                   /* Xkb extension base event code */
                   type;
                                   /* X server serial number for event */
   unsigned long serial;
                                   /* True #
   Bool
                   send event;
                                      synthetically generated */
   Display *
                   display;
                                   /* server connection where event generated */
   Time
                   time;
                                   /* server time when event generated */
    int
                   xkb type;
                                   /* XkbCompatMapNotify */
                                   /* Xkb device ID, will not be
   int
                   device;
                                      XkbUseCoreKbd */
                   changed groups; /* number of group maps changed */
   unsigned int
                   first si;
                                   /* index to 1st changed symbol
    int
```

```
interpretation */
int num_si; /* number of changed symbol
interpretations */
int num_total_si; /* total number of valid symbol
interpretations */
} XkbCompatMapNotifyEvent;
```

changed\_groups is the number of group compatibility maps that have changed. If you are maintaining a corresponding copy of the compatibility map, or get a fresh copy from the server using XkbGetCompatMap, changed\_groups references groups [0.. changed\_groups -1] in the XkbCompatMapRec structure.

first\_si is the index of the first changed symbol interpretation, num\_si is the number of changed symbol interpretations, and num\_total\_si is the total number of valid symbol interpretations. If you are maintaining a corresponding copy of the compatibility map, or get a fresh copy from the server using XkbGetCompatMap, first\_si, num\_si, and num\_total\_si are appropriate for use with the compat.sym\_interpret vector in this structure.

## Allocating and Freeing the Compatibility Map

If you are modifying the compatibility map, you need to allocate a new compatibility map if you do not already have one available. To do so, use XkbAllocCompatMap.

```
Status XkbAllocCompatMap(xkb, which, num_si);

xkb keyboard description in which to allocate compat map
which mask of compatibility map components to allocate
num si number of symbol interpretations to allocate
```

xkb specifies the keyboard description for which compatibility maps are to be allocated. The compatibility map is the compat field in this structure.

which specifies the compatibility map components to be allocated (see XkbGetCompatMap, in section 17.2). which is an inclusive OR of the bits shown in Table 17.2.

num\_si specifies the total number of entries to allocate in the symbol interpretation vector (xkb.compat.sym\_interpret).

Note that symbol interpretations in a compatibility map (the <code>sym\_interpret</code> vector of XkbSymInterpretRec structures) are also allocated using this same function. To ensure that there is sufficient space in the symbol interpretation vector for entries to be added, use XkbAllocCompatMap specifying <code>which</code> as <code>XkbSymInterpretMask</code> and the number of free symbol interpretations needed in <code>num\_si</code>.

XkbAllocCompatMap returns Success if successful, BadMatch if xkb is NULL, or BadAlloc if errors are encountered when attempting to allocate storage.

To free an entire compatibility map or selected portions of one, use XkbFreeCompatMap.

free\_map

 $True \Longrightarrow free \ XkbCompatMapRec \ structure \ itself$ 

which specifies the compatibility map components to be freed (see XkbGetCompatMap, in section 17.2). which is an inclusive OR of the bits shown in Table 17.2

free\_map indicates whether the XkbCompatMapRec structure itself should be freed. If free\_map is True, which is ignored, all non-NULL compatibility map components are freed, and the compat field in the XkbDescRec referenced by xkb is set to NULL.

## **Chapter 18. Symbolic Names**

The core protocol does not provide any information to clients other than that actually used to interpret events. This makes it difficult to write an application that presents the keyboard to a user in an easy-to-understand way. Such applications have to examine the vendor string and keycodes to determine the type of keyboard connected to the server and then examine keysyms and modifier mappings to determine the effects of most modifiers (the Shift, Lock and Control modifiers are defined by the core protocol but no semantics are implied for any other modifiers).

To make it easier for applications to present a keyboard to the user, Xkb supports symbolic names for most components of the keyboard extension. Most of these symbolic names are grouped into the *names* component of the keyboard description.

### The XkbNamesRec Structure

The names component of the keyboard description is defined as follows:

```
#define
             XkbKeyNameLength
                                    4
#define
             XkbKeyNumVirtualMods
                                    16
#define
             XkbKeyNumIndicators
                                    32
#define
             XkbKeyNumKbdGroups
                                    4
#define
             XkbMaxRadioGroups
typedef struct {
              name[XkbKeyNameLength];
                                            /* symbolic key names */
} XkbKeyNameRec, *XkbKeyNamePtr;
typedef struct {
    char
              real[XkbKeyNameLength];
              /* this key name must be in the keys array */
              alias[XkbKeyNameLength];
    char
              /* symbolic key name as alias for the key */
} XkbKeyAliasRec, *XkbKeyAliasPtr;
typedef struct _XkbNamesRec {
                    keycodes;
                                      /* identifies range and meaning
    Atom
                                         of keycodes */
    Atom
                    geometry;
                                      /* identifies physical location,
                                         size, and shape of keys */
    Atom
                    symbols;
                                      /* identifies the symbols logically
                                         bound to the keys */
                                      /* identifies the set of key types */
   Atom
                    types;
    Atom
                    compat;
                                      /* identifies actions for keys using
                                         core protocol */
    At.om
                    vmods[XkbNumVirtualMods]; /* symbolic names for
                                                   virtual modifiers */
                    indicators[XkbNumIndicators]; /* symbolic names
    Atom
                                                       for indicators */
    Atom
                    groups[XkbNumKbdGroups];
                                               /* symbolic names for
                                                   keyboard groups */
    XkbKeyNamePtr
                    keys;
                                      /* symbolic key name array */
```

```
/* real/alias symbolic name pairs array */
   XkbKeyAliasPtr key_aliases;
   Atom *
                    radio groups;
                                     /* radio group name array */
   Atom
                    phys_symbols;
                                     /* identifies the symbols engraved
                                        on the keyboard */
   unsigned char
                    num keys;
                                     /* number of keys in the keys array */
   unsigned char
                    num key aliases; /* number of keys in the
                                        key_aliases array */
   unsigned short num rg;
                                     /* number of radio groups */
} XkbNamesRec, *XkbNamesPtr;
```

The keycodes name identifies the range and meaning of the keycodes returned by the keyboard in question. The geometry name, on the other hand, identifies the physical location, size and shape of the various keys on the keyboard. As an example to distinguish between these two names, consider function keys on PC-compatible keyboards. Function keys are sometimes above the main keyboard and sometimes to the left of the main keyboard, but the same keycode is used for the key that is logically F1 regardless of physical position. Thus, all PC-compatible keyboards share a similar keycodes name but may have different geometry names.

### Note

The keycodes name is intended to be a very general description of the keycodes returned by a keyboard; a single keycodes name might cover keyboards with differing numbers of keys provided all keys have the same semantics when present. For example, 101 and 102 key PC keyboards might use the same name. In these cases, applications can use the keyboard <code>geometry</code> name to determine which subset of the named keycodes is in use.

The *symbols* name identifies the symbols logically bound to the keys. The symbols name is a human or application-readable description of the intended locale or usage of the keyboard with these symbols. The *phys\_symbols* name, on the other hand, identifies the symbols actually engraved on the keyboard. Given this, the *symbols* name and *phys\_symbols* names might be different. For example, the description for a keyboard that has English US engravings, but that is using Swiss German symbols might have a *phys\_symbols* name of "en\_US" and a *symbols* name of "de\_CH."

The *types* name provides some information about the set of key types (see section 15.2) that can be associated with the keyboard. In addition, each key type can have a name, and each shift level of a type can have a name. Although these names are stored in the map description with each of the types, they are accessed using the same methods as the other symbolic names.

The compat name provides some information about the rules used to bind actions to keys that are changed using core protocol requests.

Xkb provides symbolic names for each of the 4 keyboard groups, 16 virtual modifiers, 32 keyboard indicators, and 4 keyboard groups. These names are held in the *vmods*, *indicators*, and *groups* fixed-length arrays.

Each key has a four-byte symbolic name. All of the symbolic key names are held in the *keys* array, and *num\_keys* reports the number of entries that are in the keys array. For each key, the key name links keys with similar functions or in similar positions on keyboards that report different keycodes. For example, the **F1** key may emit keycode 23 on one keyboard and keycode 86 on another. By naming this key "FK01" on both keyboards, the keyboard layout designer can reuse parts of keyboard descriptions for different keyboards.

Key aliases allow the keyboard layout designer to assign multiple key names to a single key. This allows the keyboard layout designer to refer to keys using either their position or their "function". For example, a keyboard layout designer may wish to refer to the left arrow key on a PC keyboard using the ISO9995-5 positional specification of A31 or using the functional specification of LEFT. The  $key\_aliases$  field holds a variable-length array of real and alias key name pairs, and the total number of entries in the  $key\_aliases$  array is held in  $num\_key\_aliases$ . For each real and alias key name pair, the real field refers to the a name in the keys array, and the alias field refers to the alias for that key. Using the previous example, the keyboard designer may use the name A31 in the keys array, but also define the name LEFT as an alias for A31 in the  $key\_aliases$  array.

### **Note**

Key aliases defined in the geometry component of a keyboard mapping (see Chapter 13, *Keyboard Geometry*) override those defined in the keycodes component of the server database, which are stored in the XkbNamesRec (xkb->names). Therefore, consider the key aliases defined by the geometry before considering key aliases supplied by the XkbNamesRec.

A radio group is a set of keys whose behavior simulates a set of radio buttons. Once a key in a radio group is pressed, it stays logically depressed until another key in the group is pressed, at which point the previously depressed key is logically released. Consequently, at most one key in a radio group can be logically depressed at one time.

Each radio group in the keyboard description can have a name. These names are held in the variable-length array radio\_groups, and num\_rg tells how many elements are in the radio\_groups array.

## Symbolic Names Masks

Xkb provides several functions that work with symbolic names. Each of these functions uses a mask to specify individual fields of the structures described above. These masks and their relationships to the fields in a keyboard description are shown in Table 18.1.

**Table 18.1. Symbolic Names Masks** 

Mask Bit	Value	Keyboard Component	Field
XkbKeycodesNameMask	(1<<0)	Xkb->names	keycodes
XkbGeometryNameMask	(1<<1)	Xkb->names	geometry
XkbSymbolsNameMask	(1<<2)	Xkb->names	symbols
XkbPhysSymbolsNameMask	(1<<3)	Xkb->names	phys_symbols
XkbTypesNameMask	(1<<4)	Xkb->names	type
XkbCompatNameMask	(1<<5)	Xkb->names	compat
XkbKeyTypeNamesMask	(1<<6)	Xkb->map	type[*].name
XkbKTLevelNamesMask	(1<<7)	Xkb->map	type[*].lvl_names[*]
XkbIndicatorNamesMask	(1<<8)	Xkb->names	indicators[*]
XkbKeyNamesMask	(1<<9)	Xkb->names	keys[*], num_keys
XkbKeyAliasesMask	(1<<10)	Xkb->names	key_aliases[*], num_key_aliases
XkbVirtualModNamesMask	(1<<11)	Xkb->names	vmods[*]
XkbGroupNamesMask	(1<<12)	Xkb->names	groups[*]
XkbRGNamesMask	(1<<13)	Xkb->names	radio_groups[*], num_rg
XkbComponentNamesMask	(0x3f)	Xkb->names	keycodes,
			geometry,
			symbols,
			physical symbols,
			types, and
			compatibility map
XkbAllNamesMask	(0x3fff)	Xkb->names	all name components

## **Getting Symbolic Names From the Server**

To obtain symbolic names from the server, use XkbGetNames.

Status **XkbGetNames**(dpy, which, xkb);

dpy connection to the X server

which mask of names or map components to be updated

xkb keyboard description to be updated

XkbGetNames retrieves symbolic names for the components of the keyboard extension from the X server. The *which* parameter specifies the name components to be updated in the *xkb* parameter, and is the bitwise inclusive OR of the valid names mask bits defined in Table 18.1.

If the names field of the keyboard description xkb is NULL, XkbGetNames allocates and initializes the names component of the keyboard description before obtaining the values specified by which. If

the *names* field of xkb is not NULL, XkbGetNames obtains the values specified by which and copies them into the keyboard description xkb.

If the *map* component of the *xkb* parameter is NULL, XkbGetNames does not retrieve type or shift level names, even if XkbKeyTypeNamesMask or XkbKTLevelNamesMask are set in *which*.

XkbGetNames can return Success, or BadAlloc, BadLength, BadMatch, and BadImplementation errors.

To free symbolic names, use XkbFreeNames (see section 18.6)

### Changing Symbolic Names on the Server

To change the symbolic names in the server, first modify a local copy of the keyboard description and then use either XkbSetNames, or, to save network traffic, use a XkbNameChangesRec structure and call XkbChangeNames to download the changes to the server. XkbSetNames and XkbChangeNames can generate BadAlloc, BadAtom, BadLength, BadMatch, and BadImplementation errors.

```
Bool XkbSetNames(dpy, which, first_type, num_types, xkb);

dpy connection to the X server

which mask of names or map components to be changed

first_type first type whose name is to be changed

num_types number of types for which names are to be changed

keyboard description from which names are to be taken
```

Use XkbSetNames to change many names at the same time. For each bit set in which, XkbSetNames takes the corresponding value (or values in the case of arrays) from the keyboard description xkb and sends it to the server.

The <code>first\_type</code> and <code>num\_types</code> arguments are used only if XkbKeyTypeNamesMask or XkbKTLevelNamesMask is set in <code>which</code> and specify a subset of the types for which the corresponding names are to be changed. If either or both of these mask bits are set but the specified types are illegal, XkbSetNames returns False and does not update any of the names specified in <code>which</code>. The specified types are illegal if <code>xkb</code> does not include a map component or if <code>first\_type</code> and <code>num\_types</code> specify types that are not defined in the keyboard description.

### The XkbNameChangesRec Structure

The XkbNameChangesRec allows applications to identify small modifications to the symbolic names and effectively reduces the amount of traffic sent to the server:

```
typedef struct XkbNameChanges {
    unsigned int
                       changed;
                                           /* name components that have
                                              changed */
    unsigned char
                                           /* first key type with a new name */
                       first_type;
    unsigned char
                                           /* number of types with new names */
                       num types;
                                           /* first key type with new level
   unsigned char
                       first_lvl;
                                              names */
                       num lvls;
                                           /* number of key types with new
    unsigned char
                                              level names */
```

```
unsigned char
                       num_aliases;
                                           /* if key aliases changed,
                                              total number of key aliases */
    unsigned char
                                           /* if radio groups changed, total
                       num_rg;
                                              number of radio groups */
                                           /* first key with a new name */
    unsigned char
                       first_key;
    unsigned char
                       num keys;
                                           /* number of keys with new names */
    unsigned short
                       changed_vmods;
                                           /* mask of virtual modifiers
                                              for which names have changed */
                       changed_indicators;
                                             /* mask of indicators
    unsigned long
                                                for which names were changed */
    unsigned char
                                           /* mask of groups for
                       changed_groups;
                                              which names were changed */
} XkbNameChangesRec, *XkbNameChangesPtr;
```

The *changed* field specifies the name components that have changed and is the bitwise inclusive OR of the valid names mask bits defined in Table 18.1. The rest of the fields in the structure specify the ranges that have changed for the various kinds of symbolic names, as shown in Table 18.2.

Table 18.2. XkbNameChanges Fields

Mask	Fields	Component	Field
XkbKeyTypeNamesMask	first_type,	Xkb->map	type[*].name
XkbKTLevelNamesMask	num_types first_lvl,	Xkb->map	type[*].lvl_names[*]
	num_lvls		
XkbKeyAliasesMask	num_aliases	Xkb->names	key_aliases[*]
XkbRGNamesMask	num_rg	Xkb->names	radio_groups[*]
XkbKeyNamesMask	first_key,	Xkb->names	keys[*]
	num_keys		
XkbVirtual ModNames Mask	changed_vmods Xkb->names		vmods[*]
XkbIndicatorNamesMask	changed_indica	to <b>X</b> kb->names	indicators[*]
XkbGroupNamesMask	changed_group	s Xkb->names	groups[*]

XkbChangeNames provides a more flexible method for changing symbolic names than XkbSetNames and requires the use of an XkbNameChangesRec structure.

```
Bool XkbChangeNames (dpy, xkb, changes);

dpy connection to the X server

xkb keyboard description from which names are to be taken

changes names map components to be updated on the server
```

XkbChangeNames copies any names specified by *changes* from the keyboard description, xkb, to the X server specified by dpy. XkbChangeNames aborts and returns False if any illegal type names or type shift level names are specified by *changes*.

## **Tracking Name Changes**

Whenever a symbolic name changes in the server's keyboard description, the server sends a XkbNamesNotify event to all interested clients. To receive name notify events, use XkbSelectEvents (see section 4.3) with XkbNamesNotifyMask in both the bits\_to\_change and values\_for\_bits parameters.

To receive events for only specific names, use XkbSelectEventDetails. Set the event\_type parameter to XkbNamesNotify, and set both the bits\_to\_change and values\_for\_bits detail parameter to a mask composed of a bitwise OR of masks in Table 18.1.

The structure for the XkbNamesNotify event is defined as follows:

```
typedef struct {
    int
                                     /* Xkb extension base event code */
                    type;
                                     /* X server serial number for event */
    unsigned long
                    serial;
                                     /* True # synthetically generated */
    Bool
                    send_event;
    Display *
                    display;
                                     /* server connection where event generated */
                                     /* server time when event generated */
   Time
                    time;
    int
                    xkb_type;
                                     /* XkbNamesNotify */
                                     /* Xkb device ID, will not be
                    device;
    int
                                        XkbUseCoreKbd */
                                     /* mask of name components
    unsigned int
                    changed;
                                        that have changed */
    int
                    first_type;
                                     /* first key type with a new name */
                                     /* number of types with new names */
    int
                    num_types;
                    first_lvl;
    int
                                     /* first key type with new level names */
                                     /* number of key types with new level names */
    int
                    num_lvls;
    int
                    num aliases;
                                     /* if key aliases changed, total number
                                        of key aliases */
                                        /* if radio groups changed,
    int
                    num_radio_groups;
                                          total number of radio groups */
                                     /* mask of virtual modifiers for
    unsigned int
                    changed_vmods;
                                        which names have changed */
    unsigned int
                    changed_groups; /* mask of groups for
                                        which names were changed */
    unsigned int
                                          /* mask of indicators for which
                    changed_indicators;
                                               names were changed */
    int
                    first_key;
                                     /* first key with a new name */
                    num_keys;
                                     /* number of keys with new names */
    int
} XkbNamesNotifyEvent;
```

The *changed* field specifies the name components that have changed and is the bitwise inclusive OR of the valid names mask bits defined in Table 18.1. The other fields in this event are interpreted as the likenamed fields in an XkbNameChangesRec, as previously defined.

When your application receives a XkbNamesNotify event, you can note the changed names in a changes structure using XkbNoteNameChanges.

```
void XkbNoteNameChanges(old, new, wanted);

old XkbNameChangesRec structure to be updated

new event from which changes are to be copied

wanted types of names for which changes are to be noted
```

The wanted parameter is the bitwise inclusive OR of the valid names mask bits shown in Table 18.1. XkbNoteNameChanges copies any changes that are reported in new and specified in wanted into the changes record specified by old.

To update the local copy of the keyboard description with the actual values, pass to XkbGetNameChanges the results of one or more calls to XkbNoteNameChanges.

Status **XkbGetNameChanges**(dpy, xkb, changes);

dpy connection to the X server

*xkb* keyboard description to which names are copied

changes names components to be obtained from the server

XkbGetNameChanges examines the *changes* parameter, retrieves the necessary information from the server, and places the results into the *xkb* keyboard description.

XkbGetNameChanges can generate BadAlloc, BadImplementation, and BadMatch errors.

### **Allocating and Freeing Symbolic Names**

Most applications do not need to directly allocate symbolic names structures. Do not allocate a names structure directly using malloc or Xmalloc if your application changes the number of key aliases or radio groups or constructs a symbolic names structure without loading the necessary components from the X server. Instead use XkbAllocNames.

Status **XkbAllocNames**(xkb, which, num\_rg, num\_key\_aliases);

xkb keyboard description for which names are to be allocated

which mask of names to be allocated

num\_rg total number of radio group names needed

num\_key\_aliases total number of key aliases needed

XkbAllocNames can return BadAlloc, BadMatch, and BadValue errors. The which parameter is the bitwise inclusive OR of the valid names mask bits defined in Table 18.1.

Do not free symbolic names structures directly using free or XFree. Use XkbFreeNames instead.

void XkbFreeNames(xkb, which, free\_map);

xkb keyboard description for which names are to be freed

which mask of names components to be freed

 $free\_map$  True  $\Rightarrow$  XkbNamesRec structure itself should be freed

The which parameter is the bitwise inclusive OR of the valid names mask bits defined in Table 18.1.

# Chapter 19. Replacing a Keyboard "On the Fly"

Some operating system and X server implementations allow "hot plugging" of input devices. When using these implementations, input devices can be unplugged and new ones plugged in without restarting the software that is using those devices. There is no provision in the standard X server for notification of client programs if input devices are unplugged and/or new ones plugged in. In the case of the X keyboard, this could result in the X server having a keymap that does not match the new keyboard.

If the X server implementation supports the X input device extension, a client program may also change the X keyboard programmatically. The XChangeKeyboardDevice input extension request allows a client to designate an input extension keyboard device as the X keyboard, in which case the old X keyboard device becomes inaccessible except via the input device extension. In this case, core protocol MappingNotify and input extension XChangeDeviceNotify events are generated to notify all clients that a new keyboard with a new keymap has been designated.

When a client opens a connection to the X server, the server reports the minimum and maximum keycodes. The server keeps track of the minimum and maximum keycodes last reported to each client. When delivering events to a particular client, the server filters out any events that fall outside of the valid range for the client.

Xkb provides an XkbNewKeyboardNotify event that reports a change in keyboard geometry and/or the range of supported keycodes. The server can generate an XkbNewKeyboardNotify event when it detects a new keyboard or in response to an XkbGetKeyboardByName request that loads a new keyboard description. Selecting for XkbNewKeyboardNotify events allows Xkb-aware clients to be notified whenever a keyboard change occurs that may affect the keymap.

When a client requests XkbNewKeyboardNotify events, the server compares the range of keycodes for the current keyboard to the range of keycodes that are valid for the client. If they are not the same, the server immediately sends the client an XkbNewKeyboardNotify event. Even if the "new" keyboard is not new to the server, it is new to this particular client.

When the server sends an XkbNewKeyboardNotify event to a client to inform it of a new keycode range, it resets the stored range of legal keycodes for the client to the keycode range reported in the event; it does not reset this range for the client if it does not sent an XkbNewKeyboardNotify event to a client. Because Xkb-unaware clients and Xkb-aware clients that do not request XkbNewKeyboardNotify events are never sent these events, the server's notion of the legal keycode range never changes, and these clients never receive events from keys that fall outside of their notion of the legal keycode range.

Clients that have not selected to receive XkbNewKeyboardNotify events do, however, receive the XkbNewKeyboardNotify event when a keyboard change occurs. Clients that have not selected to receive this event also receive numerous other events detailing the individual changes that occur when a keyboard change occurs.

Clients wishing to track changes in min\_key\_code and max\_key\_code must watch for both XkbNewKeyboardNotify and XkbMapNotify events, because a simple mapping change causes an XkbMapNotify event and may change the range of valid keycodes, but does not cause an XkbNewKeyboardNotify event. If a client does not select for XkbNewKeyboardNotify events, the server restricts the range of keycodes reported to the client.

In addition to filtering out-of-range key events, Xkb:

• Adjusts core protocol MappingNotify events to refer only to keys that match the stored legal range.

- Reports keyboard mappings for keys that match the stored legal range to clients that issue a core protocol GetKeyboardMapping request.
- Reports modifier mappings only for keys that match the stored legal range to clients that issue a core protocol GetModifierMapping request.
- Restricts the core protocol ChangeKeyboardMapping and SetModifierMapping requests to keys that fall inside the stored legal range.

In short, Xkb does everything possible to hide from Xkb-unaware clients the fact that the range of legal keycodes has changed, because such clients cannot be expected to deal with them. Xkb events and requests are not modified in this manner; all Xkb events report the full range of legal keycodes. No requested Xkb events are discarded, and no Xkb requests have their keycode range clamped.

The structure for the XkbNewKeyboardNotify event is defined as follows:

```
typedef struct _XkbNewKeyboardNotify {
    int
                   type;
                                 /* Xkb extension base event code */
   unsigned long
                  serial;
                                /* X server serial number for event */
                               /* True # synthetically generated */
   Bool
                  send_event;
   Display *
                                /* server connection where event generated */
                  display;
                                 /* server time when event generated */
   Time
                  time;
    int
                  xkb_type;
                               /* XkbNewKeyboardNotify */
                                /* device ID of new keyboard */
    int
                  device;
                               /* device ID of old keyboard */
    int
                  old device;
                  min_key_code; /* min keycode of new keyboard */
    int
    int
                  max_key_code; /* max keycode of new keyboard */
    int
                  old_min_key_code; /* min keycode of old keyboard */
                  old_max_key_code; /* max keycode of old keyboard */
    int
   unsigned int
                  changed;
                                 /* changed aspects - see masks below */
                                 /* major request that caused change */
   char
                  req_major;
    char
                  req_minor;
                                 /* minor request that caused change */
} XkbNewKeyboardNotifyEvent;
```

To receive name notify events, use XkbSelectEvents (see section 4.3) with XkbNewKeyboardNotifyMask in both the bits\_to\_change and values\_for\_bits parameters. To receive events for only specific names, use XkbSelectEventDetails. Set the event\_type parameter to XkbNewKeyboardNotify, and set both the bits\_to\_change and values\_for\_bits detail parameter to a mask composed of a bitwise OR of masks in Table 19.1.

Table 19.1. XkbNewKeyboardNotifyEvent Details

XkbNewKeyboardNotify Event Details	Value	Circumstances
XkbNKN_KeycodesMask	(1L<<0)	Notification of keycode range changes wanted
XkbNKN_GeometryMask	(1L<<1)	Notification of geometry changes wanted
XkbNKN_DeviceIDMask	(1L<<2)	Notification of device ID changes wanted
XkbAllNewKeyboardEventsMask	(0x7)	Includes all of the above masks

The req\_major and req\_minor fields indicate what type of keyboard change has occurred.

If  $req\_major$  and  $req\_minor$  are zero, the device change was not caused by a software request to the server — a spontaneous change has occurred, such as hot-plugging a new device. In this case, device is the device identifier for the new, current X keyboard device, but no implementation-independent guarantee can be made about  $old\_device$ .  $old\_device$  may be identical to device (an implementor is permitted to reuse the device specifier when the device changes); or it may be different. Note that  $req\_major$  and  $req\_minor$  being zero do not necessarily mean that the physical keyboard device has changed; rather, they only imply a spontaneous change outside of software control (some systems have keyboards that can change personality at the press of a key).

If the keyboard change is the result of an X Input Extension ChangeKeyboardDevice request,  $req\_major$  contains the input extension major opcode, and  $req\_minor$  contains the input extension request number for X\_ChangeKeyboardDevice. In this case, device and  $old\_device$  are different, with device being the identifier for the new, current X keyboard device, and  $old\_device$  being the identifier for the former device.

If the keyboard change is the result of an XkbGetKeyboardByName function call, which generates an X\_kbGetKbdByName request,  $req\_major$  contains the Xkb extension base event code (see section 2.4), and  $req\_minor$  contains the event code for the Xkb extension request X\_kbGetKbdByName. device contains the device identifier for the new device, but nothing definitive can be said for  $old\_device$ ; it may be identical to device, or it may be different, depending on the implementation.

# Chapter 20. Server Database of Keyboard Components

The X server maintains a database of keyboard components, identified by component type. The database contains all the information necessary to build a complete keyboard description for a particular device, as well as to assemble partial descriptions. Table 20.1 identifies the component types and the type of information they contain.

**Table 20.1. Server Database Keyboard Components** 

<b>Component Type</b>	Component Primary Contents	May also contain	
Keymap	Complete keyboard description		
	Normally assembled using a complete component from each of the other types		
Keycodes	Symbolic name for each key	Aliases for some keys	
	Minimum and maximum legal keycodes	Symbolic names for indicators	
		Description of indicators physically present	
Types	Key types	Real modifier bindings and symbolic names for some virtual modifiers	
Compatibility	Rules used to assign actions to keysyms	Maps for some indicators	
		Real modifier bindings and symbolic names for some virtual modifiers	
Symbols	Symbol mapping for keyboard keys	Explicit actions and behaviors for some keys	
	Modifier mapping	Real modifier bindings and symbolic names for some virtual modifiers	
	Symbolic names for groups		
Geometry	Layout of the keyboard	Aliases for some keys; overrides keycodes component aliases	
		Symbolic names for some indicators	
		Description of indicators physically present	

While a keymap is a database entry for a complete keyboard description, and therefore logically different from the individual component database entries, the rules for processing keymap entries are identical to those for the individual components. In the discussion that follows, the term component is used to refer to either individual components or a keymap.

There may be multiple entries for each of the component types. An entry may be either *complete* or *partial*. Partial entries describe only a piece of the corresponding keyboard component and are designed to be combined with other entries of the same type to form a complete entry.

### Server Database of Keyboard Components

For example, a partial symbols map might describe the differences between a common ASCII keyboard and some national layout. Such a partial map is not useful on its own because it does not include those symbols that are the same on both the ASCII and national layouts (such as function keys). On the other hand, this partial map can be used to configure *any* ASCII keyboard to use a national layout.

When a keyboard description is built, the components are processed in the order in which they appear in Table 20.1; later definitions override earlier ones.

### **Component Names**

Component names have the form "class(member)" where class describes a subset of the available components for a particular type and the optional member identifies a specific component from that subset. For example, the name "atlantis(acme)" for a symbols component might specify the symbols used for the atlantis national keyboard layout by the vendor "acme." Each class has an optional default member — references that specify a class but not a member refer to the default member of the class, if one exists. Xkb places no constraints on the interpretation of the class and member names used in component names.

The *class* and *member* names are both specified using characters from the Latin-1 character set. Xkb implementations must accept all alphanumeric characters, minus ('-') and underscore ('\_') in class or member names, and must not accept parentheses, plus, vertical bar, percent sign, asterisk, question mark, or white space. The use of other characters is implementation-dependent.

## Listing the Known Keyboard Components

You may ask the server for a list of components for one or more component types. The request takes the form of a set of patterns, one pattern for each of the component types, including a pattern for the complete keyboard description. To obtain this list, use XkbListComponents.

<pre>XkbComponentListPtr max_inout);</pre>	${\tt XkbListComponents} ( dpy ,$	device_spec,	ptrns,
dpy	connection to X server		
device_spec	device ID, or XkbUseCoreKbd		
ptrns	namelist for components of interes	est	
max_inout	max # returned names, # left over		

XkbListComponents queries the server for a list of component names matching the patterns specified in ptrns. It waits for a reply and returns the matching component names in an XkbComponentListRec structure. When you are done using the structure, you should free it using XkbFreeComponentList. device\_spec indicates a particular device in which the caller is interested. A server is allowed (but not required) to restrict its reply to portions of the database that are relevant for that particular device.

ptrns is a pointer to an XkbComponentNamesRec, described below. Each of the fields in ptrns contains a pattern naming the components of interest. Each of the patterns is composed of characters from the ISO Latin1 encoding, but can contain only parentheses, the wildcard characters '?' and '\*', and characters permitted in a component class or member name (see section 20.1). A pattern may be NULL, in which case no components for that type is returned. Pattern matches with component names are case sensitive. The '?' wildcard matches any single character, except a left or right parenthesis; the '\*' wildcard matches any number of characters, except a left or right parenthesis. If an implementation allows additional characters in a component class or member name other than those required by the Xkb extension (see

section 20.1), the result of comparing one of the additional characters to either of the wildcard characters is implementation-dependent.

If a pattern contains illegal characters, the illegal characters are ignored. The matching process is carried out as if the illegal characters were omitted from the pattern.

max\_inout is used to throttle the amount of data passed to and from the server. On input, it specifies the maximum number of names to be returned (the total number of names in all component categories). Upon return from XkbListComponents, max\_inout contains the number of names that matched the request but were not returned because of the limit.

The component name patterns used to describe the request are passed to XkbListComponents using an XkbComponentNamesRec structure. This structure has no special allocation constraints or interrelationships with other structures; allocate and free this structure using standard malloc and free calls or their equivalent:

```
typedef struct _XkbComponentNames {
   char *
                 keymap;
                         /* keymap names */
   char *
                 keycodes; /* keycode names */
    char *
                 types;
                            /* type names */
                            /* compatibility map names */
   char *
                 compat;
   char *
                 symbols;
                            /* symbol names */
    char *
                 geometry;
                            /* geometry names */
} XkbComponentNamesRec, *XkbComponentNamesPtr;
```

XkbListComponents returns a pointer to an XkbComponentListRec:

```
typedef struct _XkbComponentList {
    int
                         num keymaps;
                                          /* number of entries in keymap */
    int
                         num_keycodes;
                                         /* number of entries in keycodes */
    int
                        num_types;
                                         /* number of entries in types */
                                         /* number of entries in compat */
    int
                        num compat;
    int
                        num symbols;
                                         /* number of entries in symbols */
                                          /* number of entries in geometry;
   int
                        num_geometry;
   XkbComponentNamePtr keymap;
                                          /* keymap names */
                                          /* keycode names */
   XkbComponentNamePtr keycodes;
                                          /* type names */
   XkbComponentNamePtr types;
   XkbComponentNamePtr compat;
                                          /* compatibility map names */
                                          /* symbol names */
   XkbComponentNamePtr symbols;
                                          /* geometry names */
   XkbComponentNamePtr geometry;
} XkbComponentListRec, *XkbComponentListPtr;
typedef struct _XkbComponentName {
   unsigned short
                         flags;
                                          /* hints regarding component name */
                                          /* name of component */
    char *
                         name;
} XkbComponentNameRec, *XkbComponentNamePtr;
```

Note that the structure used to specify patterns on input is an XkbComponentNamesRec, and that used to hold the individual component names upon return is an XkbComponentNameRec (no trailing 's' in Name).

When you are done using the structure returned by XkbListComponents, free it using XkbFreeComponentList.

```
void XkbFreeComponentList(list);
```

list

pointer to XkbComponentListRec to free

### **Component Hints**

A set of flags is associated with each component; these flags provide additional hints about the component's use. These hints are designated by bit masks in the flags field of the XkbComponentNameRec structures contained in the XkbComponentListRec returned from XkbListComponents. The least significant byte of the flags field has the same meaning for all types of keyboard components; the interpretation of the most significant byte is dependent on the type of component. The flags bits are defined in Table 20.2. The symbols hints in Table 20.2 apply only to partial symbols components (those with XkbLC\_Partial also set); full symbols components are assumed to specify all of the pieces.

The alphanumeric, modifier, keypad or function keys symbols hints should describe the primary intent of the component designer and should not be simply an exhaustive list of the kinds of keys that are affected. For example, national keyboard layouts affect primarily alphanumeric keys, but many affect a few modifier keys as well; such mappings should set only the XkbLC\_AlphanumericKeys hint. In general, symbols components should set only one of the four flags ( XkbLC\_AlternateGroup may be combined with any of the other flags).

Table 20.2. XkbComponentNameRec Flags Bits

<b>Component Type</b>	Component Hints (flags)	Meaning	Value
All Components	XkbLC_Hidden	Do not present to user	(1L<<0)
	XkbLC_Default	Default member of class	(1L<<1)
	XkbLC_Partial	Partial component	(1L<<2)
Keymap	none		
Keycodes	none		
Types	none		
Compatibility	none		
Symbols	XkbLC_AlphanumericKeys	Bindings primarily for alphanumeric keyboard section	(1L<<8)
	XkbLC_ModifierKeys	Bindings primarily for modifier keys	(1L<<9)
	XkbLC_KeypadKeys	Bindings primarily for numeric keypad keys	(1L<<10)
	XkbLC_FunctionKeys	Bindings primarily for function keys	(1L<<11)
	XkbLC_AlternateGroup	Bindings for an alternate group	(1L<<12)
Geometry	none		

## **Building a Keyboard Description Using the Server Database**

A client may request that the server fetch one or more components from its database and use those components to build a new server keyboard description. The new keyboard description may be built from

scratch, or it may be built starting with the current keyboard description for a particular device. Once the keyboard description is built, all or part of it may be returned to the client. The parts returned to the client need not include all of the parts used to build the description. At the time it requests the server to build a new keyboard description, a client may also request that the server use the new description internally to replace the current keyboard description for a specific device, in which case the behavior of the device changes accordingly.

To build a new keyboard description from a set of named components, and to optionally have the server use the resulting description to replace an active one, use XkbGetKeyboardByName.

XkbDescPtr XkbGetKeyboardByName(dpy, device\_spec, names, want, need, load);

dpy connection to X server

device\_spec device ID, or XkbUseCoreKbd

names of components to fetch

want desired structures in returned record

need mandatory structures in returned record

load True → load into device\_spec

names contains a set of expressions describing the keyboard components the server should use to build the new keyboard description. want and need are bit fields describing the parts of the resulting keyboard description that should be present in the returned XkbDescRec.

The individual fields in names are component expressions composed of keyboard component names (no wildcarding as may be used in XkbListComponents), the special component name symbol '%', and the special operator characters '+' and '|'. A component expression is parsed left to right, as follows:

- The special component name "computed" may be used in *keycodes* component expressions and refers to a component consisting of a set of keycodes computed automatically by the server as needed.
- The special component name "canonical" may be used in *types* component expressions and refers to a partial component defining the four standard key types: *ALPHABETIC*, *ONE\_LEVEL*, *TWO\_LEVEL*, and *KEYPAD*.
- The special component name '%' refers to the keyboard description for the device specified in device\_spec or the keymap names component. If a keymap names component is specified that does not begin with '+' or '|' and does not contain '%', then '%' refers to the description generated by the keymap names component. Otherwise, it refers to the keyboard description for device\_spec.
- The '+' operator specifies that the following component should *override* the currently assembled description; any definitions that are present in both components are taken from the second.
- The '|' operator specifies that the next specified component should *augment* the currently assembled description; any definitions that are present in both components are taken from the first.
- If the component expression begins with an operator, a leading '%' is implied.
- If any unknown or illegal characters appear anywhere in the expression, the entire expression is invalid and is ignored.

For example, if names->symbols contained the expression "+de", it specifies that the default member of the "de" class of symbols should be applied to the current keyboard mapping, overriding any existing definitions (it could also be written "+de(default)").

Here is a slightly more involved example: the expression "acme(ascii)+de(basic)|iso9995-3" constructs a German (de) mapping for the ASCII keyboard supplied by the "acme" vendor. The new definition begins with the symbols for the ASCII keyboard for Acme (acme(ascii)), overrides them with definitions for the basic German keyboard (de(basic)), and then applies the definitions from the default iso9995-3 keyboard (iso9995-3) to any undefined keys or groups of keys (part three of the iso9995 standard defines a common set of bindings for the secondary group, but allows national layouts to override those definitions where necessary).

#### Note

The interpretation of the above expression components (acme, ascii, de, basic, iso9995-3) is not defined by Xkb; only the operations and their ordering are.

Note that the presence of a keymap names component that does not contain '%' (either explicit or implied by virtue of an expression starting with an operator) indicates a description that is independent of the keyboard description for the device specified in <code>device\_spec</code>. The same is true of requests in which the keymap names component is empty and all five other names components contain expressions void of references to '%'. Requests of this form allow you to deal with keyboard definitions independent of any actual device.

The server parses all non-NULL fields in names and uses them to build a keyboard description. However, before parsing the expressions in names, the server ORs the bits in want and need together and examines the result in relationship to the expressions in names. Table 20.3 identifies the components that are required for each of the possible bits in want or need. If a required component has not been specified in the names structure (the corresponding field is NULL), the server substitutes the expression "%", resulting in the component values being taken from device\_spec. In addition, if load is True, the server modifies names if necessary (again using a "%" entry) to ensure all of the following fields are non-NULL: types, keycodes, symbols, and compat.

Table 20.3. Want and Need Mask Bits and Required Names Components

want or need mask bit	Required names Components	value
XkbGBN_TypesMask	Types	(1L<<0)
XkbGBN_CompatMapMask	Compat	(1L<<1)
XkbGBN_ClientSymbolsMask	Types + Symbols + Keycodes	(1L<<2)
XkbGBN_ServerSymbolsMask	Types + Symbols + Keycodes	(1L<<3)
XkbGBN_SymbolsMask	Symbols	(1L<<1)
XkbGBN_IndicatorMapMask	Compat	(1L<<4)
XkbGBN_KeyNamesMask	Keycodes	(1L<<5)
XkbGBN_GeometryMask	Geometry	(1L<<6)
XkbGBN_OtherNamesMask	Types + Symbols + Keycodes + Compat + Geometry	(1L<<7)
XkbGBN_AllComponentsMask		(0xff)


need specifies a set of keyboard components that the server must be able to resolve in order for XkbGetKeyboardByName to succeed; if any of the components specified in need cannot be successfully resolved, XkbGetKeyboardByName fails.

want specifies a set of keyboard components that the server should attempt to resolve, but that are not mandatory. If the server is unable to resolve any of these components, XkbGetKeyboardByName still succeeds. Bits specified in want that are also specified in need have no effect in the context of want.

If <code>load</code> is True, the server updates its keyboard description for <code>device\_spec</code> to match the result of the keyboard description just built. If load is False, the server's description for device <code>device\_spec</code> is not updated. In all cases, the parts specified by <code>want</code> and <code>need</code> from the just-built keyboard description are returned.

The names structure in an XkbDescRec keyboard description record (see Chapter 18, Symbolic Names) contains one field for each of the five component types used to build a keyboard description. When a keyboard description is built from a set of database components, the corresponding fields in this names structure are set to match the expressions used to build the component.

The entire process of building a new keyboard description from the server database of components and returning all or part of it is diagrammed in Figure 20.1:



The information returned to the client in the XkbDescRec is essentially the result of a series of calls to extract information from a fictitious device whose description matches the one just built. The calls corresponding to each of the mask bits are summarized in Table 20.4, together with the XkbDescRec components that are filled in.

Table 20.4. XkbDescRec Components Returned for Values of Want & Needs

Request (want+need)	Fills in Xkb components	<b>Equivalent Function Call</b>
XkbGBN_TypesMask	map.types	XkbGetUpdatedMap(dpy, XkbTypesMask, Xkb)
XkbGBN_ServerSymbolsMask	server	XkbGetUpdatedMap(dpy, XkbAllClientInfoMask, Xkb)
XkbGBN_ClientSymbolsMask	map, including map.types	XkbGetUpdatedMap(dpy, XkbAllServerInfoMask, Xkb)
XkbGBN_IndicatorMaps	indicators	XkbGetIndicatorMap(dpy, XkbAllIndicators, Xkb)
XkbGBN_CompatMapMask	compat	XkbGetCompatMap(dpy, XkbAllCompatMask, Xkb)
XkbGBN_GeometryMask	geom	XkbGetGeometry(dpy, Xkb)
XkbGBN_KeyNamesMask	names.keys	XkbGetNames(dpy, XkbKeyNamesMask
	names.key_aliases	XkbKeyAliasesMask, Xkb)
XkbGBN_OtherNamesMask	names.keycodes	XkbGetNames(dpy, XkbAllNamesMask &
	names.geometry	(VILLE N
	names.symbols	~(XkbKeyNamesMask   XkbKeyAliasesMask),
	names.types	Xkb)
	map.types[*].lvl_names[*]	
	names.compat	
	names.vmods	
	names.indicators	
	names.groups	
	names.radio_groups	
	names.phys_symbols	

There is no way to determine which components specified in want (but not in need) were actually fetched, other than breaking the call into successive calls to XkbGetKeyboardByName and specifying individual components.

XkbGetKeyboardByName always sets  $min\_key\_code$  and  $max\_key\_code$  in the returned XkbDescRec structure.

XkbGetKeyboardByName is synchronous; it sends the request to the server to build a new keyboard description and waits for the reply. If successful, the return value is non-NULL.

 ${\tt XkbGetKeyboardByName\ generates\ a\ BadMatch\ protocol\ error\ if\ errors\ are\ encountered\ when\ building\ the\ keyboard\ description.}$ 

If you simply want to obtain information about the current keyboard device, rather than generating a new keyboard description from elements in the server database, use XkbGetKeyboard (see section 6.2).

XkbDescPtr XkbGetKeyboard(dpy, which, device\_spec);

dpy connection to X server

which mask of components of XkbDescRec of interest

device\_spec device ID

XkbGetKeyboard is used to read the current description for one or more components of a keyboard device. It calls XkbGetKeyboardByName as follows:

XkbGetKeyboardByName (dpy, device\_spec, NULL, which, which, False).

# Chapter 21. Attaching Xkb Actions to X Input Extension Devices

The X input extension allows an X server to support multiple keyboards, as well as other input devices, in addition to the core X keyboard and pointer. The input extension categorizes devices by grouping them into classes. Keyboards and other input devices with keys are classified as KeyClass devices by the input extension. Other types of devices supported by the input extension include, but are not limited to: mice, tablets, touchscreens, barcode readers, button boxes, trackballs, identifier devices, data gloves, and eye trackers. Xkb provides additional control over all X input extension devices, whether they are KeyClass devices or not, as well as the core keyboard and pointer.

If an X server implements support for both the input extension and Xkb, the server implementor determines whether interaction between Xkb and the input extension is allowed. Implementors are free to restrict the effects of Xkb to only the core X keyboard device or allow interaction between Xkb and the input extension.

Several types of interaction between Xkb and the input extension are defined by Xkb. Some or all may be allowed by the X server implementation.

Regardless of whether the server allows interaction between Xkb and the input extension, the following access is provided:

- Xkb functionality for the core X keyboard device and its mapping is accessed via the functions described in the other chapters of this specification.
- Xkb functionality for the core X pointer device is accessed via the XkbGetDeviceInfo and XkbSetDeviceInfo functions described in this chapter.

If all types of interaction are allowed between Xkb and the input extension, the following additional access is provided:

- If allowed, Xkb functionality for additional KeyClass devices supported by the input extension is
  accessed via those same functions.
- If allowed, Xkb functionality for non- KeyClass devices supported by the input extension is also accessed via the XkbGetDeviceInfo and XkbSetDeviceInfo functions described in this chapter.

Each device has an X Input Extension device ID. Each device may have several classes of feedback. For example, there are two types of feedbacks that can generate bells: bell feedback and keyboard feedback (BellFeedbackClass). A device can have more than one feedback of each type; the feedback ID identifies the particular feedback within its class.

A keyboard feedback has:

- Auto-repeat status (global and per key)
- 32 LEDs
- A bell

An indicator feedback has:

• Up to 32 LEDs

If the input extension is present and the server allows interaction between the input extension and Xkb, then the core keyboard, the core keyboard indicators, and the core keyboard bells may each be addressed using an appropriate device spec, class, and ID. The constant XkbDfltXIId may be used as the device ID to specify the core keyboard indicators for the core indicator feedback. The particular device ID corresponding to the core keyboard feedback and the core indicator feedback may be obtained by calling XkbGetDeviceInfo and specifying XkbUseCoreKbd as the device\_spec; the values will be returned in dflt\_kbd\_fb and dflt\_led\_fb.

If the server does not allow Xkb access to input extension KeyClass devices, attempts to use Xkb requests with those devices fail with a BadKeyboard error. Attempts to access non- KeyClass input extension devices via XkbGetDeviceInfo and XkbSetDeviceInfo fail silently if Xkb access to those devices is not supported by the X server.

#### XkbDeviceInfoRec

Information about X Input Extension devices is transferred between a client program and the Xkb extension in an XkbDeviceInfoRec structure:

```
typedef struct {
                                    /* name for device */
   char *
                    name;
                                    /* name for class of devices */
   Atom
                    type;
                                    /* device of interest */
   unsigned short
                    device_spec;
   Bool
                    has_own_state; /* True # this device has
                                       its own state */
                                    /* bits indicating supported capabilities */
   unsigned short
                    supported;
                                    /* bits indicating unsupported capabilities */
   unsigned short
                    unsupported;
   unsigned short
                    num_btns;
                                    /* number of entries in btn acts */
                                    /* button actions */
   XkbAction *
                    btn_acts;
                                    /* total number of entries in LEDs vector */
   unsigned short
                    sz_leds;
                                    /* number of valid entries in LEDs vector */
   unsigned short
                    num_leds;
                                    /* input extension ID of default
   unsigned short
                    dflt_kbd_fb;
                                       (core kbd) indicator */
   unsigned short
                                    /* input extension ID of default
                    dflt_led_fb;
                                       indicator feedback */
   XkbDeviceLedInfoPtr leds;
                                    /* LED descriptions */
} XkbDeviceInfoRec, *XkbDeviceInfoPtr;
typedef struct {
   unsigned short
                                    /* class for this LED device */
                    led_class;
   unsigned short
                                    /* ID for this LED device */
                    led_id;
   unsigned int
                    phys_indicators; /* bits for which LEDs physically present */
   unsigned int
                    maps_present; /* bits for which LEDs have maps in maps */
                    names_present; /* bits for which LEDs are in names */
   unsigned int
   unsigned int
                                    /* 1 bit # corresponding LED is on */
                    state;
   Atom
                    names[XkbNumIndicators]; /* names for LEDs */
                                    /* indicator maps for each LED */
   XkbIndicatorMapRec
                        maps;
} XkbDeviceLedInfoRec, *XkbDeviceLedInfoPtr;
```

The type field is a registered symbolic name for a class of devices (for example, "TABLET"). If a device is a keyboard (that is, is a member of KeyClass), it has its own state, and has\_own\_state is True. If has\_own\_state is False, the state of the core keyboard is used. The supported and unsupported fields are masks where each bit indicates a capability. The meaning of the mask bits is listed in Table 21.1, together with the fields in the XkbDeviceInfoRec structure that are associated with the capability

represented by each bit. The same bits are used to indicate the specific information desired in many of the functions described subsequently in this section.

Table 21.1. XkbDeviceInfoRec Mask Bits

Name	XkbDeviceInfoRec Fields Effected	Value	Capability If Set
XkbXI_KeyboardsMask		(1L << 0)	Clients can use all Xkb requests and events with KeyClass devices supported by the input device extension.
XkbXI_ButtonActionsMask	num_btns btn_acts	(1L <<1)	Clients can assign key actions to buttons on non- KeyClass input extension devices.
XkbXI_IndicatorNamesMask	leds->names	(1L <<2)	Clients can assign names to indicators on non- KeyClass input extension devices.
XkbXI_IndicatorMapsMask	leds->maps	(1L <<3)	Clients can assign indicator maps to indicators on non-KeyClass input extension devices.
XkbXI_IndicatorStateMask	leds->state	(1L <<4)	Clients can request the status of indicators on non- KeyClass input extension devices.
XkbXI_IndicatorsMask	sz_leds	(0x1c)	XkbXI_IndicatorNames- Mask
	num_leds leds->*		XkbXI_IndicatorMaps- Mask
			XkbXI_IndicatorState- Mask
XkbXI_UnsupportedFeaturesMask	unsupported	(1L <<15)	
XkbXI_AllDeviceFeaturesMask	Those selected by Value column masks	(0x1e)	XkbXI_IndicatorsMask
	Column masks		XkbXI_ButtonActions- Mask
XkbXI_AllFeaturesMask	Those selected by Value column masks	(0x1f)	XkbXI_AllDevice- FeaturesMask
			XkbXI_KeyboardsMask
XkbXI_AllDetailsMask	Those selected by Value column masks	(0x801f)	XkbXI_AllFeaturesMask
			XkbXI_Unsupported- FeaturesMask

The name, type, has\_own\_state, supported, and unsupported fields are always filled in when a valid reply is returned from the server involving an XkbDeviceInfoRec. All of the other fields are modified only if the particular function asks for them.

## **Querying Xkb Features for Non-KeyClass Input Extension Devices**

To determine whether the X server allows Xkb access to particular capabilities of input devices other than the core X keyboard, or to determine the status of indicator maps, indicator names or button actions on a non-KeyClass extension device, use XkbGetDeviceInfo.

XkbDeviceInfoPtr XkbGetDeviceInfo(dpy, which, device\_spec, ind\_class, ind\_id);

dpy connection to X server

which mask indicating information to return

device\_spec device ID, or XkbUseCoreKbd

ind\_class feedback class for indicator requests

ind id feedback ID for indicator requests

XkbGetDeviceInfo returns information about the input device specified by device\_spec. Unlike the device\_spec parameter of most Xkb functions, device\_spec does not need to be a keyboard device. It must, however, indicate either the core keyboard or a valid X Input Extension device.

The *which* parameter is a mask specifying optional information to be returned. It is an inclusive OR of one or more of the values from Table 21.1 and causes the returned XkbDeviceInfoRec to contain values for the corresponding fields specified in the table.

The XkbDeviceInfoRec returned by XkbGetDeviceInfo always has values for name (may be a null string, ""), type, supported, unsupported, has\_own\_state, dflt\_kbd\_fb, and dflt\_led\_fb. Other fields are filled in as specified by which.

Upon return, the *supported* field will be set to the inclusive OR of zero or more bits from Table 21.1; each bit set indicates an optional Xkb extension device feature supported by the server implementation, and a client may modify the associated behavior.

If the XkbXI\_ButtonActionsMask bit is set in which, the XkbDeviceInfoRec returned will have the button actions (btn\_acts field) filled in for all buttons.

If which includes one of the bits in XkbXI\_IndicatorsMask, the feedback class of the indicators must be specified in ind\_class, and the feedback ID of the indicators must be specified in ind\_id. If the request does not include any of the bits in XkbXI\_IndicatorsMask, the ind\_class and ind\_id parameters are ignored. The class and ID can be obtained via the input device extension XListInputDevices request.

If any of the XkbXI\_IndicatorsMask bits are set in which, the XkbDeviceInfoRec returned will have filled in the portions of the leds structure corresponding to the indicator feedback identified by ind\_class and ind\_id. The leds vector of the XkbDeviceInfoRec is allocated if necessary and sz\_leds and num\_leds filled in. The led\_class, led\_id and phys\_indicators fields of the leds entry corresponding to ind\_class and ind\_id are always filled in. If which contains XkbXI\_IndicatorNamesMask, the names\_present and names fields of the leds structure

corresponding to <code>ind\_class</code> and <code>ind\_id</code> are returned. If <code>which</code> contains XkbXI\_IndicatorStateMask, the corresponding <code>state</code> field is updated. If <code>which</code> contains XkbXI\_IndicatorMapsMask, the <code>maps present</code> and <code>maps</code> fields are updated.

Xkb provides convenience functions to request subsets of the information available via XkbGetDeviceInfo. These convenience functions mirror some of the mask bits. The functions all take an XkbDeviceInfoPtr as an input argument and operate on the X Input Extension device specified by the <code>device\_spec</code> field of the structure. Only the parts of the structure indicated in the function description are updated. The XkbDeviceInfoRec structure used in the function call can be obtained by calling XkbGetDeviceInfo or can be allocated by calling XkbAllocDeviceInfo (see section 21.3).

These convenience functions are described as follows.

To query the button actions associated with an X Input Extension device, use XkbGetDeviceButtonActions.

Status **XkbGetDeviceButtonActions**(dpy, device\_info, all\_buttons, first\_button, num\_buttons);

dpy connection to X server

device\_info structure to update with results

all\_buttons True  $\rightarrow$  get information for all buttons

first button number of first button for which info is desired

num buttons number of buttons for which info is desired

XkbGetDeviceButtonActions queries the server for the desired button information for the device indicated by the <code>device\_spec</code> field of <code>device\_info</code> and waits for a reply. If successful, XkbGetDeviceButtonActions backfills the button actions (<code>btn\_acts</code> field of <code>device\_info</code>) for only the requested buttons, updates the <code>name</code>, <code>type</code>, <code>supported</code>, and <code>unsupported</code> fields, and returns Success.

all\_buttons, first\_button and num\_buttons specify the device buttons for which actions should be returned. Setting all\_buttons to True requests actions for all device buttons; if all\_buttons is False, first\_button and num\_buttons specify a range of buttons for which actions are requested.

If a compatible version of Xkb is not available in the server or the Xkb extension has not been properly initialized, XkbGetDeviceButtonActions returns BadAccess. If allocation errors occur, a BadAlloc status is returned. If the specified device (device\_info->device\_spec) is invalid, a BadKeyboard status is returned. If the device has no buttons, a BadMatch status is returned. If first\_button and num\_buttons specify illegal buttons, a BadValue status is returned.

To query the indicator names, maps, and state associated with an LED feedback of an input extension device, use XkbGetDeviceLedInfo.

Status **XkbGetDeviceLedInfo**(dpy, device\_info, led\_class, led\_id, which);

dpy connection to X server

device info structure to update with results

led\_class LED feedback class assigned by input extension

led\_id LED feedback ID assigned by input extension

which mask indicating desired information

XkbGetDeviceLedInfo queries the server for the desired LED information for the feedback specified by <code>led\_class</code> and <code>led\_id</code> for the X input extension device indicated by <code>device\_spec>device\_info</code> and waits for a reply. If successful, <code>XkbGetDeviceLedInfo</code> backfills the relevant fields of <code>device\_info</code> as determined by <code>which</code> with the results and returns Success. Valid values for <code>which</code> are the inclusive OR of any of <code>XkbXI\_IndicatorNamesMask</code>, <code>XkbXI\_IndicatorMapsMask</code>, and <code>XkbXI\_IndicatorStateMask</code>.

The fields of <code>device\_info</code> that are filled in when this request succeeds are <code>name</code>, <code>type</code>, <code>supported</code>, and <code>unsupported</code>, and portions of the <code>leds</code> structure corresponding to <code>led\_class</code> and <code>led\_id</code> as indicated by the bits set in <code>which</code>. The <code>device\_info->leds</code> vector is allocated if necessary and <code>sz\_leds</code> and <code>num\_leds</code> filled in. The <code>led\_class</code>, <code>led\_id</code> and <code>phys\_indicators</code> fields of the <code>device\_info->leds</code> entry corresponding to <code>led\_class</code> and <code>led\_id</code> are always filled in.

If which contains XkbXI\_IndicatorNamesMask, the names\_present and names fields of the device\_info->leds structure corresponding to led\_class and led\_id are updated, if which contains XkbXI\_IndicatorStateMask, the corresponding state field is updated, and if which contains XkbXI\_IndicatorMapsMask, the maps\_present and maps fields are updated.

If a compatible version of Xkb is not available in the server or the Xkb extension has not been properly initialized, XkbGetDeviceLedInfo returns BadAccess. If allocation errors occur, a BadAlloc status is returned. If the device has no indicators, a BadMatch error is returned. If ledClass or ledID have illegal values, a BadValue error is returned. If they have legal values but do not specify a feedback that contains LEDs and is associated with the specified device, a BadMatch error is returned.

## Allocating, Initializing, and Freeing the XkbDeviceInfoRec Structure

To obtain an XkbDeviceInfoRec structure, use XkbGetDeviceInfo or XkbAllocDeviceInfo.

XkbDeviceInfoPtr XkbAllocDeviceInfo(device\_spec, n\_buttons, sz\_leds);

device spec device ID with which structure will be used

n\_buttons number of button actions to allocate space for

sz\_leds number of LED feedbacks to allocate space for

XkbAllocDeviceInfo allocates space for an XkbDeviceInfoRec structure and initializes that structure's device\_spec field with the device ID specified by device\_spec. If n\_buttons is nonzero, n\_buttons XkbActions are linked into the XkbDeviceInfoRec structure and initialized to zero. If sz\_leds is nonzero, sz\_leds XkbDeviceLedInfoRec structures are also allocated and linked into the XkbDeviceInfoRec structure. If you request XkbDeviceLedInfoRec structures be allocated using this request, you must initialize them explicitly.

To obtain an XkbDeviceLedInfoRec structure, use XkbAllocDeviceLedInfo.

Status XkbAllocDeviceLedInfo(device\_info, num\_needed);

device\_info structure in which to allocate LED space

num\_needed number of indicators to allocate space for

XkbAllocDeviceLedInfo allocates space for an XkbDeviceLedInfoRec and places it in device\_info. If num\_needed is nonzero, num\_needed XkbIndicatorMapRec structures are also allocated and linked into the XkbDeviceLedInfoRec structure. If you request XkbIndicatorMapRec structures be allocated using this request, you must initialize them explicitly. All other fields are initialized to zero.

To initialize an XkbDeviceLedInfoRec structure, use XkbAddDeviceLedInfo.

 XkbDeviceLedInfoPtr
 XkbAddDeviceLedInfo(device\_info, led\_class, led\_id);

 device\_info
 structure in which to add LED info

 led\_class
 input extension class for LED device of interest

 led\_id
 input extension ID for LED device of interest

XkbAddDeviceLedInfo first checks to see whether an entry matching  $led\_class$  and  $led\_id$  already exists in the  $device\_info->leds$  array. If it finds a matching entry, it returns a pointer to that entry. Otherwise, it checks to be sure there is at least one empty entry in  $device\_info->leds$  and extends it if there is not enough room. It then increments  $device\_info->num\_leds$  and fills in the next available entry in  $device\_info->leds$  with  $led\_class$  and  $led\_id$ .

If successful, XkbAddDeviceLedInfo returns a pointer to the XkbDeviceLedInfoRec structure that was initialized. If unable to allocate sufficient storage, or if <code>device\_info</code> points to an invalid XkbDeviceInfoRec structure, or if <code>led\_class</code> or <code>led\_id</code> are inappropriate, XkbAddDeviceLedInfo returns NULL.

To allocate additional space for button actions in an XkbDeviceInfoRec structure, use XkbResizeDeviceButtonActions.

Status XkbResizeDeviceButtonActions(device\_info, new\_total);

device\_infostructure in which to allocate button actionsnew\_totalnew total number of button actions needed

XkbResizeDeviceButtonActions reallocates space, if necessary, to make sure there is room for a total of <code>new\_total</code> button actions in the <code>device\_info</code> structure. Any new entries allocated are zeroed. If successful, XkbResizeDeviceButtonActions returns Success. If new\_total is zero, all button actions are deleted, <code>device\_info->num\_btns</code> is set to zero, and <code>device\_info->btn\_acts</code> is set to NULL. If device\_info is invalid or new\_total is greater than 255, BadValue is returned. If a memory allocation failure occurs, a BadAlloc is returned.

To free an XkbDeviceInfoRec structure, use XkbFreeDeviceInfo.

void XkbFreeDeviceInfo(device\_info, which, free\_all);

device\_info pointer to XkbDeviceInfoRec in which to free items

which mask of components of device\_info to free

free\_all True \_\_ free everything, including device\_info

If free\_all is True, the XkbFreeDeviceInfo frees all components of device\_info and the XkbDeviceInfoRec structure pointed to by device\_info itself. If free\_all is False, the value of which determines which subcomponents are freed. which is an inclusive OR of one or more of the values from Table 21.1. If which contains XkbXI\_ButtonActionsMask, all button actions

associated with <code>device\_info</code> are freed, <code>device\_info->btn\_acts</code> is set to NULL, and <code>device\_info->num\_btns</code> is set to zero. If which contains all bits in XkbXI\_IndicatorsMask, all XkbDeviceLedInfoRec structures associated with <code>device\_info</code> are freed, <code>device\_info->leds</code> is set to NULL, and <code>device\_info->sz\_leds</code> and <code>device\_info->num\_leds</code> are set to zero. If which contains XkbXI\_IndicatorMapsMask, all indicator maps associated with <code>device\_info</code> are cleared, but the number of LEDs and the leds structures themselves are preserved. If which contains XkbXI\_IndicatorNamesMask, all indicator names associated with <code>device\_info</code> are cleared, but the number of LEDs and the leds structures themselves are preserved. If which contains XkbXI\_IndicatorStateMask, the indicator state associated with the <code>device\_info</code> leds are set to zeros but the number of LEDs and the leds structures themselves are preserved.

## Setting Xkb Features for Non-KeyClass Input Extension Devices

The Xkb extension allows clients to assign any key action to either core pointer or input extension device buttons. This makes it possible to control the keyboard or generate keyboard key events from extension devices or from the core pointer.

Key actions assigned to core X pointer buttons or input extension device buttons cause key events to be generated as if they had originated from the core X keyboard.

Xkb implementations are required to support key actions for the buttons of the core pointer device, but support for actions on extension devices is optional. Implementations that do not support button actions for extension devices must not set the XkbXI\_ButtonActionsMask bit in the supported field of an XkbDeviceInfoRec structure.

If a client attempts to modify valid characteristics of a device using an implementation that does not support modification of those characteristics, no protocol error is generated. Instead, the server reports a failure for the request; it also sends an XkbExtensionDeviceNotify event to the client that issued the request if the client has selected to receive these events.

To change characteristics of an X Input Extension device in the server, first modify a local copy of the device structure and then use either XkbSetDeviceInfo, or, to save network traffic, use an XkbDeviceChangesRec structure (see section 21.6) and call XkbChangeDeviceInfo to download the changes to the server.

To modify some or all of the characteristics of an X Input Extension device, use XkbSetDeviceInfo.

Bool **XkbSetDeviceInfo**(dpy, which, device\_info);

dpy connection to X server

which mask indicating characteristics to modify

device\_info structure defining the device and modifications

XkbSetDeviceInfo sends a request to the server to modify the characteristics of the device specified in the <code>device\_info</code> structure. The particular characteristics modified are identified by the bits set in <code>which</code> and take their values from the relevant fields in <code>device\_info</code> (see Table 21.1). XkbSetDeviceInfo returns True if the request was successfully sent to the server. If the X server implementation does not allow interaction between the X input extension and the Xkb Extension, the function does nothing and returns False.

The which parameter specifies which aspects of the device should be changed and is a bitmask composed of an inclusive OR or one or more of the following bits: XkbXI\_ButtonActionsMask,

XkbXI\_IndicatorNamesMask, XkbXI\_IndicatorMapsMask. If the features requested to be manipulated in *which* are valid for the device, but the server does not support assignment of one or more of them, that particular portion of the request is ignored.

If the device specified in <code>device\_info->device\_spec</code> does not contain buttons and a request affecting buttons is made, or the device does not contain indicators and a request affecting indicators is made, a BadMatch protocol error results.

If the XkbXI\_ButtonActionsMask bit is set in the supported mask returned by XkbGetDeviceInfo, the Xkb extension allows applications to assign key actions to buttons on input extension devices other than the core keyboard device. If the XkbXI\_ButtonActionsMask is set in which, the actions for all buttons specified in device\_info are set to the XkbActions specified in device\_info->btn\_acts. If the number of buttons requested to be updated is not valid for the device, XkbSetDeviceInfo returns False and a BadValue protocol error results.

If the XkbXI\_IndicatorMapsMask and / or XkbXI\_IndicatorNamesMask bit is set in the supported mask returned by XkbGetDeviceInfo, the Xkb extension allows applications to assign maps and / or names to the indicators of nonkeyboard extension devices. If supported, maps and / or names can be assigned to all extension device indicators, whether they are part of a keyboard feedback or part of an indicator feedback.

If the XkbXI\_IndicatorMapsMask and / or XkbXI\_IndicatorNamesMask flag is set in which, the indicator maps and / or names for all device\_info->num\_leds indicator devices specified in device\_info->leds are set to the maps and / or names specified in device\_info->leds. device\_info->leds-led\_class and led\_id specify the input extension class and device ID for each indicator device to modify; if they have invalid values, a BadValue protocol error results and XkbSetDeviceInfo returns False. If they have legal values but do not specify a keyboard or indicator class feedback for the device in question, a BadMatch error results. If any of the values in device\_info->leds->names are not a valid Atom or None, a BadAtom protocol error results.

Xkb provides convenience functions to modify subsets of the information accessible via XkbSetDeviceInfo. Only the parts of the structure indicated in the function description are modified. These convenience functions are described as follows.

To change only the button actions for an input extension device, use XkbSetDeviceButtonActions.

Bool **XkbSetDeviceButtonActions**(dpy, device\_info, first\_button, num buttons);

dpy connection to X server

device\_info structure defining the device and modifications

first\_button number of first button to update, 0 relative

num buttons number of buttons to update

XkbSetDeviceButtonActions assigns actions to the buttons of the device specified in device\_info>device\_spec. Actions are assigned to num\_buttons buttons beginning with first\_button and are taken from the actions specified in device\_info->btn\_acts.

If the server does not support assignment of Xkb actions to extension device buttons, XkbSetDeviceButtonActions has no effect and returns False. If the device has no buttons or if first\_button or num\_buttons specify buttons outside of the valid range as determined by device\_info->num\_btns, the function has no effect and returns False. Otherwise, XkbSetDeviceButtonActions sends a request to the server to change the actions for the specified buttons and returns True.

If the actual request sent to the server involved illegal button numbers, a BadValue protocol error is generated. If an invalid device identifier is specified in device\_info->device\_spec, a BadKeyboard protocol error results. If the actual device specified in device\_info->device\_spec does not contain buttons and a request affecting buttons is made, a BadMatch protocol error is generated.

### XkbExtensionDeviceNotify Event

The Xkb extension generates XkbExtensionDeviceNotify events when the status of an input extension device changes or when an attempt is made to use an Xkb feature that is not supported by a particular device.

#### Note

Events indicating an attempt to use an unsupported feature are delivered only to the client requesting the event.

To track changes to the status of input extension devices or attempts to use unsupported features of a device, select to receive XkbExtensionDeviceNotify events by calling either XkbSelectEvents or XkbSelectEventDetails (see section 4.3).

To receive XkbExtensionDeviceNotify events under all possible conditions, call XkbSelectEvents and pass XkbExtensionDeviceNotifyMask in both bits\_to\_change and values\_for\_bits.

The XkbExtensionDeviceNotify event has no event details. However, you can call XkbSelectEventDetails using XkbExtensionDeviceNotify as the event\_type and specifying XkbAllExtensionDeviceEventsMask in bits\_to\_change and values\_for\_bits. This has the same effect as a call to XkbSelectEvents.

The structure for XkbExtensionDeviceNotify events is:

```
typedef struct {
                                    /* Xkb extension base event code */
    int
                   type;
    unsigned long
                   serial;
                                    /* X server serial number for event */
                                    /* True # synthetically generated */
    Bool
                   send_event;
                                    /* server connection where event generated */
    Display *
                   display;
                                    /* server time when event generated */
   Time
                   time;
                                    /* XkbExtensionDeviceNotifyEvent */
    int
                   xkb_type;
                                    /* Xkb device ID, will not be XkbUseCoreKbd */
    int
                   device;
                                    /* reason for the event */
    unsigned int
                   reason;
    unsigned int
                   supported;
                                    /* mask of supported features */
    unsigned int
                                    /* unsupported features this client
                   unsupported;
                                       attempted to use */
                                    /* first button that changed */
    int
                   first_btn;
                   num btns;
                                    /* number of buttons that changed */
                                    /* indicators with names or maps */
                   leds_defined;
    unsigned int
    unsigned int
                   led_state;
                                    /* current state of the indicators */
                                    /* feedback class for LED changes */
    int
                   led_class;
                                    /* feedback ID for LED changes */
    int
                   led_id;
} XkbExtensionDeviceNotifyEvent;
```

The XkbExtensionDeviceNotify event has fields enabling it to report changes in the state (on/off) of all of the buttons for a device, but only for one LED feedback associated with a device. You will get multiple events when more than one LED feedback changes state or configuration.

### **Tracking Changes to Extension Devices**

Changes to an Xkb extension device may be tracked by listening to XkbExtensionDeviceNotify events and accumulating the changes in an XkbDeviceChangesRec structure. The changes noted in the structure may then be used in subsequent operations to update either a server configuration or a local copy of an Xkb extension device configuration. The changes structure is defined as follows:

```
typedef struct _XkbDeviceChanges {
                                  /* bits indicating what has changed */
   unsigned int
                    changed;
   unsigned short first_btn;
                                  /* number of first button which changed,
                                     if any */
   unsigned short num_btns;
                                  /* number of buttons that have changed */
   XkbDeviceLedChangesRec leds;
} XkbDeviceChangesRec, *XkbDeviceChangesPtr;
typedef struct _XkbDeviceLedChanges {
   unsigned short led_class;
                                  /* class of this indicator feedback bundle */
   unsigned short led id;
                                  /* ID of this indicator feedback bundle */
                                  /* bits indicating which names have changed */
   unsigned int
                    names;
                                  /* bits indicating which maps have changed */
   unsigned int
                    maps;
   struct _XkbDeviceLedChanges *next; /* link to indicator change record
                                          for next set */
} XkbDeviceLedChangesRec, *XkbDeviceLedChangesPtr;
```

A local description of the configuration and state of a device may be kept in an XkbDeviceInfoRec structure. The actual state or configuration of the device may change because of XkbSetDeviceInfo and XkbSetButtonActions requests made by clients or by user interaction with the device. The X server sends an XkbExtensionDeviceNotify event to all interested clients when the state of any buttons or indicators or the configuration of the buttons or indicators on the core keyboard or any input extension device changes. The event reports the state of indicators for a single indicator feedback, and the state of up to 128 buttons. If more than 128 buttons or more than one indicator feedback are changed, the additional buttons and indicator feedbacks are reported in subsequent events. Xkb provides functions with which you can track changes to input extension devices by noting the changes that were made and then requesting the changed information from the server.

To note device changes reported in an XkbExtensionDeviceNotify event, use XkbNoteDeviceChanges.

```
void XkbNoteDeviceChanges (old, new, wanted);

old structure tracking state changes

new event indicating state changes

wanted mask indicating changes to note
```

The wanted field specifies the changes that should be noted in old, and is composed of the bitwise inclusive OR of one or more of the masks from Table 21.1. The reason field of the event in new indicates the types of changes the event is reporting. XkbNoteDeviceChanges updates the XkbDeviceChangesRec specified by old with the changes that are both specified in wanted and contained in new->reason.

To update a local copy of the state and configuration of an X input extension device with the changes previously noted in an XkbDeviceChangesRec structure, use XkbGetDeviceInfoChanges.

To query the changes that have occurred in the button actions or indicator names and indicator maps associated with an input extension device, use XkbGetDeviceInfoChanges.

Status **XkbGetDeviceInfoChanges**(dpy, device\_info, changes);

dpy connection to X server

device\_info structure to update with results

changes contains notes of changes that have occurred

The changes->changed field indicates which attributes of the device specified in *changes->device* have changed. The parameters describing the changes are contained in the other fields of *changes*. XkbGetDeviceInfoChanges uses that information to call XkbGetDeviceInfo to obtain the current status of those attributes that have changed. It then updates the local description of the device in *device\_info* with the new information.

To update the server's description of a device with the changes noted in an XkbDeviceChangesRec, use XkbChangeDeviceInfo.

Bool **XkbChangeDeviceInfo**(dpy, device\_info, changes);

dpy connection to X server

device\_info local copy of device state and configuration

changes note specifying changes in device\_info

XkbChangeDeviceInfo updates the server's description of the device specified in <code>device\_info-device\_spec</code> with the changes specified in <code>changes</code> and contained in <code>device\_info</code>. The update is made by an XkbSetDeviceInfo request.

## **Chapter 22. Debugging Aids**

The debugging aids are intended for use primarily by Xkb implementors and are optional in any implementation.

There are two bitmasks that may be used to control debugging. One bitmask controls the output of debugging information, and the other controls behavior. Both bitmasks are initially all zeros.

To change the values of any of the debug controls, use XkbSetDebuggingFlags.

Bool **XkbSetDebuggingFlags**(display, mask, flags, msg, ctrls\_mask, ctrls, ret\_flags, ret\_ctrls);

display connection to X server

mask selecting debug output flags to change

flags values for debug output flags selected by mask

msg message to print right now

ctrls\_mask mask selecting debug controls to change

ctrls values for debug controls selected by ctrls\_mask

ret\_flags resulting state of all debug output flags

ret\_ctrls resulting state of all debug controls

XkbSetDebuggingFlags modifies the debug output flags as specified by mask and flags, modifies the debug controls flags as specified by ctrls\_mask and ctrls, prints the message msg, and backfills ret\_flags and ret\_ctrls with the resulting debug output and debug controls flags.

When bits are set in the debug output masks, mask and flags, Xkb prints debug information corresponding to each bit at appropriate points during its processing. The device to which the output is written is implementation-dependent, but is normally the same device to which X server error messages are directed; thus the bits that can be set in mask and flags is implementation-specific. To turn on a debug output selection, set the bit for the output in the mask parameter and set the corresponding bit in the flags parameter. To turn off event selection for an event, set the bit for the output in the mask parameter and do not set the corresponding bit in the flags parameter.

When bits are set in the debug controls masks, ctrls\_mask and ctrls, Xkb modifies its behavior according to each controls bit. ctrls\_mask and ctrls are related in the same way that mask and flags are. The valid controls bits are defined in Table 22.1.

**Table 22.1. Debug Control Masks** 

<b>Debug Control Mask</b>	Value	Meaning
XkbDF_DisableLocks	(1 << 0)	Disable actions that lock modifiers

XkbSetDebuggingFlags returns True if successful and False otherwise. The only protocol error it may generate is BadAlloc, if for some reason it is unable to allocate storage.

XkbSetDebuggingFlags is intended for developer use and may be disabled in production X servers. If it is disabled, XkbSetDebuggingFlags has no effect and does not generate any protocol errors.



## **Glossary**

Allocator Xkb provides functions, known as allocators, to create and initialize Xkb data

structures.

Audible Bell An audible bell is the sound generated by whatever bell is associated with the

keyboard or input extension device, as opposed to any other audible sound

generated elsewhere in the system.

Autoreset Controls The autoreset controls configure the boolean controls to automatically be enabled

or disabled at the time a program exits.

Base Group The group in effect as a result of all actions other than a previous lock or latch

request; the base group is transient. For example, the user pressing and holding a group shift key that shifts to Group2 would result in the base group being group 2

at that point in time. Initially, base group is always Group1.

Base Modifiers Modifiers that are turned on as a result of some actions other than previous lock

or latch requests; base modifiers are transient. For example, the user pressing and holding a key bound to the Shift modifier would result in Shift being a base

modifier at that point in time.

Base Event Code A number assigned by the X server at run time that is assigned to the extension

to identify events from that extension.

Base State The base group and base modifiers represent keys that are physically or logically

down; these constitute the base state.

Boolean Controls Global keyboard controls that may be selectively enabled and disabled under

program control and that may be automatically set to an on or off condition upon

client program exit.

Canonical Key Types The canonical key types are predefined key types that describe the types of keys

available on most keyboards. The definitions for the canonical key types are held in the first XkbNumRequiredTypes entries of the *types* field of the client map

and are indexed using the following constants:

• XkbOneLevelIndex

• XkbTwoLevelIndex

XkbAlphabeticIndex

XkbKeypadIndex

Client Map The key mapping information needed to convert arbitrary keycodes to symbols.

Compat Name The *compat* name is a string that provides some information about the rules used

to bind actions to keys that are changed using core protocol requests.

Compatibility State When an Xkb-extended X server connects to an Xkb-unaware client, the

compatibility state remaps the keyboard group into a core modifier whenever

possible.

Compatibility Grab State The grab state that results from applying the compatibility map to the Xkb grab

state.

Compatibility Map

The definition of how to map core protocol keyboard state to Xkb keyboard state.

Component Expression

An expression used to describe server keyboard database components to be loaded. It describes the order in which the components should be loaded and the rules by which duplicate attributes should be resolved.

Compose Processing

The process of mapping a series of keysyms to a string is known as compose processing.

Consumed Modifier

Xkb normally consumes modifiers in determining the appropriate symbol for an event, that is, the modifiers are not considered during any of the later stages of event processing. For those rare occasions when a modifier *should* be considered despite having been used to look up a symbol, key types include an optional *preserve* field.

Core Event

An event created from the core X server.

Detectable Auto-Repeat

Detectable auto-repeat allows a client to detect an auto-repeating key. If a client requests and the server supports detectable auto-repeat, Xkb generates KeyRelease events only when the key is physically released. Thus the client receives a number of KeyPress events for that key without intervening KeyRelease events until the key is finally released, when a KeyRelease event is received.

Effective Group

The effective group is the arithmetic sum of the locked, latched, and base groups. The effective keyboard group is always brought back into range depending on the value of the *GroupsWrap* control for the keyboard. If an event occurs with an effective group that is legal for the keyboard as a whole, but not for the key in question, the group *for that event only* is normalized using the algorithm specified by the *group\_info* member of the key symbol map (XkbSymMapRec).

Effective Mask

An Xkb modifier definition consists of a set of bit masks corresponding to the eight real modifiers; a similar set of bitmasks corresponding to the 16 named virtual modifiers; and an effective mask. The effective mask represents the set of all real modifiers that can logically be set either by setting any of the real modifiers or by setting any of the virtual modifiers in the definition.

Effective Modifier

The effective modifiers are the bitwise union of the base, latched and locked modifiers.

**Extension Device** 

Any keyboard or other input device recognized by the X input extension.

Global Keyboard Controls

Controls that affect the way Xkb generates key events. The controls affect all keys, as opposed to per-key controls that are for a single key. Global controls include

- · RepeatKeys Control
- · DetectableAuto-repeat
- SlowKeys
- · BounceKeys
- · StickyKeys
- MouseKeys
- MouseKeysAccel

- AccessXKeys
- · AccessXTimeout
- AccessXFeedback
- · Overlay1
- Overlay2
- · EnabledControls

See Keysym Group

of the grab group and the grab modifiers.

Grab State

Group

Group Index A number used as the internal representation for a group number. Group1 through

Group 4 have indices of 0 through 3.

Groups Wrap Control If a group index exceeds the maximum number of groups permitted for the specified keyboard, it is wrapped or truncated back into range as specified by the

global *GroupsWrap* control. *GroupsWrap* can have the following values:

The grab state is the state used when matching events to passive grabs. It consists

WrapIntoRange ClampIntoRange RedirectIntoRange

Key Type An attribute of a key that identifies which modifiers affect the shift level of a key

and the number of groups on the key.

Key Width The maximum number of shift levels in any group for the key type associated with

a key.

Keysym Group A keysym group is a logical state of the keyboard providing access to a collection

of characters. A group usually contains a set of characters that logically belong together and that may be arranged on several shift levels within that group. For example, Group1 could be the English alphabet, and Group2 could be Greek. Xkb supports up to four different groups for an input device or keyboard. Groups are in the range 1–4 (Group1–Group4), and are often referred to as G1–G4 and indexed

as 0-3.

Indicator An indicator is a feedback mechanism such as an LED on an input device. Using

Xkb, a client application can determine the names of the various indicators, determine and control the way that the individual indicators should be updated to reflect keyboard changes, and determine which of the 32 keyboard indicators

reported by the protocol are actually present on the keyboard.

Indicator Feedback An indicator feedback describes the state of a bank of up to 32 lights. It has a mask

where each bit corresponds to a light and an associated value mask that specifies

which lights are on or off.

Indicator Map An indicator has its own set of attributes that specify whether clients can explicitly

set its state and whether it tracks the keyboard state. The indicator map is the collection of these attributes for each indicator and is held in the *maps* array,

which is an array of XkbIndicatorRec structures.

Input Extension

An extension to the core X protocol that allows an X server to support multiple keyboards, as well as other input devices, in addition to the core X keyboard and pointer. Other types of devices supported by the input extension include, but are not limited to: mice, tablets, touchscreens, barcode readers, button boxes, trackballs, identifier devices, data gloves, and eye trackers.

Key Action

A key action consists of an operator and some optional data. Once the server has applied the global controls and per-key behavior and has decided to process a key event, it applies key actions to determine the effects of the key on the internal state of the server. Xkb supports actions that do the following:

- · Change base, latched, or locked modifiers or group
- Move the core pointer or simulate core pointer button events
- Change most aspects of keyboard behavior
- · Terminate or suspend the server
- · Send a message to interested clients
- Simulate events on other keys

Key Alias

A key alias is a symbolic name for a specific physical key. Key aliases allow the keyboard layout designer to assign multiple key names to a single key. This allows the keyboard layout designer to refer to keys using either their position or their "function". Key aliases can be specified both in the symbolic names component and in the keyboard geometry. Both sets of aliases are always valid, but key alias definitions in the keyboard geometry have priority; if both symbolic names and geometry include aliases, you should consider the definitions from the geometry before considering the definitions from the symbolic names section.

Key Behavior

The behaviors field of the server map is an array of XkbBehavior, indexed by keycode, and contains the behavior for each key. The X server uses key behavior to determine whether to process or filter out any given key event; key behavior is independent of keyboard modifier or group state. Each key has exactly one behavior.

Key behaviors include:

- · XkbKB Default
- XkbKB\_Lock
- XkbKB\_RadioGroup
- XkbKB\_Overlay1
- XkbKB\_Overlay2

Key Symbol Map

A key symbol map describes the symbols bound to a key and the rules to be used to interpret those symbols. It is an array of XkbSymMapRec structures indexed by keycode.

Key Type

Key types are used to determine the shift level of a key given the current state of the keyboard. There is one key type for each group for a key. Key types are defined using the XkbKeyTypeRec and XkbKTMapEntryRec structures. Xkb

allows up to XkbMaxKeyTypes (255) key types to be defined, but requires at least XkbNumRequiredTypes (4) predefined types to be in a key map.

keyboard bell. Some input devices may have more than one bell, identified by

bell\_class and bell\_id.

Keyboard Components There are five types of components stored in the X server database of keyboard

components. They correspond to the >symbols, geometry, keycodes,

compat, and types symbolic names associated with a keyboard.

Keyboard Feedback A keyboard feedback includes the following:

Keyclick volume Bell volume Bell pitch Bell duration Global auto-repeat Per key auto-repeat

32 LEDs

Key Width, Key Type Width

The maximum number of shift levels for a type is referred to as the width of a

key type.

Keyboard Geometry Keyboard geometry describes the physical appearance of the keyboard, including

the shape, location, and color of all keyboard keys or other visible keyboard components such as indicators and is stored in a XkbGeometryRec structure. The information contained in a keyboard geometry is sufficient to allow a client

program to draw an accurate two-dimensional image of the keyboard.

Keyboard Geometry Name The keyboard geometry name describes the physical location, size, and shape of

the various keys on the keyboard and is part of the XkbNamesRec structure.

Keyboard State Keyboard state encompasses all of the transitory information necessary to map a

physical key press or release to an appropriate event.

Keycode A numeric value returned to the X server when a key on a keyboard is pressed or

released, indicating which key is being modulated. Keycode numbers are in the range 1 <= keycode <= max, where max is the number of physical keys on the

device.

Keycode Name

The keycode name describes the range and meaning of the keycodes returned by

the keyboard and is part of the XkbNamesRec structure.

Latched Group A latched group is a group index that is combined with the base and locked group

to form the effective group. It applies only to the next key event that does not change the keyboard state. The latched group can be changed by keyboard activity

or via Xkb extension library functions.

Latched Modifier Latched modifiers are the set of modifiers that are combined with the base

modifiers and the locked modifiers to form the effective modifiers. It applies only

to the next key event that does not change the keyboard state.

LED A light emitting diode. However, for the purposes of the X keyboard extension

specification, a LED is any form of visual two-state indicator that is either on or

off.

Locked Group A locked group is a group index that is combined with the base and latched group

to form the effective group. When a group is locked, it supersedes any previous locked group and remains the locked group for all future key events, until a new group is locked. The locked group can be changed by keyboard activity or via Xkb

extension library functions.

Locked Modifiers Locked modifiers are the set of modifiers that are combined with the base

modifiers and the latched modifiers to form the effective modifiers. A locked

modifier applies to all future key events until it is explicitly unlocked.

Lookup State The lookup state is composed of the lookup group and the lookup modifiers, and

it is the state an Xkb-capable or Xkb-aware client should use to map a keycode

to a keysym.

Modifier A modifier is a logical condition that is either set or unset. The modifiers control

the Shift Level selected when a key event occurs. Xkb supports the core protocol eight modifiers (Shift, Lock, Control, and Mod1 through Mod5), called the *real* modifiers. In addition, Xkb extends modifier flexibility by providing a set of sixteen named virtual modifiers, each of which can be bound to any set of the

eight real modifiers.

Modifier Key A modifier key is a key whose operation has no immediate effect, but that, for as

long as it is held down, modifies the effect of other keys. A modifier key may be,

for example, a shift key or a control key.

Modifier Definition An Xkb modifier definition, held in an XkbModsRec, consists of a set of real

modifiers, a set of virtual modifiers, and an effective mask. The mask is the union of the real modifiers and the set of real modifiers to which the virtual modifiers

map; the mask cannot be explicitly changed.

Nonkeyboard Extension

Device

An input extension device that is not a keyboard. Other types of devices supported by the input extension include, but are not limited to: mice, tablets, touchscreens, barcode readers, button boxes, trackballs, identifier devices, data gloves, and eye

trackers.

Outlines An outline is a list of one or more points that describes a single closed polygon,

used in the geometry specification for a keyboard.

Physical Indicator Mask

The physical indicator mask is a field in the XkbIndicatorRec that indicates

which indicators are bound to physical LEDs on the keyboard; if a bit is set in *phys\_indicators*, then the associated indicator has a physical LED associated with it. This field is necessary because some indicators may not have

corresponding physical LEDs on the keyboard.

Physical Symbol Keyboard

Name

The *symbols* keyboard name identifies the symbols logically bound to the keys. The symbols name is a human or application-readable description of the intended local control of the bound with these symbols. The plant was a local control of the local control of

locale or usage of the keyboard with these symbols. The *phys\_symbols* keyboard name, on the other hand, identifies the symbols actually engraved on

the keyboard.

Preserved Modifier Xkb normally consumes modifiers in determining the appropriate symbol for an

event, that is, the modifiers are not considered during any of the later stages of event processing. For those rare occasions when a modifier *should* be considered despite having been used to look up a symbol, key types include an optional *preserve* field. If a modifier is present in the *preserve* list, it is a preserved

modifier.

Radio Group A radio group is a set of keys whose behavior simulates a set of radio buttons.

Once a key in a radio group is pressed, it stays logically depressed until another key in the group is pressed, at which point the previously depressed key is logically released. Consequently, at most one key in a radio group can be logically depressed

at one time.

Real Modifier Xkb supports the eight core protocol modifiers (Shift, Lock, Control, and Mod1

through Mod5); these are called the *real* modifiers, as opposed to the set of sixteen named virtual modifiers that can be bound to any set of the eight real modifiers.

Server Internal Modifiers Modifiers that the server uses to determine the appropriate symbol for an event;

internal modifiers are normally consumed by the server.

Shift Level One of several states (normally 2 or 3) governing which graphic character is

produced when a key is actuated.

Symbol Keyboard Name The symbols keyboard name identifies the symbols logically bound to the keys.

The symbols name is a human or application-readable description of the intended locale or usage of the keyboard with these symbols. The <code>phys\_symbols</code> keyboard name, on the other hand, identifies the symbols actually engraved on

the keyboard.

Symbolic Name Xkb supports symbolic names for most components of the keyboard extension.

Most of these symbolic names are grouped into the names component of the

keyboard description.

State Field The portion of a client-side core protocol event that holds the modifier, group, and

button state information pertaining to the event.

Types Name The *types* name provides some information about the set of key types that can be

associated with the keyboard. In addition, each key type can have a name, and

each shift level of a type can have a name.

Valuator A valuator reports a range of values for some entity, like a mouse axis, a slider,

or a dial.

Virtual Modifier Xkb provides a set of sixteen named virtual modifiers that can be bound to any set

of the eight real modifiers. Each virtual modifier can be bound to any set of the

real modifiers (Shift, Lock, Control, and Mod1 – Mod5).

Virtual Modifier Mapping Xkb maintains a virtual modifier mapping, which lists the virtual modifiers

associated with each key.

Xkb-aware Client A client application that initializes Xkb extension and is consequently bound to

an Xlib that includes the Xkb extension.

Xkb-capable Client A client application that makes no Xkb extension Xlib calls but is bound to an

Xlib that includes the Xkb extension.

Xkb-unaware Client A client application that makes no Xkb extension Xlib calls and is bound to an

Xlib that does not include the Xkb extension.

#### XkbMapNotify, 129 Index XkbNamesNotify, 198 XkbNewKeyboardNotify, 201 XkbStateNotify, 24 Α action modifiers, 153 G audible bell, 48 grab group, 21 auto-repeat grab modifiers, 21 controls, 58 grab state, 21 detectable, 59 group auto-reset mask, 56 base, 20 effective, 20 B grab, 21 BadAccess, 7 ISO9995, 20 BadKeyboard, 9 keysym, 20, 23 base group, 20 lookup, 21 base modifiers, 20 radio, 3 bell, 48 group compatibility map, 182 audible, 48 boolean controls, 54 indicators, 34 C K changes data structures, 12 client map, 122, 133 keyboard description, 2 compose processing, 86 keysym groups, 20, 23 controls, 54 boolean, 54 library, 85 level, 122 non-boolean, 54 library controls, 85 server, 54 lookup group, 21 lookup modifiers, 21 D lookup state, 21 detectable auto-repeat, 59 M Ε map effective group, 20 client, 122, 133 effective modifiers, 20 group compatibility, 182 server, 122, 149 errors, 4, 9 BadAccess, 7 mask BadKeyboard, 9 auto-reset, 56 event, 15 events, 14 MappingNotify, 87, 90 real modifiers, 22 mask, 15 modifier definition, 21 NewKeyboardNotify, 87 modifiers, 20 XkbAccessXNotify, 66 action, 153 XkbActionMessage, 167 base, 20 XkbAnyEvent, 15 effective, 20 XkbCompatMapNotify, 190 grab, 21 XkbControlsNotify, 81 lookup, 21 XkbEvent, 18 names, 32 XkbExtensionDeviceNotify, 223 real, 22, 30 XkbIndicatorMapNotify, 45 virtual, 30

XkbIndicatorStateNotify, 45

virtual mapping, 31

N	XkbAllocGeomOverlayKeys, 119
non-boolean controls, 54	XkbAllocGeomOverlayRows, 119
non boolean controls, 54	XkbAllocGeomOverlays, 118
R	XkbAllocGeomPoints, 116
	XkbAllocGeomProps, 115
radio group, 3	XkbAllocGeomRows, 118
real modifiers, 22, 30	XkbAllocGeomSectionDoodads, 120
	XkbAllocGeomSections, 117
S	XkbAllocGeomShapes, 117
server controls, 54	XkbAllocIndicatorMaps, 47
server map, 122, 149	XkbAllocKeyboard, 29
shift level, 122	XkbAllocNames, 200
state	XkbAllocServerMap, 131
grab, 21	XkbAnyAction, 152
lookup, 21	XkbAnyEvent, 15
	XkbApplyCompatMapToKey, 189
V	XkbBehavior, 173
valuator, 170	XkbBell, 50
virtual modifier mapping, 31	XkbBellEvent, 52
virtual modifiers, 30	XkbChangeControls, 81
virtual modificis, 50	XkbChangeDeviceInfo, 225
V	XkbChangeEnabledControls, 56
X	XkbChangeIndicators, 45
Xkb-aware client, 21	XkbChangeMap, 128
Xkb-capable client, 21	XkbChangeNames, 198
XkbAccessXNotifyEvent, 66	XkbChangeTypesOfKey, 145
XkbAction, 151	XkbClientMapRec, 134
XkbActionCtrls, 166	XkbCompatMapNotifyEvent, 190
XkbActionMessageEvent, 167	XkbCompatMapRec, 181
XkbAddDeviceLedInfo, 220	XkbComponentListRec, 206
XkbAddGeomColor, 111	XkbComponentNameRec, 206
XkbAddGeomDoodad, 113	XkbComponentNamesRec, 206
XkbAddGeomKey, 112	XkbComputeRowBounds, 110
XkbAddGeomKeyAlias, 111	XkbComputeSectionBounds, 110
XkbAddGeomOutline, 112	XkbComputeShapeBounds, 109
XkbAddGeomOverlay, 113	XkbComputeShapeTop, 109
XkbAddGeomOverlayKey, 114	XkbControlsChangesRec, 80
XkbAddGeomOverlayRow, 113	XkbControlsNotifyEvent, 81
XkbAddGeomProperty, 111	XkbControlsRec, 73
XkbAddGeomRow, 113	XkbCopyKeyType, 140
XkbAddGeomSection, 112	XkbCopyKeyTypes, 141
XkbAddGeomShape, 112	XkbCtrlsAction, 165
XkbAddSymInterpret, 190	XkbDescRec, 27
XkbAllocClientMap, 130	XkbDeviceBell, 50
XkbAllocCompatMap, 191	XkbDeviceBellEvent, 51
XkbAllocControls, 83	XkbDeviceBtnAction, 169
XkbAllocDeviceInfo, 219	XkbDeviceChangesRec, 224
XkbAllocDeviceLedInfo, 219	XkbDeviceInfoRec, 215
XkbAllocGeomColors, 116	XkbDeviceLedChangesRec, 224
XkbAllocGeomDoodads, 120	XkbDeviceLedInfoRec, 215
XkbAllocGeometry, 120	XkbDeviceValuatorAction, 170
XkbAllocGeomKeyAliases, 116	XkbEvent, 18
XkbAllocGeomKeys, 115	XkbExtensionDeviceNotifyEvent, 223
XkhAllocGeomOutlines 114	XkhFindOverlayForKey 110

XkbForceBell, 52 XkbForceDeviceBell, 52 XkbFreeClientMap, 131 XkbFreeCompatMap, 191 XkbFreeComponentList, 206

XkbFreeControls, 83
XkbFreeDeviceInfo, 220
XkbFreeGeomColors, 116
XkbFreeGeomDoodads, 120
XkbFreeGeometry, 120
XkbFreeGeomKeyAliases, 116
XkbFreeGeomKeys, 115
XkbFreeGeomOutlines, 114

XkbFreeGeomOverlayKeys, 119 XkbFreeGeomOverlayRows, 119 XkbFreeGeomOverlays, 118 XkbFreeGeomPoints, 117 XkbFreeGeomProperties, 115 XkbFreeGeomSections, 118 XkbFreeGeomSections, 118 XkbFreeGeomShapes, 117 XkbFreeIndicatorMaps, 47 XkbFreeKeyboard, 29

XkbGeometryRec, 95 XkbGetAccessXTimeout, 64 XkbGetAutoRepeatRate, 58 XkbGetAutoResetControls, 56 XkbGetBounceKeysDelay, 69 XkbGetCompatMap, 187 XkbGetControls, 79

XkbFreeNames, 200

XkbFreeServerMap, 132

XkbGetControlsChanges, 82 XkbGetDetectableAutorepeat, 59 XkbGetDeviceButtonActions, 218

XkbGetDeviceInfo, 217

XkbGetDeviceInfoChanges, 225 XkbGetDeviceLedInfo, 218 XkbGetGeometry, 108 XkbGetIndicatorChanges, 46 XkbGetIndicatorMap, 41 XkbGetIndicatorState, 40 XkbGetKeyActions, 171 XkbGetKeyBehaviors, 174 XkbGetKeyboard, 28, 28 XkbGetKeyboardByName, 208

XkbGetKeyExplicitComponents, 176 XkbGetKeyModifierMap, 147 XkbGetKeySyms, 145 XkbGetKeyTypes, 139

XkbGetKeyVirtualModMap, 178

XkbGetMap, 124

XkbGetNameChanges, 200 XkbGetNamedDeviceIndicator, 41 XkbGetNamedGeometry, 109 XkbGetNamedIndicator, 42 XkbGetNames, 196

XkbGetPerClientControls, 83

XkbGetSlowKeysDelay, 68

XkbGetState, 24

XkbGetStickyKeysOptions, 70 XkbGetUpdatedMap, 125 XkbGetVirtualMods, 177 XkbGetXlibControls, 88 XkbGroupAction, 155 XkbIgnoreExtension, 9 XkbIndicatorChangesRec, 45 XkbIndicatorMapNotifyEvent, 45

XkbIndicatorMapRec, 35 XkbIndicatorRec, 34

XkbIndicatorStateNotifyEvent, 45 XkbInitCanonicalKeyTypes, 139

XkbISOAction, 161
XkbKeyAction, 151
XkbKeyActionEntry, 151
XkbKeyActionsPtr, 151
XkbKeyActionsPtr, 151
XkbKeyAliasRec, 193
XkbKeyCodeToKeysym, 91
XkbKeyGroupInfo, 143
XkbKeyGroupSWidth, 144
XkbKeyGroupWidth, 144
XkbKeyHasActions, 150
XkbKeyNameRec, 193
XkbKeyNumActions, 151
XkbKeyNumGroups, 143
XkbKeyNumGroups, 144
XkbKeySymEntry, 145

XkbKeySymsOffset, 144 XkbKeySymsPtr, 144 XkbKeysymToModifiers, 92 XkbKeyType, 142 XkbKeyTypeIndex, 142 XkbKeyTypeRec, 135

XkbKeyTypesForCoreSymbols, 188

XkbKTMapEntryRec, 135 XkbLatchGroup, 23 XkbLatchModifiers, 23 XkbLibraryVersion, 7 XkbListComponents, 205 XkbLockGroup, 23 XkbLockModifiers, 22 XkbLookupKeyBinding, 92 XkbLookupKeySym, 92 XkbMapChangesRec, 126 XkbMapNotifyEvent, 129

XkbModAction, 153 XkbModActionVMods, 155

XkbMessageAction, 166

XkbModsRec, 30 XkbName, 6

XkbNameChangesRec, 197 XkbNamesNotifyEvent, 198

XkbNamesRec, 193

XkbNewKeyboardNotifyEvent, 201 XkbNoteControlsChanges, 82 XkbNoteDeviceChanges, 224 XkbNoteIndicatorChanges, 46

XkbNoteNameChanges, 199 XkbOpenDisplay, 8

XkbOutOfRangeGroupInfo, 143 XkbOutOfRangeGroupNumber, 143

XkbPtrAction, 157 XkbPtrActionX, 158 XkbPtrActionY, 158 XkbPtrBtnAction, 158 XkbPtrDfltAction, 160 XkbQueryExtension, 7 XkbRedirectKeyAction, 168 XkbRefreshKeyboardMapping, 93 XkbResizeDeviceButtonActions, 220

XkbResizeKeyActions, 172 XkbResizeKeySyms, 146 XkbResizeKeyType, 140

XkbSAActionSetCtrls, 166 XkbSAGroup, 157 XkbSAPtrDfltValue, 160

XkbSARedirectSetVMods, 169

XkbSARedirectSetVModsMask, 169

XkbSARedirectVMods, 169

XkbSARedirectVModsMask, 168

XkbSAScreen, 164 XkbSASetGroup, 157 XkbSASetPtrDfltValue, 161 XkbSASetScreen, 165 XkbSelectEventDetails, 17

XkbSelectEvents, 16 XkbServerMapRec, 149

XkbSetAccessXTimeout, 65 XkbSetAutoRepeatRate, 59

XkbSetAutoResetControls, 57

XkbSetBounceKeysDelay, 69

XkbSetCompatMap, 189

XkbSetControls, 80

XkbSetDebuggingFlags, 226

XkbSetDetectableAutorepeat, 60 XkbSetDeviceButtonActions, 222

XkbSetDeviceInfo, 221

XkbSetIgnoreLockMods, 72

XkbSetIndicatorMap, 43

XkbSetMap, 126

XkbSetModActionVMods, 155

XkbSetNamedDeviceIndicator, 44

XkbSetNamedIndicator, 44

XkbSetNames, 197

XkbSetPerClientControls, 84 XkbSetPtrActionX, 158 XkbSetPtrActionY, 158

XkbSetServerInternalMods, 73 XkbSetSlowKeysDelay, 68 XkbSetStickyKeysOptions, 70 XkbSetXlibControls, 88 XkbStateNotifvEvent, 24

XkbStateRec, 24

XkbSwitchScreenAction, 164 XkbSymInterpretRec, 184 XkbSymMapRec, 141 XkbTranslateKeyCode, 93 XkbTranslateKeySym, 93 XkbUpdateMapFromCore, 187

XkbUseCoreKbd, 10

XkbVirtualModsToReal, 31

XkbXlibControlsImplemented, 88

XKeycodeToKeysym, 91 XKeysymToKeycode, 91 XLookupKeysym, 91 XLookupString, 85, 91 XRebindKeysym, 91

XRefreshKeyboardMapping, 91