

## Reusing this material





This work is licensed under a Creative Commons Attribution-NonCommercial-ShareAlike 4.0 International License.

https://creativecommons.org/licenses/by-nc-sa/4.0/

This means you are free to copy and redistribute the material and adapt and build on the material under the following terms: You must give appropriate credit, provide a link to the license and indicate if changes were made. If you adapt or build on the material you must distribute your work under the same license as the original.

Note that this presentation contains images owned by others. Please seek their permission before reusing these images.



# What is profiling?



 Analysing your code to find out the proportion of execution time spent in different routines.

• Essential to know this if we are going to target optimisation.

- No point optimising routines that don't significantly contribute to the overall execution time.
  - can just make your code less readable/maintainable



# Code profiling



- Code profiling is the first step for anyone interested in performance optimisation
- Profiling works by instrumenting code at compile time
  - Thus it's (usually) controlled by compiler flags
  - Can reduce performance
- Standard profiles return data on:
  - Number of function calls
  - Amount of time spent in sections of code
- Also tools that will return hardware specific data
  - Cache misses, TLB misses, cache re-use, flop rate, etc...
  - Useful for in-depth performance optimisation



## Sampling and tracing



- Many profilers work by sampling the program counter at regular intervals (normally 100 times per second).
  - low overhead, little effect on execution time
- Builds a statistical picture of which routines the code is spending time in.
  - if the run time is too small (< ~10 seconds) there aren't enough samples for good statistics
- Tracing can get more detailed information by recording some data (e.g. time stamp) at entry/exit to functions
  - higher overhead, more effect on runtime
  - unrestrained use can result in huge output files



#### Standard Unix profilers



- Standard Unix profilers are prof and gprof
- Many other profiling tools use same formats
- Usual compiler flags are -p and -pg:
  - ftn -p mycode.F90 -o myprog for prof
  - cc -pg mycode.c -o myprog for gprof
- When code is run it produces instrumentation log
  - mon.out for prof
  - gmon.out for gprof
- Then run prof/gprof on your executable program
  - eg. gprof myprog (not gprof gmon.out)



# Standard profilers



• prof myprog reads mon.out and produces this:

%Time	Seconds	Cumsecs	#Calls	msec/call	Name
32.4	0.71	0.71	14	50.7	relax_
28.3	0.62	1.33	14	44.3	resid_
11.4	0.25	1.58	3	83.	f90_close
5.9	0.13	1.71	1629419	0.0001	_mcount
5.0	0.11	1.82	339044	0.0003	f90_slr_i4
5.0	0.11	1.93	167045	0.0007	inrange_single
2.7	0.06	1.99	507	0.12	_read
2.7	0.06	2.05	1	60.	MAIN_



## Standard profilers



- gprof myprog reads gmon.out and produces something very similar
- gprof also produces a program calltree sorted by inclusive times
- Both profilers list all routines, including obscure system ones
  - Of note: mcount(), \_mcount(), moncontrol(), \_moncontrol()
     monitor() and \_monitor() are all overheads of the profiling
     implementation itself
  - \_mcount() is called every time your code calls a function; if it's high in the profile, it can indicate high function-call overhead
  - gprof assumes calls to a routine from different parents take the same amount of time – may not be true



# The Golden Rules of profiling



- Profile your code
  - The compiler/runtime will NOT do all the optimisation for you.
- Profile your code yourself
  - Don't believe what anyone tells you. They're wrong.
- Profile on the hardware you want to run on
  - Don't profile on your laptop if you plan to run on ARCHER2.
- Profile your code running the full-sized problem
  - The profile will almost certainly be qualitatively different for a test case.
- Keep profiling your code as you optimise
  - Concentrate your efforts on the thing that slows your code down.
  - This will change as you optimise.
  - So keep on profiling.



#### CrayPAT



Can do both statistic sampling and function/loop level tracing.

#### Recommended usage:

- 1. Build and instrument code
- 2. Run code and get statistic profile
- 3. Re-instrument based on profile
- 4. Re-run code to get more detailed tracing



#### Example with CrayPAT



- Load performance tools software module load perftools-base (automatically loaded on ARCHER2)
   module load perftools-lite
- Re-build application (keep .o files)
   make clean
   make
- Application automatically instrumented for you
- Run the instrumented application to get top time consuming routines
  - You should get performance profiling in your Slurm output file
  - You should get a performance file <executable\_name+93500-1088s>



#### Example with CrayPAT



CrayPat/X: Version 20.10.0 Revision 7ec62de47 09/16/20 16:57:54 lite lite-samples Experiment:

```
Table 1: Profile by Function
Samp% | Samp | Imb. | Imb. | Group
              | Samp | Samp% | Function=[MAX10]
                               PE=HIDE
  51.6% | 157.8 | 24.2 | 13.4% | MPI ALLTOALL
   1.4% | 4.4 | 5.6 | 56.4% | MPI ALLREDUCE
  10.5% | 32.2 | 17.8 | 36.0% | riemann
   9.9% | 30.4 | 20.6 | 40.7% | parabola
   4.8% | 14.8 | 11.2 | 43.5% | sweepz
   4.6% | 13.9 | 10.1 | 42.3% | remap
          10.7 | 9.3 | 46.7% | sweepy
           7.0 | 9.0 | 56.4% | paraset
   1.4% | 4.2 | 5.8 | 58.0% | states
```

Program invocation:

/lus/cls01095/work/z19/z19/adrianj/DistributedStream/src/./distributed streams

For a complete report with expanded tables and notes, run: pat report/lus/cls01095/work/z19/z19/adrianj/DistributedStream/src/distributed streams+93500-1088s

For help identifying callers of particular functions: \_pat\_report -O callers+src /lus/cls01095/work/z19/z19/adrianj/DistributedStream/src/distributed\_streams+93500-1088s To see the entire call tree:

pat\_report -O calltree+src /lus/cls01095/work/z19/z19/adrianj/DistributedStream/src/distributed\_streams+93500-1088s

For interactive, graphical performance analysis, run: app2 /lus/cls01095/work/z19/z19/adrianj/DistributedStream/src/distributed streams+93500-1088s



```
This table shows functions, and line numbers within functions, that
 have significant exclusive sample hits, averaged across ranks.
 or use: pat_report -v -O samp_profile+src ...
able 2: Profile by Group, Function, and Line
 54.4% | 166.4 | -- | -- | MPI
  51.6% | 157.8 | 24.2 | 13.4% | MPI ALLTOALL
  1.4% | 4.4 | 5.6 | 56.4% | MPI ALLREDUCE
     1.3% | 4.0 | 6.0 | 60.5% | line.27
```

#### Example with CrayPAT



- Load performance tools software
   <del>module load perftools-base</del> (automatically loaded on ARCHER2)
   <del>module load perftools</del>
- Re-build application (keep .o files)
   make clean
   make
- Instrument application for automatic profiling analysis
  - You should get an instrumented program a.out+pat pat\_build -O apa a.out
- Run the instrumented application (...+pat) to get top time consuming routines
  - You should get a performance file ("<sdatafile>.xf") or multiple files in a directory
     <sdatadir>



# Example with CrayPAT (2/2)



- Generate text report and an .apa instrumentation file pat\_report [<sdatafile>.xf | <sdatadir>]
  - Inspect the .apa file and sampling report whether additional instrumentation is needed
    - See especially sites "Libraries to trace" and "HWPC group to collect"
- Instrument application for further analysis (a.out+apa) pat\_build -0 <apafile>.apa
- Run application (...+apa)
- Generate text report and visualization file (.ap2)
   pat\_report -o my\_text\_report.txt <data>
- View report in text and/or with Cray Apprentice<sup>2</sup>
   app2 <datafile>.ap2

## Finding single-core hotspots



- Remember: pay attention only to user routines that consume significant portion of the total time
- View the key hardware counters, for example
  - L1 and L2 cache metrics
  - use of vector (SSE/AVX) instructions





- CrayPAT has mechanisms for finding "the" hotspot in a routine (e.g. in case the routine contains several and/or long loops)
  - CrayPAT API
    - Possibility to give labels to "PAT regions"
  - Loop statistics (works only with Cray compiler)
    - Compile & link with CCE using -h profile\_generate
    - pat\_report will generate loop statistics if the flag is enabled



Time%		25.2%			
Time		15.801180	secs		Elektrone file ala
Imb. Time		2.582609	secs	<b>&gt;</b>	Flat profile da
Imb. Time%		14.7%			
Calls	0.026M/sec	460,800.0	calls		
CPU_CLK_UNHALTED:THREAD_P		77,964,376,624			
CPU_CLK_UNHALTED:REF_P		2,689,572,161			
DTLB_LOAD_MISSES:MISS_CAUSE	S_A_WALK	20,626,569			
DTLB_STORE_MISSES:MISS_CAUS	SES_A_WALK	17,745,058			
L1D: REPLACEMENT		2,753,483,367			
L2_RQSTS:ALL_DEMAND_DATA_RD	1,912,839,218			HW counter	
L2_RQSTS:DEMAND_DATA_RD_HIT	1,757,495,428			values	
FP_COMP_OPS_EXE:SSE_SCALAR_	1,597			values	
FP_COMP_OPS_EXE:SSE_FP_SCAL	1,556,036,610				
FP_COMP_OPS_EXE:X87		1,878,388,524			
FP_COMP_OPS_EXE:SSE_PACKED_	_SINGLE	302,976,589		J	
SIMD_FP_256:PACKED_SINGLE		5,003,127,724			
User time (approx)	17.476 secs	47,202,147,918	cycles	180.0% Tin	ne e
CPU_CLK	2.90GHz				
HW FP Ops / User time	2,556.183M/sec	44,671,354,883	•	11.8% <mark>peak(D</mark> F	P)
Total SP ops	2,448.698M/sec	42,792,964,761	•		Derived
Total DP ops	107.485M/sec	1,878,390,122	ops		Derived
MFLOPS (aggregate)	61,348.39M/sec				metrics
D2 cache hit, miss ratio	94.4% hits		misses		
D2 to D1 bandwidth	6,680.690MiB/sec		-		
Average Time per Call		0.000034	secs		

# Hardware performance counters



- CrayPAT can interface with HWPCs
  - Gives extra information on how hardware is behaving
  - Very useful for understanding (& optimising) application performance
- Provides information on
  - hardware features, e.g. caches, vectorisation and memory bandwidth
- Available on per-program and per-function basis
  - Per-function information only available through tracing
- Number of simultaneous counters limited by hardware
  - 2 counters available with AMD Rome processors
  - If you need more, you'll need multiple runs
- Most counters accessed through the PAPI interface
  - Either native counters or derived metrics constructed from these



#### Hardware counters selection



- HWPCs collected using CrayPAT
  - Compile and instrument code for profiling as before
- Set PAT\_RT\_PERFCTR environment variable at runtime
  - e.g. in the job script
    - Hardware counter events are not collected by default (except with APA)
- export PAT\_RT\_PERFCTR=...
  - either a list of named PAPI counters
  - or <set number> = a pre-defined (and useful) set of counters
    - recommended way to use HWPCs
    - there are 8 groups to choose from
      - To see them:
        - pat\_help -> counters -> rome -> groups
        - man hwpc
        - More
           /opt/cray/pe/perftools/20.10.0/share/counters/CounterGroups.amd\_fam23mod49



Technical term for AMD Rome

#### Predefined AMD Rome HW Counter Groups

0: Summary with translation lookaside buffer activity

1: Summary with branch activity

default: mem\_bw

default\_samp: default

mem\_bw: memory bandwidth

mem\_bw\_1: memory load bandwidth, stalls

mem\_bw\_2: memory load bandwidth, cycles

stalls: Dispatch stalls for load, store, fp

#### Example: mem\_bw

```
USER / sweepy_
                                                  14.6%
Time%
Time
                                               8.738150 secs
Imb. Time
                                               3.077320 secs
Imb. Time%
                                                  27.2%
Calls
                                                  100.0 calls
                        11.547 /sec
CPU CLK UNHALTED: THREAD P
                                         92,754,888,918
CPU CLK UNHALTED: REF P
                                          2,759,876,135
L1D: REPLACEMENT
                                          1,813,741,166
L2 RQSTS:ALL DEMAND DATA RD
                                          1,891,459,700
L2 RQSTS:DEMAND DATA RD HIT
                                          1,644,133,800
                                             98,952,928
LLC MISSES
LLC REFERENCES
                                            690,626,471
User time (approx) 8.660 secs
                                         23,390,899,520 cycles 100.0% Time
CPU CLK
                         3.36GHz
D2 cache hit, miss ratio 86.4% hits
                                                  13.6% misses
L3 cache hit, miss ratio 85.7% hits
                                                14.3% misses
D2 to D1 bandwidth 13,330.757MiB/sec 121,053,420,792 bytes
Average Time per Call
                                               0.087381 secs
CrayPat Overhead: Time 0.0%
```

## Interpreting the performance numbers



- Performance numbers are an average over all ranks
  - explains non-integer values
- This does not always make sense
  - e.g. if ranks are not all doing the same thing:
    - Leader-worker schemes
    - MPMD apruns combining multiple, different programs
- Want them to only process data for certain ranks
  - pat\_report -sfilter\_input='condition' ...
  - condition should be an expression involving pe, e.g.
    - pe<1024 for the first 1024 ranks only
    - pe%2==0 for every second rank



# OpenMP data collection and reporting

epcc

- Give finer-grained profiling of threaded routines
  - Measure overhead incurred entering and leaving
    - Parallel regions
      - #pragma omp parallel
    - Work-sharing constructs within parallel regions
      - #pragma omp for
- Timings and other data now shown per-thread
  - rather than per-rank
- OpenMP tracing enabled with pat\_build -gomp ...
  - CCE: insert tracing points around parallel regions automatically
  - AMD, Gnu: need to use CrayPAT API manually



# OpenMP data collection and reporting



- Load imbalance for hybrid MPI/OpenMP programs
  - now calculated across all threads in all ranks
  - imbalances for MPI and OpenMP combined
    - Can choose to see imbalance in each programming model separately
    - See next slide for details

- Data displayed by default in pat\_report
  - no additional options needed
  - Report focuses on where program is spending its time
  - Assumes all requested resources should be used
    - you may have reasons not to want to do this, of course



#### Memory usage



- Knowing how much memory each rank uses is important:
  - What is the minimum number of cores I can run this problem on?
    - given there is 256GB (~254GB usable) of memory per node (128 cores)
  - Does memory usage scale well in the application?
  - Is memory usage balanced across the ranks in the application?
  - Is my application spending too much time allocating and freeing?



#### Heap statistics

#### **Memory per rank**

~254GB usable memory per node




```
Notes for table 5:
                                           Too many allocs/frees?
                                           Would show up as ETC time in
  Table option:
                                           CrayPAT report
    -0 heap_hiwater
  Options implied by table option;
    -d am@,ub,ta,ua,t∕f,nf,ac,ab √b pe=[mmm]
  This table shows only lines with Tracked Heap HiWater MBytes > 0.
Table 5: Heap Stats during Main Program
                                                   |PE[mmm]
 Tracked
             Total
                      Total
                               Tracked
                                          Tracked
                               Objects
            Allocs
                      Frees
                                           MBytes
                                                                Memory leaks
    Heap
                                                                Not usually a problem in HPC
 HiWater
                                   Not
                                               Not
  MBytes
                                 Freed
                                            Freed
   9.794
               915
                        910
                                            1.011 | Total
               1170
    9.943
                        1103
                                             1.046 | pe.0
                                      68
    9.909
                715
                         712
                                             1.010
                                                     lpe.22
    9.446
               1278
                        1275
```



#### Viewing data

- Apprentice 2 tool
  - GUI for exploring code/data
  - Insight summaries
- Can install desktop version
- /opt/cray/pe/perftools /\$(current\_version)/share /desktop\_installers/







#### Summary



- Profiling is essential to identify performance bottlenecks
  - even at single core level
- CrayPAT has some very useful extra features
  - can pinpoint and characterise the hotspot loops (not just routines)
  - hardware performance counters give extra insight into performance
  - well-integrated view of hybrid programming models
    - most commonly MPI/OpenMP
    - also CAF, UPC, SHMEM, pthreads, OpenACC, CUDA
  - information on memory usage
- And remember the Golden Rules
  - including the one about not believing what anyone tells you

