$$PV = \mu RT$$

Here, T is constant for this process

So the equation of state for isothermal process is given by

$$PV = constant \qquad (8.28)$$

This implies that if the gas goes from one equilibrium state (P_1, V_1) to another equilibrium state (P_2, V_2) the following relation holds for this process

$$P_1 V_1 = P_2 V_2 \qquad (8.29)$$

Since PV = constant, P is inversely proportional to V $(P \propto \frac{1}{V})$. This implies that PV graph is a hyperbola. The pressure-volume graph for constant temperature is also called isotherm.

Figure 8.25 shows the PV diagram for quasi-static isothermal expansion and quasi-static isothermal compression.

We know that for an ideal gas the internal energy is a function of temperature only. For an isothermal process since temperature is constant, the internal energy is also constant. This implies that dU or $\Delta U = 0$.

For an isothermal process, the first law of thermodynamics can be written as follows,

$$Q = W \qquad (8.30)$$

From equation (8.30), we infer that the heat supplied to a gas is used to do only external work. It is a common misconception that when there is flow of heat to the system, the temperature will increase. For isothermal process this is not true. The isothermal compression takes place when the piston of the cylinder is pushed. This will increase the internal energy which will flow out of the system through thermal contact. This is shown in Figure 8.26.

FQ6O5




Figure 8.26 Isothermal expansion and isothermal compression




Figure 8.25 (a) Quasi-static isothermal expansion (b) Quasi-static isothermal compression

UNIT-8(XI-Physics_Vol-2).indd 125 02-01-2023 15:25:52