D1.1d - VISHNU Command-line
interface specifications

**D1.1d - VISHNU Command-line interface specifications** 



# COLLABORATORS

	TITLE:  D1.1d - VISHNU Cor specifications	nmand-line interface		
ACTION	NAME	DATE	SIGNATURE	
WRITTEN BY	Benjamin Isnard, Daouda Traoré, Eugène Pamba Capo-Chichi, Kevin Coulomb, and Ibrahima Cissé	July 8, 2011		

# REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
0	05/01/2011	Formatting example	SysFera
1	13/01/2011	First release	SysFera
2	10/02/2011	Removed UMS::SessionStateType. Added UMS::StatusType, UMS::PrivilegeType. Modified UMS::addVishnuUser, UMS::updateUser, UMS::addLocalAccount, UMS::addMachine, UMS::updateMachine, UMS::listSessions, UMS::restoreConfiguration.	SysFera
3	18/02/2011	Renamed all commands to follow C-style command names with vishnu prefix.  Added the help option to all commands.  Modified update_machine and export_commands.  Removed the VISHNU_SESSION_KEY environment variable on all commands.	SysFera

# REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
4	15/04/2011	Updates for TMS: Modified description of machineld parameter, vishnu_submit_job service. Modified name of get_all_jobs_output to get_completed_jobs_output. Added input parameter outDir to get_job_output and get_completed_jobs_output. Added vishnu_get_machine_refresh_period service. Removed set_machine_env service. Removed jobPriority option in submit_job. Updates for IMS: Add option in exportCommand, getMetricCurrentValue, getProcesses, getMetricHistory, restart and getSystemThreshold. Add services stop and getSystemInfo.	SysFera
5	21/04/2011	Updates for TMS: Removed vishnu_get_machine_refresh_period and vishnu_set_machine_refresh_period services. Added UNDEFINED status of JobStatus Enum. Added UNDEFINED priority of JobPriority Enum. Removed of outputPah and errorPath of ListJobsOptions. Removed scriptContent in Job class. Added ERRCODE_ALREADY_TERMINATED, ERRCODE_ALREADY_CANCELED, ERRCODE_JOB_IS_NOT_TERMINATED in exception list. Modified values of JobPriority Enum. Modified values of QueuePriority and QueueStatus. Added UNDEFINED priority of QueuePriority. Added option queueName in vishnu_list_queues.	SysFera
6	24/05/2011	Updates of UMS: Added new error code for addLocalAccount and updateLocalAccount.	SysFera

# **Contents**

1	Docu	ument presentation	1
	1.1	Document objectives	1
	1.2	Document structure	1
	1.3	References	1
	1.4	Glossary	1
	1.5	Generic command definition format	2
	1.6	Environment variables and options	2
2	Com	nmands specification for User Man <mark>ageme</mark> nt Service (UMS)	4
	2.1	Command definitions	4
		2.1.1 vishnu_connect	4
		2.1.2 vishnu_reconnect	5
		2.1.3 vishnu_add_user	5
		2.1.4 vishnu_update_user	5
		2.1.5 vishnu_delete_user	6
		2.1.6 vishnu_close	6
		2.1.7 vishnu_change_password	7
		2.1.8 vishnu_reset_password	7
		2.1.9 vishnu_add_local_account	7
		2.1.10 vishnu_update_local_account	9
		2.1.11 vishnu_delete_local_account	9
		2.1.12 vishnu_save_configuration	10
		2.1.13 vishnu_restore_configuration	10
		2.1.14 vishnu_add_machine	11
		2.1.15 vishnu_update_machine	11
		2.1.16 vishnu_delete_machine	12
		2.1.17 vishnu_list_local_accounts	12
		2.1.18 vishnu_list_machines	12
		2.1.19 vishnu_list_history_cmd	
		2.1.20 vishnu_list_options	

			vishnu_list_users	
			vishnu_list_sessions	
			vishnu_configure_default_option	
			vishnu_configure_option	
	2.2	Parame	eters definitions	16
3	Com	ımands	specification for Tasks Management Service (TMS)	17
	3.1	Comm	and definitions	17
		3.1.1	vishnu_submit_job	17
		3.1.2	vishnu_get_job_info	18
		3.1.3	vishnu_get_job_progress	18
		3.1.4	vishnu_list_queues	18
		3.1.5	vishnu_list_jobs	19
		3.1.6	vishnu_get_job_output	19
		3.1.7	vishnu_get_completed_jobs_output	20
		3.1.8	vishnu_cancel_job	20
	3.2	Parame	eters definitions	21
4	Com	nmands	specification for Information Management Service (IMS)	22
	4.1	Comm	and definitions	22
		4.1.1	vishnu_export_commands	22
		4.1.1 4.1.2	vishnu_export_commands	
				22
		4.1.2	vishnu_get_metric_current_value	22 23
		4.1.2 4.1.3	vishnu_get_metric_current_value   vishnu_get_metric_history   vishnu_get_processes   vishnu_set_system_info	<ul><li>22</li><li>23</li><li>23</li><li>23</li></ul>
		4.1.2 4.1.3 4.1.4	vishnu_get_metric_current_value	<ul><li>22</li><li>23</li><li>23</li><li>23</li></ul>
		4.1.2 4.1.3 4.1.4 4.1.5	vishnu_get_metric_current_value   vishnu_get_metric_history   vishnu_get_processes   vishnu_set_system_info	<ul><li>22</li><li>23</li><li>23</li><li>23</li><li>24</li></ul>
		4.1.2 4.1.3 4.1.4 4.1.5 4.1.6	vishnu_get_metric_current_value	22 23 23 23 24 24 25
		4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7	vishnu_get_metric_current_value	22 23 23 23 24 24 25
		4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9	vishnu_get_metric_current_value	22 23 23 24 24 25 25
		4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11	vishnu_get_metric_current_value   vishnu_get_metric_history   vishnu_get_processes   vishnu_set_system_info   vishnu_set_system_threshold   vishnu_get_system_threshold   vishnu_define_user_identifier   vishnu_define_machine_identifier   vishnu_define_job_identifier   vishnu_define_job_identifier   vishnu_define_transfer_identifier	22 23 23 24 24 25 25 25 26
		4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11 4.1.12	vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold vishnu_get_system_threshold vishnu_define_user_identifier vishnu_define_machine_identifier vishnu_define_job_identifier vishnu_define_transfer_identifier vishnu_define_transfer_identifier	22 23 23 24 24 25 25 25 26 26
		4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11 4.1.12	vishnu_get_metric_current_value   vishnu_get_metric_history   vishnu_get_processes   vishnu_set_system_info   vishnu_set_system_threshold   vishnu_get_system_threshold   vishnu_define_user_identifier   vishnu_define_machine_identifier   vishnu_define_job_identifier   vishnu_define_job_identifier   vishnu_define_transfer_identifier	22 23 23 24 24 25 25 25 26 26
		4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11 4.1.12 4.1.13	vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold vishnu_get_system_threshold vishnu_define_user_identifier vishnu_define_machine_identifier vishnu_define_job_identifier vishnu_define_transfer_identifier vishnu_define_transfer_identifier	222 233 233 244 245 255 256 266 27
		4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11 4.1.12 4.1.13 4.1.14	vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold vishnu_get_system_threshold vishnu_define_user_identifier vishnu_define_machine_identifier vishnu_define_transfer_identifier vishnu_define_transfer_identifier vishnu_load_shed vishnu_load_shed vishnu_set_update_frequency	22 23 23 24 24 25 25 26 26 27 27
		4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11 4.1.12 4.1.13 4.1.14 4.1.15	vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold vishnu_get_system_threshold vishnu_define_user_identifier vishnu_define_machine_identifier vishnu_define_job_identifier vishnu_define_transfer_identifier vishnu_define_transfer_identifier vishnu_load_shed vishnu_set_update_frequency vishnu_get_update_frequency	22 23 23 24 24 25 25 26 26 27 27 27
		4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11 4.1.12 4.1.13 4.1.14 4.1.15 4.1.16	vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold vishnu_get_system_threshold vishnu_define_user_identifier vishnu_define_machine_identifier vishnu_define_job_identifier vishnu_define_transfer_identifier vishnu_define_transfer_identifier vishnu_load_shed vishnu_set_update_frequency vishnu_get_update_frequency vishnu_stop .	22 23 23 24 24 25 25 26 26 27 27 27 28

5	Com	nmands	specification for File Management Service (FMS)	30
	5.1	Comm	and definitions	. 30
		5.1.1	vishnu_create_file	. 30
		5.1.2	vishnu_create_dir	. 30
		5.1.3	vishnu_remove_file	. 31
		5.1.4	vishnu_remove_dir	. 31
		5.1.5	vishnu_ch_grp	. 31
		5.1.6	vishnu_ch_mod	. 32
		5.1.7	vishnu_head_of_file	. 32
		5.1.8	vishnu_tail_of_file	. 33
		5.1.9	vishnu_content_of_file	. 33
		5.1.10	vishnu_list_dir	. 33
		5.1.11	vishnu_copy_file	. 34
		5.1.12	vishnu_copy_async_file	. 34
		5.1.13	vishnu_move_file	. 35
		5.1.14	vishnu_move_async_file	. 35
		5.1.15	vishnu_stop_file_transfer	. 37
		5.1.16	vishnu_list_file_transfers	. 37
		5.1.17	vishnu_get_file_info	. 38
	5.2	Parame	eters definitions	38

# **Chapter 1**

# Document presentation

# 1.1 Document objectives

This document presents the detailed specifications of the VISHNU command line user interface.

These specifications include the definition of all commands including administration commands.

# 1.2 Document structure

The document is divided into 4 parts corresponding to the 4 modules that compose the Vishnu system:

- UMS: Users Management Service
- TMS: Tasks Management Service
- FMS: Files Management Service
- IMS: Information Management Service

Each module corresponds to a chapter in the document, and each chapter contains the following sections:

- A first section describing the definition of all commands provided by the package.
- A second section describing the definition of all enumerated values used as command parameters.

## 1.3 References

• D1.1a: VISHNU General specifications

# 1.4 Glossary

• VISHNU admin: any user having the administrator privilege

## 1.5 Generic command definition format

This section presents the generic format used in the following chapters to describe the commands. It also details the environment variables required and the user options.

A commands is defined as follows:

#### Access

Here is detailed the access level of the command line (i.e. the privilege required to use this command)

#### **Description**

Here is detailed the purpose of the command line.

#### Example of use

Here is detailed an example of the use of the command line which starts by optional arguments preceded by a short letter and the required arguments at the end.

myCommand -l acLogin -s sshKeyPath userId

#### **Parameters**

The following table contains all the input argu<mark>ments</mark> of the command with their type and description, their short letter for options and a required flag.

Parameter	Type	Option	Description	Required
userId	string		This is an example of a required argument	YES
acLogin	string	1	This is an example of an optional argument	NO
sshKeyPath	string	S	This is an example of an optional argument	NO

The following table contains the list of environment variables information. These environment variables can be mandatory or optional and the value will be overriden by the corresponding command-line option if applicable. When the user option flag is true, the value for this variable can be defined persistently as a user option stored in the database (see the "vishnu\_configure\_option" command.

## **Environment variables**

Name	Parameter	Туре	Description	Required	User option
VISHNU_CONFIG_FILE	N/A	string	This is an example of an environment variable	YES	NO

#### Note:

For each command line the -h option can be used for help.

# 1.6 Environment variables and options

Here is detailed the way to use the user options which are stored in the database and environment variables in VISHNU.

# Example 1.1 Pseudo code

# **Chapter 2**

# Commands specification for User Management Service (UMS)

# 2.1 Command definitions

# 2.1.1 vishnu connect

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_connect command opens a session

# Example of use

vishnu\_connect[-h][-p closePolicy][-d sessionInactivityDelay][-s substituteUserId]userId

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required	
userId	string		userId represents the VISHNU user identifier	YES	
password	string		password represents the password of the user, it is an interactive parameter	vord of the user, it is YES	
closePolicy	SessionCloseType	p	is an option for closing session automatically	NO	
sessionInactivityDelay	int	d	is the maximum delay in seconds between two user requests when the CLOSE_ON_TIMEOUT policy is set	NO	
substituteUserId	string	s	is an admin option which allows an admin to open a session as if she was another user identified by her userId	NO	

#### **Environment variables**

Name	Parameter	Туре	Description	Required	User option
VISHNU_CLOSE_POLICY	closePolicy	SessionCloseType	is an option for closing session automatically	NO	YES

# 2.1.2 vishnu\_reconnect

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_reconnect command reconnects to a session that is still active

#### Example of use

vishnu\_reconnect[-h] userId sessionId

#### **Parameters**

Parameter	Type	<b>Option</b>	Description	Required
userId	string		userId represents the VISHNU user identifier	YES
password	string		password represents the password of the user, it is an interactive parameter	YES
sessionId	string		sessionId is the identifier of the session defined in the database	YES

#### **Environment variables**

This command defines no environment variables.

# 2.1.3 vishnu\_add\_user

#### Access

This command line can be used by ADMIN users only

#### Description

The vishnu\_add\_user command adds a new VISHNU user

#### Example of use

vishnu\_add\_user [-h] firstname lastname privilege email

#### **Parameters**

Parameter	Type	Option	Description	Required
firstname	string		is the firstname of the user	YES
lastname	string		is the lastname of the user	YES
privilege	PrivilegeType		is the privilege of the user (admin or simple user)	YES
email	string		is the email of the user	YES

#### **Environment variables**

This command defines no environment variables.

# 2.1.4 vishnu\_update\_user

#### Access

This command line can be used by ADMIN users only

# **Description**

The vishnu\_update\_user command updates the user information except the userId and the password

#### Example of use

vishnu\_update\_user[-h][-f firstname][-l lastname][-p privilege][-m email][-s status]userId

#### **Parameters**

Parameter	Type	Option	Description	Required
userId	string		represents the VISHNU user identifier	YES
firstname	string	f	represents the updated firstname of the user	NO
lastname	string	1	represents the updated lastname of the user	NO
privilege	PrivilegeType	p	represents the updated privilege of the user	NO
email	string	m	represents the updated email adress of the user	NO
status	StatusType	S	represents the status of the user (LOCKED or ACTIVE)	NO

#### **Environment variables**

This command defines no environment variables.

# 2.1.5 vishnu\_delete\_user

#### Access

This command line can be used by ADMIN users only

# Description

The vishnu\_delete\_user command removes a user from VISHNU

#### Example of use

vishnu\_delete\_user[-h] userId

#### **Parameters**

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier of the user who will be deleted from VISHNU	YES

#### **Environment variables**

This command defines no environment variables.

# 2.1.6 vishnu\_close

#### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_close command closes the session

# Example of use

vishnu\_close[-h]

#### **Parameters**

This command defines no arguments.

#### **Environment variables**

This command defines no environment variables.

# 2.1.7 vishnu\_change\_password

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_change\_password command changes the password

#### Example of use

vishnu\_change\_password[-h] userId

#### **Parameters**

Parameter	Type	<b>Option</b>	<b>Descri</b> ption	Req <mark>uired</mark>
userId	string		userId represents the VISHNU user identifier	YES
password	string		password represents the password of the user, it is an interactive parameter	YES
passwordNew	string		passwordNew represents the new password of the user, it is an interactive parameter	YES

#### **Environment variables**

This command defines no environment variables.

# 2.1.8 vishnu\_reset\_password

#### Access

This command line can be used by ADMIN users only

#### Description

The vishnu\_reset\_password command resets the password of a user

#### Example of use

vishnu\_reset\_password[-h] userId

#### **Parameters**

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier of the user whose password will be reset	YES

#### **Environment variables**

This command defines no environment variables.

#### 2.1.9 vishnu\_add\_local\_account

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_add\_local\_account command adds a new local user configuration

# Example of use

vishnu\_add\_local\_account [-h] userId machineId acLogin sshKeyPath homeDirectory



Parameter	Type	Option	Description	Required
userId	string		The userId represents the VISHNU user identifier	YES
uscriu	sumg		of the user of the local user configuration	1 L3
machineId	string		The MachineId represents the identifier of the	YES
macimieid	sumg		machine associated to the local user configuration	
acLogin	string		accLogin represents the login of the user on the	YES
acLogin	sumg		associated machine	1123
sshKeyPath	string		sshKeyPath is the path of the ssh key of the user	YES
SSHIKCYI atti	sumg		on the associated machine	1123
homeDirectory	string		HomeDirectory is the path of the home directory	YES
	Sumg		of the user on the associated machine	1 ES

This command defines no environment variables.

# 2.1.10 vishnu\_update\_local\_account

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_update\_local\_account command updates a local user configuration

#### Example of use

vishnu\_update\_local\_account[-h][-l acLogin][-s sshKeyPath][-d homeDirectory]userId machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
userId	string		The userId represents the VISHNU user identifier	YES
useria	Sumg		of the user of the local user configuration	1123
machineId	string		The MachineId represents the identifier of the	YES
macminera	sumg		machine associated to the local user configuration	1123
acLogin	string	1	accLogin represents the login of the user on the	NO
acLogin	Sumg	1	associated machine	
sshKeyPath	string	C	sshKeyPath is the path of the ssh key of the user	NO
SSIIKCYI dui	Sumg	3	on the associated machine	110
homeDirectory	string	d	HomeDirectory is the path of the home directory	NO
nomeDirectory	Sumg	u	of the user on the associated machine	110

#### **Environment variables**

This command defines no environment variables.

# 2.1.11 vishnu\_delete\_local\_account

#### Access

This command line can be used by any VISHNU user

## **Description**

The vishnu\_delete\_local\_account command removes a local user configuration (for a given user on a given machine) from VISHNU

#### Example of use

vishnu\_delete\_local\_account [-h] userId machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
			userId represents the VISHNU user identifier of	
userId	string		the user whose local configuration will be deleted	YES
			for the given machine	
			machineId represents the identifier of the	_
machineId	string		machine whose local configuration will be	YES
			deleted for the given user	

#### **Environment variables**

This command defines no environment variables.

# 2.1.12 vishnu\_save\_configuration

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_save\_configuration command saves the configuration of VISHNU

# Example of use

vishnu\_save\_configuration[-h]

#### **Parameters**

This command defines no arguments.

#### **Environment variables**

This command defines no environment variables.

# 2.1.13 vishnu\_restore\_configuration

#### Access

This command line can be used by ADMIN users only

#### Description

The vishnu\_restore\_configuration command restores the configuration of VISHNU

#### Example of use

vishnu\_restore\_configuration[-h] filePath

#### **Parameters**

Parameter	Type	Option	Description	Required
filePath	string		The filePath is the path of the file used to restore VISHNU configuration	YES

# **Environment variables**

This command defines no environment variables.

# 2.1.14 vishnu\_add\_machine

#### Access

This command line can be used by ADMIN users only

#### Description

The vishnu\_add\_machine command adds a new machine in VISHNU

#### Example of use

vishnu\_add\_machine[-h] name site language sshPublicKeyFile machineDescription

#### **Parameters**

Parameter	Type	Option	Description	Req <mark>uired</mark>
name	string		represents the name of the machine	YES
site	string		represents the location of the machine	YES
language	string		represents the language used for the description of the machine	YES
sshPublicKeyFile	string		contains the path to the SSH public key used by VISHNU to access local user accounts	YES
machineDescription	string		represents the description of the machine	YES

#### **Environment variables**

This command defines no environment variables.

# 2.1.15 vishnu\_update\_machine

# Access

This command line can be used by ADMIN users only

# Description

The vishnu\_update\_machine command updates machine description

### Example of use

vishnu\_update\_machine[-h][-n name][-s site][-d machineDescription][-l language][-t status][--k sshPublicKeyFile] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string	1	represents the identifier of the machine	YES
name	string	n	represents the name of the machine	NO
site	string	S	represents the location of the machine	NO
machineDescription	string	d	represents the description of the machine	NO
language	string	1	represents the language used for the description of the machine	NO
status	StatusType	t	represents the status of the machine	NO
sshPublicKeyFile	string	k	contains the path to the SSH public key used by VISHNU to access local user accounts	NO

# **Environment variables**

This command defines no environment variables.

# 2.1.16 vishnu\_delete\_machine

#### Access

This command line can be used by ADMIN users only

#### Description

The vishnu\_delete\_machine command removes a machine from VISHNU

#### Example of use

vishnu\_delete\_machine[-h] machineId

#### **Parameters**

Parameter	Type	<b>Option</b>	<b>Descri</b> ption	Required
machineId	string		machine machine machine machine	YES

#### **Environment variables**

This command defines no environment variables.

# 2.1.17 vishnu\_list\_local\_accounts

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_list\_local\_accounts command lists the local user configurations

#### Example of use

vishnu\_list\_local\_accounts[-h][-a][-u userId][-i machineId]

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
adminListOption	boolean	a	is an admin option for listing all local configurations of all users	NO
userId	string	u	is an admin option for listing the local configurations of a specific user	NO
machineId	string	i	is an option for listing local user configurations on a specific machine	NO

#### **Environment variables**

This command defines no environment variables.

# 2.1.18 vishnu\_list\_machines

#### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_list\_machines command lists the machines that are accessible through VISHNU

#### Example of use

vishnu\_list\_machines[-h][-u userId][-a][-m machineId]

#### **Parameters**

Parameter	Type	Option	Description	Required
userId	string	u	is an admin option for listing machines in which	NO
			a specific user has a local configuration	
listAllmachine	boolean	a	is an option for listing all VISHNU machines	NO
machineId	string	m	is an option for listing information about a	NO
machineId string	m	specific machine	NO	

#### **Environment variables**

This command defines no environment variables.

# 2.1.19 vishnu\_list\_history\_cmd

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_list\_history\_cmd command lists the commands

#### Example of use

vishnu\_list\_history\_cmd[-h][-a][-u userId][-i sessionId][-s startDateOption][-e endDateOption]

#### **Parameters**

Parameter	Type	Option	Description	Required
adminListOption	boolean	a	is an admin option for listing all commands of all users	NO
userId	string	u	is an admin option for listing commands launched by a specific user identified by his/her userId	NO
sessionId	string	i	lists all commands launched within a specific session	NO
startDateOption	long	S	allows the user to organize the commands listed by providing the start date (the UNIX timestamp of the start date is used)	NO
endDateOption	long	e	allows the user to organize the commands listed by providing the end date (the timestamp of the end date is used). By default, the end date is the current day	NO

#### **Environment variables**

This command defines no environment variables.

# 2.1.20 vishnu\_list\_options

#### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_list\_options command lists the options of the user

#### Example of use

vishnu\_list\_options[-h][-a][-u userId][-n optionName]

#### **Parameters**

Parameter	Type	Option	Description	Required
listAllDeftValue	boolean	a	is an option for listing all default option values defined by VISHNU administrator	NO
userId	string	u	is an admin option for listing the options of a specific user	NO
optionName	string	n	allows the user to get the value of a specific option identified by its name	NO

#### **Environment variables**

This command defines no environment variables.

# 2.1.21 vishnu\_list\_users

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_list\_users command lists VISHNU users

#### Example of use

vishnu\_list\_users[-h][-i userIdOption]

#### **Parameters**

Parameter	Type	Option	Description	Required
userIdOption	string	i	allows an admin to get information about a specific user identified by his/her userId	NO

#### **Environment variables**

This command defines no environment variables.

# 2.1.22 vishnu list sessions

#### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_list\_sessions command lists all sessions of the user

#### Example of use

vishnu\_list\_sessions[-h][-t status][-p sessionClosePolicy][-d sessionInactivityDelay][-m machineId][-a][-u userId][-i sessionId][-s startDateOption][-e endDateOption]

Parameter	Type	Option	Description	Required
status	StatusType	t	specifies the status of the sessions which will be listed	NO

Parameter	Type	Option	Description	Required
sessionClosePolicy	SessionCloseType	p	specifies the closure mode of the sessions which will be listed (CLOSE_ON_TIMEOUT or CLOSE_ON_DISCONNECT)	NO
sessionInactivityDelay	int	d	specifies the inactivity delay in seconds of the sessions which will be listed	NO
machineId	string	m	allows the user to list sessions opened on a specific machine	NO
adminListOption	boolean	a	is an admin option for listing all sessions of all users	NO
userId	string	u	is an admin option for listing sessions opened by a specific user	NO
sessionId	string	i	allows the user to list all commands launched within a specific session	NO
startDateOption	long	S	allows the user to organize the commands listed by providing the start date (the UNIX timestamp of the start date is used)	NO
endDateOption	long	e	allows the user to organize the commands listed by providing the end date (the timestamp of the end date is used). By default, the end date is the current day	NO

This command defines no environment variables.

# 2.1.23 vishnu\_configure\_default\_option

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_configure\_default\_option command configures a default option value

# Example of use

vishnu\_configure\_default\_option[-h] optionName value

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	Requir <mark>ed</mark>
optionName	string		represents the name of an option	YES
value	string		represents the value of an option	YES

# **Environment variables**

This command defines no environment variables.

# 2.1.24 vishnu\_configure\_option

#### Access

This command line can be used by any VISHNU user

## **Description**

The vishnu\_configure\_option command configures an option of the user

# Example of use

vishnu\_configure\_option[-h] optionName value

# **Parameters**

Parameter	Type	Option	Description	Required
optionName	string		represents the name of an option	YES
value	string		represents the value of an option	YES

#### **Environment variables**

This command defines no environment variables.

# 2.2 Parameters definitions

Enumeration UMS::CommandStatusType Type

Name	Valu	ie e
FAILURE	0	
SUCCESS	1	

**Enumeration UMS::PrivilegeType Type** 

Name	Value
USER	0
ADMIN	1

**Enumeration UMS::SessionCloseType Type** 

Name	Value
UNDEFINED	0
CLOSE_ON_TIMEOUT	1
CLOSE_ON_DISCONNECT	2

**Enumeration UMS::StatusType Type** 

Name	Value
INACTIVE	0
ACTIVE	1

# **Chapter 3**

# Commands specification for Tasks Management Service (TMS)

# 3.1 Command definitions

# 3.1.1 vishnu submit job

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_submit\_job command submits a job on a machine through the use of a script (scriptFilePath)

# Example of use

vishnu\_submit\_job[-h][-n name][-q queue][-t wallTime][-m memory][-P nbCpu][-N nbNodesAndCpu-PerNode][-o outputPath][-e errorPath] machineId scriptFilePath

#### **Parameters**

Parameter	Туре	Option	Description	Required
machineId	string		Is the id of the machine on which the job must be submitted	YES
scriptFilePath	string		The path to the file containing the characteristics (job command, and batch scheduler directive required or optional) of the job to submit.	YES
name	string	n	Assigns a job name. The default is the path of job	NO
queue	string	q	Assigns the queue or class of the job	NO
wallTime	int	t	The maximum wall-clock time during which the job can run	NO
memory	int	m	Is the memory size that the job requires	NO
nbCpu	int	P	The number of cpu that the job requires	NO
nbNodesAndCpuPerNode	string	N	The number of nodes and processors per node	NO
outputPath	string	0	Assigns the path and file for job output	NO
errorPath	string	e	Assigns the path and file for job error	NO

#### **Environment variables**

This command defines no environment variables.

# 3.1.2 vishnu\_get\_job\_info

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_get\_job\_info command gets information on a job from its id

#### Example of use

vishnu\_get\_job\_info[-h] machineId jobId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine on which the job is running	YES
jobId	string		The id of the job	YES

#### **Environment variables**

This command defines no environment variables.

# 3.1.3 vishnu\_get\_job\_progress

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_get\_job\_progress command gets the progression status of jobs

#### Example of use

vishnu\_get\_job\_progress[-h][-i jobId][-u jobOwner] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine to get the jobs progression	YES
jobId	string	i	Specifies the id of the job whose progression the user wants to see.	NO
jobOwner	string	u	Specifies the owner of the job.	NO

# **Environment variables**

This command defines no environment variables.

# 3.1.4 vishnu\_list\_queues

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_list\_queues command gets queues information

#### Example of use

vishnu\_list\_queues[-h][-q queueName] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId string		Is the id of the machine that the user wants to list	YES	
		queues		
queueName string	a /	if it is given, listQueues gives information only of	NO	
queuervame	ueueName string	q	this queue	NO

#### **Environment variables**

This command defines no environment variables.

# 3.1.5 vishnu\_list\_jobs

#### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_list\_jobs command gets a list of all submitted jobs

#### Example of use

vishnu\_list\_jobs[-h][-i jobId][-P nbCpu][-d fromSubmitDate][-D toSubmitDate][-u owner][-s status][-p priority][-q queue] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine on which the jobs are running	YES
jobId	string	i	lists the job with the specified id	NO
nbCpu	int	P	lists the jobs with the specified number of CPUs	NO
fromSubmitDate	long	d	lists the jobs submitted after the specified date (UNIX timestamp)	NO
toSubmitDate	long	D	lists jobs submitted before the specified date (UNIX timestamp)	NO
owner	string	u	lists the jobs submitted by the specified owner	NO
status	JobStatus	S	lists the jobs with the specified status	NO
priority	JobPriority	p	lists the jobs with the specified priority	NO
queue	string	q	the jobs with the specified queue name	NO

#### **Environment variables**

This command defines no environment variables.

# 3.1.6 vishnu\_get\_job\_output

#### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_get\_job\_output command gets standard output and error output files of a job given its id

## Example of use

vishnu\_get\_job\_output[-h][-o outDir] machineId jobId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		gets outputPath and errorPath of a job from its id	YES
jobId	string		The Id of the job	YES
outDir	string	o	The output directory where the files will be stored (default is current directory)	NO

#### **Environment variables**

This command defines no environment variables.

# 3.1.7 vishnu\_get\_completed\_jobs\_output

#### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_get\_completed\_jobs\_output command gets standard output and error output files of completed jobs (applies only once for each job)

# Example of use

vishnu\_get\_completed\_jobs\_output[-h][-o outDir] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine on which the jobs are been submitted	YES
outDir	string	o	Specifies the output directory where the files will be stored (by default, the current directory).	NO

### **Environment variables**

This command defines no environment variables.

# 3.1.8 vishnu\_cancel\_job

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_cancel\_job command cancels a job from its id

#### Example of use

vishnu\_cancel\_job[-h] machineId jobId

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine on which the job is running	YES
jobId	string		The Id of the job	YES

This command defines no environment variables.

# 3.2 Parameters definitions

# **Enumeration TMS::JobPriority Type**

Name	Value
UNDEFINED	-1
VERY_LOW	1
LOW	2
NORMAL	3
HIGH	4
VERY_HIGH	5

# **Enumeration TMS::JobStatus Type**

Name		Value
UNDEFINED		-1
SUBMITTED	7	1
QUEUED		2
WAITING		3
RUNNING		4
TERMINATED		5
CANCELLED	7	6
ALREADY_DOV	VNLOADEI	7

# **Enumeration TMS::QueuePriority Type**

Name	<b>Va</b> lue
UNDEFINED	-1
VERY_LOW	1
LOW	2
NORMAL	3
HIGH	4
VERY_HIGH	5

# **Enumeration TMS::QueueStatus Type**

Name	Value
NOT_STARTED	0
STARTED	1
RUNNING	2

# **Chapter 4**

# Commands specification for Information Management Service (IMS)

# 4.1 Command definitions

#### 4.1.1 vishnu export commands

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_export\_commands command exports all the commands made by a user during a session

#### Example of use

vishnu\_export\_commands[-h][-t exportType] oldSessionId

#### **Parameters**

Parameter	Type	Option	Description	Required
oldSessionId	string		The id of the session to export (session has ended)	YES
exportType	ExportType	t	The type to export	NO

#### **Environment variables**

This command defines no environment variables.

#### 4.1.2 vishnu\_get\_metric\_current\_value

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_get\_metric\_current\_value command displays the current values of system metrics

#### Example of use

vishnu\_get\_metric\_current\_value[-h][-t metricType] machineId

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
metricType	MetricType	t	The type of the metric	NO

This command defines no environment variables.

# 4.1.3 vishnu\_get\_metric\_history

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_get\_metric\_history command displays the history of values of a system metric

#### Example of use

vishnu\_get\_metric\_history[-h][-s startTime][-e endTime][-t type] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
startTime	long	S	The start time to get the history	NO
endTime	long	e	The end time to get the history	NO
type	MetricType	t	The type of metric searched	NO

#### **Environment variables**

This command defines no environment variables.

# 4.1.4 vishnu\_get\_processes

#### Access

This command line can be used by ADMIN users only

# Description

The vishnu\_get\_processes command displays the list of the VISHNU processes running on machines

# Example of use

vishnu\_get\_processes[-h][-p machineId]

# **Parameters**

Parameter	Type	Option	Description	Required
machineId	string	p	The id of the machine	NO

### **Environment variables**

This command defines no environment variables.

# 4.1.5 vishnu\_set\_system\_info

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_set\_system\_info command updates the system information of a machine

#### Example of use

vishnu\_set\_system\_info[-h][-m memory][-d diskSpace] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
memory	long	m	Amount of RAM memory available on the machine (in Bytes)	NO
diskSpace	long	d	Amount of disk space available on the machine (in Bytes)	NO
machineId	string		The id of the machine	YES

#### **Environment variables**

This command defines no environment variables.

# 4.1.6 vishnu\_set\_system\_threshold

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_set\_system\_threshold command sets a threshold on a machine of a system

#### Example of use

vishnu\_set\_system\_threshold[-h] value machineId type handler

#### **Parameters**

Type	Option	<b>Description</b>	Required
long		The value of the threshold	YES
string		The machine ID the threshold is available	YES
MetricType		The type of the threshold	YES
string		The userId of the admin responsible for handling the threshold problems	YES
	long string MetricType	long string MetricType	long String The value of the threshold String The machine ID the threshold is available MetricType The type of the threshold The userId of the admin responsible for handling

#### **Environment variables**

This command defines no environment variables.

# 4.1.7 vishnu\_get\_system\_threshold

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_get\_system\_threshold command gets a system threshold on a machine

#### Example of use

vishnu\_get\_system\_threshold[-h][-m machineId][-t metricType]

Parameter	Type	Option	Description	Required
machineId	string	m	The id of the machine where the metric is defined	NO
metricType	MetricType	t	The type of the metric	NO

This command defines no environment variables.

# 4.1.8 vishnu\_define\_user\_identifier

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_define\_user\_identifier command defines the shape of the identifiers automatically generated for the users

#### Example of use

vishnu\_define\_user\_identifier[-h] format

#### **Parameters**

Parameter	Туре	Option	Description	Required
format	string		The new format to use	YES

#### **Environment variables**

This command defines no environment variables.

### 4.1.9 vishnu\_define\_machine\_identifier

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_define\_machine\_identifier command defines the shape of the identifiers automatically generated for the machines

# Example of use

vishnu\_define\_machine\_identifier[-h] format

#### **Parameters**

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

#### **Environment variables**

This command defines no environment variables.

# 4.1.10 vishnu\_define\_job\_identifier

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_define\_job\_identifier command defines the shape of the identifiers automatically generated for the jobs

# Example of use

vishnu\_define\_job\_identifier[-h] format

#### **Parameters**

Parameter	Type	Option	Description	Required
format	string	/	The new format to use	YES

#### **Environment variables**

This command defines no environment variables.

# 4.1.11 vishnu\_define\_transfer\_identifier

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_define\_transfer\_identifier command defines the shape of the identifiers automatically generated for the file transfers

#### Example of use

vishnu\_define\_transfer\_identifier[-h] format

#### **Parameters**

Parameter	Туре	Option	Description	Required
format	string		The new format to use	YES

#### **Environment variables**

This command defines no environment variables.

# 4.1.12 vishnu\_load\_shed

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_load\_shed command sheds load on a machine

#### Example of use

vishnu\_load\_shed[-h] machineId loadShedType

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine to stop	YES
loadShedType	LoadShedType		Selects a load shedding mode (SOFT: stops all services and they can be restarted, HARD: stops all services, they cannot be restarted)	YES

#### **Environment variables**

This command defines no environment variables.

# 4.1.13 vishnu\_set\_update\_frequency

#### Access

This command line can be used by ADMIN users only

#### Description

The vishnu\_set\_update\_frequency command sets the update frequency of the IMS tables

#### Example of use

vishnu\_set\_update\_frequency[-h] freq

#### **Parameters**

Parameter	Type	<b>Option</b>	Description	Req <mark>uire</mark> d
freq	int		Frequency the data are updated, in second	YES

#### **Environment variables**

This command defines no environment variables.

# 4.1.14 vishnu\_get\_update\_frequency

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_get\_update\_frequency command gets the update frequency of the IMS database

### Example of use

vishnu\_get\_update\_frequency[-h]

# **Parameters**

This command defines no arguments.

#### **Environment variables**

This command defines no environment variables.

# 4.1.15 vishnu\_stop

#### Access

This command line can be used by ADMIN users only

# Description

The vishnu\_stop command to stop (and do not try to relaunch) a SeD

# Example of use

vishnu\_stop[-h] processName machineId

Parameter	Type	Option	Description	Required
processName	string		The name of the process (the name of the executable)	YES
machineId	string		The id of the machine	YES

This command defines no environment variables.

# 4.1.16 vishnu\_get\_system\_info

#### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_get\_system\_info command to get the system info on a machine

#### Example of use

vishnu\_get\_system\_info[-h][-m machineId]

#### **Parameters**

Parameter	Type	Option	<b>Des</b> cription	Required
machineId	string	m	The machine id	NO

#### **Environment variables**

This command defines no environment variables.

# 4.1.17 vishnu\_restart

#### Access

This command line can be used by ADMIN users only

# Description

The vishnu\_restart command to restart a SeD or a MA

#### Example of use

vishnu\_restart[-h][-v vishnuConf][-t sedType] machineId

#### **Parameters**

Parameter	Type	<b>Option</b>	Description	Required
machineId	string		The id of the machine where to restart	YES
vishnuConf	string	V	The path to the vishnu configuration file	NO
sedType	SeDType	t	The type of the vishnu sed	NO

#### **Environment variables**

This command defines no environment variables.

# 4.2 Parameters definitions

# **Enumeration IMS::ExportType Type**

Name	Value
UNDEFINED	0
SHELL	1

# **Enumeration IMS::LoadShedType Type**

Name	Value
UNDEFINED	0
HARD	1
SOFT	2

# **Enumeration IMS::MetricType Type**

Name	Value
UNDEFINED	0
CPUUSE	1
FREEDISKSPACE	2
FREEMEMORY	3

# **Enumeration IMS::ProcessState Type**

Name	Value
UNDEFINED	0
RUNNING	1
DOWN	2
DELETED	3

# **Enumeration IMS::SeDType Type**

Name		Value
UNDEFINE	ED	0
UMS		1
TMS		2
FMS		3
IMS		4

# **Chapter 5**

# Commands specification for File Management Service (FMS)

# 5.1 Command definitions

# 5.1.1 vishnu create file

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_create\_file command creates files on remote machines.

# Example of use

vishnu\_create\_file[-h] path

#### **Parameters**

Type	Option	<b>Description</b>	Required
string		The file to create following the pattern [host:]file	YES
			The file to create following the pattern [host:]file

#### **Environment variables**

This command defines no environment variables.

# 5.1.2 vishnu\_create\_dir

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_create\_dir command creates directories on remote machines.

#### Example of use

vishnu\_create\_dir[-h] path

Parameter	Type	Option	Description	Required
path	string		The directory to create following the pattern [host:]directory path.	YES

This command defines no environment variables.

# 5.1.3 vishnu\_remove\_file

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_remove\_file command removes files from remote hosts.

#### Example of use

vishnu\_remove\_file [-h] [-r] path

#### **Parameters**

Parameter	Type	Option	Description	Required
path	string		The file to remove following the pattern [host:]file path	YES
isRecursive	boolean	r	It specifies when the remove command is recursive (case of directory) or not.	NO

#### **Environment variables**

This command defines no environment variables.

# 5.1.4 vishnu\_remove\_dir

# Access

This command line can be used by any VISHNU user

# Description

The vishnu\_remove\_dir command removes directories (and subdirectories) from remote machines.

# Example of use

 ${\tt vishnu\_remove\_dir} \, [-h] \, {\tt path} \,$ 

#### **Parameters**

Parameter	Type	Option	Description	Required
path	string		The directory to remove following the pattern [host:]directory path	YES

# **Environment variables**

This command defines no environment variables.

# 5.1.5 vishnu\_ch\_grp

#### Access

This command line can be used by any VISHNU user

# **Description**

The vishnu\_ch\_grp command changes group owner of remote files/directories.

#### Example of use

vishnu\_ch\_grp [-h] group path

#### **Parameters**

Parameter	Type	Option	Description	Required
group	string		the new group owner of file/directory	YES
path	string		The file/directory following the pattern [host:]file path	YES

#### **Environment variables**

This command defines no environment variables.

# 5.1.6 vishnu\_ch\_mod

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_ch\_mod command changes access rights of remote files/directories.

#### Example of use

vishnu\_ch\_mod[-h] mode path

#### **Parameters**

Parameter	Туре	Option	Description	Required
mode	mode_t		the access rigths of file/directory in octal system.	YES
path	string		The file/directory following the pattern [host:]file path	YES

#### **Environment variables**

This command defines no environment variables.

# 5.1.7 vishnu\_head\_of\_file

#### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_head\_of\_file command displays a few first lines of files located on remote machines.

## Example of use

vishnu\_head\_of\_file[-h][-n nline] path

Parameter	Type	Option	Description	Required
path	string		The file following the pattern [host:]file path	YES
nline	int	n	the number of line to get	NO

This command defines no environment variables.

# 5.1.8 vishnu\_tail\_of\_file

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_tail\_of\_file command displays a few last lines of files located on remote machines

#### Example of use

vishnu\_tail\_of\_file[-h][-n nline] path

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
path	string		The file following the pattern [host:]file path	YES
nline	int	n	the number of line to get	NO

#### **Environment variables**

This command defines no environment variables.

# 5.1.9 vishnu\_content\_of\_file

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_content\_of\_file command displays content of files located on remote machines

#### Example of use

vishnu\_content\_of\_file [-h] path

#### **Parameters**

Parameter	Type	Option	Description	Required
path	string		The file to display following the pattern [host:]file path	YES

#### **Environment variables**

This command defines no environment variables.

#### 5.1.10 vishnu list dir

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_list\_dir command displays the content of a remote directory.

#### Example of use

vishnu\_list\_dir[-h][-l][-a] path

#### **Parameters**

Parameter	Type	Option	Description	Required
path	string		The directory to list following the pattern [host: directory path]	YES
longFormat	boolean	1	It specifies the long display format (all available file informations)	NO
allFiles	boolean	a	Allows to display all files including hidden files	NO

#### **Environment variables**

This command defines no environment variables.

# 5.1.11 vishnu\_copy\_file

#### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_copy\_file command executes a synchronous copy of file.

# Example of use

vishnu\_copy\_file[-h][-r][-c trCommand] src dest

#### **Parameters**

Parameter	Type	Option	Description	Required	
src s	string		The source file to copy following the pattern	YES	
	Sumg		[host:]file path		
dest	string		The path of the destination file	YES	
isRecursive	boolean		It specifies when the copy is recursive (case of	NO	
	boolean	1	directory) or not.	NO	
trCommand	TransferCommand	С	the command to use to perform file transfer.	NO	

#### **Environment variables**

Name	Parameter	Туре	Description	Req <mark>uire</mark> d	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

# 5.1.12 vishnu\_copy\_async\_file

#### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_copy\_async\_file command executes an asynchronous copy of file.

#### Example of use

 $\verb|vishnu_copy_async_file[-h][-r][-c trCommand]| src dest|\\$ 

Parameter	Type	Option	1 1	
src	string		The source file to copy following the pattern [host:]file path	YES
dest	string		The path of the destination file	YES
isRecursive	boolean	r	It specifies when the copy is recursive (case of directory) or not.	NO
trCommand	TransferCommand	c	the command to use to perform file transfer.	NO

Name	Parameter	Type	Description	Required	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

# 5.1.13 vishnu\_move\_file

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_move\_file command executes a synchronous move of file.

# Example of use

vishnu\_move\_file[-h][-r][-c trCommand] src dest

#### **Parameters**

Parameter	Type	Option	<b>D</b> escription	Required
ero	string		The source file to move following the pattern	YES
src string		[host:]file path	1123	
dest	string		The path of the destination file	YES
isRecursive	boolean		It specifies when the copy is recursive (case of	NO
ISRECUISIVE	boolean	Γ	directory) or not.	INO
trCommand	TransferCommand	c	the command to use to perform file transfer.	NO

#### **Environment variables**

Name	Parameter	Туре	Description	Required	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

# 5.1.14 vishnu\_move\_async\_file

# Access

This command line can be used by any VISHNU user

# Description

The vishnu\_move\_async\_file command executes an asynchronous move of file.

#### Example of use

 $\label{lem:vishnu_move_async_file} \\ \text{vishnu_move\_async\_file} \\ \text{[-h][-r][-c} \\ \\ \textit{trCommand]} \\ \textit{src dest} \\ \\ \text{} \\ \\ \text{} \\$ 

Parameter	Type	Option	Description	Required
src	string		The source file to move following the pattern [host:]file path	YES
dest	string		The path of the destination file	YES
isRecursive	boolean	r	It specifies when the copy is recursive (case of directory) or not.	NO
trCommand	TransferCommand	c	the command to use to perform file transfer.	NO

Name	Parameter	Type	Description	Required	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

# 5.1.15 vishnu\_stop\_file\_transfer

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_stop\_file\_transfer command stops an execution of a set of file transfers.

# Example of use

vishnu\_stop\_file\_transfer[-h][-i transferId][-m fromMachineId][-u userId]

#### **Parameters**

Parameter	Type	Option	Description	Required
transferId	string	i	a given transfer id	NO
fromMachineId	string	m	the machine that is the source or destination of the file transfer	NO
userId	string	u	allows an admin to stop file transfers of a specific user	NO

#### **Environment variables**

This command defines no environment variables.

# 5.1.16 vishnu\_list\_file\_transfers

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_list\_file\_transfers command displays the history of all file transfers submitted by User.

### Example of use

vishnu\_list\_file\_transfers[-h][-t transferId][-m fromMachineId][-u userId][-s status]

Parameter	Type	Option	Description	Required
transferId	string	t	a given transfer id	NO
fromMachineId	string	m	the machine that is the source of the file transfer	NO

Parameter	Type	Option	Description	Required
userId	string	u	allows the admin to list file transfers initiated by a specific user	NO
status	Status	S	the file transfer status	NO

This command defines no environment variables.

# 5.1.17 vishnu\_get\_file\_info

#### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_get\_file\_info command displays the information of files.

#### Example of use

vishnu\_get\_file\_info[-h] path

#### **Parameters**

Parameter	Type	Option	Description	Required
path	string		The file whose inode information will be	YES
F	312338		displayed	

#### **Environment variables**

This command defines no environment variables.

# 5.2 Parameters definitions

**Enumeration FMS::FileType Type** 

Name	Value
BLOCK	0
CHARACTER	1
DIRECTORY	2
SYMBOLICLINK	3
SCKT	4
FIFO	5
REGULAR	6

# **Enumeration FMS::Status Type**

Name	Value
INPROGRESS	0
COMPLETED	1
CANCELLED	2
FAILED	3
UNDEFINED	4

**Enumeration FMS::TransferCommand Type** 

Name	Value
SCP	0
RSYNC	1
UNDEFINED	2