D1.1d - VISHNU Command-line
interface specifications

D1.1d - VISHNU Command-line interface specifications



COLLABORATORS

	TITLE : D1.1d - VISHNU Co			
ACTION	NAME	DATE	SIGNATURE	
WRITTEN BY	Benjamin Isnard, Daouda Traoré, Eugène Pamba Capo-Chichi, Kevin Coulomb, and Ibrahima Cissé	February 18, 2011		

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
0	05/01/2011	Formatting example	SysFera
1	13/01/2011	First release	SysFera
2	10/02/2011	Removed UMS::SessionStateType. Added UMS::StatusType, UMS::PrivilegeType. Modified UMS::addVishnuUser, UMS::updateUser, UMS::addLocalAccount, UMS::addMachine, UMS::updateMachine, UMS::listSessions, UMS::restoreConfiguration.	SysFera
3	18/02/2011	Renamed all commands to follow C-style command names with vishnu prefix. Added the help option to all commands. Modified update_machine and export_commands.	SysFera

Contents

1	Doc	ument presentation	1
	1.1	Document objectives	1
	1.2	Document structure	1
	1.3	References	1
	1.4	Glossary	1
	1.5	Generic command definition format	2
	1.6	Environment variables and options	2
2	Com	nmands specification for User Man <mark>ageme</mark> nt Service (U <mark>MS)</mark>	4
	2.1	Command definitions	4
		2.1.1 vishnu_connect	4
		2.1.2 vishnu_reconnect	5
		2.1.3 vishnu_add_user	5
		2.1.4 vishnu_update_user	6
		2.1.5 vishnu_delete_user	6
		2.1.6 vishnu_close	7
		2.1.7 vishnu_change_password	7
		2.1.8 vishnu_reset_password	8
		2.1.9 vishnu_add_local_account	8
		2.1.10 vishnu_update_local_account	9
		2.1.11 vishnu_delete_local_account	9
		2.1.12 vishnu_save_configuration	10
		2.1.13 vishnu_restore_configuration	10
		2.1.14 vishnu_add_machine	11
		2.1.15 vishnu_update_machine	11
		2.1.16 vishnu_delete_machine	12
		2.1.17 vishnu_list_local_account	13
		2.1.18 vishnu_list_machine	13
		2.1.19 vishnu_list_history_cmd	14
		2.1.20 vishnu_list_options	14

		2.1.21	vishnu_list_users	15
		2.1.22	vishnu_list_sessions	15
		2.1.23	vishnu_configure_default_option	16
		2.1.24	vishnu_configure_option	17
	2.2	Parame	eters definitions	17
3	Com	nmands	specification for Tasks Management Service (TMS)	19
	3.1	Comm	and definitions	19
		3.1.1	vishnu_submit_job	19
		3.1.2	vishnu_get_job_info	20
		3.1.3	vishnu_get_job_progress	20
		3.1.4	vishnu_list_queues	21
		3.1.5	vishnu_list_jobs	21
		3.1.6	vishnu_get_job_out_put	22
		3.1.7	vishnu_get_all_jobs_out_put	22
		3.1.8	vishnu_cancel_job	23
		3.1.9	vishnu_set_machine_env	23
			vishnu_set_machine_refresh_period	
	3.2	Parame	eters definitions	24
	3.2	1 aranic		
4			specification for Information Management Service (IMS)	26
4		nmands		26
4	Com	nmands	specification for Informatio <mark>n Man</mark> ageme <mark>nt Ser</mark> vice (IMS)	26 26
4	Com	nmands Comma	specification for Information Management Service (IMS) and definitions	262626
4	Com	nmands Comma	specification for Information Management Service (IMS) and definitions	26 26 26 26
4	Com	Comma 4.1.1 4.1.2	specification for Information Management Service (IMS) and definitions	26 26 26 26 27
4	Com	Comma 4.1.1 4.1.2 4.1.3	specification for Information Management Service (IMS) and definitions vishnu_export_commands vishnu_get_metric_current_value vishnu_get_metric_history	26 26 26 26 27 27
4	Com	Comma 4.1.1 4.1.2 4.1.3 4.1.4	specification for Information Management Service (IMS) and definitions vishnu_export_commands vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes	26 26 26 26 27 27 28
4	Com	Annands Comma 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5	specification for Information Management Service (IMS) and definitions vishnu_export_commands vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info	26 26 26 27 27 28 28
4	Com	Amands Comma 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6	specification for Information Management Service (IMS) and definitions vishnu_export_commands vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold	26 26 26 27 27 28 28 29
4	Com	Amands Comma 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7	specification for Information Management Service (IMS) and definitions vishnu_export_commands vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold vishnu_get_system_threshold	26 26 26 27 27 28 28 29
4	Com	4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9	specification for Information Management Service (IMS) and definitions vishnu_export_commands vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold vishnu_get_system_threshold vishnu_define_user_identifier	26 26 26 27 27 28 28 29 29
4	Com	4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10	specification for Information Management Service (IMS) and definitions vishnu_export_commands vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold vishnu_get_system_threshold vishnu_define_user_identifier vishnu_define_machine_identifier	26 26 26 27 27 28 28 29 29 30 30
4	Com	4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11	specification for Information Management Service (IMS) and definitions vishnu_export_commands vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold vishnu_get_system_threshold vishnu_define_user_identifier vishnu_define_machine_identifier vishnu_define_job_identifier	26 26 26 27 27 28 28 29 29 30 30 31
4	Com	4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11	specification for Information Management Service (IMS) and definitions vishnu_export_commands vishnu_get_metric_current_value vishnu_get_processes vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold vishnu_get_system_threshold vishnu_get_system_threshold vishnu_define_user_identifier vishnu_define_machine_identifier vishnu_define_job_identifier vishnu_define_job_identifier	26 26 26 27 27 28 28 29 30 30 31 31
4	Com	4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11 4.1.12 4.1.13	specification for Information Management Service (IMS) and definitions vishnu_export_commands vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold vishnu_get_system_threshold vishnu_define_user_identifier vishnu_define_machine_identifier vishnu_define_job_identifier vishnu_define_transfer_identifier vishnu_load_shed vishnu_load_shed	26 26 26 27 27 28 28 29 30 30 31 31 32
4	Com	4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11 4.1.12 4.1.13	specification for Information Management Service (IMS) and definitions vishnu_export_commands vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold vishnu_get_system_threshold vishnu_define_user_identifier vishnu_define_machine_identifier vishnu_define_transfer_identifier vishnu_define_transfer_identifier vishnu_load_shed vishnu_load_shed vishnu_set_update_frequency	26 26 26 27 27 28 28 29 30 30 31 31 32 32

5	Com	mands	specification for File Management Service (FMS)	35
	5.1	Comm	nand definitions	. 35
		5.1.1	vishnu_create_file	. 35
		5.1.2	vishnu_create_dir	. 35
		5.1.3	vishnu_remove_file	. 36
		5.1.4	vishnu_remove_dir	. 36
		5.1.5	vishnu_ch_grp	. 37
		5.1.6	vishnu_ch_mod	. 37
		5.1.7	vishnu_head_of_file	. 38
		5.1.8	vishnu_tail_of_file	. 38
		5.1.9	vishnu_content_of_file	. 38
		5.1.10	vishnu_list_dir	. 39
		5.1.11	vishnu_copy_file	. 39
		5.1.12	vishnu_copy_async_file	. 40
		5.1.13	vishnu_move_file	. 40
		5.1.14	vishnu_move_async_file	. 41
		5.1.15	vishnu_stop_file_transfer	. 41
		5.1.16	vishnu_list_file_transfer_status	. 42
		5.1.17	vishnu_list_file_transfers	. 42
	5.2	Doromo	eters definitions	12

Chapter 1

Document presentation

1.1 Document objectives

This document presents the detailed specifications of the VISHNU command line user interface.

These specifications include the definition of all commands including administration commands.

1.2 Document structure

The document is divided into 4 parts corresponding to the 4 modules that compose the Vishnu system:

- UMS: Users Management Service
- TMS: Tasks Management Service
- FMS: Files Management Service
- IMS: Information Management Service

Each module corresponds to a chapter in the document, and each chapter contains the following sections:

- A first section describing the definition of all commands provided by the package.
- A second section describing the definition of all enumerated values used as command parameters.

1.3 References

• D1.1a: VISHNU General specifications

1.4 Glossary

• VISHNU admin: any user having the administrator privilege

1.5 Generic command definition format

This section presents the generic format used in the following chapters to describe the commands. It also details the environment variables required and the user options.

A commands is defined as follows:

Access

Here is detailed the access level of the command line (i.e. the privilege required to use this command)

Description

Here is detailed the purpose of the command line.

Example of use

Here is detailed an example of the use of the command line which starts by optional arguments preceded by a short letter and the required arguments at the end.

myCommand -l acLogin -s sshKeyPath userId

Parameters

The following table contains all the input arguments of the command with their type and description, their short letter for options and a required flag.

Parameter	Type	Option	Description	Required
userId	string		This is an example of a required argument	YES
acLogin	string	1	This is an example of an optional argument	NO
sshKeyPath	string	S	This is an example of an optional argument	NO

The following table contains the list of environment variables information, a required flag and a user option flag. When the user option flag is true, the environment variable can be defined as a user option stored in the database.

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	This is an example of an environment variable	YES	NO

Note:

For each command line the -h option can be used for help.

1.6 Environment variables and options

Here is detailed the way to use the user options which are stored in the database and environment variables in VISHNU.

Example 1.1 Pseudo code

```
if (the option is provided in the command line) {
    optionValue = option
} else {
    if (an environment variable exists) {
        optionValue = EnVariable_Value

    } else {

        if (a value has been defined in the user configuration) {
            optionValue = user_Option
        }
        else {
            //The default value of the option defined by VISHNU admin is used optionValue = defaultValueOption
        }
    }
}
```

Chapter 2

Commands specification for User Management Service (UMS)

2.1 Command definitions

2.1.1 vishnu connect

Access

This command line can be used by any VISHNU user

Description

The vishnu_connect command opens a session

Example of use

vishnu_connect[-h][-p closePolicy][-d sessionInactivityDelay][-s substituteUserId]userId

Parameters

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier	YES
password	string password represents the password of the user, it is an interactive parameter		YES	
closePolicy	SessionCloseType	p	is an option for closing session automatically	NO
sessionInactivityDelay	is the maximum delay in seconds between two		NO	
substituteUserId	string	s	is an admin option which allows an admin to open a session as if she was another user identified by her userId	NO

Name	Parameter	Туре	Description	Required	User option
VISHNU_CLOSE_POLICY	closePolicy	SessionCloseType	is an option for closing session automatically	NO	YES

2.1.2 vishnu_reconnect

Access

This command line can be used by any VISHNU user

Description

The vishnu_reconnect command reconnects to a session that is still active

Example of use

vishnu_reconnect[-h] userId sessionId

Parameters

Parameter	Type	Option	Descri ption	Required
userId	string		userId represents the VISHNU user identifier	YES
password	string		password represents the password of the user, it is an interactive parameter	YES
sessionId	string		sessionId is the identifier of the session defined in the database	YES

Environment variables

This command defines no environment variables.

2.1.3 vishnu_add_user

Access

This command line can be used by ADMIN users only

Description

The vishnu_add_user command adds a new VISHNU user

Example of use

vishnu_add_user[-h] firstname lastname privilege email

Parameters

Parameter	Type	Option	Description	Required
firstname	string		is the firstname of the user	YES
lastname	string		is the lastname of the user	YES
privilege	PrivilegeType		is the privilege of the user (admin or simple user)	YES
email	string		is the email of the user	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.4 vishnu_update_user

Access

This command line can be used by ADMIN users only

Description

The vishnu_update_user command updates the user information except the userId and the password

Example of use

vishnu_update_user[-h][-f firstname][-l lastname][-p privilege][-m email][-s status]userId

Parameters

Parameter	Type	Option	Description	Req <mark>uired</mark>
userId	string		represents the VISHNU user identifier	YES
firstname	string	f	represents the updated firstname of the user	NO
lastname	string	1	represents the updated lastname of the user	NO
privilege	PrivilegeType	p	represents the updated privilege of the user	NO
email	string	m	represents the updated email adress of the user	NO
status	StatusType	S	represents the status of the user (LOCKED or ACTIVE)	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.5 vishnu_delete_user

Access

This command line can be used by ADMIN users only

Description

The vishnu_delete_user command removes a user from VISHNU

Example of use

vishnu_delete_user[-h] userId

Parameters

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier of the user who will be deleted from VISHNU	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.6 vishnu_close

Access

This command line can be used by any VISHNU user

Description

The vishnu_close command closes the session

Example of use

vishnu_close[-h]

Parameters

This command defines no arguments.

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.7 vishnu_change_password

Access

This command line can be used by any VISHNU user

Description

The vishnu_change_password command changes the password

Example of use

vishnu_change_password[-h] userId

Parameters

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier	YES
password	string		password represents the password of the user, it is an interactive parameter	YES
passwordNew	string		passwordNew represents the new password of the user, it is an interactive parameter	YES

Environment variables

This command defines no environment variables.

2.1.8 vishnu_reset_password

Access

This command line can be used by ADMIN users only

Description

The vishnu_reset_password command resets the password of a user

Example of use

vishnu_reset_password[-h] userId

Parameters

Parameter	Type	Option	Descri ption	Required
userId	string		userId represents the VISHNU user identifier of the user whose password will be reset	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.9 vishnu_add_local_account

Access

This command line can be used by any VISHNU user

Description

The vishnu_add_local_account command adds a new local user configuration

Example of use

vishnu_add_local_account [-h] userId machineId acLogin sshKeyPath homeDirectory

Parameters

Parameter	Type	Option	Description	Required
userId	string		The userId represents the VISHNU user identifier	YES
useria	string		of the user of the local user configuration	1123
machineId	string		The MachineId represents the identifier of the	YES
macmileid	sung		machine associated to the local user configuration	1123
acLogin	string		accLogin represents the login of the user on the	YES
acLogin	sumg		associated machine	125
sshKeyPath	string		sshKeyPath is the path of the ssh key of the user	YES
ssinceyraui	String		on the associated machine	1125
homeDirectory	string		HomeDirectory is the path of the home directory	YES
nomeDirectory	String		of the user on the associated machine	1123

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.10 vishnu_update_local_account

Access

This command line can be used by any VISHNU user

Description

The vishnu_update_local_account command updates a local user configuration

Example of use

vishnu_update_local_account[-h][-l acLogin][-s sshKeyPath][-d homeDirectory]userId machineId

Parameters

Parameter	Type		Option	Description	Required
userId	string			The userId represents the VISHNU user identifier of the user of the local user configuration	YES
machineId	string			The MachineId represents the identifier of the machine associated to the local user configuration	YES
acLogin	string	,	1	accLogin represents the login of the user on the associated machine	NO
sshKeyPath	string		s	sshKeyPath is the path of the ssh key of the user on the associated machine	NO
homeDirectory	string		d	HomeDirectory is the path of the home directory of the user on the associated machine	NO

Environment variables

Name	Parameter	Type	Description	R <mark>equi</mark> red	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.11 vishnu_delete_local_account

Access

This command line can be used by any VISHNU user

Description

The vishnu_delete_local_account command removes a local user configuration (for a given user on a given machine) from VISHNU

Example of use

vishnu_delete_local_account [-h] userId machineId

Parameter	Type	Option	Description	Required
			userId represents the VISHNU user identifier of	
userId	string		the user whose local configuration will be deleted	YES
			for the given machine	
			machineId represents the identifier of the	
machineId	string		machine whose local configuration will be	YES
			deleted for the given user	

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.12 vishnu_save_configuration

Access

This command line can be used by ADMIN users only

Description

The vishnu_save_configuration command saves the configuration of VISHNU

Example of use

vishnu_save_configuration[-h]

Parameters

This command defines no arguments.

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.13 vishnu_restore_configuration

Access

This command line can be used by ADMIN users only

Description

The vishnu_restore_configuration command restores the configuration of VISHNU

Example of use

vishnu_restore_configuration[-h] filePath

Parameter	Type	Option	Description	Required
filePath	string		The filePath is the path of the file used to restore VISHNU configuration	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.14 vishnu_add_machine

Access

This command line can be used by ADMIN users only

Description

The vishnu_add_machine command adds a new machine in VISHNU

Example of use

vishnu_add_machine[-h] name site language sshPublicKeyFile

Parameters

Parameter	Type	Option	Description	Required
name	string		represents the name of the machine	YES
site	string		represents the location of the machine	YES
machineDescription	string		represents the description of the machine, it is an interactive parameter	YES
language	string		represents the language used for the description of the machine	YES
sshPublicKeyFile	string		contains the path to the SSH public key used by VISHNU to access local user accounts	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.15 vishnu_update_machine

Access

This command line can be used by ADMIN users only

Description

The vishnu_update_machine command updates machine description

Example of use

vishnu_update_machine[-h][-n name][-s site][-d][-l language][-t status][-k sshPublicKeyFile] machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		represents the identifier of the machine	YES
name	string	n	represents the name of the machine	NO
site	string	S	represents the location of the machine	NO
machineDescription	string	d	represents the description of the machine, it is an interactive parameter	NO
language	string	1	represents the language used for the description of the machine	NO
status	StatusType	t	represents the status of the machine	NO
sshPublicKeyFile	string	k	contains the path to the SSH public key used by VISHNU to access local user accounts	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.16 vishnu_delete_machine

Access

This command line can be used by ADMIN users only

Description

The vishnu_delete_machine command removes a machine from VISHNU

Example of use

vishnu_delete_machine[-h] machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		machineId represents the identifier of the machine	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.17 vishnu_list_local_account

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_local_account command lists the local user configurations

Example of use

vishnu_list_local_account [-h] [-a] [-u userId] [-i machineId]

Parameters

Parameter	Type	Option	Description	Req <mark>uire</mark> d
adminListOption	boolean	a	is an admin option for listing all local configurations of all users	NO
userId	string	u	is an admin option for listing the local configurations of a specific user	NO
machineId	string	i	is an option for listing local user configurations on a specific machine	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.18 vishnu_list_machine

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_machine command lists the machines in which the local user configurations are defined for the given user

Example of use

vishnu_list_machine[-h][-u userId][-a][-m machineId]

Parameters

Parameter	Type	Option	Description	Required
userId	string	u	is an admin option for listing machines in which a specific user has a local configuration	NO
listAllmachine	boolean	a	is an option for listing all VISHNU machines	NO
machineId	string	m	is an option for listing information about a specific machine	NO

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.19 vishnu_list_history_cmd

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_history_cmd command lists the commands

Example of use

vishnu_list_history_cmd[-h][-a][-u userId][-i sessionId][-s startDateOption][-e endDateOption]

Parameters

Parameter	Type	Option	Description	Required
adminListOption	boolean	a	is an admin option for listing all commands of all users	NO
userId	string	u	is an admin option for listing commands launched by a specific user identified by his/her userId	NO
sessionId	string	i	lists all commands launched within a specific session	NO
startDateOption	long	S	allows the user to organize the commands listed by providing the start date (the UNIX timestamp of the start date is used)	NO
endDateOption	long	e	allows the user to organize the commands listed by providing the end date (the timestamp of the end date is used). By default, the end date is the current day	NO

Environment variables

Name	Parameter	Туре	Description	Req <mark>uire</mark> d	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.20 vishnu_list_options

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_options command lists the options of the user

Example of use

vishnu_list_options[-h][-a][-u userId][-n optionName]

Parameters

Parameter	Type	Option	Description	Required
listAllDeftValue	boolean	a	is an option for listing all default option values defined by VISHNU administrator	NO
userId	string	u	is an admin option for listing the options of a specific user	NO
optionName	string	n	allows the user to get the value of a specific option identified by its name	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.21 vishnu_list_users

Access

This command line can be used by ADMIN users only

Description

The vishnu_list_users command lists VISHNU users

Example of use

vishnu_list_users[-h][-i userIdOption]

Parameters

Type	Option	Description	Required
string	i	allows an admin to get information about a	NO
			allows an admin to get information about a

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.22 vishnu_list_sessions

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_sessions command lists all sessions of the user

Example of use

vishnu_list_sessions[-h][-t status][-p sessionClosePolicy][-d sessionInactivityDelay][-m machineId][-a][-u userId][-i sessionId][-s startDateOption][-e endDateOption]

Parameters

Parameter	Type	Option	Description	Required
status	StatusType	t	specifies the status of the sessions which will be listed	NO
sessionClosePolicy	SessionCloseType	p	specifies the closure mode of the sessions which will be listed (CLOSE_ON_TIMEOUT or CLOSE_ON_DISCONNECT)	NO
sessionInactivityDelay	int	d	specifies the inactivity delay in seconds of the sessions which will be listed	NO
machineId	string	m	allows the user to list sessions opened on a specific machine	NO
adminListOption	boolean	a	is an admin option for listing all sessions of all users	NO
userId	string	u	is an admin option for listing sessions opened by a specific user	NO
sessionId	string	i	allows the user to list all commands launched	
startDateOption	long	s	allows the user to organize the commands listed by providing the start date (the UNIX timestamp of the start date is used)	
endDateOption	long	e	allows the user to organize the commands listed by providing the end date (the timestamp of the end date is used). By default, the end date is the current day	NO

Environment variables

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.23 vishnu_configure_default_option

Access

This command line can be used by ADMIN users only

Description

The vishnu_configure_default_option command configures a default option value

Example of use

vishnu_configure_default_option[-h] optionName value

Parameter	Type	Option	Description	Required
optionName	string		represents the name of an option	YES
value	string		represents the value of an option	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.24 vishnu_configure_option

Access

This command line can be used by any VISHNU user

Description

The vishnu_configure_option command configures an option of the user

Example of use

vishnu_configure_option[-h] optionName value

Parameters

Parameter	Type	Option	Description	Required
optionName	string		represents the name of an option	YES
value	string		represents the value of an option	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.2 Parameters definitions

Enumeration UMS::PrivilegeType Type

Name	Value
USER	0
ADMIN	1

Enumeration UMS::SessionCloseType Type

Name	Value
UNDEFINED	0
CLOSE_ON_TIMEOUT	1
CLOSE_ON_DISCONNECT	2

Enumeration UMS::StatusType Type

Name	Value
INACTIVE	0
ACTIVE	1

Chapter 3

Commands specification for Tasks Management Service (TMS)

3.1 Command definitions

3.1.1 vishnu submit job

Access

This command line can be used by any VISHNU user

Description

The vishnu_submit_job command submits job on a machine through the use of a script (scriptFilePath). The script is a shell script which will be executed by a command shell such as sh or csh

Example of use

vishnu_submit_job[-h][-n name][-p priority][-q queue][-t wallTime][-m memory][-P nbCpu][-N n-bNodesAndCpuPerNode][-0 outPutPath][-e errorPath] machineId scriptFilePath

Parameters

Parameter	Туре	Option	Description	Required
machineId	string		Is the id of the machine where the job must be submitted	YES
scriptFilePath	string		The path to the file containing the characteristics (job command, and batch scheduler directive required or optional) of the job to submit.	YES
name	string	n	Assigns a job name. The default is the path of job.	NO
priority	JobPriority	p	Assigns priority of the job.	NO
queue	string	q	Assigns the queue or class of the job.	NO
wallTime	int	t	The maximum wall-clock time during which the job can run.	NO
memory	int	m	Is the memory size that the job requires.	NO
nbCpu	int	P	The number of cpu that the job requires.	NO
nbNodesAndCpuPerNode	string	N	The number of nodes and processors per node.	NO
outPutPath	string	0	Assigns the path and file for job output.	NO
errorPath	string	e	Assigns the path and file for job error.	NO

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.2 vishnu_get_job_info

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_job_info command gets information on a job from its id

Example of use

vishnu_get_job_info[-h] machineId jobId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES
jobId	string	/	The id of the job	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.3 vishnu_get_job_progress

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_job_progress command gets the progression status of jobs

Example of use

vishnu_get_job_progress[-h][-i jobId][-u jobOwner] machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine to get the jobs	YES
machinera sumg	String		progression.	TLS
jobId	string	i	Represents the id of the job that the user wants to	NO
Joold	Sumg	1	see the progression of.	110
jobOwner	string	u	Represents the owner of the job.	NO

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.4 vishnu_list_queues

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_queues command gets queues information

Example of use

vishnu_list_queues[-h] machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.5 vishnu_list_jobs

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_jobs command gets a list of all submitted jobs

Example of use

vishnu_list_jobs[-h][-i jobId][-P nbCpu][-d fromSubmitDate][-D toSubmitDate][-u owner][-s s-tatus][-p priority][-o outPutPath][-e errorPath][-q queue]machineId

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES
jobId	string	i	To list job which has this id.	NO
nbCpu	int	P	To list jobs which have this number of cpu.	NO
fromSubmitDate	long	d	List jobs submitted after this date (unix timestamp).	NO
toSubmitDate	long	D	List jobs submitted before this date (unix timestamp)	NO
owner	string	u	To list all jobs submitted by this owner.	NO
status	JobStatus	S	To list jobs which have this status.	NO

Parameter	Type	Option	Description	Required
priority	JobPriority	p	To list jobs which have this priority	NO
outPutPath	string	0	Gets the path and file for each job output.	NO
errorPath	string	e	Gets the path and file for each job error.	NO
queue	string	q	To list jobs which have this queue name.	NO

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	sessionKev	string	The sessionKey is the identifier of the session	YES	NO
	sessionicy	sumg	generated by VISHNU	1123	110

3.1.6 vishnu_get_job_out_put

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_job_out_put command gets outputPath and errorPath of a job from its id

Example of use

vishnu_get_job_out_put [-h] machineId jobId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES
jobId	string		The Id of the job	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.7 vishnu_get_all_jobs_out_put

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_all_jobs_out_put command dynamically gets outputPath and errorPath of completed jobs

Example of use

vishnu_get_all_jobs_out_put [-h] machineId

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.8 vishnu_cancel_job

Access

This command line can be used by any VISHNU user

Description

The vishnu_cancel_job command cancels a job from its id

Example of use

vishnu_cancel_job[-h] machineId jobId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES
jobId	string		The Id of the job	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.9 vishnu_set_machine_env

Access

This command line can be used by ADMIN users only

Description

The vishnu_set_machine_env command sets environment variables on a remote machine

Example of use

vishnu_set_machine_env[-h] machineId listEnv

Parameters

I	Parameter	Туре	Option	Description	Required
r	nachineId	string		Represents the machine id	YES
1:	istEnv	string		Represents the list environement variables	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.10 vishnu_set_machine_refresh_period

Access

This command line can be used by ADMIN users only

Description

The vishnu_set_machine_refresh_period command sets the refresh period of output and error files contents

Example of use

vishnu_set_machine_refresh_period[-h] machineId value

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
value	int	/	Is the refresh interval value (in seconds)	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.2 Parameters definitions

Enumeration TMS::JobPriority Type

Name	Value
VERY_LOW	100
LOW	200
NORMAL	300
HIGH	400
VERY_HIGH	500

Enumeration TMS::JobStatus Type

Name	Value
RUNNING	0
WAITING	1
COMPLETED	2
CANCELED	3
HELD	4
QUEUED	5
FAILED	6
NOT_SUBMITTED	7

Enumeration TMS::QueuePriority Type

Name	Value
VERY_LOW	0
LOW	1
NORMAL	2
HIGH	3
VERY_HIGH	4

Enumeration TMS::QueueStatus Type

Name	Value
STARTED	0
RUNNING	1
NOT_STARTED	2
NOT_AVAILABLE	3

Chapter 4

Commands specification for Information Management Service (IMS)

4.1 Command definitions

4.1.1 vishnu export commands

Access

This command line can be used by any VISHNU user

Description

The vishnu_export_commands command exports all the commands made by a user during a session

Example of use

vishnu_export_commands [-h] oldSessionId

Parameters

Parameter	Type	Option	Description	Required
oldSessionId	string		The id of the session to export (session has ended)	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command (current session key)	YES	NO

4.1.2 vishnu_get_metric_current_value

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_metric_current_value command retrieve the current value of a metric on a machine

Example of use

vishnu_get_metric_current_value[-h] machineId metricType

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
metricType	MetricType		Type of metric	YES

Environment variables

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the	YES	NO
			command		

4.1.3 vishnu_get_metric_history

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_metric_history command retrieve the history of values of a metric on a machine

Example of use

vishnu_get_metric_history[-h] machineId startTime endTime metricType

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
startTime	long		Start time of metric history	YES
endTime	long		End time of metric history	YES
metricType	MetricType		Type of metric	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.4 vishnu_get_processes

Access

This command line can be used by ADMIN users only

Description

The vishnu_get_processes command gets the list of the processes running over a front machine

Example of use

vishnu_get_processes[-h] machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine the user wants the running	YES
			processes	TES

Environment variables

Name	Parameter	Туре	Description	Required	User option
			The key of the session of the		
VISHNU_SESSION_KEY	sessionKey	string	user that submits the	YES	NO
			command		

4.1.5 vishnu_set_system_info

Access

This command line can be used by ADMIN users only

Description

The vishnu_set_system_info command updates the system information of a machine

Example of use

vishnu_set_system_info[-h][-m memory][-d diskSpace] machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
memory	long	m	Amount of RAM memory available on the machine (in Bytes)	NO
diskSpace	long	d	Amount of disk space available on the machine (in Bytes)	NO

Environment variables

Name	Parameter	Туре	Description	Re <mark>quir</mark> ed	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the	YES	NO
			command		

4.1.6 vishnu_set_system_threshold

Access

This command line can be used by ADMIN users only

Description

The vishnu_set_system_threshold command sets a threshold on a machine of a system

Example of use

 $\verb|vishnu_set_system_threshold[-h]| \textit{machineId thresholdType value}|$

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
thresholdType	MetricType		The type of the metric to set	YES
value	double		The threshold value	YES

Name	Parameter	Туре	Description	Required	User option
			The key of the session of the		
VISHNU_SESSION_KEY	sessionKey	string	user that submits the	YES	NO
			command		

4.1.7 vishnu_get_system_threshold

Access

This command line can be used by ADMIN users only

Description

The vishnu_get_system_threshold command gets a System threshold on a machine

Example of use

vishnu_get_system_threshold[-h] machineId type

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
type	MetricType		The threshold type desired	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.8 vishnu_define_user_identifier

Access

This command line can be used by ADMIN users only

Description

The vishnu_define_user_identifier command defines the shape of the identifiers automatically generated for the users

Example of use

vishnu_define_user_identifier[-h] format

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.9 vishnu_define_machine_identifier

Access

This command line can be used by ADMIN users only

Description

The vishnu_define_machine_identifier command defines the shape of the identifiers automatically generated for the machines

Example of use

vishnu_define_machine_identifier [-h] format

Parameters

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

Environment variables

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.10 vishnu_define_job_identifier

Access

This command line can be used by ADMIN users only

Description

The vishnu_define_job_identifier command defines the shape of the identifiers automatically generated for the jobs

Example of use

 $\verb|vishnu_define_job_identifier[-h]| format|$

Parameters

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.11 vishnu_define_transfer_identifier

Access

This command line can be used by ADMIN users only

Description

The vishnu_define_transfer_identifier command defines the shape of the identifiers automatically generated for the file transfers

Example of use

vishnu_define_transfer_identifier [-h] format

Parameters

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.12 vishnu_load_shed

Access

This command line can be used by ADMIN users only

Description

The vishnu_load_shed command load sheds a machine

Example of use

vishnu_load_shed[-h] machineId loadShedType

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine to stop	YES
			Selects a load shedding mode (SOFT: stops all	
loadShedType	LoadShedType		services and they can be restarted, HARD: stops	YES
			all services, they cannot be restarted)	

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.13 vishnu_set_update_frequency

Access

This command line can be used by ADMIN users only

Description

The vishnu_set_update_frequency command sets the update frequency of the IMS tables

Example of use

vishnu_set_update_frequency[-h] freq

Parameters

Parameter	Type	Option	Description	Required
freq	int		Frequency the data are updated, in second	YES

Environment variables

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of t user that submits the command	he YES	NO

4.1.14 vishnu_get_update_frequency

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_update_frequency command gets the update frequency of the IMS database

Example of use

vishnu_get_update_frequency[-h]

Parameters

This command defines no arguments.

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.15 vishnu_restart

Access

This command line can be used by ADMIN users only

Description

The vishnu_restart command restarts the whole VISHNU infrastructure. Actions are saved and restarted from the beginning once the infrastructure has been restarted

Example of use

vishnu_restart[-h][-n componentName][-m machineId][-f file] type

Parameters

Parameter	Type	Option	Description	Required
type	RestartType		The type of restart	YES
componentName	string	n	If not restarting all, the name of the component to restart	NO
machineId	string	m	The id of the machine where the component is to be relaunched	NO
file	string	f	The config file to use to restart	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.2 Parameters definitions

Enumeration IMS::LoadShedType Type

Name	Va <mark>lue</mark>
SOFT	0
HARD	1

Enumeration IMS::MetricType Type

Name	Value
CPUNBR	0
CPUUSE	1
DISKSPACE	2
FREEDISKSPACE	3
MEMORY	4
FREEMEMORY	5

Enumeration IMS::RestartType Type

Name	Value
ALL	0
SED	1

Name	Value
AGENT	2
DAEMON	3

Chapter 5

Commands specification for File Management Service (FMS)

5.1 Command definitions

5.1.1 vishnu create file

Access

This command line can be used by any VISHNU user

Description

The vishnu_create_file command creates files on remote machines.

Example of use

vishnu_create_file[-h][-m mode] path

Parameters

Parameter	Туре	Option	Description	Required
path	string		The file to create following the pattern [host:]file path	YES
mode	int	m	The file access permissions in octal numeral system	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.2 vishnu_create_dir

Access

This command line can be used by any VISHNU user

Description

The vishnu_create_dir command creates directories on remote machines.

Example of use

vishnu_create_dir[-h][-m mode] path

Parameters

Parameter	Type	Option	Description	Required
path	string		The directory to create following the pattern [host:]directory path	YES
mode	int	m	the new directories permission access in octal numeral system	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.3 vishnu_remove_file

Access

This command line can be used by any VISHNU user

Description

The vishnu_remove_file command removes files from remote hosts.

Example of use

vishnu_remove_file [-h] path

Parameters

Parameter	Type	Option	Description	Required
path	string		The file to remove following the pattern [host:]file path	YES

Environment variables

Name	Parameter	Туре	Description	Re <mark>quir</mark> ed	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.4 vishnu_remove_dir

Access

This command line can be used by any VISHNU user

Description

The vishnu_remove_dir command removes directories (and subdirectories) from remote machines.

Example of use

vishnu_remove_dir[-h] path

Parameters

Parameter	Type	Option	Description	Required
path	string		The directory to remove following the pattern [host:]directory path	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.5 vishnu_ch_grp

Access

This command line can be used by any VISHNU user

Description

The vishnu_ch_grp command changes group owner of remote files/directories.

Example of use

 ${\tt vishnu_ch_grp} \; [-h] \; {\it path group} \;$

Parameters

Parameter	Type	Option	Description	Required
path	string		The file/directory following the pattern [host:]file path	YES
group	string		the new group owner of file/directory	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.6 vishnu_ch_mod

Access

This command line can be used by any VISHNU user

Description

The vishnu_ch_mod command changes access rights of remote files/directories.

Example of use

 $\verb|vishnu_ch_mod[-h]| path mode|$

Parameters

Parameter	Type	Option	Description	Required
path	string		The file/directory following the pattern [host:]file path	YES
mode	int		the access rigths of file/directory in octal system.	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.7 vishnu_head_of_file

Access

This command line can be used by any VISHNU user

Description

The vishnu_head_of_file command displays a few first lines of files located on remote machines.

Example of use

vishnu_head_of_file[-h][-n nLine] path

Parameters

Parameter	Type	Option	Description	Required
path	string		The file following the pattern [host:]file path	YES
nLine	int	n	Number of lines to display	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.8 vishnu_tail_of_file

Access

This command line can be used by any VISHNU user

Description

The vishnu_tail_of_file command displays a few last lines of files located on remote machines

Example of use

 $vishnu_tail_of_file [-h] [-n \ \textit{nLine}] \ \textit{path}$

Parameters

Parameter	Type	Option	Description	Required
path	string		The file following the pattern [host:]file path	YES
nLine	int	n	number of lines to display	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.9 vishnu_content_of_file

Access

This command line can be used by any VISHNU user

Description

The vishnu_content_of_file command displays content of files located on remote machines

Example of use

vishnu_content_of_file [-h] path

Parameters

Parameter	Type	Option	Description	Required
path	string		The file to display following the pattern [host: file path	YES

Environment variables

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.10 vishnu_list_dir

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_dir command displays the content of a remote directory.

Example of use

vishnu_list_dir[-h][-l][-a] path

Parameters

Parameter	Type	Option	Description	Required	
path string	string		The directory to list following the pattern	YES	
	String .		[host:]directory path	125	
longFormat	boolean	1	It specifies the long display format (all available	NO	
	boolean	1	file informations)	110	
allFiles	boolean	a	Allows to display all files including hidden files	NO	

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.11 vishnu_copy_file

Access

This command line can be used by any VISHNU user

Description

The vishnu_copy_file command executes a synchronous copy of file.

Example of use

 $\verb|vishnu_copy_file[-h][-r][-c trCommand]| src dest|\\$

Parameters

Parameter	Type	Option	Description	Required	
src string	string		The source file to copy following the pattern	YES	
	Sumg		[host:]file path	ILS	
dest	string		The path of the destination file	YES	
isRecursive	boolean	. /	It specifies when the copy is recursive (case of	NO	
Iskecuisive	boolean	1	directory) or not.	NO	
trCommand	TransferCommand	c	the command to use to perform file transfer.	NO	

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

5.1.12 vishnu_copy_async_file

Access

This command line can be used by any VISHNU user

Description

The vishnu_copy_async_file command executes an asynchronous copy of file.

Example of use

vishnu_copy_async_file[-h][-r][-c trCommand] src dest

Parameters

Parameter	Type	Option	Description	Required
src st	string		The source file to copy following the pattern	YES
	sumg		[host:]file path	TLS
dest	string		The path of the destination file	YES
isRecursive	boolean		It specifies when the copy is recursive (case of	NO
	boolean	1	directory) or not.	NO
trCommand	TransferCommand	c	the command to use to perform file transfer.	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

5.1.13 vishnu_move_file

Access

This command line can be used by any VISHNU user

Description

The vishnu_move_file command executes a synchronous move of file.

Example of use

vishnu_move_file[-h][-c trCommand] src dest

Parameters

Parameter	Type	Option	Description	Required
src	string		The source file to move following the pattern [host:]file path	YES
dest	string		The path of the destination file	YES
trCommand	TransferCommand	c	the command to use to perform file transfer.	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

5.1.14 vishnu_move_async_file

Access

This command line can be used by any VISHNU user

Description

The vishnu_move_async_file command executes an asynchronous move of file.

Example of use

vishnu_move_async_file[-h][-c trCommand] src dest

Parameters

Parameter	Type	Option	Description	Required
ero	string		The source file to move following the pattern	YES
src string		[host:]file path	ILS	
dest	string		The path of the destination file	YES
trCommand	TransferCommand	c	the command to use to perform file transfer.	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

5.1.15 vishnu_stop_file_transfer

Access

This command line can be used by any VISHNU user

Description

The vishnu_stop_file_transfer command stops an execution of a set of file transfers.

Example of use

vishnu_stop_file_transfer[-h][-i transferId][-m fromMachineId][-u userId]

Parameters

Parameter	Type	Option	Description	Required
transferId	string	i	a given transfer id	NO
fromMachineId	string	m	the machine that is the source of the file transfer	NO
userId	string	u	allows an admin to stop file transfers of a specific user	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.16 vishnu_list_file_transfer_status

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_file_transfer_status command displays the status of all file transfers submitted by User.

Example of use

vishnu_list_file_transfer_status[-h][-i transferId][-m fromMachineId][-u userId]

Parameters

Parameter	Type	Option	Description	Required
transferId	string	i	a given transfer id	NO
fromMachineId	string	m	the machine that is the source of the file transfer	NO
userId	string	u	allows the admin to list file transfers initiated by a specific user	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.17 vishnu_list_file_transfers

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_file_transfers command displays the history of all file transfers submitted by User.

Example of use

vishnu_list_file_transfers[-h][-m fromMachineId][-u userId][-s status]

Parameters

Parameter	Type	Option	Description	Required
fromMachineId	string	m	the machine that is the source of the file transfer	NO
userId	string	u	allows the admin to list file transfers initiated by a specific user	NO
status	Status	S	the file transfer status	NO

Environment variables

Name	Parameter	Type	Description	Desc	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	The s	YES	NO

5.2 Parameters definitions

Enumeration FMS::FileType Type

Name	Value
BLOCK	0
CHARACTER	1
DIRECTORY	2
SYMBOLICLINK	3
SCKT	4
FIFO	5
REGULAR	6

Enumeration FMS::Status Type

Name	V alue
INPROGRESS	0
COMPLETED	1
CANCELLED	2
FAILED	3

Enumeration FMS::TransferCommand Type

Name	Value
SCP	0
RSYNC	1