VISHNU D1.0 - Command line
interface specifications

VISHNU D1.0 - Command line interface specifications



COLLABORATORS

	TITLE : VISHNU D1.0 - Commar fications	nd line interface speci-	
ACTION	NAME	DATE	SIGNATURE
WRITTEN BY	Benjamin Isnard, Daouda Traoré, Eugène Pamba Capo-Chichi, Kevin Coulomb, and Ibrahima Cissé	10 janvier 2011	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
0	05/01/2011	Formatting example	B.Isnard

Table des matières

1	Docu	ument pi	resentation	1
	1.1	Docume	ent objectives	1
	1.2	Docume	ent structure	1
	1.3	Referen	nces	1
	1.4	Glossar	y	1
	1.5	Generic	command definition format	1
2	Com	ımands s	specification for User Man <mark>agement</mark> System (UMS)	3
	2.1	Comma	and definitions	3
		2.1.1	UMS connect	3
		2.1.2	UMS reconnect	4
		2.1.3	UMS addVishnuUser	4
		2.1.4	UMS updateUser	5
		2.1.5	UMS deleteUser	5
		2.1.6	UMS close	6
		2.1.7	UMS changePassword	6
		2.1.8	UMS resetPassword	7
		2.1.9	UMS addLocalAccount	7
		2.1.10	UMS updateLocalAccount	8
		2.1.11	UMS deleteLocalAccount	8
		2.1.12	UMS saveConfiguration	9
		2.1.13	UMS restoreConfiguration	9
		2.1.14	UMS addMachine	10
		2.1.15	UMS deleteMachine	10
		2.1.16	UMS listLocalAccount	11
		2.1.17	UMS listMachine	11
		2.1.18	UMS listOptions	12
		2.1.19	UMS listHistoryCmd	12
		2.1.20	UMS listUsers	13
		2.1.21	UMS listSessions	13
			UMS configureOption	
			UMS configureDefaultOption	
	2.2		ters definitions	

3	Com	ımands s	specification for Tasks Management System (TMS)	16
	3.1	Comma	and definitions	16
		3.1.1	TMS submitJob	16
		3.1.2	TMS listJobs	17
		3.1.3	TMS getJobInfo	17
		3.1.4	TMS cancelJob	18
		3.1.5	TMS getJobOutPut	18
		3.1.6	TMS getAllJobsOutPut	19
		3.1.7	TMS listQueues	19
		3.1.8	TMS setMachineEnv	20
		3.1.9	TMS setMachineRefreshPeriod	20
		3.1.10	TMS getJobProgress	21
	3.2	Parame	ters definitions	21
	C	,		22
4			specification for Information Management System (IMS)	23
	4.1		and definitions	
			IMS getUpdateFrequency	
			IMS export	
			IMS getMetricVal	
			IMS getCurrentData	
			IMS getProcesses	
			IMS setSystemThreshold	
			IMS getSystemThreshold	
			IMS defineUserIdentifier	
			IMS defineMachineIdentifier	
			IMS defineJobIdentifier	
			IMS defineTransferIdentifier	
			IMS loadShed	
			IMS setUpdateFrequency	
			IMS restart	
	4.2		ters definitions	
	4.2	Parame	ters definitions	31
5	API	specifica	ation for File Management System (FMS)	32
	5.1	Comma	and definitions	32
		5.1.1	FMS createFile	32
		5.1.2	FMS createDir	32
		5.1.3	FMS removeFile	33

5.1.4	FMS removeDir	33
5.1.5	FMS chGrpOfFile	34
5.1.6	FMS chModOfFile	34
5.1.7	FMS headOfFile	35
5.1.8	FMS tailOfFile	35
5.1.9	FMS listDir	35
5.1.10	FMS copyFile	36
5.1.11	FMS copyAsyncFile	36
5.1.12	FMS moveFile	37
5.1.13	FMS moveAsyncFile	37
5.1.14	FMS stopFileTransfer	38
5.1.15	FMS stopAllFileTransfer	38
5.1.16	FMS stopAllUsersFileTransfer	39
5.1.17	FMS getFileTransferStatus	39
5.1.18	FMS listFilesTransferStatus	40
5.1.19	FMS listAllUsersFilesTransferStatus	40
5.1.20	FMS DisplayFilesTransferHistory	41
5.1.21	FMS DisplayAllUsersFilesTransferHistory	41
	FMS GetFilesInfo	
Doroma	store definitions	42

Chapitre 1

Document presentation

1.1 Document objectives

This document presents the detailed specifications of the Vishnu command line user interface.

These specifications include the definition of all commands. ###FIXME###

1.2 Document structure

The document is divided into 4 parts corresponding to the 4 modules that compose the Vishnu system:

- UMS: Users Management System
- TMS: Tasks Management System
- FMS: Files Management System
- IMS : Information Management System

Each module corresponds to a chapter in the document, and each chapter contains the following sections:

- A first section describing the definition of all commands provided by the package
- A second section describing the definition of all data types used ###FIXME###

1.3 References

TODO - ajouter ref. vers les specs générales

1.4 Glossary

1.5 Generic command definition format

This section presents the generic format used in the following chapters to describe the commands. It also details the environment variables required and the user options.

A commands is defined as follows:

Access

Here is detailed the access of the command line for any VISHNU user or only for admin.

Description

Here is detailed the purpose of the command line.

Example of use

Here is detailed an example of the use of the command line which start by optional arguments preceded by a short letter and the required arguments at the end.

myCommand -l acLogin -s sshKeyPath userId

Parameters

The following table contains all the input arguments of the command with their type and description, their short letter for options and a required flag.

Parameter	Type	Option	Description	Requ <mark>ired</mark>
userId	string		This is an example of a required argument	YES
acLogin	string	1	This is an example of an optional argument	NO
sshKeyPath	string	S	This is an example of an optional argument	NO

The following table contains the list of environment variables information, a required flag and a user option flag. The user option flag means that this parameter is a user option that can be define as an environment variable.

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	This is an example of an environment variable	YES	NO

Chapitre 2

Commands specification for User Management System (UMS)

2.1 Command definitions

2.1.1 UMS connect

Access

This command line can be used by any Vishnu user.

Description

The connect command line opens a session

Example of use

connect -p closePolicy -d sessionInactivityDelay -s substituteUserId userId

Parameters

Parameter	Type	Option	Description	Required	
userId	string		userId represents the VISHNU user identifier	YES	
password string			password represents the password of the user, it is an interactive parameter	YES	
closePolicy	SessionCloseType			NO	
sessionInactivityDelay	int	d	The sessionInactivityDelay is the maximum delay between two API commands when the CLOSE_ON_TIMEOUT option is set	NO	
substituteUserId	string	s	is an option which allows an admin to open a session as he/she was a specific user identified by his/her userId	NO	

Name	Parameter	Туре	Description	Required	User option
VISHNU_CLOSE_POLICY	closePolicy	SessionCloseType	is an option for closing session automatically	NO	YES

2.1.2 UMS reconnect

Access

This command line can be used by any Vishnu user.

Description

The reconnect command line returns the sessionKey of a session in which the user was disconnected previously without closing it

Example of use

reconnect userId sessionId

Parameters

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier	YES
password	string		password represents the password of the user, it is an interactive parameter	YES
sessionId	string		sessionId is the identifier of the session defined in the database	YES

Environment variables

Nama	Parameter	Tyme	Dogarintian	Required	User
Name	Farameter	Туре	Description	Kequireu	option

2.1.3 UMS addVishnuUser

Access

This command line can be used by ADMIN users only

Description

The addVishnuUser command line adds a new VISHNU user

Example of use

addVishnuUser -w password -f firstname -l lastname -p privilege -m email userId

Parameters

Parameter	Type	Option	Description	Required
userId	string		represents the VISHNU user identifier	YES
			is the password of the user. At the beginning, an	
password	string	W	admin can give a temporary password or it is	NO
			automatically generated by the System.	
firstname	string	f	is the firstname of the user	NO
lastname	string	1	is the lastname of the user	NO
privilege	int	p	is the privilege of the user (admin or simple user)	NO
email	string	m	is the email of the user	NO

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.4 UMS updateUser

Access

This command line can be used by ADMIN users only

Description

The updateUser command line updates the user information except the userId and password

Example of use

updateUser -f firstname -l lastname -p privilege -m email userId

Parameters

Parameter	Type	Or	otion	Description	Required
firstname	string	f		represents the updated firstname of the user	NO
lastname	string	1		represents the updated lastname of the user	NO
privilege	string	p		represents the updated privilege of the user	NO
email	string	m		represents the updated email adress of the user	NO
userId	string			represents the VISHNU user identifier of the user	YES
	sumg			whose information will be updated	1 LO

Environment variables

Name	Parameter	Type	Description	Required	User option
			The sessionKey is the		
VISHNU_SESSION_KEY	sessionKey	string	identifier of the session	YES	NO
			generated by VISHNU		

2.1.5 UMS deleteUser

Access

This command line can be used by ADMIN users only

Description

The deleteUser command line removes a user from VISHNU

Example of use

deleteUser userId

Parameters

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier of the user who will be deleted from VISHNU	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.6 UMS close

Access

This command line can be used by any Vishnu user.

Description

The close command line closes the session identified by the session key

Example of use

close

Parameters

This command defines no arguments.

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session	YES	NO
			generated by VISHNU		

2.1.7 UMS changePassword

Access

This command line can be used by any Vishnu user.

Description

The changePassword command line changes the password

Example of use

changePassword userId

Parameters

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier	YES
password	string		password represents the password of the user, it is an interactive parameter	YES
passwordNew	string		passwordNew represents the new password of the user, it is an interactive parameter	YES

Nama	Danamatan	Type	Decarintian	Doguinad	User
Name	Farameter	Type	Description	Kequireu	option

2.1.8 UMS resetPassword

Access

This command line can be used by ADMIN users only

Description

The resetPassword command line resets the password of a user

Example of use

resetPassword userId

Parameters

Parameter	Type	Option	Description	Req <mark>uired</mark>
userId	string		userId represents the VISHNU user identifier of the user whose password will be reset	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.9 UMS addLocalAccount

Access

This command line can be used by any Vishnu user.

Description

The addLocalAccount command line adds a new local user configuration

Example of use

addLocalAccount -l acLogin -s sshKeyPath -h HomeDirectory userId machineId

Parameters

Parameter	Type	Option	Description	Required
userId	string		The userId represents the VISHNU user identifier of the user of the local user configuration	YES
machineId	string		The MachineId represents the identifier of the machine associated to the local user configuration	YES
acLogin	string	1	accLogin represents the login of the user on the associated machine	NO
sshKeyPath	string	s	sshKeyPath is the path of the ssh key of the user on the associated machine	NO
HomeDirectory	string	h	HomeDirectory is the path of the home directory of the user on the associated machine	NO

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.10 UMS updateLocalAccount

Access

This command line can be used by any Vishnu user.

Description

The updateLocalAccount command line updates a local user configuration

Example of use

updateLocalAccount -l acLogin -s sshKeyPath -h HomeDirectory userId machineId

Parameters

Parameter	Type		Option	Description	Required	
userId string	string			The userId represents the VISHNU user identifier	YES	
useriu	Sumg			of the user of the local user configuration	1123	
machineId string			The MachineId represents the identifier of the	YES		
			machine associated to the local user configuration	ILS		
acLogin	acLogin string		1	accLogin represents the login of the user on the	NO	
acLogiii	sumg			associated machine		
sshKeyPath	string		c	sshKeyPath is the path of the ssh key of the user	NO	
ssificeyradi		5	on the associated machine			
HomeDirectory str	string		h	HomeDirectory is the path of the home directory	NO	
	sumg		11	of the user on the associated machine	NO	

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.11 UMS deleteLocalAccount

Access

This command line can be used by any Vishnu user.

Description

The deleteLocalAccount command line removes a local user configuration (for a given user on a given machine) from VISHNU

Example of use

deleteLocalAccount userId machineId

Parameter	Type	Option	Description	Required
			userId represents the VISHNU user identifier of	
userId	string		the user whose local configuration will be deleted	YES
			for the given machine	
			machineId represents the identifier of the	
machineId	string		machine whose local configuration will be	YES
			deleted for the given user	

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.12 UMS saveConfiguration

Access

This command line can be used by ADMIN users only

Description

The saveConfiguration command line saves the configuration of VISHNU

Example of use

saveConfiguration

Parameters

This command defines no arguments.

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.13 UMS restoreConfiguration

Access

This command line can be used by ADMIN users only

Description

The restoreConfiguration command line restores the configuration of VISHNU

Example of use

restoreConfiguration -d descConf

Parameter	Type	Option	Description	Required
descConf	string	d	represents the description of the configuration	NO

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.14 UMS addMachine

Access

This command line can be used by ADMIN users only

Description

The addMachine command line adds a new machine in VISHNU

Example of use

addMachine -n name -s site -d totalDiskSpace -m totalMemory -t machineDescription -l language machineId

Parameters

Parameter	Type	0	ption	Description	Required
machineId	string			represents the identifier of the machine	YES
name	string	n		represents the name of the machine	NO
site	string	S		represents the location of the machine	NO
totalDiskSpace	string	d		represents the total disk space of the machine	NO
totalMemory	string	m	ı	represents the total memory of the machine	NO
machineDescription	string	t		represents the description of the machine	NO
language	string	1		represents the language in which the description has been done	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
			The sessionKey is the		
VISHNU_SESSION_KEY	sessionKey	string	identifier of the session	YES	NO
			generated by VISHNU		

2.1.15 UMS deleteMachine

Access

This command line can be used by ADMIN users only

Description

The deleteMachine command line removes a machine from VISHNU

Example of use

deleteMachine machineId

Parameter	Type	Option	Description	Required
machineId	string		machineId represents the identifier of the machine	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.16 UMS listLocalAccount

Access

This command line can be used by any Vishnu user.

Description

The listLocalAccount command line lists the local user configurations

Example of use

listLocalAccount -a -u userId -i machineId

Parameters

Parameter	Type	Option	Description	Required
AdminListOption	boolean	a	is an admin option for listing all local configurations of all users	NO
userId	string	ů	is an admin option for listing the local configurations of a specific user	NO
machineId	string	i	is an option for listing local user configurations on a specific machine	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.17 UMS listMachine

Access

This command line can be used by any Vishnu user.

Description

The listMachine command line lists the machines in which local user configurations are defined for the given user

Example of use

listMachine -u userId -a -m machineId

Parameter	Type	Option	Description	Required
userId	string	u	is an admin option for listing machines in which a specific user has a local configuration	NO
ListAllOption	boolean	a	is an admin option for listing all machine defined in the database	NO

Parameter	Type	Option	Description	Required
machineId	string	m	is an option for listing information about a specific machine	NO

Name	Parameter	Туре	Description	Required	User option
			The sessionKey is the		
VISHNU_SESSION_KEY	sessionKey	string	identifier of the session	YES	NO
			generated by VISHNU		

2.1.18 UMS listOptions

Access

This command line can be used by any Vishnu user.

Description

The listOptions command line lists the options of the user

Example of use

listOptions -a -u userId -n optionName

Parameters

Parameter	Type	Option	Description	Required
AdminListOption	boolean	a	is an admin option for listing all user options defined in VISHNU	NO
userId	string	u	is an admin option for listing the options of a specific user	NO
optionName	string	n	allows the user to list a specific option identified by its name	NO

Environment variables

Name	Parameter	Type	Description	Re <mark>qui</mark> red	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.19 UMS listHistoryCmd

Access

This command line can be used by any Vishnu user.

Description

The listHistoryCmd command line lists the commands

Example of use

listHistoryCmd -a -u userId -i sessionId -s startDateOption -e endDateOption

Parameter	Type	Option	Description	Required
AdminListOption	boolean	a	is an admin option for listing all commands of all	NO
1			users	
userId	string	u	is an admin option for listing commands launched	NO
usciiu	Sumg	u u	by a specific user identified by his/her userId	110
sessionId	atrina	. /	lists all commands launched within a specific	NO
sessioniu	string	1	session	NO
			allows the user to organize the commands listed	_
startDateOption	long	S	by providing the start date (the UNIX timestamp	NO
			of the start date is used)	
			allows the user to organize the commands listed	
and Data Ontion	long		by providing the end date (the timestamp of the	NO
endDateOption	long	e	end date is used). By default, the end date is the	NO
			current day	

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.20 UMS listUsers

Access

This command line can be used by ADMIN users only

Description

The listUsers command line lists users

Example of use

listUsers -i userIdOption

Parameters

Parameter	Type	Option	Description	Required
userIdOption	string	i	allows an admin to list one user identified by his/her userId	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.21 UMS listSessions

Access

This command line can be used by any Vishnu user.

Description

The listSessions command line lists all sessions of the user

Example of use

listSessions -t sessionListOption -p sessionClosePolicy -d sessionInactivityDelay -m machineId -a -u userId -i sessionId -s start-DateOption -e endDateOption

Parameters

Parameter	Type	Option	Description	Required
sessionListOption	SessionStateType	t	specifies the type of the sessions which will be listed (INACTIVE or ACTIVE)	NO
sessionClosePolicy	SessionCloseType	p	specifies the closure mode of the sessions which will be listed (CLOSE_ON_TIMEOUT or CLOSE_ON_DISCONNECT)	NO
sessionInactivityDelay	int	d	specifies the inactivity delay of the sessions which will be listed	NO
machineId	string	m	allows the user to list sessions opened on a specific machine	NO
AdminListOption	boolean	a	is an admin option for listing all sessions of all users	NO
userId	string	u	is an admin option for listing sessions opened by a specific user	NO
sessionId	string	i	allows the user to list all commands launched within a specific session	NO
startDateOption	long	S	allows the user to organize the commands listed by providing the start date (the UNIX timestamp of the start date is used)	NO
endDateOption	long	e	allows the user to organize the commands listed by providing the end date (the timestamp of the end date is used). By default, the end date is the current day	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.22 UMS configureOption

Access

This command line can be used by any Vishnu user.

Description

The configureOption command line configures an option

Example of use

configureOption optionName value

Parameter	Type	Option	Description	Required
optionName	string		represents the name of an option	YES
value	string		represents the value of an option	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.23 UMS configureDefaultOption

Access

This command line can be used by ADMIN users only

Description

The configureDefaultOption command line configures a default option value

Example of use

configureDefaultOption optionName value

Parameters

Parameter	Type	Option	Description	Required
optionName	string		represents the name of an option	YES
value	string		represents the value of an option	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.2 Parameters definitions

Enumeration UMS::SessionCloseType Type

Name	Value
CLOSE_ON_DISCONNECT	0
CLOSE_ON_TIMEOUT	1

Enumeration UMS: :SessionStateType Type

Name	Value
INACTIVE	0
ACTIVE	1

Chapitre 3

Commands specification for Tasks Management System (TMS)

3.1 Command definitions

3.1.1 TMS submitJob

Access

This command line can be used by any Vishnu user.

Description

The submitJob command line submits job on a machine through the use of a script (scriptFilePath). The script is a shell script which will be executed by a command shell such as sh or csh.

Example of use

submitJob -n name -p priority -q queue -t wallTime -m memory -P nbCpu -N nbNodesAndCpuPerNode -o OutPutPath -e Error-Path machineId scriptFilePath

Parameters

Parameter	Type	Option	Description	Required
machineId	string	Is the id of the machine where the job must be submitted		YES
scriptFilePath	string	The path to the file containing the characteristics (job command, and batch scheduler directive required or optional) of the job to submit.		YES
name	string	n	Assigns a job name. The default is the name of job path.	NO
priority	JobPriority	p	Assigns priority of the job.	NO
queue	string	q	Assigns the queue or class of the job.	NO
wallTime	int	t	The maximum wall-clock time during which the job can run.	NO
memory	int	m	The size of memory that the job will use.	NO
nbCpu	int	P	The number of cpu that the job will use.	NO
nbNodesAndCpuPerNode	int	N	The number of nodes and processors per node.	NO
OutPutPath	string	0	Assigns the path and file for job output.	NO
ErrorPath	string	e	Assigns the path and file for job error.	NO

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.2 TMS listJobs

Access

This command line can be used by any Vishnu user.

Description

The listJobs command line gets a list of all submitted jobs

Example of use

listJobs -i JobId -P nbCpu -d fromSubmitDate -D toSubmitDate -u owner -s status -p priority -o OutPutPath -e ErrorPath -q queue machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string	/	Machine hash key	YES
JobId	string	i	To list job which has this id.	NO
nbCpu	int	P	To list jobs which have this number of cpu.	NO
fromSubmitDate	long	d	List jobs submitted after this date (unix timestamp).	NO
toSubmitDate	long	D	List jobs submitted before this date (unix timestamp)	NO
owner	string	u	To list all jobs submitted by this owner.	NO
status	JobStatus	S	To list jobs which have this status.	NO
priority	JobPriority	p	To list jobs which have this priority	NO
OutPutPath	string	0	Gets the path and file for each job output.	NO
ErrorPath	string	e	Gets the path and file for each job error.	NO
queue	string	q	To list jobs which have this queue name.	NO

Environment variables

Name	Parameter	Туре	Description	Req <mark>uir</mark> ed	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.3 TMS getJobInfo

Access

This command line can be used by any Vishnu user.

Description

The getJobInfo command line gets information on a job from it Id

Example of use

getJobInfo machineId jobId

Parameter	Type	Option Description	Required
machineId	string	Machine hash key	YES
jobId	string	The id of the job	YES

Name	Parameter	Туре	Description	Required	User option
			The sessionKey is the		
VISHNU_SESSION_KEY	sessionKey	string	identifier of the session	YES	NO
			generated by VISHNU		

3.1.4 TMS cancelJob

Access

This command line can be used by any Vishnu user.

Description

The cancelJob command line cancels a job from it Id

Example of use

cancelJob machineId jobId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES
jobId	string		The Id of the job	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.5 TMS getJobOutPut

Access

This command line can be used by any Vishnu user.

Description

The getJobOutPut command line gets outputPath and errorPath of a job from it Id

Example of use

getJobOutPut machineId jobId

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES
jobId	string		The Id of the job	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.6 TMS getAllJobsOutPut

Access

This command line can be used by any Vishnu user.

Description

The getAllJobsOutPut command line gets outputPath and errorPath of completed jobs dynamically

Example of use

getAllJobsOutPut machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.7 TMS listQueues

Access

This command line can be used by any Vishnu user.

Description

The listQueues command line gets queues information

Example of use

listQueues machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.8 TMS setMachineEnv

Access

This command line can be used by ADMIN users only

Description

The setMachineEnv command line sets environment variables on a remote machine

Example of use

setMachineEnv machineId listEnv

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Represents the machine id	YES
listEnv	string	/	Represents the list environement variables	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.9 TMS setMachineRefreshPeriod

Access

This command line can be used by ADMIN users only

Description

The setMachineRefreshPeriod command line sets the refresh period of output and error file content

Example of use

setMachineRefreshPeriod machineId value

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
value	int		Is the refresh interval value (in seconds)	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.10 TMS getJobProgress

Access

This command line can be used by any Vishnu user.

Description

The getJobProgress command line get the progression status of jobs.

Example of use

getJobProgress -i jobId -u jobOwner machineId

Parameters

Parameter	Type		Option	Description	Required
machineId string	string	ıg		Is the id of the machine to get the jobs	YES
macminera	String		7	progression.	1 LS
jobId	string		i	Represents the id of the job that the user wants to	NO
joold	Sumg		1	see its progression.	110
jobOwner	string		u	Represents the owner of the job.	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.2 Parameters definitions

Enumeration TMS:: JobPriority Type

Name	Value
VERY_LOW	100
LOW	200
NORMAL	300
HIGH	400
VERY_HIGH	500

Enumeration TMS:: JobStatus Type

Name	Value
RUNNING	0
WAITING	1
COMPLETED	2
CANCELED	3
HELD	4

Name	Value
QUEUED	5
FAILED	6
NOT_SUBMITTED	7

Enumeration TMS::QueuePriority Type

Name	Value
VERY_LOW	0
LOW	1
NORMAL	2
HIGH	3
VERY_HIGH	4

Enumeration TMS : : QueueStatus Type

Name		V alue
STARTED		0
RUNNING		1
NOT_STAR	TED	2
NOT_AVAII	LABLE	3

Chapitre 4

Commands specification for Information Management System (IMS)

4.1 Command definitions

4.1.1 IMS getUpdateFrequency

Access

This command line can be used by any Vishnu user.

Description

The getUpdateFrequency command line gets the update frequency of the IMS database

Example of use

getUpdateFrequency

Parameters

This command defines no arguments.

Environment variables

Name	Parameter	Туре	Description	Re <mark>quir</mark> ed	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.2 IMS export

Access

This command line can be used by any Vishnu user.

Description

The export command line exports all the commands made by a user during a session

Example of use

export oldSessionKey exportType

Parameter	Type	Option	Description	Required
oldSessionKey	string		The key of the session to export (session has ended)	YES
exportType	ExportType		The format to export	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command (current session key)	YES	NO

4.1.3 IMS replay

Access

This command line can be used by any Vishnu user.

Description

The replay command line replays a script of VISHNU commands

Example of use

replay filename type

Parameters

Parameter	Type	Option	Description	Required
filename	string		A file containing the commands to replay	YES
type	ExportType	\ \ \	The type of the script to execute (python, shell)	YES

Environment variables

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.4 IMS getMetricVal

Access

This command line can be used by any Vishnu user.

Description

The getMetricVal command line gets data from a metric

Example of use

getMetricVal machineId startTime endTime metricType

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES

Parameter	Type	Option	Description	Required
startTime	long		The start time to look for the metric	YES
endTime	long		The end time to search	YES
metricType	MetricType		The metric types	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.5 IMS getCurrentData

Access

This command line can be used by any Vishnu user.

Description

The getCurrentData command line gets data corresponding to the datatype on a machine

Example of use

getCurrentData machineId dataType

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine the user wants the total diskSpace	YES
dataType	MetricType		The type of data the user wants to get	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.6 IMS getProcesses

Access

This command line can be used by ADMIN users only

Description

The getProcesses command line gets the list of the processes running over a front machine

Example of use

getProcesses machineId

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine the user wants the running	YES
			processes	1 LS

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the	YES	NO
			command		

4.1.7 IMS setSystemThreshold

Access

This command line can be used by ADMIN users only

Description

The setSystemThreshold command line sets a threshold on a machine of a system

Example of use

setSystemThreshold machineId tresholdType value

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine the user wants to set the treshold over	YES
tresholdType	MetricType		The type of the metric to set	YES
value	double		The treshold value	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.8 IMS getSystemThreshold

Access

This command line can be used by ADMIN users only

Description

The getSystemThreshold command line gets a System threshold on a machine

Example of use

 $getSystemThreshold\ machine Id\ type$

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine the user wants to get the treshold over	YES
type	MetricType		The treshold type desired	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.9 IMS defineUserIdentifier

Access

This command line can be used by ADMIN users only

Description

The defineUserIdentifier command line defines the shape of the identifiers automatically generated for the users

Example of use

defineUserIdentifier format

Parameters

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.10 IMS defineMachineIdentifier

Access

This command line can be used by ADMIN users only

Description

The defineMachineIdentifier command line defines the shape of the identifiers automatically generated for the machines

Example of use

defineMachineIdentifier format

Parameter	Type	Option Description		Required
format	string		The new format to use	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.11 IMS defineJobIdentifier

Access

This command line can be used by ADMIN users only

Description

The defineJobIdentifier command line defines the shape of the identifiers automatically generated for the jobs

Example of use

defineJobIdentifier format

Parameters

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.12 IMS defineTransferIdentifier

Access

This command line can be used by ADMIN users only

Description

The defineTransferIdentifier command line defines the shape of the identifiers automatically generated for the file transfers

Example of use

defineTransferIdentifier format

Parameters

Parameter	Type	Option Description		Required
format	string		The new format to use	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.13 IMS loadShed

Access

This command line can be used by ADMIN users only

Description

The loadShed command line loads shed a machine, 2 modes are available, soft or hard. Soft flushes the machine, hard stops the machine

Example of use

loadShed machineId loadShedType

Parameters

Parameter	Type	Option	Description	Required
machineId	string	/	The id of the machine to stop	YES
loadShedType	LoadShedType		Type of load shedding	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the	YES	NO
VISHNU_SESSION_KEY	sessionKey	string	user that submits the command	YES	

4.1.14 IMS setUpdateFrequency

Access

This command line can be used by ADMIN users only

Description

The setUpdateFrequency command line sets the update frequency of the IMS tables

Example of use

setUpdateFrequency freq

Parameters

Parameter	Type	Option	Description	Required
freq	int		Frequency the data are updated, in second	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.15 IMS restart

Access

This command line can be used by ADMIN users only

Description

The restart command line restarts the whole VISHNU infrastructure. Actions are saved and restarted from the beginning once the infrastructure has been restarted

Example of use

restart -n componentName type

Parameters

Parameter	Type	Option	Description	Required
type	RestartType	t	The type of restart desired	YES
componentName	string	n	If not restarting all, the name of the component to restart	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.16 IMS updateMachine

Access

This command line can be used by ADMIN users only

Description

The updateMachine command line updates the machines information in the database (description, diskspace or memory)

Example of use

updateMachine -l lang machineId CompoMachine

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine to update	YES
CompoMachine	CompoMachine		A description of the type of component to change	YES
lang	string	1	For machine description, the language used	NO

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.2 Parameters definitions

Enumeration IMS::CompoMachine Type

Name	Value
DESC	0
DISKSPACE	1
RAM	2

Enumeration IMS : :ExportType Type

Name		Value
PYTHON		0
SHELL	7	1

Enumeration IMS::LoadShedType Type

Name	Value
SOFT	0
HARD	1

Enumeration IMS: :MetricType Type

Name	Val ue
CPUNBR	0
CPUUSE	1
DISKSPACE	2
FREEDISKSPACE	3
MEMORY	4
FREEMEMORY	5

Enumeration IMS::RestartType Type

Name	Value
ALL	0
SED	1
AGENT	2
DAEMON	3
MACHINE	4

Chapitre 5

API specification for File Management System (FMS)

5.1 Command definitions

5.1.1 FMS createFile

Access

This command line can be used by any Vishnu user.

Description

The createFile command line creates files on remote machines.

Example of use

createFile -m mode machineId sessionKey -null listOfStrings

Parameters

Parameter	Type	Option	D escription	Require
machineId	string		The machine identifier	YES
sessionKey	string		The session identifier	YES
listOfStrings	string		the dynamic list of strings.	NO
mode	long	m	the file access permissions.	NO

Environment variables

Name	Parameter	Type	Description	Required	User
Name	1 at affected	Туре	Description	Kequireu	option

5.1.2 FMS createDir

Access

This command line can be used by any Vishnu user.

Description

The createDir command line creates directories on remote machines.

Example of use

createDir -m mode machineId sessionKey -null listOfStrings

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session idientifier	YES
listOfStrings	string		the dynamic list of strings.	NO
mode	long	m	the new directories permission access.	NO

Environment variables

Name Parame	ter Type	Description	Required User option
-------------	----------	-------------	----------------------

5.1.3 FMS removeFile

Access

This command line can be used by any Vishnu user.

Description

The removeFile command line removes files from remote hosts.

Example of use

removeFile machineId sessionKey -null listOfStrings

Parameters

Parameter	Type	Option	D escription	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session id	YES
listOfStrings	string		the dynamic list of strings.	NO

Environment variables

me Parameter T	lvne	Description	R <mark>equi</mark> red	User option
----------------	------	-------------	-------------------------	----------------

5.1.4 FMS removeDir

Access

This command line can be used by any Vishnu user.

Description

The removeDir command line removes directories (and subdirectories) from remote machines.

Example of use

removeDir machineId sessionKey -null listOfStrings

Parameter	Type	Option	Description	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session id	YES
listOfStrings	string		the dynamic list of strings.	NO

Name	Parameter	Туре	Description	Rec	quired User option	
------	-----------	------	-------------	-----	--------------------	--

5.1.5 FMS chGrpOfFile

Access

This command line can be used by any Vishnu user.

Description

The chGrpOfFile command line changes group owner of remote files.

Example of use

chGrpOfFile machineId sessionKey -null listOfStrings group

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session id	YES
listOfStrings	string	7	the dynamic list of strings.	NO
group	string		the new group owner of files.	YES

Environment variables

Nama	Danamatan	Type	Decarintian	Required User
Name	Parameter	Туре	Description	option

5.1.6 FMS chModOfFile

Access

This command line can be used by any Vishnu user.

Description

The chModOfFile command line changes access rights of remote files.

Example of use

chModOfFile machineId sessionKey -null listOfStrings mode

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session id	YES
listOfStrings	string		the dynamic list of strings.	NO
mode	long		the access rigths of a file	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
------	-----------	------	-------------	----------	----------------

5.1.7 FMS headOfFile

Access

This command line can be used by any Vishnu user.

Description

The headOfFile command line displays a few first lines of files located on remote machines.

Example of use

headOfFile -n nLine machineId sessionKey -null listOfStrings

Parameters

Parameter	Type	Option	Description	Req <mark>uire</mark> d
machineId	string		The machine identifier	YES
sessionKey	string		The session id	YES
listOfStrings	string		the dynamic list of strings.	NO
nLine	int	n	number of lines to display	NO

Environment variables

Nama	Doromotor	Type	Description	Required	User
Name	Parameter	Type	Description	Required	option

5.1.8 FMS tailOfFile

Access

This command line can be used by any Vishnu user.

Description

The tailOfFile command line displays a few last lines of files located on remote machines

Example of use

tailOfFile -n nLine machineId sessionKey -null listOfStrings

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session id	YES
listOfStrings	string		the dynamic list of strings.	NO
nLine	int	n	number of lines to display	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
					option

5.1.9 FMS listDir

Access

This command line can be used by any Vishnu user.

Description

The listDir command line displays the contents of remote directory.

Example of use

listDir machineId sessionKey -null listOfStrings -

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session id	YES
listOfStrings	string		the dynamic list of strings.	NO
isRecursive	boolean	TO DO	TO DO	NO

Environment variables

Name Parameter	Туре	Description	Required User option
----------------	------	-------------	----------------------

5.1.10 FMS copyFile

Access

This command line can be used by any Vishnu user.

Description

The copyFile command line executes a synchronous copy of file.

Example of use

copyFile - -c transferCommand machineId sessionKey -null listOfStrings dest

Parameters

Parameter	Type	Option	Des cription	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session ididentifier	YES
listOfStrings	string		the dynamic list of strings.	NO
dest	string		The path of the destination file	YES
isRecursive	boolean	TO DO	TO DO	NO
transferCommand	TransferCommand	c	the command to use to perform file transfer.	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_TRANSFER_CMD	transferComma	nd Fransfer Command	the command to use to perform file transfer.	NO	YES

5.1.11 FMS copyAsyncFile

Access

This command line can be used by any Vishnu user.

Description

The copyAsyncFile command line executes an asynchronous copy of file.

Example of use

copyAsyncFile - -c transferCommand machineId sessionKey -null listOfStrings dest

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session identifier	YES
listOfStrings	string		the dynamic list of strings.	NO
dest	string		The path of the destination file	YES
isRecursive	boolean	TO DO	TO DO	NO
transferCommand	TransferCommand	С	the command to use to perform file transfer.	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_TRANSFER_CMD	transferComma	nd Fransfer Comma	the command to use to perform file transfer.	NO	YES

5.1.12 FMS moveFile

Access

This command line can be used by any Vishnu user.

Description

The moveFile command line executes a synchronous move of file.

Example of use

moveFile -c transferCommand machineId sessionKey -null listOfStrings dest

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session identifier	YES
listOfStrings	string		the dynamic list of strings.	NO
dest	string		The path of the destination file	YES
transferCommand	TransferCommand	c	the command to use to perform file transfer.	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_TRANSFER_CMD	transferComma	nd Fransfer Command	the command to use to perform file transfer.	NO	YES

5.1.13 FMS moveAsyncFile

Access

This command line can be used by any Vishnu user.

Description

The moveAsyncFile command line executes an asynchronous move of file.

Example of use

moveAsyncFile -c transferCommand machineId sessionKey -null listOfStrings dest

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session identifier	YES
listOfStrings	string		the dynamic list of strings.	NO
dest	string		The path of the destination file	YES
transferCommand	TransferCommand	c	the command to use to perform file transfer.	NO

Environment variables

Name	Parameter	Туре	1	Description	Required	User option
VISHNU_TRANSFER_CMD	transferCom <mark>ma</mark>	nd Fransfer Com	mand	the command to use to perform file transfer.	NO	YES

5.1.14 FMS stopFileTransfer

Access

This command line can be used by any Vishnu user.

Description

The stopFileTransfer command line stops an execution of an set of file transfer.

Example of use

stopFileTransfer machineId sessionKey - listOfLongs

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session identifier	YES
listOfLongs	long	TO DO	TO DO	NO

Environment variables

Name Parameter Type Description	Required	User option
---------------------------------	----------	----------------

5.1.15 FMS stopAllFileTransfer

Access

This command line can be used by any Vishnu user.

Description

The stopAllFileTransfer command line stops all file transfer in a session.

Example of use

stopAllFileTransfer -k sessionKey -m machineId -n nbFileTransfers -s status -u userId

Parameters

Parameter	Type	Option	Description	Required
sessionKey	string	k	the command to use to perform file transfer.	NO
machineId	string	m	the command to use to perform file transfer.	NO
nbFileTransfers	int	n	the command to use to perform file transfer.	NO
status	Status	S	the command to use to perform file transfer.	NO
userId	string	u	the user identifier	NO

Environment variables

Name	Parameter	Type	Description	Required Use opti	
				oper	011

5.1.16 FMS stopAllUsersFileTransfer

Access

This command line can be used by ADMIN users only

Description

The stopAllUsersFileTransfer command line stops all users file transfer.

Example of use

stopAllUsersFileTransfer -k sessionKey -m machineId -n nbFileTransfers -s status -u userId

Parameters

Parameter	Type	Option	Description	Required
sessionKey	string	k	the command to use to perform file transfer.	NO
machineId	string	m	the command to use to perform file transfer.	NO
nbFileTransfers	int	n	the command to use to perform file transfer.	NO
status	Status	S	the command to use to perform file transfer.	NO
userId	string	u	the user identifier	NO

Environment variables

Name	Parameter	Туре	Description	Required Use opti	
------	-----------	------	-------------	-------------------	--

5.1.17 FMS getFileTransferStatus

Access

This command line can be used by any Vishnu user.

Description

The getFileTransferStatus command line gives the status of a list of file transfer.

Example of use

 $getFileTransferStatus\ machineId\ sessionKey\ -\ listOfLongs$

Parameter	Type	Option	Description	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session identifier	YES
listOfLongs	long	TO DO	TO DO	NO

Name	Parameter	Type	Description	Required	User option
------	-----------	------	-------------	----------	-------------

5.1.18 FMS listFilesTransferStatus

Access

This command line can be used by any Vishnu user.

Description

The listFilesTransferStatus command line displays the status of all files transfer submitted by User.

Example of use

listFilesTransferStatus -k sessionKey -m machineId -n nbFileTransfers -s status -u userId

Parameters

Parameter	Type	Option	Description	Required
sessionKey	string	k	the command to use to perform file transfer.	NO
machineId	string	m	the command to use to perform file transfer.	NO
nbFileTransfers	int	n	the command to use to perform file transfer.	NO
status	Status	S	the command to use to perform file transfer.	NO
userId	string	u	the user identifier	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
					- I

5.1.19 FMS listAllUsersFilesTransferStatus

Access

This command line can be used by ADMIN users only

Description

The listAllUsersFilesTransferStatus command line displays the status of all files transfer submitted by User.

Example of use

listAllUsersFilesTransferStatus machineId sessionKey -k sessionKey -m machineId -n nbFileTransfers -s status -u userId

Parameter	Type	Option	Description	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session id	YES
sessionKey	string	k	the command to use to perform file transfer.	NO
machineId	string	m	the command to use to perform file transfer.	NO

Parameter	Type	Option	Description	Required
nbFileTransfers	int	n	the command to use to perform file transfer.	NO
status	Status	S	the command to use to perform file transfer.	NO
userId	string	u	the user identifier	NO

opuon		Name	Parameter	Type	Description	Required	User option
-------	--	------	-----------	------	-------------	----------	-------------

5.1.20 FMS DisplayFilesTransferHistory

Access

This command line can be used by any Vishnu user.

Description

The DisplayFilesTransferHistory command line displays the history of all files transfer submitted by User.

Example of use

DisplayFilesTransferHistory -k sessionKey -m machineId -n nbFileTransfers -s status -u userId

Parameters

Parameter	Type	Option Description		Required
sessionKey	string	k	the command to use to perform file transfer.	NO
machineId	string	m	the command to use to perform file transfer.	NO
nbFileTransfers	int	n	the command to use to perform file transfer.	NO
status	Status	S	the command to use to perform file transfer.	NO
userId	string	u	the user identifier	NO

Environment variables

Nama	Donomoton	Tuno	Decarintian	Required	User
Name	Parameter	Туре	Description	Requireu	option

5.1.21 FMS DisplayAllUsersFilesTransferHistory

Access

This command line can be used by ADMIN users only

Description

The DisplayAllUsersFilesTransferHistory command line displays the history of all files transfer submitted by all Users.

Example of use

DisplayAllUsersFilesTransferHistory -k sessionKey -m machineId -n nbFileTransfers -s status -u userId

Parameter	Type	Option	Description	Required
sessionKey	string	k	the command to use to perform file transfer.	NO
machineId	string	m	the command to use to perform file transfer.	NO
nbFileTransfers	int	n	the command to use to perform file transfer.	NO
status	Status	s	the command to use to perform file transfer.	NO
userId	string	u	the user identifier	NO

Name	Parameter	Туре	Description	Rec	quired User option	
------	-----------	------	-------------	-----	--------------------	--

5.1.22 FMS GetFilesInfo

Access

This command line can be used by any Vishnu user.

Description

The GetFilesInfo command line displays the information of files.

Example of use

GetFilesInfo machineId sessionKey -null listOfStrings

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The machine identifier	YES
sessionKey	string		The session id	YES
listOfStrings	string		the dynamic list of strings.	NO

Environment variables

Nama	Doromotor	Type	Description	Required	User
Name	Parameter	Type	Description	Required	option

5.2 Parameters definitions

Enumeration FMS::FileType Type

Name	Value
BLOCK	0
CHARACTER	1
DIRECTORY	2
SYMBOLICLINK	3
SCKT	4
FIFO	5
REGULAR	6

Enumeration FMS::Status Type

Name	Value
INPROGRESS	0
COMPLETED	1
CANCELLED	2
FAILED	3

Enumeration FMS::TransferCommand Type

Name	Value
SCP	0

Name	Value
RSYNC	1