# D1.1c - VISHNU A.P.I. specifications



### COLLABORATORS

	TITLE : D1.1c - VISHNU A.P.I.	specifications		
ACTION	NAME	DATE	SIGNATURE	
WRITTEN BY	Benjamin Isnard, Daouda Traoré, Eugène Pamba Capo-Chichi, Kevin Coulomb, and Ibrahima Cissé	February 16, 2011		

### REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
0	05/01/2011	Formatting example	SysFera
1	13/01/2011	First release	SysFera
2	10/02/2011	Removed UMS::AddUserOptions, UMS::AddMachineOptions and UMS::UpdateUserOptions classes and UMS::SessionStateType. Added function UMS::reconnect, UMS::StatusType. Modified UMS::restoreConfiguration and UMS::Configuration class	SysFera

# **Contents**

1	Docu	ument p	resentation		1
	1.1	Docum	ent objectives		1
	1.2	Docum	ent structure	<i>l</i> .	1
	1.3	Generi	definition formats presentation		1
		1.3.1	Methods definition format		2
			1.3.1.1 Generic method definition format		2
			1.3.1.2 C++ specific aspects		2
			1.3.1.3 Python specific aspects		2
			1.3.1.4 Web Services specific aspects		3
		1.3.2	Data types definition format		3
			1.3.2.1 Generic data defin <mark>ition f</mark> ormat		3
			1.3.2.2 C++ specific aspects		3
			1.3.2.3 Python specific aspects		3
			1.3.2.4 Web Services specific aspects		3
	1.4	Web S	rvices description		3
	1.5	Refere	ces		4
	1.6	Glossa	y		4
2	API	specific	ntion for User Management Service (UMS)		5
	2.1	Definit	on of the functions of the package		5
		2.1.1	Function UMS::connect		5
		2.1.2	Function UMS::reconnect		6
		2.1.3	Function UMS::addUser		6
		2.1.4	Function UMS::updateUser		8
		2.1.5	Function UMS::deleteUser		9
		2.1.6	Function UMS::close		9
		2.1.7	Function UMS::changePassword		10
		2.1.8	Function UMS::resetPassword		10
		2.1.9	Function UMS::addLocalAccount		12
		2.1.10	Function UMS::updateLocalAccount		13

		2.1.11	Function UMS::deleteLocalAccount	13
		2.1.12	Function UMS::saveConfiguration	14
		2.1.13	Function UMS::restoreConfiguration	15
		2.1.14	Function UMS::addMachine	15
		2.1.15	Function UMS::updateMachine	16
		2.1.16	Function UMS::deleteMachine	16
		2.1.17	Function UMS::listLocalAccount	17
		2.1.18	Function UMS::listMachine	18
		2.1.19	Function UMS::listHistoryCmd	18
		2.1.20	Function UMS::listOptions	19
		2.1.21	Function UMS::listUsers	20
		2.1.22	Function UMS::listSessions	20
		2.1.23	Function UMS::configureDefaultOption	21
			Function UMS::configureOption	
		2.1.25	Function UMS::vishnuInitialize	22
		2.1.26	Function UMS::vishnuFinalize	23
			Function UMS::restore	
	2.2	Data ty	rpes definitions	23
3	ΔPI	snecific	ation for Tasks Management Service (TMS)	28
3	3.1	_	ion of the functions of the package	
	3.1	3.1.1	Function TMS::submitJob	
		3.1.2	Function TMS::getJobInfo	
		3.1.3	Function TMS::getJobProgress	
		3.1.4	Function TMS::listQueues	
		3.1.5	Function TMS::listJobs	
		3.1.6	Function TMS::getJobOutPut	
		3.1.7	Function TMS::getAllJobsOutPut	
		3.1.8	Function TMS::cancelJob	
		3.1.9	Function TMS::setMachineEnv	
		3.1.10	Function TMS::setMachineRefreshPeriod	
	3.2		rpes definitions	
4		•	ation for Information Management Service (IMS)	39
	4.1		ion of the functions of the package	
		4.1.1	Function IMS::exportCommands	
		4.1.2	Function IMS::getMetricCurrentValue	
		4.1.3	Function IMS::getMetricHistory	
		4.1.4	Function IMS::getProcesses	41

		4.1.5	Function IMS::setSystemInfo	
		4.1.6	Function IMS::setSystemThreshold	
		4.1.7	Function IMS::getSystemThreshold	42
		4.1.8	Function IMS::defineUserIdentifier	43
		4.1.9	Function IMS::defineMachineIdentifier	43
		4.1.10	Function IMS::defineJobIdentifier	44
		4.1.11	Function IMS::defineTransferIdentifier	44
		4.1.12	Function IMS::loadShed	45
		4.1.13	Function IMS::setUpdateFrequency	45
		4.1.14	Function IMS::getUpdateFrequency	46
	4.2	Data ty	pes definitions	46
5	API	_	ation for File Management Service (FMS)	48
	5.1	Definit	ion of the functions of the package	48
		5.1.1	Function FMS::createFile	48
		5.1.2	Function FMS::createDir	49
		5.1.3	Function FMS::removeFile	49
		5.1.4	Function FMS::removeDir	
		5.1.5	Function FMS::chGrp	50
		5.1.6	Function FMS::chMod	51
		5.1.7	Function FMS::headOfFile	52
		5.1.8	Function FMS::tailOfFile	52
		5.1.9	Function FMS::contentOfFile	53
		5.1.10	Function FMS::listDir	53
		5.1.11	Function FMS::copyFile	54
		5.1.12	Function FMS::copyAsyncFile	55
		5.1.13	Function FMS::moveFile	56
		5.1.14	Function FMS::moveAsyncFile	56
		5.1.15	Function FMS::stopFileTransfer	57
		5.1.16	Function FMS::listFileTransferStatus	57
		5.1.17	Function FMS::listFileTransfers	58
		5.1.18	Function FMS::getFilesInfo	59
	5.2	Data ty	vnes definitions	59

## **Chapter 1**

# Document presentation

### 1.1 Document objectives

This document presents the detailed specifications of the VISHNU APIs (Application Programming Interfaces). The following APIs are included in the project:

- C++ API
- Python (v2.x) API
- Web services (WSDL 1.1) API

These specifications include the definition of all methods and all data types in a format that is common to all APIs. Therefore the description is not tied to a particular implementation and all implementations will follow the same logic and will differ only when the language that is used imposes some constraints.

Specific aspects of each implementation language are described in the section 1.3.

#### 1.2 Document structure

The document is divided into 4 parts corresponding to the four modules that compose the VISHNU system:

- UMS: Users Management Service
- TMS: Tasks Management Service
- FMS: Files Management Service
- IMS: Information Management Service

Each module corresponds to a chapter in the document, and each chapter contains the following sections:

- A first section describing the definition of all the methods provided by the library
- A second section describing the definition of all the data types provided by the library

### 1.3 Generic definition formats presentation

This section presents the formats used in the following chapters to describe the methods and data types provided by the libraries. It also details the particular implementation constraints for each language.

#### 1.3.1 Methods definition format

The following paragraphs show how all methods (or "operations" in the Web Services terminology) are specified in this document. First, the generic format used for each Vishnu module is explained, then the aspects that are specific to each implementation language are detailed.

#### 1.3.1.1 Generic method definition format

#### **Parameters**

The following table contains all the input and output parameters of the method, along with their type and description, and their optional or required flag.

Parameter	Type	Description	Mode	Required
sessionKey	string	This is an example of a required input parameter	IN	yes
listOfJobs	ListJobs	This is an example of an output parameter	OUT	yes

#### Access

Here is detailed the access level of the method 'myMethod' (i.e. the privilege required to use this method)

#### **Description**

Here is detailed the purpose of the method 'myMethod'

#### **Return Value**

Here are detailed the different return codes provided by the method. Please note that these return codes may be implemented differently depending on the language, for example by using an exception mechanism. In all implementations the library will provide a way of mapping the code to a human-readable message that will contain detailed information about the context of the exception that happened.

Name	Description
VISHNU_OK	The service was performed successfully.
TMS_UNKNOWN_MACHINE	This is the human-readable generic message that will be available to the user of the API.

#### **Signature**

This shows the C++ signature of the method.

int **myMethod**(const string& sessionKey, ListJobs& listOfJobs);

#### 1.3.1.2 C++ specific aspects

- The output parameters will be implemented as references in the method signature.
- The methods will always return an integer with a default value for success.
- The methods will throw exceptions for each error message specified. The exception will contain additional details provided by the server.

#### 1.3.1.3 Python specific aspects

• The output parameters will be implemented as a Python tuple returned by the method.

#### 1.3.1.4 Web Services specific aspects

- The input and output parameters will be implemented as Java Beans: a "Request" bean containing the input parameters and a "Response" bean containing the output parameters.
- The methods will throw exceptions for each error message specified. The exception will contain additional details provided by the server.
- The VishnuInitialize() and VishnuFinalize() methods are not applicable to the WS API.
- Methods with restricted access (administration) are not included in the WS API.

### 1.3.2 Data types definition format

The following paragraphs show how all data types are specified in this document. First, the generic format used for each Vishnu data type is explained, then the aspects that are specific to each implementation language are detailed.

#### 1.3.2.1 Generic data definition format

#### **Class Module::Class Content**

Name	Type	Description
Class attribute name	Class attribute type	Description/usage of the attribute

#### 1.3.2.2 C++ specific aspects

- All attributes of the class will be private.
- For each attribute of the class a couple of getter/setter methods will be implemented.
- The string type will be mapped to the C++ STL string type.

### 1.3.2.3 Python specific aspects

- For each attribute of the class a couple of getter/setter methods will be implemented.
- The string type will be mapped to standard Python strings.

#### 1.3.2.4 Web Services specific aspects

- When a single instance of object is used as input or output parameter, the attributes of the object will be mapped respectively to attributes of the 'Request' or 'Response' Java Bean.
- When multiple instances of object are used as input or output parameters (for example list of machines or list or users) the 'Request' or 'Response' Java Bean will contain a 'data' subclass containing the instances. This follows the standard WSDL/Java mapping for Apache-CXF.

### 1.4 Web Services description

The Web Services are fully described by the following documents which are attached to the current document:

• UMS.wsdl: WSDL file for the UMS module

• TMS.wsdl: WSDL file for the TMS module

• FMS.wsdl: WSDL file for the FMS module

 • IMS.wsdl : WSDL file for the IMS module

### 1.5 References

• D1.1a : VISHNU General specifications

### 1.6 Glossary

None

# **Chapter 2**

# API specification for User Management Service (UMS)

### 2.1 Definition of the functions of the package

### 2.1.1 Function UMS::connect

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
userId	string	userId represents the VISHNU user identifier	IN	yes
password	string	password represents the password of the user	IN	yes
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	OUT	yes
options	ConnectOptions	options is an object which encapsulates the options available for the connect method. It allows the user to choose the way for closing the session automatically on TIMEOUT or on DISCONNECT and the possibility for an admin to open a session as he/she was a specific user	IN	no

### Description

The connect() function opens a session

#### **Return Value**

Name	Description
VISHNU_OK	The service was performed successfully
NOT_AUTHENTICATED	Unknown user
UNKNOWN_CLOSURE_MODE	The name of the closure mode is unknown
INCORRECT TIMEOUT	The value of the timeout is incorrect (negative or higher than
INCORRECT_TIMEOUT	the TIMEOUT treshold)
UNKNOWN_USERID	The userId is unknown
NO_ADMIN	The user is not an administrator
INCORRECT_PASSWORD_SIZE	The size of the password is incorrect

Name	Description
INCORRECT_USERID_SIZE	The size of the userId is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

int **connect**(const string& userId, const string& password, string& sessionKey, const ConnectOptions& options = ConnectOptions());

#### 2.1.2 Function UMS::reconnect

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
userId	string	userId represents the VISHNU user identifier	IN	yes
password	string	password represents the password of the user	IN	yes
sessionId	string	sessionId is the identifier of the session defined in the database	IN	yes
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	OUT	yes

#### Description

The reconnect() function returns the sessionKey of a session in which the user was disconnected previously without closing it

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description	
VISHNU_OK	The service was performed successfully	
NOT_AUTHENTICATED	Unknown user	
INCORRECT_USERID_SIZE	The size of the userId is incorrect	
INCORRECT_PASSWORD_SIZE	The size of the password is incorrect	
SESSION INCOMPATIBILITY	This session identifier is incompatible with the authenticated	
_	user	
UNKNOWN_SESSION_ID	The session Id is unknown	
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.	
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized	
UNKNOWN_MACHINE_FOR_SESSION	This session has been opened with another machine	
DB_ERROR	A problem occurs with the database	
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available	

#### Signature

 $int \ \textbf{reconnect} (const \ string \& \ userId \ , \ const \ string \& \ password, \ const \ string \& \ sessionId, \ string \& \ sessionKey);$ 

#### 2.1.3 Function UMS::addUser

#### Access

This function can be used by ADMIN users only

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
newUser	User	Object containing the new user information IN		yes

The addUser() function adds a new VISHNU user

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
INCORRECT_USERID_SIZE	The size of the userId is incorrect
INCORRECT_PASSWORD_SIZE	The size of the password is incorrect
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
USERID_EXISTING	The userId already exists in the database
INVALID_MAIL_ADRESS	The mail adress is invalid
USERID_REQUIRED	The userId must to be defined
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

#### Signature

int addUser(const string& sessionKey, const User& newUser);

### 2.1.4 Function UMS::updateUser

#### Access

This function can be used by ADMIN users only

#### **Parameters**

Parameter	Type	Description	Mo <mark>de</mark>	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
user	User	Object containing user information	IN	yes

### Description

The updateUser() function updates the user information except the userId and the password

### **Return Value**

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
UNKNOWN_USERID	The userId is unknown
INVALID_MAIL_ADRESS	The mail adress is invalid
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.

Name	Description
INCORRECT_USERID_SIZE	The size of the userId is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

int updateUser(const string& sessionKey, const User& user);

### 2.1.5 Function UMS::deleteUser

#### Access

This function can be used by ADMIN users only

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
userId	string	userId represents the VISHNU user identifier of the user who will be deleted from VISHNU	IN	yes

### **Description**

The deleteUser() function removes a user from VISHNU

### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
UNKNOWN_USERID	The userId is unknown
NO_ADMIN	The user is not an administrator
INCORRECT_USERID_SIZE	The size of the userId is incorrect
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

#### **Signature**

int deleteUser(const string& sessionKey, const string& userId);

### 2.1.6 Function UMS::close

### Access

This function can be used by any VISHNU user

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes

The close() function closes the session identified by the session key

### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	<b>Description</b>
VISHNU_OK	The service was performed successfully
COMMAND_RUNNING	Command(s) is/are running
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

#### Signature

int close(const string& sessionKey);

### 2.1.7 Function UMS::changePassword

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
userId	string	userId represents the VISHNU user identifier	IN	yes
password	string	password represents the password of the user	IN	yes
passwordNew	string	pas <mark>sword</mark> New represents the new password of the user	IN	yes

### Description

The changePassword() function changes the password

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NOT_AUTHENTICATED	Unknown user
INCORRECT_USERID_SIZE	The size of the userId is incorrect
INCORRECT_PASSWORD_SIZE	The size of the password is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

### **Signature**

 $int \ \textbf{changePassword} (const\ string\&\ userId,\ const\ string\&\ password,\ const\ string\&\ passwordNew);$ 

### 2.1.8 Function UMS::resetPassword

#### Access

This function can be used by ADMIN users only

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
userId	string	userId represents the VISHNU user identifier of the user whose password will be reset	IN	yes

The resetPassword() function resets the password of a user

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
UNKNOWN_USERID	The userId is unknown
INCORRECT_USERID_SIZE	The size of the userId is incorrect
INCORRECT_PASSWORD_SIZE	The size of the password is incorrect
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

### **Signature**

int **resetPassword**(const string& sessionKey, const string& userId);

### 2.1.9 Function UMS::addLocalAccount

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mo <mark>de</mark>	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
newAccount	LocalAccount	newAccount is the object which encapsulates the new local user configuration	IN	yes
sshPublicKey	string	The SSH public key generated by VISHNU for accessing a local account	OUT	yes

### **Description**

The addLocalAccount() function adds a new local user configuration

### **Return Value**

Name	Description
VISHNU_OK	The service was performed successfully
LOCAL_ACCOUNT_EXIST	The local account already exists for the given user on the given machine
USERID_REQUIRED	The userId must to be defined

Name	Description
MACHINEID_REQUIRED	The machineId must to be defined
UNKNOWN_USERID	The userId is unknown
UNKNOWN_MACHINE	The machineId is unknown
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

int addLocalAccount(const string& sessionKey, const LocalAccount& newAccount, string& sshPublicKey);

### 2.1.10 Function UMS::updateLocalAccount

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
LocalAccUpd	LocalAccount	is an object which encapsulates the local user configuration changes except the machineId and the userId	IN	yes

### Description

The updateLocalAccount() function updates a local user configuration

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	<b>Description</b>		
UNKNOWN_USERID	The userId is unknown		
UNKNOWN_MACHINE	The machineId is unknown		
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized		
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.		
UNKNOWN LOCAL ACCOUNT	The local configuration for the given user on the given machine		
ONKNOWN_LOCAL_ACCOUNT	is unknown		
DB_ERROR	A problem occurs with the database		
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available		

### **Signature**

int updateLocalAccount(const string& sessionKey, const LocalAccount& LocalAccUpd);

### 2.1.11 Function UMS::deleteLocalAccount

#### Access

This function can be used by any VISHNU user

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
userId	string	userId represents the VISHNU user identifier of the user whose local configuration will be deleted for the given machine	IN	yes
machineId	string	machineId represents the identifier of the machine whose local configuration will be deleted for the given user	IN	yes

The deleteLocalAccount() function removes a local user configuration (for a given user on a given machine) from VISHNU

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
UNKNOWN_LOCAL_ACCOUNT	The local configuration for the given user on the given machine
UNKNOWN_LOCAL_ACCOUNT	is unknown
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

#### Signature

int deleteLocalAccount(const string& sessionKey, const string& userId, const string& machineId);

### 2.1.12 Function UMS::saveConfiguration

#### Access

This function can be used by ADMIN users only

#### **Parameters**

Parameter	Type	Description	Mode	:	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN		yes
configuration	Configuration	The configuration is an object which encapsulates the configuration description	OUT		yes

### Description

The saveConfiguration() function saves the configuration of VISHNU

#### **Return Value**

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
SAVE_CONFIG_ERROR	A problem occurs during the configuration saving
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

int saveConfiguration(const string& sessionKey, Configuration);

### 2.1.13 Function UMS::restoreConfiguration

#### Access

This function can be used by ADMIN users only

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
filePath	string	The filePath is the path of the file used to restore VISHNU configuration	IN	yes

### Description

The restoreConfiguration() function restores the configuration of VISHNU

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
RESTORE_CONFIG_ERROR	A problem occurs during the configuration restoring
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

### **Signature**

int **restoreConfiguration**(const string& sessionKey, const string& filePath);

### 2.1.14 Function UMS::addMachine

#### Access

This function can be used by ADMIN users only

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU		yes
newMachine	Machine	is an object which encapsulates the information of the machine which will be added in VISHNU except the machine id which will be created automatically by VISHNU	IN	yes

#### **Description**

The addMachine() function adds a new machine in VISHNU

### **Return Value**

Name	Description
VISHNU_OK	The service was performed successfully
MACHINE_EXISTING	The machineId already exists in the database
MACHINEID_REQUIRED	The machineId must to be defined
NO_ADMIN	The user is not an administrator
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

int addMachine(const string& sessionKey, const Machine & newMachine);

### 2.1.15 Function UMS::updateMachine

#### Access

This function can be used by ADMIN users only

#### **Parameters**

Parameter	Type	D <mark>escriptio</mark> n	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
machine	Machine	existing machine information	IN	yes

### **Description**

The updateMachine() function updates machine description

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	<b>Description</b>
VISHNU_OK	The service was performed successfully
MACHINEID_REQUIRED	The machineId must to be defined
UNKNOWN_MACHINE	The machineId is unknown
NO_ADMIN	The user is not an administrator
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

#### Signature

int updateMachine(const string& sessionKey, const Machine& machine);

### 2.1.16 Function UMS::deleteMachine

#### Access

This function can be used by ADMIN users only

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
machineId	string	machineId represents the identifier of the machine	IN	yes

The deleteMachine() function removes a machine from VISHNU

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
UNKNOWN_MACHINE	The machineId is unknown
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

#### **Signature**

int **deleteMachine**(const string& sessionKey, const string& machineId);

### 2.1.17 Function UMS::listLocalAccount

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
listLocalAcct	ListLocalAccounts	listLocalAccount is the list of the local user configuations	OUT	yes
options	ListLocalAccOptions	allows an admin to list all local configurations of all users or a simple user to list his/her local user configurations on a specific machine	IN	no

### **Description**

The listLocalAccount() function lists the local user configurations

### **Return Value**

Name	Description
VISHNU_OK	The service was performed successfully
UNKNOWN_USERID	The userId is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
INCORRECT_DATE_OPTION	The date option is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

int **listLocalAccount**(const string& sessionKey, ListLocalAccounts& **listLocalAccO**ptions& options = ListLocalAccOptions());

### 2.1.18 Function UMS::listMachine

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
listMachine	ListMachines	listLocalAccount is the list of the local configs	OUT	yes
options	ListMachineOptions	allows a user to list all VISHNU machines or information about a specific machine and an admin to list machines used by a specific user	IN	no

### Description

The listMachine() function lists the machines in which the local user configurations are defined for the given user

#### Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
UNKNOWN_USERID	The userId is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
INCORRECT_DATE_OPTION	The date option is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

### Signature

int **listMachine**(const string& sessionKey, ListMachines& listMachine, const ListMachineOptions& options = ListMachineOptions());

### 2.1.19 Function UMS::listHistoryCmd

#### Access

This function can be used by any VISHNU user

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
listCommands	ListCommands	listCommands is the list of commands	OUT	yes
options	ListCmdOptions	allows the user to list commands by using several optional criteria: a period, specific session and for admin to list all commands of all VISHNU users or commands from a specific user	IN	no

The listHistoryCmd() function lists the commands

### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
UNKNOWN_USERID	The userId is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
INCORRECT_DATE_OPTION	The date option is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

#### Signature

int **listHistoryCmd**(const string& sessionKey, ListCommands& listCommands, const ListCmdOptions& options = ListCmdOptions());

### 2.1.20 Function UMS::listOptions

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	IN	yes
listOptValues	ListOptionsValues	listOptValues is an object which encapsulates the list of options	OUT	yes
options	ListOptOptions	allows to list a specific option or all default options values or for an admin to list options of a specific user	IN	no

### **Description**

The listOptions() function lists the options of the user

### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
UNKNOWN_USERID	The userId is unknown
UNKNOWN_OPTION	the name of the option is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
INCORRECT_DATE_OPTION	The date option is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

### Signature

int **listOptions**(const string& sessionKey, ListOptionsValues& listOptValues, const ListOptOptions& options = ListOptOptions());

#### 2.1.21 Function UMS::listUsers

#### Access

This function can be used by ADMIN users only

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	IN	yes
listuser	ListUsers	listuser is the list of users	OUT	yes
userIdOption	string	allows an admin to get information about a specific user identified by his/her userId	IN	no

### **Description**

The listUsers() function lists VISHNU users

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	<b>Description</b>
NO_ADMIN	The user is not an administrator
UNKNOWN_USERID	The userId is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
INCORRECT_DATE_OPTION	The date option is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

### Signature

int **listUsers**(const string& sessionKey, ListUsers& listuser, const string& userIdOption = string());

### 2.1.22 Function UMS::listSessions

### Access

This function can be used by any VISHNU user

Parameter	Туре	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU		yes
listsession	ListSessions	listsession is the list of sessions	OUT	yes
options	ListSessionOptions	allows the user to list sessions using several optional criteria such as: the state of sessions (actives or inactives, by default, all sessions are listed), a period, a specific session or for admin to list all sessions of all users or sessions of a specific user.	IN	no

The listSessions() function lists all sessions of the user

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
UNKNOWN_USERID	The userId is unknown
UNKNOWN_SESSION_OPTION	The name of the session option is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
INCORRECT_DATE_OPTION	The date option is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

#### Signature

int **listSessions**(const string& sessionKey, ListSession const ListSessionOptions action options); int **listSession**(const string& sessionKey, ListSessionOptions);

### 2.1.23 Function UMS::configureDefaultOption

#### Access

This function can be used by ADMIN users only

#### **Parameters**

Parameter	Type	<b>Description</b>	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
optionValue	OptionValue	The option Value is an object which encapsulates the option information	IN	yes

### Description

The configureDefaultOption() function configures a default option value

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
UNKNOWN_OPTION	the name of the option is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

### Signature

int configureDefaultOption(const string& sessionKey, const OptionValue& optionValue);

### 2.1.24 Function UMS::configureOption

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
optionValue	OptionValue	The option Value is an object which encapsulates the option information	IN	yes

### Description

The configureOption() function configures an option of the user

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
UNKNOWN_OPTION	the name of the option is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

#### Signature

int **configureOption**(const string& sessionKey, const OptionValue& optionValue);

### 2.1.25 Function UMS::vishnulnitialize

### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
configPath	string	configPath is the path of VISHNU configuration file	IN	yes

### Description

The vishnuInitialize() function initializes VISHNU

### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
INCORRECT_CFG_PATH	The configuration file path is incorrect

#### **Signature**

int vishnuInitialize(const string& configPath);

### 2.1.26 Function UMS::vishnuFinalize

#### Access

This function can be used by any VISHNU user

#### **Parameters**

This command defines no parameters.

### Description

The vishnuFinalize() function allows a user to go out properly from VISHNU

#### Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
VISHNU_FINALIZE_ERROR	An error occurs during vishnuFinalize

#### **Signature**

int vishnuFinalize();

### 2.1.27 Function UMS::restore

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	<b>Description</b>	Mode	Required
file	string	file containing a sql script to restore the database	IN	yes

### **Description**

The restore() function initializes VISHNU environment for tests

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully

#### Signature

int restore(const string& file);

### 2.2 Data types definitions

#### **Class UMS::Command Content**

Name	Type	Description
commandId	string	is the identifier of a command
sessionId string	The sessionId is the identifier of the session define in the	
Sessioniu	string	database

Name	Type	Description
machineId	string	The machineId is the identifier of the machine used by
macmileid		the command
cmdDescription	string	cmdDescription is the description of the command
cmdStartTime	long	cmdStartTime is the date of the command beginning (the
CindStartTime		UNIX timestamps is used)
cmdEndTime	long	cmdEndTime is the date of the command end (the UNIX
Cindend i nne		timestamps is used)

### **Class UMS::Configuration Content**

Name	Type	Description
listConfUsers	List of User	is the list of users objects
listConfMachines	List of Machine	is a list of machines objects
listConfLocalAccounts	List of LocalAccount	is the list of LocalAccount objects

### **Class UMS::ConnectOptions Content**

Name	Type	Description
closePolicy	SessionCloseType	is an option for closing session automatically
sessionInactivityDelay int		The sessionInactivityDelay is the maximum delay in
	int	seconds between two API commands when the
		CLOSE_ON_TIMEOUT option is set
substituteUserId string	atrin a	is an option which allows an admin to open a session as
	sumg	if he/she was a specific user identified by his/her userId

### Class UMS::ListCmdOptions Content

Name	Type	Description
adminListOption	boolean	is an admin option for listing all commands of all users
userId	string	is an admin option for listing commands launched by a specific user identified by his/her userId
sessionId	string	lists all commands launched within a specific session
startDateOption	long	allows the user to organize the commands listed by providing the start date (the UNIX timestamp of date is used)
endDateOption	long	allows the user to organize the commands listed by providing the end date (the timestamp of the end date is used). By default, the end date is the current day

### **Class UMS::ListCommands Content**

Name	Type	Description
Commands	List of Command	is the list of commands objects

### Class UMS::ListLocalAccOptions Content

Name	Type	Description
adminListOption 1	boolean	is an admin option for listing all local configurations of
adillilListOption	Doolean	all users
userId	atrina	is an admin option for listing the local configurations of
useriu	string	a specific user
machineId	string	is an option for listing local user configurations on a
macmilletu	Sumg	specific machine

#### Class UMS::ListLocalAccounts Content

Name	Type	Description
aggounts	List of LocalAccount	is a list of LocalAccount objects which encapsulates
accounts		local user configurations

### **Class UMS::ListMachineOptions Content**

Name	Туре	Description
userId	string	is an admin option for listing machines in which a specific user has a local configuration
listAllmachine	boolean	is an option for listing all VISHNU machines
machineId	string	is an option for listing information about a specific machine

### **Class UMS::ListMachines Content**

Name	Type	<b>Description</b>
machines	List of Machine	is a list of machines objects which encapsulates the machines information

### Class UMS::ListOptOptions Content

Name	Type	Description
listAllDeftValue	boolean	is an option for listing all default option values defined
listAliDelt value	boolean	by VISHNU administrator
I.I	atrina	is an admin option for listing the options of a specific
userId	string	user
antian Nama	atain a	allows the user to get the value of a specific option
optionName	string	identified by its name

### **Class UMS::ListOptionsValues Content**

Name	Type	Description
optionValues	List of OptionValue	is a list of optionValue objects which encapsulates the
option values		optionValue information

### Class UMS::ListSessionOptions Content

Name	Type	Description
status	StatusType	specifies the status of the sessions which will be listed
		specifies the closure mode of the sessions which will be
sessionClosePolicy	SessionCloseType	listed (CLOSE_ON_TIMEOUT or
		CLOSE_ON_DISCONNECT)
sessionInactivityDelay	int	specifies the inactivity delay in seconds of the sessions
sessionmactivityDetay	IIIt	which will be listed
machineId	string	allows the user to list sessions opened on a specific
machineid		machine
adminListOption	boolean	is an admin option for listing all sessions of all users
userId	string	is an admin option for listing sessions opened by a
		specific user
sessionId	string	allows the user to list all commands launched within a
		specific session

Name	Type	Description
		allows the user to organize the commands listed by
startDateOption	long	providing the start date (the UNIX timestamp of the start
		date is used)
		allows the user to organize the commands listed by
endDateOption	long	providing the end date (the timestamp of the end date is
		used). By default, the end date is the current day

### **Class UMS::ListSessions Content**

Name	Type	Description
sessions	List of Session	is the list of session objects

### **Class UMS::ListUsers Content**

Name	Type	Description
users	List of User	is the list of users objects

### **Class UMS::LocalAccount Content**

Name	Type	7	Description
userId	string		The userId represents the VISHNU user identifier of the
uscriu	Sumg		user of the local user configuration
machineId	etring	tuin a	The MachineId represents the identifier of the machine
macimierd	string		associated to the local user configuration
acLogin	string		accLogin represents the login of the user on the
			associated machine
sshKeyPath	string		sshKeyPath is the path of the ssh key of the user on the
ssirkeyi atti	Sumg		associated machine
homoDiractory	string		HomeDirectory is the path of the home directory of the
homeDirectory stri			user on the associated machine

### **Class UMS::Machine Content**

Name	Туре	Description
machineId	string	represents the identifier of the machine
name	string	represents the name of the machine
site	string	represents the location of the machine
machineDescription	string	represents the description of the machine
language	string	represents the language in which the description of the
language	sumg	machine has been done
status	StatusType	represents the status of the machine

### **Class UMS::OptionValue Content**

Name	Type	Description
optionName	string	represents the name of an option
value	string	represents the value of an option

### **Class UMS::Session Content**

Name	Type	Description
sessionId	string	represents the VISHNU session identifier of the session

Name	Type	Description
userId	string	represents the VISHNU user identifier of the user who
usciiu	sung	has opened the session
sessionKey	string	is the key of the session generated by VISHNU
dateLastConnect	long	is the date of the last connection to the session (the
dateLastConnect	long	UNIX timestamps is used)
dateCreation	long	is the date of the first connection to the session (the
dateCreation	long	UNIX timestamps is used)
dateClosure	long	is the date of the closure of the session (the UNIX
dateClosule	long	timestamps is used)
status	StatusType	represents the status of the session
closePolicy	SessionCloseType	is the way to close the session
timeout	long	is the inactivity delay in seconds associated to the
timeout	iong	CLOSE_ON_TIMEOUT option

### **Class UMS::User Content**

Name	Type	Description
userId	string	represents the VISHNU user identifier
		is the password of the user. At the beginning, an admin
password	string	can give a temporary password or it is automatically
		generated by the System.
firstname	string	is the firstname of the user
lastname	string	is the lastname of the user
privilege	PrivilegeType	is the privilege of the user (admin or simple user)
email	string	is the email of the user
status	StatusType	represents the status of the user

### **Enumeration UMS::PrivilegeType Type**

Name	Value
USER	0
ADMIN	1

### **Enumeration UMS::SessionCloseType Type**

Name	Value
UNDEFINED	0
CLOSE_ON_TIMEOUT	1
CLOSE_ON_DISCONNECT	2

### **Enumeration UMS::StatusType Type**

Name	Value
INACTIVE	0
ACTIVE	1

# **Chapter 3**

# API specification for Tasks Management Service (TMS)

### 3.1 Definition of the function<mark>s of t</mark>he <mark>package</mark>

### 3.1.1 Function TMS::submitJob

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	IN	yes
machineId	string	Is the id of the machine where the job must be submitted	IN	yes
scriptFilePath	string	The path to the file containing the characteristics (job command, and batch scheduler directive required or optional) of the job to submit.	IN	yes
jobId	string	Is the returned id of the submitted job	OUT	yes
jobPath	string	Is the path to the file containing job characteristics	OUT	yes
options	SubmitOptions	Is an instance of the class SubmitOptions. Each optionnal value is associated to a set operation (e.g: setNbCpu()) in the class SubmitOptions. If no set operation is not called on the instance object options, the job is submitted with the options defined in the scriptFilePath. Otherewise the job is submitted with the optionnal values set by the options object and optionnal values defined in the scriptFilePath, but optionnal values set by SubmitOptions object take precedence over those in scriptFilePath. With in the object options or within the scriptFilePath, the last occurance of an optionnal value takes precedence over earlier occurance.	IN	no

#### Description

The submitJob() function submits job on a machine through the use of a script (scriptFilePath). The script is a shell script which will be executed by a command shell such as sh or csh

### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description		
VISHNU_OK	The service was performed successfully.		
TMS_UNKNOWN_MACHINE	The machine is not known.		
TMS_BATCH_SCHEDULER_ERROR	Indicates an error caused by the underlying batch scheduler		
TMS_INVALID_PATH	The path to the file containing the characteristics of the job to submit is not a valid path		
TMS_INVALID_RESPONSE	Indicates that the implementation produced a response that does not match the criteria defined by the specification.		
TMS_INVALID_REQUEST	Indicates that the request is not valid.		
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.		
TMS_PERMISSION_DENIED	Indicates the requested operation is not allowed for provided user.		
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.		
TMS_SUBMIT_SERVICE_NOT_AVAILABLE	Indicates that the service to perform the submit operation is not found.		
TMS_UNKNOWN_BATCH_SCHEDULER_TYPE	Indicates that the batch scheduler type is not known.		
TMS_UNKNOWN_QUEUE	Indicates that the specified queue by the user is not known.		
DB_ERROR	A problem occurs with the database		

#### Signature

int **submitJob**(const string& sessionKey, const string& machineId, const string& scriptFilePath, string& jobId, string& jobPath, const SubmitOptions& options = SubmitOptions());

### 3.1.2 Function TMS::getJobInfo

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	IN	yes
machineId	string	Machine hash key	IN	yes
jobId	string	The id of the job	IN	yes
jobInfos	Job	The resulting information on the job	OUT	yes

### **Description**

The getJobInfo() function gets information on a job from its id

#### **Return Value**

Name	Description
TMS_BATCH_SCHEDULER_ERROR	Indicates an error caused by the underlying batch scheduler
TMS_INVALID_REQUEST	Indicates that the request is not valid.
TMS INVALID RESPONSE	Indicates that the implementation produced a response that does
TWIS_IN VALID_REST ONSE	not match the criteria defined by the specification.
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.
TMS PERMISSION DENIED	Indicates the requested operation is not allowed for provided
TWIS_I ERWISSION_DENIED	user.
VISHNU_OK	The service was performed successfully.

Name	Description
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.
TMS_UNKNOWN_BATCH_SCHEDULER_TYPE	Indicates that the batch scheduler type is not known.
TMS_UNKNOWN_MACHINE	The machine is not known.
DB_ERROR	A problem occurs with the database

int getJobInfo(const string& sessionKey, const string& machineId, const string& jobId, Job& jobInfos);

### 3.1.3 Function TMS::getJobProgress

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	IN	yes
machineId	string	Is the id of the machine to get the jobs progression.	IN	yes
progress	Progression	Is the object containing jobs progression information	OUT	yes
options	ProgressOptions	Is an object containing the available options jobs for progression .		no

### Description

The getJobProgress() function gets the progression status of jobs

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description		
VISHNU_OK	The service was performed successfully.		
TMS_INVALID_REQUEST	Indicates that the request is not valid.		
TMS_UNKNOWN_MACHINE	The machine is not known.		
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.		
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.		
TMS SUBMIT SERVICE NOT AVAILABLE	Indicates that the service to perform the submit operation is not		
TWIS_SOBWIT_SERVICE_NOT_AVAILABLE	found.		
DB_ERROR	A problem occurs with the database		

### **Signature**

int **getJobProgress**(const string& sessionKey, const string& machineId, Progression& progress, const ProgressOptions& options = ProgressOptions());

### 3.1.4 Function TMS::listQueues

#### Access

This function can be used by any VISHNU user

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	IN	yes
machineId	string	Machine hash key	IN	yes
listofQueues	ListQueues	The list of queues	OUT	yes

The listQueues() function gets queues information

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description		
TMS_BATCH_SCHEDULER_ERROR	Indicates an error caused by the underlying batch scheduler		
TMS_INVALID_RESPONSE	Indicates that the implementation produced a response that does not match the criteria defined by the specification.		
TMS_INVALID_REQUEST	Indicates that the request is not valid.		
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.		
TMS_PERMISSION_DENIED	Indicates the requested operation is not allowed for provided user.		
VISHNU_OK	The service was performed successfully.		
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.		
TMS_UNKNOWN_BATCH_SCHEDULER_TYPE	Indicates that the batch scheduler type is not known.		
TMS_UNKNOWN_MACHINE	The machine is not known.		
DB_ERROR	A problem occurs with the database		

### Signature

int listQueues(const string& sessionKey, const string& machineId, ListQueues& listofQueues);

### 3.1.5 Function TMS::listJobs

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the identifier of the session generated	IN	MOS
		by VISHNU		yes
machineId	string	Machine hash key	IN	yes
listOfJobs	ListJobs	The constructed object list of jobs	OUT	yes
options	ListJobsOptions	Additional options for jobs listing	IN	no

### Description

The listJobs() function gets a list of all submitted jobs

#### **Return Value**

Name	Description	
TMS_BATCH_SCHEDULER_ERROR	Indicates an error caused by the underlying batch scheduler	
TMS_INVALID_RESPONSE	Indicates that the implementation produced a response that does not match the criteria defined by the specification.	

Name	Description
TMS_INVALID_REQUEST	Indicates that the request is not valid.
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.
TMS PERMISSION DENIED	Indicates the requested operation is not allowed for provided
TWIS_T ERWINSTON_DENTED	user.
VISHNU_OK	The service was performed successfully.
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.
TMS_UNKNOWN_BATCH_SCHEDULER_TYPE	Indicates that the batch scheduler type is not known.
TMS_UNKNOWN_MACHINE	The machine is not known.
DB_ERROR	A problem occurs with the database

int **listJobs**(const string& sessionKey, const string& machineId, ListJobs& listOfJobs, const ListJobsOptions& options = ListJobsOptions());

## 3.1.6 Function TMS::getJobOutPut

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	D <mark>escrip</mark> tion	Mode	Required
sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	IN	yes
machineId	string	Machine hash key	IN	yes
jobId	string	The Id of the job	IN	yes
outputPath	string	The path of the file containing the output result of the job	OUT	yes
errorPath	string	The path of the file containing the errors that has been occurred during the execution of the job	OUT	yes

## Description

The getJobOutPut() function gets outputPath and errorPath of a job from its id

## **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
TMS_BATCH_SCHEDULER_ERROR	Indicates an error caused by the underlying batch scheduler
TMS_INVALID_RESPONSE	Indicates that the implementation produced a response that does not match the criteria defined by the specification.
TMS_INVALID_REQUEST	Indicates that the request is not valid.
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.
VISHNU_OK	The service was performed successfully.
TMS_PERMISSION_DENIED	Indicates the requested operation is not allowed for provided user.
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.
TMS_UNKNOWN_BATCH_SCHEDULER_TYPE	Indicates that the batch scheduler type is not known.
TMS_UNKNOWN_MACHINE	The machine is not known.
DB_ERROR	A problem occurs with the database

## Signature

int **getJobOutPut**(const string& sessionKey, const string& machineId, const string& jobId, string& outputPath, string& error-Path);

## 3.1.7 Function TMS::getAllJobsOutPut

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	IN	yes
machineId	string	Machine hash key	IN	yes
listOfResults	ListJobResults	Is the list of jobs results	OUT	yes

## Description

The getAllJobsOutPut() function dynamically gets outputPath and errorPath of completed jobs

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description	
TMS_BATCH_SCHEDULER_ERROR	Indicates an error caused by the underlying batch scheduler	
TMS_INVALID_RESPONSE	Indicates that the implementation produced a response that does not match the criteria defined by the specification.	
TMS_INVALID_REQUEST	Indicates that the request is not valid.	
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.	
VISHNU_OK	The service was performed successfully.	
TMS_PERMISSION_DENIED	Indicates the requested operation is not allowed for provided user.	
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.	
TMS_UNKNOWN_BATCH_SCHEDULER_TYPE	Indicates that the batch scheduler type is not known.	
TMS_UNKNOWN_MACHINE	The machine is not known.	
DB_ERROR	A problem occurs with the database	

#### **Signature**

int getAllJobsOutPut(const string& sessionKey, const string& machineId, ListJobResults& listOfResults);

## 3.1.8 Function TMS::cancelJob

#### Access

This function can be used by any VISHNU user

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	IN	yes
machineId	string	Machine hash key	IN	yes
jobId	string	The Id of the job	IN	yes
infoMsg	string	The information message	OUT	yes

The cancelJob() function cancels a job from its id

## **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description	
TMS_BATCH_SCHEDULER_ERROR	Indicates an error caused by the underlying batch scheduler	
TMS_INVALID_RESPONSE	Indicates that the implementation produced a response that does not match the criteria defined by the specification.	
TMS_INVALID_REQUEST	Indicates that the request is not valid.	
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.	
TMS_PERMISSION_DENIED	Indicates the requested operation is not allowed for provided user.	
VISHNU_OK	The service was performed successfully.	
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.	
TMS_UNKNOWN_BATCH_SCHEDULER_TYPE	Indicates that the batch scheduler type is not known.	
TMS_UNKNOWN_MACHINE	The machine is not known.	
DB_ERROR	A problem occurs with the database	

## **Signature**

int cancelJob(const string& sessionKey, const string& machineId, const string& jobId, string& infoMsg);

#### 3.1.9 Function TMS::setMachineEnv

#### Access

This function can be used by ADMIN users only

## **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	IN	yes
machineId	string	Represents the machine id	IN	yes
listEnv	string	Represents the list environement variables	IN	yes

#### Description

The setMachineEnv() function sets environment variables on a remote machine

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully.
TMS_UNKNOWN_MACHINE	The machine is not known.

#### **Signature**

int **setMachineEnv**(const string& sessionKey, const string& machineId, const string& listEnv);

## 3.1.10 Function TMS::setMachineRefreshPeriod

#### Access

This function can be used by ADMIN users only

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	IN	yes
machineId	string	The id of the machine	IN	yes
value	int	Is the refresh interval value (in seconds)	IN	yes

## Description

The setMachineRefreshPeriod() function sets the refresh period of output and error files contents

## **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	<b>Description</b>	
VISHNU_OK	The service was performed successfully.	
TMS_UNKNOWN_MACHINE	The machine is not known.	

## Signature

int **setMachineRefreshPeriod**(const string& sessionKey, const string& machineId, const int& value);

# 3.2 Data types definitions

## **Class TMS::Job Content**

Name	Type	<b>Description</b>	
sessionId	string	Is the id of the session that contained the job submission	
sessioniu	sumg	command	
submitMachineId	string	Is the id of the machine on which the job has been	
submitiviaenneid	string	s <mark>ubmitt</mark> ed.	
submitMachineName	string	Is the name of the machine on which the job has been	
	string	submitted.	
jobId	string	Represents the id to job.	
jobName	string	Represents the name assigned to the job.	
jobPath	string	Is the path to the file containing job characteristics.	
outputPath	string	Is the path to the job output results.	
errorPath	string	Is the path to the file containing errors occured during	
		job's execution.	
jobPrio	JobPriority	Represents the job priority.	
nbCpus	int	Is the number of cpu used by the job.	
jobWorkingDir	string	Indicates the directory where the job has been launched.	
status	JobStatus	The current status of the job.	
submitDate	long	Date and time when job was submitted (unix timestamp)	
endDate	long	Represents the execution end date of the job (unix	
elidDate	iong	timestamp)	
owner	string Represents the job owner.		
jobQueue	string Is the name of the queue or class associated to the job		
wallClockLimit	long	Is the maximum wall-clock time during which the job	
WanClockLillit	long	can run (in seconds)	
groupName	string	Represents the job owner group name.	
jobDescription	string Is the textual description of the job.		

Name	Type	Description
memLimit	int	Represents the memory size limit of the job.
nbNodes	int	Is the total number of nodes used by the job.
nbNodesAndCpuPerNode	string	Is the number of nodes and processors per node used by
		the job.

## Class TMS::JobResult Content

Name	Type	Description
jobId	string	Represents the id of the job.
outputPath	string	Is the path to the job output results.
errorPath	string	Is the path to the file containing errors occured during job's execution.

## Class TMS::ListJobResults Content

Name	Type	<b>Description</b>
nbJobs	string	Is the number of jobs.
Results	List of JobResult	Represents the list of completed jobs results.

## Class TMS::ListJobs Content

Name	Type	Description
nbJobs	long	Represents the total number of jobs in the list.
nbRunningJobs	long	Represents of running jobs in the list.
nbWaitingJobs	long	Represents the total number of waiting jobs in the list.
jobs	List of Job	Is a list of job information (jobId, jobName,).

## **Class TMS::ListJobsOptions Content**

Name	Type	Description
jobId	string	To list job which has this id.
nbCpu	int	To list jobs which have this number of cpu.
fromSubmitDate	long	List jobs submitted after this date (unix timestamp).
toSubmitDate	long	List jobs submitted before this date (unix timestamp)
owner	string	To list all jobs submitted by this owner.
status	JobStatus	To list jobs which have this status.
priority	JobPriority	To list jobs which have this priority
outPutPath	string	Gets the path and file for each job output.
errorPath	string	Gets the path and file for each job error.
queue	string	To list jobs which have this queue name.

## **Class TMS::ListQueues Content**

Name	Type	Description
nbQueues	int	Represents the number of queues.
queues	List of Queue	Represents the list of queues.

## **Class TMS::ProgressOptions Content**

Name	Type	Description
jobId	string	Represents the id of the job that the user wants to see the progression of.

Name	Type	Description
jobOwner	string	Represents the owner of the job.

## **Class TMS::Progression Content**

Name	Type	Description
jobId	string	Represents the job id.
jobName	string	Represents the job name.
wallTime	int	Represents the job wall time.
startTime	long	Start date and time of the job (unix timestamp)
endTime	long	End date and time of the job (unix timestamp)
percent	double	Represent the job progression.
status	JobStatus	Represents the job status.

## **Class TMS::Queue Content**

Name	Type	<b>Description</b>
name	string	Is the queue name.
maxJobCpu	int	Is the maximum number of Cups that a job can use.
maxProcCpu	int	Is the maximum number of Cpus of the queue.
memory	int	Represents the queue memory size.
wallTime	long	Is the total wallTime of the queue.
node	int	Is the maximum number of nodes of the queue.
nbRunningJobs	int	Is the total running jobs in the queue.
nbJobsInQueue	int	Is the total number of jobs in the queue.
state	QueueStatus	Is the status of the queue.
priority	QueuePriority	Represents the priority of the queue.
description	string	Is the queue description.

## **Class TMS::SubmitOptions Content**

Name	Type	<b>Description</b>
name	string	Assigns a job name. The default is the path of job.
priority	JobPriority	Assigns priority of the job.
queue	string	Assigns the queue or class of the job.
wallTime	int	The maximum wall-clock time during which the job can run.
memory	int	Is the memory size that the job requires.
nbCpu	int	The number of cpu that the job requires.
nbNodesAndCpuPerNode	string	The number of nodes and processors per node.
outPutPath	string	Assigns the path and file for job output.
errorPath	string	Assigns the path and file for job error.

# **Enumeration TMS::JobPriority Type**

Name	Value
VERY_LOW	100
LOW	200
NORMAL	300
HIGH	400
VERY_HIGH	500

## **Enumeration TMS::JobStatus Type**

Name	Value
RUNNING	0
WAITING	1
COMPLETED	2
CANCELED	3
HELD	4
QUEUED	5
FAILED	6
NOT_SUBMITTED	7

# **Enumeration TMS::QueuePriority Type**

Name	Value
VERY_LOW	0
LOW	1
NORMAL	2
HIGH	3
VERY_HIGH	4

# **Enumeration TMS::QueueStatus Type**

Name	Value
STARTED	0
RUNNING	1
NOT_STARTED	2
NOT_AVAILABLE	3

# **Chapter 4**

# API specification for Information Management Service (IMS)

# 4.1 Definition of the functions of the package

## 4.1.1 Function IMS::exportCommands

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	<b>Description</b>	Mode	Required
sessionKey	string	The key of the session of the user that submits the command (current session key)	IN	yes
oldSessionKey	string	The key of the session to export (session has ended)	IN	yes
filename	string	The path of the output file containing the Vishnu shell commands	INOUT	yes

## Description

The exportCommands() function exports all the commands made by a user during a session

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

#### **Signature**

int exportCommands(const string& sessionKey, const string& oldSessionKey, string& filename);

## 4.1.2 Function IMS::getMetricCurrentValue

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Туре	Description	Mode	Required
sessionKey	string	The key of the session of the user that submits the command	IN	yes
machineId	string	The id of the machine	IN	yes
metricType	MetricType	Type of metric	IN	yes
metricValue	Metric	Value of the metric	OUT	yes

#### Description

The getMetricCurrentValue() function retrieve the current value of a metric on a machine

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

#### Signature

int **getMetricCurrentValue**(const string& sessionKey, const string& machineId, const MetricType& metricType, Metric& metricValue);

## 4.1.3 Function IMS::getMetricHistory

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The key of the session of the user that submits the command	IN	yes
machineId	string	The id of the machine	IN	yes
startTime	long	Start time of metric history	IN	yes
endTime	long	End time of metric history	IN	yes
metricType	MetricType	Type of metric	IN	yes
metricValues	ListMetric	List of metric values	OUT	yes

## Description

The getMetricHistory() function retrieve the history of values of a metric on a machine

#### **Return Value**

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

int **getMetricHistory**(const string& sessionKey, const string& machineId, const long& startTime, const long& endTime, const MetricType& metricType, ListMetric& metricValues);

## 4.1.4 Function IMS::getProcesses

#### Access

This function can be used by ADMIN users only

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The key of the session of the user that submits the command	IN	yes
machineId	string	The id of the machine the user wants the running processes	IN	yes
process	ListProcesses	The list of the Vishnu processes on the machine	OUT	yes

#### **Description**

The getProcesses() function gets the list of the processes running over a front machine

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
INVALID_PARAMETER	If a parameter is invalid

#### **Signature**

int getProcesses(const string& sessionKey, const string& machineId, ListProcesses& process);

## 4.1.5 Function IMS::setSystemInfo

#### Access

This function can be used by ADMIN users only

## **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The key of the session of the user that submits the command	IN	yes
machineId	string	The id of the machine	IN	yes
systemInfo	SystemInfo	Contains system information to store in Vishnu database	IN	yes

## Description

The setSystemInfo() function updates the system information of a machine

#### **Return Value**

Name	Description
VISHNU_OK	Error code returned if success

Name	Description
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

int setSystemInfo(const string& sessionKey, const string& machineId, const SystemInfo& systemInfo);

## 4.1.6 Function IMS::setSystemThreshold

#### Access

This function can be used by ADMIN users only

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The key of the session of the user that submits the command	IN	yes
machineId	string	The id of the machine	IN	yes
thresholdType	MetricType	The type of the metric to set	IN	yes
value	double	The threshold value	IN	yes

#### Description

The setSystemThreshold() function sets a threshold on a machine of a system

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

#### **Signature**

int setSystemThreshold(const string& sessionKey, const string& machineId, const MetricType& thresholdType, const double& value);

## 4.1.7 Function IMS::getSystemThreshold

#### Access

This function can be used by ADMIN users only

## **Parameters**

Parameter	Туре	Description	Mode	Required
sessionKey	string	The key of the session of the user that submits the command	IN	yes
machineId	string	The id of the machine	IN	yes
type	MetricType	The threshold type desired	IN	yes
value	double	The threshold value	OUT	yes

## Description

The getSystemThreshold() function gets a System threshold on a machine

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

#### **Signature**

int **getSystemThreshold**(const string& sessionKey, const string& machineId, const MetricType& type, double& value);

#### 4.1.8 Function IMS::defineUserIdentifier

#### Access

This function can be used by ADMIN users only

#### **Parameters**

Parameter	Type	D <mark>escriptio</mark> n	Mode	Required
sessionKey	string	The key of the session of the user that submits the command	IN	yes
format	string	The new format to use	IN	yes

#### **Description**

The defineUserIdentifier() function defines the shape of the identifiers automatically generated for the users

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	<b>Description</b>
VISHNU_OK	Error code returned if success
INVALID_PARAMETER	If a parameter is invalid
DB_ERROR	The database generated an error

## **Signature**

int defineUserIdentifier(const string& sessionKey, const string& format);

## 4.1.9 Function IMS::defineMachineIdentifier

#### Access

This function can be used by ADMIN users only

Parameter	Type	Description	Mode	Required
sessionKey	string	The key of the session of the user that submits the command	IN	yes
format	string	The new format to use	IN	yes

The defineMachineIdentifier() function defines the shape of the identifiers automatically generated for the machines

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	<b>Description</b>
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

#### **Signature**

int defineMachineIdentifier(const string& sessionKey, const string& format);

## 4.1.10 Function IMS::defineJobIdentifier

#### Access

This function can be used by ADMIN users only

#### **Parameters**

Parameter	Type	<b>Description</b>	Mode	Required
sessionKey	string	The key of the session of the user that submits the command	IN	yes
format	string	The new format to use	IN	yes

## Description

The defineJobIdentifier() function defines the shape of the identifiers automatically generated for the jobs

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

#### Signature

int **defineJobIdentifier**(const string& sessionKey, const string& format);

## 4.1.11 Function IMS::defineTransferIdentifier

#### Access

This function can be used by ADMIN users only

Parameter	Type	Description	Mode	Required
sessionKey	string	The key of the session of the user that submits the command	IN	yes
format	string	The new format to use	IN	yes

The defineTransferIdentifier() function defines the shape of the identifiers automatically generated for the file transfers

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

## Signature

int defineTransferIdentifier(const string& sessionKey, const string& format);

## 4.1.12 Function IMS::loadShed

#### Access

This function can be used by ADMIN users only

#### **Parameters**

Parameter	Type	<b>D</b> escription	Mode	Required
sessionKey	string	The key of the session of the user that submits the command	IN	yes
machineId	string	The id of the machine to stop	IN	yes
loadShedType	LoadShedType	Selects a load shedding mode (SOFT: stops all services and they can be restarted, HARD: stops all services, they cannot be restarted)	IN	yes

## Description

The loadShed() function load sheds a machine

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
COMPONENT_ERROR	If a component is unavailable
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

## **Signature**

int loadShed(const string& sessionKey, const string& machineId, const LoadShedType& loadShedType);

## 4.1.13 Function IMS::setUpdateFrequency

#### Access

This function can be used by ADMIN users only

Parameter	Type	Description	Mode	Required
sessionKey	string	The key of the session of the user that submits the command	IN	yes
freq	int	Frequency the data are updated, in second	IN	yes

The setUpdateFrequency() function sets the update frequency of the IMS tables

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

#### **Signature**

int setUpdateFrequency(const string& sessionKey, const int& freq);

## 4.1.14 Function IMS::getUpdateFrequency

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	<b>Description</b>	Mode	Required
sessionKey	string	The key of the session of the user that submits the command	IN	yes
freq	int	Frequency the data are updated, in second	OUT	yes

## Description

The getUpdateFrequency() function gets the update frequency of the IMS database

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

#### **Signature**

int getUpdateFrequency(const string& sessionKey, int& freq);

# 4.2 Data types definitions

Class IMS::ListMetric Content

Name	Type	Description
metric	List of Metric	The metrics of the list

## **Class IMS::ListProcesses Content**

Name	Type	Description
processName	List of string	The Vishnu processes of the list

## **Class IMS::Metric Content**

Name	Type	Description
type	MetricType	The type of the metric
value	double	The value of the metric
time	int	The timestamp the metric had the value

## Class IMS::SystemInfo Content

Name	Type	<b>Description</b>
memory	long	Amount of RAM memory available on the machine (in Bytes)
diskSpace	long	Amount of disk space available on the machine (in Bytes)

# **Enumeration IMS::LoadShedType Type**

Name	Value	
SOFT	0	
HARD	1	

## **Enumeration IMS::MetricType Type**

Name	Value
CPUNBR	0
CPUUSE	1
DISKSPACE	2
FREEDISKSPACE	3
MEMORY	4
FREEMEMORY	5

# **Chapter 5**

# API specification for File Management Service (FMS)

# 5.1 Definition of the functions of the package

## 5.1.1 Function FMS::createFile

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	<b>Description</b>	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The file to create following the pattern [host:]file path	IN	yes
mode	int	The file access permissions in octal numeral system	IN	no

#### **Description**

The createFile() function creates files on remote machines.

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed successfully.
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

## **Signature**

int **createFile**(const string& sessionKey, const string& path, const int& mode = 644);

## 5.1.2 Function FMS::createDir

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The directory to create following the pattern [host:]directory path	IN	yes
mode	int	the new directories permission access in octal numeral system	IN	no

## Description

The createDir() function creates directories on remote machines.

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed successfully.
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

## Signature

int **createDir**(const string& sessionKey, const string& path, const int& mode = 755);

## 5.1.3 Function FMS::removeFile

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The file to remove following the pattern [host:]file path	IN	yes

## **Description**

The removeFile() function removes files from remote hosts.

#### **Return Value**

Name	Description
VISHNU_OK	The service has been performed successfully.

Name	Description
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER an option or a parameter provided is invalid for this ser	
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

int removeFile(const string& sessionKey, const string& path);

#### 5.1.4 Function FMS::removeDir

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Туре	<b>Description</b>	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The directory to remove following the pattern [host:]directory path	IN	yes

## **Description**

The removeDir() function removes directories (and subdirectories) from remote machines.

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	<b>Description</b>		
VISHNU_OK	The service has been performed successfully.		
INVALID_SESSION_KEY	Invalid provided session key.		
INVALID_MACHINE_ID	Invalid provided machine identifier.		
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.		
FMS_INVALID_PATH	The path provided is invalid.		
FMS_INVALID_CFG_FILE	Option unknown in the config file.		
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.		
FMS_PERMISSION_DENIED	User does not have permission access.		
DB_ERROR	A problem occurs with the database.		

## **Signature**

int **removeDir**(const string& sessionKey, const string& path);

## 5.1.5 Function FMS::chGrp

#### Access

This function can be used by any VISHNU user

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The file/directory following the pattern [host:]file path	IN	yes
group	string	the new group owner of file/directory	IN	yes

The chGrp() function changes group owner of remote files/directories.

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed successfully.
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

## Signature

int chGrp(const string& sessionKey, const string& path, const string& group);

## 5.1.6 Function FMS::chMod

#### Access

This function can be used by any VISHNU user

## **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The file/directory following the pattern [host:]file path	IN	yes
mode	int	the access rigths of file/directory in octal system.	IN	yes

## Description

The chMod() function changes access rights of remote files/directories.

## **Return Value**

Name	Description
VISHNU_OK	The service has been performed successfully.
INVALID_SESSION_KEY	Invalid provided session key.
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.

int chMod(const string& sessionKey, const string& path, const int& mode);

## 5.1.7 Function FMS::headOfFile

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The file following the pattern [host:]file path	IN	yes
fileContent	string	The first "nLine" lines of the file	OUT	yes
nLine	int	Number of lines to display	IN	no

## Description

The headOfFile() function displays a few first lines of files located on remote machines.

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed successfully.
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

## **Signature**

int **headOfFile**(const string& sessionKey, const string& path, string& fileContent, const int& nLine = 10);

## 5.1.8 Function FMS::tailOfFile

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The file following the pattern [host:]file path	IN	yes
fileContent	string	The last "nLine" lines of the file	OUT	yes
nLine	int	number of lines to display	IN	no

## Description

The tailOfFile() function displays a few last lines of files located on remote machines

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed successfully.
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

#### Signature

int tailOfFile(const string& sessionKey, const string& path, string& fileContent, const int& nLine = 10);

## 5.1.9 Function FMS::contentOfFile

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The file to display following the pattern [host:]file path	IN	yes
fileContent	string	The content of the file	OUT	yes

## Description

The contentOfFile() function displays content of files located on remote machines

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed successfully.
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

#### Signature

int contentOfFile(const string& sessionKey, const string& path, string& fileContent);

## 5.1.10 Function FMS::listDir

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The directory to list following the pattern	IN	Vac
paul		[host:]directory path	111	yes
dirContent	StringList	The content of the directory (only files names with short	OUT	Mac
diffentent		format, all files informations with long format)	001	yes
options	LsDirOptions	List of options for the listDir command	IN	no

## Description

The listDir() function displays the content of a remote directory.

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed succesfully.

## Signature

int **listDir**(const string& sessionKey, const string& path, StringList& dirContent, const LsDirOptions& options = LsDirOptions());

## 5.1.11 Function FMS::copyFile

## Access

This function can be used by any VISHNU user

## **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
src	string	The source file to copy following the pattern [host:]file path	IN	yes
dest	string	The path of the destination file	IN	yes
options	CopyFileOptions	the copy options	IN	no

## Description

The copyFile() function executes a synchronous copy of file.

#### **Return Value**

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

int **copyFile**(const string& sessionKey, const string& src, const string& dest, const CopyFileOptions& options = CopyFileOptions());

## 5.1.12 Function FMS::copyAsyncFile

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	<b>Description</b>	Mode	Required
sessionKey	string	The session key	IN	yes
src	string	The source file to copy following the pattern [host:]file path	IN	yes
dest	string	The path of the destination file	IN	yes
thrId	long	A file transfer identifier (allowing for instance to ckeck the status of a file transfer, or to cancel it)	OUT	yes
options	CopyFileOptions	the copy options	IN	no

#### Description

The copyAsyncFile() function executes an asynchronous copy of file.

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

#### Signature

int **copyAsyncFile**(const string& sessionKey, const string& src, const string& dest, long& thrId, const CopyFileOptions& options = CopyFileOptions());

## 5.1.13 Function FMS::moveFile

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Туре	Description	Mode	Required
sessionKey	string	The session key	IN	yes
src	string	The source file to move following the pattern [host:]file path	IN	yes
dest	string	The path of the destination file	IN	yes
options	MvFileOptions	The move command options	IN	no

## **Description**

The moveFile() function executes a synchronous move of file.

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

## Signature

int **moveFile**(const string& sessionKey, const string& src, const string& dest, const MvFileOptions& options = MvFileOptions());

## 5.1.14 Function FMS::moveAsyncFile

## Access

This function can be used by any VISHNU user

## **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
src	string	The source file to move following the pattern [host:]file path	IN	yes
dest	string	The path of the destination file	IN	yes
thrId	long	The file tranfer identifier (allowing for instance to ckeck the status of a file transfer, or to cancel it)	OUT	yes
options	MvFileOptions	The mv command options	IN	no

## Description

The moveAsyncFile() function executes an asynchronous move of file.

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

#### Signature

int **moveAsyncFile**(const string& sessionKey, const string& src, const string& dest, long& thrId, const MvFileOptions& options = MvFileOptions());

## 5.1.15 Function FMS::stopFileTransfer

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
options	StopTransferOptions	The stop file transfer command options	IN	no

## Description

The stopFileTransfer() function stops an execution of a set of file transfers.

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

#### **Signature**

 $int \ \textbf{stopFileTransfer} (const \ string \& \ session Key, \ const \ Stop Transfer Options \& \ options = Stop Transfer Options());$ 

#### 5.1.16 Function FMS::listFileTransferStatus

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
options	LsTrStatusOptions	The filter options	IN	no

## **Description**

The listFileTransferStatus() function displays the status of all file transfers submitted by User.

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

## Signature

int **listFileTransferStatus**(const string& sessionKey, const **LsTrS**tatusOptions& options = LsTrStatusOptions());

## 5.1.17 Function FMS::listFileTransfers

## Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
options	LsTransferOptions	The filter options	IN	no

## **Description**

The listFileTransfers() function displays the history of all file transfers submitted by User.

#### **Return Value**

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.

Name	Description
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

int listFileTransfers(const string& sessionKey, const LsTransferOptions& options = LsTransferOptions());

## 5.1.18 Function FMS::getFilesInfo

#### Access

This function can be used by any VISHNU user

#### **Parameters**

Parameter	Туре	Description	Mode	Required
sessionKey	string	The session key	IN	yes
pathList	string	The file whose inode information will be displayed	IN	yes
filesinfo	FileStat	The inode information	OUT	yes

## Description

The getFilesInfo() function displays the information of files.

#### **Return Value**

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

## Signature

int getFilesInfo(const string& sessionKey, const string& pathList, FileStat& filesinfo);

# 5.2 Data types definitions

## **Class FMS::CopyFileOptions Content**

Name	Type	Description
isRecursive	boolean	It specifies when the copy is recursive (case of directory) or not.
trCommand	TransferCommand	the command to use to perform file transfer.

#### **Class FMS::FileStat Content**

Name	Type	Description
path	string	The path of the file
owner	string	The name of the owner of the file
group	string	The group name of the owner
uid	long	The user identifier of the owner
gid	long	The group identifier of the owner
size	long	The size of the file in bytes
atime	long	The time of last access
mtime	long	The time of last modification
ctime	long	The time of the last change of the inode information
type	FileType	The file type

## **Class FMS::LsDirOptions Content**

Name	Type	Description
longFormat	boolean	It specifies the long display format (all available file informations)
allFiles	boolean	Allows to display all files including hidden files

## Class FMS::LsTrStatusOptions Content

Name	Type	Description
transferId	string	a given transfer id
fromMachineId	string	the machine that is the source of the file transfer
userId	string	allows the admin to list file transfers initiated by a
usciiu	Sumg	specific user

## **Class FMS::LsTransferOptions Content**

Name	Type	Description
fromMachineId	string	the machine that is the source of the file transfer
userId	string	allows the admin to list file transfers initiated by a specific user
status	Status	the file transfer status

## Class FMS::MvFileOptions Content

Name	Type	Description
trCommand	TransferCommand	the command to use to perform file transfer.

## Class FMS::StopTransferOptions Content

Name	Type	Description
transferId	string	a given transfer id
fromMachineId	string	the machine that is the source of the file transfer
userId	string	allows an admin to stop file transfers of a specific user

## **Class FMS::StringList Content**

Name	Type	Description
listOfStrings	List of string	the dynamic list of strings.

# **Enumeration FMS::FileType Type**

Name	Value
BLOCK	0
CHARACTER	1
DIRECTORY	2
SYMBOLICLINK	3
SCKT	4
FIFO	5
REGULAR	6

## **Enumeration FMS::Status Type**

Name	Value
INPROGRESS	0
COMPLETED	1
CANCELLED	2
FAILED	3

# **Enumeration FMS::TransferCommand Type**

Name		Value
SCP		0
RSYNC	-	1