D1.1d - VISHNU Command-line
interface specifications

**D1.1d - VISHNU Command-line interface specifications** 



## COLLABORATORS

	TITLE:  D1.1d - VISHNU Co	mmand-line interface		
ACTION	NAME	DATE	SIGNATURE	
WRITTEN BY	Benjamin Isnard, Daouda Traoré, Eugène Pamba Capo-Chichi, Kevin Coulomb, and Ibrahima Cissé	June 29, 2012		

## REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
0	05/01/2011	Formatting example	SysFera
1	13/01/2011	First release	SysFera
2	10/02/2011	Removed UMS::SessionStateType. Added UMS::StatusType, UMS::PrivilegeType. Modified UMS::addVishnuUser, UMS::updateUser, UMS::addLocalAccount, UMS::addMachine, UMS::updateMachine, UMS::listSessions, UMS::restoreConfiguration.	SysFera
3	18/02/2011	Renamed all commands to follow C-style command names with vishnu prefix.  Added the help option to all commands.  Modified update_machine and export_commands.  Removed the VISHNU_SESSION_KEY environment variable on all commands.	SysFera

## **REVISION HISTORY**

NUMBER	DATE	DESCRIPTION	NAME
4	15/04/2011	Updates for TMS: Modified description of machineld parameter, vishnu_submit_job service. Modified name of get_all_jobs_output to get_completed_jobs_output. Added input parameter outDir to get_job_output and get_completed_jobs_output. Added vishnu_get_machine_refresh_period service. Removed set_machine_env service. Removed jobPriority option in submit_job. Updates for IMS: Add option in exportCommand, getMetricCurrentValue, getProcesses, getMetricHistory, restart and getSystemThreshold. Add services stop and getSystemInfo.	SysFera
5	21/04/2011	Updates for TMS: Removed vishnu_get_machine_refresh_period and vishnu_set_machine_refresh_period services. Added UNDEFINED status of JobStatus Enum. Added UNDEFINED priority of JobPriority Enum. Removed of outputPah and errorPath of ListJobsOptions. Removed scriptContent in Job class. Added ERRCODE_ALREADY_TERMINATED, ERRCODE_ALREADY_CANCELED, ERRCODE_JOB_IS_NOT_TERMINATED in exception list. Modified values of JobPriority Enum. Modified values of QueuePriority and QueueStatus. Added UNDEFINED priority of QueuePriority. Added option queueName in vishnu_list_queues.	SysFera
6	24/05/2011	Updates of UMS: Added new error code for addLocalAccount and updateLocalAccount.	SysFera
10	15/12/2011	Updates of TMS: Extended vishnu_submit_job options. Updates of FMS: Added recursive option to vishnu_create_dir command. Updates of UMS: Added vishnu_current_session_id command. Added -w option to connect and reconnect command.	SysFera

## REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
11	10/01/2012	Updates of TMS: Modified decription of vishnu_submit_job command (to take into account automatic submission).  Extended vishnu_submit_job options (added load criterion option for automatic submission, added option to select a queue automatically). Modified decription of vishnu_list_jobs command (to take into account listing of jobs on all machines).  Extended vishnu_list_jobs options (added multipleStatus option for combination of several job states, added option to list all jobs submitted by the underlying batch scheduler (VISHNU jobs and jobs submitted out of VISHNU).	SysFera
12	20/01/2012	Updates of UMS: Added vishnu_connect_m and vishnu_reconnect_m respectively for connection and reconnection using multiple VISHNU accounts defined on the .netrc file. Modified vishnu_list_users option -u to -i for userId and added a new option for user-authentication system. Added vishnu_add_authentication_system, vishnu_update_authentication_system, vishnu_delete_authentication_system, vishnu_list_authentication_system, vishnu_add_auth_account, vishnu_update_auth_account, vishnu_delete_auth_account, vishnu_list_auth_account. Updates of IMS: Added vishnu_define_auth_identifier	SysFera

# **Contents**

1	Docu	cument presentation	1
	1.1	Document objectives	. 1
	1.2	Document structure	. 1
	1.3	References	. 1
	1.4	Glossary	. 1
	1.5	Generic command definition format	. 2
	1.6	Environment variables and options	. 2
2	Com	mmands specification for User Man <mark>ageme</mark> nt Service (UMS)	4
	2.1	Command definitions	
		2.1.1 vishnu_connect	. 4
		2.1.2 vishnu_connect_m	. 5
		2.1.3 vishnu_reconnect	. 5
		2.1.4 vishnu_reconnect_m	. 6
		2.1.5 vishnu_add_user	. 6
		2.1.6 vishnu_update_user	. 6
		2.1.7 vishnu_delete_user	. 7
		2.1.8 vishnu_close	. 7
		2.1.9 vishnu_change_password	. 8
		2.1.10 vishnu_reset_password	. 8
		2.1.11 vishnu_add_local_account	. 8
		2.1.12 vishnu_update_local_account	. 9
		2.1.13 vishnu_delete_local_account	. 9
		2.1.14 vishnu_save_configuration	. 10
		2.1.15 vishnu_restore_configuration	. 10
		2.1.16 vishnu_add_machine	. 11
		2.1.17 vishnu_update_machine	. 11
		2.1.18 vishnu_delete_machine	. 12
		2.1.19 vishnu_list_local_accounts	. 12
		2.1.20 vishnu_list_machines	. 13

		2.1.21	vishnu_list_history_cmd	13
		2.1.22	vishnu_list_options	14
		2.1.23	vishnu_list_users	14
		2.1.24	vishnu_list_sessions	14
		2.1.25	vishnu_configure_default_option	15
		2.1.26	vishnu_configure_option	16
		2.1.27	vishnu_current_session_id	16
		2.1.28	vishnu_add_auth_system	16
		2.1.29	vishnu_update_auth_system	17
		2.1.30	vishnu_delete_auth_system	18
		2.1.31	vishnu_list_auth_systems	18
		2.1.32	vishnu_add_auth_account	18
		2.1.33	vishnu_update_auth_account	19
		2.1.34	vishnu_delete_auth_account	19
		2.1.35	vishnu_list_auth_accounts	20
		2.1.36	vishnu_set_ssh_key	20
	2.2	Parame	eters definitions	21
2	Com	manda	specification for Tasks Management Service (TMS)	22
,	3.1		and definitions	
	3.1	3.1.1	vishnu_submit_job	
		3.1.2	vishnu_get_job_info	
		3.1.2	vishnu_get_job_progress	
		3.1.4	vishnu_list_queues	
		3.1.5	vishnu_list_jobs	
		3.1.6	vishnu_get_job_output	
		3.1.7	vishnu_get_job_output	
		3.1.8	vishnu_cancel_job	
	3.2		eters definitions	
	3.2	1 aranic	acts definitions	20
4	Com		specification for Information Management Service (IMS)	28
	4.1	Comm	and definitions	28
		4.1.1	vishnu_export_commands	28
		4.1.2	vishnu_get_metric_current_value	28
		4.1.3	vishnu_get_metric_history	29
		4.1.4	vishnu_get_processes	29
		4.1.5	vishnu_set_system_info	29
		4.1.6	vishnu_set_system_threshold	30
		4.1.7	vishnu_get_system_threshold	30

		4.1.8	vishnu_define_user_identifier	31
		4.1.9	vishnu_define_machine_identifier	31
		4.1.10	vishnu_define_job_identifier	31
		4.1.11	vishnu_define_transfer_identifier	32
		4.1.12	vishnu_define_auth_identifier	32
		4.1.13	vishnu_load_shed	33
		4.1.14	vishnu_set_update_frequency	33
		4.1.15	vishnu_get_update_frequency	33
		4.1.16	vishnu_stop	34
		4.1.17	vishnu_get_system_info	34
		4.1.18	vishnu_restart	34
	4.2	Parame	eters definitions	35
_	~	_		
5			specification for File Management Service (FMS)	37
	5.1		and definitions	
		5.1.1	vishnu_create_file	
		5.1.2	vishnu_create_dir	
		5.1.3	vishnu_remove_file	
		5.1.4	vishnu_remove_dir	38
		5.1.5	vishnu_ch_grp	39
		5.1.6	vishnu_ch_mod	39
		5.1.7	vishnu_head_of_file	39
		5.1.8	vishnu_tail_of_file	40
		5.1.9	vishnu_content_of_file	40
		5.1.10	vishnu_list_dir	40
		5.1.11	vishnu_copy_file	41
		5.1.12	vishnu_copy_async_file	41
		5.1.13	vishnu_move_file	42
		5.1.14	vishnu_move_async_file	42
		5.1.15	vishnu_stop_file_transfer	43
			vishnu_list_file_transfers	
		5.1.17	vishnu_get_file_info	44
	5.2	Doromo	sters definitions	44

## **Chapter 1**

# Document presentation

## 1.1 Document objectives

This document presents the detailed specifications of the VISHNU command line user interface.

These specifications include the definition of all commands including administration commands.

## 1.2 Document structure

The document is divided into 4 parts corresponding to the 4 modules that compose the Vishnu system:

- UMS: Users Management Service
- TMS: Tasks Management Service
- FMS: Files Management Service
- IMS: Information Management Service

Each module corresponds to a chapter in the document, and each chapter contains the following sections:

- A first section describing the definition of all commands provided by the package.
- A second section describing the definition of all enumerated values used as command parameters.

## 1.3 References

• D1.1a: VISHNU General specifications

## 1.4 Glossary

• VISHNU admin: any user having the administrator privilege

## 1.5 Generic command definition format

This section presents the generic format used in the following chapters to describe the commands. It also details the environment variables required and the user options.

A commands is defined as follows:

#### Access

Here is detailed the access level of the command line (i.e. the privilege required to use this command)

#### **Description**

Here is detailed the purpose of the command line.

#### Example of use

Here is detailed an example of the use of the command line which starts by optional arguments preceded by a short letter and the required arguments at the end.

myCommand -l acLogin -s sshKeyPath userId

#### **Parameters**

The following table contains all the input arguments of the command with their type and description, their short letter for options and a required flag.

Parameter	Type	Option	Description	Required
userId	string		This is an example of a required argument	YES
acLogin	string	1	This is an example of an optional argument	NO
sshKeyPath	string	S	This is an example of an optional argument	NO

The following table contains the list of environment variables information. These environment variables can be mandatory or optional and the value will be overriden by the corresponding command-line option if applicable. When the user option flag is true, the value for this variable can be defined persistently as a user option stored in the database (see the "vishnu\_configure\_option" command.

## **Environment variables**

Name	Parameter	Туре	Description	Required	User option
VISHNU_CONFIG_FILE	N/A	string	This is an example of an environment variable	YES	NO

#### Note:

For each command line the -h option can be used for help.

## 1.6 Environment variables and options

Here is detailed the way to use the user options which are stored in the database and environment variables in VISHNU.

## Example 1.1 Pseudo code

```
if (the option is provided in the command line) {
    optionValue = option
} else {
    if (an environment variable exists) {
        optionValue = EnVariable_Value

    } else {

        if (a value has been defined in the user configuration) {
            optionValue = user_Option
        }
        else {
            //The default value of the option defined by VISHNU admin is used optionValue = defaultValueOption
        }
    }
}
```

# **Chapter 2**

# Commands specification for User Management Service (UMS)

## 2.1 Command definitions

## 2.1.1 vishnu connect

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_connect command opens a session

## Example of use

vishnu\_connect[-h][-p closePolicy][-d sessionInactivityDelay][-s substituteUserId][-u userId]
[-w password]

#### **Parameters**

Parameter	Type	Option	Description	Required
closePolicy	SessionCloseType	p	is an option for closing session automatically	NO
			is the maximum delay in seconds between two	
sessionInactivityDelay	int	d	user requests when the CLOSE_ON_TIMEOUT	NO
			policy is set	
			is an admin option which allows an admin to	
substituteUserId	string	s	open a session as if she was another user	NO
			identified by her userId	
userId string u userId represents the		userId represents the VISHNU user identifier	NO	
password	string	W	password represents the password of the user	NO

#### **Environment variables**

Name	Parameter	Туре	Description	Required	User option
VISHNU_CLOSE_POLICY	closePolicy	SessionCloseType	is an option for closing session automatically	NO	YES

## 2.1.2 vishnu\_connect\_m

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_connect\_m command opens a session by trying multiple couples (userId, password) each in turn

#### Example of use

vishnu\_connect\_m[-h][-p closePolicy][-d sessionInactivityDelay][-s substituteUserId]userIdp-wd

#### **Parameters**

Parameter	Type	Option	Description	Required
closePolicy	SessionCloseType	p	is an option for closing session automatically	NO
			is the maximum delay in seconds between two	
sessionInactivityDelay	int	d	user requests when the CLOSE_ON_TIMEOUT	NO
			policy is set	
			is an admin option which allows an admin to	
substituteUserId	string	S	open a session as if she was another user	NO
			identified by her userId	
			userId represents the VISHNU user identifier.	
userId	string		There may be various users id used set	YES
			alternatively with the corresponding password.	
			represents the password of the user. There may	
pwd	string		be various password used set alternatively with	YES
			the corresponding userId.	

#### **Environment variables**

Name	Parameter	Туре	Description	Required	User option
VISHNU_CLOSE_POLICY	closePolicy	SessionCloseType	is an option for closing session automatically	NO	YES

## 2.1.3 vishnu\_reconnect

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_reconnect command reconnects to a session that is still active

#### Example of use

vishnu\_reconnect[-h][-u userId][-w password] sessionId

Parameter	Type	Option	Description	Required
sessionId	string		sessionId is the identifier of the session defined in	YES
	string		the database	1123
userId	string	u	userId represents the VISHNU user identifier	NO
password	string	W	password represents the password of the user	NO

This command defines no environment variables.

## 2.1.4 vishnu\_reconnect\_m

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_reconnect\_m command reconnects to a session that is still active by trying multiple couples (userId, password) each in turn

#### Example of use

vishnu\_reconnect\_m [-h] sessionId userId pwd

#### **Parameters**

Parameter	Type	<b>Option</b>	<b>Description</b>	Required
sessionId	string		sessionId is the identifier of the session defined in the database	YES
userId	string		userId represents the VISHNU user identifier	YES
pwd	string		represents the password of the user	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.5 vishnu\_add\_user

#### Access

This command line can be used by ADMIN users only

## Description

The vishnu\_add\_user command adds a new VISHNU user

#### Example of use

vishnu\_add\_user[-h] firstname lastname privilege email

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	<b>Required</b>
firstname	string		is the firstname of the user	YES
lastname	string		is the lastname of the user	YES
privilege	PrivilegeType		is the privilege of the user (admin or simple user)	YES
email	string		is the email of the user	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.6 vishnu\_update\_user

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_update\_user command updates the user information except the userId and the password

#### Example of use

vishnu\_update\_user[-h][-f firstname][-l lastname][-p privilege][-m email][-s status]userId

#### **Parameters**

Parameter	Type	Option	Description	Required
userId	string	/	represents the VISHNU user identifier	YES
firstname	string	f	represents the updated firstname of the user	NO
lastname	string	1	represents the updated lastname of the user	NO
privilege	PrivilegeType	p	represents the updated privilege of the user	NO
email	string	m	represents the updated email address of the user	NO
status	StatusType	S	represents the status of the user (LOCKED or ACTIVE)	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.7 vishnu\_delete\_user

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_delete\_user command removes a user from VISHNU

## Example of use

vishnu\_delete\_user[-h] userId

#### **Parameters**

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier of the user who will be deleted from VISHNU	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.8 vishnu\_close

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_close command closes the session

## Example of use

vishnu\_close[-h]

This command defines no arguments.

#### **Environment variables**

This command defines no environment variables.

## 2.1.9 vishnu\_change\_password

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_change\_password command changes the password

#### Example of use

vishnu\_change\_password[-h] userId

#### **Parameters**

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier	YES
password	string		password represents the password of the user, it is an interactive parameter	YES
passwordNew	string		passwordNew represents the new password of the user, it is an interactive parameter	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.10 vishnu\_reset\_password

## Access

This command line can be used by ADMIN users only

## Description

The vishnu\_reset\_password command resets the password of a user

## Example of use

vishnu\_reset\_password[-h] userId

#### **Parameters**

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier of the user whose password will be reset	YES

## **Environment variables**

This command defines no environment variables.

## 2.1.11 vishnu\_add\_local\_account

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_add\_local\_account command adds a new local user configuration

#### Example of use

vishnu\_add\_local\_account [-h] userId machineId acLogin sshKeyPath homeDirectory

#### **Parameters**

Parameter	Type	Option	Description	Required
userId	string		The userId represents the VISHNU user identifier	YES
usciiu	Sumg	/ /	of the user of the local user configuration	1123
machineId	string		The MachineId represents the identifier of the	YES
machinera	String		machine associated to the local user configuration	ILS
acLogin	string		accLogin represents the login of the user on the	YES
acLogin	string		associated machine	ILS
sshKeyPath	string		sshKeyPath is the path of the ssh key of the user	YES
string	String		on the associated machine	1125
homeDirectory	string		HomeDirectory is the path of the home directory	YES
HomeDirectory	string		of the user on the associated machine	ILO

#### **Environment variables**

This command defines no environment variables.

## 2.1.12 vishnu\_update\_local\_account

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_update\_local\_account command updates a local user configuration

#### Example of use

vishnu\_update\_local\_account[-h][-l acLogin][-s sshKeyPath][-d homeDirectory]userId machineId

## **Parameters**

Parameter	Type	Option	Description	Required
userId	string		The userId represents the VISHNU user identifier	YES
usciiu	sumg		of the user of the local user configuration	TES
machineId	string		The MachineId represents the identifier of the	YES
macminerd	sumg		machine associated to the local user configuration	TES
acLogin	string	1	acLogin represents the login of the user on the	NO
acLogiii	sumg	1	associated machine	NO
sshKeyPath	string	c	sshKeyPath is the path of the ssh key of the user	NO
string string	S	on the associated machine	NO	
homeDirectory	string	d	HomeDirectory is the path of the home directory	NO
	sumg	u u	of the user on the associated machine	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.13 vishnu\_delete\_local\_account

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_delete\_local\_account command removes a local user configuration (for a given user on a given machine) from VISHNU

#### Example of use

vishnu\_delete\_local\_account [-h] userId machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
			userId represents the VISHNU user identifier of	
userId	string		the user whose local configuration will be deleted	YES
			for the given machine	
			machineId represents the identifier of the	
machineId	string		machine whose local configuration will be	YES
			deleted for the given user	

#### **Environment variables**

This command defines no environment variables.

## 2.1.14 vishnu\_save\_configuration

#### Access

This command line can be used by ADMIN users only

## Description

The vishnu\_save\_configuration command saves the configuration of VISHNU

## Example of use

vishnu\_save\_configuration[-h]

#### **Parameters**

This command defines no arguments.

#### **Environment variables**

This command defines no environment variables.

## 2.1.15 vishnu\_restore\_configuration

#### Access

This command line can be used by ADMIN users only

## Description

The vishnu\_restore\_configuration command restores the configuration of VISHNU

#### Example of use

vishnu\_restore\_configuration [-h] filePath

Parameter	Type	Option	Description	Required
filePath	string		The filePath is the path of the file used to restore VISHNU configuration	YES

This command defines no environment variables.

## 2.1.16 vishnu\_add\_machine

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_add\_machine command adds a new machine in VISHNU

#### Example of use

vishnu\_add\_machine[-h] name site language sshPublicKeyFile machineDescription

#### **Parameters**

Parameter	Type	Optio	n Description	Required
name	string		represents the name of the machine	YES
site	string		represents the location of the machine	YES
language	string		represents the language used for the description of the machine	YES
sshPublicKeyFile	string		contains the path to the SSH public key used by VISHNU to access local user accounts	YES
machineDescription	string		represents the description of the machine	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.17 vishnu\_update\_machine

#### Access

This command line can be used by ADMIN users only

## Description

The vishnu\_update\_machine command updates machine description

## Example of use

vishnu\_update\_machine[-h][-n name][-s site][-d machineDescription][-l language][-t status][-k sshPublicKeyFile] machineId

Parameter	Type	Option	Description	Required
machineId	string		represents the identifier of the machine	YES
name	string	n	represents the name of the machine	NO
site	string	S	represents the location of the machine	NO
machineDescription	string	d	represents the description of the machine	NO
language	string	1	represents the language used for the description of the machine	NO

Parameter	Type	Option	Description	Required
status	StatusType	t	represents the status of the machine	NO
sshPublicKeyFile	string	k	contains the path to the SSH public key used by VISHNU to access local user accounts	NO

This command defines no environment variables.

## 2.1.18 vishnu\_delete\_machine

#### Access

This command line can be used by ADMIN users only

## Description

The vishnu\_delete\_machine command removes a machine from VISHNU

#### Example of use

vishnu\_delete\_machine[-h] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		machineId represents the identifier of the machine	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.19 vishnu\_list\_local\_accounts

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_list\_local\_accounts command lists the local user configurations

## Example of use

vishnu\_list\_local\_accounts[-h][-a][-u userId][-i machineId]

## **Parameters**

Parameter	Type	Option	Description	Required
adminListOption	boolean	a	is an admin option for listing all local configurations of all users	NO
userId	string	u	is an admin option for listing the local configurations of a specific user	NO
machineId	string	i	is an option for listing local user configurations on a specific machine	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.20 vishnu\_list\_machines

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_list\_machines command lists the machines that are accessible through VISHNU

#### Example of use

vishnu\_list\_machines[-h][-u userId][-a][-m machineId]

#### **Parameters**

Parameter	Type	Option	Description	Req <mark>uire</mark> d
userId	string	u	is an admin option for listing machines in which a specific user has a local configuration	NO
listAllMachine	boolean	a	is an option for listing all VISHNU machines	NO
machineId	string	m	is an option for listing information about a specific machine	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.21 vishnu\_list\_history\_cmd

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_list\_history\_cmd command lists the commands

#### Example of use

vishnu\_list\_history\_cmd[-h][-a][-u userId][-i sessionId][-s startDateOption][-e endDateOption]

#### **Parameters**

Parameter	Type	Option	Description	Required
adminListOption	boolean	a	is an admin option for listing all commands of all	NO
adminiListOption	boolean	a	users	
userId	string	u	is an admin option for listing commands launched	NO
useria	string	u	by a specific user identified by his/her userId	110
sessionId	string	i	lists all commands launched within a specific	NO
sessiona	string	1	session	110
			allows the user to organize the commands listed	
startDateOption	long	S	by providing the start date (the UNIX timestamp	NO
			of the start date is used)	
			allows the user to organize the commands listed	
endDateOption	long	e	by providing the end date (the timestamp of the	NO
chabateOption	long		end date is used). By default, the end date is the	110
			current day	

## **Environment variables**

This command defines no environment variables.

## 2.1.22 vishnu\_list\_options

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_list\_options command lists the options of the user

#### Example of use

vishnu\_list\_options[-h][-a][-u userId][-n optionName]

#### **Parameters**

Parameter	Type	Option	Description	Req <mark>uire</mark> d
listAllDeftValue	boolean	a	is an option for listing all default option values defined by VISHNU administrator	NO
userId	string	u	is an admin option for listing the options of a specific user	NO
optionName	string	n	allows the user to get the value of a specific option identified by its name	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.23 vishnu\_list\_users

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_list\_users command lists VISHNU users

#### Example of use

vishnu\_list\_users[-h][-u userId][-i authSystemId]

#### **Parameters**

Parameter	Type	Option	Description	Required
userId	string	u	allows an admin to get information about a specific user identified by his/her userId	NO
authSystemId	string	i	is an option to list users who have local user-authentication configurations on a specific user-authentication system	NO

## **Environment variables**

This command defines no environment variables.

## 2.1.24 vishnu\_list\_sessions

## Access

This command line can be used by any VISHNU user

## **Description**

The vishnu\_list\_sessions command lists all sessions of the user

## Example of use

vishnu\_list\_sessions[-h][-t status][-p sessionClosePolicy][-d sessionInactivityDelay][-m machineId][-a][-u userId][-i sessionId][-s startDateOption][-e endDateOption]

#### **Parameters**

Parameter	Type	Option	Description	Required
status	StatusType	t	specifies the status of the sessions which will be listed	NO
sessionClosePolicy	SessionCloseType	p	specifies the closure mode of the sessions which will be listed (CLOSE_ON_TIMEOUT or CLOSE_ON_DISCONNECT)	NO
sessionInactivityDelay	int	d	specifies the inactivity delay in seconds of the sessions which will be listed	NO
machineId	string	m	allows the user to list sessions opened on a specific client's machine by using its name	NO
adminListOption	boolean	a	is an admin option for listing all sessions of all users	NO
userId	string	u	is an admin option for listing sessions opened by a specific user	NO
sessionId	string	i	allows the user to list all commands launched within a specific session	NO
startDateOption	long	s	allows the user to organize the commands listed by providing the start date (the UNIX timestamp of the start date is used)	NO
endDateOption	long	e	allows the user to organize the commands listed by providing the end date (the timestamp of the end date is used). By default, the end date is the current day	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.25 vishnu\_configure\_default\_option

#### Access

This command line can be used by ADMIN users only

#### Description

The vishnu\_configure\_default\_option command configures a default option value

#### Example of use

vishnu\_configure\_default\_option[-h] optionName value

#### **Parameters**

Parameter	Type	Option	Description	Required
optionName	string		represents the name of an option	YES
value	string		represents the value of an option	YES

## **Environment variables**

This command defines no environment variables.

## 2.1.26 vishnu\_configure\_option

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_configure\_option command configures an option of the user

#### Example of use

vishnu\_configure\_option[-h] optionName value

#### **Parameters**

Parameter	Туре	<b>Option</b>	Description	Req <mark>uired</mark>
optionName	string		represents the name of an option	YES
value	string		represents the value of an option	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.27 vishnu\_current\_session\_id

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_current\_session\_id command display the session id

#### Example of use

vishnu\_current\_session\_id[-h]

#### **Parameters**

This command defines no arguments.

#### **Environment variables**

This command defines no environment variables.

## 2.1.28 vishnu\_add\_auth\_system

#### Access

This command line can be used by ADMIN users only

## Description

The vishnu\_add\_auth\_system command adds a new user-authentication system in VISHNU

## Example of use

vishnu\_add\_auth\_system [-h] [-b ldapBase] name URI authLogin authPassword userPasswordEncryption type

Parameter	Type	Option	Description	Required
name	string		corresponds to the user-authentication system's name	YES

Parameter	Type	Option	Description	Required	
URI	string		is the URI of the user-authentication systems (by	YES	
String			the form host:port for LDAP)	ILS	
authLogin	string		is the login used to connect to the	YES	
autilLogiii	string		user-authentication system	TLS	
authPassword	string		is the password used to connect to the	YES	
autiii ussword	sumg		user-authentication system	TES	
userPasswordEncryption	EncryptionMethod		represents the encryption method used to encrypt	YES	
useri usswordEneryption	Eliciyptioniviculou		user's password	TES	
type	AuthType		represents the type of the user-authentication	YES	
type	rumrype		systems	TES	
ldapBase	string	b	is an option for user-authentication system based	NO	
Таприлос	String		on LDAP which specifies the DN of the root entry	110	

This command defines no environment variables.

## 2.1.29 vishnu\_update\_auth\_system

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_update\_auth\_system command updates a user-authentication system in VISHNU

## Example of use

vishnu\_update\_auth\_system[-h][-n name][-i URI][-u authLogin][-w authPassword][-e userPasswordEncryption][-t type][-s status][-b ldapBase]authSystemId

#### **Parameters**

Parameter	Type	Option	<b>Des</b> cription	Required
authSystemId	string		is the identifier, generated by VISHNU, of the user-authentication system	YES
name	string	n	corresponds to the user-authentication system's name	NO
URI	string	i	is the URI of the user-authentication systems (by the form host:port for LDAP)	NO
authLogin	string	u	is the login used to connect to the user-authentication system	NO
authPassword	string	w	is the password used to connect to the user-authentication system	NO
userPasswordEncryption	EncryptionMethod	e	represents the encryption method used to encrypt user's password	NO
type	AuthType	t	represents the type of the user-authentication system	NO
status	StatusType	s	represents the status of the user-authentication system	NO
ldapBase	string	b	is an option for user-authentication system based on LDAP which specifies the DN of the root entry	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.30 vishnu\_delete\_auth\_system

#### Access

This command line can be used by ADMIN users only

#### Description

The vishnu\_delete\_auth\_system command removes a user-authentication system from VISHNU

#### Example of use

vishnu\_delete\_auth\_system[-h] authSystemId

#### **Parameters**

Parameter	Type	<b>Option</b>	<b>Descri</b> ption	Required
authSystemId	string		authSystemId is the identifier of the user-authentication system	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.31 vishnu\_list\_auth\_systems

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_list\_auth\_systems command lists VISHNU user-authentification systems

#### Example of use

vishnu\_list\_auth\_systems[-h][-a][-f][-u userId][-i authSystemId]

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
listAllAuthSystems	boolean	a	is an option for listing all VISHNU user-authentication systems	NO
listFullInfo	boolean	f	is an admin option for listing full VISHNU user-authentication systems information such as all concerned only the administrator: authLogin, authPassword and userPasswordEncryption	NO
userId	string	u	is an admin option for listing all user-authentication systems in which a specific user has local user-authentication configs	NO
authSystemId	string	i	is an option for listing a specific user-authentication system	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.32 vishnu\_add\_auth\_account

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_add\_auth\_account command adds a new local user-authentication configuration

#### Example of use

vishnu\_add\_auth\_account[-h][-u userId]authSystemId acLogin

#### **Parameters**

Parameter	Type	Option	Description	Required
authSystemId	string		is the identifier of the user-authentication system	YES
userId	string	u	represents an admin option to add a user-authentication account of a specific user	NO
acLogin	string		acLogin represents the login of the user on the associated user-authentication system	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.33 vishnu\_update\_auth\_account

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_update\_auth\_account command updates a local user-authentication configuration

#### Example of use

vishnu\_update\_auth\_account [-h] [-u userId] [-l acLogin] authSystemId

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
authSystemId	string		is the identifier of the user-authentication system	YES
userId	string	u	represents an admin option to add a user-authentication account of a specific user	NO
acLogin	string	1	is an option to change the login of the user on the associated user-authentication system	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.34 vishnu\_delete\_auth\_account

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_delete\_auth\_account command removes a local user-authentication configuration from VISHNU

#### Example of use

vishnu\_delete\_auth\_account[-h][-u userId] authSystemId

Parameter	Type	Option	Description	Required
authSystemId	string		authSystemId is the identifier of the	YES
aumsystemia	sumg		user-authentication system	TES
			is an admin option which represents the VISHNU	
userId	string	u	identifier of the user whose local	NO
			user-authentication configuration will be deleted	

This command defines no environment variables.

## 2.1.35 vishnu\_list\_auth\_accounts

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_list\_auth\_accounts command lists local user-authentication configurations

## Example of use

vishnu\_list\_auth\_accounts[-h][-a][-u userId][-i authSystemId]

## **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
listAll	boolean	a	is an admin option for listing all local	NO
IISTAII	boolean	a	user-authentication configurations of VISHNU	NO
			is an admin option for listing all local	
userId	string	u	user-authentication configurations of a specific	NO
			user identified by his/her userId	
outh Cyctom Id	atrina	;	is an option for listing local user-configuration of	NO
authSystemId	string	1	a specific user-authentication system	INO

#### **Environment variables**

This command defines no environment variables.

## 2.1.36 vishnu\_set\_ssh\_key

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_set\_ssh\_key command allows to add or remove a given key to/from the authorized keys of a user's remote account.

## Example of use

vishnu\_set\_ssh\_key[-h][-a][-r] rlogin sshPubKey

Parameter	Type	Option	Description	Required
rlogin	string		A ssh-compliant form of login information in the remote account (e.g. user@machine)	YES
sshPubKey	string		The key add to the remote account	YES
addOption	boolean	a	option for adding a key	NO
removeOption	boolean	r	option for removing a key	NO

This command defines no environment variables.

## 2.2 Parameters definitions

**Enumeration UMS::AuthType Type** 

Name	Value
UNDEFINED	-1
LDAP	0

**Enumeration UMS::CommandStatusType Type** 

Name	Value
FAILURE	0
SUCCESS	1

**Enumeration UMS::EncryptionMethod Type** 

Name		Value
UNDEFIN	ED	-1
SSHA		 0

**Enumeration UMS::PrivilegeType Type** 

Name	Value	
USER	0	
ADMIN	1	

**Enumeration UMS::SessionCloseType Type** 

Name	V <mark>alue</mark>
DEFAULT	0
CLOSE_ON_TIMEOUT	1
CLOSE_ON_DISCONNECT	2

**Enumeration UMS::StatusType Type** 

Name	Value
UNDEFINED	-1
INACTIVE	0
ACTIVE	1

## **Chapter 3**

# Commands specification for Tasks Management Service (TMS)

## 3.1 Command definitions

## 3.1.1 vishnu submit job

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_submit\_job command submits a job on a machine through the use of a script (scriptFilePath). If the machine identifier is equal to autom, the job will be automatically submitted on a best machine (for now three criterions are used: minimum number of waiting jobs, minimum number of running jobs and the total number of jobs) through the use of a script (scriptFilePath) which must be generic script using VISHNU's generic directives for all batch schedulers

## Example of use

vishnu\_submit\_job[-h][-n name][-q queue][-t wallTime][-m memory][-P nbCpu][-N nbNodesAndCpu-PerNode][-o outputPath][-e errorPath][-M mailNotification][-u mailNotifyUser][-g group][-D workingDir][-T cpuTime][-Q][-L loadType]machineId scriptFilePath

Parameter	Type	Option	Description	Required
machineId	atnina		Is the id of the machine on which the job must be	YES
macimierd	string	1	submitted	
			The path to the file containing the characteristics	
scriptFilePath	string		(job command, and batch scheduler directive	YES
			required or optional) of the job to submit.	
name	string	n	Assigns a job name. The default is the path of job	NO
queue	string	q	Assigns the queue or class of the job	NO
wallTime	int	t	The maximum wall-clock time during which the	NO
wanTime		1	job can run (in seconds)	
mamory	int	m	Is the memory size that the job requires (in	NO
memory		m	MegaBytes)	NO
nbCpu	int	P	The number of cpu per node that the job requires	NO
	string N		The number of nodes and processors per node (in	
nbNodesAndCpuPerNode			the format nbNodes:nbCpuPerNode). For	
		N	example if you want to use 4 nodes with 3 cpus	NO
			for each node, you must specify these numbers	
		by "4:3"		

Parameter	Type	Option	Description	Required
outputPath	string	0	Assigns the path and file for job output	NO
errorPath	string	e	Assigns the path and file for job error	NO
mailNotification	string	М	Assigns the notification type of the job. Valid type values are BEGIN, END, ERROR, and ALL (any state change)	NO
mailNotifyUser	string	u	The name of user to receive email notification of state changes as defined by the option mailNotification. The default value is the submitting user	NO
group	string	g	Assigns a job group name.	NO
workingDir	string	D	Assigns a job remote working dir	NO
cpuTime	string	Т	Assigns a job cpu limit time (in seconds or in the format [[HH:]MM:]SS)	NO
selectQueueAutom	boolean	Q	allows to select automatically a queue which has the number of nodes requested by the user	NO
loadType	LoadType	L	The criterion to automatically submit a job (for now three criterions are used: minimum number of waiting jobs, minimum number of running jobs and the total number of jobs). This option is used only if the machine identifier is equal to autom (this keyword is used to submit automatically a job)	NO

This command defines no environment variables.

## 3.1.2 vishnu\_get\_job\_info

## Access

This command line can be used by any VISHNU user

## Description

The vishnu\_get\_job\_info command gets information on a job from its id

## Example of use

vishnu\_get\_job\_info[-h] machineId jobId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine on which the job is running	YES
jobId	string		The id of the job	YES

## **Environment variables**

This command defines no environment variables.

## 3.1.3 vishnu\_get\_job\_progress

#### Access

This command line can be used by any VISHNU user

## **Description**

The vishnu\_get\_job\_progress command gets the progression status of jobs

#### Example of use

vishnu\_get\_job\_progress[-h][-i jobId][-u jobOwner] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine to get the jobs progression	YES
jobId	string	i	Specifies the id of the job whose progression the user wants to see.	NO
jobOwner	string	u	Specifies the owner of the job.	NO

#### **Environment variables**

This command defines no environment variables.

## 3.1.4 vishnu\_list\_queues

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_list\_queues command gets queues information

#### Example of use

vishnu\_list\_queues[-h][-q queueName] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine that the user wants to list queues	YES
queueName	string	q	if it is given, listQueues gives information only of this queue	NO

## **Environment variables**

This command defines no environment variables.

#### 3.1.5 vishnu\_list\_jobs

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_list\_jobs command gets a list of all submitted jobs on a machine. If machine identifier is equal to all, submitted jobs on all machines are listed

#### Example of use

vishnu\_list\_jobs[-h][-i jobId][-P nbCpu][-d fromSubmitDate][-D toSubmitDate][-u owner][-s status][-p priority][-q queue][-S multipleStatus][-b] machineId

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine on which the jobs are running	YES
jobId	string	i	lists the job with the specified id	NO
nbCpu	int	P	lists the jobs with the specified number of CPUs per node	NO
fromSubmitDate	long	d	lists the jobs submitted after the specified date (UNIX timestamp)	NO
toSubmitDate	long	D	lists jobs submitted before the specified date (UNIX timestamp)	NO
owner	string	u	lists the jobs submitted by the specified owner	NO
status	JobStatus	S	lists the jobs with the specified status	NO
priority	JobPriority	p	lists the jobs with the specified priority	NO
queue	string	q	the jobs with the specified queue name	NO
multipleStatus	string	S	lists the jobs with the specified status (combination of multiple status). Its format contains the first letter or the value (interger) of each chosen status. For exemple to list the cancelled and terminated jobs, you use the format CT or 65	NO
batchJob	boolean	b	allows to select all jobs submitted through the underlying batch scheduler (jobs submitted through vishnu and out of vishnu)	NO

This command defines no environment variables.

## 3.1.6 vishnu\_get\_job\_output

## Access

This command line can be used by any VISHNU user

## Description

The vishnu\_get\_job\_output command gets standard output and error output files of a job given its id

## Example of use

vishnu\_get\_job\_output[-h][-o outDir] machineId jobId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		gets outputPath and errorPath of a job from its id	YES
jobId	string		The Id of the job	YES
outDir	string	О	The output directory where the files will be stored (default is current directory)	NO

## **Environment variables**

This command defines no environment variables.

## 3.1.7 vishnu\_get\_completed\_jobs\_output

## Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_get\_completed\_jobs\_output command gets standard output and error output files of completed jobs (applies only once for each job)

#### Example of use

vishnu\_get\_completed\_jobs\_output[-h][-o outDir] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine on which the jobs are been submitted	YES
outDir	string	o	Specifies the output directory where the files will be stored (by default, the current directory).	NO

#### **Environment variables**

This command defines no environment variables.

## 3.1.8 vishnu\_cancel\_job

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_cancel\_job command cancels a job from its id. If job id is equal to all, all submitted jobs by all users will be cancelled if the user is an administrator, and only jobs submitted by the user will be cancelled if the user is not an administrator.

#### Example of use

vishnu\_cancel\_job[-h] machineId jobId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine on which the job is running	YES
jobId	string		The Id of the job	YES

#### **Environment variables**

This command defines no environment variables.

## 3.2 Parameters definitions

#### **Enumeration TMS::JobPriority Type**

Name	Value
UNDEFINED	-1
VERY_LOW	1
LOW	2
NORMAL	3
HIGH	4
VERY_HIGH	5

## **Enumeration TMS::JobStatus Type**

Name	Value
UNDEFINED	-1
SUBMITTED	1
QUEUED	2
WAITING	3
RUNNING	4
TERMINATED	5
CANCELLED	6
ALREADY_DOWNLOADE	7

## **Enumeration TMS::LoadType Type**

Name	Value
USE_NB_WAITING_JOBS	0
USE_NB_JOBS	1
USE_NB_RUNNING_JOBS	2

## **Enumeration TMS::QueuePriority Type**

Name		Value
UNDEFINE	D	-1
VERY_LOW	V	1
LOW	7	2
NORMAL		3
HIGH		4
VERY_HIG	H	5

## **Enumeration TMS::QueueStatus Type**

Name	<b>Val</b> ue
NOT_STARTED	0
STARTED	1
RUNNING	2

## **Chapter 4**

# Commands specification for Information Management Service (IMS)

## 4.1 Command definitions

#### 4.1.1 vishnu export commands

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_export\_commands command exports all the commands made by a user during a session

#### Example of use

vishnu\_export\_commands[-h][-t exportType] oldSessionId

#### **Parameters**

Parameter	Type	Option	Description	Required
oldSessionId	string		The id of the session to export (session has ended)	YES
exportType	ExportType	t	The type to export	NO

#### **Environment variables**

This command defines no environment variables.

#### 4.1.2 vishnu\_get\_metric\_current\_value

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_get\_metric\_current\_value command displays the current values of system metrics

#### Example of use

vishnu\_get\_metric\_current\_value[-h][-t metricType] machineId

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
metricType	MetricType	t	The type of the metric	NO

This command defines no environment variables.

## 4.1.3 vishnu\_get\_metric\_history

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_get\_metric\_history command displays the history of values of a system metric

#### Example of use

vishnu\_get\_metric\_history[-h][-s startTime][-e endTime][-t type] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
startTime	long	S	The start time to get the history	NO
endTime	long	e	The end time to get the history	NO
type	MetricType	t	The type of metric searched	NO

## **Environment variables**

This command defines no environment variables.

## 4.1.4 vishnu\_get\_processes

## Access

This command line can be used by ADMIN users only

## Description

The vishnu\_get\_processes command displays the list of the VISHNU processes running on machines

## Example of use

vishnu\_get\_processes[-h][-p machineId]

## **Parameters**

Parameter	Type	Option	Description	Required
machineId	string	p	The id of the machine	NO

## **Environment variables**

This command defines no environment variables.

## 4.1.5 vishnu\_set\_system\_info

#### Access

This command line can be used by ADMIN users only

# **Description**

The vishnu\_set\_system\_info command updates the system information of a machine

### Example of use

vishnu\_set\_system\_info[-h][-m memory][-d diskSpace] machineId

### **Parameters**

Parameter	Type	Option	Description	Required
memory	long	m	Amount of RAM memory available on the machine (in Bytes)	NO
diskSpace	long	d	Amount of disk space available on the machine (in Bytes)	NO
machineId	string		The id of the machine	YES

### **Environment variables**

This command defines no environment variables.

# 4.1.6 vishnu\_set\_system\_threshold

### Access

This command line can be used by ADMIN users only

# Description

The vishnu\_set\_system\_threshold command sets a threshold on a machine of a system

# Example of use

vishnu\_set\_system\_threshold[-h] value machineId type handler

### **Parameters**

Type	Option	<b>Description</b>	Required
long		The value of the threshold	YES
string		The machine ID the threshold is available	YES
MetricType		The type of the threshold	YES
string		The userId of the admin responsible for handling the threshold problems	YES
	long string MetricType	long string MetricType	long String The value of the threshold String The machine ID the threshold is available MetricType The type of the threshold The userId of the admin responsible for handling

### **Environment variables**

This command defines no environment variables.

# 4.1.7 vishnu\_get\_system\_threshold

# Access

This command line can be used by ADMIN users only

# **Description**

The vishnu\_get\_system\_threshold command gets a system threshold on a machine

# Example of use

vishnu\_get\_system\_threshold[-h][-m machineId][-t metricType]

Parameter	Type	Option	Description	Required
machineId	string	m	The id of the machine where the metric is defined	NO
metricType	MetricType	t	The type of the metric	NO

### **Environment variables**

This command defines no environment variables.

# 4.1.8 vishnu\_define\_user\_identifier

### Access

This command line can be used by ADMIN users only

### **Description**

The vishnu\_define\_user\_identifier command defines the shape of the identifiers automatically generated for the users

### Example of use

vishnu\_define\_user\_identifier[-h] format

### **Parameters**

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

### **Environment variables**

This command defines no environment variables.

# 4.1.9 vishnu\_define\_machine\_identifier

# Access

This command line can be used by ADMIN users only

# **Description**

The vishnu\_define\_machine\_identifier command defines the shape of the identifiers automatically generated for the machines

# Example of use

vishnu\_define\_machine\_identifier[-h] format

# **Parameters**

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

### **Environment variables**

This command defines no environment variables.

# 4.1.10 vishnu\_define\_job\_identifier

### Access

This command line can be used by ADMIN users only

# Description

The vishnu\_define\_job\_identifier command defines the shape of the identifiers automatically generated for the jobs

# Example of use

vishnu\_define\_job\_identifier[-h] format

### **Parameters**

Parameter	Type	Option	Description	Required
format	string	/	The new format to use	YES

### **Environment variables**

This command defines no environment variables.

# 4.1.11 vishnu\_define\_transfer\_identifier

# Access

This command line can be used by ADMIN users only

# Description

The vishnu\_define\_transfer\_identifier command defines the shape of the identifiers automatically generated for the file transfers

### Example of use

vishnu\_define\_transfer\_identifier[-h] format

### **Parameters**

Parameter	Туре	Option	Description	Required
format	string		The new format to use	YES

### **Environment variables**

This command defines no environment variables.

# 4.1.12 vishnu\_define\_auth\_identifier

### Access

This command line can be used by ADMIN users only

### **Description**

The vishnu\_define\_auth\_identifier command defines the shape of the identifiers automatically generated for the authentication system

# Example of use

vishnu\_define\_auth\_identifier[-h] format

# **Parameters**

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

### **Environment variables**

This command defines no environment variables.

# 4.1.13 vishnu\_load\_shed

### Access

This command line can be used by ADMIN users only

# Description

The vishnu\_load\_shed command sheds load on a machine

# Example of use

vishnu\_load\_shed[-h] machineId loadShedType

### **Parameters**

Parameter	Type	Option	<b>Descri</b> ption	Req <mark>uired</mark>
machineId	string		The id of the machine to stop	YES
			Selects a load shedding mode (SOFT: stops all	
loadShedType	LoadShedType		services and they can be restarted, HARD: stops	YES
			all services, they cannot be restarted)	

### **Environment variables**

This command defines no environment variables.

# 4.1.14 vishnu\_set\_update\_frequency

### Access

This command line can be used by ADMIN users only

# Description

The vishnu\_set\_update\_frequency command sets the update frequency of the IMS tables

# Example of use

vishnu\_set\_update\_frequency[-h] freq

# **Parameters**

Parameter	Type	Option	Description	Required
freq	int		Frequency the data are updated, in second	YES

# **Environment variables**

This command defines no environment variables.

# 4.1.15 vishnu\_get\_update\_frequency

# Access

This command line can be used by any VISHNU user

# **Description**

The vishnu\_get\_update\_frequency command gets the update frequency of the IMS database

# Example of use

vishnu\_get\_update\_frequency[-h]

This command defines no arguments.

### **Environment variables**

This command defines no environment variables.

# 4.1.16 vishnu\_stop

### Access

This command line can be used by ADMIN users only

# **Description**

The vishnu\_stop command to stop (and do not try to relaunch) a SeD

# Example of use

vishnu\_stop[-h] processName machineId

### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
processName	string		The name of the process (the name of the executable)	YES
machineId	string	7	The id of the machine	YES

### **Environment variables**

This command defines no environment variables.

# 4.1.17 vishnu\_get\_system\_info

### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_get\_system\_info command to get the system info on a machine

### Example of use

vishnu\_get\_system\_info[-h][-m machineId]

# **Parameters**

Parameter	Type	Option	Description	Required
machineId	string	m	The machine id	NO

### **Environment variables**

This command defines no environment variables.

# 4.1.18 vishnu\_restart

### Access

This command line can be used by ADMIN users only

# Description

The vishnu\_restart command to restart a SeD or a MA

# Example of use

vishnu\_restart[-h][-v vishnuConf][-t sedType] machineId

# **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine where to restart	YES
vishnuConf	string	v	The path to the vishnu configuration file	NO
sedType	SeDType	t	The type of the vishnu sed	NO

# **Environment variables**

This command defines no environment variables.

# 4.2 Parameters definitions

**Enumeration IMS::ExportType Type** 

Name	Value
UNDEFINED	0
SHELL	1

**Enumeration IMS::LoadShedType Type** 

Name	Value
UNDEFINED	0
HARD	1
SOFT	2

**Enumeration IMS::MetricType Type** 

Name	Value
UNDEFINED	0
CPUUSE	1
FREEDISKSPACE	2
FREEMEMORY	3

**Enumeration IMS::ProcessState Type** 

Name	Value
UNDEFINED	0
RUNNING	1
DOWN	2
DELETED	3

**Enumeration IMS::SeDType Type** 

Name	Value
UNDEFINED	0
UMS	1
TMS	2
FMS	3

Name	Value
IMS	4

# **Chapter 5**

# Commands specification for File Management Service (FMS)

# 5.1 Command definitions

# 5.1.1 vishnu create file

### Access

This command line can be used by any VISHNU user

### **Description**

The vishnu\_create\_file command creates files on remote machines.

# Example of use

vishnu\_create\_file[-h] path

### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
path	string		The file to create following the pattern [host:]file	YES
patii	string		path.	1123

### **Environment variables**

This command defines no environment variables.

# 5.1.2 vishnu\_create\_dir

### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_create\_dir command creates directories on remote machines.

# Example of use

vishnu\_create\_dir[-h][-p] path

Parameter	Type	Option	Description	Required
path	string		The directory to create following the pattern [host:]directory path.	YES
isRecursive	boolean	p	It specifies when the create command is recursive (create parent directory also) or not	NO

# **Environment variables**

This command defines no environment variables.

# 5.1.3 vishnu\_remove\_file

# Access

This command line can be used by any VISHNU user

# Description

The vishnu\_remove\_file command removes files from remote hosts.

# Example of use

vishnu\_remove\_file [-h] [-r] path

# **Parameters**

Parameter	Type	Option	Description	Required
path	string		The file to remove following the pattern [host:]file path	YES
isRecursive	boolean	r	It specifies when the remove command is recursive (case of directory) or not	NO

# **Environment variables**

This command defines no environment variables.

# 5.1.4 vishnu\_remove\_dir

### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_remove\_dir command removes directories (and subdirectories) from remote machines.

# Example of use

vishnu\_remove\_dir[-h] path

# **Parameters**

Parameter	Type	Option	Description	Required
path	string		The directory to remove following the pattern [host:]directory path	YES

# **Environment variables**

This command defines no environment variables.

# 5.1.5 vishnu\_ch\_grp

### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_ch\_grp command changes group owner of remote files/directories.

# Example of use

vishnu\_ch\_grp [-h] group path

### **Parameters**

Parameter	Type	Option	Description	Req <mark>uired</mark>
group	string		the new group owner of file/directory	YES
path	string		The file/directory following the pattern [host:]file path	YES

### **Environment variables**

This command defines no environment variables.

# 5.1.6 vishnu\_ch\_mod

# Access

This command line can be used by any VISHNU user

### **Description**

The vishnu\_ch\_mod command changes access rights of remote files/directories.

### Example of use

vishnu\_ch\_mod[-h] mode path

# **Parameters**

Parameter	Type	Option	Description	Required
mode	mode_t		the access rigths of file/directory in octal system.	YES
path	string		The file/directory following the pattern [host:]file path	YES

# **Environment variables**

This command defines no environment variables.

# 5.1.7 vishnu\_head\_of\_file

### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_head\_of\_file command displays a few first lines of files located on remote machines.

# Example of use

 $\label{lem:vishnu_head_of_file[-h][-n nline]} path$ 

Parameter	Type	Option	Description	Required
path	string		The file following the pattern [host:]file path	YES
nline	int	n	the number of line to get	NO

### **Environment variables**

This command defines no environment variables.

# 5.1.8 vishnu\_tail\_of\_file

### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_tail\_of\_file command displays a few last lines of files located on remote machines

### Example of use

vishnu\_tail\_of\_file[-h][-n nline] path

### **Parameters**

Parameter	Type	Option	Description	Required
path	string		The file following the pattern [host:]file path	YES
nline	int	n	the number of line to get	NO

# **Environment variables**

This command defines no environment variables.

# 5.1.9 vishnu\_content\_of\_file

# Access

This command line can be used by any VISHNU user

# **Description**

The vishnu\_content\_of\_file command displays content of files located on remote machines

# Example of use

vishnu\_content\_of\_file[-h] path

### **Parameters**

Parameter	Type	Option	Description	Required
path	string		The file to display following the pattern [host:]file path	YES

# **Environment variables**

This command defines no environment variables.

# 5.1.10 vishnu\_list\_dir

# Access

This command line can be used by any VISHNU user

# Description

The vishnu\_list\_dir command displays the content of a remote directory.

# Example of use

 $vishnu_list_dir[-h][-l][-a]$  path

### **Parameters**

Parameter	Type	Option	Description	Required
path	string		The directory to list following the pattern [host:]directory path	YES
longFormat	boolean	1	It specifies the long display format (all available file informations)	NO
allFiles	boolean	a	Allows to display all files including hidden files	NO

# **Environment variables**

This command defines no environment variables.

# 5.1.11 vishnu\_copy\_file

# Access

This command line can be used by any VISHNU user

# Description

The vishnu\_copy\_file command executes a synchronous copy of file.

# Example of use

vishnu\_copy\_file[-h][-r][-t trCommand] src dest

# **Parameters**

Parameter	Туре	Option	<b>Description</b>	Required
src strin	string		The source file to copy following the pattern	YES
	Sumg		[host:]file path	1 ES
dest	string		The path of the destination file	YES
isRecursive	boolean	r	It specifies when the copy is recursive (case of	NO
	boolean		directory) or not.	NO
trCommand	TransferCommand	t	the command to use to perform file transfer.	NO

### **Environment variables**

Name	Parameter	Туре	Description	Required	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

# 5.1.12 vishnu\_copy\_async\_file

# Access

This command line can be used by any VISHNU user

# Description

The vishnu\_copy\_async\_file command executes an asynchronous copy of file.

# Example of use

vishnu\_copy\_async\_file[-h][-r][-t trCommand] src dest

# **Parameters**

Parameter	Type	Option	Description	Required
src	string		The source file to copy following the pattern [host:]file path	YES
dest	string		The path of the destination file	YES
isRecursive	boolean	r	It specifies when the copy is recursive (case of directory) or not.	NO
trCommand	TransferCommand	t	the command to use to perform file transfer.	NO

### **Environment variables**

Name	Parameter	Туре	Description	Required	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

# 5.1.13 vishnu\_move\_file

# Access

This command line can be used by any VISHNU user

# **Description**

The vishnu\_move\_file command executes a synchronous move of file.

### Example of use

vishnu\_move\_file[-h][-r][-t trCommand] src dest

# **Parameters**

Parameter	Туре	Option	Description	Required	
src string	etring		The source file to move following the pattern	YES	
	Sumg	sung	[host:]file path	ILO	
dest	string		The path of the destination file	YES	
isRecursive	boolean	r	It specifies when the copy is recursive (case of	NO	
			directory) or not.	110	
trCommand	TransferCommand	t	the command to use to perform file transfer.	NO	

### **Environment variables**

Name	Parameter	Туре	Description	Required	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

# 5.1.14 vishnu\_move\_async\_file

### Access

This command line can be used by any VISHNU user

# **Description**

The vishnu\_move\_async\_file command executes an asynchronous move of file.

# Example of use

### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
src	string		The source file to move following the pattern [host:]file path	YES
dest	string	/	The path of the destination file	YES
isRecursive	boolean	r	It specifies when the copy is recursive (case of directory) or not.	NO
trCommand	TransferCommand	t	the command to use to perform file transfer.	NO

### **Environment variables**

Name	Parameter	Туре	<b>Description</b>	Required	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

# 5.1.15 vishnu\_stop\_file\_transfer

# Access

This command line can be used by any VISHNU user

# **Description**

The vishnu\_stop\_file\_transfer command stops an execution of a set of file transfers.

# Example of use

vishnu\_stop\_file\_transfer[-h][-i transferId][-m fromMachineId][-u userId]

# **Parameters**

Parameter	Type	Option	Description	Required
transferId	string	i	a given transfer id	NO
fromMachineId	string	m	the machine that is the source or destination of the file transfer	NO
userId	string	u	allows an admin to stop file transfers of a specific user	NO

# **Environment variables**

This command defines no environment variables.

# 5.1.16 vishnu\_list\_file\_transfers

### Access

This command line can be used by any VISHNU user

# Description

The vishnu\_list\_file\_transfers command displays the history of all file transfers submitted by User.

# Example of use

vishnu\_list\_file\_transfers[-h][-t transferId][-m fromMachineId][-u userId][-s status]

# **Parameters**

Parameter	Type	Option	Description	Required
transferId	string	t	a given transfer id	NO
fromMachineId	string	m	the machine that is the source of the file transfer	NO
userId	string	u	allows the admin to list file transfers initiated by a specific user	NO
status	Status	S	the file transfer status	NO

### **Environment variables**

This command defines no environment variables.

# 5.1.17 vishnu\_get\_file\_info

# Access

This command line can be used by any VISHNU user

# **Description**

The vishnu\_get\_file\_info command displays the information of files.

# Example of use

vishnu\_get\_file\_info[-h] path

# **Parameters**

Parameter	Type	Option	Description	Required
path	atrina		The file whose inode information will be	YES
paui	string		displayed	1 ES

# **Environment variables**

This command defines no environment variables.

# 5.2 Parameters definitions

**Enumeration FMS::FileType Type** 

Name	Value
BLOCK	0
CHARACTER	1
DIRECTORY	2
SYMBOLICLINK	3
SCKT	4
FIFO	5
REGULAR	6

# **Enumeration FMS::Status Type**

Name	Value
INPROGRESS	0
COMPLETED	1

Name	Value
CANCELLED	2
FAILED	3
UNDEFINED	4

# **Enumeration FMS::TransferCommand Type**

Name	Value
SCP	0
RSYNC	1
UNDEFINED	2