Package 'bsvars'

December 11, 2023

Type Package

```
Title Bayesian Estimation of Structural Vector Autoregressive Models
Version 2.1.0
Date 2023-12-11
Description Efficient algorithms for Bayesian estimation of Structural Vector Autoregres-
      sive (SVAR) models via Markov chain Monte Carlo methods. A wide range of SVAR mod-
      els is considered, including homo- and heteroskedastic specifications and those with non-
      normal structural shocks. The heteroskedastic SVAR model setup is similar as in Woź-
      niak & Droumaguet (2015) <doi:10.13140/RG.2.2.19492.55687> and Lütkepohl & Woź-
      niak (2020) <doi:10.1016/j.jedc.2020.103862>. The sampler of the structural matrix fol-
      lows Waggoner & Zha (2003) <doi:10.1016/S0165-1889(02)00168-9>, whereas that for autore-
      gressive parameters fol-
      lows Chan, Koop, Yu (2022) <a href="https://www.joshuachan.org/papers/0ISV.pdf">https://www.joshuachan.org/papers/0ISV.pdf</a>. The speci-
      fication of Markov switching heteroskedasticity is inspired by Song & Woź-
      niak (2021) <doi:10.1093/acrefore/9780190625979.013.174>, and that of Stochastic Volatil-
      ity model by Kastner & Frühwirth-Schnatter (2014) <doi:10.1016/j.csda.2013.01.002>.
License GPL (>= 3)
Maintainer Tomasz Woźniak <wozniak.tom@pm.me>
Encoding UTF-8
Imports Rcpp (>= 1.0.7), RcppProgress (>= 0.1), RcppTN, GIGrvg, R6,
      stochvol
Suggests tinytest
LinkingTo Rcpp, RcppProgress, RcppArmadillo, RcppTN
BugReports https://github.com/bsvars/bsvars/issues
RoxygenNote 7.2.3
URL https://bsvars.github.io/bsvars/
NeedsCompilation yes
Author Tomasz Woźniak [aut, cre] (<a href="https://orcid.org/0000-0003-2212-2378">https://orcid.org/0000-0003-2212-2378</a>)
Depends R (>= 3.5.0)
Repository CRAN
Date/Publication 2023-12-11 21:50:02 UTC
```

${\sf R}$ topics documented:

osvars-package	
compute_conditional_sd	. 5
compute_fitted_values	
compute_historical_decompositions	
compute_impulse_responses	
compute_regime_probabilities	. 10
compute_structural_shocks	
compute_variance_decompositions	. 13
estimate	. 14
estimate.BSVAR	. 17
estimate.BSVARMIX	. 19
estimate.BSVARMSH	. 22
estimate.BSVARSV	. 25
estimate.PosteriorBSVAR	. 28
estimate.PosteriorBSVARMIX	30
estimate.PosteriorBSVARMSH	. 33
estimate.PosteriorBSVARSV	37
orecast	
Forecast.PosteriorBSVAR	41
Sorecast.PosteriorBSVARMIX	
Sorecast.PosteriorBSVARMSH	
Sorecast.PosteriorBSVARSV	
normalise_posterior	
specify_bsvar	
specify_bsvar_mix	51
specify_bsvar_msh	
specify_bsvar_sv	
specify_data_matrices	
specify_identification_bsvars	
specify_posterior_bsvar	
specify_posterior_bsvar_mix	
specify_posterior_bsvar_msh	
specify_posterior_bsvar_sv	
specify_prior_bsvar	
specify_prior_bsvar_mix	
specify_prior_bsvar_msh	
specify_prior_bsvar_sv	
specify_starting_values_bsvar	
specify_starting_values_bsvar_mix	
specify_starting_values_bsvar_msh	
specify_starting_values_bsvar_sv	
is_fiscal_ex	
ıs_fiscal_lsuw	
verify_autoregression	
verify autoregression.PosteriorBSVAR	
verify autoregression PosteriorBSVARMIX	104

bsvars-package 3

	verify autoregress	sion.PosteriorBSVA	RMSH															. 10
	verify_autoregress	sion.PosteriorBSVA	RSV .															. 10
	verify_volatility .																	. 11
	verify_volatility.P	osteriorBSVAR .																. 11
	verify_volatility.P	osteriorBSVARMIX																. 11
	verify_volatility.P	osteriorBSVARMSI	Η															. 11
	verify_volatility.P	osteriorBSVARSV																. 11
Index																		11
bsvai	rs-package	Bayesian Estima	tion of	Stri	ıctu	ıral	Veci	tor .	Aut	ore	egre	ess	ive	M	loa	lel	5	

Description

Efficient and fast algorithms for Bayesian estimation of Structural Vector Autoregressive (SVAR) models via Markov chain Monte Carlo methods. A wide range of SVAR models is considered, including homo- and heteroskedastic specifications and those with non-normal structural shocks. The heteroskedastic SVAR model setup is similar as in Woźniak & Droumaguet (2015) <doi:10.13140/RG.2.2.19492.55687> and Lütkepohl & Woźniak (2020) <doi:10.1016/j.jedc.2020.103862>. The sampler of the structural matrix follows Waggoner & Zha (2003) ,doi:10.1016/S0165-1889(02)00168-9>, whereas that for autoregressive parameters follows Chan, Koop, Yu (2022) https://www.joshuachan.org/papers/OISV.pdf>. The specification of Markov switching heteroskedasticity is inspired by Song & Woźniak (2021) <doi:10.1093/acrefore/9780190625979.013.174>, and that of Stochastic Volatility model by Kastner & Frühwirth-Schnatter (2014) <doi:10.1016/j.csda.2013.01.002>.

Details

All the SVAR models in this package are specified by two equations, including the reduced form equation:

$$Y = AX + E$$

where Y is an NxT matrix of dependent variables, X is a KxT matrix of explanatory variables, E is an NxT matrix of reduced form error terms, and A is an NxK matrix of autoregressive slope coefficients and parameters on deterministic terms in X.

The structural equation is given by:

$$BE = U$$

where U is an NxT matrix of structural form error terms, and B is an NxN matrix of contemporaneous relationships.

Finally, all of the models share the following assumptions regarding the structural shocks U, namely, joint conditional normality given the past observations collected in matrix X, and temporal and contemporaneous independence. The latter implies zero correlations and autocorrelations.

The various SVAR models estimated differ by the specification of structural shocks variances. The different models include:

- · homoskedastic model with unit variances
- · heteroskedastic model with stationary Markov switching in the variances

4 bsvars-package

- · heteroskedastic model with non-centred Stochastic Volatility process for variances
- · heteroskedastic model with centred Stochastic Volatility process for variances
- non-normal model with a finite mixture of normal components and component-specific variances
- heteroskedastic model with sparse Markov switching in the variances where the number of heteroskedastic components is estimated
- non-normal model with a sparse mixture of normal components and component-specific variances where the number of heteroskedastic components is estimated

Note

This package is currently in active development. Your comments, suggestions and requests are warmly welcome!

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Woźniak, T., and Droumaguet, M., (2022) Bayesian Assessment of Identifying Restrictions for Heteroskedastic Structural VARs.

```
# upload data
data(us_fiscal_lsuw) # upload dependent variables
data(us_fiscal_ex)
                   # upload exogenous variables
# specify the model and set seed
specification = specify_bsvar_sv$new(us_fiscal_lsuw, p = 4, exogenous = us_fiscal_ex)
set.seed(123)
# run the burn-in
burn_in = estimate(specification, 10)
# estimate the model
posterior = estimate(burn_in, 10, thin = 2)
# compute impulse responses 2 years ahead
            = compute_impulse_responses(posterior, horizon = 8)
# compute forecast error variance decomposition 2 years ahead
fevd
             = compute_variance_decompositions(posterior, horizon = 8)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_sv$new(p = 4, exogenous = us_fiscal_ex) |>
```

```
estimate(S = 10) |>
estimate(S = 20) |>
compute_variance_decompositions(horizon = 8) -> fevds
```

```
compute_conditional_sd
```

Computes posterior draws of structural shock conditional standard deviations

Description

Each of the draws from the posterior estimation of a model is transformed into a draw from the posterior distribution of the structural shock conditional standard deviations.

Usage

```
compute_conditional_sd(posterior)
```

Arguments

posterior

posterior estimation outcome - an object of either of the classes: PosteriorB-SVAR, PosteriorBSVARMSH, PosteriorBSVARMIX, or PosteriorBSVARSV obtained by running the estimate function. The interpretation depends on the normalisation of the shocks using function normalise_posterior(). Verify if the default settings are appropriate.

Value

An object of class PosteriorSigma, that is, an NxTxS array with attribute PosteriorSigma containing S draws of the structural shock conditional standard deviations.

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

See Also

```
estimate, normalise_posterior
```

```
# upload data
data(us_fiscal_lsuw)

# specify the model and set seed
set.seed(123)
specification = specify_bsvar$new(us_fiscal_lsuw, p = 1)
```

```
# run the burn-in
             = estimate(specification, 10)
burn_in
# estimate the model
             = estimate(burn_in$get_last_draw(), 50)
posterior
# compute structural shocks' conditional standard deviations
             = compute_conditional_sd(posterior)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvarsnew(p = 1) \mid >
 estimate(S = 50) \mid >
 estimate(S = 100) \mid >
 compute_conditional_sd() -> csd
```

compute_fitted_values Computes posterior draws of dependent variables' fitted values

Description

Each of the draws from the posterior estimation of a model is transformed into a draw from the posterior distribution of the fitted values.

Usage

```
compute_fitted_values(posterior)
```

Arguments

posterior

posterior estimation outcome - an object of either of the classes: PosteriorB-SVAR, PosteriorBSVARMSH, PosteriorBSVARMIX, or PosteriorBSVARSV obtained by running the estimate function.

Value

An object of class PosteriorFitted, that is, an NxTxS array with attribute PosteriorFitted containing S draws of the fitted values.

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

See Also

estimate

Examples

```
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
set.seed(123)
specification = specify_bsvar$new(us_fiscal_lsuw, p = 1)
# run the burn-in
             = estimate(specification, 10)
burn in
# estimate the model
             = estimate(burn_in, 50)
posterior
# compute dependent variables' fitted values
fitted
             = compute_fitted_values(posterior)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar$new(p = 1) |>
 estimate(S = 50) \mid >
 estimate(S = 100) \mid >
 compute_fitted_values() -> fitted
```

compute_historical_decompositions

Computes posterior draws of historical decompositions

Description

Each of the draws from the posterior estimation of a model is transformed into a draw from the posterior distribution of the historical decompositions.

Usage

```
compute_historical_decompositions(posterior)
```

Arguments

posterior

posterior estimation outcome - an object of either of the classes: PosteriorB-SVAR, PosteriorBSVARMSH, PosteriorBSVARMIX, or PosteriorBSVARSV obtained by running the estimate function. The interpretation depends on the normalisation of the shocks using function normalise_posterior(). Verify if the default settings are appropriate.

Value

An object of class PosteriorHD, that is, an NxNxTxS array with attribute PosteriorHD containing S draws of the historical decompositions.

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Kilian, L., & Lütkepohl, H. (2017). Structural VAR Tools, Chapter 4, In: Structural vector autoregressive analysis. Cambridge University Press.

See Also

```
estimate, normalise_posterior
```

```
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
set.seed(123)
specification = specify_bsvar$new(us_fiscal_lsuw, p = 1)
# run the burn-in
        = estimate(specification, 10)
burn_in
# estimate the model
posterior
            = estimate(burn_in, 50)
# compute historical decompositions
            = compute_historical_decompositions(posterior)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvarsnew(p = 1) \mid >
 estimate(S = 50) \mid >
 estimate(S = 100) \mid >
 compute_historical_decompositions() -> hd
```

compute_impulse_responses

Computes posterior draws of impulse responses

Description

Each of the draws from the posterior estimation of a model is transformed into a draw from the posterior distribution of the impulse responses.

Usage

compute_impulse_responses(posterior, horizon, standardise = FALSE)

Arguments

posterior posterior estimation outcome - an object of either of the classes: PosteriorB-

SVAR, PosteriorBSVARMSH, PosteriorBSVARMIX, or PosteriorBSVARSV obtained by running the estimate function. The interpretation depends on the normalisation of the shocks using function normalise_posterior(). Verify if

the default settings are appropriate.

horizon a positive integer number denoting the forecast horizon for the impulse re-

sponses computations.

standardise a logical value. If TRUE, the impulse responses are standardised so that the vari-

ables' own shocks at horizon 0 are equal to 1. Otherwise, the parameter esti-

mates determine this magnitude.

Value

An object of class PosteriorIR, that is, an NxNx(horizon+1)xS array with attribute PosteriorIR containing S draws of the impulse responses.

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Kilian, L., & Lütkepohl, H. (2017). Structural VAR Tools, Chapter 4, In: Structural vector autoregressive analysis. Cambridge University Press.

See Also

estimate, normalise_posterior

Examples

```
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
set.seed(123)
specification = specify_bsvar$new(us_fiscal_lsuw, p = 1)
# run the burn-in
burn_in
             = estimate(specification, 10)
# estimate the model
posterior
             = estimate(burn_in, 50)
# compute impulse responses 2 years ahead
irf
            = compute_impulse_responses(posterior, horizon = 8)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar$new(p = 1) |>
 estimate(S = 10) \mid >
 estimate(S = 50) \mid >
 compute_impulse_responses(horizon = 8) -> ir
```

compute_regime_probabilities

Computes posterior draws of regime probabilities

Description

Each of the draws from the posterior estimation of a model is transformed into a draw from the posterior distribution of the regime probabilities. These represent either the realisations of the regime indicators, when type = "realized", filtered probabilities, when type = "filtered", forecasted regime probabilities, when type = "forecasted", or the smoothed probabilities, when type = "smoothed", .

Usage

```
compute_regime_probabilities(
  posterior,
  type = c("realized", "filtered", "forecasted", "smoothed")
)
```

Arguments

posterior posterior estimation outcome of regime-dependent heteroskedastic models - an

object of either of the classes: PosteriorBSVARMSH, or PosteriorBSVARMIX

obtained by running the estimate function.

type one of the values "realized", "filtered", "forecasted", or "smoothed"

denoting the type of probabilities to be computed.

Value

An object of class PosteriorRegimePr, that is, an MxTxS array with attribute PosteriorRegimePr containing S draws of the regime probabilities.

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Song, Y., and Woźniak, T., (2021) Markov Switching. *Oxford Research Encyclopedia of Economics and Finance*, Oxford University Press, doi:10.1093/acrefore/9780190625979.013.174.

See Also

```
estimate, normalise_posterior
```

```
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
set.seed(123)
specification = specify_bsvar_msh$new(us_fiscal_lsuw, p = 2, M = 2)
# run the burn-in
burn_in
        = estimate(specification, 10)
# estimate the model
posterior = estimate(burn_in, 50)
# compute the posterior draws of realized regime indicators
            = compute_regime_probabilities(posterior)
# compute the posterior draws of filtered probabilities
             = compute_regime_probabilities(posterior, "filtered")
filtered
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_msh$new(p = 1, M = 2) >
```

```
estimate(S = 10) |>
estimate(S = 50) -> posterior
regimes = compute_regime_probabilities(posterior)
filtered = compute_regime_probabilities(posterior, "filtered")
```

```
compute_structural_shocks
```

Computes posterior draws of structural shocks

Description

Each of the draws from the posterior estimation of a model is transformed into a draw from the posterior distribution of the structural shocks.

Usage

```
compute_structural_shocks(posterior)
```

Arguments

posterior

posterior estimation outcome - an object of either of the classes: PosteriorB-SVAR, PosteriorBSVARMSH, PosteriorBSVARMIX, or PosteriorBSVARSV obtained by running the estimate function. The interpretation depends on the normalisation of the shocks using function normalise_posterior(). Verify if the default settings are appropriate.

Value

An object of class PosteriorShocks, that is, an NxTxS array with attribute PosteriorShocks containing S draws of the structural shocks.

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

See Also

```
estimate, normalise_posterior
```

```
# upload data
data(us_fiscal_lsuw)

# specify the model and set seed
set.seed(123)
specification = specify_bsvar$new(us_fiscal_lsuw, p = 2)
```

```
# run the burn-in
             = estimate(specification, 10)
burn_in
# estimate the model
            = estimate(burn_in$get_last_draw(), 50)
posterior
# compute structural shocks
             = compute_structural_shocks(posterior)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar$new(p = 1) |>
 estimate(S = 10) \mid >
 estimate(S = 50) \mid >
 compute_structural_shocks() -> ss
```

compute_variance_decompositions

Computes posterior draws of the forecast error variance decomposition

Description

Each of the draws from the posterior estimation of a model is transformed into a draw from the posterior distribution of the forecast error variance decomposition.

Usage

```
compute_variance_decompositions(posterior, horizon)
```

Arguments

posterior posterior estimation outcome - an object of one of the classes: PosteriorBSVAR,

PosteriorBSVARMSH, PosteriorBSVARMIX, or PosteriorBSVARSV obtained by running the estimate function. The interpretation depends on the normalisation of the shocks using function normalise_posterior(). Verify if the default

settings are appropriate.

horizon a positive integer number denoting the forecast horizon for the impulse re-

sponses computations.

Value

An object of class PosteriorFEVD, that is, an NxNx(horizon+1)xS array with attribute Posterior-FEVD containing S draws of the forecast error variance decomposition.

14 estimate

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Kilian, L., & Lütkepohl, H. (2017). Structural VAR Tools, Chapter 4, In: Structural vector autoregressive analysis. Cambridge University Press.

See Also

```
compute_impulse_responses, estimate, normalise_posterior
```

Examples

```
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
set.seed(123)
specification = specify_bsvar$new(us_fiscal_lsuw, p = 2)
# run the burn-in
burn_in
             = estimate(specification, 10)
# estimate the model
posterior
             = estimate(burn_in$get_last_draw(), 50)
# compute forecast error variance decomposition 2 years ahead
             = compute_variance_decompositions(posterior, horizon = 8)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar*new(p = 2) \mid >
 estimate(S = 10) \mid >
 estimate(S = 50) \mid >
 compute_variance_decompositions(horizon = 8) -> fevd
```

estimate

Bayesian estimation of Structural Vector Autoregressions via Gibbs sampler

Description

Estimates homo- or heteroskedastic SVAR models using the Gibbs sampler proposed by Waggoner & Zha (2003) for the structural matrix B and the equation-by-equation sampler by Chan, Koop, & Yu (2021) for the autoregressive slope parameters A. Additionally, the parameter matrices A and

estimate 15

B follow a Minnesota prior and generalised-normal prior distributions respectively with the matrix-specific overall shrinkage parameters estimated using a hierarchical prior distribution. A variety of models for conditional variances are possible including versions of Stochastic Volatility and Markov-switching heteroskedasticity. Non-normal specifications include finite and sparse normal mixture model for the structural shocks. See section **Details** for the model equations.

Usage

```
estimate(specification, S, thin = 10, show_progress = TRUE)
```

Arguments

specification an object of class BSVAR, BSVARMSH, BSVARMIX, or BSVARSV generated

using one of the specify_bsvar* functions or an object of class PosteriorB-SVAR, PosteriorBSVARMSH, PosteriorBSVARMIX, or PosteriorBSVARSV generated using the function estimate. The latter type of input facilitates the continuation of the MCMC sampling starting from the last draw of the previous

run.

S a positive integer, the number of posterior draws to be generated

thin a positive integer, specifying the frequency of MCMC output thinning

show_progress a logical value, if TRUE the estimation progress bar is visible

Details

The homoskedastic SVAR model is given by the reduced form equation:

$$Y = AX + E$$

where Y is an NxT matrix of dependent variables, X is a KxT matrix of explanatory variables, E is an NxT matrix of reduced form error terms, and A is an NxK matrix of autoregressive slope coefficients and parameters on deterministic terms in X.

The structural equation is given by

$$BE = U$$

where U is an NxT matrix of structural form error terms, and B is an NxN matrix of contemporaneous relationships.

The structural shocks, U, are temporally and contemporaneously independent and jointly normally distributed with zero mean and unit variances.

The various SVAR models estimated differ by the specification of structural shocks variances. Their specification depends on the specify_bsvar* function used. The different models include:

- homoskedastic model with unit variances
- heteroskedastic model with stationary Markov switching in the variances
- · heteroskedastic model with Stochastic Volatility process for variances
- non-normal model with a finite mixture of normal components and component-specific variances
- heteroskedastic model with sparse Markov switching in the variances where the number of heteroskedastic components is estimated
- non-normal model with a sparse mixture of normal components and component-specific variances where the number of heteroskedastic components is estimated

16 estimate

Value

An object of class PosteriorBSVAR, PosteriorBSVARMSH, PosteriorBSVARMIX, or PosteriorBSVARSV containing the Bayesian estimation output and containing two elements:

posterior a list with a collection of S draws from the posterior distribution generated via Gibbs sampler containing many arrays and vectors whose selection depends on the model specification. last_draw an object of class BSVAR, BSVARMSH, BSVARMIX, or BSVARSV with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Sampling from the generalised-normal full conditional posterior distribution of matrix B is implemented using the Gibbs sampler by:

Waggoner, D.F., and Zha, T., (2003) A Gibbs sampler for structural vector autoregressions. *Journal of Economic Dynamics and Control*, **28**, 349–366, doi:10.1016/S01651889(02)001689.

Sampling from the multivariate normal full conditional posterior distribution of each of the A matrix row is implemented using the sampler by:

Chan, J.C.C., Koop, G, and Yu, X. (2021) Large Order-Invariant Bayesian VARs with Stochastic Volatility.

See Also

specify_bsvar_msh, specify_bsvar_mix, specify_bsvar_sv, normalise_posterior

```
# simple workflow
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar$new(us_fiscal_lsuw, p = 4)
set.seed(123)
# run the burn-in
       = estimate(specification, 50)
burn in
# estimate the model
posterior
          = estimate(burn_in, 100)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
```

estimate.BSVAR 17

```
specify_bsvar$new(p = 1) |>
estimate(S = 50) |>
estimate(S = 100) |>
compute_impulse_responses(horizon = 8) -> irf
```

estimate.BSVAR

Bayesian estimation of a homoskedastic Structural Vector Autoregression via Gibbs sampler

Description

Estimates the homoskedastic SVAR using the Gibbs sampler proposed by Waggoner & Zha (2003) for the structural matrix B and the equation-by-equation sampler by Chan, Koop, & Yu (2021) for the autoregressive slope parameters A. Additionally, the parameter matrices A and B follow a Minnesota prior and generalised-normal prior distributions respectively with the matrix-specific overall shrinkage parameters estimated using a hierarchical prior distribution. See section **Details** for the model equations.

Usage

```
## S3 method for class 'BSVAR'
estimate(specification, S, thin = 10, show_progress = TRUE)
```

Arguments

 $specification \quad an object of class \ BSVAR \ generated \ using \ the \ specify_bsvar\\ specify_$

S a positive integer, the number of posterior draws to be generated

thin a positive integer, specifying the frequency of MCMC output thinning

show_progress a logical value, if TRUE the estimation progress bar is visible

Details

The homoskedastic SVAR model is given by the reduced form equation:

$$Y = AX + E$$

where Y is an NxT matrix of dependent variables, X is a KxT matrix of explanatory variables, E is an NxT matrix of reduced form error terms, and A is an NxK matrix of autoregressive slope coefficients and parameters on deterministic terms in X.

The structural equation is given by

$$BE = U$$

where U is an NxT matrix of structural form error terms, and B is an NxN matrix of contemporaneous relationships.

Finally, the structural shocks, U, are temporally and contemporaneously independent and jointly normally distributed with zero mean and unit variances.

18 estimate.BSVAR

Value

An object of class PosteriorBSVAR containing the Bayesian estimation output and containing two elements:

posterior a list with a collection of S draws from the posterior distribution generated via Gibbs sampler containing:

 $\bf A$ an NxKxS array with the posterior draws for matrix A

 $\bf B$ an NxNxS array with the posterior draws for matrix B

hyper a 5xS matrix with the posterior draws for the hyper-parameters of the hierarchical prior distribution

last_draw an object of class BSVAR with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Sampling from the generalised-normal full conditional posterior distribution of matrix B is implemented using the Gibbs sampler by:

Waggoner, D.F., and Zha, T., (2003) A Gibbs sampler for structural vector autoregressions. *Journal of Economic Dynamics and Control*, **28**, 349–366, doi:10.1016/S01651889(02)001689.

Sampling from the multivariate normal full conditional posterior distribution of each of the A matrix row is implemented using the sampler by:

Chan, J.C.C., Koop, G, and Yu, X. (2021) Large Order-Invariant Bayesian VARs with Stochastic Volatility.

See Also

```
specify_bsvar, specify_posterior_bsvar, normalise_posterior
```

estimate.BSVARMIX 19

estimate.BSVARMIX

Bayesian estimation of a Structural Vector Autoregression with shocks following a finite mixture of normal components via Gibbs sampler

Description

Estimates the SVAR with non-normal residuals following a finite M mixture of normal distributions proposed by Woźniak & Droumaguet (2022). Implements the Gibbs sampler proposed by Waggoner & Zha (2003) for the structural matrix B and the equation-by-equation sampler by Chan, Koop, & Yu (2021) for the autoregressive slope parameters A. Additionally, the parameter matrices A and B follow a Minnesota prior and generalised-normal prior distributions respectively with the matrix-specific overall shrinkage parameters estimated thanks to a hierarchical prior distribution. The finite mixture of normals model is estimated using the prior distributions and algorithms proposed by Woźniak & Droumaguet (2022). See section **Details** for the model equations.

Usage

```
## S3 method for class 'BSVARMIX'
estimate(specification, S, thin = 10, show_progress = TRUE)
```

Arguments

specification an object of class BSVARMIX generated using the specify_bsvar_mix\$new() function.

S a positive integer, the number of posterior draws to be generated thin a positive integer, specifying the frequency of MCMC output thinning show_progress a logical value, if TRUE the estimation progress bar is visible

Details

The heteroskedastic SVAR model is given by the reduced form equation:

$$Y = AX + E$$

where Y is an NxT matrix of dependent variables, X is a KxT matrix of explanatory variables, E is an NxT matrix of reduced form error terms, and A is an NxK matrix of autoregressive slope coefficients and parameters on deterministic terms in X.

20 estimate.BSVARMIX

The structural equation is given by

$$BE = U$$

where U is an NxT matrix of structural form error terms, and B is an NxN matrix of contemporaneous relationships.

Finally, the structural shocks, U, are temporally and contemporaneously independent and finite-mixture of normals distributed with zero mean. The conditional variance of the nth shock at time t is given by:

$$Var_{t-1}[u_{n,t}] = s_{n,s_t}^2$$

where s_t is a the regime indicator of the regime-specific conditional variances of structural shocks s_{n,s_t}^2 . In this model, the variances of each of the structural shocks sum to M.

The regime indicator s_t is either such that:

- the regime probabilities are non-zero which requires all regimes to have a positive number occurrences over the sample period, or
- sparse with potentially many regimes with zero occurrences over the sample period and in which the number of regimes is estimated.

These model selection also with this respect is made using function specify_bsvar_mix.

Value

An object of class PosteriorBSVARMIX containing the Bayesian estimation output and containing two elements:

posterior a list with a collection of S draws from the posterior distribution generated via Gibbs sampler containing:

 $\bf A$ an NxKxS array with the posterior draws for matrix A

 ${\bf B}$ an NxNxS array with the posterior draws for matrix B

hyper a 5xS matrix with the posterior draws for the hyper-parameters of the hierarchical prior distribution

sigma2 an NxMxS array with the posterior draws for the structural shocks conditional variances

PR_TR an MxMxS array with the posterior draws for the transition matrix.

xi an MxTxS array with the posterior draws for the regime allocation matrix.

pi_0 an MxS matrix with the posterior draws for the ergodic probabilities

sigma an NxTxS array with the posterior draws for the structural shocks conditional standard deviations' series over the sample period

last_draw an object of class BSVARMIX with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

estimate.BSVARMIX 21

References

The model, prior distributions, and estimation algorithms were proposed by

Woźniak, T., and Droumaguet, M., (2022) Bayesian Assessment of Identifying Restrictions for Heteroskedastic Structural VARs

Some more analysis on heteroskedastic SVAR models was proposed by:

Lütkepohl, H., and Woźniak, T., (2020) Bayesian Inference for Structural Vector Autoregressions Identified by Markov-Switching Heteroskedasticity. *Journal of Economic Dynamics and Control* **113**, 103862, doi:10.1016/j.jedc.2020.103862.

Sampling from the generalised-normal full conditional posterior distribution of matrix B is implemented using the Gibbs sampler by:

Waggoner, D.F., and Zha, T., (2003) A Gibbs sampler for structural vector autoregressions. *Journal of Economic Dynamics and Control*, **28**, 349–366, doi:10.1016/S01651889(02)001689.

Sampling from the multivariate normal full conditional posterior distribution of each of the A matrix row is implemented using the sampler by:

Chan, J.C.C., Koop, G, and Yu, X. (2021) Large Order-Invariant Bayesian VARs with Stochastic Volatility.

The estimation of the mixture of normals heteroskedasticity closely follows procedures described by:

Song, Y., and Woźniak, T., (2021) Markov Switching. *Oxford Research Encyclopedia of Economics and Finance*, Oxford University Press, doi:10.1093/acrefore/9780190625979.013.174.

and

Frühwirth-Schnatter, S., (2006) Finite Mixture and Markov Switching Models. Springer Series in Statistics. New York: Springer, doi:10.1007/9780387357683.

The sparse model is inspired by:

Malsiner-Walli, G., Frühwirth-Schnatter, S., and Grün, B. (2016) Model-based clustering based on sparse finite Gaussian mixtures. *Statistics and Computing*, **26**(1–2), 303–324, doi:10.1007/s11222-01495002.

The forward-filtering backward-sampling is implemented following the proposal by:

Chib, S. (1996) Calculating posterior distributions and modal estimates in Markov mixture models. *Journal of Econometrics*, **75**(1), 79–97, doi:10.1016/03044076(95)017704.

See Also

```
specify_bsvar_mix, specify_posterior_bsvar_mix, normalise_posterior
```

22 estimate.BSVARMSH

estimate.BSVARMSH

Bayesian estimation of a Structural Vector Autoregression with Markov-switching heteroskedasticity via Gibbs sampler

Description

Estimates the SVAR with Markov-switching heteroskedasticity with M regimes (MS(M)) proposed by Woźniak & Droumaguet (2022). Implements the Gibbs sampler proposed by Waggoner & Zha (2003) for the structural matrix B and the equation-by-equation sampler by Chan, Koop, & Yu (2021) for the autoregressive slope parameters A. Additionally, the parameter matrices A and B follow a Minnesota prior and generalised-normal prior distributions respectively with the matrix-specific overall shrinkage parameters estimated thanks to a hierarchical prior distribution. The MS model is estimated using the prior distributions and algorithms proposed by Woźniak & Droumaguet (2022). See section **Details** for the model equations.

Usage

```
## S3 method for class 'BSVARMSH'
estimate(specification, S, thin = 10, show_progress = TRUE)
```

Arguments

specification an object of class BSVARMSH generated using the specify_bsvar_msh\$new() function.

S a positive integer, the number of posterior draws to be generated thin a positive integer, specifying the frequency of MCMC output thinning show_progress a logical value, if TRUE the estimation progress bar is visible

estimate.BSVARMSH 23

Details

The heteroskedastic SVAR model is given by the reduced form equation:

$$Y = AX + E$$

where Y is an NxT matrix of dependent variables, X is a KxT matrix of explanatory variables, E is an NxT matrix of reduced form error terms, and A is an NxK matrix of autoregressive slope coefficients and parameters on deterministic terms in X.

The structural equation is given by

$$BE = U$$

where U is an NxT matrix of structural form error terms, and B is an NxN matrix of contemporaneous relationships.

Finally, the structural shocks, U, are temporally and contemporaneously independent and jointly normally distributed with zero mean. The conditional variance of the nth shock at time t is given by:

$$Var_{t-1}[u_{n.t}] = s_{n.s_t}^2$$

where s_t is a Markov process driving the time-variability of the regime-specific conditional variances of structural shocks $s_{n.s_t}^2$. In this model, the variances of each of the structural shocks sum to M

The Markov process s_t is either:

- stationary, irreducible, and aperiodic which requires all regimes to have a positive number occurrences over the sample period, or
- sparse with potentially many regimes with zero occurrences over the sample period and in which the number of regimes is estimated.

These model selection also with this respect is made using function specify_bsvar_msh.

Value

An object of class PosteriorBSVARMSH containing the Bayesian estimation output and containing two elements:

posterior a list with a collection of S draws from the posterior distribution generated via Gibbs sampler containing:

 $\bf A$ an NxKxS array with the posterior draws for matrix A

B an NxNxS array with the posterior draws for matrix B

hyper a 5xS matrix with the posterior draws for the hyper-parameters of the hierarchical prior distribution

sigma2 an NxMxS array with the posterior draws for the structural shocks conditional variances

PR TR an MxMxS array with the posterior draws for the transition matrix.

xi an MxTxS array with the posterior draws for the regime allocation matrix.

pi_0 an MxS matrix with the posterior draws for the initial state probabilities

sigma an NxTxS array with the posterior draws for the structural shocks conditional standard deviations' series over the sample period

last_draw an object of class BSVARMSH with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

24 estimate.BSVARMSH

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

The model, prior distributions, and estimation algorithms were proposed by

Woźniak, T., and Droumaguet, M., (2022) Bayesian Assessment of Identifying Restrictions for Heteroskedastic Structural VARs

Some more analysis on heteroskedastic SVAR models was proposed by:

Lütkepohl, H., and Woźniak, T., (2020) Bayesian Inference for Structural Vector Autoregressions Identified by Markov-Switching Heteroskedasticity. *Journal of Economic Dynamics and Control* **113**, 103862, doi:10.1016/j.jedc.2020.103862.

Sampling from the generalised-normal full conditional posterior distribution of matrix B is implemented using the Gibbs sampler by:

Waggoner, D.F., and Zha, T., (2003) A Gibbs sampler for structural vector autoregressions. *Journal of Economic Dynamics and Control*, **28**, 349–366, doi:10.1016/S01651889(02)001689.

Sampling from the multivariate normal full conditional posterior distribution of each of the A matrix row is implemented using the sampler by:

Chan, J.C.C., Koop, G, and Yu, X. (2021) Large Order-Invariant Bayesian VARs with Stochastic Volatility.

The estimation of the Markov-switching heteroskedasticity closely follows procedures described by:

Song, Y., and Woźniak, T., (2021) Markov Switching. *Oxford Research Encyclopedia of Economics and Finance*, Oxford University Press, doi:10.1093/acrefore/9780190625979.013.174.

and

Frühwirth-Schnatter, S., (2006) Finite Mixture and Markov Switching Models. Springer Series in Statistics. New York: Springer, doi:10.1007/9780387357683.

The sparse model is inspired by:

Malsiner-Walli, G., Frühwirth-Schnatter, S., and Grün, B. (2016) Model-based clustering based on sparse finite Gaussian mixtures. *Statistics and Computing*, **26**(1–2), 303–324, doi:10.1007/s11222-01495002.

The forward-filtering backward-sampling is implemented following the proposal by:

Chib, S. (1996) Calculating posterior distributions and modal estimates in Markov mixture models. *Journal of Econometrics*, **75**(1), 79–97, doi:10.1016/03044076(95)017704.

See Also

```
specify_bsvar_msh, specify_posterior_bsvar_msh, normalise_posterior
```

estimate.BSVARSV 25

```
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_msh$new(us_fiscal_lsuw, p = 1, M = 2)
set.seed(123)
# run the burn-in
             = estimate(specification, 10)
burn_in
# estimate the model
posterior
             = estimate(burn_in, 50)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_msh$new(p = 1, M = 2) >
 estimate(S = 10) \mid >
 estimate(S = 50) \mid >
 compute_impulse_responses(horizon = 4) -> irf
```

estimate.BSVARSV

Bayesian estimation of a Structural Vector Autoregression with Stochastic Volatility heteroskedasticity via Gibbs sampler

Description

Estimates the SVAR with Stochastic Volatility (SV) heteroskedasticity proposed by Lütkepohl, Shang, Uzeda, and Woźniak (2022). Implements the Gibbs sampler proposed by Waggoner & Zha (2003) for the structural matrix B and the equation-by-equation sampler by Chan, Koop, & Yu (2021) for the autoregressive slope parameters A. Additionally, the parameter matrices A and B follow a Minnesota prior and generalised-normal prior distributions respectively with the matrix-specific overall shrinkage parameters estimated thanks to a hierarchical prior distribution. The SV model is estimated using a range of techniques including: simulation smoother, auxiliary mixture, ancillarity-sufficiency interweaving strategy, and generalised inverse Gaussian distribution summarised by Kastner & Frühwirth-Schnatter (2014). See section **Details** for the model equations.

Usage

```
## S3 method for class 'BSVARSV'
estimate(specification, S, thin = 10, show_progress = TRUE)
```

Arguments

```
specification an object of class BSVARSV generated using the specify_bsvar_sv$new() function.

S a positive integer, the number of posterior draws to be generated thin a positive integer, specifying the frequency of MCMC output thinning show_progress a logical value, if TRUE the estimation progress bar is visible
```

26 estimate.BSVARSV

Details

The heteroskedastic SVAR model is given by the reduced form equation:

$$Y = AX + E$$

where Y is an NxT matrix of dependent variables, X is a KxT matrix of explanatory variables, E is an NxT matrix of reduced form error terms, and A is an NxK matrix of autoregressive slope coefficients and parameters on deterministic terms in X.

The structural equation is given by

$$BE = U$$

where U is an NxT matrix of structural form error terms, and B is an NxN matrix of contemporaneous relationships. Finally, the structural shocks, U, are temporally and contemporaneously independent and jointly normally distributed with zero mean.

Two alternative specifications of the conditional variance of the nth shock at time t can be estimated: non-centred Stochastic Volatility by Lütkepohl, Shang, Uzeda, and Woźniak (2022) or centred Stochastic Volatility by Chan, Koop, & Yu (2021).

The non-centred Stochastic Volatility by Lütkepohl, Shang, Uzeda, and Woźniak (2022) is selected by setting argument centred_sv of function specify_bsvar_sv\$new() to value FALSE. It has the conditional variances given by:

$$Var_{t-1}[u_{n,t}] = exp(w_n h_{n,t})$$

where w_n is the estimated conditional standard deviation of the log-conditional variance and the log-volatility process $h_{n,t}$ follows an autoregressive process:

$$h_{n,t} = g_n h_{n,t-1} + v_{n,t}$$

where $h_{n,0} = 0$, g_n is an autoregressive parameter and $v_{n,t}$ is a standard normal error term.

The centred Stochastic Volatility by Chan, Koop, & Yu (2021) is selected by setting argument centred_sv of function specify_bsvar_sv\$new() to value TRUE. Its conditional variances are given by:

$$Var_{t-1}[u_{n,t}] = exp(h_{n,t})$$

where the log-conditional variances $h_{n,t}$ follow an autoregressive process:

$$h_{n.t} = g_n h_{n.t-1} + v_{n.t}$$

where $h_{n.0} = 0$, g_n is an autoregressive parameter and $v_{n.t}$ is a zero-mean normal error term with variance $s_{v.n}^2$.

Value

An object of class PosteriorBSVARSV containing the Bayesian estimation output and containing two elements:

posterior a list with a collection of S draws from the posterior distribution generated via Gibbs sampler containing:

A an NxKxS array with the posterior draws for matrix A

estimate.BSVARSV 27

 ${\bf B}$ an NxNxS array with the posterior draws for matrix B

hyper a 5xS matrix with the posterior draws for the hyper-parameters of the hierarchical prior distribution

h an NxTxS array with the posterior draws of the log-volatility processes

rho an NxS matrix with the posterior draws of SV autoregressive parameters

omega an NxS matrix with the posterior draws of SV process conditional standard deviations

S an NxTxS array with the posterior draws of the auxiliary mixture component indicators

sigma2_omega an NxS matrix with the posterior draws of the variances of the zero-mean normal prior for omega

s_ an S-vector with the posterior draws of the scale of the gamma prior of the hierarchical prior for sigma2_omega

last_draw an object of class BSVARSV with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

The model, prior distributions, and estimation algorithms were proposed by

Lütkepohl, H., Shang, F., Uzeda, L., and Woźniak, T. (2022) Partial Identification of Heteroskedastic Structural VARs: Theory and Bayesian Inference.

Sampling from the generalised-normal full conditional posterior distribution of matrix B is implemented using the Gibbs sampler by:

Waggoner, D.F., and Zha, T., (2003) A Gibbs sampler for structural vector autoregressions. *Journal of Economic Dynamics and Control*, **28**, 349–366, doi:10.1016/S01651889(02)001689.

Sampling from the multivariate normal full conditional posterior distribution of each of the A matrix row is implemented using the sampler by:

Chan, J.C.C., Koop, G, and Yu, X. (2021) Large Order-Invariant Bayesian VARs with Stochastic Volatility.

Many of the techniques employed for the estimation of the Stochastic Volatility model are summarised by:

Kastner, G. and Frühwirth-Schnatter, S. (2014) Ancillarity-Sufficiency Interweaving Strategy (ASIS) for Boosting MCMC Estimation of Stochastic Volatility Models. *Computational Statistics & Data Analysis*, **76**, 408–423, doi:10.1016/j.csda.2013.01.002.

See Also

specify_bsvar_sv, specify_posterior_bsvar_sv, normalise_posterior

28 estimate.PosteriorBSVAR

Examples

```
# simple workflow
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_sv$new(us_fiscal_lsuw, p = 1)
set.seed(123)
# run the burn-in
burn_in
           = estimate(specification, 10)
# estimate the model
           = estimate(burn_in, 10, thin = 2)
posterior
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_sv$new(p = 1) |>
 estimate(S = 10) \mid >
 estimate(S = 10, thin = 2) >
 compute_impulse_responses(horizon = 4) -> irf
```

estimate.PosteriorBSVAR

Bayesian estimation of a homoskedastic Structural Vector Autoregression via Gibbs sampler

Description

Estimates the homoskedastic SVAR using the Gibbs sampler proposed by Waggoner & Zha (2003) for the structural matrix B and the equation-by-equation sampler by Chan, Koop, & Yu (2021) for the autoregressive slope parameters A. Additionally, the parameter matrices A and B follow a Minnesota prior and generalised-normal prior distributions respectively with the matrix-specific overall shrinkage parameters estimated using a hierarchical prior distribution. See section **Details** for the model equations.

Usage

```
## S3 method for class 'PosteriorBSVAR'
estimate(specification, S, thin = 10, show_progress = TRUE)
```

Arguments

specification

an object of class PosteriorBSVAR generated using the estimate.BSVAR() function. This setup facilitates the continuation of the MCMC sampling starting from the last draw of the previous run.

estimate.PosteriorBSVAR 29

S a positive integer, the number of posterior draws to be generated thin a positive integer, specifying the frequency of MCMC output thinning show_progress a logical value, if TRUE the estimation progress bar is visible

Details

The homoskedastic SVAR model is given by the reduced form equation:

$$Y = AX + E$$

where Y is an NxT matrix of dependent variables, X is a KxT matrix of explanatory variables, E is an NxT matrix of reduced form error terms, and A is an NxK matrix of autoregressive slope coefficients and parameters on deterministic terms in X.

The structural equation is given by

$$BE = U$$

where U is an NxT matrix of structural form error terms, and B is an NxN matrix of contemporaneous relationships.

Finally, the structural shocks, U, are temporally and contemporaneously independent and jointly normally distributed with zero mean and unit variances.

Value

An object of class PosteriorBSVAR containing the Bayesian estimation output and containing two elements:

posterior a list with a collection of S draws from the posterior distribution generated via Gibbs sampler containing:

A an NxKxS array with the posterior draws for matrix A

 ${\bf B}$ an NxNxS array with the posterior draws for matrix B

hyper a 5xS matrix with the posterior draws for the hyper-parameters of the hierarchical prior distribution

last_draw an object of class BSVAR with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Sampling from the generalised-normal full conditional posterior distribution of matrix B is implemented using the Gibbs sampler by:

Waggoner, D.F., and Zha, T., (2003) A Gibbs sampler for structural vector autoregressions. *Journal of Economic Dynamics and Control*, **28**, 349–366, doi:10.1016/S01651889(02)001689.

Sampling from the multivariate normal full conditional posterior distribution of each of the A matrix row is implemented using the sampler by:

Chan, J.C.C., Koop, G, and Yu, X. (2021) Large Order-Invariant Bayesian VARs with Stochastic Volatility.

See Also

specify_bsvar, specify_posterior_bsvar, normalise_posterior

Examples

```
# simple workflow
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar$new(us_fiscal_lsuw, p = 1)
set.seed(123)
# run the burn-in
burn_in
           = estimate(specification, 50)
# estimate the model
           = estimate(burn_in, 100)
posterior
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar$new(p = 1) |>
 estimate(S = 50) \mid >
 estimate(S = 100) >
 compute_impulse_responses(horizon = 4) -> irf
```

estimate.PosteriorBSVARMIX

Bayesian estimation of a Structural Vector Autoregression with shocks following a finite mixture of normal components via Gibbs sampler

Description

Estimates the SVAR with non-normal residuals following a finite M mixture of normal distributions proposed by Woźniak & Droumaguet (2022). Implements the Gibbs sampler proposed by Waggoner & Zha (2003) for the structural matrix B and the equation-by-equation sampler by Chan, Koop, & Yu (2021) for the autoregressive slope parameters A. Additionally, the parameter matrices A and B follow a Minnesota prior and generalised-normal prior distributions respectively with the matrix-specific overall shrinkage parameters estimated thanks to a hierarchical prior distribution. The finite mixture of normals model is estimated using the prior distributions and algorithms proposed by Woźniak & Droumaguet (2022). See section **Details** for the model equations.

Usage

```
## S3 method for class 'PosteriorBSVARMIX'
estimate(specification, S, thin = 10, show_progress = TRUE)
```

Arguments

specification an object of class PosteriorBSVARMIX generated using the estimate.BSVAR()

function. This setup facilitates the continuation of the MCMC sampling starting

from the last draw of the previous run.

S a positive integer, the number of posterior draws to be generated

thin a positive integer, specifying the frequency of MCMC output thinning

show_progress a logical value, if TRUE the estimation progress bar is visible

Details

The heteroskedastic SVAR model is given by the reduced form equation:

$$Y = AX + E$$

where Y is an NxT matrix of dependent variables, X is a KxT matrix of explanatory variables, E is an NxT matrix of reduced form error terms, and A is an NxK matrix of autoregressive slope coefficients and parameters on deterministic terms in X.

The structural equation is given by

$$BE = U$$

where U is an NxT matrix of structural form error terms, and B is an NxN matrix of contemporaneous relationships.

Finally, the structural shocks, U, are temporally and contemporaneously independent and finite-mixture of normals distributed with zero mean. The conditional variance of the nth shock at time t is given by:

$$Var_{t-1}[u_{n.t}] = s_{n.s_t}^2$$

where s_t is a the regime indicator of the regime-specific conditional variances of structural shocks s_{n,s_t}^2 . In this model, the variances of each of the structural shocks sum to M.

The regime indicator s_t is either such that:

- the regime probabilities are non-zero which requires all regimes to have a positive number occurrences over the sample period, or
- sparse with potentially many regimes with zero occurrences over the sample period and in which the number of regimes is estimated.

These model selection also with this respect is made using function specify_bsvar_mix.

Value

An object of class PosteriorBSVARMIX containing the Bayesian estimation output and containing two elements:

posterior a list with a collection of S draws from the posterior distribution generated via Gibbs sampler containing:

 $\bf A$ an NxKxS array with the posterior draws for matrix A

 ${\bf B}$ an NxNxS array with the posterior draws for matrix B

hyper a 5xS matrix with the posterior draws for the hyper-parameters of the hierarchical prior distribution

sigma2 an NxMxS array with the posterior draws for the structural shocks conditional variances

PR_TR an MxMxS array with the posterior draws for the transition matrix.

xi an MxTxS array with the posterior draws for the regime allocation matrix.

pi_0 an MxS matrix with the posterior draws for the ergodic probabilities

sigma an NxTxS array with the posterior draws for the structural shocks conditional standard deviations' series over the sample period

last_draw an object of class BSVARMIX with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

The model, prior distributions, and estimation algorithms were proposed by

Woźniak, T., and Droumaguet, M., (2022) Bayesian Assessment of Identifying Restrictions for Heteroskedastic Structural VARs

Some more analysis on heteroskedastic SVAR models was proposed by:

Lütkepohl, H., and Woźniak, T., (2020) Bayesian Inference for Structural Vector Autoregressions Identified by Markov-Switching Heteroskedasticity. *Journal of Economic Dynamics and Control* **113**, 103862, doi:10.1016/j.jedc.2020.103862.

Sampling from the generalised-normal full conditional posterior distribution of matrix B is implemented using the Gibbs sampler by:

Waggoner, D.F., and Zha, T., (2003) A Gibbs sampler for structural vector autoregressions. *Journal of Economic Dynamics and Control*, **28**, 349–366, doi:10.1016/S01651889(02)001689.

Sampling from the multivariate normal full conditional posterior distribution of each of the A matrix row is implemented using the sampler by:

Chan, J.C.C., Koop, G, and Yu, X. (2021) Large Order-Invariant Bayesian VARs with Stochastic Volatility.

The estimation of the mixture of normals heteroskedasticity closely follows procedures described by:

Song, Y., and Woźniak, T., (2021) Markov Switching. *Oxford Research Encyclopedia of Economics and Finance*, Oxford University Press, doi:10.1093/acrefore/9780190625979.013.174.

and

Frühwirth-Schnatter, S., (2006) Finite Mixture and Markov Switching Models. Springer Series in Statistics. New York: Springer, doi:10.1007/9780387357683.

The sparse model is inspired by:

Malsiner-Walli, G., Frühwirth-Schnatter, S., and Grün, B. (2016) Model-based clustering based on sparse finite Gaussian mixtures. *Statistics and Computing*, **26**(1–2), 303–324, doi:10.1007/s11222-01495002.

The forward-filtering backward-sampling is implemented following the proposal by:

Chib, S. (1996) Calculating posterior distributions and modal estimates in Markov mixture models. *Journal of Econometrics*, **75**(1), 79–97, doi:10.1016/03044076(95)017704.

See Also

specify_bsvar_mix, specify_posterior_bsvar_mix, normalise_posterior

Examples

```
# simple workflow
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_mix$new(us_fiscal_lsuw, p = 1, M = 2)
set.seed(123)
# run the burn-in
burn_in
           = estimate(specification, 10)
# estimate the model
posterior
           = estimate(burn_in, 50)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_mix$new(p = 1, M = 2) >
 estimate(S = 10) \mid >
 estimate(S = 50) \mid >
 compute_impulse_responses(horizon = 4) -> irf
```

estimate.PosteriorBSVARMSH

Bayesian estimation of a Structural Vector Autoregression with Markov-switching heteroskedasticity via Gibbs sampler

Description

Estimates the SVAR with Markov-switching heteroskedasticity with M regimes (MS(M)) proposed by Woźniak & Droumaguet (2022). Implements the Gibbs sampler proposed by Waggoner & Zha (2003) for the structural matrix B and the equation-by-equation sampler by Chan, Koop, & Yu (2021) for the autoregressive slope parameters A. Additionally, the parameter matrices A and B follow a Minnesota prior and generalised-normal prior distributions respectively with the matrix-specific overall shrinkage parameters estimated thanks to a hierarchical prior distribution. The MS model is estimated using the prior distributions and algorithms proposed by Woźniak & Droumaguet (2022). See section **Details** for the model equations.

Usage

```
## S3 method for class 'PosteriorBSVARMSH'
estimate(specification, S, thin = 10, show_progress = TRUE)
```

Arguments

specification an object of class PosteriorBSVARMSH generated using the estimate.BSVAR()

function. This setup facilitates the continuation of the MCMC sampling starting

from the last draw of the previous run.

S a positive integer, the number of posterior draws to be generated

thin a positive integer, specifying the frequency of MCMC output thinning

show_progress a logical value, if TRUE the estimation progress bar is visible

Details

The heteroskedastic SVAR model is given by the reduced form equation:

$$Y = AX + E$$

where Y is an NxT matrix of dependent variables, X is a KxT matrix of explanatory variables, E is an NxT matrix of reduced form error terms, and A is an NxK matrix of autoregressive slope coefficients and parameters on deterministic terms in X.

The structural equation is given by

$$BE = U$$

where U is an NxT matrix of structural form error terms, and B is an NxN matrix of contemporaneous relationships.

Finally, the structural shocks, U, are temporally and contemporaneously independent and jointly normally distributed with zero mean. The conditional variance of the nth shock at time t is given by:

$$Var_{t-1}[u_{n.t}] = s_{n.s_t}^2$$

where s_t is a Markov process driving the time-variability of the regime-specific conditional variances of structural shocks $s_{n.s_t}^2$. In this model, the variances of each of the structural shocks sum to M

The Markov process s_t is either:

- stationary, irreducible, and aperiodic which requires all regimes to have a positive number occurrences over the sample period, or
- sparse with potentially many regimes with zero occurrences over the sample period and in which the number of regimes is estimated.

These model selection also with this respect is made using function specify_bsvar_msh.

Value

An object of class PosteriorBSVARMSH containing the Bayesian estimation output and containing two elements:

posterior a list with a collection of S draws from the posterior distribution generated via Gibbs sampler containing:

A an NxKxS array with the posterior draws for matrix A

 ${\bf B}$ an NxNxS array with the posterior draws for matrix B

hyper a 5xS matrix with the posterior draws for the hyper-parameters of the hierarchical prior distribution

sigma2 an NxMxS array with the posterior draws for the structural shocks conditional variances

PR_TR an MxMxS array with the posterior draws for the transition matrix.

xi an MxTxS array with the posterior draws for the regime allocation matrix.

pi_0 an MxS matrix with the posterior draws for the initial state probabilities

sigma an NxTxS array with the posterior draws for the structural shocks conditional standard deviations' series over the sample period

last_draw an object of class BSVARMSH with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

The model, prior distributions, and estimation algorithms were proposed by

Woźniak, T., and Droumaguet, M., (2022) Bayesian Assessment of Identifying Restrictions for Heteroskedastic Structural VARs

Some more analysis on heteroskedastic SVAR models was proposed by:

Lütkepohl, H., and Woźniak, T., (2020) Bayesian Inference for Structural Vector Autoregressions Identified by Markov-Switching Heteroskedasticity. *Journal of Economic Dynamics and Control* **113**, 103862, doi:10.1016/j.jedc.2020.103862.

Sampling from the generalised-normal full conditional posterior distribution of matrix B is implemented using the Gibbs sampler by:

Waggoner, D.F., and Zha, T., (2003) A Gibbs sampler for structural vector autoregressions. *Journal of Economic Dynamics and Control*, **28**, 349–366, doi:10.1016/S01651889(02)001689.

Sampling from the multivariate normal full conditional posterior distribution of each of the A matrix row is implemented using the sampler by:

Chan, J.C.C., Koop, G, and Yu, X. (2021) Large Order-Invariant Bayesian VARs with Stochastic Volatility.

The estimation of the Markov-switching heteroskedasticity closely follows procedures described by:

Song, Y., and Woźniak, T., (2021) Markov Switching. *Oxford Research Encyclopedia of Economics and Finance*, Oxford University Press, doi:10.1093/acrefore/9780190625979.013.174.

and

Frühwirth-Schnatter, S., (2006) Finite Mixture and Markov Switching Models. Springer Series in Statistics. New York: Springer, doi:10.1007/9780387357683.

The sparse model is inspired by:

Malsiner-Walli, G., Frühwirth-Schnatter, S., and Grün, B. (2016) Model-based clustering based on sparse finite Gaussian mixtures. *Statistics and Computing*, **26**(1–2), 303–324, doi:10.1007/s11222-01495002.

The forward-filtering backward-sampling is implemented following the proposal by:

Chib, S. (1996) Calculating posterior distributions and modal estimates in Markov mixture models. *Journal of Econometrics*, **75**(1), 79–97, doi:10.1016/03044076(95)017704.

See Also

```
specify_bsvar_msh, specify_posterior_bsvar_msh, normalise_posterior
```

```
# simple workflow
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_msh$new(us_fiscal_lsuw, p = 1, M = 2)
set.seed(123)
# run the burn-in
burn_in
       = estimate(specification, 10)
# estimate the model
posterior
           = estimate(burn_in, 50)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_msh$new(p = 1, M = 2) >
 estimate(S = 10) |>
 estimate(S = 50) \mid >
 compute_impulse_responses(horizon = 4) -> irf
```

estimate.PosteriorBSVARSV

Bayesian estimation of a Structural Vector Autoregression with Stochastic Volatility heteroskedasticity via Gibbs sampler

Description

Estimates the SVAR with Stochastic Volatility (SV) heteroskedasticity proposed by Lütkepohl, Shang, Uzeda, and Woźniak (2022). Implements the Gibbs sampler proposed by Waggoner & Zha (2003) for the structural matrix B and the equation-by-equation sampler by Chan, Koop, & Yu (2021) for the autoregressive slope parameters A. Additionally, the parameter matrices A and B follow a Minnesota prior and generalised-normal prior distributions respectively with the matrix-specific overall shrinkage parameters estimated thanks to a hierarchical prior distribution. The SV model is estimated using a range of techniques including: simulation smoother, auxiliary mixture, ancillarity-sufficiency interweaving strategy, and generalised inverse Gaussian distribution summarised by Kastner & Frühwirth-Schnatter (2014). See section **Details** for the model equations.

Usage

```
## S3 method for class 'PosteriorBSVARSV'
estimate(specification, S, thin = 10, show_progress = TRUE)
```

Arguments

specification an object of class PosteriorBSVARSV generated using the estimate.BSVAR()

function. This setup facilitates the continuation of the MCMC sampling starting

from the last draw of the previous run.

S a positive integer, the number of posterior draws to be generated

thin a positive integer, specifying the frequency of MCMC output thinning

show_progress a logical value, if TRUE the estimation progress bar is visible

Details

The heteroskedastic SVAR model is given by the reduced form equation:

$$Y = AX + E$$

where Y is an NxT matrix of dependent variables, X is a KxT matrix of explanatory variables, E is an NxT matrix of reduced form error terms, and A is an NxK matrix of autoregressive slope coefficients and parameters on deterministic terms in X.

The structural equation is given by

$$BE = U$$

where U is an NxT matrix of structural form error terms, and B is an NxN matrix of contemporaneous relationships. Finally, the structural shocks, U, are temporally and contemporaneously independent and jointly normally distributed with zero mean.

Two alternative specifications of the conditional variance of the nth shock at time t can be estimated: non-centred Stochastic Volatility by Lütkepohl, Shang, Uzeda, and Woźniak (2022) or centred Stochastic Volatility by Chan, Koop, & Yu (2021).

The non-centred Stochastic Volatility by Lütkepohl, Shang, Uzeda, and Woźniak (2022) is selected by setting argument centred_sv of function specify_bsvar_sv\$new() to value FALSE. It has the conditional variances given by:

$$Var_{t-1}[u_{n.t}] = exp(w_n h_{n.t})$$

where w_n is the estimated conditional standard deviation of the log-conditional variance and the log-volatility process $h_{n,t}$ follows an autoregressive process:

$$h_{n.t} = g_n h_{n.t-1} + v_{n.t}$$

where $h_{n,0} = 0$, g_n is an autoregressive parameter and $v_{n,t}$ is a standard normal error term.

The centred Stochastic Volatility by Chan, Koop, & Yu (2021) is selected by setting argument centred_sv of function specify_bsvar_sv\$new() to value TRUE. Its conditional variances are given by:

$$Var_{t-1}[u_{n.t}] = exp(h_{n.t})$$

where the log-conditional variances $h_{n,t}$ follow an autoregressive process:

$$h_{n.t} = g_n h_{n.t-1} + v_{n.t}$$

where $h_{n.0} = 0$, g_n is an autoregressive parameter and $v_{n.t}$ is a zero-mean normal error term with variance $s_{v,n}^2$.

Value

An object of class PosteriorBSVARSV containing the Bayesian estimation output and containing two elements:

posterior a list with a collection of S draws from the posterior distribution generated via Gibbs sampler containing:

 $\bf A$ an NxKxS array with the posterior draws for matrix A

 ${\bf B}$ an NxNxS array with the posterior draws for matrix B

hyper a 5xS matrix with the posterior draws for the hyper-parameters of the hierarchical prior distribution

h an NxTxS array with the posterior draws of the log-volatility processes

rho an NxS matrix with the posterior draws of SV autoregressive parameters

omega an NxS matrix with the posterior draws of SV process conditional standard deviations

S an NxTxS array with the posterior draws of the auxiliary mixture component indicators

sigma2_omega an NxS matrix with the posterior draws of the variances of the zero-mean normal prior for omega

s_ an S-vector with the posterior draws of the scale of the gamma prior of the hierarchical prior for sigma2_omega

last_draw an object of class BSVARSV with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

The model, prior distributions, and estimation algorithms were proposed by

Lütkepohl, H., Shang, F., Uzeda, L., and Woźniak, T. (2022) Partial Identification of Heteroskedastic Structural VARs: Theory and Bayesian Inference.

Sampling from the generalised-normal full conditional posterior distribution of matrix B is implemented using the Gibbs sampler by:

Waggoner, D.F., and Zha, T., (2003) A Gibbs sampler for structural vector autoregressions. *Journal of Economic Dynamics and Control*, **28**, 349–366, doi:10.1016/S01651889(02)001689.

Sampling from the multivariate normal full conditional posterior distribution of each of the A matrix row is implemented using the sampler by:

Chan, J.C.C., Koop, G, and Yu, X. (2021) Large Order-Invariant Bayesian VARs with Stochastic Volatility.

Many of the techniques employed for the estimation of the Stochastic Volatility model are summarised by:

Kastner, G. and Frühwirth-Schnatter, S. (2014) Ancillarity-Sufficiency Interweaving Strategy (ASIS) for Boosting MCMC Estimation of Stochastic Volatility Models. *Computational Statistics & Data Analysis*, **76**, 408–423, doi:10.1016/j.csda.2013.01.002.

See Also

```
specify_bsvar_sv, specify_posterior_bsvar_sv, normalise_posterior
```

```
# simple workflow
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_sv$new(us_fiscal_lsuw, p = 1)
set.seed(123)
# run the burn-in
burn in
          = estimate(specification, 10)
# estimate the model
posterior = estimate(burn_in, 20)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_sv$new(p = 1) |>
```

40 forecast

```
estimate(S = 10) |>
estimate(S = 10, thin = 2) |>
compute_impulse_responses(horizon = 4) -> irf
```

forecast

Forecasting using Structural Vector Autoregression

Description

Samples from the joint predictive density of all of the dependent variables at forecast horizons from 1 to horizon specified as an argument of the function.

Usage

```
forecast(posterior, horizon, exogenous_forecast)
```

Arguments

posterior

posterior estimation outcome - an object of either of the classes: PosteriorB-SVAR, PosteriorBSVARMSH, PosteriorBSVARMIX, or PosteriorBSVARSV ob-

tained by running the estimate function.

horizon

a positive integer, specifying the forecasting horizon.

exogenous_forecast

a matrix of dimension horizon x d containing forecasted values of the exogenous variables.

Value

A list of class Forecasts containing the draws from the predictive density and for heteroskedastic models the draws from the predictive density of structural shocks conditional standard deviations. The output elements include:

forecasts an NxTxS array with the draws from predictive density

forecasts_sigma provided only for heteroskedastic models, an NxTxS array with the draws from the predictive density of structural shocks conditional standard deviations

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

forecast.PosteriorBSVAR 41

Examples

```
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
set.seed(123)
specification = specify_bsvar$new(us_fiscal_lsuw, p = 1)
# run the burn-in
burn_in
             = estimate(specification, 10)
# estimate the model
posterior = estimate(burn_in, 20)
# sample from predictive density 1 year ahead
predictive
             = forecast(posterior, 4)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar$new(p = 1) |>
 estimate(S = 10) \mid >
 estimate(S = 20) \mid >
 forecast(horizon = 4) -> predictive
```

forecast.PosteriorBSVAR

Forecasting using Structural Vector Autoregression

Description

Samples from the joint predictive density of all of the dependent variables at forecast horizons from 1 to horizon specified as an argument of the function.

Usage

```
## S3 method for class 'PosteriorBSVAR'
forecast(posterior, horizon, exogenous_forecast = NULL)
```

Arguments

posterior posterior estimation outcome - an object of class PosteriorBSVAR obtained by

running the estimate function.

horizon a positive integer, specifying the forecasting horizon.

exogenous_forecast

a matrix of dimension horizon x d containing forecasted values of the exogenous variables.

Value

A list of class Forecasts containing the draws from the predictive density. The output list includes element:

forecasts an NxTxS array with the draws from predictive density

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

Examples

```
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
set.seed(123)
specification = specify_bsvar$new(us_fiscal_lsuw, p = 1)
# run the burn-in
burn_in = estimate(specification, 10)
# estimate the model
posterior = estimate(burn_in, 20)
# sample from predictive density 1 year ahead
predictive = forecast(posterior, 4)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvarsnew(p = 1) \mid >
 estimate(S = 10) \mid >
 estimate(S = 20) \mid >
 forecast(horizon = 4) -> predictive
```

forecast.PosteriorBSVARMIX

Forecasting using Structural Vector Autoregression

Description

Samples from the joint predictive density of all of the dependent variables at forecast horizons from 1 to horizon specified as an argument of the function.

Usage

```
## S3 method for class 'PosteriorBSVARMIX'
forecast(posterior, horizon, exogenous_forecast = NULL)
```

Arguments

posterior posterior estimation outcome - an object of class PosteriorBSVARMIX obtained

by running the estimate function.

horizon a positive integer, specifying the forecasting horizon.

exogenous_forecast

a matrix of dimension horizon x d containing forecasted values of the exoge-

nous variables.

Value

A list of class Forecasts containing the draws from the predictive density and for heteroskedastic models the draws from the predictive density of structural shocks conditional standard deviations. The output elements include:

forecasts an NxTxS array with the draws from predictive density

forecasts_sigma provided only for heteroskedastic models, an NxTxS array with the draws from the predictive density of structural shocks conditional standard deviations

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

```
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
set.seed(123)
specification = specify_bsvar_mix$new(us_fiscal_lsuw, p = 1, M = 2)
# run the burn-in
burn_in
            = estimate(specification, 10)
# estimate the model
            = estimate(burn_in, 20)
posterior
# sample from predictive density 1 year ahead
predictive
            = forecast(posterior, 4)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_mix$new(p = 1, M = 2) >
```

```
estimate(S = 10) |>
estimate(S = 20) |>
forecast(horizon = 4) -> predictive
```

forecast.PosteriorBSVARMSH

Forecasting using Structural Vector Autoregression

Description

Samples from the joint predictive density of all of the dependent variables at forecast horizons from 1 to horizon specified as an argument of the function.

Usage

```
## S3 method for class 'PosteriorBSVARMSH'
forecast(posterior, horizon, exogenous_forecast = NULL)
```

Arguments

posterior posterior estimation outcome - an object of class PosteriorBSVARMSH obtained

by running the estimate function.

horizon a positive integer, specifying the forecasting horizon.

exogenous_forecast

a matrix of dimension horizon x d containing forecasted values of the exoge-

nous variables.

Value

A list of class Forecasts containing the draws from the predictive density and for heteroskedastic models the draws from the predictive density of structural shocks conditional standard deviations. The output elements include:

forecasts an NxTxS array with the draws from predictive density

forecasts_sigma provided only for heteroskedastic models, an NxTxS array with the draws from the predictive density of structural shocks conditional standard deviations

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

Examples

```
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
set.seed(123)
specification = specify_bsvar_msh$new(us_fiscal_lsuw, p = 1, M = 2)
# run the burn-in
burn_in
             = estimate(specification, 10)
# estimate the model
posterior = estimate(burn_in, 20)
# sample from predictive density 1 year ahead
predictive
             = forecast(posterior, 4)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_msh$new(p = 1, M = 2) >
 estimate(S = 10) \mid >
 estimate(S = 20) \mid >
 forecast(horizon = 4) -> predictive
```

forecast.PosteriorBSVARSV

Forecasting using Structural Vector Autoregression

Description

Samples from the joint predictive density of all of the dependent variables at forecast horizons from 1 to horizon specified as an argument of the function.

Usage

```
## S3 method for class 'PosteriorBSVARSV'
forecast(posterior, horizon, exogenous_forecast = NULL)
```

Arguments

posterior posterior estimation outcome - an object of class PosteriorBSVARSV obtained

by running the estimate function.

horizon a positive integer, specifying the forecasting horizon.

exogenous_forecast

a matrix of dimension horizon x d containing forecasted values of the exogenous variables.

46 normalise_posterior

Value

A list of class Forecasts containing the draws from the predictive density and for heteroskedastic models the draws from the predictive density of structural shocks conditional standard deviations. The output elements include:

forecasts an NxTxS array with the draws from predictive density

forecasts_sigma provided only for heteroskedastic models, an NxTxS array with the draws from the predictive density of structural shocks conditional standard deviations

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

```
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
set.seed(123)
specification = specify_bsvar_sv$new(us_fiscal_lsuw, p = 1)
# run the burn-in
burn_in
             = estimate(specification, 10)
# estimate the model
posterior
            = estimate(burn_in, 10, thin = 2)
# sample from predictive density 1 year ahead
predictive
             = forecast(posterior, 4)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_svsnew(p = 1) \mid >
 estimate(S = 10) \mid >
 estimate(S = 10, thin = 2) >
 forecast(horizon = 4) -> predictive
```

normalise_posterior 47

Description

Normalises the sign of rows of matrix B MCMC draws, provided as the first argument posterior_B, relative to matrix B_hat, provided as the second argument of the function. The implemented procedure proposed by Waggoner, Zha (2003) normalises the MCMC output in an optimal way leading to the unimodal posterior. Only normalised MCMC output is suitable for the computations of the posterior characteristics of the B matrix elements and their functions such as the impulse response functions and other economically interpretable values.

Usage

```
normalise_posterior(posterior, B_hat)
```

Arguments

posterior posterior estimation outcome - an object of either of classes: PosteriorBSVAR,

PosteriorBSVARMSH, PosteriorBSVARMIX, or PosteriorBSVARSV containing, amongst other draws, the S draws from the posterior distribution of the NxN matrix of contemporaneous relationships B. These draws are to be normalised

with respect to:

B_hat an NxN matrix specified by the user to have the desired row signs

Value

Nothing. The normalised elements overwrite the corresponding elements of the first argument posterior_B by reference.

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Waggoner, D.F., and Zha, T., (2003) Likelihood Preserving Normalization in Multiple Equation Models. *Journal of Econometrics*, **114**(2), 329–47, doi:10.1016/S03044076(03)000873.

See Also

```
estimate
```

```
# upload data
data(us_fiscal_lsuw)

# specify the model and set seed
specification = specify_bsvar_sv$new(us_fiscal_lsuw, p = 4)
set.seed(123)

# run the burn-in
burn_in = estimate(specification, 10)
```

48 specify_bsvar

```
# estimate the model
posterior = estimate(burn_in, 10, thin = 1)

# normalise the posterior
BB = posterior$last_draw$starting_values$B  # get the last draw of B
B_hat = diag((-1) * sign(diag(BB))) %*% BB  # set negative diagonal elements
normalise_posterior(posterior, B_hat)  # draws in posterior are normalised
```

specify_bsvar

R6 Class representing the specification of the homoskedastic BSVAR model

Description

The class BSVAR presents complete specification for the homoskedastic bsvar model.

Public fields

p a non-negative integer specifying the autoregressive lag order of the model. identification an object IdentificationBSVAR with the identifying restrictions. prior an object PriorBSVAR with the prior specification. data_matrices an object DataMatricesBSVAR with the data matrices. starting_values an object StartingValuesBSVAR with the starting values.

Methods

Public methods:

```
specify_bsvar$new()
specify_bsvar$get_data_matrices()
specify_bsvar$get_identification()
specify_bsvar$get_prior()
specify_bsvar$get_starting_values()
specify_bsvar$clone()
```

Method new(): Create a new specification of the homoskedastic bsvar model BSVAR.

```
Usage:
specify_bsvar$new(
  data,
  p = 1L,
  B,
  exogenous = NULL,
  stationary = rep(FALSE, ncol(data))
)
```

specify_bsvar 49

```
Arguments:
```

data a (T+p)xN matrix with time series data.

p a positive integer providing model's autoregressive lag order.

B a logical NxN matrix containing value TRUE for the elements of the structural matrix B to be estimated and value FALSE for exclusion restrictions to be set to zero.

exogenous a (T+p)xd matrix of exogenous variables.

stationary an N logical vector - its element set to FALSE sets the prior mean for the autoregressive parameters of the Nth equation to the white noise process, otherwise to random walk.

Returns: A new complete specification for the homoskedastic bsvar model BSVAR.

Method get_data_matrices(): Returns the data matrices as the DataMatricesBSVAR object.

```
Usage:
```

```
specify_bsvar$get_data_matrices()
Examples:
data(us_fiscal_lsuw)
spec = specify_bsvar$new(
    data = us_fiscal_lsuw,
    p = 4
)
spec$get_data_matrices()
```

Method get_identification(): Returns the identifying restrictions as the IdentificationB-SVARs object.

```
Usage:
```

```
specify_bsvar$get_identification()
Examples:
data(us_fiscal_lsuw)
spec = specify_bsvar$new(
    data = us_fiscal_lsuw,
    p = 4
)
spec$get_identification()
```

Method get_prior(): Returns the prior specification as the PriorBSVAR object.

Usage:

```
specify_bsvar$get_prior()
Examples:
data(us_fiscal_lsuw)
spec = specify_bsvar$new(
    data = us_fiscal_lsuw,
    p = 4
)
spec$get_prior()
```

50 specify_bsvar

```
Method get_starting_values(): Returns the starting values as the StartingValuesBSVAR
object.
    Usage:
    specify_bsvar$get_starting_values()
    Examples:
    data(us_fiscal_lsuw)
    spec = specify_bsvar$new(
        data = us_fiscal_lsuw,
        p = 4
)
    spec$$get_starting_values()$

Method clone(): The objects of this class are cloneable with this method.
    Usage:
    specify_bsvar$clone(deep = FALSE)
    Arguments:
    deep Whether to make a deep clone.
```

See Also

```
estimate, specify_posterior_bsvar
```

specify_bsvar_mix 51

```
spec = specify_bsvar$new(
  data = us_fiscal_lsuw,
  p = 4
)
spec$get_identification()
## Method `specify_bsvar$get_prior`
data(us_fiscal_lsuw)
spec = specify_bsvar$new(
  data = us_fiscal_lsuw,
  p = 4
spec$get_prior()
## -----
## Method `specify_bsvar$get_starting_values`
data(us_fiscal_lsuw)
spec = specify_bsvar$new(
  data = us_fiscal_lsuw,
)
spec$get_starting_values()
```

specify_bsvar_mix

R6 Class representing the specification of the BSVAR model with a zero-mean mixture of normals model for structural shocks.

Description

The class BSVARMIX presents complete specification for the BSVAR model with a zero-mean mixture of normals model for structural shocks.

Super class

bsvars::BSVARMSH->BSVARMIX

Public fields

p a non-negative integer specifying the autoregressive lag order of the model. identification an object IdentificationBSVARs with the identifying restrictions. prior an object PriorBSVARMIX with the prior specification.

52 specify_bsvar_mix

data_matrices an object DataMatricesBSVAR with the data matrices.

 $starting_values\ an\ object\ Starting\ Values BSVARMIX\ with\ the\ starting\ values.$

finiteM a logical value - if true a finite mixture model is estimated. Otherwise, a sparse mixture model is estimated in which M=20 and the number of visited states is estimated.

Methods

Public methods:

- specify_bsvar_mix\$new()
- specify_bsvar_mix\$clone()

Method new(): Create a new specification of the BSVAR model with a zero-mean mixture of normals model for structural shocks, BSVARMIX.

```
Usage:
specify_bsvar_mix$new(
  data,
  p = 1L,
  M,
  B,
  exogenous = NULL,
  stationary = rep(FALSE, ncol(data)),
  finiteM = TRUE
)
Arguments:
```

data a (T+p)xN matrix with time series data.

p a positive integer providing model's autoregressive lag order.

M an integer greater than 1 - the number of components of the mixture of normals.

B a logical NxN matrix containing value TRUE for the elements of the structural matrix B to be estimated and value FALSE for exclusion restrictions to be set to zero.

exogenous a (T+p)xd matrix of exogenous variables.

stationary an N logical vector - its element set to FALSE sets the prior mean for the autoregressive parameters of the Nth equation to the white noise process, otherwise to random walk.

finiteM a logical value - if true a finite mixture model is estimated. Otherwise, a sparse mixture model is estimated in which M=20 and the number of visited states is estimated.

Returns: A new complete specification for the bsvar model with a zero-mean mixture of normals model for structural shocks, BSVARMIX.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
specify_bsvar_mix$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
estimate, specify_posterior_bsvar_mix
```

Examples

```
data(us_fiscal_lsuw)
spec = specify_bsvar_mix$new(
   data = us_fiscal_lsuw,
   p = 4,
   M = 2
)
```

specify_bsvar_msh

R6 Class representing the specification of the BSVAR model with Markov Switching Heteroskedasticity.

Description

The class BSVARMSH presents complete specification for the BSVAR model with Markov Switching Heteroskedasticity.

Public fields

p a non-negative integer specifying the autoregressive lag order of the model.

identification an object IdentificationBSVARs with the identifying restrictions.

prior an object PriorBSVARMSH with the prior specification.

data_matrices an object DataMatricesBSVAR with the data matrices.

starting_values an object Starting Values BSVARMSH with the starting values.

finiteM a logical value - if true a stationary Markov switching model is estimated. Otherwise, a sparse Markov switching model is estimated in which M=20 and the number of visited states is estimated.

Methods

Public methods:

- specify_bsvar_msh\$new()
- specify_bsvar_msh\$get_data_matrices()
- specify_bsvar_msh\$get_identification()
- specify_bsvar_msh\$get_prior()
- specify_bsvar_msh\$get_starting_values()
- specify_bsvar_msh\$clone()

Method new(): Create a new specification of the BSVAR model with Markov Switching Heteroskedasticity, BSVARMSH.

```
Usage:
 specify_bsvar_msh$new(
    data,
    p = 1L
   Μ,
    В,
    exogenous = NULL,
    stationary = rep(FALSE, ncol(data)),
    finiteM = TRUE
 Arguments:
 data a (T+p)xN matrix with time series data.
 p a positive integer providing model's autoregressive lag order.
 M an integer greater than 1 - the number of Markov process' heteroskedastic regimes.
 B a logical NxN matrix containing value TRUE for the elements of the structural matrix B to be
     estimated and value FALSE for exclusion restrictions to be set to zero.
 exogenous a (T+p)xd matrix of exogenous variables.
 stationary an N logical vector - its element set to FALSE sets the prior mean for the autore-
     gressive parameters of the Nth equation to the white noise process, otherwise to random
     walk.
 finiteM a logical value - if true a stationary Markov switching model is estimated. Otherwise,
     a sparse Markov switching model is estimated in which M=20 and the number of visited
     states is estimated.
          A new complete specification for the bsvar model with Markov Switching Het-
 eroskedasticity, BSVARMSH.
Method get_data_matrices(): Returns the data matrices as the DataMatricesBSVAR object.
 Usage:
 specify_bsvar_msh$get_data_matrices()
 Examples:
 data(us_fiscal_lsuw)
 spec = specify_bsvar_msh$new(
     data = us_fiscal_lsuw,
     p = 4,
     M = 2
 spec$get_data_matrices()
Method get_identification(): Returns the identifying restrictions as the IdentificationB-
SVARs object.
 Usage:
 specify_bsvar_msh$get_identification()
 Examples:
```

```
data(us_fiscal_lsuw)
 spec = specify_bsvar_msh$new(
    data = us_fiscal_lsuw,
    p = 4,
    M = 2
 )
 spec$get_identification()
Method get_prior(): Returns the prior specification as the PriorBSVARMSH object.
 specify_bsvar_msh$get_prior()
 Examples:
 data(us_fiscal_lsuw)
 spec = specify_bsvar_msh$new(
    data = us_fiscal_lsuw,
    p = 4,
    M = 2
 )
 spec$get_prior()
Method get_starting_values(): Returns the starting values as the StartingValuesBSVARMSH
object.
 Usage:
 specify_bsvar_msh$get_starting_values()
 Examples:
 data(us_fiscal_lsuw)
 spec = specify_bsvar_msh$new(
    data = us_fiscal_lsuw,
    p = 4,
    M = 2
 spec$get_starting_values()
Method clone(): The objects of this class are cloneable with this method.
 Usage:
 specify_bsvar_msh$clone(deep = FALSE)
 Arguments:
 deep Whether to make a deep clone.
```

See Also

estimate, specify_posterior_bsvar_msh

```
data(us_fiscal_lsuw)
spec = specify_bsvar_msh$new(
  data = us_fiscal_lsuw,
  p = 4,
  M = 2
)
## -----
## Method `specify_bsvar_msh$get_data_matrices`
data(us_fiscal_lsuw)
spec = specify_bsvar_msh$new(
  data = us_fiscal_lsuw,
  p = 4,
  M = 2
)
spec$get_data_matrices()
## Method `specify_bsvar_msh$get_identification`
data(us_fiscal_lsuw)
spec = specify_bsvar_msh$new(
  data = us_fiscal_lsuw,
  p = 4,
  M = 2
spec$get_identification()
## Method `specify_bsvar_msh$get_prior`
## -----
data(us_fiscal_lsuw)
spec = specify_bsvar_msh$new(
  data = us_fiscal_lsuw,
  p = 4,
  M = 2
)
spec$get_prior()
## Method `specify_bsvar_msh$get_starting_values`
```

```
data(us_fiscal_lsuw)
spec = specify_bsvar_msh$new(
   data = us_fiscal_lsuw,
   p = 4,
   M = 2
)
spec$get_starting_values()
```

specify_bsvar_sv

R6 Class representing the specification of the BSVAR model with Stochastic Volatility heteroskedasticity.

Description

The class BSVARSV presents complete specification for the BSVAR model with Stochastic Volatility heteroskedasticity.

Public fields

p a non-negative integer specifying the autoregressive lag order of the model.

identification an object IdentificationBSVARs with the identifying restrictions.

prior an object PriorBSVARSV with the prior specification.

data_matrices an object DataMatricesBSVAR with the data matrices.

starting_values an object Starting Values BSVARSV with the starting values.

centred_sv a logical value - if true a centred parameterisation of the Stochastic Volatility process is estimated. Otherwise, its non-centred parameterisation is estimated. See Lütkepohl, Shang, Uzeda, Woźniak (2022) for more info.

Methods

Public methods:

- specify_bsvar_sv\$new()
- specify_bsvar_sv\$get_data_matrices()
- specify_bsvar_sv\$get_identification()
- specify_bsvar_sv\$get_prior()
- specify_bsvar_sv\$get_starting_values()
- specify_bsvar_sv\$clone()

Method new(): Create a new specification of the BSVAR model with Stochastic Volatility heteroskedasticity, BSVARSV.

Usage:

```
specify_bsvar_sv$new(
    data,
    p = 1L
   Β,
    exogenous = NULL,
    centred_sv = FALSE,
    stationary = rep(FALSE, ncol(data))
 )
 Arguments:
 data a (T+p)xN matrix with time series data.
 p a positive integer providing model's autoregressive lag order.
 B a logical NxN matrix containing value TRUE for the elements of the structural matrix B to be
     estimated and value FALSE for exclusion restrictions to be set to zero.
 exogenous a (T+p)xd matrix of exogenous variables.
 centred_sv a logical value. If FALSE a non-centred Stochastic Volatility processes for condi-
     tional variances are estimated. Otherwise, a centred process is estimated.
 stationary an N logical vector - its element set to FALSE sets the prior mean for the autore-
     gressive parameters of the Nth equation to the white noise process, otherwise to random
     walk.
 Returns:
          A new complete specification for the bsvar model with Stochastic Volatility het-
 eroskedasticity, BSVARSV.
Method get_data_matrices(): Returns the data matrices as the DataMatricesBSVAR object.
 specify_bsvar_sv$get_data_matrices()
 Examples:
 data(us_fiscal_lsuw)
 spec = specify_bsvar_sv$new(
     data = us_fiscal_lsuw,
 spec$get_data_matrices()
Method get_identification(): Returns the identifying restrictions as the IdentificationB-
SVARs object.
 Usage:
 specify_bsvar_sv$get_identification()
 Examples:
 data(us_fiscal_lsuw)
 spec = specify_bsvar_sv$new(
     data = us_fiscal_lsuw,
     p = 4
```

)

spec\$get_identification()

```
Method get_prior(): Returns the prior specification as the PriorBSVARSV object.
       specify_bsvar_sv$get_prior()
       Examples:
       data(us_fiscal_lsuw)
       spec = specify_bsvar_sv$new(
          data = us_fiscal_lsuw,
          p = 4
       )
       spec$get_prior()
     Method get_starting_values(): Returns the starting values as the StartingValuesBSVARSV
     object.
       Usage:
       specify_bsvar_sv$get_starting_values()
       Examples:
       data(us_fiscal_lsuw)
       spec = specify_bsvar_sv$new(
          data = us_fiscal_lsuw,
       )
       spec$get_starting_values()
     Method clone(): The objects of this class are cloneable with this method.
       Usage:
       specify_bsvar_sv$clone(deep = FALSE)
       Arguments:
       deep Whether to make a deep clone.
See Also
    estimate, specify_posterior_bsvar_sv
Examples
   data(us_fiscal_lsuw)
   spec = specify_bsvar_sv$new(
      data = us_fiscal_lsuw,
      p = 4
    ## Method `specify_bsvar_sv$get_data_matrices`
```

```
data(us_fiscal_lsuw)
spec = specify_bsvar_sv$new(
  data = us_fiscal_lsuw,
  p = 4
)
spec$get_data_matrices()
## Method `specify_bsvar_sv$get_identification`
data(us_fiscal_lsuw)
spec = specify_bsvar_sv$new(
  data = us_fiscal_lsuw,
  p = 4
)
spec$get_identification()
## -----
## Method `specify_bsvar_sv$get_prior`
## -----
data(us_fiscal_lsuw)
spec = specify_bsvar_sv$new(
  data = us_fiscal_lsuw,
  p = 4
)
spec$get_prior()
## -----
## Method `specify_bsvar_sv$get_starting_values`
data(us_fiscal_lsuw)
spec = specify_bsvar_sv$new(
  data = us_fiscal_lsuw,
  p = 4
)
spec$get_starting_values()
```

specify_data_matrices 61

Description

The class DataMatricesBSVAR presents the data matrices of dependent variables, Y, and regressors, X, for the homoskedastic bsvar model.

Public fields

```
Y an NxT matrix of dependent variables, Y. X an KxT matrix of regressors, X.
```

Methods

Public methods:

```
• specify_data_matrices$new()
```

- specify_data_matrices\$get_data_matrices()
- specify_data_matrices\$clone()

Method new(): Create new data matrices DataMatricesBSVAR.

```
Usage:
specify_data_matrices$new(data, p = 1L, exogenous = NULL)
Arguments:
data a (T+p)xN matrix with time series data.
p a positive integer providing model's autoregressive lag order.
exogenous a (T+p)xd matrix of exogenous variables. This matrix should not include a constant term.
```

Returns: New data matrices DataMatricesBSVAR.

Method get_data_matrices(): Returns the data matrices DataMatricesBSVAR as a list.

```
Usage:
specify_data_matrices$get_data_matrices()
Examples:
data(us_fiscal_lsuw)
YX = specify_data_matrices$new(data = us_fiscal_lsuw, p = 4)
YX$get_data_matrices()
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
specify_data_matrices$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

Examples

```
data(us_fiscal_lsuw)
YX = specify_data_matrices$new(data = us_fiscal_lsuw, p = 4)
dim(YX$Y); dim(YX$X)

## -------
## Method `specify_data_matrices$get_data_matrices`
## -------
data(us_fiscal_lsuw)
YX = specify_data_matrices$new(data = us_fiscal_lsuw, p = 4)
YX$get_data_matrices()
```

```
specify_identification_bsvars
```

R6 Class Representing IdentificationBSVARs

Description

The class IdentificationBSVARs presents the identifying restrictions for the bsvar models.

Public fields

VB a list of N matrices determining the unrestricted elements of matrix B.

Methods

Public methods:

- specify_identification_bsvars\$new()
- specify_identification_bsvars\$get_identification()
- specify_identification_bsvars\$set_identification()
- specify_identification_bsvars\$clone()

Method new(): Create new identifying restrictions IdentificationBSVARs.

```
Usage:
```

```
specify_identification_bsvars$new(N, B)
```

Arguments:

N a positive integer - the number of dependent variables in the model.

B a logical NxN matrix containing value TRUE for the elements of the structural matrix B to be estimated and value FALSE for exclusion restrictions to be set to zero.

Returns: Identifying restrictions IdentificationBSVARs.

Method get_identification(): Returns the elements of the identification pattern IdentificationBSVARs as a list.

```
Usage:
 specify_identification_bsvars$get_identification()
 Examples:
       = matrix(c(TRUE,TRUE,FALSE,FALSE,TRUE,FALSE,TRUE,TRUE), 3, 3); B
 spec = specify_identification_bsvars$new(N = 3, B = B)
 spec$get_identification()
Method set_identification(): Set new starting values Starting Values BSVAR.
 specify_identification_bsvars$set_identification(N, B)
 Arguments:
 N a positive integer - the number of dependent variables in the model.
 B a logical NxN matrix containing value TRUE for the elements of the structural matrix B to be
     estimated and value FALSE for exclusion restrictions to be set to zero.
 Examples:
 spec = specify_identification_bsvars$new(N = 3) # specify a model with the default option
       = matrix(c(TRUE, TRUE, TRUE, FALSE, FALSE, TRUE, FALSE, TRUE, TRUE), 3, 3); B
 spec$set_identification(N = 3, B = B) # modify an existing specification
 spec$get_identification()
                                            # check the outcome
Method clone(): The objects of this class are cloneable with this method.
 Usage:
 specify_identification_bsvars$clone(deep = FALSE)
 Arguments:
 deep Whether to make a deep clone.
```

```
spec = specify_identification_bsvars$new(N = 3) # specify a model with the default option
B = matrix(c(TRUE,TRUE,FALSE,FALSE,TRUE,FALSE,TRUE,TRUE), 3, 3); B
spec$set_identification(N = 3, B = B) # modify an existing specification
spec$get_identification() # check the outcome
```

```
specify_posterior_bsvar
```

R6 Class Representing PosteriorBSVAR

Description

The class PosteriorBSVAR contains posterior output and the specification including the last MCMC draw for the homoskedastic bsvar model. Note that due to the thinning of the MCMC output the starting value in element last_draw might not be equal to the last draw provided in element posterior.

Public fields

last_draw an object of class BSVAR with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

posterior a list containing Bayesian estimation output collected in elements an NxNxS array B, an NxKxS array A, and a 5xS matrix hyper.

Methods

Public methods:

- specify_posterior_bsvar\$new()
- specify_posterior_bsvar\$get_posterior()
- specify_posterior_bsvar\$get_last_draw()
- specify_posterior_bsvar\$is_normalised()
- specify_posterior_bsvar\$set_normalised()
- specify_posterior_bsvar\$clone()

Method new(): Create a new posterior output PosteriorBSVAR.

Usage:

```
specify_posterior_bsvar$new(specification_bsvar, posterior_bsvar)
```

Arguments

specification_bsvar an object of class BSVAR with the last draw of the current MCMC run as the starting value.

posterior_bsvar a list containing Bayesian estimation output collected in elements an NxNxS array B, an NxKxS array A, and a 5xS matrix hyper.

Returns: A posterior output PosteriorBSVAR.

specify_posterior_bsvar 65

Method get_posterior(): Returns a list containing Bayesian estimation output collected in elements an NxNxS array B, an NxKxS array A, and a 5xS matrix hyper.

```
Usage:
specify_posterior_bsvar$get_posterior()
Examples:
data(us_fiscal_lsuw)
specification = specify_bsvar$new(us_fiscal_lsuw)
set.seed(123)
estimate = estimate(specification, 50)
estimate$get_posterior()
```

Method get_last_draw(): Returns an object of class BSVAR with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

```
Usage:
specify_posterior_bsvar$get_last_draw()
Examples:
data(us_fiscal_lsuw)

# specify the model and set seed
specification = specify_bsvar$new(us_fiscal_lsuw, p = 4)
set.seed(123)

# run the burn-in
burn_in = estimate(specification, 10)

# estimate the model
posterior = estimate(burn_in, 10)
```

Method is_normalised(): Returns TRUE if the posterior has been normalised using normalise_posterior() and FALSE otherwise.

```
Usage:
specify_posterior_bsvar$is_normalised()
Examples:
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar$new(us_fiscal_lsuw, p = 4)
set.seed(123)
# estimate the model
posterior = estimate(specification, 10, thin = 1)
```

```
# check normalisation status beforehand
 posterior$is_normalised()
 # normalise the posterior
 BB
            = posterior$last_draw$starting_values$B
                                                          # get the last draw of B
 B_hat
            = diag((-1) * sign(diag(BB))) %*% BB
                                                       # set negative diagonal elements
 normalise_posterior(posterior, B_hat)
                                                       # draws in posterior are normalised
 # check normalisation status afterwards
 posterior$is_normalised()
Method set_normalised(): Sets the private indicator normalised to TRUE.
 Usage:
 specify_posterior_bsvar$set_normalised(value)
 Arguments:
 value (optional) a logical value to be passed to indicator normalised.
 Examples:
 # This is an internal function that is run while executing normalise_posterior()
 # Observe its working by analysing the workflow:
 # upload data
 data(us_fiscal_lsuw)
 # specify the model and set seed
 specification = specify_bsvar$new(us_fiscal_lsuw, p = 4)
 set.seed(123)
 # estimate the model
 posterior = estimate(specification, 10, thin = 1)
 # check normalisation status beforehand
 posterior$is_normalised()
 # normalise the posterior
 BB
            = posterior$last_draw$starting_values$B
                                                          # get the last draw of B
 B_hat
            = diag(sign(diag(BB))) %*% BB
                                                     # set positive diagonal elements
 normalise_posterior(posterior, B_hat)
                                                       # draws in posterior are normalised
 # check normalisation status afterwards
 posterior$is_normalised()
Method clone(): The objects of this class are cloneable with this method.
 Usage:
 specify_posterior_bsvar$clone(deep = FALSE)
 Arguments:
 deep Whether to make a deep clone.
```

See Also

```
estimate, specify_bsvar
```

```
# This is a function that is used within estimate()
data(us_fiscal_lsuw)
specification = specify_bsvar$new(us_fiscal_lsuw, p = 4)
set.seed(123)
estimate
           = estimate(specification, 50)
class(estimate)
## -----
## Method `specify_posterior_bsvar$get_posterior`
data(us_fiscal_lsuw)
specification = specify_bsvar$new(us_fiscal_lsuw)
set.seed(123)
estimate
           = estimate(specification, 50)
estimate$get_posterior()
## -----
## Method `specify_posterior_bsvar$get_last_draw`
## -----
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar$new(us_fiscal_lsuw, p = 4)
set.seed(123)
# run the burn-in
burn_in = estimate(specification, 10)
# estimate the model
posterior = estimate(burn_in, 10)
## -----
## Method `specify_posterior_bsvar$is_normalised`
## -----
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar$new(us_fiscal_lsuw, p = 4)
set.seed(123)
```

```
# estimate the model
              = estimate(specification, 10, thin = 1)
posterior
# check normalisation status beforehand
posterior$is_normalised()
# normalise the posterior
             = posterior$last_draw$starting_values$B
                                                        # get the last draw of B
B_hat
            = diag((-1) * sign(diag(BB))) %*% BB
                                                      # set negative diagonal elements
normalise_posterior(posterior, B_hat)
                                                    # draws in posterior are normalised
# check normalisation status afterwards
posterior$is_normalised()
## Method `specify_posterior_bsvar$set_normalised`
## -----
# This is an internal function that is run while executing normalise_posterior()
# Observe its working by analysing the workflow:
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar$new(us_fiscal_lsuw, p = 4)
set.seed(123)
# estimate the model
posterior = estimate(specification, 10, thin = 1)
# check normalisation status beforehand
posterior$is_normalised()
# normalise the posterior
RR
             = posterior$last_draw$starting_values$B
                                                        # get the last draw of B
                                                      # set positive diagonal elements
B_hat
            = diag(sign(diag(BB))) %*% BB
                                                    # draws in posterior are normalised
normalise_posterior(posterior, B_hat)
# check normalisation status afterwards
posterior$is_normalised()
```

Description

The class PosteriorBSVARMIX contains posterior output and the specification including the last MCMC draw for the bsvar model with a zero-mean mixture of normals model for structural shocks. Note that due to the thinning of the MCMC output the starting value in element last_draw might not be equal to the last draw provided in element posterior.

Public fields

last_draw an object of class BSVARMIX with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

posterior a list containing Bayesian estimation output.

Methods

Public methods:

```
• specify_posterior_bsvar_mix$new()
```

```
• specify_posterior_bsvar_mix$get_posterior()
```

```
• specify_posterior_bsvar_mix$get_last_draw()
```

```
• specify_posterior_bsvar_mix$is_normalised()
```

- specify_posterior_bsvar_mix\$set_normalised()
- specify_posterior_bsvar_mix\$clone()

Method new(): Create a new posterior output PosteriorBSVARMIX.

```
Usage:
```

```
specify_posterior_bsvar_mix$new(specification_bsvar, posterior_bsvar)
```

Arguments:

specification_bsvar an object of class BSVARMIX with the last draw of the current MCMC run as the starting value.

posterior_bsvar a list containing Bayesian estimation output.

Returns: A posterior output PosteriorBSVARMIX.

Method get_posterior(): Returns a list containing Bayesian estimation output.

```
Usage:
```

```
specify_posterior_bsvar_mix$get_posterior()

Examples:
data(us_fiscal_lsuw)
specification = specify_bsvar_mix$new(us_fiscal_lsuw, M = 2)
set.seed(123)
estimate = estimate(specification, 10, thin = 1)
estimate$get_posterior()
```

Method get_last_draw(): Returns an object of class BSVARMIX with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

Usage:

specify_posterior_bsvar_mix\$set_normalised(value)

```
Usage:
 specify_posterior_bsvar_mix$get_last_draw()
 Examples:
 data(us_fiscal_lsuw)
 # specify the model and set seed
 specification = specify_bsvar_mix$new(us_fiscal_lsuw, p = 4, M = 2)
 # run the burn-in
 set.seed(123)
 burn_in
                 = estimate(specification, 10, thin = 2)
 # estimate the model
 posterior
                = estimate(burn_in, 10, thin = 2)
Method is_normalised(): Returns TRUE if the posterior has been normalised using normalise_posterior()
and FALSE otherwise.
 Usage:
 specify_posterior_bsvar_mix$is_normalised()
 Examples:
 # upload data
 data(us_fiscal_lsuw)
 # specify the model and set seed
 specification = specify_bsvar_mix$new(us_fiscal_lsuw, p = 4, M = 2)
 # estimate the model
 set.seed(123)
                = estimate(specification, 10, thin = 1)
 posterior
 # check normalisation status beforehand
 posterior$is_normalised()
 # normalise the posterior
                                                         # get the last draw of B
            = posterior$last_draw$starting_values$B
 B_hat
            = diag((-1) * sign(diag(BB))) %*% BB
                                                      # set negative diagonal elements
 normalise_posterior(posterior, B_hat)
                                                      # draws in posterior are normalised
 # check normalisation status afterwards
 posterior$is_normalised()
Method set_normalised(): Sets the private indicator normalised to TRUE.
```

```
Arguments:
  value (optional) a logical value to be passed to indicator normalised.
  Examples:
   # This is an internal function that is run while executing normalise_posterior()
   # Observe its working by analysing the workflow:
  # upload data
  data(us_fiscal_lsuw)
   # specify the model and set seed
   specification = specify_bsvar_mix$new(us_fiscal_lsuw, p = 4, M = 2)
   set.seed(123)
  # estimate the model
  posterior
                  = estimate(specification, 10, thin = 1)
  # check normalisation status beforehand
  posterior$is_normalised()
  # normalise the posterior
  BB
             = posterior$last_draw$starting_values$B
                                                           # get the last draw of B
  B hat
              = diag(sign(diag(BB))) %*% BB
                                                      # set positive diagonal elements
  normalise_posterior(posterior, B_hat)
                                                        # draws in posterior are normalised
  # check normalisation status afterwards
  posterior$is_normalised()
 Method clone(): The objects of this class are cloneable with this method.
   Usage:
   specify_posterior_bsvar_mix$clone(deep = FALSE)
  Arguments:
   deep Whether to make a deep clone.
estimate, specify_bsvar_mix
```

See Also

```
# This is a function that is used within estimate()
data(us_fiscal_lsuw)
specification = specify_bsvar_mix$new(us_fiscal_lsuw, p = 4, M = 2)
set.seed(123)
estimate
              = estimate(specification, 10, thin = 1)
class(estimate)
```

```
## Method `specify_posterior_bsvar_mix$get_posterior`
data(us_fiscal_lsuw)
specification = specify_bsvar_mix$new(us_fiscal_lsuw, M = 2)
set.seed(123)
           = estimate(specification, 10, thin = 1)
estimate$get_posterior()
## -----
## Method `specify_posterior_bsvar_mix$get_last_draw`
## -----
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_mix$new(us_fiscal_lsuw, p = 4, M = 2)
# run the burn-in
set.seed(123)
             = estimate(specification, 10, thin = 2)
burn_in
# estimate the model
posterior = estimate(burn_in, 10, thin = 2)
## Method `specify_posterior_bsvar_mix$is_normalised`
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_mix$new(us_fiscal_lsuw, p = 4, M = 2)
# estimate the model
set.seed(123)
             = estimate(specification, 10, thin = 1)
posterior
# check normalisation status beforehand
posterior$is_normalised()
# normalise the posterior
BB
            = posterior$last_draw$starting_values$B
                                                       # get the last draw of B
           = diag((-1) * sign(diag(BB))) %*% BB
                                                    # set negative diagonal elements
normalise_posterior(posterior, B_hat)
                                                  # draws in posterior are normalised
# check normalisation status afterwards
posterior$is_normalised()
```

```
## Method `specify_posterior_bsvar_mix$set_normalised`
# This is an internal function that is run while executing normalise_posterior()
# Observe its working by analysing the workflow:
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_mix$new(us_fiscal_lsuw, p = 4, M = 2)
set.seed(123)
# estimate the model
              = estimate(specification, 10, thin = 1)
# check normalisation status beforehand
posterior$is_normalised()
# normalise the posterior
                                                          # get the last draw of B
             = posterior$last_draw$starting_values$B
            = diag(sign(diag(BB))) %*% BB
                                                        # set positive diagonal elements
B_hat
normalise_posterior(posterior, B_hat)
                                                      # draws in posterior are normalised
# check normalisation status afterwards
posterior$is_normalised()
```

```
specify_posterior_bsvar_msh
```

R6 Class Representing PosteriorBSVARMSH

Description

The class PosteriorBSVARMSH contains posterior output and the specification including the last MCMC draw for the bsvar model with Markov Switching Heteroskedasticity. Note that due to the thinning of the MCMC output the starting value in element last_draw might not be equal to the last draw provided in element posterior.

Public fields

last_draw an object of class BSVARMSH with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

posterior a list containing Bayesian estimation output.

Methods

```
Public methods:
```

```
• specify_posterior_bsvar_msh$new()
```

- specify_posterior_bsvar_msh\$get_posterior()
- specify_posterior_bsvar_msh\$get_last_draw()
- specify_posterior_bsvar_msh\$is_normalised()
- specify_posterior_bsvar_msh\$set_normalised()
- specify_posterior_bsvar_msh\$clone()

Method new(): Create a new posterior output PosteriorBSVARMSH.

```
Usage:
```

```
specify_posterior_bsvar_msh$new(specification_bsvar, posterior_bsvar)
```

Arguments:

specification_bsvar an object of class BSVARMSH with the last draw of the current MCMC run as the starting value.

posterior_bsvar a list containing Bayesian estimation output.

Returns: A posterior output PosteriorBSVARMSH.

Method get_posterior(): Returns a list containing Bayesian estimation output.

```
Usage:
```

```
specify_posterior_bsvar_msh$get_posterior()

Examples:
data(us_fiscal_lsuw)
specification = specify_bsvar_msh$new(us_fiscal_lsuw, M = 2)
set.seed(123)
estimate = estimate(specification, 10, thin = 1)
estimate$get_posterior()
```

Method get_last_draw(): Returns an object of class BSVARMSH with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

```
Usage:
```

```
specify_posterior_bsvar_msh$get_last_draw()
Examples:
data(us_fiscal_lsuw)

# specify the model and set seed
specification = specify_bsvar_msh$new(us_fiscal_lsuw, p = 4, M = 2)

# run the burn-in
set.seed(123)
burn_in = estimate(specification, 10, thin = 2)
```

set.seed(123)

```
# estimate the model
 posterior
                = estimate(burn_in, 10, thin = 2)
Method is_normalised(): Returns TRUE if the posterior has been normalised using normalise_posterior()
and FALSE otherwise.
 Usage:
 specify_posterior_bsvar_msh$is_normalised()
 Examples:
 # upload data
 data(us_fiscal_lsuw)
 # specify the model and set seed
 specification = specify_bsvar_msh$new(us_fiscal_lsuw, p = 4, M = 2)
 # estimate the model
 set.seed(123)
 posterior
                 = estimate(specification, 10, thin = 1)
 # check normalisation status beforehand
 posterior$is_normalised()
 # normalise the posterior
 BB
            = posterior$last_draw$starting_values$B
                                                         # get the last draw of B
                                                       # set negative diagonal elements
 B hat
            = diag((-1) * sign(diag(BB))) %*% BB
 normalise_posterior(posterior, B_hat)
                                                       # draws in posterior are normalised
 # check normalisation status afterwards
 posterior$is_normalised()
Method set_normalised(): Sets the private indicator normalised to TRUE.
 Usage:
 specify_posterior_bsvar_msh$set_normalised(value)
 Arguments:
 value (optional) a logical value to be passed to indicator normalised.
 Examples:
 # This is an internal function that is run while executing normalise_posterior()
 # Observe its working by analysing the workflow:
 # upload data
 data(us_fiscal_lsuw)
 # specify the model and set seed
```

specification = specify_bsvar_msh\$new(us_fiscal_lsuw, p = 4, M = 2)

```
# estimate the model
 posterior
                 = estimate(specification, 10, thin = 1)
 # check normalisation status beforehand
 posterior$is_normalised()
 # normalise the posterior
            = posterior$last_draw$starting_values$B
                                                         # get the last draw of B
 B_hat
            = diag(sign(diag(BB))) %*% BB # set positive diagonal elements
 normalise_posterior(posterior, B_hat)
                                                      # draws in posterior are normalised
 # check normalisation status afterwards
 posterior$is_normalised()
Method clone(): The objects of this class are cloneable with this method.
 specify_posterior_bsvar_msh$clone(deep = FALSE)
 Arguments:
 deep Whether to make a deep clone.
```

See Also

```
estimate, specify_bsvar_msh
```

```
# This is a function that is used within estimate()
data(us_fiscal_lsuw)
specification = specify_bsvar_msh$new(us_fiscal_lsuw, p = 4, M = 2)
set.seed(123)
             = estimate(specification, 10, thin = 1)
estimate
class(estimate)
## -----
## Method `specify_posterior_bsvar_msh$get_posterior`
data(us_fiscal_lsuw)
specification = specify_bsvar_msh$new(us_fiscal_lsuw, M = 2)
set.seed(123)
             = estimate(specification, 10, thin = 1)
estimate
estimate$get_posterior()
## Method `specify_posterior_bsvar_msh$get_last_draw`
```

```
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_msh$new(us_fiscal_lsuw, p = 4, M = 2)
# run the burn-in
set.seed(123)
burn_in
              = estimate(specification, 10, thin = 2)
# estimate the model
posterior = estimate(burn_in, 10, thin = 2)
## -----
## Method `specify_posterior_bsvar_msh$is_normalised`
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_msh$new(us_fiscal_lsuw, p = 4, M = 2)
# estimate the model
set.seed(123)
posterior
              = estimate(specification, 10, thin = 1)
# check normalisation status beforehand
posterior$is_normalised()
# normalise the posterior
BB
             = posterior$last_draw$starting_values$B
                                                         # get the last draw of B
            = diag((-1) * sign(diag(BB))) %*% BB
                                                      # set negative diagonal elements
normalise_posterior(posterior, B_hat)
                                                    # draws in posterior are normalised
# check normalisation status afterwards
posterior$is_normalised()
## Method `specify_posterior_bsvar_msh$set_normalised`
# This is an internal function that is run while executing normalise_posterior()
# Observe its working by analysing the workflow:
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_msh$new(us_fiscal_lsuw, p = 4, M = 2)
set.seed(123)
```

```
# estimate the model
posterior
              = estimate(specification, 10, thin = 1)
# check normalisation status beforehand
posterior$is_normalised()
# normalise the posterior
BB
             = posterior$last_draw$starting_values$B
                                                           # get the last draw of B
             = diag(sign(diag(BB))) %*% BB
B_hat
                                                        # set positive diagonal elements
                                                      # draws in posterior are normalised
normalise_posterior(posterior, B_hat)
# check normalisation status afterwards
posterior$is_normalised()
```

```
specify_posterior_bsvar_sv
```

R6 Class Representing PosteriorBSVARSV

Description

The class PosteriorBSVARSV contains posterior output and the specification including the last MCMC draw for the bsvar model with Stochastic Volatility heteroskedasticity. Note that due to the thinning of the MCMC output the starting value in element last_draw might not be equal to the last draw provided in element posterior.

Public fields

last_draw an object of class BSVARSV with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

posterior a list containing Bayesian estimation output.

Methods

Public methods:

- specify_posterior_bsvar_sv\$new()
- specify_posterior_bsvar_sv\$get_posterior()
- specify_posterior_bsvar_sv\$get_last_draw()
- specify_posterior_bsvar_sv\$is_normalised()
- specify_posterior_bsvar_sv\$set_normalised()
- specify_posterior_bsvar_sv\$clone()

Method new(): Create a new posterior output PosteriorBSVARSV.

```
Usage:
```

```
specify_posterior_bsvar_sv$new(specification_bsvar, posterior_bsvar)
```

Arguments:

specification_bsvar an object of class BSVARSV with the last draw of the current MCMC run as the starting value.

posterior_bsvar a list containing Bayesian estimation output.

Returns: A posterior output PosteriorBSVARSV.

Method get_posterior(): Returns a list containing Bayesian estimation.

```
Usage:
specify_posterior_bsvar_sv$get_posterior()
Examples:
data(us_fiscal_lsuw)
specification = specify_bsvar_sv$new(us_fiscal_lsuw)
set.seed(123)
estimate = estimate(specification, 5, thin = 1)
estimate$get_posterior()
```

Method get_last_draw(): Returns an object of class BSVARSV with the last draw of the current MCMC run as the starting value to be passed to the continuation of the MCMC estimation using estimate().

```
Usage:
specify_posterior_bsvar_sv$get_last_draw()
Examples:
data(us_fiscal_lsuw)

# specify the model and set seed
specification = specify_bsvar_sv$new(us_fiscal_lsuw, p = 4)
set.seed(123)

# run the burn-in
burn_in = estimate(specification, 5, thin = 1)

# estimate the model
posterior = estimate(burn_in, 5, thin = 1)
```

Method is_normalised(): Returns TRUE if the posterior has been normalised using normalise_posterior() and FALSE otherwise.

```
Usage:
specify_posterior_bsvar_sv$is_normalised()
Examples:
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
```

```
specification = specify_bsvar_sv$new(us_fiscal_lsuw, p = 4)
 # estimate the model
 set.seed(123)
 posterior
                 = estimate(specification, 5, thin = 1)
 # check normalisation status beforehand
 posterior$is_normalised()
 # normalise the posterior
 BB
            = posterior$last_draw$starting_values$B
                                                         # get the last draw of B
 B_hat
                                                      # set negative diagonal elements
            = diag((-1) * sign(diag(BB))) %*% BB
                                                      # draws in posterior are normalised
 normalise_posterior(posterior, B_hat)
 # check normalisation status afterwards
 posterior$is_normalised()
Method set_normalised(): Sets the private indicator normalised to TRUE.
 Usage:
 specify_posterior_bsvar_sv$set_normalised(value)
 Arguments:
 value (optional) a logical value to be passed to indicator normalised.
 Examples:
 # This is an internal function that is run while executing normalise_posterior()
 # Observe its working by analysing the workflow:
 # upload data
 data(us_fiscal_lsuw)
 # specify the model and set seed
 specification = specify_bsvar_sv$new(us_fiscal_lsuw, p = 4)
 # estimate the model
 set.seed(123)
 posterior
                 = estimate(specification, 5, thin = 1)
 # check normalisation status beforehand
 posterior$is_normalised()
 # normalise the posterior
                                                         # get the last draw of B
 BB
            = posterior$last_draw$starting_values$B
 B_hat
            = diag(sign(diag(BB))) %*% BB
                                                    # set positive diagonal elements
 normalise_posterior(posterior, B_hat)
                                                      # draws in posterior are normalised
 # check normalisation status afterwards
 posterior$is_normalised()
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
specify_posterior_bsvar_sv$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
estimate, specify_bsvar_sv
```

```
# This is a function that is used within estimate()
data(us_fiscal_lsuw)
specification = specify_bsvar_sv$new(us_fiscal_lsuw, p = 4)
set.seed(123)
estimate
           = estimate(specification, 5, thin = 1)
class(estimate)
## Method `specify_posterior_bsvar_sv$get_posterior`
data(us_fiscal_lsuw)
specification = specify_bsvar_sv$new(us_fiscal_lsuw)
set.seed(123)
           = estimate(specification, 5, thin = 1)
estimate
estimate$get_posterior()
## -----
## Method `specify_posterior_bsvar_sv$get_last_draw`
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_sv$new(us_fiscal_lsuw, p = 4)
set.seed(123)
# run the burn-in
burn_in = estimate(specification, 5, thin = 1)
# estimate the model
posterior = estimate(burn_in, 5, thin = 1)
## Method `specify_posterior_bsvar_sv$is_normalised`
```

```
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_sv$new(us_fiscal_lsuw, p = 4)
# estimate the model
set.seed(123)
posterior
              = estimate(specification, 5, thin = 1)
# check normalisation status beforehand
posterior$is_normalised()
# normalise the posterior
BB
             = posterior$last_draw$starting_values$B
                                                         # get the last draw of B
B hat
            = diag((-1) * sign(diag(BB))) %*% BB
                                                      # set negative diagonal elements
normalise_posterior(posterior, B_hat)
                                                    # draws in posterior are normalised
# check normalisation status afterwards
posterior$is_normalised()
## Method `specify_posterior_bsvar_sv$set_normalised`
## -----
# This is an internal function that is run while executing normalise_posterior()
# Observe its working by analysing the workflow:
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_sv$new(us_fiscal_lsuw, p = 4)
# estimate the model
set.seed(123)
              = estimate(specification, 5, thin = 1)
posterior
# check normalisation status beforehand
posterior$is_normalised()
# normalise the posterior
BB
             = posterior$last_draw$starting_values$B
                                                         # get the last draw of B
B_hat
            = diag(sign(diag(BB))) %*% BB
                                                      # set positive diagonal elements
normalise_posterior(posterior, B_hat)
                                                    # draws in posterior are normalised
# check normalisation status afterwards
posterior$is_normalised()
```

specify_prior_bsvar 83

specify_prior_bsvar

R6 Class Representing PriorBSVAR

Description

The class PriorBSVAR presents a prior specification for the homoskedastic bsvar model.

Public fields

- A an NxK matrix, the mean of the normal prior distribution for the parameter matrix A.
- A_V_inv a KxK precision matrix of the normal prior distribution for each of the row of the parameter matrix A. This precision matrix is equation invariant.
- B_V_inv an NxN precision matrix of the generalised-normal prior distribution for the structural matrix B. This precision matrix is equation invariant.
- B_nu a positive integer greater of equal than N, a shape parameter of the generalised-normal prior distribution for the structural matrix B.
- hyper_nu_B a positive scalar, the shape parameter of the inverted-gamma 2 prior for the overall shrinkage parameter for matrix B.
- hyper_a_B a positive scalar, the shape parameter of the gamma prior for the second-level hierarchy for the overall shrinkage parameter for matrix B.
- hyper_s_BB a positive scalar, the scale parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix B.
- hyper_nu_BB a positive scalar, the shape parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix B.
- hyper_nu_A a positive scalar, the shape parameter of the inverted-gamma 2 prior for the overall shrinkage parameter for matrix A.
- hyper_a_A a positive scalar, the shape parameter of the gamma prior for the second-level hierarchy for the overall shrinkage parameter for matrix A.
- hyper_s_AA a positive scalar, the scale parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix A.
- hyper_nu_AA a positive scalar, the shape parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix A.

Methods

Public methods:

- specify_prior_bsvar\$new()
- specify_prior_bsvar\$get_prior()
- specify_prior_bsvar\$clone()

Method new(): Create a new prior specification PriorBSVAR.

```
Usage:
```

```
specify_prior_bsvar$new(N, p, d = 0, stationary = rep(FALSE, N))
```

84 specify_prior_bsvar

```
Arguments:
 N a positive integer - the number of dependent variables in the model.
 p a positive integer - the autoregressive lag order of the SVAR model.
 d a positive integer - the number of exogenous variables in the model.
 stationary an N logical vector - its element set to FALSE sets the prior mean for the autore-
     gressive parameters of the Nth equation to the white noise process, otherwise to random
 Returns: A new prior specification PriorBSVAR.
 Examples:
 # a prior for 3-variable example with one lag and stationary data
 prior = specify_prior_bsvar$new(N = 3, p = 1, stationary = rep(TRUE, 3))
 prior$A # show autoregressive prior mean
Method get_prior(): Returns the elements of the prior specification PriorBSVAR as a list.
 Usage:
 specify_prior_bsvar$get_prior()
 Examples:
 # a prior for 3-variable example with four lags
 prior = specify_prior_bsvar$new(N = 3, p = 4)
 prior$get_prior() # show the prior as list
Method clone(): The objects of this class are cloneable with this method.
 Usage:
 specify_prior_bsvar$clone(deep = FALSE)
 Arguments:
 deep Whether to make a deep clone.
```

```
# a prior for 3-variable example with four lags
prior = specify_prior_bsvar$new(N = 3, p = 4)
prior$get_prior() # show the prior as list
```

```
specify_prior_bsvar_mix
```

R6 Class Representing PriorBSVARMIX

Description

The class PriorBSVARMIX presents a prior specification for the bsvar model with a zero-mean mixture of normals model for structural shocks.

Super classes

```
bsvars::PriorBSVAR -> bsvars::PriorBSVARMSH -> PriorBSVARMIX
```

Public fields

- A an NxK matrix, the mean of the normal prior distribution for the parameter matrix A.
- A_V_inv a KxK precision matrix of the normal prior distribution for each of the row of the parameter matrix A. This precision matrix is equation invariant.
- B_V_inv an NxN precision matrix of the generalised-normal prior distribution for the structural matrix *B*. This precision matrix is equation invariant.
- B_nu a positive integer greater of equal than N, a shape parameter of the generalised-normal prior distribution for the structural matrix B.
- hyper_nu_B a positive scalar, the shape parameter of the inverted-gamma 2 prior for the overall shrinkage parameter for matrix B.
- hyper_a_B a positive scalar, the shape parameter of the gamma prior for the second-level hierarchy for the overall shrinkage parameter for matrix B.
- hyper_s_BB a positive scalar, the scale parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix B.
- hyper_nu_BB a positive scalar, the shape parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix B.
- hyper_nu_A a positive scalar, the shape parameter of the inverted-gamma 2 prior for the overall shrinkage parameter for matrix A.
- hyper_a_A a positive scalar, the shape parameter of the gamma prior for the second-level hierarchy for the overall shrinkage parameter for matrix A.
- hyper_s_AA a positive scalar, the scale parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix A.
- hyper_nu_AA a positive scalar, the shape parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix A.

- sigma_nu a positive scalar, the shape parameter of the inverted-gamma 2 for mixture component-dependent variances of the structural shocks, $\sigma_{n,s_{+}}^{2}$.
- sigma_s a positive scalar, the scale parameter of the inverted-gamma 2 for mixture component-dependent variances of the structural shocks, $\sigma_{n.s_t}^2$.
- PR_TR an MxM matrix, the matrix of hyper-parameters of the row-specific Dirichlet prior distribution for the state probabilities the Markov process s_t . Its rows must be identical.

Methods

Public methods:

• specify_prior_bsvar_mix\$clone()

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
specify_prior_bsvar_mix$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

Examples

```
prior = specify_prior_bsvar_mixnew(N = 3, p = 1, M = 2) # specify the prior priorA # show autoregressive prior mean
```

```
specify_prior_bsvar_msh
```

R6 Class Representing PriorBSVARMSH

Description

The class PriorBSVARMSH presents a prior specification for the bsvar model with Markov Switching Heteroskedasticity.

Super class

```
bsvars::PriorBSVAR -> PriorBSVARMSH
```

Public fields

A an NxK matrix, the mean of the normal prior distribution for the parameter matrix A.

- A_V_inv a KxK precision matrix of the normal prior distribution for each of the row of the parameter matrix A. This precision matrix is equation invariant.
- B_V_inv an NxN precision matrix of the generalised-normal prior distribution for the structural matrix B. This precision matrix is equation invariant.

- B_nu a positive integer greater of equal than N, a shape parameter of the generalised-normal prior distribution for the structural matrix B.
- hyper_nu_B a positive scalar, the shape parameter of the inverted-gamma 2 prior for the overall shrinkage parameter for matrix B.
- hyper_a_B a positive scalar, the shape parameter of the gamma prior for the second-level hierarchy for the overall shrinkage parameter for matrix B.
- hyper_s_BB a positive scalar, the scale parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix B.
- hyper_nu_BB a positive scalar, the shape parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix B.
- hyper_nu_A a positive scalar, the shape parameter of the inverted-gamma 2 prior for the overall shrinkage parameter for matrix A.
- hyper $_a$ A a positive scalar, the shape parameter of the gamma prior for the second-level hierarchy for the overall shrinkage parameter for matrix A.
- hyper_s_AA a positive scalar, the scale parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix A.
- hyper_nu_AA a positive scalar, the shape parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix A.
- sigma_nu a positive scalar, the shape parameter of the inverted-gamma 2 for MS state-dependent variances of the structural shocks, $\sigma_{n,s}^2$.
- sigma_s a positive scalar, the scale parameter of the inverted-gamma 2 for MS state-dependent variances of the structural shocks, σ_{n,s_4}^2 .
- PR_TR an MxM matrix, the matrix of hyper-parameters of the row-specific Dirichlet prior distribution for transition probabilities matrix P of the Markov process s_t .

Methods

Public methods:

- specify_prior_bsvar_msh\$new()
- specify_prior_bsvar_msh\$get_prior()
- specify_prior_bsvar_msh\$clone()

Method new(): Create a new prior specification PriorBSVARMSH.

```
Usage:
```

```
specify_prior_bsvar_msh$new(N, p, d = 0, M, stationary = rep(FALSE, N))
```

Arguments

- N a positive integer the number of dependent variables in the model.
- p a positive integer the autoregressive lag order of the SVAR model.
- d a positive integer the number of exogenous variables in the model.
- M an integer greater than 1 the number of Markov process' heteroskedastic regimes.
- stationary an N logical vector its element set to FALSE sets the prior mean for the autoregressive parameters of the Nth equation to the white noise process, otherwise to random walk.

Returns: A new prior specification PriorBSVARMSH.

Method get_prior(): Returns the elements of the prior specification PriorBSVARMSH as a list.

```
Usage:
specify_prior_bsvar_msh$get_prior()

Examples:
# a prior for 3-variable example with four lags and two regimes
prior = specify_prior_bsvar_msh$new(N = 3, p = 4, M = 2)
prior$get_prior() # show the prior as list
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
specify_prior_bsvar_msh$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

Examples

```
{\it R6~Class~Representing~PriorBSVARSV}
```

Description

The class PriorBSVARSV presents a prior specification for the bsvar model with Stochastic Volatility heteroskedasticity.

Super class

```
bsvars::PriorBSVAR -> PriorBSVARSV
```

Public fields

- A an NxK matrix, the mean of the normal prior distribution for the parameter matrix A.
- A_V_inv a KxK precision matrix of the normal prior distribution for each of the row of the parameter matrix A. This precision matrix is equation invariant.
- B_V_inv an NxN precision matrix of the generalised-normal prior distribution for the structural matrix *B*. This precision matrix is equation invariant.
- B_nu a positive integer greater of equal than N, a shape parameter of the generalised-normal prior distribution for the structural matrix B.
- hyper_nu_B a positive scalar, the shape parameter of the inverted-gamma 2 prior for the overall shrinkage parameter for matrix B.
- hyper_a_B a positive scalar, the shape parameter of the gamma prior for the second-level hierarchy for the overall shrinkage parameter for matrix B.
- hyper_s_BB a positive scalar, the scale parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix B.
- hyper_nu_BB a positive scalar, the shape parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix B.
- hyper_nu_A a positive scalar, the shape parameter of the inverted-gamma 2 prior for the overall shrinkage parameter for matrix A.
- hyper_a_A a positive scalar, the shape parameter of the gamma prior for the second-level hierarchy for the overall shrinkage parameter for matrix A.
- hyper_s_AA a positive scalar, the scale parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix A.
- hyper_nu_AA a positive scalar, the shape parameter of the inverted-gamma 2 prior for the third-level of hierarchy for overall shrinkage parameter for matrix A.
- sv_a_ a positive scalar, the shape parameter of the gamma prior in the hierarchical prior for σ_{ω}^2 .
- sv_s_ a positive scalar, the scale parameter of the gamma prior in the hierarchical prior for σ_{ω}^2 .

Methods

Public methods:

- specify_prior_bsvar_sv\$new()
- specify_prior_bsvar_sv\$get_prior()
- specify_prior_bsvar_sv\$clone()

Method new(): Create a new prior specification PriorBSVARSV.

```
Usage:
```

```
specify_prior_bsvar_sv$new(N, p, d = 0, stationary = rep(FALSE, N))
```

Arguments:

- N a positive integer the number of dependent variables in the model.
- p a positive integer the autoregressive lag order of the SVAR model.
- d a positive integer the number of exogenous variables in the model.

stationary an N logical vector - its element set to FALSE sets the prior mean for the autoregressive parameters of the Nth equation to the white noise process, otherwise to random walk.

Returns: A new prior specification PriorBSVARSV.

Method get_prior(): Returns the elements of the prior specification PriorBSVARSV as a list.

```
Usage:
specify_prior_bsvar_sv$get_prior()

Examples:
# a prior for 3-variable example with four lags
prior = specify_prior_bsvar_sv$new(N = 3, p = 4)
prior$get_prior() # show the prior as list
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
specify_prior_bsvar_sv$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

Examples

```
specify_starting_values_bsvar

R6 Class Representing StartingValuesBSVAR
```

Description

The class Starting Values BSVAR presents starting values for the homoskedastic bsvar model.

Public fields

```
A an NxK matrix of starting values for the parameter A.
```

B an NxN matrix of starting values for the parameter B.

hyper a (2*N+1)x2 matrix of starting values for the shrinkage hyper-parameters of the hierarchical prior distribution.

Methods

Public methods:

- specify_starting_values_bsvar\$new()
- specify_starting_values_bsvar\$get_starting_values()
- specify_starting_values_bsvar\$set_starting_values()
- specify_starting_values_bsvar\$clone()

Method new(): Create new starting values Starting Values BSVAR.

```
Usage:
```

```
specify_starting_values_bsvar$new(N, p, d = 0)
```

Arguments:

N a positive integer - the number of dependent variables in the model.

p a positive integer - the autoregressive lag order of the SVAR model.

d a positive integer - the number of exogenous variables in the model.

Returns: Starting values Starting Values BSVAR.

Examples:

```
\# starting values for a homoskedastic bsvar with 4 lags for a 3-variable system sv = specify\_starting\_values\_bsvar\$new(N = 3, p = 4)
```

Method get_starting_values(): Returns the elements of the starting values StartingValues-BSVAR as a list.

Usage:

```
specify_starting_values_bsvar$get_starting_values()
```

Examples

```
\# starting values for a homoskedastic bsvar with 1 lag for a 3-variable system sv = specify\_starting\_values\_bsvar\$new(N = 3, p = 1) sv\$get\_starting\_values() \# show starting values as list
```

Method set_starting_values(): Returns the elements of the starting values StartingValues-BSVAR as a list.

Usage:

```
specify_starting_values_bsvar$set_starting_values(last_draw)
```

Arguments:

last_draw a list containing the last draw of elements B - an NxN matrix, A - an NxK matrix, and hyper - a vector of 5 positive real numbers.

Returns: An object of class StartingValuesBSVAR including the last draw of the current MCMC as the starting value to be passed to the continuation of the MCMC estimation using estimate().

Examples:

```
# starting values for a homoskedastic bsvar with 1 lag for a 3-variable system
sv = specify_starting_values_bsvar$new(N = 3, p = 1)

# Modify the starting values by:
sv_list = sv$get_starting_values()  # getting them as list
sv_list$A <- matrix(rnorm(12), 3, 4)  # modifying the entry
sv$set_starting_values(sv_list)  # providing to the class object</pre>
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
specify_starting_values_bsvar$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

```
sv = specify_starting_values_bsvar$new(N = 3, p = 1)

# Modify the starting values by:
sv_list = sv$get_starting_values()  # getting them as list
sv_list$A <- matrix(rnorm(12), 3, 4)  # modifying the entry
sv$set_starting_values(sv_list)  # providing to the class object</pre>
```

```
specify_starting_values_bsvar_mix
```

R6 Class Representing Starting Values BSVARMIX

Description

The class StartingValuesBSVARMIX presents starting values for the bsvar model with a zero-mean mixture of normals model for structural shocks.

Super classes

bsvars::StartingValuesBSVAR -> bsvars::StartingValuesBSVARMSH -> StartingValuesBSVARMIX

Public fields

- A an NxK matrix of starting values for the parameter A.
- B an NxN matrix of starting values for the parameter B.
- hyper a (2*N+1)x2 matrix of starting values for the shrinkage hyper-parameters of the hierarchical prior distribution.
- sigma2 an NxM matrix of starting values for the MS state-specific variances of the structural shocks. Its elements sum to value M over the rows.
- PR_TR an MxM matrix of starting values for the probability matrix of the Markov process. Its rows must be identical and the elements of each row sum to 1 over the rows.
- xi an MxT matrix of starting values for the Markov process indicator. Its columns are a chosen column of an identity matrix of order M.
- pi_0 an M-vector of starting values for mixture components state probabilities. Its elements sum to 1.

Methods

Public methods:

- specify_starting_values_bsvar_mix\$new()
- specify_starting_values_bsvar_mix\$clone()

Method new(): Create new starting values Starting Values BSVARMIX.

```
Usage:
```

```
specify_starting_values_bsvar_mix$new(N, p, M, T, d = 0, finiteM = TRUE)
```

Arguments:

N a positive integer - the number of dependent variables in the model.

p a positive integer - the autoregressive lag order of the SVAR model.

M an integer greater than 1 - the number of components of the mixture of normals.

T a positive integer - the the time series dimension of the dependent variable matrix Y.

d a positive integer - the number of exogenous variables in the model.

finiteM a logical value - if true a finite mixture model is estimated. Otherwise, a sparse mixture model is estimated in which M=20 and the number of visited states is estimated.

Returns: Starting values Starting Values BSVARMIX.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
```

```
specify_starting_values_bsvar_mix$clone(deep = FALSE)
```

Arguments:

deep Whether to make a deep clone.

Examples

```
# starting values for a bsvar model for a 3-variable system
sv = specify_starting_values_bsvar_mix$new(N = 3, p = 1, M = 2, T = 100)
```

```
specify_starting_values_bsvar_msh
```

R6 Class Representing Starting Values BSVARMSH

Description

The class StartingValuesBSVARMSH presents starting values for the bsvar model with Markov Switching Heteroskedasticity.

Super class

bsvars::StartingValuesBSVAR -> StartingValuesBSVARMSH

Public fields

A an NxK matrix of starting values for the parameter A.

B an NxN matrix of starting values for the parameter B.

hyper a (2*N+1)x2 matrix of starting values for the shrinkage hyper-parameters of the hierarchical prior distribution.

sigma2 an NxM matrix of starting values for the MS state-specific variances of the structural shocks. Its elements sum to value M over the rows.

- PR_TR an MxM matrix of starting values for the transition probability matrix of the Markov process. Its elements sum to 1 over the rows.
- xi an MxT matrix of starting values for the Markov process indicator. Its columns are a chosen column of an identity matrix of order M.
- pi_0 an M-vector of starting values for state probability at time t=0. Its elements sum to 1.

Methods

Public methods:

- specify_starting_values_bsvar_msh\$new()
- specify_starting_values_bsvar_msh\$get_starting_values()
- specify_starting_values_bsvar_msh\$set_starting_values()
- specify_starting_values_bsvar_msh\$clone()

Method new(): Create new starting values Starting Values BSVAR-MS.

```
Usage:
```

```
specify_starting_values_bsvar_msh$new(N, p, M, T, d = 0, finiteM = TRUE)
```

Arguments.

- N a positive integer the number of dependent variables in the model.
- p a positive integer the autoregressive lag order of the SVAR model.
- M an integer greater than 1 the number of Markov process' heteroskedastic regimes.
- T a positive integer the the time series dimension of the dependent variable matrix Y.
- d a positive integer the number of exogenous variables in the model.
- finiteM a logical value if true a stationary Markov switching model is estimated. Otherwise, a sparse Markov switching model is estimated in which M=20 and the number of visited states is estimated.

Returns: Starting values Starting Values BSVAR-MS.

Method get_starting_values(): Returns the elements of the starting values Starting Values BSVAR-MS as a list.

Usage:

```
specify_starting_values_bsvar_msh$get_starting_values()
```

Examples:

```
\# starting values for a homoskedastic bsvar with 1 lag for a 3-variable system sv = specify\_starting\_values\_bsvar\_msh$new(N = 3, p = 1, M = 2, T = 100) <math>sv\$get\_starting\_values() \# show starting values as list
```

Method set_starting_values(): Returns the elements of the starting values StartingValues-BSVARMSH as a list.

Usage:

```
specify_starting_values_bsvar_msh$set_starting_values(last_draw)
```

Arguments:

last_draw a list containing the last draw.

Returns: An object of class Starting Values BSVAR-MS including the last draw of the current MCMC as the starting value to be passed to the continuation of the MCMC estimation using estimate().

Examples:

```
# starting values for a bsvar model with 1 lag for a 3-variable system
sv = specify_starting_values_bsvar_msh$new(N = 3, p = 1, M = 2, T = 100)

# Modify the starting values by:
sv_list = sv$get_starting_values()  # getting them as list
sv_list$A <- matrix(rnorm(12), 3, 4)  # modifying the entry
sv$set_starting_values(sv_list)  # providing to the class object</pre>
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
```

```
specify_starting_values_bsvar_msh$clone(deep = FALSE)
```

Arguments:

deep Whether to make a deep clone.

```
# starting values for a bsvar model for a 3-variable system
sv = specify_starting_values_bsvar_msh$new(N = 3, p = 1, M = 2, T = 100)
## Method `specify_starting_values_bsvar_msh$get_starting_values`
# starting values for a homoskedastic bsvar with 1 lag for a 3-variable system
sv = specify_starting_values_bsvar_msh$new(N = 3, p = 1, M = 2, T = 100)
sv$get_starting_values() # show starting values as list
## -----
## Method `specify_starting_values_bsvar_msh$set_starting_values`
## -----
# starting values for a bsvar model with 1 lag for a 3-variable system
sv = specify_starting_values_bsvar_msh$new(N = 3, p = 1, M = 2, T = 100)
# Modify the starting values by:
sv_list = sv$get_starting_values() # getting them as list
sv_list$A <- matrix(rnorm(12), 3, 4) # modifying the entry</pre>
sv$set_starting_values(sv_list)
                               # providing to the class object
```

```
specify\_starting\_values\_bsvar\_sv\\ R6\ Class\ Representing\ Starting\ ValuesBSVARSV
```

Description

The class Starting Values BSVARSV presents starting values for the bsvar model with Stochastic Volatility heteroskedasticity.

Super class

```
bsvars::StartingValuesBSVAR->StartingValuesBSVARSV
```

Public fields

A an NxK matrix of starting values for the parameter A.

B an NxN matrix of starting values for the parameter B.

hyper a (2*N+1)x2 matrix of starting values for the shrinkage hyper-parameters of the hierarchical prior distribution.

h an NxT matrix with the starting values of the log-volatility processes.

rho an N-vector with values of SV autoregressive parameters.

omega an N-vector with values of SV process conditional standard deviations.

sigma2v an N-vector with values of SV process conditional variances.

S an NxT integer matrix with the auxiliary mixture component indicators.

sigma2_omega an N-vector with variances of the zero-mean normal prior for ω_n .

s_ a positive scalar with the scale of the gamma prior of the hierarchical prior for σ_{ω}^2 .

Methods

Public methods:

- specify_starting_values_bsvar_sv\$new()
- specify_starting_values_bsvar_sv\$get_starting_values()
- specify_starting_values_bsvar_sv\$set_starting_values()
- specify_starting_values_bsvar_sv\$clone()

Method new(): Create new starting values Starting Values BSVARSV.

```
Usage:
```

```
specify_starting_values_bsvar_sv$new(N, p, T, d = 0)
```

Arguments:

N a positive integer - the number of dependent variables in the model.

p a positive integer - the autoregressive lag order of the SVAR model.

T a positive integer - the the time series dimension of the dependent variable matrix Y.

d a positive integer - the number of exogenous variables in the model.

Returns: Starting values Starting Values BSVARSV.

Method get_starting_values(): Returns the elements of the starting values StartingValues-BSVARSV as a list.

```
Usage:
```

```
specify_starting_values_bsvar_sv$get_starting_values()
```

Examples:

```
\# starting values for a bsvar model with 1 lag for a 3-variable system sv = specify\_starting\_values\_bsvar\_sv$new(N = 3, p = 1, T = 100) <math>sv\$get\_starting\_values() \# show starting values as list
```

Method set_starting_values(): Returns the elements of the starting values StartingValues-BSVAR SV as a list.

```
Usage:
```

```
specify_starting_values_bsvar_sv$set_starting_values(last_draw)
```

Arguments:

last_draw a list containing the last draw of the current MCMC run.

Returns: An object of class StartingValuesBSVAR including the last draw of the current MCMC as the starting value to be passed to the continuation of the MCMC estimation using estimate().

Examples:

```
# starting values for a bsvar model with 1 lag for a 3-variable system
sv = specify_starting_values_bsvar_sv$new(N = 3, p = 1, T = 100)

# Modify the starting values by:
sv_list = sv$get_starting_values()  # getting them as list
sv_list$A <- matrix(rnorm(12), 3, 4)  # modifying the entry
sv$set_starting_values(sv_list)  # providing to the class object</pre>
```

Method clone(): The objects of this class are cloneable with this method.

Usage:

```
specify_starting_values_bsvar_sv$clone(deep = FALSE)
```

Arguments:

deep Whether to make a deep clone.

```
# starting values for a bsvar model for a 3-variable system
sv = specify_starting_values_bsvar_sv$new(N = 3, p = 1, T = 100)
## ------
```

us_fiscal_ex 99

us_fiscal_ex

A 3-variable system of exogenous variables for the US fiscal model for the period 1948 $Q1-2023\ Q2$

Description

Exogenous variables used to identify the US fiscal policy shocks.

Usage

```
data(us_fiscal_ex)
```

Format

A matrix and a ts object with time series of 302 observations on 3 variables:

t a time trend

t^2 a quadratic trend

1975Q2 a dummy variable taking the value of 1 for quarter 2 1975 and zero elsewhere

The series are as described by Mertens & Ravn (2014). The data was used by Lütkepohl, Shang, Uzeda, Woźniak (2023).

References

Mertens, K., and Ravn, M.O. (2014) A Reconciliation of SVAR and Narrative Estimates of Tax Multipliers, *Journal of Monetary Economics*, 68(S), S1–S19. DOI: doi:10.1016/j.jmoneco.2013.04.004. Lütkepohl, H., Shang, F., Uzeda, L., and Woźniak, T. (2023) Partial Identification of Heteroskedastic Structural VARs: Theory and Bayesian Inference.

100 us_fiscal_lsuw

Examples

```
data(us_fiscal_ex)  # upload the data
plot(us_fiscal_ex)  # plot the data
```

us_fiscal_lsuw

A 3-variable US fiscal system for the period 1948 $Q1-2023\ Q2$

Description

A system used to identify the US fiscal policy shocks.

Usage

```
data(us_fiscal_lsuw)
```

Format

A matrix and a ts object with time series of 302 observations on 3 variables:

ttr quarterly US total tax revenue expressed in log, real, per person terms

gs quarterly US total government spending expressed in log, real, per person terms

gdp quarterly US gross domestic product expressed in log, real, per person terms

The series are as described by Mertens & Ravn (2014) in footnote 3 and main body on page S3 of the paper. Differences with respect to Mertens & Ravn's data:

- The sample period is from quarter 1 of 1948 to quarter 2 of 2023,
- The population variable is not from Francis & Ramey (2009) but from the FRED (with the same definition),
- The original monthly population data is transformed to quarterly by taking monthly averages.

Source

U.S. Bureau of Economic Analysis, National Income and Product Accounts, https://www.bea.gov/products/national-income-and-product-accounts

FRED Economic Database, Federal Reserve Bank of St. Louis, https://fred.stlouisfed.org/

References

Francis, N., and Ramey, V.A. (2009) Measures of per capita Hours and Their Implications for the Technology-hours Debate. *Journal of Money, Credit and Banking*, 41(6), 1071-1097, DOI: doi:10.1111/j.15384616.2009.00247.x.

Mertens, K., and Ravn, M.O. (2014) A Reconciliation of SVAR and Narrative Estimates of Tax Multipliers, *Journal of Monetary Economics*, 68(S), S1–S19. DOI: doi:10.1016/j.jmoneco.2013.04.004.

Lütkepohl, H., Shang, F., Uzeda, L., and Woźniak, T. (2022) Partial Identification of Heteroskedastic Structural VARs: Theory and Bayesian Inference.

verify_autoregression 101

Examples

```
data(us_fiscal_lsuw) # upload the data
plot(us_fiscal_lsuw) # plot the data
```

verify_autoregression Verifies hypotheses involving autoregressive parameters

Description

Computes the logarithm of Bayes factor for the joint hypothesis, H_0 , possibly for many autoregressive parameters represented by argument hypothesis via Savage-Dickey Density Ration (SDDR). The logarithm of Bayes factor for this hypothesis can be computed using the SDDR as the difference of logarithms of the marginal posterior distribution ordinate at the restriction less the marginal prior distribution ordinate at the same point:

$$logp(H_0|data) - logp(H_0)$$

Therefore, a negative value of the difference is the evidence against hypothesis. The estimation of both elements of the difference requires numerical integration.

Usage

```
verify_autoregression(posterior, hypothesis)
```

Arguments

posterior the posterior element of the list from the estimation outcome

hypothesis an NxK matrix of the same dimension as the autoregressive matrix A with nu-

meric values for the parameters to be verified, in which case the values represent the joint hypothesis, and missing value NA for these parameters that are not tested

Value

An object of class SDDR that is a list of three components:

logSDDR a scalar with values of the logarithm of the Bayes factors for the autoregressive hypothesis for each of the shocks

log_SDDR_se an N-vector with estimation standard errors of the logarithm of the Bayes factors reported in output element logSDDR that are computed based on 30 random sub-samples of the log-ordinates of the marginal posterior and prior distributions.

components a list of three components for the computation of the Bayes factor

log_denominator an N-vector with values of the logarithm of the Bayes factor denominators

log_numerator an N-vector with values of the logarithm of the Bayes factor numerators

log_numerator_s an NxS matrix of the log-full conditional posterior density ordinates computed to estimate the numerator log_denominator_s an NxS matrix of the log-full conditional posterior density ordinates computed
to estimate the denominator

se_components a 30-vector containing the log-Bayes factors on the basis of which the standard errors are computed

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Woźniak, T., and Droumaguet, M., (2022) Bayesian Assessment of Identifying Restrictions for Heteroskedastic Structural VARs

```
# simple workflow
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar$new(us_fiscal_lsuw, p = 1)
set.seed(123)
# estimate the model
posterior
          = estimate(specification, 10, thin = 1)
# verify autoregression
            = matrix(NA, ncol(us_fiscal_lsuw), ncol(us_fiscal_lsuw) + 1)
HØ
H0[1,3]
           = 0  # a hypothesis of no Granger causality from gdp to ttr
sddr
            = verify_autoregression(posterior, H0)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvarsnew(p = 1) \mid >
 estimate(S = 10, thin = 1) \mid >
 verify_autoregression(hypothesis = H0) -> sddr
```

Description

Computes the logarithm of Bayes factor for the joint hypothesis, H_0 , possibly for many autoregressive parameters represented by argument hypothesis via Savage-Dickey Density Ration (SDDR). The logarithm of Bayes factor for this hypothesis can be computed using the SDDR as the difference of logarithms of the marginal posterior distribution ordinate at the restriction less the marginal prior distribution ordinate at the same point:

$$logp(H_0|data) - logp(H_0)$$

Therefore, a negative value of the difference is the evidence against hypothesis. The estimation of both elements of the difference requires numerical integration.

Usage

```
## S3 method for class 'PosteriorBSVAR'
verify_autoregression(posterior, hypothesis)
```

Arguments

posterior the posterior element of the list from the estimation outcome

hypothesis an NxK matrix of the same dimension as the autoregressive matrix A with nu-

meric values for the parameters to be verified, in which case the values represent the joint hypothesis, and missing value NA for these parameters that are not tested

Value

An object of class SDDR that is a list of three components:

logSDDR a scalar with values of the logarithm of the Bayes factors for the autoregressive hypothesis for each of the shocks

log_SDDR_se an N-vector with estimation standard errors of the logarithm of the Bayes factors reported in output element logSDDR that are computed based on 30 random sub-samples of the log-ordinates of the marginal posterior and prior distributions.

components a list of three components for the computation of the Bayes factor

log_denominator an N-vector with values of the logarithm of the Bayes factor denominators

log_numerator an N-vector with values of the logarithm of the Bayes factor numerators

log_numerator_s an NxS matrix of the log-full conditional posterior density ordinates computed to estimate the numerator

log_denominator_s an NxS matrix of the log-full conditional posterior density ordinates computed
to estimate the denominator

se_components a 30-vector containing the log-Bayes factors on the basis of which the standard errors are computed

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Woźniak, T., and Droumaguet, M., (2022) Bayesian Assessment of Identifying Restrictions for Heteroskedastic Structural VARs

Examples

```
# simple workflow
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar$new(us_fiscal_lsuw, p = 1)
set.seed(123)
# estimate the model
posterior = estimate(specification, 10, thin = 1)
# verify autoregression
            = matrix(NA, ncol(us_fiscal_lsuw), ncol(us_fiscal_lsuw) + 1)
                     # a hypothesis of no Granger causality from gdp to ttr
H0[1,3]
            = verify_autoregression(posterior, H0)
sddr
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvarsnew(p = 1) \mid >
 estimate(S = 10, thin = 1) \mid >
 verify_autoregression(hypothesis = H0) -> sddr
```

 ${\tt verify_autoregression.PosteriorBSVARMIX}$

Verifies hypotheses involving autoregressive parameters

Description

Computes the logarithm of Bayes factor for the joint hypothesis, H_0 , possibly for many autoregressive parameters represented by argument hypothesis via Savage-Dickey Density Ration (SDDR). The logarithm of Bayes factor for this hypothesis can be computed using the SDDR as the difference of logarithms of the marginal posterior distribution ordinate at the restriction less the marginal prior distribution ordinate at the same point:

$$logp(H_0|data) - logp(H_0)$$

Therefore, a negative value of the difference is the evidence against hypothesis. The estimation of both elements of the difference requires numerical integration.

Usage

```
## S3 method for class 'PosteriorBSVARMIX'
verify_autoregression(posterior, hypothesis)
```

Arguments

posterior the posterior element of the list from the estimation outcome

hypothesis an NxK matrix of the same dimension as the autoregressive matrix A with nu-

meric values for the parameters to be verified, in which case the values represent the joint hypothesis, and missing value NA for these parameters that are not tested

Value

An object of class SDDR that is a list of three components:

logSDDR a scalar with values of the logarithm of the Bayes factors for the autoregressive hypothesis for each of the shocks

log_SDDR_se an N-vector with estimation standard errors of the logarithm of the Bayes factors reported in output element logSDDR that are computed based on 30 random sub-samples of the log-ordinates of the marginal posterior and prior distributions.

components a list of three components for the computation of the Bayes factor

log_denominator an N-vector with values of the logarithm of the Bayes factor denominators

log_numerator an N-vector with values of the logarithm of the Bayes factor numerators

log_numerator_s an NxS matrix of the log-full conditional posterior density ordinates computed to estimate the numerator

log_denominator_s an NxS matrix of the log-full conditional posterior density ordinates computed to estimate the denominator

se_components a 30-vector containing the log-Bayes factors on the basis of which the standard errors are computed

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Woźniak, T., and Droumaguet, M., (2022) Bayesian Assessment of Identifying Restrictions for Heteroskedastic Structural VARs

```
specification = specify_bsvar_mix$new(us_fiscal_lsuw, p = 1, M = 2)
set.seed(123)
# estimate the model
             = estimate(specification, 10, thin = 1)
posterior
# verify autoregression
             = matrix(NA, ncol(us_fiscal_lsuw), ncol(us_fiscal_lsuw) + 1)
H0[1,3]
                       # a hypothesis of no Granger causality from gdp to ttr
sddr
             = verify_autoregression(posterior, H0)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_mix$new(p = 1, M = 2) >
 estimate(S = 10, thin = 1) \mid >
 verify_autoregression(hypothesis = H0) -> sddr
```

verify_autoregression.PosteriorBSVARMSH

Verifies hypotheses involving autoregressive parameters

Description

Computes the logarithm of Bayes factor for the joint hypothesis, H_0 , possibly for many autoregressive parameters represented by argument hypothesis via Savage-Dickey Density Ration (SDDR). The logarithm of Bayes factor for this hypothesis can be computed using the SDDR as the difference of logarithms of the marginal posterior distribution ordinate at the restriction less the marginal prior distribution ordinate at the same point:

$$logp(H_0|data) - logp(H_0)$$

Therefore, a negative value of the difference is the evidence against hypothesis. The estimation of both elements of the difference requires numerical integration.

Usage

```
## S3 method for class 'PosteriorBSVARMSH'
verify_autoregression(posterior, hypothesis)
```

Arguments

posterior the posterior element of the list from the estimation outcome

meric values for the parameters to be verified, in which case the values represent the joint hypothesis, and missing value NA for these parameters that are not tested

Value

An object of class SDDR that is a list of three components:

logSDDR a scalar with values of the logarithm of the Bayes factors for the autoregressive hypothesis for each of the shocks

log_SDDR_se an N-vector with estimation standard errors of the logarithm of the Bayes factors reported in output element logSDDR that are computed based on 30 random sub-samples of the log-ordinates of the marginal posterior and prior distributions.

components a list of three components for the computation of the Bayes factor

- log_denominator an N-vector with values of the logarithm of the Bayes factor denominators
- log_numerator an N-vector with values of the logarithm of the Bayes factor numerators
- log_numerator_s an NxS matrix of the log-full conditional posterior density ordinates computed to estimate the numerator
- **log_denominator_s** an NxS matrix of the log-full conditional posterior density ordinates computed to estimate the denominator
- **se_components** a 30-vector containing the log-Bayes factors on the basis of which the standard errors are computed

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Woźniak, T., and Droumaguet, M., (2022) Bayesian Assessment of Identifying Restrictions for Heteroskedastic Structural VARs

```
# simple workflow
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_msh$new(us_fiscal_lsuw, p = 1, M = 2)
set.seed(123)
# estimate the model
          = estimate(specification, 10, thin = 1)
posterior
# verify autoregression
           = matrix(NA, ncol(us_fiscal_lsuw), ncol(us_fiscal_lsuw) + 1)
H0[1,3]
                    # a hypothesis of no Granger causality from gdp to ttr
sddr
           = verify_autoregression(posterior, H0)
# workflow with the pipe |>
```

```
set.seed(123)
us_fiscal_lsuw |>
   specify_bsvar_msh$new(p = 1, M = 2) |>
   estimate(S = 10, thin = 1) |>
   verify_autoregression(hypothesis = H0) -> sddr
```

verify_autoregression.PosteriorBSVARSV

Verifies hypotheses involving autoregressive parameters

Description

Computes the logarithm of Bayes factor for the joint hypothesis, H_0 , possibly for many autoregressive parameters represented by argument hypothesis via Savage-Dickey Density Ration (SDDR). The logarithm of Bayes factor for this hypothesis can be computed using the SDDR as the difference of logarithms of the marginal posterior distribution ordinate at the restriction less the marginal prior distribution ordinate at the same point:

$$logp(H_0|data) - logp(H_0)$$

Therefore, a negative value of the difference is the evidence against hypothesis. The estimation of both elements of the difference requires numerical integration.

Usage

```
## S3 method for class 'PosteriorBSVARSV'
verify_autoregression(posterior, hypothesis)
```

Arguments

posterior the posterior element of the list from the estimation outcome

hypothesis an NxK matrix of the same dimension as the autoregressive matrix A with nu-

meric values for the parameters to be verified, in which case the values represent the joint hypothesis, and missing value NA for these parameters that are not tested

Value

An object of class SDDR that is a list of three components:

logSDDR a scalar with values of the logarithm of the Bayes factors for the autoregressive hypothesis for each of the shocks

log_SDDR_se an N-vector with estimation standard errors of the logarithm of the Bayes factors reported in output element logSDDR that are computed based on 30 random sub-samples of the log-ordinates of the marginal posterior and prior distributions.

components a list of three components for the computation of the Bayes factor

log_denominator an N-vector with values of the logarithm of the Bayes factor denominators

log_numerator an N-vector with values of the logarithm of the Bayes factor numerators

log_numerator_s an NxS matrix of the log-full conditional posterior density ordinates computed
to estimate the numerator

log_denominator_s an NxS matrix of the log-full conditional posterior density ordinates computed to estimate the denominator

se_components a 30-vector containing the log-Bayes factors on the basis of which the standard errors are computed

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Woźniak, T., and Droumaguet, M., (2022) Bayesian Assessment of Identifying Restrictions for Heteroskedastic Structural VARs

Examples

```
# simple workflow
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_sv$new(us_fiscal_lsuw, p = 1)
set.seed(123)
# estimate the model
           = estimate(specification, 10, thin = 1)
posterior
# verify autoregression
            = matrix(NA, ncol(us_fiscal_lsuw), ncol(us_fiscal_lsuw) + 1)
HØ
H0[1,3]
                     # a hypothesis of no Granger causality from gdp to ttr
sddr
            = verify_autoregression(posterior, H0)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_sv$new(p = 1) |>
 estimate(S = 10, thin = 1) >
 verify_autoregression(hypothesis = H0) -> sddr
```

verify_volatility

verify_volatility

Verifies heteroskedasticity of structural shocks equation by equation

Description

Computes the logarithm of Bayes factor for the homoskedasticity hypothesis for each of the structural shocks via Savage-Dickey Density Ration (SDDR). The hypothesis of homoskedasticity, H_0 , is represented by model-specific restrictions. Consult help files for individual classes of models for details. The logarithm of Bayes factor for this hypothesis can be computed using the SDDR as the difference of logarithms of the marginal posterior distribution ordinate at the restriction less the marginal prior distribution ordinate at the same point:

$$logp(H_0|data) - logp(H_0)$$

Therefore, a negative value of the difference is the evidence against homoskedasticity of the structural shock. The estimation of both elements of the difference requires numerical integration.

Usage

verify_volatility(posterior)

Arguments

posterior

the posterior element of the list from the estimation outcome

Value

An object of class SDDR that is a list of three components:

logSDDR an N-vector with values of the logarithm of the Bayes factors for the homoskedasticity hypothesis for each of the shocks

log_SDDR_se an N-vector with estimation standard errors of the logarithm of the Bayes factors reported in output element logSDDR that are computed based on 30 random sub-samples of the log-ordinates of the marginal posterior and prior distributions.

components a list of three components for the computation of the Bayes factor

log denominator an N-vector with values of the logarithm of the Bayes factor denominators

log numerator an N-vector with values of the logarithm of the Bayes factor numerators

log_numerator_s an NxS matrix of the log-full conditional posterior density ordinates computed to estimate the numerator

se_components an Nx30 matrix containing the log-Bayes factors on the basis of which the standard errors are computed

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Lütkepohl, H., and Woźniak, T., (2020) Bayesian Inference for Structural Vector Autoregressions Identified by Markov-Switching Heteroskedasticity. *Journal of Economic Dynamics and Control* **113**, 103862, doi:10.1016/j.jedc.2020.103862.

Lütkepohl, H., Shang, F., Uzeda, L., and Woźniak, T., (2023) Partial Identification of Heteroskedastic Structural VARs: Theory and Bayesian Inference.

Examples

```
# simple workflow
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_sv$new(us_fiscal_lsuw, p = 1)
set.seed(123)
# estimate the model
posterior
         = estimate(specification, 10, thin = 1)
# verify heteroskedasticity
sddr
           = verify_volatility(posterior)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_sv$new(p = 1) |>
 estimate(S = 10, thin = 1) >
 verify_volatility() -> sddr
```

verify_volatility.PosteriorBSVAR

Verifies heteroskedasticity of structural shocks equation by equation

Description

Displays information that the model is homoskedastic.

Usage

```
## S3 method for class 'PosteriorBSVAR'
verify_volatility(posterior)
```

Arguments

posterior

the posterior element of the list from the estimation outcome

Value

Nothing. Just displays a message: The model is homoskedastic.

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Lütkepohl, H., and Woźniak, T., (2020) Bayesian Inference for Structural Vector Autoregressions Identified by Markov-Switching Heteroskedasticity. *Journal of Economic Dynamics and Control* **113**, 103862, doi:10.1016/j.jedc.2020.103862.

Lütkepohl, H., Shang, F., Uzeda, L., and Woźniak, T., (2023) Partial Identification of Heteroskedastic Structural VARs: Theory and Bayesian Inference.

Examples

```
# simple workflow
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar$new(us_fiscal_lsuw, p = 1)
set.seed(123)
# estimate the model
           = estimate(specification, 5, thin = 1)
posterior
# verify heteroskedasticity
           = verify_volatility(posterior)
sddr
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar$new(p = 1) |>
 estimate(S = 5, thin = 1) >
 verify_volatility() -> sddr
```

Description

Computes the logarithm of Bayes factor for the homoskedasticity hypothesis for each of the structural shocks via Savage-Dickey Density Ration (SDDR). The hypothesis of homoskedasticity is represented by restriction:

$$H_0: \sigma_{n.1}^2 = \dots = \sigma_{n.M}^2 = 1$$

The logarithm of Bayes factor for this hypothesis can be computed using the SDDR as the difference of logarithms of the marginal posterior distribution ordinate at the restriction less the marginal prior distribution ordinate at the same point:

$$log p(\omega_n = 0|data) - log p(\omega_n = 0)$$

Therefore, a negative value of the difference is the evidence against homoskedasticity of the structural shock. The estimation of both elements of the difference requires numerical integration.

Usage

```
## S3 method for class 'PosteriorBSVARMIX'
verify_volatility(posterior)
```

Arguments

posterior

the posterior element of the list from the estimation outcome

Value

An object of class SDDR that is a list of three components:

logSDDR an N-vector with values of the logarithm of the Bayes factors for the homoskedasticity hypothesis for each of the shocks

log_SDDR_se an N-vector with estimation standard errors of the logarithm of the Bayes factors reported in output element logSDDR that are computed based on 30 random sub-samples of the log-ordinates of the marginal posterior and prior distributions.

components a list of three components for the computation of the Bayes factor

log_denominator an N-vector with values of the logarithm of the Bayes factor denominators

log_numerator an N-vector with values of the logarithm of the Bayes factor numerators

log_numerator_s an NxS matrix of the log-full conditional posterior density ordinates computed
to estimate the numerator

se_components an Nx30 matrix containing the log-Bayes factors on the basis of which the standard errors are computed

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Lütkepohl, H., and Woźniak, T., (2020) Bayesian Inference for Structural Vector Autoregressions Identified by Markov-Switching Heteroskedasticity. *Journal of Economic Dynamics and Control* **113**, 103862, doi:10.1016/j.jedc.2020.103862.

Lütkepohl, H., Shang, F., Uzeda, L., and Woźniak, T., (2023) Partial Identification of Heteroskedastic Structural VARs: Theory and Bayesian Inference.

See Also

```
specify_bsvar_mix, estimate
```

Examples

```
# simple workflow
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_mixnew(us_fiscal_lsuw, p = 1, M = 2)
set.seed(123)
# estimate the model
           = estimate(specification, 10, thin = 1)
posterior
# verify heteroskedasticity
           = verify_volatility(posterior)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_mixsnew(p = 1, M = 2) >
 estimate(S = 10, thin = 1) \mid >
 verify_volatility() -> sddr
```

verify_volatility.PosteriorBSVARMSH

Verifies heteroskedasticity of structural shocks equation by equation

Description

Computes the logarithm of Bayes factor for the homoskedasticity hypothesis for each of the structural shocks via Savage-Dickey Density Ration (SDDR). The hypothesis of homoskedasticity is represented by restriction:

$$H_0: \sigma_{n.1}^2 = \dots = \sigma_{n.M}^2 = 1$$

The logarithm of Bayes factor for this hypothesis can be computed using the SDDR as the difference of logarithms of the marginal posterior distribution ordinate at the restriction less the marginal prior distribution ordinate at the same point:

$$log p(\omega_n = 0|data) - log p(\omega_n = 0)$$

Therefore, a negative value of the difference is the evidence against homoskedasticity of the structural shock. The estimation of both elements of the difference requires numerical integration.

Usage

```
## S3 method for class 'PosteriorBSVARMSH'
verify_volatility(posterior)
```

Arguments

posterior the posterior element of the list from the estimation outcome

Value

An object of class SDDR that is a list of three components:

logSDDR an N-vector with values of the logarithm of the Bayes factors for the homoskedasticity hypothesis for each of the shocks

log_SDDR_se an N-vector with estimation standard errors of the logarithm of the Bayes factors reported in output element logSDDR that are computed based on 30 random sub-samples of the log-ordinates of the marginal posterior and prior distributions.

components a list of three components for the computation of the Bayes factor

log_denominator an N-vector with values of the logarithm of the Bayes factor denominators

log_numerator an N-vector with values of the logarithm of the Bayes factor numerators

log_numerator_s an NxS matrix of the log-full conditional posterior density ordinates computed to estimate the numerator

se_components an Nx30 matrix containing the log-Bayes factors on the basis of which the standard errors are computed

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Lütkepohl, H., and Woźniak, T., (2020) Bayesian Inference for Structural Vector Autoregressions Identified by Markov-Switching Heteroskedasticity. *Journal of Economic Dynamics and Control* **113**, 103862, doi:10.1016/j.jedc.2020.103862.

Lütkepohl, H., Shang, F., Uzeda, L., and Woźniak, T., (2023) Partial Identification of Heteroskedastic Structural VARs: Theory and Bayesian Inference.

See Also

```
specify_bsvar_msh, estimate
```

Examples

```
# simple workflow
# upload data
data(us_fiscal_lsuw)
# specify the model and set seed
specification = specify_bsvar_msh$new(us_fiscal_lsuw, p = 1, M = 2)
set.seed(123)
# estimate the model
posterior
           = estimate(specification, 10, thin = 1)
# verify heteroskedasticity
           = verify_volatility(posterior)
# workflow with the pipe |>
set.seed(123)
us_fiscal_lsuw |>
 specify_bsvar_msh$new(p = 1, M = 2) >
 estimate(S = 10, thin = 1) >
 verify_volatility() -> sddr
```

verify_volatility.PosteriorBSVARSV

Verifies heteroskedasticity of structural shocks equation by equation

Description

Computes the logarithm of Bayes factor for the homoskedasticity hypothesis for each of the structural shocks via Savage-Dickey Density Ration (SDDR). The hypothesis of homoskedasticity is represented by restriction:

$$H_0: \omega_n = 0$$

The logarithm of Bayes factor for this hypothesis can be computed using the SDDR as the difference of logarithms of the marginal posterior distribution ordinate at the restriction less the marginal prior distribution ordinate at the same point:

$$log p(\omega_n = 0|data) - log p(\omega_n = 0)$$

Therefore, a negative value of the difference is the evidence against homoskedasticity of the structural shock. The estimation of both elements of the difference requires numerical integration.

Usage

```
## S3 method for class 'PosteriorBSVARSV'
verify_volatility(posterior)
```

Arguments

posterior the posterior element of the list from the estimation outcome

Value

An object of class SDDR that is a list of three components:

logSDDR an N-vector with values of the logarithm of the Bayes factors for the homoskedasticity hypothesis for each of the shocks

log_SDDR_se an N-vector with estimation standard errors of the logarithm of the Bayes factors reported in output element logSDDR that are computed based on 30 random sub-samples of the log-ordinates of the marginal posterior and prior distributions.

components a list of three components for the computation of the Bayes factor

log_denominator an N-vector with values of the logarithm of the Bayes factor denominators

log_numerator an N-vector with values of the logarithm of the Bayes factor numerators

log_numerator_s an NxS matrix of the log-full conditional posterior density ordinates computed
to estimate the numerator

se_components an Nx30 matrix containing the log-Bayes factors on the basis of which the standard errors are computed

Author(s)

Tomasz Woźniak <wozniak.tom@pm.me>

References

Lütkepohl, H., and Woźniak, T., (2020) Bayesian Inference for Structural Vector Autoregressions Identified by Markov-Switching Heteroskedasticity. *Journal of Economic Dynamics and Control* **113**, 103862, doi:10.1016/j.jedc.2020.103862.

Lütkepohl, H., Shang, F., Uzeda, L., and Woźniak, T., (2023) Partial Identification of Heteroskedastic Structural VARs: Theory and Bayesian Inference.

See Also

```
specify_bsvar_sv, estimate
```

Examples

Index

* datasets	specify_bsvar, 16, 18, 30, 48, 67
us_fiscal_ex,99	specify_bsvar_mix, 16, 20, 21, 31, 33, 51,
us_fiscal_lsuw, 100	71, 114
* models	specify_bsvar_msh, 16, 23, 24, 34, 36, 53,
bsvars-package, 3	76, 116
* package	specify_bsvar_sv, 16, 27, 39, 57, 81, 117
bsvars-package, 3	specify_data_matrices, 60
* ts	specify_identification_bsvars, 62
bsvars-package, 3	specify_posterior_bsvar, 18, 30, 50, 64
, ,	specify_posterior_bsvar_mix, 21, 33, 53,
bsvars (bsvars-package), 3	68
bsvars-package, 3	${\tt specify_posterior_bsvar_msh}, {\it 24, 36, 55},$
	73
compute_conditional_sd, 5	specify_posterior_bsvar_sv, 27, 39, 59,
compute_fitted_values, 6	78
compute_historical_decompositions, 7	specify_prior_bsvar,83
compute_impulse_responses, 9, 14	specify_prior_bsvar_mix, 85
compute_regime_probabilities, 10	specify_prior_bsvar_msh, 86
compute_structural_shocks, 12	specify_prior_bsvar_sv, 88
compute_variance_decompositions, 13	specify_starting_values_bsvar,90
	specify_starting_values_bsvar_mix,93
estimate, 5, 6, 8, 9, 11, 12, 14, 14, 47, 50, 53,	specify_starting_values_bsvar_msh,94
55, 59, 67, 71, 76, 81, 114, 116, 117	specify_starting_values_bsvar_sv,97
estimate.BSVAR, 17	
estimate.BSVARMIX, 19	us_fiscal_ex,99
estimate.BSVARMSH, 22	us_fiscal_lsuw, 100
estimate.BSVARSV, 25	101
estimate.PosteriorBSVAR, 28	verify_autoregression, 101
estimate.PosteriorBSVARMIX, 30	verify_autoregression.PosteriorBSVAR,
estimate.PosteriorBSVARMSH, 33	102
estimate.PosteriorBSVARSV, 37	$\begin{tabular}{l} verify_autoregression. Posterior BSVARMIX, \\ 104 \end{tabular}$
forecast, 40	$verify_autoregression. Posterior BSVARMSH,\\$
forecast.PosteriorBSVAR,41	106
forecast.PosteriorBSVARMIX,42	verify_autoregression.PosteriorBSVARSV,
forecast.PosteriorBSVARMSH,44	108
forecast.PosteriorBSVARSV,45	verify_volatility, 110
	verify_volatility.PosteriorBSVAR,111
normalise_posterior, 5, 8, 9, 11, 12, 14, 16,	verify_volatility.PosteriorBSVARMIX,
18, 21, 24, 27, 30, 33, 36, 39, 46	112

120 INDEX

```
\begin{tabular}{ll} verify\_volatility.PosteriorBSVARMSH,\\ 114\\ verify\_volatility.PosteriorBSVARSV,\\ 116\\ \end{tabular}
```