

Regular button


Initiate an action or event when clicked.

- Overview
- Specs
- Guidelines

States


All button variants support five distinct interaction states: default, hover, pressed, focus and disabled. To learn more about each interaction state, visit the [button guidelines](#).

- onLite
- onHeavy
- onPhoto



Size

The buttons come in three sizes: small, medium and large. The width of the buttons adapt to the content inside. Each size can be made full-width.




If the text exceeds the maximum width of the button, it should be truncated and shown with an ellipsis.


Size	Usage	Height	Target height	Max width	Icon size
Small	Where there is limited space.	38px	38px	800px	S
Medium	Default button for components and pages.	48px	48px	800px	M
Large	In larger components, such as heroes, or for specific use cases.	56px	56px	800px	M
Full-width	Within a fixed-width panel or container.	Matches S, M, or L	Matches S, M, or L	100% of container width	Matches S, M, or L

Placement


When arranging buttons, always consider their hierarchy and align them according to typical reading patterns. Primary buttons should always be placed before secondary buttons.




Place the primary button on the left to align it with typical reading patterns.



Place the primary button above the secondary button to emphasize the main action.




Don't place two primary buttons side by side.



Don't place secondary button left of the primary button.

Spacing

In both horizontal and vertical arrangements, buttons should have the `spacing-xs` token (16px) applied as `spacing` between them. Always ensure there is consistent spacing between each button in the group.



Color

> onLite

▼ onHeavy

Primary

Default





#ffffff





#ffffff

Action Primary Default onHeavy





#171a22





#171a22

Text Always Black

Hover





#f4f6f9





#c7ccd3

Action Primary Hover onHeavy





#171a22





#171a22

Text Always Black

Focus





#e9edf3





#e9edf3

Action Primary Pressed onHeavy









#171a22

#171a22

Text Always Black




#ffffff




#ffffff

Action Focus onHeavy

Pressed



#e9edf3



#e9edf3

Action Primary Pressed onHeavy



#171a22



#171a22

Text Always Black

Disabled




#a6acb5



#3c414a

Action Disabled



#d9dde3



#a6acb5

Action Disabled Content

Secondary

Default




#ffffff



#ffffff

Action Primary Default onHeavy

Hover



#f4f6f9



#c7ccd3

Action Primary Hover onHeavy




#171a22


#171a22

Text Always Black

Focus




#ffffff




#ffffff

Action Focus onHeavy




#e9edf3




#e9edf3

Action Primary Pressed onHeavy

Pressed



#e9edf3



#e9edf3

Action Primary Pressed onHeavy



#171a22



#171a22

Text Always Black

Disabled



#a6acb5



#3c414a

Action Disabled

Tertiary

Default




#ffffff




#ffffff

Action Primary Default onHeavy

Hover




#f4f6f9




#c7ccd3

Action Primary Hover onHeavy

Focus



#ffffff



#ffffff

Action Focus onHeavy




#ffffff




#ffffff

Action Primary Default onHeavy

Pressed



#e9edf3



#e9edf3

Action Primary Pressed onHeavy

Disabled



#a6acb5



#3c414a

Action Disabled

> onPhoto



Regular button
Overview

Regular button
Guidelines

