

Share

Provide ways to share content.


- Overview
- Specs
- Guidelines

Properties

Property	Values	Default
Size Variant	S L	L
State Variant	Default Hover Active Focus Disabled	Default

States

- Share button
- Share menu items



The share button, as well as the share options in the mini menu, have five interaction states.

- Default
- Hover
- Focus
- Active or pressed
- Disabled

To learn more about each interaction state, visit the [button guidelines](#).

Typography

Size	Share button label	Share menu item label
Small	heading-2xs-300	heading-2xs-300

Size	Share button label	Share menu item label
Large	heading-xs-300	heading-2xs-300

Size specs

Share button size

The share button has a small and large size.

Small

Large

Element	Property	Description	Value/px	Token
Download button	height		40	-
	spacing	between icon and label	8	spacing-2xs
Icon	width, height		small / 16	-

Share menu size

The share menu has one size that adapts to the viewport.

Mobile

Desktop and tablet

Element	Property	Description	Value/px	Token
Share menu	width		100%	-
	spacing	between menu items	24	spacing-s
	margin padding top		24	spacing-s
	padding-bottom, padding-left, padding-right		16	spacing-xs
	border		1	stroke-m
Share menu item	height		40	-
	spacing	between icon and label	8	spacing-2xs
Share menu item label	max height		35	-
	max width		170	-
Download icon	width, height		16	-
Close button	width, height		40	-

Limitations

Share menu


The mini menu can contain a maximum of six share options.

Character limit

Each share option in the share menu has a maximum of 25 characters.


Placement

Place the share component close to the content it refers to. Ideally, position it in the top-right or bottom-right corner of the related content, though other placements are acceptable if needed.




With Download button

The share button should always be placed to the left of the [Download](#) button.



Place the share button to the left of the download button.







Don't place the download button to the left of the share button.

Floating Share menu placement

- The share menu is positioned near the button and adjusts automatically to stay visible within the viewport.
- If space is limited, the menu shifts or flips its position for optimal display.

This ensures the menu remains accessible and easy to interact with across different screen sizes.




Color

- Share button color
- Share menu item color
- Page overlay color

Default




#595e6a




#f1f4f7

Text Secondary

Hover




#171a22




#f8fafc

Text Primary

Focus



#595e6a



#f1f4f7

Text Secondary



#2e323a




#f1f4f7

Active



#171a22



#f8fafc

Text Primary

Disabled



#a6acb5



#3c414a

Action Disabled



Share
Overview

Share
Guidelines

