## Lesson 8 Companion

## Confidence intervals for a single mean:

I'm not going to re-hash the example code from Lesson 6 here so please review that document if you have any questions. Instead I'm going to demonstrate finding critical values using the t-distribution. I will use the time estimates data from Lesson 7.

```
library(tidyverse)
estimates = read_table2("http://www.isi-stats.com/isi/data/chap3/TimeEstimate.txt")
sample_stat = mean(estimates$Time)
sample_size = nrow(estimates)
standard_deviation = sd(estimates$Time)
```

Once again, if we are interested in finding a confidence interval (CI), we will start with the sample statistic as the center of our range of plausible values for parameter value. From here we need to establish our critical values or "the multiplier" in the book's equation. Unfortunately, as the t-distribution is shaped a little bit differently depending on the degrees of freedom (related to the sample size here), we don't have something similar to the 68-95-99 Rule. Fortunately, R is awesome and that's not a big deal.

Just like **pnorm()** has a sibling **qnorm()**, **pt()** has a sibling **qt()**. They're basically a superhero family that we can use to calculate our critical values. For a 95% CI, we would use:

```
qt(0.025, df = sample_size - 1)
## [1] -2.063899
qt(0.975, df = sample_size - 1)
```

## ## [1] 2.063899

That's pretty close to 2 which is why the book suggests the 2SD Method for both the one-sample z-interval and the one-sample t-interval. Unlike the one-sample z-interval we can't easily "relocate" our t-distribution to be centered at our sample statistic using parameters in the qt() function but the equation offered in your book basically accomplishes this.

```
lower = sample_stat + qt(0.025, df = sample_size - 1) *
  (standard_deviation / sqrt(sample_size))

upper = sample_stat + qt(0.975, df = sample_size - 1) *
  (standard_deviation / sqrt(sample_size))

paste("(",lower, ",", upper, ")")
```

```
## [1] "( 11.5643745096081 , 16.0356254903919 )"
```

I want to stress taking a moment at this point and asking yourself: "Does this make sense as a range of plausible values for my parameter?" I, of course, never make a msitaek in coding but you just might and so it helps to examine your answer as a check. Is it plausible, given what we know (our sample), that we can be

95% confident that the population average time estimate is between 11.6 and 16.0 seconds? I think it is and therefore I can be fairly comfortable that I've accurately calculated this CI. It's not a definitive check but it just might save you from making a silly mistake.

You may recall seeing a very similar CI supplied by our  $\mathbf{t.test}()$  function last lesson. Try to control your excitement but R will calculate a CI for whatever confidence level your want using this function. Another way to check your answer!

```
null_mean = 10

t.test(estimates, mu = null_mean, alternative = "two.sided", conf.level = 0.95)

##

## One Sample t-test

##

## data: estimates

## t = 3.5081, df = 24, p-value = 0.001806

## alternative hypothesis: true mean is not equal to 10

## 95 percent confidence interval:

## 11.56437 16.03563

## sample estimates:

## mean of x

## 13.8
```

## Practical importance:

Let's discuss the practical importance of the outcome of our test. We see that the result is statistically significant meaning that our sample statistic was too unlikely to happen by chance alone (p-value of 0.001806). We can also see that we are 95% confident that the true length estimate falls between 11.6 and 16 seconds. Is the difference between this range and 10 seconds (null hypothesis value) practically important?

While the answer to this is obviously a matter of opinion, I would say our result is practically important. We are 95% confident that the average person, at best, overestimates the snippet length by at least 15%. That seems like a lot to me and suggests that there is evidence that we may not be good estimators of time.