

Q Search

Topics >

Qt 6.4 > qmake Manual > Replace Functions

Replace Functions

qmake provides functions for processing the contents of variables during the configuration process. These functions are called *replace functions*. Typically, they return values that you can assign to other variables. You can obtain these values by prefixing a function with the \$\$ operator. Replace functions can be divided into built-in functions and function libraries.

See also Test Functions.

Built-in Replace Functions

Basic replace functions are implemented as built-in functions.

absolute_path(path[, base])

Returns the absolute path of path.

If base is not specified, uses the current directory as the base directory. If it is a relative path, it is resolved relative to the current directory before use.

For example, the following call returns the string "/home/johndoe/myproject/readme.txt":

```
message($$absolute_path("readme.txt", "/home/johndoe/myproject"))
```

This function was introduced in Qt 5.0.

See also clean_path(), relative_path().

basename(variablename)

Returns the basename of the file specified in variablename.

For example:

```
FILE = /etc/passwd
FILENAME = $$basename(FILE) #passwd
```



- blob returns the entire contents of the file as one value
- lines returns each line as a separate value (without line endings)
- true (default value) and false return file contents as separate values, split according to qmake value list splitting rules (as in variable assignments). If mode is false, values that contain only a newline character are inserted into the list to indicate where line breaks were in the file.

clean_path(path)

Returns path with directory separators normalized (converted to "/") and redundant ones removed, and "."s resolved (as far as possible). This function is a wrapper around QDir::cleanPath.

This function was introduced in Qt 5.0.

See also absolute _path(), relative _path(), shell _path(), system _path().

dirname(file)

Returns the directory name part of the specified file. For example:

```
FILE = /etc/X11R6/XF86Config
DIRNAME = $$dirname(FILE) #/etc/X11R6
```

enumerate_vars

Returns a list of all defined variable names.

This function was introduced in Qt 5.0.

escape_expand(arg1 [, arg2 ..., argn])

Accepts an arbitrary number of arguments. It expands the escape sequences \n , \r , \t for each argument and returns the arguments as a list.

Note: If you specify the string to expand literally, you need to escape the backslashes, as illustrated by the following code snippet:

```
message("First line$$escape_expand(\\n)Second line")
```

find(variablename, substr)

Returns all the values in variablename that match the regular expression substr.

```
MY_VAR = one two three four

MY_VAR2 = $$join(MY_VAR, " -L", -L) -Lfive
```



MY_VAR2 will contain '-Lone -Ltwo -Lthree -Lfour -Lfive', and MY_VAR3 will contain 'three two three'.

files(pattern[, recursive=false])

Expands the specified wildcard pattern and returns a list of filenames. If recursive is true, this function descends into subdirectories.

first(variablename)

Returns the first value of variablename.

For example, the following call returns firstname:

```
CONTACT = firstname middlename surname phone
message($$first(CONTACT))
```

See also take_first(), last().

format number(number[, options...])

Returns number in the format specified by options. You can specify the following options:

- ibase=n sets the base of the input to n
- obase=n sets the base of the output to n
- > width=n sets the minimum width of the output to n. If the output is shorter than width, it is padded with spaces
- zeropad pads the output with zeroes instead of spaces
- padsign prepends a space to positive values in the output
- alwayssign prepends a plus sign to positive values in the output
- leftalign places the padding to the right of the value in the output

Floating-point numbers are currently not supported.

For example, the following call converts the hexadecimal number BAD to 002989:

```
message($$format_number(BAD, ibase=16 width=6 zeropad))
```

This function was introduced in Qt 5.0.

fromfile(filename, variablename)

Evaluates filename as a gmake project file and returns the value assigned to variablename.

See also infile().



\$\$(variablename) syntax. The getenv function, however, supports environment variables with parentheses in their name.

This function was introduced in Qt 5.12.

join(variablename, glue, before, after)

Joins the value of variablename with glue. If this value is not empty, this function prefixes the value with before and suffixes it with after. variablename is the only required field, the others default to empty strings. If you need to encode spaces in glue, before, or after, you must quote them.

last(variablename)

Returns the last value of variablename.

For example, the following call returns phone:

```
CONTACT = firstname middlename surname phone
message($$last(CONTACT))
```

See also take_last(), first().

list(arg1 [, arg2 ..., argn])

Takes an arbitrary number of arguments. It creates a uniquely named variable that contains a list of the arguments, and returns the name of that variable. You can use the variable to write a loop as illustrated by the following code snippet

```
for(var, $$list(foo bar baz)) {
    ...
}
```

instead of:

```
values = foo bar baz
for(var, values) {
    ...
}
```

lower(arg1 [, arg2 ..., argn])

Takes an arbitrary number of arguments and converts them to lower case.

See also upper().



If start is not given, it defaults to zero. This usage is equivalent to \$\$first(variablename).

If end is not given, it defaults to start. This usage represents simple array indexing, as exactly one element will be returned.

It is also possible to specify start and end in a single argument, with the numbers separated by two periods.

Negative numbers represent indices starting from the end of the list, with -1 being the last element.

If either index is out of range, an empty list is returned.

If end is smaller than start, the elements are returned in reverse order.

Note: The fact that the end index is inclusive and unordered implies that an empty list will be returned only when an index is invalid (which is implied by the input variable being empty).

See also str_member().

num_add(arg1 [, arg2 ..., argn])

Takes an arbitrary number of numeric arguments and adds them up, returning the sum.

Subtraction is implicitly supported due to the possibility to simply prepend a minus sign to a numeric value to negate it:

```
sum = $$num_add($$first, -$$second)
```

If the operand may be already negative, another step is necessary to normalize the number:

```
second_neg = -$$second
second_neg ~= s/^--//
sum = $$num_add($$first, $$second_neg)
```

This function was introduced in Qt 5.8.

prompt(question [, decorate])

Displays the specified question, and returns a value read from stdin.

If decorate is true (the default), the question gets a generic prefix and suffix identifying it as a prompt.

quote(string)

Converts a whole string into a single entity and returns the result. This is just a fancy way of enclosing the string into double quotes.

re escape(string)



read_registry(tree, key[, flag])

Returns the value of registry key key inside the tree tree.

Only the trees HKEY_CURRENT_USER (HKCU) and HKEY_LOCAL_MACHINE (HKLM) are supported.

The flag may be WOW64_32KEY (32) or WOW64_64KEY (64).

Note: This function is available only on Windows hosts.

This function was introduced in Qt 5.12.1.

relative_path(filePath[, base])

Returns the path to filePath relative to base.

If base is not specified, it is the current project directory. If it is relative, it is resolved relative to the current project directory before use.

If filePath is relative, it is first resolved against the base directory; in that case, this function effectively acts as \$\$clean_path().

This function was introduced in Qt 5.0.

See also absolute_path(), clean_path().

replace(string, old_string, new_string)

Replaces each instance of old_string with new_string in the contents of the variable supplied as string. For example, the code

```
MESSAGE = This is a tent.
message($$replace(MESSAGE, tent, test))
```

prints the message:

This is a test.

resolve_depends(variablename, prefix)

This is an internal function that you will typically not need.

This function was introduced in Qt 5.0.

reverse(variablename)

Returns the values of variablename in reverse order.



section(variablename, separator, begin, end)

Returns a section of the value of variablename. This function is a wrapper around QString::section.

For example, the following call outputs surname:

```
CONTACT = firstname:middlename:surname:phone
message($$section(CONTACT, :, 2, 2))
```

shadowed(path)

Maps the path from the project source directory to the build directory. This function returns path for in-source builds. It returns an empty string if path points outside of the source tree.

This function was introduced in Qt 5.0.

shell_path(path)

Converts all directory separators within path to separators that are compatible with the shell that is used while building the project (that is, the shell that is invoked by the make tool). For example, slashes are converted to backslashes when the Windows shell is used.

This function was introduced in Qt 5.0.

See also system_path().

shell_quote(arg)

Quotes arg for the shell that is used while building the project.

This function was introduced in Qt 5.0.

See also system_quote().

size(variablename)

Returns the number of values of variablename.

See also str_size().

sort_depends(variablename, prefix)

This is an internal function that you will typically not need.

This function was introduced in Qt 5.0.

sorted(variablename)

Returns the list of values in variablename with entries sorted in ascending ASCII order.

Numerical sorting can be accomplished by zero-padding the values to a fixed length with the help of the format_number() function.



split(variablename, separator)

Splits the value of variablename into separate values, and returns them as a list. This function is a wrapper around QString::split.

For example:

```
CONTACT = firstname:middlename:surname:phone
message($$split(CONTACT, :))
```

sprintf(string, arguments...)

Replaces %1-%9 in string with the arguments passed in the comma-separated list of function arguments and returns the processed string.

str_member(arg [, start [, end]])

This function is identical to member(), except that it operates on a string value instead of a list variable, and consequently the indices refer to character positions.

This function can be used to implement many common string slicing operations:

```
# $$left(VAR, len)
left = $$str_member(VAR, 0, $$num_add($$len, -1))

# $$right(VAR, len)
right = $$str_member(VAR, -$$num, -1)

# $$mid(VAR, off, len)
mid = $$str_member(VAR, $$off, $$num_add($$off, $$len, -1))

# $$mid(VAR, off)
mid = $$str_member(VAR, $$off, -1)

# $$reverse(VAR)
reverse = $$str_member(VAR, -1, 0)
```

Note: In these implementations, a zero len argument needs to be handled separately.

See also member(), num_add().

This function was introduced in Qt 5.8.

str_size(arg)

Returns the number of characters in the argument.

See also size().



system(command[, mode[, stsvar]])

You can use this variant of the system function to obtain stdout from the command and assign it to a variable.

For example:

```
UNAME = $$system(uname -s)
contains( UNAME, [lL]inux ):message( This looks like Linux ($$UNAME) to me )
```

Like \$\$cat(), the *mode* argument takes blob, lines, true, and false as value. However, the legacy word splitting rules (i.e. empty or true, and false) differ subtly.

If you pass stsvar, the command's exit status will be stored in that variable. If the command crashes, the status will be -1, otherwise a non-negative exit code of the command's choosing. Usually, comparing the status with zero (success) is sufficient.

See also the test variant of system().

system_path(path)

Converts all directory separators within path to separators that are compatible with the shell that is used by the system() functions to invoke commands. For example, slashes are converted to backslashes for the Windows shell.

This function was introduced in Qt 5.0.

See also shell path().

system_quote(arg)

Quotes arg for the shell that is used by the system() functions.

This function was introduced in Qt 5.0.

See also shell_quote().

take first(variablename)

Returns the first value of variablename and removes it from the source variable.

This provides convenience for implementing queues, for example.

This function was introduced in Qt 5.8.

See also take_last(), first().

take_last(variablename)

Returns the last value of variablename and removes it from the source variable.

This provides convenience for implementing stacks, for example.

This function was introduced in Qt 5.8.



urrique(variableriarrie)

Returns the list of values in variablename with duplicate entries removed. For example:

```
ARGS = 1 2 3 2 5 1
ARGS = $$unique(ARGS) #1 2 3 5
```

upper(arg1 [, arg2 ..., argn])

Takes an arbitrary number of arguments and converts them to upper case.

See also lower().

val_escape(variablename)

Escapes the values of variablename in a way that enables parsing them as qmake code.

This function was introduced in Qt 5.0.

< Variables Test Functions >

© 2022 The Qt Company Ltd. Documentation contributions included herein are the copyrights of their respective owners. The documentation provided herein is licensed under the terms of the GNU Free Documentation License version 1.3 as published by the Free Software Foundation. Qt and respective logos are trademarks of The Qt Company Ltd. in Finland and/or other countries worldwide. All other trademarks are property of their respective owners.













Company

About Us

Investors

Newsroom

Careers

Office Locations

Licensing

Terms & Conditions

Open Source

FAQ

Support

Support Services

For Customers

Support Center



Training Contact Us

Customer Success

Community

Contribute to Qt

Forum

Wiki

Downloads

Marketplace

© 2022 The Qt Company

Feedback Sign In