The Classic CPU Performance Equation

We can now write this basic performance equation in terms of **instruction count** (the number of instructions executed by the program), CPI, and clock cycle time:

instruction count The number of instructions executed by the program.

CPU time = Instruction count \times CPI \times Clock cycle time

or, since the clock rate is the inverse of clock cycle time:

$$CPU time = \frac{Instruction count \times CPI}{Clock rate}$$

These formulas are particularly useful because they separate the three key factors that affect performance. We can use these formulas to compare two different implementations or to evaluate a design alternative if we know its impact on these three parameters.

Comparing Code Segments

A compiler designer is trying to decide between two code sequences for a particular computer. The hardware designers have supplied the following facts:

EXAMPLE

	CPI for each instruction class			
	A	В	C	
CPI	1	2	3	

For a particular high-level language statement, the compiler writer is considering two code sequences that require the following instruction counts:

	Instruction counts for each instruction class		
Code sequence	A	В	C
1	2	1	2
2	4	1	1

Which code sequence executes the most instructions? Which will be faster? What is the CPI for each sequence?