Main and cross axes (OPTIONAL)

Note: This material has been included for completeness. But many are able to use flexbox satisfactorily without it. None of the material here will appear in any graded question.

CONCEPTS


Before we step deeper into flexbox, there are a few concepts we should make sure to understand.

Main axis and cross axis

Every flexbox has two axes. The "main" axis is the major axis along which all the flex items are being laid. So, when the flex-direction is row, the main axis is horizontal, running left to right. When the flex-direction is column, the main axis is vertical, running top to bottom. (Quick quiz: what if the flex-direction isrow-reverse?).

The "cross" axis runs perpendicular to the main axis. It is the direction that items might wrap. So with flex-flow: row wrap; the cross axis is vertical and runs top to bottom. And with flex-flow: row wrap-reverse; it is vertical running bottom to top.

Start and end



In the illustration above, we see the main and cross axes as they would be for flex-flow:row wrap; And in that illustration, we also see the start and end points for both the main and cross axes. Take a moment and visualize how both the axes *and* the start and end points would change for each of these combinations for flex-flow

- row wrap
- row wrap-reverse
- row-reverse wrap
- row-reverse wrap-reverse
- column wrap
- column wrap-reverse

- column-reverse wrap
- column-reverse wrap-reverse

main axis for sizing, cross axis for alignment

The terms "main" and "cross" appear in the descriptions of flexbox and in the many online tutorials you might find. But they are **not**used in the names of any CSS properties or values. The following properties control behavior along the main axis. We are already familiar with all of them, except justify-content.

- flex
- flex-grow
- flex-shrink
- flex-basis
- justify-content

All the properties above control how a flex item might be *sized*, except justify-content which controls how a flexbox container spaces out and positions flex-items.

And obversely, the following list of properties controls behavior along the cross axis:

- align-content
- align-items
- align-self

These properties all govern how a flex item might be *aligned* or positioned along the cross axis. They also support a simple **stretch**value, which we will see when we cover them.

Important: flexbox items can have their size and position influenced on the main axis, with flex-grow, and others. But on the cross axis, with the exception of a coarse stretch option, we can only influence their position. This distinction is very important. In the cross axis direction our ability to influence the sizing is limited. When not using stretch we'll get the normal sizing behavior (block level elements take vertical size of content, etc) or use the regular sizing properties (min-height, max-height, height, etc)

flex-start and flex-end are contextual

We will begin to see the values flex-start and flex-end in the next section as we look at alignment and justification. Just as the terms "main" and "cross" do not appear as CSS terms, know thatflex-start and flex-end are contextual. When used with thejustify-content property, flex-start and flex-end refer to the "main start" and "main end" sides (as in the illustration above). When used with any of the flexbox align properties, flex-start and flex-end refer to the "cross start" and "cross end" sides.