This week

- Assignment I due Tuesday: you'll have proved your baremetal mettle!
- Lab 2 prep
 - do pre-lab reading!
 - bring your tools if you have them



Goals for today

- Pointers, pointers, and more pointers!
- ARM addressing modes, translation to/from C
- Details: volatile qualifier, bare-metal build

Memory


Memory is a linear sequence of bytes

Addresses start at 0, go to 2³²-1 (32-bit architecture)

100000000₁₆ 4 GB

02000000016

512 MB



ARM load/store instructions

```
ldr r0, [r1]
str r0, [r1]
```

Store is a misfit among ARM instructions — operands are in order of src, dst (reverse of all other instructions)

ASM and memory

At the assembly level, a 4-byte word could represent

- an address,
- an int,
- 4 characters
- an ARM instruction

The Idr/str instructions are agnostic to type: assembly has no type system to guide or restrict us on what we do with those words.

Funny program

pc is the register containing the address of the current instruction (processor updates it on each execution, changes it on branch instructions)

What does this program do?

```
ldr r1, [pc]
add r1, r1, #1
str r1, [pc]
```

C pointer types

An address is a memory location, represented as an unsigned int (because this is a 32-bit architecture).

A pointer is a variable that holds an address.

The "pointee" is the data stored at that address.

| * | 0x05 | 0x00 | 0x00 | 0x00 |
|----------|------|------|------|------|
| | 0x0c | 0x81 | 0x00 | 0x00 |

Why Pointers?

Access specific memory locations like FSEL2

Pointers can be used to reference elements of an array

Pointers allow for creating dynamic data structures at runtime

Pointers can be used to efficiently share/pass references without making copies of large data structures

Pointers are used in data structures to reference other data structures

```
int val = 5;
int* ptr = &val;
```

0x0000810c

| * | 0x05 | 0x00 | 0x00 | 0x00 |
|----------|------|------|------|------|
| | 0x0c | 0x81 | 0x00 | 0x00 |

0x0000810c

0x00008110


| → | 0x05 | 0x00 | 0x00 | 0x00 |
|----------|------|------|------|------|
| | 0x0c | 0x81 | 0x00 | 0x00 |

0x0000810c

| | 0x07 | 0x00 | 0x00 | 0x00 |
|---------|------|------|------|------|
| | 0x0c | 0x81 | 0x00 | 0x00 |

0x0000810c

0x00008110



$$*ptr = 7;$$


0x0000810c

0x00008110

| | 0x07 | 0x00 | 0x00 | 0x00 |
|---------|------|------|------|------|
| | 0x0c | 0x81 | 0x00 | 0x00 |

0x0000810c

0x00008110



| <pre>int val = 5;</pre> | 0x0000810c | \ | 0x05 | 0x00 | 0x00 | 0x00 |
|--------------------------------|------------|-------------|------|------|------|------|
| <pre>int* ptr = &val</pre> | 0x00008110 | | 0x0c | 0x81 | 0x00 | 0x00 |
| | | Γ | | | | |
| *ptr = 7; | 0x0000810c | | 0x07 | 0x00 | 0x00 | 0x00 |
| • | 0x00008110 | | 0x0c | 0x81 | 0x00 | 0x00 |
| | 0.000010 | [| | | | |
| | 0x0000810c | | 0x07 | 0x00 | 0x00 | 0x00 |
| int** dptr = &ptr | 0x00008110 | > | 0x0c | 0x81 | 0x00 | 0x00 |
| | 0x00008114 | | 0x10 | 0x81 | 0x00 | 0x00 |
| | | | | | | |
| | 0x0000810c | | 0x07 | 0x00 | 0x00 | 0x00 |
| *dptr = NULL; | 0x00008110 | \ | 0x00 | 0x00 | 0x00 | 0x00 |

0x00008114

0x10 0x81 0x00 0x00

```
char a = 'a';
char b = 'b'
char* ptr = &b;
```

0x0000810c

| | -0×61 | 0x62 | | |
|---|-------|------|------|------|
| | ʻa' | ʻb' | 0x00 | 0x00 |
| 1 | 0x0d | 0x81 | 0x00 | 0x00 |


```
char a = 'a';
char b = 'b'
char* ptr = &b;
```

0x0000810c

0x00008110

*ptr = 'c';

0x0000810c




```
char a = 'a';
char b = 'b'
char* ptr = &b;

*ptr = 'c';

0x0000810c
0x00008110

0x00008110

0x00008110
```



char a = 'a'; char b = 'b' char* ptr = &b;

0x0000810c

0x00008110

*ptr = 'c';

0x0000810c

0x00008110

char** dptr = &ptr;

0x0000810c

0x00008110

0x00008114

| *d | ptr | = | NUL | L ; |
|----|-----|---|-----|------------|
| • | P | | | · — , |

0x0000810c

0x00008110

0x00008114

| | -0×61 | 0x62 | | |
|---|-------|------|------|------|
| | ʻa' | ʻb' | 0x00 | 0x00 |
| \ | 0x0d | 0x81 | 0x00 | 0x00 |
| | | 0x63 | | |
| | 'a' | 'C' | 0x00 | 0x00 |
| \ | 0x0c | 0x81 | 0x00 | 0x00 |
| | | | | |
| | ʻa' | 'C' | 0x00 | 0x00 |
| | 0x0c | 0x81 | 0x00 | 0x00 |
| | 0x10 | 0x81 | 0x00 | 0x00 |
| | | _ | | _ |

'a'

0x00 0x00

|0x00|0x00

0x00|0x00|0x00|0x00

C pointer types

C has a type system: tracks the type of each variable.

Operations required to respect the data type.

Can't multiply int*'s, can't deference an int

Distinguishes pointer variables by type of pointee

- Dereferencing an int* is an int
- Dereferencing a char* is a char

C arrays

An array allocates multiple instances of a type contiguously in memory

```
char ab[2];
ab[0] = 'a';
ab[1] = 'b';
```

0x0000810c

| UXOI | UXOZ | |
|------|------|--|
| 'a' | ʻb' | |

OVET OVED

```
int ab[2];
ab[0] = 'a';
ab[1] = 9;

0x00008100
0x00008110
```

| 'a' | 0x00 | 0x00 | 0x00 |
|------|------|------|------|
| 0x09 | 0x00 | 0x00 | 0x00 |

Arrays and Pointers

You can assign an array to a pointer

```
int ab[2] = \{5, 7\};
int* ptr = ab; // ptr = &(ab[0]);
```

Incrementing pointers advances address by size of type

```
ptr = ptr + 1; // now points to ab[1]
```

What does the assembly look like? What if ab is a char[2] and ptr is a char*?

Pointer basics: & *

```
int m, n, *p, *q;
p = &n;
*p = n; // same as prev line?
q = p;
*q = *p; // same as prev line?
p = &m, q = &n;
*p = *q;
m = n;  // same as prev line?
```

Pointers and arrays

```
int n, arr[4], *p;
p = arr;
p = &arr[0]; // same as prev line?
*p = 3;
p[0] = 3; // same as prev line?
n = *(arr + 1);
n = arr[1]; // same as prev line?
```

Fancier addressing modes

Preindex, non-updating

Preindex, writeback (update dst before use)

Postindex (update dst after use)

Fancier addressing modes

Preindex, non-updating

Preindex, writeback (update dst before use)

Postindex (update dst after use)

C-strings

```
char *s = "Stanford";
  char arr[] = "University";
  char oldschool[] = {'L','e','l','a','n','d'};
  char buf[100];
  char *ptr;
                                                     64
                                                     63
   which assignments are valid?
                                                     61
  ptr = s;
                                                     6c
 ptr = arr;
                                                     65
3 ptr = buf;
                                                     4c
4 arr = ptr;
5 buf = oldschool;
```

What does a typecast actually do?

Aside: why is this even allowed?

Casting between different types of pointers — perhaps plausible

Casting between pointers and int — sketchy

Casting between pointers and float — bizarre

```
int *p; double *q; char *s;
```

```
ch = *(char *)p;
val = *(int *)s;
val = *(int *)q;
```

Power of Types and Pointers

```
struct gpio {
  unsigned int fsel[6];
  unsigned int reservedA;
  unsigned int set[2];
  unsigned int reservedB;
  unsigned int clr[2];
  unsigned int reservedC;
  unsigned int lev[2];
};
```

| Address | Field Name | Description | Size | Read/ Write |
|--------------|------------|-------------------------|------|----------------|
| 0x 7E20 0000 | GPFSEL0 | GPIO Function Select 0 | 32 | R/W |
| 0x 7E20 0000 | GPFSEL0 | GPIO Function Select 0 | 32 | R/W |
| 0x 7E20 0004 | GPFSEL1 | GPIO Function Select 1 | 32 | R/W |
| 0x 7E20 0008 | GPFSEL2 | GPIO Function Select 2 | 32 | R/W |
| 0x 7E20 000C | GPFSEL3 | GPIO Function Select 3 | 32 | R/W |
| 0x 7E20 0010 | GPFSEL4 | GPIO Function Select 4 | 32 | R/W |
| 0x 7E20 0014 | GPFSEL5 | GPIO Function Select 5 | 32 | R/W |
| 0x 7E20 0018 | - | Reserved | - | - |
| 0x 7E20 001C | GPSET0 | GPIO Pin Output Set 0 | 32 | w |
| 0x 7E20 0020 | GPSET1 | GPIO Pin Output Set 1 | 32 | w |
| 0x 7E20 0024 | - | Reserved | - | - |
| 0x 7E20 0028 | GPCLR0 | GPIO Pin Output Clear 0 | 32 | w |
| 0x 7E20 002C | GPCLR1 | GPIO Pin Output Clear 1 | 32 | w |
| 0x 7E20 0030 | - | Reserved | - | - |
| 0x 7E20 0034 | GPLEV0 | GPIO Pin Level 0 | 32 | R |
| 0x 7E20 0038 | GPLEV1 | GPIO Pin Level 1 | 32 | R |

```
volatile struct gpio *gpio = (struct gpio *)0x20200000;
gpio->fsel[0] = ...
```

Pointers: the fault in our *s

Pointers are ubiquitous in C, and inherently dangerous. Be vigilant!


Q. For what reasons might a pointer be invalid?

Q. What is consequence of using an invalid pointer?










C vs. Assembly

```
.equ DELAY, 0x3F0000
ldr r0, FSEL2
mov r1, #1
str r1, [r0]
mov r1, \#(1 << 20)
loop:
  ldr r0, SETO
  str r1, [r0]
  mov r2, #DELAY
  wait1:
    subs r2, #1
    bne wait1
  ldr r0, CLR0
  str r1, [r0]
  mov r2, #DELAY
  wait2:
    subs r2, #1
    bne wait2
  b loop
```





Let's do it!

Know your tools

Assembler (as)

- Transform assembly code (text) into object code (binary machine instructions)
- Mechanical translation, few surprises

Compiler (gcc)

- Transform C code (text) into object code
- (likely staged C-> asm -> object)
- Complex translation, high artistry

When coding directly in assembly, the instructions you see are the instructions you get, no surprises!

For C source, you may need to drop down to see what compiler has generated to be sure of what you're getting.

What transformations are *legal*? What transformations are *desirable*?

```
int i, j;
i = 1;
i = 2;
j = i;
// can be optimized to
i = 2;
j = i;
// is this ever not equivalent/ok?
```

button.c

The little button that wouldn't

Peripheral Registers

These registers are mapped into the address space of the processor (memory-mapped IO).

These registers may behave differently than memory.

For example: Writing a I into a bit in a SET register causes I to be output; writing a 0 into a bit in SET register does not affect the output value. Writing a I to the CLR register, sets the output to 0; write a 0 to a clear register has no effect. Neither SET or CLR can be read. To read the current value use the LEV (level) register.

volatile

For an ordinary variable, the compiler can use its knowledge of when it is read/written to optimize accesses as long as it keeps the same externally visible behavior.

However, for a variable that can be read/written externally (by another process, by peripheral), these optimizations will not be valid.

The **volatile** qualifier applied to a variable informs the compiler that it cannot remove, coalesce, cache, or reorder references. The generated assembly must faithfully execute each access to the variable as given in the C code.

What is 'bare metal'?

The default build process for C assumes a *hosted* environment. It provides standard libraries, all the stuff that happens before main.

To build bare-metal, our makefile disables these defaults; we must supply our own versions when needed.

```
int getRandomNumber()
{
    return 4; // chosen by fair dice roll.
    // guaranteed to be random.
}
```

Makefile settings

Compile freestanding

CFLAGS =-ffreestanding

Link without standard libs and start files

LDFLAGS = -nostdlib

Link with gcc to support division (violates

LDLIBS = -lgcc

Must supply own replacement for libs/start

That's where the fun is...!

Pseudo-instruction!

(assemblers are helpful)

LDR pseudo-instruction

Which of these **mov** instructions are valid?

```
mov r0, #0x7e
mov r0, #0x7e00000
mov r0, #0xfff00
mov r0, #0xfffffff
mov r0, #0x107e
```

LDR pseudo-instruction

Which of these **mov** instructions are valid?

```
mov r0, #0x7e
mov r0, #0x7e00000
mov r0, #0xfff00
mov r0, #0xfffffff
mov r0, #0x107e
```

For **Idr**= pseudo-instruction, any 32-bit constant is valid. If we replace **mov** with **Idr**=, what does assembler emit?

```
1dr r0, =0x107e
```

Program to set gpio 47 high (green led on Pi)

```
ldr r0, =0x20200020
mov r1, #(1<<15)
str r1, [r0]</pre>
```

Assembler emits:

```
e59f0004 ldr r0, [pc, #4]
e3a01902 mov r1, #32768; 0x8000
e5801000 str r1, [r0]
20200020 .word 0x20200020
```

Quiz: what does this program do

```
... on linux?
   ... on MacOS?
   ... on your Pi?
int main(int argc, char *argv[])
    unsigned int *start = 0x0,
                  *end = (unsigned int *)0x100000;
    for (unsigned int *addr = start; addr < end;
addr++)
         *addr = 0;
```