Lecture21 Memory Virtualization

1. 内存虚拟化

依托于CPU虚拟化


为什么需要内存虚拟化?

OS以为自己独占机器的全部物理内存

- 操作系统内核直接管理物理内存
 - 。 物理地址从0开始连续增长
 - 。 向上层进程提供虚拟内存的抽象
- 如果VM使用的是真实物理地址

正确性: 相当于进程看到了全部的物理地址,可能会修改其它"进程"的数据

安全性: 可能会被其它虚拟机访问到本虚拟机的数据



Physical Memory

内存虚拟化的目标

- 为虚拟机提供虚拟的物理地址空间
 - 物理地址从0开始增长
- 隔离不同虚拟机的物理地址空间
 - 。 VM-1无法访问其他的内存

三种地址


- 客户虚拟地址(Guest Virtual Address, GVA)
 - 虚拟机内进程使用的虚拟地址
- 客户物理地址(Guest Physical Address, GPA)
 - 虚拟机内使用的"假"物理地址
- 主机物理地址(Host Physical Address, HPA)
 - 真实寻址的物理地址
 - GPA需要翻译成HPA才能访存

怎么实现内存虚拟化?

- 1. 影子页表(Shadow Page Table)
- 2. 直接页表(Direct Page Table)
- 3. 硬件虚拟化

方法1: 影子页表

Shadow Page Table



硬件限制,只能由一套翻译机制

SPT: 直接将GVA -> HPA

VMM管理

Shadow Page Table 设置

```
set_cr3 (guest page table):
  for GVA in 0 to 2<sup>20</sup>
    if guest page table[GVA] & PTE_P:
        GPA = guest page table[GVA] >> 12
        HPA = host page table[GPA] >> 12
        shadow page table[GVA] = (HPA<<12)|PTE_P
    else
        shadow page table[GVA] = 0

CR3 = PHYSICAL_ADDR(shadow page table)</pre>
```

VMM维护了两个数据结构 guest_page_table 和 host_page_table

Guest OS修改页表,如何生效?

- Real hardware would start using the new page table's mappings
 - Virtual machine monitor has a separate shadow page table
- Goal:
 - VMM needs to intercept when guest OS modifies page table, update shadow page table accordingly
- Technique:
 - Use the read/write bit in the PTE to mark those pages read-only
 - If guest OS tries to modify them, hardware triggers page fault
 - Page fault handled by VMM: update shadow page table & restart guest

Trap住对页表进行写操作的指令(将SPT所在的页标记为read-only)

Guest内核如何与Guest应用隔离?

- How do we selectively allow / deny access to kernel-only pages in guest PT?
 - Hardware doesn't know about the virtual U/K bit
- Idea:
 - Generate two shadow page tables, one for U, one for K
 - When guest OS switches to U mode, VMM must invoke set_ptp(current, 0)

1个页表 -> 2个页表

U-SPT和K-SPT

方法2: Direct Paging(Para-virtualization)

- Modify the guest OS
 - No GPA is needed, just GVA and HPA
 - Guest OS directly manages its HPA space
 - Use hypercall to let the VMM update the page table
 - The hardware CR3 will point to guest page table
- VMM will check all the page table operations
 - The guest page tables are read-only to the guest

Guest直接管页表会带来安全风险,因此不能直接写CR3和页表,必须通过VMM来执行这种操作 (hypercall)

可以通过batch的思想去优化写入的性能

Positive

- Easy to implement and more clear architecture
- Better performance: guest can batch to reduce trap

Negatives

- Not transparent to the guest OS
- The guest now knows much info, e.g., HPA
 - · May use such info to trigger rowhammer attacks

方法3: 硬件虚拟化对内存翻译的支持

- · Intel VT-x和ARM硬件虚拟化都有对应的内存虚拟化
 - Intel Extended Page Table (EPT)
 - ARM Stage-2 Page Table (第二阶段页表)

・ 新的页表

- 将GPA翻译成HPA
- 此表被VMM直接控制
- 每一个VM有一个对应的页表


影子页表中每一个进程一个SPT,因为创建进程时会创建页表而SPT: GVA->HPA

本方法中的页表: GPA->HPA, 所以每个VM一个这种页表

翻译的过程

翻译过程

- ・ 总共24次内存访问
 - 为什么?
 - 25-1
 - 读TTBR0_EL1无需内存访问



TLB: 缓存地址翻译的结果

- · 回顾: TLB不仅可以缓存第一阶段地址翻译结果
- · TLB也可以第二阶段地址翻译后的结果
 - 包括第一阶段的翻译结果(GVA->GPA)
 - 包括第二阶段的翻译结果(GPA->HPA)
 - 大大提升GVA->HPA的翻译性能:不需要24次内存访问
- ・ 切换VTTBR_EL2时
 - 理论上应将前一个VM的TLB项全部刷掉

TLB刷新

・ 刷TLB相关指令

- 清空全部
 - TLBI VMALLS12E1IS
- 清空指定GVA
 - TLBI VAE1IS
- 清空指定GPA
 - TLBI IPAS2E1IS

VMID (Virtual Machine IDentifier)

- VMM为不同进程分配8/16 VMID,将VMID填写在VTTBR EL2的高8/16位
- VMID位数由VTCR_EL2的第19位 (VS位) 决定
- 避免刷新上个VM的TLB

如何处理缺页异常

- 两阶段翻译的缺页异常分开处理
- 第一阶段缺页异常
 - 。 直接调用VM的Page fault handler
 - 。 修改第一阶段页表不会引起任何虚拟机下陷
- 第二阶段缺页异常
 - 。 虚拟机下陷,直接调用VMM的Page fault handler

第二阶段页表的优缺点

- 优点
 - 1. VMM实现简单
 - 2. 不需要捕捉Guest Page Table的更新
 - 3. 减少内存开销:每个VM对应一个页表
- 缺点
 - 1. TLB miss时性能开销较大

如何实现虚拟机级别的内存换页?


・ 具体场景: 将虚拟机A的128MB内存转移到虚拟机B中

- 虚拟机A对内存的使用较少
- 虚拟机B对内存需求较大

问题

- VMM无法识别虚拟机内存的语义
- 两层内存换页机制
 - VM与VMM的换页机制可能彼此冲突,造成开销。

内存气球机制



VMM调upcall, 此时swap发生在VM的kmalloc中

红色的圈圈是一个驱动

缺点:太慢了

• 优点:修改了少量的代码,解决了两层swap冲突的问题