

YOU

You said We got an issue in my virtualbox after upgrading from 7.1.4r to .1.6r so, this is the issue what err... We got an issue in my virtualbox after upgrading from 7.1.4r to .1.6r so, this is the issue what error is this for VM Name: Parrot Security 6.0 The VM session was aborted. Result Code: NS_ERROR_FAILURE (0x80004005) Component: SessionMachine Interface: ISession {c0447716-ff5a-4795-b57a-ecd5fffa18a4}. I need us to try starting machine from terminal and see logs so we can know the issue

YOU

You said We got an issue in my virtualbox after upgrading from 7.1.4r to .1.6r so, this is the issue what err...

GEMINI

To view the full terminal log and isolate why the VM session is aborting after the VirtualBox 7.1.6 update, run the VM directly from your terminal using VBoxManage startvm.

Run VM from Terminal

Open your terminal and run the following command to start the VM in headless mode so all logs dump directly to the console:

Bash

VBoxManage startvm "Parrot Security 6.0" --type headless

If you prefer to attempt launching the full Graphical User Interface (GUI) window while capturing output, run:

Bash

VBoxManage startvm "Parrot Security 6.0" --type gui

How to verify success:

If the launch fails, the command will immediately output specific error lines directly into your terminal screen instead of just showing the generic NS_ERROR_FAILURE (0x80004005) dialog.

Check the Latest VBox.log File

If the terminal command produces a brief error or aborts immediately without detailed logs, check the persistent VirtualBox log file for the exact crash line.

Run this command to inspect the last 50 lines of the current log:

Bash

tail -n 50 "\$HOME/VirtualBox VMs/Parrot Security 6.0/Logs/VBox.log"

Look specifically near the end of the log output for lines containing ERROR, FATAL, or kernel module mismatch issues (such as vboxdrv version conflicts following the update).

What error output or console lines do you see when running the VBoxManage startvm command?

YOU

```
You said [Wed Sep 09 9:46:48 AM][remac@Intel5]~ [REMAC]$ VBoxManage startvm "Parrot Security 6.0" -...  
[Wed Sep 09 9:46:48 AM][remac@Intel5]~  
[REMAC]$ VBoxManage startvm "Parrot Security 6.0" --type headless  
Waiting for VM "Parrot Security 6.0" to power on...  
VBoxManage: error: The VM session was aborted  
VBoxManage: error: Details: code NS_ERROR_FAILURE (0x80004005), component SessionMachine, interface ISession  
[Wed Sep 09 9:47:04 AM][remac@Intel5]~  
[REMAC]$ VBoxManage list vms  
"Parrot Security 6.0" {ebaaeb5e-97bd-461b-8f88-0e5d2dfd7bdf}  
"Aether Lab" {255fb132-afd6-424c-9c5a-cbfb9c39e60}  
"Windows XP sp2" {cfaf11a7-da2e-45ab-ab50-b7b5fc65f262}  
"WINDOWS 10 - ENTERPRISE" {509ccbdf-2c27-4705-ac01-d0fc9b580321}  
[Wed Sep 09 9:47:07 AM][remac@Intel5]~  
[REMAC]$
```

YOU

```
You said [Wed Sep 09 9:46:48 AM][remac@Intel5]~ [REMAC]$ VBoxManage startvm "Parrot Security 6.0" -...
```

GEMINI

Since the front-end CLI returns the same high-level session abort error, the underlying cause will be recorded directly in the guest machine's log file or system ring buffer (dmesg).

Step 1: Read the Critical Error Lines from VBox.log

Run this command to search for error and fatal fault lines in the latest log file:

```
Bash  
grep -iE "error|fatal|fail" "$HOME/VirtualBox VMs/Parrot Security 6.0/Logs/VBox.log" | tail -n 25
```

How to verify: Check if the output points to a graphics driver issue (3D acceleration), missing extension pack version alignment, or saved state corruption.

Step 2: Check Kernel Ring Buffer for Driver Mismatches

VirtualBox updates (like 7.1.4 to 7.1.6) frequently break when host kernel modules (vboxdrv, vboxnetflt, vboxnetadp) are mismatched or blocked by Secure Boot/DKMS.

Run:

```
Bash  
sudo dmesg | grep -i vbox | tail -n 20
```

How to verify: Look for module loading failures, vboxdrv version mismatch errors, or kernel execution blocks.

Step 3: Clear Saved State (If VM was suspended during upgrade)

If the VM was in a saved state prior to upgrading to 7.1.6, the state snapshot is incompatible with the new engine binaries.

Discard the state (this does not affect your VM data/disk):

```
Bash  
VBoxManage discardstate "Parrot Security 6.0"
```

How to verify: Run `VBoxManage startvm "Parrot Security 6.0" --type headless` again to see if it boots cleanly.

What lines show up in your terminal when you run the `grep` and `dmesg` commands above?

You said `[Wed Sep 09 9:47:29 AM][remac@Intel5]~` `[REMAC]$ grep -iE "error|fatal|fail"`
`"$HOME/Virtual...`

`[Wed Sep 09 9:47:29 AM][remac@Intel5]~`
`[REMAC]$ grep -iE "error|fatal|fail" "$HOME/VirtualBox VMs/Parrot Security 6.0/Logs/VBox.log" | tail -n 25`
 00:00:00.228912 IgnoreConnectFailure <integer> = 0x0000000000000000 (0)
 00:00:00.241490 TM: GIP - CPU: iCpuSet=0x0 idCpu=0x0 idApic=0x0 iGipCpu=0x0 i64TSCDelta=0 enmState=3
 u64CpuHz=2711969906(*) cErrors=0
 00:00:00.241496 TM: GIP - CPU: iCpuSet=0x1 idCpu=0x1 idApic=0x2 iGipCpu=0x3 i64TSCDelta=0 enmState=3
 u64CpuHz=2711969584(*) cErrors=0
 00:00:00.241501 TM: GIP - CPU: iCpuSet=0x2 idCpu=0x2 idApic=0x1 iGipCpu=0x1 i64TSCDelta=0 enmState=3
 u64CpuHz=2711969893(*) cErrors=0
 00:00:00.241506 TM: GIP - CPU: iCpuSet=0x3 idCpu=0x3 idApic=0x3 iGipCpu=0x2 i64TSCDelta=0 enmState=3
 u64CpuHz=2711968565(*) cErrors=0
 00:00:00.317372 IntNet#0: szNetwork={HostInterfaceNetworking-wlp1s0} enmTrunkType=3 szTrunk=
 {4026531840/wlp1s0} fFlags=0x14001 cbRecv=325632 cbSend=196608 flgnoreConnectFailure=false
 00:00:00.318141 IntNet#1: szNetwork={HostInterfaceNetworking-vboxnet0} enmTrunkType=3 szTrunk={vboxnet0}
 fFlags=0x14000 cbRecv=325632 cbSend=196608 flgnoreConnectFailure=false
 00:00:00.318808 IntNet#2: szNetwork={TopGun} enmTrunkType=2 szTrunk={} fFlags=0x14000 cbRecv=325632
 cbSend=196608 flgnoreConnectFailure=false
 00:00:00.324222 HM: VM-entry Xcpt error-code optional = false
 00:00:00.334165 rldrNativeLoad: dlopen('D3DCompiler_47.so', RTLD_NOW | RTLD_LOCAL) failed:
 D3DCompiler_47.so: cannot open shared object file: No such file or directory

`[Wed Sep 09 9:47:30 AM][remac@Intel5]~`

`[REMAC]$`

`[REMAC]$ sudo dmesg | grep -i vbox | tail -n 20`

```
[ 10.697407] VBoxNetAdp: Successfully started.
[ 32.438583] vboxdrv: 00000000b13df41e VMMR0.r0
[ 32.586352] VBoxNetFlt: attached to 'vboxnet0' / 0a:00:27:00:00:00
[ 32.586496] vboxnet0: entered promiscuous mode
[ 32.698622] vboxdrv: 000000006ccefd80 VBoxDDR0.r0
[ 32.740184] VBoxNetFlt: attached to '4026531840/wlp1s0' / fa:5e:d8:d2:3c:f7
[ 32.854529] EMT-0[2682]: segfault at 7efd9d222000 ip 00007efd856d7930 sp 00007efd9f5fea90 error 7 in
VBoxDD.so[d7930,7efd8562f000+26e000] likely on CPU 0 (core 0, socket 0)
[ 32.873827] vboxnetflt: 0 out of 0 packets were not sent (directed to host)
[ 64.798676] vboxdrv: 000000004913abe6 VBoxDDR0.r0
[ 64.866691] VBoxNetFlt: attached to '4026531840/wlp1s0' / fa:5e:d8:d2:3c:f7
[ 64.948807] EMT-0[2835]: segfault at 7f7571444000 ip 00007f755e6d7930 sp 00007f75735feb80 error 7 in
VBoxDD.so[d7930,7f755e62f000+26e000] likely on CPU 0 (core 0, socket 0)
[ 64.973520] vboxnetflt: 0 out of 0 packets were not sent (directed to host)
[ 108.726269] vboxdrv: 000000002b30cae7 VBoxDDR0.r0
[ 108.767418] VBoxNetFlt: attached to '4026531840/wlp1s0' / fa:5e:d8:d2:3c:f7
[ 108.831566] EMT-0[3381]: segfault at 7fec93600000 ip 00007fec7d6d7959 sp 00007fec935feb80 error 6 in
VBoxDD.so[d7959,7fec7d62f000+26e000] likely on CPU 0 (core 0, socket 0)
[ 108.860500] vboxnetflt: 0 out of 0 packets were not sent (directed to host)
[ 426.245220] vboxdrv: 00000000a1f79e31 VBoxDDR0.r0
[ 426.287842] VBoxNetFlt: attached to '4026531840/wlp1s0' / fa:5e:d8:d2:3c:f7
[ 426.358795] EMT-0[4910]: segfault at 7f5434022000 ip 00007f542e6d7930 sp 00007f5436dfef80 error 7 in
VBoxDD.so[d7930,7f542e62f000+26e000] likely on CPU 1 (core 1, socket 0)
[ 426.386054] vboxnetflt: 0 out of 0 packets were not sent (directed to host)
```

`[Wed Sep 09 9:47:44 AM][remac@Intel5]~`

`[REMAC]$`

`[REMAC]$ VBoxManage discardstate "Parrot Security 6.0"`

VBoxManage: error: Cannot discard the saved state as the machine is not in the Saved or Aborted-Saved state

(machine state: Aborted)

VBoxManage: error: Details: code VBOX_E_INVALID_VM_STATE (0x80bb0002), component SessionMachine, interface IMachine, callee nsISupports

VBoxManage: error: Context: "DiscardSavedState(true)" at line 1291 of file VBoxManageMisc.cpp

```
└─[Wed Sep 09 9:47:56 AM][remac@Intel5]─[~]
  └─[REMAC]$
```

YOU

You said └─[Wed Sep 09 9:47:29 AM][remac@Intel5]─[~] └─[REMAC]\$ grep -iE "error|fatal|fail" "\$HOME/Virtual...

GEMINI

The issue is a direct crash (segmentation fault) inside the VirtualBox Device Display module (VBoxDD.so):

Plaintext

EMT-0[4910]: segfault at ... in VBoxDD.so ...

rtldrNativeLoad: dlopen('D3DCompiler_47.so', RTLD_NOW | RTLD_LOCAL) failed

When upgrading to VirtualBox 7.1.6, 3D Acceleration often crashes host rendering libraries on Linux due to shader compiler dependencies or mismatched VirtualBox Extension Pack components.

Step 1: Disable 3D Acceleration for the VM

Disabling 3D Acceleration bypasses VBoxDD.so rendering execution directly.

Run:

Bash

VBoxManage modifyvm "Parrot Security 6.0" --graphicscontroller vmsvga --3dacceleration off

How to verify success:

Attempt to start the VM:

Bash

VBoxManage startvm "Parrot Security 6.0" --type gui

If the window loads without an immediate crash, the issue was caused by the 7.1.6 3D graphics pipeline.

Step 2: Check & Update the Extension Pack Version

If Step 1 does not completely resolve the session abort, check if your VirtualBox Extension Pack is still running on the old 7.1.4 version.

Check installed extension versions:

Bash

VBoxManage list extpacks

If it lists version 7.1.4, download and install the matching 7.1.6 pack:

Bash

wget https://download.virtualbox.org/virtualbox/7.1.6/Oracle_VirtualBox_Extension_Pack-7.1.6.vbox-extpack

sudo VBoxManage extpack install --replace Oracle_VirtualBox_Extension_Pack-7.1.6.vbox-extpack

How to verify success:

Re-run VBoxManage list extpacks to verify that 7.1.6 is active, then launch the VM again.

Does disabling 3D acceleration allow "Parrot Security 6.0" to boot up cleanly?

You said error Wed Sep 09 9:48:28 AM][remac@Intel5]—[~] —[REMAC]\$ VBoxManage modifyvm "Parrot Security 6.0...

error Wed Sep 09 9:48:28 AM][remac@Intel5]—[~]

—[REMAC]\$ VBoxManage modifyvm "Parrot Security 6.0" --graphicscontroller vmsvg --3dacceleration off

Oracle VirtualBox Command Line Management Interface Version 7.1.6

Copyright (C) 2005-2025 Oracle and/or its affiliates

VBoxManage: error: Unknown option: --3dacceleration

Usage - Change settings for a virtual machine that is stopped:

VBoxManage modifyvm <uuid | vmname> [--name=name] [--groups=group [,group...]] [--description=description] [--os-type=OS-type] [--icon-file=filename] [--memory=size-in-MB] [--page-fusion= on | off] [--vram=size-in-MB] [--acpi= on | off] [--ioapic= on | off] [--hardware-uuid=UUID] [--cpus=CPU-count]

[--cpu-hotplug= on | off] [--plug-cpu=CPU-ID] [--unplug-cpu=CPU-ID] [--cpu-execution-cap=number] [--x86-pae= on | off] [--x86-long-mode= on | off] [--ibpb-on-vm-exit= on | off] [--ibpb-on-vm-entry= on | off] [--spec-ctrl= on | off] [--l1d-flush-on-sched= on | off] [--l1d-flush-on-vm-entry= on | off]

[--mds-clear-on-sched= on | off] [--mds-clear-on-vm-entry= on | off] [--cpu-profile= host | Intel 8086 | Intel 80286 | Intel 80386] [--x86-hpet= on | off] [--hwpvrtex= on | off] [--triple-fault-reset= on | off] [--apic= on | off] [--x86-x2apic= on | off] [--paravirt-provider= none | default | legacy | minimal

| hyperv | kvm] [--paravirt-debug= key=value [,key=value...]] [--nested-paging= on | off] [--large-pages= on | off] [--x86-vtx-vpid= on | off] [--x86-vtx-ux= on | off] [--nested-hw-virt= on | off] [--virt-vm-save-vmload= on | off] [--accelerate-3d= on | off] [--accelerate-2d-video= on | off] [--chipset= ich9 |

piix3 | armv8virtual] [--iommu= none | automatic | amd | intel] [--tpm-type= none | 1.2 | 2.0 | host | swtpm] [--tpm-location=location] [--firmware-logo-fade-in= on | off] [--firmware-logo-fade-out= on | off] [--firmware-logo-display-time=msec] [--firmware-logo-image-path=pathname] [--firmware-boot-menu=

disabled | menuonly | messageandmenu] [--firmware-apic= disabled | apic | x2apic] [--firmware-system-time-offset=msec] [--firmware-pxe-debug= on | off] [--system-uuid-le= on | off] [--bootX= none | floppy | dvd | disk | net] [--rtc-use-utc= on | off] [--graphicscontroller= none | vboxvga | vmsvg | vboxsvg |

qemuramfb] [--snapshot-folder= default | pathname] [--firmware= bios | efi | efi32 | efi64] [--guest-memory-balloon=size-in-MB] [--default-frontend= default | name] [--vm-process-priority= default | flat | low | normal | high] [--vm-execution-engine= default | hm | hwvirt | nem | native-api | interpreter | recompiler]

VBoxManage modifyvm <uuid | vmname> [--nicN= none | null | nat | bridged | intnet | hostonly | hostonlynet | generic | natnetwork | cloud] [--nic-typeN= Am79C970A | Am79C973 | 82540EM | 82543GC | 82545EM | virtio] [--cable-connectedN= on | off] [--nic-traceN= on | off] [--nic-trace-fileN=filename]

[--nic-propertyN=name= [value]] [--nic-speedN=kbps] [--nic-boot-prioN=priority] [--nic-promiscN= deny | allow-vm | allow-all] [--nic-bandwidth-groupN= none | name] [--bridge-adapterN= none | device-name] [--cloud-networkN=network-name] [--host-only-adapterN= none | device-name]

[--host-only-netN=network-name] [--intnetN=network-name] [--nat-networkN=network-name] [--nic-generic-drivN=driver-name] [--mac-addressN= auto | MAC-address]

VBoxManage modifyvm <uuid | vmname> [--nat-netN= network | default] [--nat-pfN= [rule-name],tcp | udp,[host-IP],hostport,[guest-IP],guestport] [--nat-pfN=delete=rule-name] [--nat-tftp-prefixN=prefix] [--nat-tftp-fileN=filename] [--nat-tftp-serverN=IP-address] [--nat-bind-ipN=IP-address] [--nat-dns-pass-domainN=

on | off] [--nat-dns-proxyN= on | off] [--nat-dns-host-resolverN= on | off] [--nat-localhostreachableN= on | off] [--nat-settingsN=[mtu],[socksnd],[sockrcv],[tcpsnd],[tcpv]] [--nat-alias-modeN= default | [log],[proxyonly],[sameports]]

VBoxManage modifyvm <uuid | vmname> [--mouse= ps2 | usb | usbttablet | usbmultitouch | usbmtscreenpluspad] [--keyboard= ps2 | usb] [--uartN= off | IO-baseIRQ] [--uart-modeN= disconnected | server pipe | client pipe | tcpserver port | tcpclient hostname:port | file filename | device-name] [--uart-typeN= 16450 |

16550A | 16750] [--lpt-modeN=device-name] [--lptN= off | IO-baseIRQ] [--audio-controller= ac97 | hda | sb16] [--audio-codec= stac9700 | ad1980 | stac9221 | sb16] [--audio-driver= none | default | null | dsound | was | oss | alsa | pulse | coreaudio] [--audio-enabled= on | off] [--audio-in= on | off]

[--audio-out= on | off] [--clipboard-mode= disabled | hosttoguest | guesttohost | bidirectional] [--clipboard-file-transfers= enabled | disabled] [--drag-and-drop= disabled | hosttoguest | guesttohost | bidirectional] [--monitor-count=number] [--usb-ehci= on | off] [--usb-ohci= on | off] [--usb-xhci= on |

off] [--usb-rename=old-namew-new-name]

```
VBoxManage modifyvm <uuid | vmname> [--recording= on | off] [--recording-screens= all | none | screen-
ID[,screen-ID...]] [--recording-file=filename] [--recording-max-size=MB] [--recording-max-time=msec] [--recording-
opts= key=value[,key=value...]] [--recording-video-fps=fps] [--recording-video-rate=rate]
[--recording-video-res=width x height]
VBoxManage modifyvm <uuid | vmname> [--vrde= on | off] [--vrde-property=property-name= [property-value]] [--
vrde-extpack= default | name] [--vrde-port=port] [--vrde-address=hostip] [--vrde-auth-type= null | external | guest] [--
vrde-auth-library= default | name] [--vrde-multi-con= on | off] [--vrde-reuse-con= on
| off] [--vrde-video-channel= on | off] [--vrde-video-channel-quality=percent]
VBoxManage modifyvm <uuid | vmname> [--teleporter= on | off] [--teleporter-port=port] [--teleporter-address=
address | empty] [--teleporter-password=password] [--teleporter-password-file= filename | stdin] [--cpuid-portability-
level=level] [--cpuid-set=leaf [:subleaf]eax ebx ecx edx] [--cpuid-remove=leaf
[:subleaf]] [--cpuid-remove-all]
VBoxManage modifyvm <uuid | vmname> [--tracing-enabled= on | off] [--tracing-config=string] [--tracing-allow-vm-
access= on | off]
VBoxManage modifyvm <uuid | vmname> [--usb-card-reader= on | off]
VBoxManage modifyvm <uuid | vmname> [--autostart-enabled= on | off] [--autostart-delay=seconds]
VBoxManage modifyvm <uuid | vmname> [--guest-debug-provider= none | native | gdb | kd] [--guest-debug-io-
provider= none | tcp | udp | ipc] [--guest-debug-address= IP-Address | path] [--guest-debug-port=port]
VBoxManage modifyvm <uuid | vmname> [--pci-attach=host-PCI-address [@guest-PCI-bus-address]] [--pci-
detach=host-PCI-address]
VBoxManage modifyvm <uuid | vmname> [--testing-enabled= on | off] [--testing-mmio= on | off] [--testing-cfg-
dwordidx=value]
VBoxManage: error: Unknown option: --3dacceleration
└─[Wed Sep 09 9:48:33 AM][remac@Intel5]─[~]
└─[REMAC]$
```

YOU

```
You said error Wed Sep 09 9:48:28 AM][remac@Intel5]─[~] └─[REMAC]$ VBoxManage modifyvm "Parrot
Security 6.0...
```

GEMINI

```
The correct flag parameter for 3D acceleration in VirtualBox CLI is --accelerate-3d (or --accelerate3d).
Step 1: Run Command with Correct Flag Syntax
Run this command to disable 3D acceleration and set the graphics controller:
Bash
VBoxManage modifyvm "Parrot Security 6.0" --graphicscontroller vmsvga --accelerate-3d off
How to verify success:
Run VBoxManage showvminfo "Parrot Security 6.0" | grep -i 3d to confirm it returns 3D Acceleration: off.
Step 2: Boot the VM
Once 3D acceleration is toggled off, attempt to launch the VM again:
Bash
VBoxManage startvm "Parrot Security 6.0" --type gui
How to verify success:
The VM window should open and proceed through the bootloader stage without triggering a VBoxDD.so segfault in
dmesg.
Did the VM boot cleanly after running the updated command?
Next diagnostic options:
Check Extension Pack 7.1.6
Re-enable 3D acceleration safely
```

