

YOU

You said How do we alter system settings keyboard behaviour on my parrot os home edition so that it cannot in...
How do we alter system settings keyboard behaviour on my parrot os home edition so that it cannot interrupt my typing i.e be always dormant when typing.I get interrupted and cursor moves to a diffrent location and I realize that I have been typing madness after a while.I have not perfected touch typing.I need to use monkeytype.com more.How do I become a super touch typer btw

YOU

You said How do we alter system settings keyboard behaviour on my parrot os home edition so that it cannot in...

To stop your cursor from jumping around while typing in Parrot OS Home Edition (which uses the MATE desktop environment by default), you need to enable the "Disable touchpad while typing" feature.

The Linux Touchpad Dev Guide

1. Disable Touchpad While Typing in Parrot OS

Option A: Via Graphical Settings (Easiest)

Open the Applications Menu in the top left corner.

Go to System → Preferences → Hardware → Mouse.

Click on the Touchpad tab.

Check the box for Disable touchpad while typing.

OSTechNix

Option B: Via Terminal (If GUI settings are missing)

If your touchpad driver relies on libinput or xinput and the GUI toggle doesn't stick, run this command in your terminal:

Bash

```
gsettings set org.gnome.desktop.peripherals.touchpad disable-while-typing true
```

Alternative: Force It via xinput (If it still moves)

List your input devices:

Bash

```
xinput list
```

Find your touchpad's exact name (e.g., SynPS/2 Synaptics TouchPad or ELAN Touchpad).

Enable "Disable While Typing" directly:

Bash

```
xinput set-prop "YOUR_TOUCHPAD_NAME" "libinput Disable While Typing Enabled" 1
```

2. How to Become a "Super Touch Typer"

Mastering touch typing requires building muscle memory rather than speed forcing.

Focus on Accuracy First, Speed Second: On Monkeytype, do not try to type fast. Aim for 98%+ accuracy. Speed comes naturally as a byproduct of efficiency; rushing creates bad habits that hard-cap your WPM.

Anchor Your Index Fingers: Always return to the home row (F and J keys, which have physical bumps). Every key press should start and end from home position.

Stop Looking at the Keyboard: If you make a mistake, do not look down to fix it. Force your brain to search for the key by feeling for it.

Optimal Monkeytype Settings for Rapid Improvement

Open Monkeytype.

Set mode to Time 30 or Words 25 for quick, low-fatigue sessions.

Turn on english 1k or english 5k (under the test settings menu). The default setting uses only 200 common words, which leaves you unprepared for real-world code/text.

Enable stop on error mode (Settings → Input → Stop on Error → letter). This forces you to fix a mistake immediately before proceeding, teaching your hands correct finger placement.

Practice in short bursts: 15–20 minutes daily is far more effective than a single 2-hour marathon session.

YOU

```
You said how should this be (venv) [Mon Sep 14 7:53:49 PM][root@Intel5]—[/home/remac/projects/talentpop]
└...
how should this be (venv) [Mon Sep 14 7:53:49 PM][root@Intel5]—[/home/remac/projects/talentpop]
└───[REMAC]# xinput list
[ Virtual core pointer                id=2 [master pointer  (3)]
|   ↳ Virtual core XTEST pointer      id=4 [slave  pointer  (2)]
|   ↳ SYNA3071:00 06CB:82F1 Mouse      id=10 [slave pointer  (2)]
|   ↳ SYNA3071:00 06CB:82F1 Touchpad   id=11 [slave pointer  (2)]
|   ↳ PS/2 Generic Mouse              id=13 [slave pointer  (2)]
|   ↳ SynPS/2 Synaptics TouchPad      id=14 [slave pointer  (2)]
└ Virtual core keyboard              id=3 [master keyboard (2)]
↳ Virtual core XTEST keyboard        id=5 [slave  keyboard (3)]
↳ Power Button                      id=6 [slave  keyboard (3)]
↳ Video Bus                        id=7 [slave  keyboard (3)]
↳ Power Button                      id=8 [slave  keyboard (3)]
↳ Sleep Button                     id=9 [slave  keyboard (3)]
↳ AT Translated Set 2 keyboard      id=12 [slave keyboard (3)]
↳ HP WMI hotkeys                    id=15 [slave keyboard (3)]
(venv) [Mon Sep 14 7:54:11 PM][root@Intel5]—[/home/remac/projects/talentpop]
└───[REMAC]# xinput set-prop "YOUR_TOUCHPAD_NAME" "libinput Disable While Typing Enabled" 1
```

YOU

```
You said how should this be (venv) [Mon Sep 14 7:53:49 PM][root@Intel5]—[/home/remac/projects/talentpop]
└...
```

Replace "YOUR_TOUCHPAD_NAME" with either the exact device name in quotes or its ID number.

Based on your output, you have two potential touchpad devices listed:

SYNA3071:00 06CB:82F1 Touchpad (ID: 11) — Most likely your primary precision touchpad

SynPS/2 Synaptics TouchPad (ID: 14)

Command using ID (Fastest & Safest)

Run this for device 11:

Bash

```
xinput set-prop 11 "libinput Disable While Typing Enabled" 1
```

If device 14 is the active one instead, run:

Bash

```
xinput set-prop 14 "libinput Disable While Typing Enabled" 1
```

Command using exact device name

Bash

```
xinput set-prop "SYNA3071:00 06CB:82F1 Touchpad" "libinput Disable While Typing Enabled" 1
```

How to verify it worked

To confirm the setting took effect, run:

Bash

```
xinput list-props 11 | grep "Disable While Typing"
```

Look for the line:

Plaintext

```
libinput Disable While Typing Enabled (XXX): 1
```

If the trailing value shows 1, disable-while-typing is active.

Note: Settings applied via xinput reset when you reboot. If you want this permanent across restarts, add the command to your startup applications (System → Preferences → Personal → Startup Applications).

```
You said Help me out from this step (venv) └──[Mon Sep 14 7:55:41 PM]
[root@Intel5]—[/home/remac/projects/tale...
Help me out from this step (venv) └──[Mon Sep 14 7:55:41 PM][root@Intel5]—[/home/remac/projects/talentpop]
└──[REMAC]# xinput list-props 11
Device 'SYNA3071:00 06CB:82F1 Touchpad':
Device Enabled (189): 1
Coordinate Transformation Matrix (191): 1.000000, 0.000000, 0.000000, 0.000000, 1.000000, 0.000000, 0.000000,
0.000000, 1.000000
Device Accel Profile (321): 1
Device Accel Constant Deceleration (322): 2.500000
Device Accel Adaptive Deceleration (323): 1.000000
Device Accel Velocity Scaling (324): 12.500000
Synaptics Edges (347): 50, 1223, 36, 636
Synaptics Finger (348): 25, 30, 0
Synaptics Tap Time (349): 180
Synaptics Tap Move (350): 63
Synaptics Tap Durations (351): 180, 180, 100
Synaptics ClickPad (352): 1
Synaptics Middle Button Timeout (353): 0
Synaptics Two-Finger Pressure (354): 282
Synaptics Two-Finger Width (355): 7
Synaptics Scrolling Distance (356): -28, -28
Synaptics Edge Scrolling (357): 1, 1, 0
Synaptics Two-Finger Scrolling (358): 1, 1
Synaptics Move Speed (359): 1.000000, 1.750000, 0.138985, 0.000000
Synaptics Off (360): 0
Synaptics Locked Drags (361): 0
Synaptics Locked Drags Timeout (362): 5000
Synaptics Tap Action (363): 0, 0, 0, 0, 1, 3, 2
Synaptics Click Action (364): 1, 3, 2
Synaptics Circular Scrolling (365): 0
Synaptics Circular Scrolling Distance (366): 0.100000
Synaptics Circular Scrolling Trigger (367): 0
Synaptics Circular Pad (368): 0
Synaptics Palm Detection (369): 0
Synaptics Palm Dimensions (370): 10, 200
Synaptics Coasting Speed (371): 20.000000, 50.000000
Synaptics Pressure Motion (372): 30, 160
Synaptics Pressure Motion Factor (373): 1.000000, 1.000000
Synaptics Grab Event Device (374): 0
Synaptics Gestures (375): 1
Synaptics Capabilities (376): 1, 0, 0, 1, 1, 0, 0
Synaptics Pad Resolution (377): 12, 12
Synaptics Area (378): 0, 0, 0, 0
Synaptics Soft Button Areas (379): 636, 0, 551, 0, 0, 0, 0, 0
Synaptics Noise Cancellation (380): 7, 7
Device Product ID (314): 1739, 33521
Device Node (313): "/dev/input/event6"
(venv) └──[Mon Sep 14 7:55:45 PM][root@Intel5]—[/home/remac/projects/talentpop]
└──[REMAC]#
```

YOU

You said Help me out from this step (venv) [Mon Sep 14 7:55:41 PM]
[root@Intel5]—[/home/remac/projects/tale...

GEMINI

Your device is using the xf86-input-synaptics driver (evidenced by properties like Synaptics Palm Detection and Synaptics Off). Because of this, standard libinput commands will not work.

You have two effective ways to fix this:

1

Enable Palm Detection (Built-in Synaptics Fix)

1 min

Enable Palm Detection on your device so the driver automatically ignores accidental palm brushes while typing:

Bash

`xinput set-prop 11 "Synaptics Palm Detection" 1`

To verify: Run `xinput list-props 11 | grep "Palm Detection"`. It should show a 1 at the end.

2

Run syndaemon (Best Experience)

Recommended

Run syndaemon, which monitors your keyboard directly and disables the touchpad for 1 second every time you press a key:

Bash

`syndaemon -i 1.0 -K -d`

-i 1.0: Waits 1 second after typing stops before re-enabling the touchpad.

-K: Ignores modifier keys (like Shift or Ctrl).

-d: Runs as a background service.

To verify: Type continuously in any text editor and try moving your finger on the touchpad at the same time—the cursor will remain still until 1 second after you stop typing.

3

Make It Permanent Across Reboots

System Setup

`xinput` and `syndaemon` commands reset when you reboot. To keep this setting active permanently:

Open System → Preferences → Personal → Startup Applications.

Click Add.

Name: Disable Touchpad While Typing

Command: `syndaemon -i 1.0 -K -d`

Click Add and save.

What would you like to do next?

Adjust syndaemon delay timing

Set up Monkeytype drills