

API Documentation

REST endpoint reference for the wireguard-api backend

Blackie Networks

WireGuard VPN Management Platform · docs.blackie-networks.com

Generated 2026-08-18

API Reference

All endpoints are served from the wireguard-api backend, default port 5000. Endpoints marked Auth require an HTTP Authorization: Bearer <token> header with a JWT obtained from /api/auth/login. Endpoints marked Admin additionally require the authenticated user to hold the admin role.

```
Authorization: Bearer <jwt-token>
```

Authentication

Endpoint	Description
POST /api/auth/signup	Create an account. Sends a verification email; accepts an optional referral code.
GET /api/auth/verify-email	Verify an account via the emailed token.
POST /api/auth/resent-verification (Auth)	Resend the verification email.
POST /api/auth/login	Authenticate and receive a JWT.
GET /api/auth/me (Auth)	Return the current user's profile.
POST /api/auth/forgot-password	Request a password-reset email.
POST /api/auth/reset-password	Reset a password using the emailed token.

Clients (WireGuard peers)

Endpoint	Description
GET /api/clients (Admin)	Paginated, filterable list of all clients.
GET /api/clients/:name (Admin)	Client details.
GET /api/clients/:name/conf (Auth)	Download the client's WireGuard .conf file.
GET /api/clients/:name/autoconfig	Download an enhanced MikroTik .rsc script with a built-in connectivity test.
GET /api/clients/:name/mikrotik	Download a basic MikroTik .rsc script.
POST /api/clients/:name/ping (Auth)	Run a ping test from a client.
POST /api/clients (Admin)	Create a new client.
PUT /api/clients/:name (Admin)	Update a client.
POST /api/clients/:name/regenerate (Admin)	Regenerate a client's WireGuard keypair.
POST /api/clients/:name/enable (Admin)	Enable a client.
POST /api/clients/:name/disable (Admin)	Disable a client.
DELETE /api/clients/:name (Admin)	Delete a client.
POST /api/clients/bulk-delete (Admin)	Delete multiple clients at once.

MikroTik quick provisioning

Endpoint	Description
POST /generate-mikrotik (Admin)	Create a client and return a RouterOS .rsc script.
GET /mt/:name	Short-URL compact .rsc script; creates the client automatically if it doesn't exist.
GET /:name/configure	Shortest URL form of the full auto-configuration script.

Managed routers (Auth required on all)

Endpoint	Description
POST /api/routers	Provision a router: creates a WireGuard peer, allocates proxy ports, and starts the TCP proxy.
GET /api/routers	List the current user's routers.
GET /api/routers/:id	Router detail.
POST /api/routers/:id/renew	Renew a router's subscription.
DELETE /api/routers/:id	Deprovision a router: stops its proxy and removes the WireGuard peer.
GET /api/routers/billing/summary	Per-user router billing summary.

Personal device tunnels (Auth required on all)

Endpoint	Description
GET /api/devices	List the user's personal devices.
POST /api/devices	Add a new device tunnel.
GET /api/devices/:id/config	Download the device's WireGuard config.
DELETE /api/devices/:id	Remove a device.

Billing

Endpoint	Description
GET /api/settings/pricing	Public pricing information.
GET /api/billing/summary (Auth)	Billing summary for the current user.
GET /api/billing/transactions (Auth)	Transaction history.
POST /api/billing/add-balance (Auth)	Top up account balance.
POST /api/billing/paystack/webhook	Paystack webhook receiver; verified via request signature.
GET /api/billing/verify/:reference (Auth)	Verify a payment reference.
GET /api/billing/subscription/:routerId (Auth)	Subscription status for a router.

Profile, referrals and support (Auth required on all)

Endpoint	Description
GET /api/profile	Get the current user's profile.
PUT /api/profile	Update the current user's profile.
GET /api/referrals/code	Get the user's referral code.
GET /api/referrals/stats	Referral performance stats.
GET /api/referrals	List referred users.
POST /api/support/tickets	Open a support ticket.
GET /api/support/tickets	List the user's support tickets.
GET /api/support/tickets/:id	Ticket detail.
POST /api/support/tickets/:id/messages	Reply on a ticket.
POST /api/support/tickets/:id/close	Close a ticket.

Admin (Auth + Admin role required on all)

Endpoint	Description
GET /api/admin/stats	Platform-wide summary statistics.
GET /api/admin/analytics	Usage and growth analytics.
GET /api/admin/referrals	All referral activity.
GET /api/admin/routers	All routers across all users.
POST /api/admin/routers/:id/reconnect	Force a router to reconnect.
GET /api/admin/settings	Read platform settings.
PATCH /api/admin/settings	Update platform settings.
GET /api/admin/system-status	Backend/service health snapshot.
GET /api/admin/support-tickets	All support tickets.
GET /api/admin/transactions	All billing transactions.
GET /api/admin/users	List all users.
POST /api/admin/users	Create a user.
PATCH /api/admin/users/:id	Update a user.
DELETE /api/admin/users/:id	Delete a user.
GET /api/admin/proxy/status	TCP proxy service status.
POST /api/admin/proxy/test	Run a proxy connectivity test.
POST /api/admin/reload	Reload WireGuard peers from the database.

Misc

Endpoint	Description
GET /	Index of available endpoints.
GET /api/health	Health check.

Example: create and download a client config

```
curl -sS -X POST http://YOUR_SERVER:5000/generate-client \
  -H "Content-Type: application/json" \
  -d '{"name":"device-1","notes":"purpose"}' \
  -o device-1.conf
```