

Database Compability for Oracle® Developers Built-in Package Guide

Release 12

EDB Postgres™ Advanced Server 12

Contents

1	Intro	duction	1
	1.1	What's New	2
2	Packa	nges	3
	2.1	Package Components	4
		2.1.1 Package Specification Syntax	4
		2.1.2 Package Body Syntax	7
	2.2	Creating Packages	12
		2.2.1 Creating the Package Specification	12
		2.2.2 Creating the Package Body	13
	2.3	Referencing a Package	15
	2.4	Using Packages With User Defined Types	16
	2.5	Dropping a Package	20
3	Built	In Packages	21
	3.1	DBMS_ALERT	22
		3.1.1 REGISTER	22
		3.1.2 REMOVE	23
		3.1.3 REMOVEALL	23
		3.1.4 SIGNAL	23
		3.1.5 WAITANY	24
		3.1.6 WAITONE	25
		3.1.7 Comprehensive Example	27
	3.2	DBMS_AQ	29
		3.2.1 ENQUEUE	32
		3.2.2 DEQUEUE	35
		3.2.3 REGISTER	39
		3.2.4 UNREGISTER	41
	3.3	DBMS_AQADM	43
		3.3.1 ALTER_QUEUE	45
		3.3.2 ALTER_QUEUE_TABLE	46
		3.3.3 CREATE_QUEUE	47
		3.3.4 CREATE_QUEUE_TABLE	49
		3.3.5 DROP_QUEUE	51
		3.3.6 DROP_QUEUE_TABLE	52
		3.3.7 PURGE_QUEUE_TABLE	53
		3.3.8 START_QUEUE	54

	3.3.9	STOP_QUEUE
3.4	_	_CRYPTO 56
	3.4.1	DECRYPT
	3.4.2	ENCRYPT 59
	3.4.3	HASH
	3.4.4	MAC 62
	3.4.5	RANDOMBYTES 63
	3.4.6	RANDOMINTEGER
	3.4.7	RANDOMNUMBER
3.5	DBMS_	_JOB
	3.5.1	BROKEN
	3.5.2	CHANGE
	3.5.3	INTERVAL
	3.5.4	NEXT DATE
	3.5.5	REMOVE
	3.5.6	RUN
	3.5.7	SUBMIT
	3.5.8	WHAT
3.6		LOB
3.0	3.6.1	APPEND
	3.6.2	COMPARE
	3.6.3	CONVERTTOBLOB
	3.6.4	CONVERTIOGLOB
	3.6.5	COPY
	3.6.6	ERASE
	3.6.7	
	3.6.8	
	3.6.9	INSTR
	3.6.10	READ
	3.6.11	SUBSTR
	3.6.12	TRIM
	3.6.13	WRITE
	3.6.14	WRITEAPPEND
3.7	_	_LOCK
	3.7.1	SLEEP 92
3.8	DBMS_	_MVIEW
	3.8.1	GET_MV_DEPENDENCIES
	3.8.2	REFRESH
	3.8.3	REFRESH_ALL_MVIEWS
	3.8.4	REFRESH_DEPENDENT
3.9	DBMS_	_OUTPUT
	3.9.1	CHARARR
	3.9.2	DISABLE
	3.9.3	ENABLE
	3.9.4	GET LINE
	3.9.5	GET LINES
	3.9.6	NEW LINE
	3.9.7	PUT
	3.9.8	PUT LINE
	3.9.9	SERVEROUTPUT
3 10		PIPE
5.10	3.10.1	CREATE PIPE
	3.10.1	NEXT ITEM TYPE
		PACK_MESSAGE
	5.10.5	TRUE INTERVENCE TO THE PROPERTY OF THE PROPERT

	3.10.4 PURGE					
	3.10.5 RECEIVE_MESSAGE					
	3.10.6 REMOVE_PIPE					
	3.10.7 RESET_BUFFER					
	3.10.8 SEND_MESSAGE					
	3.10.9 UNIQUE_SESSION_NAME.					
	3.10.10 UNPACK_MESSAGE					
	3.10.11 Comprehensive Example		 	 	 	. 125
3.11	11 DBMS_PROFILER		 	 	 	. 128
	3.11.1 FLUSH_DATA		 	 	 	. 129
	3.11.2 GET_VERSION		 	 	 	. 129
	3.11.3 INTERNAL_VERSION_CHEC	K	 	 	 	. 129
	3.11.4 PAUSE_PROFILER		 	 	 	. 129
	3.11.5 RESUME_PROFILER					
	3.11.6 START_PROFILER		 	 	 	. 130
	3.11.7 STOP_PROFILER					
	3.11.8 Using DBMS_PROFILER					
	3.11.8.1 Querying the DBMS_F					
	3.11.8.2 DBMS_PROFILER - F					
	3.11.8.2.1 PLSQL_PRC					
	3.11.8.2.2 PLSQL_PRC					
	3.11.8.2.3 PLSQL PRO					
	3.11.8.2.4 PLSQL PRO	_				
3 12	12 DBMS_RANDOM	_				
3.12	3.12.1 INITIALIZE					
	3.12.2 NORMAL					
	3.12.2 NORWAL					
	3.12.4 SEED					
	3.12.5 SEED					
	3.12.6 STRING					
	3.12.7 TERMINATE					
	3.12.8 VALUE					
2.12	3.12.9 VALUE					
3.13						
	3.13.1 Using DBMS_REDACT Consta 3.13.2 ADD_POLICY					
	-					
	3.13.4 DISABLE_POLICY					
	3.13.5 ENABLE_POLICY					
	3.13.6 DROP_POLICY					
2.14	3.13.7 UPDATE_FULL_REDACTION					
3.14						
	3.14.1 ADD_POLICY					
	3.14.2 DROP_POLICY					
	3.14.3 ENABLE_POLICY					
3.15						
	3.15.1 Using Calendar Syntax to Speci					
	3.15.2 CREATE_JOB					
	3.15.3 CREATE_PROGRAM					
	3.15.4 CREATE_SCHEDULE					
	3.15.5 DEFINE_PROGRAM_ARGUN					
	3.15.6 DISABLE					
	3.15.7 DROP_JOB					
	3.15.8 DROP_PROGRAM		 	 	 	. 205

	3.15.9 DROP_PROGRAM_ARGUMENT	 206
	3.15.10 DROP_SCHEDULE	 207
	3.15.11 ENABLE	
	3.15.12 EVALUATE_CALENDAR_STRING	 209
	3.15.13 RUN_JOB	
	3.15.14 SET_JOB_ARGUMENT_VALUE	
3.16	DBMS_SESSION	
	3.16.1 SET_ROLE	 212
3.17	DBMS_SQL	
	3.17.1 BIND_VARIABLE	
	3.17.2 BIND_VARIABLE_CHAR	
	3.17.3 BIND VARIABLE RAW	
	3.17.4 CLOSE_CURSOR	
	3.17.5 COLUMN_VALUE	
	3.17.6 COLUMN_VALUE_CHAR	
	3.17.7 COLUMN_VALUE_RAW	
	3.17.8 DEFINE_COLUMN	
	3.17.9 DEFINE_COLUMN_CHAR	
	3.17.10 DEFINE_COLUMN_RAW	
	3.17.11 DESCRIBE COLUMNS	
	3.17.12 EXECUTE	
	3.17.13 EXECUTE_AND_FETCH	
	3.17.14 FETCH_ROWS	
	3.17.15 IS_OPEN	
	3.17.16 LAST_ROW_COUNT	
	3.17.17 OPEN_CURSOR	
2.10	3.17.18 PARSE	
3.18		
	3.18.1 LNAME_ARRAY	
	3.18.2 UNCL_ARRAY	
	3.18.3 ANALYZE_DATABASE, ANALYZE SCHEMA and ANALYZE PART_OBJECT	
	3.18.4 CANONICALIZE	
	3.18.5 COMMA_TO_TABLE	
	3.18.6 DB_VERSION	
	3.18.7 EXEC_DDL_STATEMENT	
	3.18.8 FORMAT_CALL_STACK	 249
	3.18.9 GET_CPU_TIME	
		250
	3.18.10 GET_DEPENDENCY	 250 251
	3.18.10 GET_DEPENDENCY	 250 251 252
	3.18.10 GET_DEPENDENCY	 250 251 252
	3.18.10 GET_DEPENDENCY	 250 251 252 253
	3.18.10 GET_DEPENDENCY	 250 251 252 253 254
	3.18.10 GET_DEPENDENCY 3.18.11 GET_HASH_VALUE 3.18.12 GET_PARAMETER_VALUE 3.18.13 GET_TIME	 250 251 252 253 254 255
3.19	3.18.10 GET_DEPENDENCY 3.18.11 GET_HASH_VALUE 3.18.12 GET_PARAMETER_VALUE 3.18.13 GET_TIME 3.18.14 NAME_TOKENIZE	250 251 252 253 254 255 258
3.19	3.18.10 GET_DEPENDENCY 3.18.11 GET_HASH_VALUE 3.18.12 GET_PARAMETER_VALUE 3.18.13 GET_TIME 3.18.14 NAME_TOKENIZE 3.18.15 TABLE_TO_COMMA	250 251 252 253 254 255 258 260
3.19	3.18.10 GET_DEPENDENCY 3.18.11 GET_HASH_VALUE 3.18.12 GET_PARAMETER_VALUE 3.18.13 GET_TIME 3.18.14 NAME_TOKENIZE 3.18.15 TABLE_TO_COMMA UTL_ENCODE	250 251 252 253 254 255 258 260 261
3.19	3.18.10 GET_DEPENDENCY 3.18.11 GET_HASH_VALUE 3.18.12 GET_PARAMETER_VALUE 3.18.13 GET_TIME 3.18.14 NAME_TOKENIZE 3.18.15 TABLE_TO_COMMA UTL_ENCODE 3.19.1 BASE64_DECODE	250 251 252 253 254 255 258 260 261 262
3.19	3.18.10 GET_DEPENDENCY 3.18.11 GET_HASH_VALUE 3.18.12 GET_PARAMETER_VALUE 3.18.13 GET_TIME 3.18.14 NAME_TOKENIZE 3.18.15 TABLE_TO_COMMA UTL_ENCODE 3.19.1 BASE64_DECODE 3.19.2 BASE64_ENCODE	250 251 252 253 254 255 258 260 261 262 263
3.19	3.18.10 GET_DEPENDENCY 3.18.11 GET_HASH_VALUE 3.18.12 GET_PARAMETER_VALUE 3.18.13 GET_TIME 3.18.14 NAME_TOKENIZE 3.18.15 TABLE_TO_COMMA UTL_ENCODE 3.19.1 BASE64_DECODE 3.19.2 BASE64_ENCODE 3.19.3 MIMEHEADER_DECODE 3.19.4 MIMEHEADER_ENCODE	250 251 252 253 254 255 258 260 261 262 263 264
3.19	3.18.10 GET_DEPENDENCY 3.18.11 GET_HASH_VALUE 3.18.12 GET_PARAMETER_VALUE 3.18.13 GET_TIME 3.18.14 NAME_TOKENIZE 3.18.15 TABLE_TO_COMMA UTL_ENCODE 3.19.1 BASE64_DECODE 3.19.2 BASE64_ENCODE 3.19.3 MIMEHEADER_DECODE 3.19.4 MIMEHEADER_ENCODE 3.19.5 QUOTED_PRINTABLE_DECODE	250 251 252 253 254 255 260 261 262 263 264 265
3.19	3.18.10 GET_DEPENDENCY 3.18.11 GET_HASH_VALUE 3.18.12 GET_PARAMETER_VALUE 3.18.13 GET_TIME 3.18.14 NAME_TOKENIZE 3.18.15 TABLE_TO_COMMA UTL_ENCODE 3.19.1 BASE64_DECODE 3.19.2 BASE64_ENCODE 3.19.3 MIMEHEADER_DECODE 3.19.4 MIMEHEADER_ENCODE 3.19.5 QUOTED_PRINTABLE_DECODE 3.19.6 QUOTED_PRINTABLE_ENCODE	250 251 252 253 254 255 260 261 262 263 264 265 266
3.19	3.18.10 GET_DEPENDENCY 3.18.11 GET_HASH_VALUE 3.18.12 GET_PARAMETER_VALUE 3.18.13 GET_TIME 3.18.14 NAME_TOKENIZE 3.18.15 TABLE_TO_COMMA UTL_ENCODE 3.19.1 BASE64_DECODE 3.19.2 BASE64_ENCODE 3.19.3 MIMEHEADER_DECODE 3.19.4 MIMEHEADER_ENCODE 3.19.5 QUOTED_PRINTABLE_DECODE 3.19.6 QUOTED_PRINTABLE_ENCODE 3.19.7 TEXT_DECODE	250 251 252 253 254 255 260 261 262 263 264 265 266 267
3.19	3.18.10 GET_DEPENDENCY 3.18.11 GET_HASH_VALUE 3.18.12 GET_PARAMETER_VALUE 3.18.13 GET_TIME 3.18.14 NAME_TOKENIZE 3.18.15 TABLE_TO_COMMA UTL_ENCODE 3.19.1 BASE64_DECODE 3.19.2 BASE64_ENCODE 3.19.3 MIMEHEADER_DECODE 3.19.4 MIMEHEADER_ENCODE 3.19.5 QUOTED_PRINTABLE_DECODE 3.19.6 QUOTED_PRINTABLE_ENCODE	250 251 252 253 254 255 258 260 261 262 263 264 265 266 267 268

3.20	UTL_F	ILE	272
	3.20.1	Setting File Permissions with utl_file.umask	273
	3.20.2	FCLOSE 2	274
	3.20.3	FCLOSE_ALL	274
	3.20.4	FCOPY	
	3.20.5	FFLUSH	276
	3.20.6	FOPEN	277
	3.20.7	FREMOVE	
	3.20.8	FRENAME	
		GET_LINE	
		IS_OPEN	
		NEW_LINE	
		PUT	
		PUT_LINE	
		PUTF	
3.21	UTL_H		
	3.21.1	HTML_PIECES	
	3.21.2	REQ	
	3.21.3	RESP	
	3.21.4	BEGIN_REQUEST	
	3.21.5	END_REQUEST	
	3.21.6	END_RESPONSE	
	3.21.7	GET_BODY_CHARSET	
	3.21.8	GET_FOLLOW_REDIRECT	
		GET_HEADER	
		GET_HEADER_BY_NAME	
		GET_HEADER_COUNT	
		GET_RESPONSE	
		GET_RESPONSE_ERROR_CHECK	
		GET_TRANSFER_TIMEOUT	
		READ_LINE	
		READ_RAW	
		READ_TEXT	
		REQUEST	
		REQUEST_PIECES	
		SET_BODY_CHARSET	
		SET_FOLLOW_REDIRECT	
		SET_HEADER	
		SET_RESPONSE_ERROR_CHECK	
		SET_TRANSFER_TIMEOUT	
		WRITE_LINE	
		WRITE_RAW	304 305
2 22		WRITE_TEXT	
3.22	3.22.1		307
	3.22.1	SEND_ATTACH_RAW	
	3.22.2	SEND ATTACH VARCHAR2	
3.23	0	AW	
5.43	3.23.1	CAST_TO_RAW	
	3.23.1	CAST_TO_VARCHAR2	
	3.23.2	CONCAT	
	3.23.4	CONVERT	
		LENGTH	
		SUBSTR	_
	5.45.0	DODDIE	. 10

	3.24	UTL_S	MTP	
		3.24.1	CONNECTION	. 318
		3.24.2	REPLY/REPLIES	. 318
		3.24.3	CLOSE_DATA	. 318
		3.24.4	COMMAND	. 318
		3.24.5	COMMAND_REPLIES	. 319
		3.24.6	DATA	. 319
		3.24.7	EHLO	. 320
		3.24.8	HELO	. 320
		3.24.9	HELP	. 320
		3.24.10	MAIL	. 321
		3.24.11	NOOP	. 321
		3.24.12	OPEN_CONNECTION	. 321
		3.24.13	OPEN_DATA	. 322
		3.24.14	QUIT	. 322
		3.24.15	RCPT	. 322
		3.24.16	RSET	. 322
		3.24.17	VRFY	. 323
		3.24.18	WRITE_DATA	. 323
		3.24.19	Comprehensive Example	. 323
	3.25	UTL_U	RL	. 325
		3.25.1	ESCAPE	. 325
		3.25.2	UNESCAPE	. 327
4				220
4	Ackn	owledge	ments	328
5	Conc	lusion		329
In	dex			330

CHAPTER 1

Introduction

Database Compatibility for Oracle means that an application runs in an Oracle environment as well as in the EDB Postgres Advanced Server (Advanced Server) environment with minimal or no changes to the application code. This guide focuses solely on the features that are related to the package support provided by Advanced Server.

For more information about using other compatibility features offered by Advanced Server, please see the complete set of Advanced Server guides, available at:

https://www.enterprisedb.com/edb-docs/

1.1 What's New

The following database compatibility for Oracle features have been added to Advanced Server 11 to create Advanced Server 12:

- Advanced Server introduces COMPOUND TRIGGERS, which are stored as a PL block that executes in response to a specified triggering event. For information, see the *Database Compatibility for Oracle Developer's Guide*.
- Advanced Server now supports new DATA DICTIONARY VIEWS that provide information compatible with the Oracle data dictionary views. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has added the LISTAGG function to support string aggregation that concatenates data from
 multiple rows into a single row in an ordered manner. For information, see the *Database Compatibility for*Oracle Developer's Reference Guide.
- Advanced Server now supports CAST (MULTISET) function, allowing subquery output to be CAST to a nested table type. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has added the MEDIAN function to calculate a median value from the set of provided values. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has added the SYS_GUID function to generate and return a globally unique identifier in the form of 16-bytes of RAW data. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server now supports an Oracle-compatible SELECT UNIQUE clause in addition to an existing SELECT DISTINCT clause. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has re-implemented default_with_rowids to create a table that includes a ROWID column in the newly created table. For information, see the *EDB Postgres Advanced Server Guide*.
- Advanced Server now supports logical decoding on the standby server, which allows creating a logical replication slot on a standby, independently of a primary server. For information, see the EDB Postgres Advanced Server Guide.
- Advanced Server introduces INTERVAL PARTITIONING, which allows a database to automatically create partitions of a specified interval as new data is inserted into a table. For information, see the *Database Compatibility for Oracle Developer's Guide*.

Note: Database Compatibility for Oracle Developer's Guide, Database Compatibility for Oracle Developer's Reference Guide, and EDB Postgres Advanced Server Guides are available at:

https://www.enterprisedb.com/edb-docs/

1.1. What's New 2

CHAPTER 2

Packages

This chapter discusses the concept of packages in Advanced Server. A *package* is a named collection of functions, procedures, variables, cursors, user-defined record types, and records that are referenced using a common qualifier – the package identifier. Packages have the following characteristics:

- Packages provide a convenient means of organizing the functions and procedures that perform a related purpose.
 Permission to use the package functions and procedures is dependent upon one privilege granted to the entire package. All of the package programs must be referenced with a common name.
- Certain functions, procedures, variables, types, etc. in the package can be declared as *public*. Public entities are visible and can be referenced by other programs that are given EXECUTE privilege on the package. For public functions and procedures, only their signatures are visible the program names, parameters if any, and return types of functions. The SPL code of these functions and procedures is not accessible to others, therefore applications that utilize a package are dependent only upon the information available in the signature not in the procedural logic itself.
- Other functions, procedures, variables, types, etc. in the package can be declared as *private*. Private entities can be referenced and used by function and procedures within the package, but not by other external applications. Private entities are for use only by programs within the package.
- Function and procedure names can be overloaded within a package. One or more functions/procedures can be defined with the same name, but with different signatures. This provides the capability to create identically named programs that perform the same job, but on different types of input.

2.1 Package Components

Packages consist of two main components:

- The *package specification*: This is the public interface, (these are the elements which can be referenced outside the package). We declare all database objects that are to be a part of our package within the specification.
- The *package body*: This contains the actual implementation of all the database objects declared within the package specification.

The package body implements the specifications in the package specification. It contains implementation details and private declarations which are invisible to the application. You can debug, enhance or replace a package body without changing the specifications. Similarly, you can change the body without recompiling the calling programs because the implementation details are invisible to the application.

2.1.1 Package Specification Syntax

The package specification defines the user interface for a package (the API). The specification lists the functions, procedures, types, exceptions and cursors that are visible to a user of the package.

The syntax used to define the interface for a package is:

```
Where <authorization clause>:=
   { AUTHID DEFINER } | { AUTHID CURRENT_USER }
Where cedure_or_function_declaration> :=
    cedure_declaration> | <function_declaration>
Where cedure_declaration> :=
   Where <function declaration> :=
   FUNCTION <func_name> [ <argument_list> ]
   RETURN <rettype> [ DETERMINISTIC ];[<restriction_pragma>;]
Where <argument_list>:=
   (<argument declaration>[,...])
Where <argument_declaration> :=
   <argname> [ IN | IN OUT | OUT ] <argtype> [ DEFAULT <value> ]
Where <restriction_pragma> :=
   PRAGMA RESTRICT_REFERENCES ( <name>, <restrictions>)
Where <restrictions> :=
   <restriction>[,...]
```

Parameters

<package_name>

<package_name> is an identifier assigned to the package - each package must have a name unique
within the schema.

AUTHID DEFINER

If you omit the AUTHID clause or specify AUTHID DEFINER, the privileges of the package owner are used to determine access privileges to database objects.

AUTHID CURRENT_USER

If you specify AUTHID CURRENT_USER, the privileges of the current user executing a program in the package are used to determine access privileges.

<declaration>

<declaration> is an identifier of a public variable. A public variable can be accessed from outside of
the package using the syntax <package_name.variable>. There can be zero, one, or more public
variables. Public variable definitions must come before procedure or function declarations.

<declaration> can be any of the following:

- Variable Declaration
- · Record Declaration
- Collection Declaration
- REF CURSOR and Cursor Variable Declaration
- TYPE Definitions for Records, Collections, and REF CURSORS
- Exception
- Object Variable Declaration

oc_name>

The name of a public procedure.

<argname>

The name of an argument. The argument is referenced by this name within the function or procedure body.

```
IN | IN OUT | OUT
```

The argument mode. IN declares the argument for input only. This is the default. IN OUT allows the argument to receive a value as well as return a value. OUT specifies the argument is for output only.

```
<arqtype>
```

The data type(s) of an argument. An argument type may be a base data type, a copy of the type of an existing column using %TYPE, or a user-defined type such as a nested table or an object type. A length must not be specified for any base type - for example, specify VARCHAR2, not VARCHAR2 (10).

The type of a column is referenced by writing <tablename.columnname> %TYPE; using this can sometimes help make a procedure independent from changes to the definition of a table.

```
DEFAULT <value>
```

The DEFAULT clause supplies a default value for an input argument if one is not supplied in the invocation. DEFAULT may not be specified for arguments with modes IN OUT or OUT.

<func< th=""><th>name></th></func<>	name>

The name of a public function.

<rettype>

The return data type.

DETERMINISTIC

DETERMINISTIC is a synonym for IMMUTABLE. A DETERMINISTIC function cannot modify the database and always reaches the same result when given the same argument values; it does not do database lookups or otherwise use information not directly present in its argument list. If you include this clause, any call of the function with all-constant arguments can be immediately replaced with the function value.

<restriction>

The following keywords are accepted for compatibility and ignored:

RNDS

RNPS

TRUST

WNDS

WNPS

2.1.2 Package Body Syntax

Package implementation details reside in the package body; the package body may contain objects that are not visible to the package user. Advanced Server supports the following syntax for the package body:

```
CREATE [ OR REPLACE ] PACKAGE BODY <package_name>
    { IS | AS }
    [ <private_declaration>; ] ...
    [ <procedure_or_function_definition> ] ...
    [ <package_initializer> ]
    END [ <package_name> ] ;
```

```
Where cprocedure_or_function_definition> :=
    cedure definition> | <function definition>
Where procedure definition> :=
   [ <options_list> ]
       { IS | AS }
          cedure_body>
       Where procedure_body> :=
    [ PRAGMA AUTONOMOUS_TRANSACTION; ]
   [ <declaration>; ][,...]
   BEGIN
       <statement>; [...]
       [ EXCEPTION
          {WHEN <exception> [OR <exception>] [...]] THEN
          <statement>; }
       [\dots]
   1
Where <function_definition> :=
   FUNCTION <func_name> [ <argument_list> ]
       RETURN <rettype> [ DETERMINISTIC ]
       [ <options_list> ]
       { IS | AS }
       <function_body>
       END [ <func_name>];
Where <function body> :=
    [ PRAGMA AUTONOMOUS_TRANSACTION; ]
   [ <declaration>; ][,...]
   BEGIN
```

```
<statement>;[...]
    [ EXCEPTION
        { WHEN <exception> [ OR <exception> ] [...] THEN <statement>; }
        [\dots]
    1
Where <argument list>:=
    ( <argument_declaration>[,...])
Where <argument_declaration> :=
    <argname>[IN | IN OUT | OUT] <argtype> [ DEFAULT <value> ]
Where options_list> :=
    <option>[...]
Where <option> :=
    STRICT
    LEAKPROOF
    PARALLEL { UNSAFE | RESTRICTED | SAFE }
    COST <execution_cost>
    ROWS <result_rows>
    SET <config_param> { TO <value> | = <value> | FROM CURRENT }
Where <package_initializer> :=
    BEGIN
        <statement; > [...]
    END;
```

Parameters

<package_name>

<package_name> is the name of the package for which this is the package body. There must be an
existing package specification with this name.

<private_declaration>

cprivate_declaration> is an identifier of a private variable that can be accessed by any
procedure or function within the package. There can be zero, one, or more private variables.
cprivate_declaration> can be any of the following:

- Variable Declaration
- · Record Declaration
- Collection Declaration
- REF CURSOR and Cursor Variable Declaration
- TYPE Definitions for Records, Collections, and REF CURSORS
- Exception
- Object Variable Declaration

c_name>

The name of the procedure being created.

PRAGMA AUTONOMOUS_TRANSACTION

PRAGMA AUTONOMOUS_TRANSACTION is the directive that sets the procedure as an autonomous transaction.

<declaration>

A variable, type, REF CURSOR, or subprogram declaration. If subprogram declarations are included, they must be declared after all other variable, type, and REF CURSOR declarations.

<statement>

An SPL program statement. Note that a DECLARE - BEGIN - END block is considered an SPL statement unto itself. Thus, the function body may contain nested blocks.

<exception>

An exception condition name such as NO_DATA_FOUND, OTHERS, etc.

<func name>

The name of the function being created.

<rettype>

The return data type, which may be any of the types listed for <argtype>. As for <argtype>, a length must not be specified for <rettype>.

DETERMINISTIC

Include DETERMINISTIC to specify that the function will always return the same result when given the same argument values. A DETERMINISTIC function must not modify the database.

Note: The DETERMINISTIC keyword is equivalent to the PostgreSQL IMMUTABLE option.

Note: If DETERMINISTIC is specified for a public function in the package body, it must also be specified for the function declaration in the package specification. (For private functions, there is no function declaration in the package specification.)

PRAGMA AUTONOMOUS TRANSACTION

PRAGMA AUTONOMOUS_TRANSACTION is the directive that sets the function as an autonomous transaction.

<declaration>

A variable, type, REF CURSOR, or subprogram declaration. If subprogram declarations are included, they must be declared after all other variable, type, and REF CURSOR declarations.

<argname>

The name of a formal argument. The argument is referenced by this name within the procedure body.

IN | IN OUT | OUT

The argument mode. IN declares the argument for input only. This is the default. IN OUT allows the argument to receive a value as well as return a value. OUT specifies the argument is for output only.

<argtype>

The data type(s) of an argument. An argument type may be a base data type, a copy of the type of an existing column using %TYPE, or a user-defined type such as a nested table or an object type. A length must not be specified for any base type - for example, specify VARCHAR2, not VARCHAR2 (10).

The type of a column is referenced by writing <tablename>. <columnname>`%TYPE; using this can sometimes help make a procedure independent from changes to the definition of a table.

```
DEFAULT <value>
```

The DEFAULT clause supplies a default value for an input argument if one is not supplied in the procedure call. DEFAULT may not be specified for arguments with modes IN OUT or OUT.

Please note: the following options are not compatible with Oracle databases; they are extensions to Oracle package syntax provided by Advanced Server only.

STRICT

The STRICT keyword specifies that the function will not be executed if called with a NULL argument; instead the function will return NULL.

LEAKPROOF

The LEAKPROOF keyword specifies that the function will not reveal any information about arguments, other than through a return value.

```
PARALLEL { UNSAFE | RESTRICTED | SAFE }
```

The PARALLEL clause enables the use of parallel sequential scans (parallel mode). A parallel sequential scan uses multiple workers to scan a relation in parallel during a query in contrast to a serial sequential scan.

When set to UNSAFE, the procedure or function cannot be executed in parallel mode. The presence of such a procedure or function forces a serial execution plan. This is the default setting if the PARALLEL clause is omitted.

When set to RESTRICTED, the procedure or function can be executed in parallel mode, but the execution is restricted to the parallel group leader. If the qualification for any particular relation has anything that is parallel restricted, that relation won't be chosen for parallelism.

When set to SAFE, the procedure or function can be executed in parallel mode with no restriction.

```
<execution cost>
```

<execution_cost> specifies a positive number giving the estimated execution cost for the function,
in units of cpu_operator_cost. If the function returns a set, this is the cost per returned row. The
default is 0.0025.

```
`<result rows>
```

<result_rows> is the estimated number of rows that the query planner should expect the function to
return. The default is 1000.

SET

Use the SET clause to specify a parameter value for the duration of the function:

<config_param> specifies the parameter name.

<value> specifies the parameter value.

FROM CURRENT guarantees that the parameter value is restored when the function ends.

<package_initializer>

The statements in the <package_initializer> are executed once per user's session when the package is first referenced.

Note: The STRICT, LEAKPROOF, PARALLEL, COST, ROWS and SET keywords provide extended functionality for Advanced Server and are not supported by Oracle.

2.2 Creating Packages

A package is not an executable piece of code; rather it is a repository of code. When you use a package, you actually execute or make reference to an element within a package.

2.2.1 Creating the Package Specification

The package specification contains the definition of all the elements in the package that can be referenced from outside of the package. These are called the public elements of the package, and they act as the package interface. The following code sample is a package specification:

```
-- Package specification for the 'emp_admin' package.
CREATE OR REPLACE PACKAGE emp_admin
  FUNCTION get_dept_name (
    p_deptno NUMBER DEFAULT 10
  RETURN VARCHAR2;
  FUNCTION update_emp_sal (
    p_empno NUMBER,
    p_raise NUMBER
  RETURN NUMBER;
  PROCEDURE hire_emp (
                    NUMBER,
    p_empno
    p_ename
                     VARCHAR2,
    p_job
                     VARCHAR2,
    p_sal
                     NUMBER,
    p_hiredate
                     DATE
                              DEFAULT
                                       sysdate,
                    NUMBER DEFAULT 0,
    p_comm
                    NUMBER,
    p_mgr
                    NUMBER DEFAULT 10
    p_deptno
  PROCEDURE fire_emp (
    p_empno NUMBER
) ;
END emp_admin;
```

This code sample creates the <code>emp_admin</code> package specification. This package specification consists of two functions and two stored procedures. We can also add the <code>OR REPLACE</code> clause to the <code>CREATE PACKAGE</code> statement for convenience.

2.2.2 Creating the Package Body

The body of the package contains the actual implementation behind the package specification. For the above emp_admin package specification, we shall now create a package body which will implement the specifications. The body will contain the implementation of the functions and stored procedures in the specification.

```
-- Package body for the 'emp_admin' package.
CREATE OR REPLACE PACKAGE BODY emp_admin
TS
   -- Function that queries the 'dept' table based on the department
   -- number and returns the corresponding department name.
   FUNCTION get_dept_name (
       p_deptno IN NUMBER DEFAULT 10
   RETURN VARCHAR2
       v_dname VARCHAR2(14);
   BEGIN
       SELECT dname INTO v_dname FROM dept WHERE deptno = p_deptno;
       RETURN v_dname;
   EXCEPTION
        WHEN NO_DATA_FOUND THEN
           DBMS_OUTPUT.PUT_LINE('Invalid department number ' | | p_deptno);
           RETURN '';
   END:
   -- Function that updates an employee's salary based on the
   -- employee number and salary increment/decrement passed
    -- as IN parameters. Upon successful completion the function
    -- returns the new updated salary.
   FUNCTION update_emp_sal (
       p_empno IN NUMBER,
       p_raise
                     IN NUMBER
   RETURN NUMBER
       v_sal
                     NUMBER := 0;
   BEGIN
       SELECT sal INTO v_sal FROM emp WHERE empno = p_empno;
        v_sal := v_sal + p_raise;
       UPDATE emp SET sal = v_sal WHERE empno = p_empno;
       RETURN v_sal;
   EXCEPTION
      WHEN NO DATA FOUND THEN
         DBMS_OUTPUT.PUT_LINE('Employee ' || p_empno || ' not found');
         RETURN -1;
      WHEN OTHERS THEN
         DBMS_OUTPUT.PUT_LINE('The following is SQLERRM:');
          DBMS_OUTPUT.PUT_LINE (SQLERRM);
          DBMS_OUTPUT.PUT_LINE('The following is SQLCODE:');
          DBMS_OUTPUT.PUT_LINE(SQLCODE);
          RETURN -1;
    END;
```

```
-- Procedure that inserts a new employee record into the 'emp' table.
    PROCEDURE hire_emp (
    p_empno NUMBER,
   p_ename VARCHAR2,
   p_ename
p_job VARCHAKZ,
p_sal NUMBER,
p_hiredate DATE DEFAULT sysdate,
p_comm NUMBER DEFAULT 0,
NUMBER,
    p_deptno NUMBER DEFAULT 10
 )
 AS
 BEGIN
    INSERT INTO emp(empno, ename, job, sal, hiredate, comm, mgr, deptno)
       VALUES(p_empno, p_ename, p_job, p_sal,
               p_hiredate, p_comm, p_mgr, p_deptno);
 END;
 -- Procedure that deletes an employee record from the 'emp' table based
 -- on the employee number.
 PROCEDURE fire_emp (
     p_empno NUMBER
 AS
     DELETE FROM emp WHERE empno = p_empno;
 END;
END;
```

2.3 Referencing a Package

To reference the types, items and subprograms that are declared within a package specification, we use the dot notation. For example:

```
<package_name>.<type_name>
<package_name>.<item_name>
<package_name.<subprogram_name</pre>
```

To invoke a function from the emp_admin package specification, we will execute the following SQL command.

```
SELECT emp_admin.get_dept_name(10) FROM DUAL;
```

Here we are invoking the <code>get_dept_name</code> function declared within the package <code>emp_admin</code>. We are passing the department number as an argument to the function, which will return the name of the department. Here the value returned should be <code>ACCOUNTING</code>, which corresponds to department number <code>10</code>.

2.4 Using Packages With User Defined Types

The following example incorporates the various user-defined types discussed in earlier chapters within the context of a package.

The package specification of emp_rpt shows the declaration of a record type, emprec_typ, and a weakly-typed REF CURSOR, emp_refcur, as publicly accessible along with two functions and two procedures. Function, open_emp_by_dept, returns the REF CURSOR type, EMP_REFCUR. Procedures, fetch_emp and close_refcur, both declare a weakly-typed REF CURSOR as a formal parameter.

```
CREATE OR REPLACE PACKAGE emp rpt
TS
   TYPE emprec_typ IS RECORD (
      empno NUMBER(4),
      ename
                 VARCHAR (10)
  TYPE emp_refcur IS REF CURSOR;
  FUNCTION get_dept_name (
      p_deptno IN NUMBER
  ) RETURN VARCHAR2;
  FUNCTION open_emp_by_dept (
      p_deptno IN emp.deptno%TYPE
  ) RETURN EMP REFCUR;
  PROCEDURE fetch_emp (
      p_refcur IN OUT SYS_REFCURSOR
  );
  PROCEDURE close_refcur (
      p_refcur IN OUT SYS_REFCURSOR
  );
  END emp_rpt;
```

The package body shows the declaration of several private variables - a static cursor, dept_cur, a table type, depttab_typ, a table variable, t_dept, an integer variable, t_dept_max, and a record variable, r_emp.

```
CREATE OR REPLACE PACKAGE BODY emp_rpt
   CURSOR dept_cur IS SELECT * FROM dept;
   TYPE depttab_typ IS TABLE of dept%ROWTYPE
       INDEX BY BINARY_INTEGER;
   t_dept DEPTTAB_TYP;
   t_dept_max INTEGER := 1;
r_emp EMPREC_TYP;
   FUNCTION get_dept_name (
       p_deptno IN NUMBER
   ) RETURN VARCHAR2
   BEGIN
       FOR i IN 1..t_dept_max LOOP
           IF p_deptno = t_dept(i).deptno THEN
               RETURN t_dept(i).dname;
           END IF;
       END LOOP;
       RETURN 'Unknown';
 FUNCTION open_emp_by_dept(
   p_deptno
                    IN emp.deptno%TYPE
```

```
) RETURN EMP_REFCUR
 TS
   emp_by_dept EMP_REFCUR;
 BEGIN
   OPEN emp_by_dept FOR SELECT empno, ename FROM emp
       WHERE deptno = p_deptno;
   RETURN emp_by_dept;
 END;
 PROCEDURE fetch_emp (
     p_refcur IN OUT SYS_REFCURSOR
 )
 IS
 BEGIN
     DBMS_OUTPUT.PUT_LINE('EMPNO ENAME');
     DBMS_OUTPUT.PUT_LINE('----');
     LOOP
         FETCH p_refcur INTO r_emp;
         EXIT WHEN p_refcur%NOTFOUND;
         DBMS_OUTPUT.PUT_LINE(r_emp.empno || ' ' || r_emp.ename);
     END LOOP;
 END;
 PROCEDURE close_refcur (
     )
 IS
 BEGIN
     CLOSE p_refcur;
 END:
BEGIN
 OPEN dept_cur;
 LOOP
     FETCH dept_cur INTO t_dept(t_dept_max);
     EXIT WHEN dept_cur%NOTFOUND;
     t_dept_max := t_dept_max + 1;
 END LOOP;
 CLOSE dept_cur;
 t_dept_max := t_dept_max - 1;
END emp_rpt;
```

This package contains an initialization section that loads the private table variable, t_dept, using the private static cursor, dept_cur.t_dept serves as a department name lookup table in function, get_dept_name.

Function, open_emp_by_dept returns a REF CURSOR variable for a result set of employee numbers and names for a given department. This REF CURSOR variable can then be passed to procedure, fetch_emp, to retrieve and list the individual rows of the result set. Finally, procedure, close_refcur, can be used to close the REF CURSOR variable associated with this result set.

The following anonymous block runs the package function and procedures. In the anonymous block's declaration section, note the declaration of cursor variable, v_emp_cur, using the package's public REF CURSOR type, EMP_REFCUR. v_emp_cur contains the pointer to the result set that is passed between the package function and procedures.

The following is the result of this anonymous block.

The following anonymous block illustrates another means of achieving the same result. Instead of using the package procedures, fetch_emp and close_refcur, the logic of these programs is coded directly into the anonymous block. In the anonymous block's declaration section, note the addition of record variable, r_emp, declared using the package's public record type, EMPREC_TYP.

```
DECLARE
              dept.deptno%TYPE DEFAULT 30;
   v_deptno
   v_emp_cur emp_rpt.EMP_REFCUR;
              emp_rpt.EMPREC_TYP;
   r emp
BEGIN
  v_emp_cur := emp_rpt.open_emp_by_dept(v_deptno);
  DBMS_OUTPUT.PUT_LINE('EMPLOYEES IN DEPT #' || v_deptno ||
      ': ' || emp_rpt.get_dept_name(v_deptno));
  DBMS_OUTPUT.PUT_LINE('EMPNO ENAME');
  DBMS_OUTPUT.PUT_LINE('----');
  LOOP
      FETCH v_emp_cur INTO r_emp;
      EXIT WHEN v_emp_cur%NOTFOUND;
      DBMS_OUTPUT.PUT_LINE(r_emp.empno || ' ' ||
     r_emp.ename);
  END LOOP;
  DBMS_OUTPUT.PUT_LINE(v_emp_cur%ROWCOUNT || ' rows were retrieved');
  CLOSE v_emp_cur;
END;
```

The following is the result of this anonymous block.

2.5 Dropping a Package

The syntax for deleting an entire package or just the package body is as follows:

```
DROP PACKAGE [ BODY ] <package_name>;
```

If the keyword, BODY, is omitted, both the package specification and the package body are deleted - i.e., the entire package is dropped. If the keyword, BODY, is specified, then only the package body is dropped. The package specification remains intact. <package_name> is the identifier of the package to be dropped.

Following statement will destroy only the package body of <emp_admin>:

```
DROP PACKAGE BODY emp_admin;
```

The following statement will drop the entire <emp_admin> package:

```
DROP PACKAGE emp_admin;
```

CHAPTER 3

Built-In Packages

This chapter describes the built-in packages that are provided with Advanced Server. For certain packages, non-superusers must be explicitly granted the EXECUTE privilege on the package before using any of the package's functions or procedures. For most of the built-in packages, EXECUTE privilege has been granted to PUBLIC by default.

For information about using the GRANT command to provide access to a package, please see the *Database Compatibility for Oracle Developers Reference Guide*, available at:

https://www.enterprisedb.com/edb-docs

All built-in packages are owned by the special sys user which must be specified when granting or revoking privileges on built-in packages:

GRANT EXECUTE ON PACKAGE SYS.UTL_FILE TO john;

3.1 DBMS_ALERT

The DBMS_ALERT package provides the capability to register for, send, and receive alerts. The following table lists the supported procedures:

Function/Procedure	Return	Description
	Type	
REGISTER(<name>)</name>	n/a	Register to be able to receive alerts
		named, <name></name>
REMOVE(<name>)</name>	n/a	Remove registration for the alert
		named, <name></name>
REMOVEALL	n/a	Remove registration for all alerts.
SIGNAL(<name>, <message>)</message></name>	n/a	Signals the alert named, <name>,</name>
		with <message></message>
WAITANY(<name> OUT, <message> OUT,</message></name>	n/a	Wait for any registered alert to occur.
<status> OUT, <timeout>)</timeout></status>		
WAITONE(<name>, <message. <status="" out,=""></message.></name>	n/a	Wait for the specified alert, <name>,</name>
OUT, <timeout>)</timeout>		to occur.

Advanced Server's implementation of DBMS_ALERT is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Advanced Server allows a maximum of 500 concurrent alerts. You can use the <code>dbms_alert.max_alerts</code> GUC variable (located in the <code>postgresql.conf</code> file) to specify the maximum number of concurrent alerts allowed on a system.

To set a value for the $dbms_alert.max_alerts$ variable, open the postgresql.conf file (located by default in /opt/PostgresPlus/10AS/data) with your choice of editor, and edit the $dbms_alert.max_alerts$ parameter as shown:

```
dbms_alert.max_alerts = <alert_count>
<alert count>
```

alert_count specifies the maximum number of concurrent alerts. By default, the value of dbms_alert.max_alerts is 100. To disable this feature, set dbms_alert.max_alerts to 0.

For the dbms_alert.max_alerts GUC to function correctly, the custom_variable_classes parameter must contain dbms_alerts:

```
custom_variable_classes = 'dbms_alert, ...'
```

After editing the postgresql.conf file parameters, you must restart the server for the changes to take effect.

3.1.1 REGISTER

The REGISTER procedure enables the current session to be notified of the specified alert.

```
REGISTER(<name> VARCHAR2)
```

Parameters

<name>

Name of the alert to be registered.

Examples

The following anonymous block registers for an alert named, alert_test, then waits for the signal.

```
DECLARE
                   VARCHAR2(30) := 'alert_test';
  v_name
  v_msg
                  VARCHAR2(80);
  v_status
                  INTEGER;
  v_timeout
                  NUMBER (3) := 120;
BEGIN
  DBMS_ALERT.REGISTER(v_name);
  DBMS_OUTPUT.PUT_LINE('Registered for alert ' || v_name);
  DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
  DBMS_ALERT.WAITONE(v_name, v_msg, v_status, v_timeout);
  DBMS_OUTPUT.PUT_LINE('Alert name : ' || v_name);
  DBMS_OUTPUT.PUT_LINE('Alert msg : ' || v_msg);
  DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
  DBMS_OUTPUT.PUT_LINE('Alert timeout: ' || v_timeout || ' seconds');
  DBMS_ALERT.REMOVE(v_name);
END;
Registered for alert alert_test
Waiting for signal...
```

3.1.2 REMOVE

The REMOVE procedure unregisters the session for the named alert.

```
REMOVE(<name> VARCHAR2)
```

Parameters

<name>

Name of the alert to be unregistered.

3.1.3 REMOVEALL

The REMOVEALL procedure unregisters the session for all alerts.

REMOVEALL

3.1.4 SIGNAL

The SIGNAL procedure signals the occurrence of the named alert.

```
SIGNAL(<name> VARCHAR2, <message> VARCHAR2)
```

Parameters

<name>

Name of the alert.

<message>

Information to pass with this alert.

Examples

The following anonymous block signals an alert for alert_test.

```
DECLARE

v_name VARCHAR2(30) := 'alert_test';

BEGIN

DBMS_ALERT.SIGNAL(v_name,'This is the message from ' || v_name);

DBMS_OUTPUT_LINE('Issued alert for ' || v_name);

END;

Issued alert for alert_test
```

3.1.5 WAITANY

The WAITANY procedure waits for any of the registered alerts to occur.

Parameters

<name>

Variable receiving the name of the alert.

<message>

Variable receiving the message sent by the SIGNAL procedure.

```
<status>
```

Status code returned by the operation. Possible values are: 0 – alert occurred; 1 – timeout occurred.

<timeout>

Time to wait for an alert in seconds.

Examples

The following anonymous block uses the WAITANY procedure to receive an alert named, alert_test or any_alert:

```
DECLARE
                    VARCHAR2(30);
   v_name
   v_msq
                    VARCHAR2(80);
   v_status
                   INTEGER;
                   NUMBER(3) := 120;
   v_timeout
BEGIN
  DBMS_ALERT.REGISTER('alert_test');
  DBMS_ALERT.REGISTER('any_alert');
  DBMS_OUTPUT.PUT_LINE('Registered for alert alert_test and any_alert');
  DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
  DBMS_ALERT.WAITANY(v_name, v_msg, v_status, v_timeout);
  DBMS_OUTPUT.PUT_LINE('Alert name : ' || v_name);
                                    : ' || v_msq);
  DBMS_OUTPUT.PUT_LINE('Alert msg
  DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
  DBMS_OUTPUT.PUT_LINE('Alert timeout: ' || v_timeout || ' seconds');
  DBMS_ALERT.REMOVEALL;
END;
```

```
Registered for alert alert_test and any_alert Waiting for signal...
```

An anonymous block in a second session issues a signal for any_alert:

```
DECLARE

v_name VARCHAR2(30) := 'any_alert';

BEGIN

DBMS_ALERT.SIGNAL(v_name,'This is the message from ' || v_name);

DBMS_OUTPUT.PUT_LINE('Issued alert for ' || v_name);

END;

Issued alert for any_alert
```

Control returns to the first anonymous block and the remainder of the code is executed:

```
Registered for alert alert_test and any_alert
Waiting for signal...
Alert name : any_alert
Alert msg : This is the message from any_alert
Alert status : 0
Alert timeout: 120 seconds
```

3.1.6 WAITONE

The WAITONE procedure waits for the specified registered alert to occur.

Parameters

<name>

Name of the alert.

<message>

Variable receiving the message sent by the SIGNAL procedure.

<status>

Status code returned by the operation. Possible values are: 0 – alert occurred; 1 – timeout occurred.

<timeout>

Time to wait for an alert in seconds.

Examples

The following anonymous block is similar to the one used in the WAITANY example except the WAITONE procedure is used to receive the alert named, alert_test.

```
DECLARE
                   VARCHAR2(30) := 'alert test';
   v name
                    VARCHAR2(80);
   v msa
   v_status
                    INTEGER;
                   NUMBER(3) := 120;
   v_timeout
BEGIN
  DBMS_ALERT.REGISTER(v_name);
  DBMS_OUTPUT.PUT_ DBMS_ALERT.REGISTER(v_name);
  DBMS OUTPUT.PUT LINE ('Registered for alert ' | | v name);
  DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
  DBMS_ALERT.WAITONE(v_name, v_msg, v_status, v_timeout);
  DBMS_OUTPUT.PUT_LINE('Alert name : ' | | v_name);
  DBMS_OUTPUT.PUT_LINE('Alert msg : ' || v_msg);
  DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
  DBMS OUTPUT.PUT LINE('Alert timeout: ' | | v timeout | | ' seconds');
  DBMS_ALERT.REMOVE(v_name); LINE('Registered for alert ' | | v_name);
  DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
  DBMS_ALERT.WAITONE(v_name, v_msg, v_status, v_timeout);
  DBMS_OUTPUT.PUT_LINE('Alert name : ' || v_name);
                                      : ' || v_msg);
  DBMS_OUTPUT.PUT_LINE('Alert msg
  DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
  DBMS_OUTPUT.PUT_LINE('Alert timeout: ' || v_timeout || ' seconds');
  DBMS ALERT.REMOVE (v name);
  END:
  Registered for alert alert_test
   Waiting for signal ...
```

Signal sent for alert_test sent by an anonymous block in a second session:

```
DECLARE

v_name VARCHAR2(30) := 'alert_test';

BEGIN

DBMS_ALERT.SIGNAL(v_name,'This is the message from ' || v_name);

DBMS_OUTPUT_LINE('Issued alert for ' || v_name);

END;

Issued alert for alert_test
```

First session is alerted, control returns to the anonymous block, and the remainder of the code is executed:

```
Registered for alert_alert_test
Waiting for signal...
Alert name : alert_test
Alert msg : This is the message from alert_test
Alert status : 0
Alert timeout: 120 seconds
```

3.1.7 Comprehensive Example

The following example uses two triggers to send alerts when the dept table or the emp table is changed. An anonymous block listens for these alerts and displays messages when an alert is received.

The following are the triggers on the dept and emp tables:

```
CREATE OR REPLACE TRIGGER dept_alert_trig
  AFTER INSERT OR UPDATE OR DELETE ON dept
DECLARE
    v_action
                VARCHAR2 (25);
BEGIN
  IF INSERTING THEN
      v_action := ' added department(s) ';
  ELSIF UPDATING THEN
      v_action := ' updated department(s) ';
  ELSIF DELETING THEN
      v_action := ' deleted department(s) ';
  END IF:
  DBMS_ALERT.SIGNAL('dept_alert', USER || v_action || 'on ' ||
      SYSDATE);
END;
CREATE OR REPLACE TRIGGER emp_alert_trig
    AFTER INSERT OR UPDATE OR DELETE ON emp
DECLARE
    v_action VARCHAR2(25);
BEGIN
  IF INSERTING THEN
      v_action := ' added employee(s) ';
  ELSIF UPDATING THEN
      v_action := ' updated employee(s) ';
  ELSIF DELETING THEN
      v_action := ' deleted employee(s) ';
  END IF;
   DBMS_ALERT.SIGNAL('emp_alert', USER || v_action || 'on ' ||
      SYSDATE);
END;
```

The following anonymous block is executed in a session while updates to the dept and emp tables occur in other sessions:

```
DECLARE
    VARCHAR2(30) := 'dept_alert';
    v_msq
                   VARCHAR2(80);
                   INTEGER;
    v_status
    v_timeout
                  NUMBER(3) := 60;
BEGIN
    DBMS_ALERT.REGISTER(v_dept_alert);
    DBMS_ALERT.REGISTER(v_emp_alert);
    DBMS_OUTPUT.PUT_LINE('Registered for alerts dept_alert and emp_alert');
    DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
    T.OOP
        DBMS_ALERT.WAITANY(v_name, v_msg, v_status, v_timeout);
        EXIT WHEN v_status != 0;
        DBMS_OUTPUT.PUT_LINE('Alert name : ' || v_name);
                                        : ' || v_msg);
        DBMS_OUTPUT.PUT_LINE('Alert msg
```

```
DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);

DBMS_OUTPUT.PUT_LINE('-----');

END LOOP;

DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);

DBMS_ALERT.REMOVEALL;

END;
```

Registered for alerts dept_alert and emp_alert Waiting for signal. . .

The following changes are made by user, mary:

```
INSERT INTO dept VALUES (50, 'FINANCE', 'CHICAGO');
INSERT INTO emp (empno, ename, deptno) VALUES (9001, 'JONES', 50);
INSERT INTO emp (empno, ename, deptno) VALUES (9002, 'ALICE', 50);
```

The following change is made by user, john:

```
INSERT INTO dept VALUES (60, 'HR', 'LOS ANGELES');
```

The following is the output displayed by the anonymous block receiving the signals from the triggers:

3.2 DBMS_AQ

EDB Postgres Advanced Server Advanced Queueing provides message queueing and message processing for the Advanced Server database. User-defined messages are stored in a queue; a collection of queues is stored in a queue table. Procedures in the DBMS_AQADM package create and manage message queues and queue tables. Use the DBMS_AQ package to add messages to a queue or remove messages from a queue, or register or unregister a PL/SQL callback procedure.

Advanced Server also provides extended (non-compatible) functionality for the DBMS_AQ package with SQL commands. Please see the *Database Compatibility for Oracle Developers Reference Guide* for detailed information about the following SQL commands:

- ALTER QUEUE
- ALTER QUEUE TABLE
- CREATE QUEUE
- CREATE QUEUE TABLE
- DROP QUEUE
- DROP QUEUE TABLE

The DBMS_AQ package provides procedures that allow you to enqueue a message, dequeue a message, and manage callback procedures. The supported procedures are:

Function/Procedure	Return Type	Description
ENQUEUE n/a		Post a message to a queue.
DEQUEUE	n/a	Retrieve a message from a queue if or when a message is available.
REGISTER	n/a	Register a callback procedure.
UNREGISTER	n/a	Unregister a callback procedure.

Advanced Server's implementation of DBMS_AQ is a partial implementation when compared to Oracle's version. Only those procedures listed in the table above are supported.

Advanced Server supports use of the constants listed below:

Constant	Description	For Parameters
DBMS_AQ.BROWSE (0)	Read the message without	dequeue_options_t.dequeue_mode
	locking.	
DBMS_AQ.LOCKED (1)	This constant is defined,	dequeue_options_t.dequeue_mode
	but will return an error if	
	used.	
DBMS_AQ.REMOVE (2)	Delete the message after	dequeue_options_t.dequeue_mode
	reading; the default.	
DBMS_AQ.REMOVE_NODATA (3)	This constant is defined,	dequeue_options_t.dequeue_mode
	but will return an error if	
	used.	
DBMS_AQ.FIRST_MESSAGE (0)	Return the first available	dequeue_options_t.navigation
	message that matches the	
	search terms.	
DBMS_AQ.NEXT_MESSAGE (1)	Return the next available	dequeue_options_t.navigation
	message that matches the	
	search terms.	
		O = == 1 = = = = = = = = = = = = = = = =

Continued on next page

3.2. DBMS AQ 29

Table 3.1 – continued from previous page

DBMS_AQ.NEXT_TRANSACTION (2)	This constant is defined,	dequeue_options_t.navigation	
	but will return an error if		
	used.		
DBMS_AQ.FOREVER (-1)	Wait forever if a message	dequeue_options_t.wait	
	that matches the search		
	term is not found, the de-		
	fault.		
DBMS_AQ.NO_WAIT (0)	Do not wait if a message	dequeue_options_t.wait	
	that matches the search		
	term is not found.		
DBMS_AQ.ON_COMMIT (0)	The dequeue is part of the	enqueue_options_t.visibility, de-	
	current transaction.	queue_options_t.visibility	
DBMS_AQ.IMMEDIATE (1)	This constant is defined,	enqueue_options_t.visibility, de-	
	but will return an error if	queue_options_t.visibility	
	used.		
DBMS_AQ.PERSISTENT (0)	The message should be	enqueue_options_t.delivery_mode	
	stored in a table.		
DBMS_AQ.BUFFERED (1)	This constant is defined,	enqueue_options_t.delivery_mode	
	but will return an error if		
	used.		
DBMS_AQ.READY (0)	Specifies that the message	message_properties_t.state	
	is ready to process.		
DBMS_AQ.WAITING (1)	Specifies that the message	message_properties_t.state	
	is waiting to be processed.		
DBMS_AQ.PROCESSED (2)	Specifies that the message	message_properties_t.state	
	has been processed.		
DBMS_AQ.EXPIRED (3)	Specifies that the message	message_properties_t.state	
	is in the exception queue.		
DBMS_AQ.NO_DELAY (0)	This constant is defined,	message_properties_t.delay	
	but will return an error if		
	used		
DBMS_AQ.NEVER (NULL)	This constant is defined,	message_properties_t.expiration	
	but will return an error if		
	used		
DBMS_AQ.NAMESPACE_AQ (0)	Accept notifications from	sys.aq\$_reg_info.namespace	
	DBMS_AQ queues.		
DBMS_AQ.NAMESPACE_ANONYMOUS	This constant is defined,	sys.aq\$_reg_info.namespace	
(1)	but will return an error if		
	used		

The DBMS_AQ configuration parameters listed in the following table can be defined in the postgresql.conf file. After the configuration parameters are defined, you can invoke the DBMS_AQ package to use and manage messages held in queues and queue tables.

Parameter	Description
dbms_aq.max_workers	The maximum number of workers to run.
dbms_aq.max_idle_time	The idle time a worker must wait before exiting.
dbms_aq.min_work_time	The minimum time a worker can run before exiting.
dbms_aq.launch_delay	The minimum time between creating workers.
dbms_aq.batch_size	The maximum number of messages to process in a single transac-
	tion. The default batch size is 10.
dbms_aq.max_databases	The size of DBMS_AQ's hash table of databases. The default value
	is 1024.
dbms_aq.max_pending_retries	The size of DBMS_AQ's hash table of pending retries. The default
	value is 1024.

3.2.1 ENQUEUE

The ENQUEUE procedure adds an entry to a queue. The signature is:

Parameters

```
<queue_name>
```

The name (optionally schema-qualified) of an existing queue. If you omit the schema name, the server will use the schema specified in the SEARCH_PATH. Please note that unlike Oracle, unquoted identifiers are converted to lower case before storing. To include special characters or use a case-sensitive name, enclose the name in double quotes.

For detailed information about creating a queue, please see DBMS_AQADM.CREATE_QUEUE.

```
<enqueue_options>
```

<enqueue_options> is a value of the type, enqueue_options_t:

```
DBMS_AQ.ENQUEUE_OPTIONS_T IS RECORD(
   visibility BINARY_INTEGER DEFAULT ON_COMMIT,
   relative_msgid RAW(16) DEFAULT NULL,
   sequence_deviation BINARY INTEGER DEFAULT NULL,
   transformation VARCHAR2(61) DEFAULT NULL,
   delivery_mode PLS_INTEGER NOT NULL DEFAULT PERSISTENT);
```

Currently, the only supported parameter values for enqueue_options_t are:

visibility	ON_COMMIT.
delivery_mode	PERSISTENT
sequence_deviation	NULL
transformation	NULL
relative_msgid	NULL

<message properties>

<message_properties> is a value of the type, message_properties_t:

```
message_properties_t IS RECORD(
    priority INTEGER,
    delay INTEGER,
    expiration INTEGER,
    correlation CHARACTER VARYING(128) COLLATE pg_catalog."C",
    attempts INTEGER,
    recipient_list "AQ$_RECIPIENT_LIST_T",
    exception_queue CHARACTER VARYING(61) COLLATE pg_catalog."C",
    enqueue_time TIMESTAMP WITHOUT TIME ZONE,
    state INTEGER,
    original_msgid BYTEA,
```

```
transaction_group CHARACTER VARYING(30) COLLATE pg_catalog."C",
  delivery_mode INTEGER
DBMS_AQ.PERSISTENT);
```

The supported values for message_properties_t are:

priority	If the queue table definition includes a sort_list that references	
	priority, this parameter affects the order that messages are dequeued. A	
	lower value indicates a higher dequeue priority.	
delay	Specify the number of seconds that will pass before a message is available for	
	dequeueing or NO_DELAY.	
expiration	Use the expiration parameter to specify the number of seconds until a message	
	expires.	
correlation	Use correlation to specify a message that will be associated with the entry; the	
	default is NULL.	
attempts	This is a system-maintained value that specifies the number of attempts to de-	
	queue the message.	
recipient_list	This parameter is not supported.	
exception_queue	Use the exception_queue parameter to specify the name of an exception	
	queue to which a message will be moved if it expires or is dequeued by a trans-	
	action that rolls back too many times.	
enqueue_time	enqueue_time is the time the record was added to the queue; this value is	
	provided by the system.	
state	This parameter is maintained by DBMS_AQ; state can be:	
	DBMS_AQ.WAITING – the delay has not been reached.	
	DBMS_AQ.READY – the queue entry is ready for processing.	
	DBMS_AQ.PROCESSED – the queue entry has been processed.	
	DBMS_AQ.EXPIRED – the queue entry has been moved to the exception	
	queue.	
original_msgid	This parameter is accepted for compatibility and ignored.	
transaction_group	This parameter is accepted for compatibility and ignored.	
delivery_mode	This parameter is not supported; specify a value of DBMS_AQ.PERSISTENT.	

<payload>

Use the <payload> parameter to provide the data that will be associated with the queue entry. The payload type must match the type specified when creating the corresponding queue table (see DBMS_AQADM. CREATE_QUEUE_TABLE).

<msgid>

Use the <msgid> parameter to retrieve a unique (system-generated) message identifier.

Example

The following anonymous block calls DBMS AQ. ENQUEUE, adding a message to a queue named work order:

3.2.2 DEQUEUE

The DEQUEUE procedure dequeues a message. The signature is:

Parameters

```
<queue_name>
```

The name (optionally schema-qualified) of an existing queue. If you omit the schema name, the server will use the schema specified in the SEARCH_PATH. Please note that unlike Oracle, unquoted identifiers are converted to lower case before storing. To include special characters or use a case-sensitive name, enclose the name in double quotes.

For detailed information about creating a queue, please see DBMS_AQADM.CREATE_QUEUE.

```
<dequeue_options>
```

<dequeue_options> is a value of the type, dequeue_options_t:

```
DEQUEUE_OPTIONS_T IS RECORD(
   consumer_name CHARACTER VARYING(30),
   dequeue_mode INTEGER,
   navigation INTEGER,
   visibility INTEGER,
   wait INTEGER,
   msgid BYTEA,
   correlation CHARACTER VARYING(128),
   deq_condition CHARACTER VARYING(4000),
   transformation CHARACTER VARYING(61),
   delivery_mode INTEGER);
```

Currently, the supported parameter values for dequeue_options_t are:

consumer_name	Must be NULL.		
dequeue_mode	The locking behavior of the dequeue operation. Must be either:		
	DBMS_AQ.BROWSE – Read the message without obtaining a lock.		
	DBMS_AQ.LOCKED – Read the message after acquiring a lock.		
	DBMS_AQ.REMOVE – Read the message before deleting the message.		
	DBMS_AQ.REMOVE_NODATA – Read the message, but do not delete the mes-		
	sage.		
navigation	Identifies the message that will be retrieved. Must be either:		
	FIRST_MESSAGE – The first message within the queue that matches the search		
	term.		
	NEXT_MESSAGE – The next message that is available that matches the first		
	term.		
visibility	Must be ON_COMMIT – if you roll back the current transaction the dequeued		
	item will remain in the queue.		
wait	Must be a number larger than 0, or:		
	DBMS_AQ.FOREVER – Wait indefinitely.		
	DBMS_AQ.NO_WAIT - Do not wait.		
msgid	The message ID of the message that will be dequeued.		
correlation	Accepted for compatibility, and ignored.		
deq_condition	A VARCHAR2 expression that evaluates to a BOOLEAN value indicating if the		
	message should be dequeued		
transformation	Accepted for compatibility, and ignored.		
delivery_mode	Must be PERSISTENT; buffered messages are not supported at this time.		

<message_properties>

<message_properties> is a value of the type, message_properties_t:

```
message_properties_t IS RECORD(
    priority INTEGER,
    delay INTEGER,
    expiration INTEGER,
    correlation CHARACTER VARYING(128) COLLATE pg_catalog."C",
    attempts INTEGER,
    recipient_list "AQ$_RECIPIENT_LIST_T",
    exception_queue CHARACTER VARYING(61) COLLATE pg_catalog."C",
    enqueue_time TIMESTAMP WITHOUT TIME ZONE,
    state INTEGER,
    original_msgid BYTEA,
    transaction_group CHARACTER VARYING(30) COLLATE pg_catalog."C",
    delivery_mode INTEGER

DBMS_AQ.PERSISTENT);
```

The supported values for $message_properties_t$ are:

priority	If the queue table definition includes a sort_list that references priority,		
	this parameter affects the order that messages are dequeued. A lower value		
	indicates a higher dequeue priority.		
delay	Specify the number of seconds that will pass before a message is available for		
	dequeueing or NO_DELAY.		
expiration	Use the expiration parameter to specify the number of seconds until a message		
	expires.		
correlation	Use correlation to specify a message that will be associated with the entry; the		
	default is NULL.		
attempts	This is a system-maintained value that specifies the number of attempts to de-		
	queue the message.		
recipient_list	This parameter is not supported.		
exception_queue	Use the exception_queue parameter to specify the name of an exception		
	queue to which a message will be moved if it expires or is dequeued by a trans-		
	action that rolls back too many times.		
enqueue_time	enqueue_time is the time the record was added to the queue; this value is		
	provided by the system.		
state	This parameter is maintained by DBMS_AQ; state can be: DBMS_AQ.WAITING		
	- the delay has not been reached. DBMS_AQ.READY - the queue entry is		
	ready for processing. DBMS_AQ.PROCESSED – the queue entry has been pro-		
	cessed. DBMS_AQ.EXPIRED – the queue entry has been moved to the excep-		
	tion queue.		
original_msgid	This parameter is accepted for compatibility and ignored.		
transaction_group	This parameter is accepted for compatibility and ignored.		
delivery_mode	This parameter is not supported; specify a value of DBMS_AQ.PERSISTENT.		

<payload>

Use the <payload> parameter to retrieve the payload of a message with a dequeue operation. The payload type must match the type specified when creating the queue table.

<msgid>

Use the <msqid> parameter to retrieve a unique message identifier.

Example

The following anonymous block calls DBMS_AQ.DEQUEUE, retrieving a message from the queue and a payload:

```
DECLARE
 message_properties DBMS_AQ.MESSAGE_PROPERTIES_T;
 message_handle raw(16);
 payload
                work_order;
BEGIN
 dequeue_options.dequeue_mode := DBMS_AQ.BROWSE;
 DBMS_AQ.DEQUEUE(
                => 'work_queue',
  queue_name
  dequeue_options => dequeue_options,
  message_properties => message_properties,
   payload => payload,
                  => message_handle
   msgid
 );
```

```
DBMS_OUTPUT.PUT_LINE(
   'The next work order is [' || payload.subject || '].'
   );
END;
```

The payload is displayed by DBMS_OUTPUT.PUT_LINE.

3.2.3 REGISTER

Use the REGISTER procedure to register an email address, procedure or URL that will be notified when an item is enqueued or dequeued. The signature is:

Parameters

```
<reg_list>
```

<reg_list> is a list of type AQ\$_REG_INFO_LIST; that provides information about each subscription that you would like to register. Each entry within the list is of the type AQ\$_REG_INFO, and may contain:

Attribute	Type	Description
name	VARCHAR2	The (optionally schema-qualified) name of the subscription.
	(128)	
namespace	NUMERIC	The only supported value is DBMS_AQ.NAMESPACE_AQ
		(0)
callback	VARCHAR2	Describes the action that will be performed upon notifica-
	(4000)	tion. Currently, only calls to PL/SQL procedures are sup-
		ported. The call should take the form:
		plsql://schema.procedure
		Where:
		schema specifies the schema in which the proce-
		dure resides.
		procedure specifies the name of the procedure
		that will be notified.
context	RAW (16)	Any user-defined value required by the callback procedure.

<count>

<count> is the number of entries in <req_list>.

Example

The following anonymous block calls <code>DBMS_AQ.REGISTER</code>, registering procedures that will be notified when an item is added to or removed from a queue. A set of attributes (of <code>sys.aq\$_reg_info</code> type) is provided for each subscription identified in the <code>DECLARE</code> section:

```
DECLARE
    subscription1 sys.aq$_reg_info;
    subscription2 sys.aq$_reg_info;
    subscription3 sys.aq$_reg_info;
    subscriptionlist sys.aq$_reg_info_list;

BEGIN
    subscription1 := sys.aq$_reg_info('q', DBMS_AQ.NAMESPACE_AQ,
    'plsql://assign_worker?PR=0',HEXTORAW('FFFF'));
    subscription2 := sys.aq$_reg_info('q', DBMS_AQ.NAMESPACE_AQ,
    'plsql://add_to_history?PR=1',HEXTORAW('FFFF'));
    subscription3 := sys.aq$_reg_info('q', DBMS_AQ.NAMESPACE_AQ,
    'plsql://reserve_parts?PR=2',HEXTORAW('FFFF'));
```

```
subscriptionlist := sys.aq$_reg_info_list(subscription1,
subscription2, subscription3);
dbms_aq.register(subscriptionlist, 3);
commit;

END;
/
```

The subscriptionlist is of type sys.aq\$_reg_info_list, and contains the previously described sys.aq\$_reg_info objects. The list name and an object count are passed to dbms_aq.register.

3.2.4 UNREGISTER

Use the UNREGISTER procedure to turn off notifications related to enqueueing and dequeueing. The signature is:

Parameter

<reg_list>

<reg_list> is a list of type AQ\$_REG_INFO_LIST; that provides information about each subscription that you would like to register. Each entry within the list is of the type AQ\$_REG_INFO, and may contain:

Attribute	Туре	Description	
name	VARCHAR2 (128)	The (optionally schema-qualified) name of the subscription.	
namespace	NUMERIC	The only supported value is DBMS_AQ.NAMESPACE_AQ (0)	
callback	VARCHAR2 (4000)	Describes the action that will be performed upon notification. Cur-	
		rently, only calls to PL/SQL procedures are supported. The call	
		should take the form:	
		plsql://schema.procedure	
		Where:	
		schema specifies the schema in which the procedure re-	
		sides.	
		procedure specifies the name of the procedure that will	
		be notified.	
context	RAW (16)	Any user-defined value required by the procedure.	

<count>

<count> is the number of entries in <req_list>.

Example

The following anonymous block calls <code>DBMS_AQ.UNREGISTER</code>, disabling the notifications specified in the example for <code>DBMS_AQ.REGISTER</code>:

```
DECLARE

subscription1 sys.aq$_reg_info;
subscription2 sys.aq$_reg_info;
subscription3 sys.aq$_reg_info;
subscriptionlist sys.aq$_reg_info_list;

BEGIN

subscription1 := sys.aq$_reg_info('q', DBMS_AQ.NAMESPACE_AQ,
'plsql://assign_worker?PR=0',HEXTORAW('FFFF'));
subscription2 := sys.aq$_reg_info('q', DBMS_AQ.NAMESPACE_AQ,
'plsql://add_to_history?PR=1',HEXTORAW('FFFF'));
subscription3 := sys.aq$_reg_info('q', DBMS_AQ.NAMESPACE_AQ,
'plsql://reserve_parts?PR=2',HEXTORAW('FFFF'));
subscription1ist := sys.aq$_reg_info_list(subscription1,
```

```
subscription2, subscription3);

dbms_aq.unregister(subscriptionlist, 3);
  commit;
END;
/
```

The subscriptionlist is of type sys.aq\$_reg_info_list, and contains the previously described sys.aq\$_reg_info objects. The list name and an object count are passed to dbms_aq.unregister.

3.3 DBMS_AQADM

EDB Postgres Advanced Server Advanced Queueing provides message queueing and message processing for the Advanced Server database. User-defined messages are stored in a queue; a collection of queues is stored in a queue table. Procedures in the DBMS_AQADM package create and manage message queues and queue tables. Use the DBMS_AQ package to add messages to a queue or remove messages from a queue, or register or unregister a PL/SQL callback procedure.

Advanced Server also provides extended (non-compatible) functionality for the DBMS_AQ package with SQL commands. Please see the *Database Compatibility for Oracle Developers Reference Guide* for detailed information about the following SQL commands:

- ALTER QUEUE
- ALTER QUEUE TABLE
- CREATE QUEUE
- CREATE QUEUE TABLE
- DROP QUEUE
- DROP QUEUE TABLE

The DBMS_AQADM package provides procedures that allow you to create and manage queues and queue tables.

Function/Procedure	Return	Description
	Type	
ALTER_QUEUE	n/a	Modify an existing queue.
ALTER_QUEUE_TABLE	n/a	Modify an existing queue table.
CREATE_QUEUE	n/a	Create a queue.
CREATE_QUEUE_TABLE	n/a	Create a queue table.
DROP_QUEUE	n/a	Drop an existing queue.
DROP_QUEUE_TABLE	n/a	Drop an existing queue table.
PURGE_QUEUE_TABLE	n/a	Remove one or more messages from a queue table.
START_QUEUE	n/a	Make a queue available for enqueueing and dequeueing procedures.
STOP_QUEUE	n/a	Make a queue unavailable for enqueueing and dequeueing proce-
		dures

Advanced Server's implementation of DBMS_AQADM is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Advanced Server supports use of the arguments listed below:

Constant	Description	For Parameters
DBMS_AQADM.TRANSACTIONAL(1)	This constant is de-	message_grouping
	fined, but will return	
	an error if used.	
DBMS_AQADM.NONE(0)	Use to specify mes-	message_grouping
	sage grouping for a	
	queue table.	
DBMS_AQADM.NORMAL_QUEUE(0)	Use with	queue_type
	create_queue	
	to specify	
	queue_type.	
DBMS_AQADM.EXCEPTION_QUEUE (1)	Use with	queue_type
	create_queue	
	to specify	
	queue_type.	
DBMS_AQADM.INFINITE(-1)	Use with	retention_time
	create_queue	
	to specify	
	retention_time.	
DBMS_AQADM.PERSISTENT (0)	The message should	enqueue_options_t.
	be stored in a table.	delivery_mode
DBMS_AQADM.BUFFERED (1)	This constant is de-	enqueue_options_t.
	fined, but will return	delivery_mode
	an error if used.	
DBMS_AQADM.PERSISTENT_OR_BUFFERED	This constant is de-	enqueue_options_t.
(2)	fined, but will return	delivery_mode
	an error if used.	

3.3.1 ALTER QUEUE

Use the ALTER_QUEUE procedure to modify an existing queue. The signature is:

```
ALTER_QUEUE(

<max_retries> IN NUMBER DEFAULT NULL,

<retry_delay> IN NUMBER DEFAULT 0

<retention_time> IN NUMBER DEFAULT 0,

<auto_commit> IN BOOLEAN DEFAULT TRUE)

<comment> IN VARCHAR2 DEFAULT NULL,
```

Parameters

```
<queue_name>
```

The name of the new queue.

```
<max_retries>
```

<max_retries> specifies the maximum number of attempts to remove a message with a dequeue
statement. The value of <max_retries> is incremented with each ROLLBACK statement. When the
number of failed attempts reaches the value specified by <max_retries>, the message is moved to the
exception queue. Specify 0 to indicate that no retries are allowed.

```
<retry_delay>
```

<retry_delay> specifies the number of seconds until a message is scheduled for re-processing after a
ROLLBACK. Specify 0 to indicate that the message should be retried immediately (the default).

```
<retention_time>
```

<retention_time> specifies the length of time (in seconds) that a message will be stored after being
dequeued. You can also specify 0 (the default) to indicate the message should not be retained after
dequeueing, or INFINITE to retain the message forever.

```
<auto commit>
```

This parameter is accepted for compatibility and ignored.

```
<comment>
```

<comment> specifies a comment associated with the queue.

Example

The following command alters a queue named work_order, setting the retry_delay parameter to 5 seconds:

```
EXEC DBMS_AQADM.ALTER_QUEUE(queue_name => 'work_order', retry_delay
=> 5);
```

3.3.2 ALTER_QUEUE_TABLE

```
Use the ALTER_QUEUE_TABLE procedure to modify an existing queue table.
```

The signature is:

Parameters

```
<queue_table>
```

The (optionally schema-qualified) name of the queue table.

```
<comment>
```

Use the <comment> parameter to provide a comment about the queue table.

```
primary_instance>
```

primary_instance> is accepted for compatibility and stored, but is ignored.

```
<secondary_instance>
```

<secondary_instance> is accepted for compatibility, but is ignored.

Example

The following command modifies a queue table named work_order_table:

```
EXEC DBMS_AQADM.ALTER_QUEUE_TABLE
      (queue_table => 'work_order_table', comment => 'This queue table
contains work orders for the shipping department.');
```

The queue table is named work order table; the command adds a comment to the definition of the queue table.

3.3.3 CREATE QUEUE

```
Use the CREATE_QUEUE procedure to create a queue in an existing queue table. The signature is:
```

```
CREATE_QUEUE(

<queue_name> IN VARCHAR2

<queue_table> IN VARCHAR2,

<queue_type> IN BINARY_INTEGER DEFAULT NORMAL_QUEUE,

<max_retries> IN NUMBER DEFAULT 5,

<retry_delay> IN NUMBER DEFAULT 0

<retention_time> IN NUMBER DEFAULT 0,

<dependency_tracking> IN BOOLEAN DEFAULT FALSE,

<comment> IN VARCHAR2 DEFAULT NULL,

<auto_commit> IN BOOLEAN DEFAULT TRUE)
```

Parameters

```
<queue_name>
```

The name of the new queue.

```
<queue_table>
```

The name of the table in which the new queue will reside.

```
<queue_type>
```

The type of the new queue. The valid values for <queue_type> are:

```
DBMS_AQADM.NORMAL_QUEUE - This value specifies a normal queue (the default).
```

DBMS_AQADM.EXCEPTION_QUEUE – This value specifies that the new queue is an exception queue. An exception queue will support only dequeue operations.

```
<max_retries>
```

<max_retries> specifies the maximum number of attempts to remove a message with a dequeue
statement. The value of <max_retries> is incremented with each ROLLBACK statement. When the
number of failed attempts reaches the value specified by <max_retries>, the message is moved to the
exception queue. The default value for a system table is 0; the default value for a user created table is 5.

```
<retry_delay>
```

<retry_delay> specifies the number of seconds until a message is scheduled for re-processing after a
ROLLBACK. Specify 0 to indicate that the message should be retried immediately (the default).

```
<retention_time>
```

<retention_time> specifies the length of time (in seconds) that a message will be stored after being
dequeued. You can also specify 0 (the default) to indicate the message should not be retained after
dequeueing, or INFINITE to retain the message forever.

```
<dependency_tracking>
```

This parameter is accepted for compatibility and ignored.

```
<comment>
```

<comment> specifies a comment associated with the queue.

```
<auto_commit>
```

This parameter is accepted for compatibility and ignored.

Example

The following anonymous block creates a queue named work_order in the work_order_table table:

```
BEGIN
DBMS_AQADM.CREATE_QUEUE ( queue_name => 'work_order', queue_table
=> 'work_order_table', comment => 'This queue contains pending work
orders.');
END;
```

3.3.4 CREATE QUEUE TABLE

```
Use the CREATE_QUEUE_TABLE procedure to create a queue table. The signature is:
```

Parameters

```
<queue_table>
```

The (optionally schema-qualified) name of the queue table.

```
<queue_payload_type>
```

The user-defined type of the data that will be stored in the queue table. Please note that to specify a RAW data type, you must create a user-defined type that identifies a RAW type.

```
<storage clause>
```

Use the <storage_clause> parameter to specify attributes for the queue table. Please note that only the TABLESPACE option is enforced; all others are accepted for compatibility and ignored. Use the TABLESPACE clause to specify the name of a tablespace in which the table will be created.

```
<storage_clause> may be one or more of the following:
```

```
TABLESPACE <tablespace_name>, PCTFREE integer, PCTUSED integer,
INITRANS integer, MAXTRANS integer or STORAGE <storage_option>.

<storage_option> may be one or more of the following:

MINEXTENTS integer, MAXEXTENTS integer, PCTINCREASE integer,
INITIAL <size_clause>, NEXT, FREELISTS integer, OPTIMAL

<size_clause>, BUFFER_POOL {KEEP|RECYCLE|DEFAULT}.

<sort list>
```

<sort_list> controls the dequeueing order of the queue; specify the names of the column(s) that
will be used to sort the queue (in ascending order). The currently accepted values are the following
combinations of enq_time and priority:

```
enq_time, priority
```

```
priority, enq_time
     priority
     enq_time
<multiple_consumers>
     <multiple consumers> queue tables is not supported.
<message_grouping>
     If specified, <message_grouping> must be NONE.
<comment>
     Use the <comment> parameter to provide a comment about the queue table.
<auto_commit>
     <auto_commit> is accepted for compatibility, but is ignored.
primary_instance>
     primary_instance> is accepted for compatibility and stored, but is ignored.
<secondary_instance>
     <secondary_instance> is accepted for compatibility, but is ignored.
<compatible>
     <compatible> is accepted for compatibility, but is ignored.
<secure>
     <secure> is accepted for compatibility, but is ignored.
```

Example

The following anonymous block first creates a type (work_order) with attributes that hold a name (a VARCHAR2), and a project description (a TEXT). The block then uses that type to create a queue table:

The queue table is named work_order_table, and contains a payload of a type work_order. A comment notes that this is the Work order message queue table.

3.3.5 DROP_QUEUE

```
Use the DROP_QUEUE procedure to delete a queue. The signature is:
```

Parameters

```
<queue_name>
```

The name of the queue that you wish to drop.

```
<auto_commit>
```

<auto_commit> is accepted for compatibility, but is ignored.

Example

The following anonymous block drops the queue named work_order:

```
BEGIN
DBMS_AQADM.DROP_QUEUE(queue_name => 'work_order');
END;
```

3.3.6 DROP_QUEUE_TABLE

Use the DROP_QUEUE_TABLE procedure to delete a queue table. The signature is:

Parameters

```
<queue table>
```

The (optionally schema-qualified) name of the queue table.

```
<force>
```

The <force> keyword determines the behavior of the DROP_QUEUE_TABLE command when dropping a table that contain entries:

If the target table contains entries and force is FALSE, the command will fail, and the server will issue an error.

If the target table contains entries and force is TRUE, the command will drop the table and any dependent objects.

```
<auto_commit>
```

<auto_commit> is accepted for compatibility, but is ignored.

Example

The following anonymous block drops a table named work_order_table:

```
BEGIN
   DBMS_AQADM.DROP_QUEUE_TABLE ('work_order_table', force => TRUE);
END;
```

3.3.7 PURGE QUEUE TABLE

Use the PURGE_QUEUE_TABLE procedure to delete messages from a queue table. The signature is:

Parameters

```
<queue_table>
```

<queue_table> specifies the name of the queue table from which you are deleting a message.

```
<purge_condition>
```

Use <purge_condition> to specify a condition (a SQL WHERE clause) that the server will evaluate
when deciding which messages to purge.

```
<purge_options>
```

```
<purge_options> is an object of the type aq$_purge_options_t. An
aq$_purge_options_t object contains:
```

Attribute	Туре	Description
Block	Boolean	Specify TRUE if an exclusive lock should be held on all queues
		within the table; the default is FALSE.
delivery_mode	INTEGER	<pre><delivery_mode> specifies the type of message that will be</delivery_mode></pre>
		purged. The only accepted value is DBMS_AQ.PERSISTENT.

Example

The following anonymous block removes any messages from the work_order_table with a value in the completed column of YES:

```
DECLARE
   purge_options dbms_aqadm.aq$_purge_options_t;

BEGIN
   dbms_aqadm.purge_queue_table('work_order_table', 'completed = YES',
   purge_options);
   END;
```

3.3.8 START QUEUE

Use the START_QUEUE procedure to make a queue available for enqueuing and dequeueing.

The signature is:

Parameters

Specify TRUE to enable enqueueing (the default), or FALSE to leave the current setting unchanged.

<dequeue>

Specify TRUE to enable dequeueing (the default), or FALSE to leave the current setting unchanged.

Example

The following anonymous block makes a queue named work_order available for enqueueing:

```
BEGIN
DBMS_AQADM.START_QUEUE
(queue_name => 'work_order);
END;
```

3.3.9 STOP QUEUE

Use the STOP_QUEUE procedure to disable enqueuing or dequeueing on a specified queue.

The signature is:

Parameters

Specify TRUE to disable enqueueing (the default), or FALSE to leave the current setting unchanged.

<dequeue>

Specify TRUE to disable dequeueing (the default), or FALSE to leave the current setting unchanged.

<wait>

Specify TRUE to instruct the server to wait for any uncompleted transactions to complete before applying the specified changes; while waiting to stop the queue, no transactions are allowed to enqueue or dequeue from the specified queue. Specify FALSE to stop the queue immediately.

Example

The following anonymous block disables enqueueing and dequeueing from the queue named work_order:

```
BEGIN
DBMS_AQADM.STOP_QUEUE(queue_name =>'work_order', enqueue=>TRUE,
dequeue=>TRUE, wait=>TRUE);
END;
```

Enqueueing and dequeueing will stop after any outstanding transactions complete.

3.4 DBMS_CRYPTO

The DBMS_CRYPTO package provides functions and procedures that allow you to encrypt or decrypt RAW, BLOB or CLOB data. You can also use DBMS_CRYPTO functions to generate cryptographically strong random values.

The following table lists the DBMS_CRYPTO Functions and Procedures.

Function/Procedure	Return Type	Description
DECRYPT(src, typ, key, iv)	RAW	Decrypts RAW data.
DECRYPT(dst INOUT, src, typ,	N/A	Decrypts BLOB data.
key, iv)		
DECRYPT(dst INOUT, src, typ,	N/A	Decrypts CLOB data.
key, iv)		
ENCRYPT(src, typ, key, iv)	RAW	Encrypts RAW data.
ENCRYPT (dst INOUT, src, typ,	N/A	Encrypts BLOB data.
key, iv)		
ENCRYPT (dst INOUT, src, typ,	N/A	Encrypts CLOB data.
key, iv)		
HASH(src, typ)	RAW	Applies a hash algorithm to RAW data.
HASH(src)	RAW	Applies a hash algorithm to CLOB data.
MAC(src, typ, key)	RAW	Returns the hashed MAC value of the given RAW data
		using the specified hash algorithm and key.
MAC(src, typ, key)	RAW	Returns the hashed MAC value of the given CLOB data
		using the specified hash algorithm and key.
RANDOMBYTES (number_bytes)	RAW	Returns a specified number of cryptographically strong
		random bytes.
RANDOMINTEGER()	INTEGER	Returns a random INTEGER.
RANDOMNUMBER()	NUMBER	Returns a random NUMBER.

DBMS_CRYPTO functions and procedures support the following error messages:

```
ORA-28239 - DBMS_CRYPTO.KeyNull
ORA-28829 - DBMS_CRYPTO.CipherSuiteNull
ORA-28827 - DBMS_CRYPTO.CipherSuiteInvalid
```

Unlike Oracle, Advanced Server will not return error ORA-28233 if you re-encrypt previously encrypted information.

Please note that RAW and BLOB are synonyms for the PostgreSQL BYTEA data type, and CLOB is a synonym for TEXT.

3.4.1 DECRYPT

The DECRYPT function or procedure decrypts data using a user-specified cipher algorithm, key and optional initialization vector. The signature of the DECRYPT function is:

```
DECRYPT
    (<src> IN RAW, <typ> IN INTEGER, <key> IN RAW, <iv> IN RAW
    DEFAULT NULL) RETURN RAW
```

The signature of the DECRYPT procedure is:

```
DECRYPT
        (<dst> INOUT BLOB, <src> IN BLOB, <typ> IN INTEGER, <key> IN RAW,
        <iv> IN RAW DEFAULT NULL)
or
    DECRYPT
        (<dst> INOUT CLOB, <src> IN CLOB, <typ> IN INTEGER, <key> IN RAW,
        <iv> IN RAW DEFAULT NULL)
```

When invoked as a procedure, DECRYPT returns BLOB or CLOB data to a user-specified BLOB.

Parameters

<dst>

<dst> specifies the name of a BLOB to which the output of the DECRYPT procedure will be written. The DECRYPT procedure will overwrite any existing data currently in <dst>.

<src>

<src> specifies the source data that will be decrypted. If you are invoking DECRYPT as a function, specify RAW data; if invoking DECRYPT as a procedure, specify BLOB or CLOB data.

<typ>

<typ> specifies the block cipher type and any modifiers. This should match the type specified when the <src> was encrypted. Advanced Server supports the following block cipher algorithms, modifiers and cipher suites:

Block Cipher Algorithms							
ENCRYPT_DES	CONSTANT INTEGER := 1;						
ENCRYPT_3DES	CONSTANT INTEGER := 3;						
ENCRYPT_AES	CONSTANT INTEGER := 4;						
ENCRYPT_AES128	CONSTANT INTEGER := 6;						
Block Cipher Modifiers							
CHAIN_CBC	CONSTANT INTEGER := 256;						
CHAIN_ECB	CONSTANT INTEGER := 768;						
Block Cipher Paddin	Block Cipher Padding Modifiers						
PAD_PKCS5	CONSTANT INTEGER := 4096;						
PAD_NONE	CONSTANT INTEGER := 8192;						
Block Cipher Suites							
DES_CBC_PKCS5	CONSTANT INTEGER := ENCRYPT_DES + CHAIN_CBC + PAD_PKCS5;						
DES3_CBC_PKCS5	CONSTANT INTEGER := ENCRYPT_3DES + CHAIN_CBC + PAD_PKCS5	;					
AES_CBC_PKCS5	CONSTANT INTEGER := ENCRYPT_AES + CHAIN_CBC + PAD_PKCS5;						

```
<key>
```

<key> specifies the user-defined decryption key. This should match the key specified when the <src> was encrypted.

<iv>

<iv>(optional) specifies an initialization vector. If an initialization vector was specified when the <src> was encrypted, you must specify an initialization vector when decrypting the <src>. The default is NULL.

Examples

The following example uses the <code>DBMS_CRYPTO.DECRYPT</code> function to decrypt an encrypted password retrieved from the passwords table:

Note that when calling <code>DECRYPT</code>, you must pass the same cipher type, key value and initialization vector that was used when <code>ENCRYPTING</code> the target.

3.4.2 ENCRYPT

The ENCRYPT function or procedure uses a user-specified algorithm, key, and optional initialization vector to encrypt RAW, BLOB or CLOB data. The signature of the ENCRYPT function is:

```
ENCRYPT
    (<src> IN RAW, <typ> IN INTEGER, <key> IN RAW,
    <iv> IN RAW DEFAULT NULL) RETURN RAW
```

The signature of the ENCRYPT procedure is:

```
ENCRYPT
        (<dst> INOUT BLOB, <src> IN BLOB, <typ> IN INTEGER, <key> IN RAW,
        <iv> IN RAW DEFAULT NULL)
or
    ENCRYPT
        (<dst> INOUT BLOB, <src> IN CLOB, <typ> IN INTEGER, <key> IN RAW,
        <iv> IN RAW DEFAULT NULL)
```

When invoked as a procedure, ENCRYPT returns BLOB or CLOB data to a user-specified BLOB.

Parameters

<dst>

<dst> specifies the name of a BLOB to which the output of the ENCRYPT procedure will be written. The ENCRYPT procedure will overwrite any existing data currently in <dst>.

<src>

<src> specifies the source data that will be encrypted. If you are invoking ENCRYPT as a function, specify RAW data; if invoking ENCRYPT as a procedure, specify BLOB or CLOB data.

<typ>

<typ> specifies the block cipher type that will be used by ENCRYPT, and any modifiers. Advanced Server supports the block cipher algorithms, modifiers and cipher suites listed below:

Block Cipher Algorithms						
ENCRYPT_DES	CONSTANT	INTEGER	;=	1;		
ENCRYPT_3DES	CONSTANT	INTEGER	:=	3;		
ENCRYPT_AES	CONSTANT	INTEGER	:=	4;		
ENCRYPT_AES128	CONSTANT	INTEGER	:=	6;		
Block Cipher Modifiers						
CHAIN_CBC	CONSTANT	INTEGER	:=	256;		
CHAIN_ECB	CONSTANT	INTEGER	:=	768;		
Block Cipher Padding Modifiers						
"PAD_PKCS5"	CONSTANT	INTEGER	:=	4096;		
PAD_NONE	CONSTANT	INTEGER	:=	8192;		
Block Cipher Suites						
DES_CBC_PKCS5	CONSTANT	INTEGER	:=	ENCRYPT_DES + CHAIN_CBC + PAD_PKCS5;		
DES3_CBC_PKCS5	CONSTANT	INTEGER	:=	<pre>ENCRYPT_3DES + CHAIN_CBC + PAD_PKCS5;</pre>		
AES_CBC_PKCS5	CONSTANT	INTEGER	:=	ENCRYPT_AES + CHAIN_CBC + PAD_PKCS5;		

<key>

<key> specifies the encryption key.

<iv>

<iv> (optional) specifies an initialization vector. By default, <iv> is NULL.

Examples

The following example uses the DBMS_CRYPTO.DES_CBC_PKCS5 Block Cipher Suite (a pre-defined set of algorithms and modifiers) to encrypt a value retrieved from the passwords table:

ENCRYPT uses a key value of my secret key and an initialization vector of my initialization vector when encrypting the password; specify the same key and initialization vector when decrypting the password.

3.4.3 HASH

The HASH function uses a user-specified algorithm to return the hash value of a RAW or CLOB value. The HASH function is available in three forms:

```
HASH

(<src> IN RAW, <typ> IN INTEGER) RETURN RAW

HASH

(<src> IN CLOB, <typ> IN INTEGER) RETURN RAW
```

Parameters

<src>

<src> specifies the value for which the hash value will be generated. You can specify a RAW, a BLOB,
or a CLOB value.

<typ>

<typ> specifies the HASH function type. Advanced Server supports the HASH function types listed below:

HASH Functions							
HASH_MD4	CONSTANT	INTEGER	:= 1;				
HASH_MD5	CONSTANT	INTEGER	:= 2;				
HASH_SH1	CONSTANT	INTEGER	:= 3;				

Examples

The following example uses DBMS_CRYPTO. HASH to find the md5 hash value of the string, cleartext source:

```
DECLARE
  typ INTEGER := DBMS_CRYPTO.HASH_MD5;
  hash_value RAW(100);
BEGIN
  hash_value := DBMS_CRYPTO.HASH('cleartext source', typ);
END;
```

3.4.4 MAC

The MAC function uses a user-specified MAC function to return the hashed MAC value of a RAW or CLOB value. The MAC function is available in three forms:

```
MAC

(<src> IN RAW, <typ> IN INTEGER, <key> IN RAW) RETURN RAW

MAC

(<src> IN CLOB, <typ> IN INTEGER, <key> IN RAW) RETURN RAW
```

Parameters

<src>

<src> specifies the value for which the MAC value will be generated. Specify a RAW, BLOB, or CLOB
value.

<typ>

<typ> specifies the MAC function used. Advanced Server supports the MAC functions listed below.

MAC Functions							
HMAC_MD5	CONSTANT	INTEGER	:= 1;				
HMAC_SH1	CONSTANT	INTEGER	:= 2;				

<key>

<key> specifies the key that will be used to calculate the hashed MAC value.

Examples

The following example finds the hashed MAC value of the string cleartext source:

```
DECLARE
  typ INTEGER := DBMS_CRYPTO.HMAC_MD5;
  key RAW(100) := 'my secret key';
  mac_value RAW(100);
BEGIN

mac_value := DBMS_CRYPTO.MAC('cleartext source', typ, key);
END;
```

DBMS_CRYPTO.MAC uses a key value of my secret key when calculating the MAC value of cleartext source.

3.4.5 RANDOMBYTES

The RANDOMBYTES function returns a RAW value of the specified length, containing cryptographically random bytes. The signature is:

```
RANDOMBYTES

(<number_bytes> IN INTEGER) RETURNS RAW
```

Parameter

```
<number_bytes>
<number_bytes> specifies the number of random bytes to be returned
```

Examples

The following example uses RANDOMBYTES to return a value that is 1024 bytes long:

```
DECLARE
  result RAW(1024);
BEGIN
  result := DBMS_CRYPTO.RANDOMBYTES(1024);
END;
```

3.4.6 RANDOMINTEGER

The RANDOMINTEGER() function returns a random INTEGER between 0 and 268, 435, 455. The signature is:

RANDOMINTEGER() RETURNS INTEGER

Examples

The following example uses the RANDOMINTEGER function to return a cryptographically strong random INTEGER value:

```
DECLARE
  result INTEGER;
BEGIN
  result := DBMS_CRYPTO.RANDOMINTEGER();
  DBMS_OUTPUT.PUT_LINE(result);
END;
```

3.4.7 RANDOMNUMBER

The RANDOMNUMBER() function returns a random NUMBER between 0 and 268, 435, 455. The signature is: RANDOMNUMBER() RETURNS NUMBER

Examples

The following example uses the RANDOMNUMBER function to return a cryptographically strong random number:

```
DECLARE
   result NUMBER;
BEGIN
   result := DBMS_CRYPTO.RANDOMNUMBER();
   DBMS_OUTPUT.PUT_LINE(result);
END;
```

3.5 DBMS_JOB

The DBMS_JOB package provides for the creation, scheduling, and managing of jobs. A job runs a stored procedure which has been previously stored in the database. The SUBMIT procedure is used to create and store a job definition. A job identifier is assigned to a job along with its associated stored procedure and the attributes describing when and how often the job is to be run.

This package relies on the pgAgent scheduler. By default, the Advanced Server installer installs pgAgent, but you must start the pgAgent service manually prior to using DBMS_JOB. If you attempt to use this package to schedule a job after un-installing pgAgent, DBMS_JOB will throw an error. DBMS_JOB verifies that pgAgent is installed, but does not verify that the service is running.

The following table lists the supported DBMS_JOB procedures:

Function/Procedure	Return	Description
	Type	
BROKEN(<job>, <broken> [,</broken></job>	n/a	Specify that a given job is either broken or not broken.
<pre><next_date>])</next_date></pre>		
CHANGE(<job, <what="">,</job,>	n/a	Change the job's parameters.
<pre><next_date>, <interval,< pre=""></interval,<></next_date></pre>		
instance, force>)		
<pre>INTERVAL(<job>, <interval>)</interval></job></pre>	n/a	Set the execution frequency by means of a date function
		that is recalculated each time the job is run. This value
		becomes the next date/time for execution.
<pre>NEXT_DATE(<job>, <next_date>)</next_date></job></pre>	n/a	Set the next date/time the job is to be run.
REMOVE(<job>)</job>	n/a	Delete the job definition from the database.
RUN(<job>)</job>	n/a	Forces execution of a job even if it is marked broken.
SUBMIT(<job> OUT, <what> [,</what></job>	n/a	Creates a job and stores its definition in the database.
<pre><next_date> [, <interval> [,</interval></next_date></pre>		
<no_parse>]]])</no_parse>		
WHAT(<job>, <what>)</what></job>	n/a	Change the stored procedure run by a job.

Advanced Server's implementation of DBMS_JOB is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Before using DBMS_JOB, a database superuser must create the pgAgent extension. Use the psql client to connect to a database and invoke the command:

```
CREATE EXTENSION pgagent;
```

When and how often a job is run is dependent upon two interacting parameters — <next_date> and <interval>. The <next_date> parameter is a date/time value that specifies the next date/time when the job is to be executed. The <interval> parameter is a string that contains a date function that evaluates to a date/time value.

Just prior to any execution of the job, the expression in the <interval> parameter is evaluated. The resulting value replaces the <next_date> value stored with the job. The job is then executed. In this manner, the expression in <interval> is repeatedly re-evaluated prior to each job execution, supplying the <next_date> date/time for the next execution.

The following examples use the following stored procedure, job_proc, which simply inserts a timestamp into table, jobrun, containing a single VARCHAR2 column.

```
CREATE TABLE jobrun (
runtime VARCHAR2(40)
);

CREATE OR REPLACE PROCEDURE job_proc
IS
BEGIN
INSERT INTO jobrun VALUES ('job_proc run at ' || TO_CHAR(SYSDATE,
'yyyy-mm-dd hh24:mi:ss'));
END;
```

3.5.1 BROKEN

The BROKEN procedure sets the state of a job to either broken or not broken. A broken job cannot be executed except by using the RUN procedure.

```
BROKEN(<job> BINARY_INTEGER, <broken> BOOLEAN [, <next_date> DATE ])
```

Parameters

<job>

Identifier of the job to be set as broken or not broken.

broken>

If set to TRUE the job's state is set to broken. If set to FALSE the job's state is set to not broken. Broken jobs cannot be run except by using the RUN procedure.

```
<next_date>
```

Date/time when the job is to be run. The default is SYSDATE.

Examples

Set the state of a job with job identifier 104 to broken:

```
BEGIN
DBMS_JOB.BROKEN(104,true);
END;
```

Change the state back to not broken:

```
BEGIN
    DBMS_JOB.BROKEN(104, false);
END;
```

3.5.2 CHANGE

The CHANGE procedure modifies certain job attributes including the stored procedure to be run, the next date/time the job is to be run, and how often it is to be run.

```
CHANGE(<job> BINARY_INTEGER <what> VARCHAR2, <next_date> DATE, <interval> VARCHAR2, <instance> BINARY_INTEGER, <force> BOOLEAN)
```

Parameters

<job>

Identifier of the job to modify.

<what>

Stored procedure name. Set this parameter to null if the existing value is to remain unchanged.

```
<next date>
```

Date/time when the job is to be run next. Set this parameter to null if the existing value is to remain unchanged.

```
<interval>
```

Date function that when evaluated, provides the next date/time the job is to run. Set this parameter to null if the existing value is to remain unchanged.

<instance>

This argument is ignored, but is included for compatibility.

<force>

This argument is ignored, but is included for compatibility.

Examples

Change the job to run next on December 13, 2007. Leave other parameters unchanged.

```
BEGIN

DBMS_JOB.CHANGE(104,NULL,TO_DATE('13-DEC-07','DD-MON-YY'),NULL, NULL,

NULL);
END;
```

3.5.3 INTERVAL

The INTERVAL procedure sets the frequency of how often a job is to be run.

```
INTERVAL(<job> BINARY_INTEGER, <interval> VARCHAR2)
```

Parameters

<job>

Identifier of the job to modify.

<interval>

Date function that when evaluated, provides the next date/time the job is to be run. If <interval> is NULL and the job is complete, the job is removed from the queue.

Examples

Change the job to run once a week:

```
BEGIN

DBMS_JOB.INTERVAL(104,'SYSDATE + 7');
END;
```

3.5.4 NEXT_DATE

The NEXT_DATE procedure sets the date/time of when the job is to be run next.

```
NEXT_DATE(<job> BINARY_INTEGER, <next_date> DATE)
```

Parameters

```
<job>
```

Identifier of the job whose next run date is to be set.

```
<next_date>
```

Date/time when the job is to be run next.

Examples

Change the job to run next on December 14, 2007:

```
BEGIN

DBMS_JOB.NEXT_DATE(104, TO_DATE('14-DEC-07','DD-MON-YY'));

END;
```

3.5.5 REMOVE

The REMOVE procedure deletes the specified job from the database. The job must be resubmitted using the SUBMIT procedure in order to have it executed again. Note that the stored procedure that was associated with the job is not deleted.

```
REMOVE(<job> BINARY_INTEGER)
```

Parameter

<job>

Identifier of the job that is to be removed from the database.

Examples

Remove a job from the database:

```
BEGIN

DBMS_JOB.REMOVE(104);

END;
```

3.5.6 RUN

The RUN procedure forces the job to be run, even if its state is broken.

```
RUN(<job> BINARY_INTEGER)
```

Parameter

<job>

Identifier of the job to be run.

Examples

Force a job to be run.

```
BEGIN

DBMS_JOB.RUN(104);

END;
```

3.5.7 SUBMIT

The SUBMIT procedure creates a job definition and stores it in the database. A job consists of a job identifier, the stored procedure to be executed, when the job is to be first run, and a date function that calculates the next date/time the job is to be run.

```
SUBMIT(<job> OUT BINARY_INTEGER, <what> VARCHAR2
[, <next_date> DATE [, <interval> VARCHAR2 [, <no_parse> BOOLEAN ]]])
```

Parameters

<job>

Identifier assigned to the job.

<what>

Name of the stored procedure to be executed by the job.

<next date>

Date/time when the job is to be run next. The default is SYSDATE.

<interval>

Date function that when evaluated, provides the next date/time the job is to run. If <interval> is set to null, then the job is run only once. Null is the default.

<no_parse>

If set to TRUE, do not syntax-check the stored procedure upon job creation – check only when the job first executes. If set to FALSE, check the procedure upon job creation. The default is FALSE.

Note: The <no_parse> option is not supported in this implementation of SUBMIT(). It is included for compatibility only.

Examples

The following example creates a job using stored procedure, job_proc. The job will execute immediately and run once a day thereafter as set by the <interval> parameter, SYSDATE + 1.

The job immediately executes procedure, job_proc, populating table, jobrun, with a row:

```
SELECT * FROM jobrun;

runtime

------
job_proc run at 2007-12-11 11:43:25
(1 row)
```

3.5.8 WHAT

The WHAT procedure changes the stored procedure that the job will execute.

```
WHAT(<job> BINARY_INTEGER, <what> VARCHAR2)
```

Parameters

<job>

Identifier of the job for which the stored procedure is to be changed.

<what>

Name of the stored procedure to be executed.

Examples

Change the job to run the list_emp procedure:

```
BEGIN

DBMS_JOB.WHAT(104,'list_emp;');

END;
```

3.6 DBMS_LOB

The \DBMS_LOB package provides the capability to operate on large objects. The following table lists the supported functions and procedures:

Function/Procedure	Return Type	Description
APPEND(<dest_lob> IN OUT,</dest_lob>	n/a	Appends one large object to another.
<pre><src_lob>)</src_lob></pre>		
COMPARE(<lob_1>, <lob_2> [,</lob_2></lob_1>	INTEGER	Compares two large objects.
<pre><amount> [, <offset_1> [,</offset_1></amount></pre>		
<offset_2>]]])</offset_2>		
CONVERTOBLOB(<dest_lob> IN</dest_lob>	n/a	Converts character data to binary.
OUT, <src_clob>, <amount>,</amount></src_clob>		
<dest_offset> IN OUT,</dest_offset>		
<pre><src_offset> IN OUT,</src_offset></pre>		
<pre><blob_csid>, <lang_context></lang_context></blob_csid></pre>		
IN OUT, <warning> OUT)</warning>		
CONVERTTOCLOB(<dest_lob> IN</dest_lob>	n/a	Converts binary data to character.
OUT, <src_blob>, <amount>,</amount></src_blob>		
<pre><dest_offset> IN OUT,</dest_offset></pre>		
<pre><src_offset> IN OUT,</src_offset></pre>		
<pre><blob_csid>, <lang_context></lang_context></blob_csid></pre>		
IN OUT, <warning> OUT)</warning>		
COPY(<dest_lob> IN OUT,</dest_lob>	n/a	Copies one large object to another.
<pre><src_lob>, <amount> [,</amount></src_lob></pre>		
<pre><dest_offset> [, <src_offset></src_offset></dest_offset></pre>		
]])		
ERASE(lob_loc IN OUT,	n/a	Erase a large object.
<pre><amount> IN OUT [, <offset></offset></amount></pre>		
])		
<pre>GET_STORAGE_LIMIT(<lob_loc>)</lob_loc></pre>	INTEGER	Get the storage limit for large objects.
GETLENGTH(<lob_loc>)</lob_loc>	INTEGER	Get the length of the large object.
<pre>INSTR(<lob_loc>, <pattern> [,</pattern></lob_loc></pre>	INTEGER	Get the position of the nth occurrence of
<offset> [, <nth>]])</nth></offset>		a pattern in the large object starting at
		<offset></offset>
READ(<lob_loc>, <amount> IN</amount></lob_loc>	n/a	Read a large object.
OUT, <offset>, <buffer> OUT)</buffer></offset>		
SUBSTR(<lob_loc> [, <amount></amount></lob_loc>	RAW, VARCHAR2	Get part of a large object.
[, <offset>]])</offset>		
TRIM(<lob_loc> IN OUT,</lob_loc>	n/a	Trim a large object to the specified length.
<newlen>)</newlen>		
WRITE(<lob_loc> IN OUT,</lob_loc>	n/a	Write data to a large object.
<pre><amount>, <offset>, <buffer>)</buffer></offset></amount></pre>		
WRITEAPPEND(<lob_loc> IN OUT,</lob_loc>	n/a	Write data from the buffer to the end of a
<pre><amount>, <buffer>)</buffer></amount></pre>		large object.

Advanced Server's implementation of $DBMS_LOB$ is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The following table lists the public variables available in the package.

Public Variables	Data Type	Value
compress off	INTEGER	0
compress_on	INTEGER	1
deduplicate_off	INTEGER	0
deduplicate_on	INTEGER	4
default_csid	INTEGER	0
default_lang_ctx	INTEGER	0
encrypt_off	INTEGER	0
encrypt_on	INTEGER	1
file_readonly	INTEGER	0
lobmaxsize	INTEGER	1073741823
lob_readonly	INTEGER	0
lob_readwrite	INTEGER	1
no_warning	INTEGER	0
opt_compress	INTEGER	1
opt_deduplicate	INTEGER	4
opt_encrypt	INTEGER	2
warn_inconvertible_char	INTEGER	1

In the following sections, lengths and offsets are measured in bytes if the large objects are BLOBs. Lengths and offsets are measured in characters if the large objects are CLOBs.

3.6.1 APPEND

The APPEND procedure provides the capability to append one large object to another. Both large objects must be of the same type.

```
APPEND(<dest_lob> IN OUT { BLOB | CLOB }, <src_lob> { BLOB | CLOB })
```

Parameters

<dest_lob>

Large object locator for the destination object. Must be the same data type as <src_lob>.

<src_lob>

Large object locator for the source object. Must be the same data type as <dest_lob>.

3.6.2 COMPARE

The COMPARE procedure performs an exact byte-by-byte comparison of two large objects for a given length at given offsets. The large objects being compared must be the same data type.

Parameters

<lob 1>

Large object locator of the first large object to be compared. Must be the same data type as <1ob_2>.

<lob_2>

Large object locator of the second large object to be compared. Must be the same data type as <1ob_1>.

<amount>

If the data type of the large objects is BLOB, then the comparison is made for <amount> bytes. If the data type of the large objects is CLOB, then the comparison is made for <amount> characters. The default is the maximum size of a large object.

```
<offset_1>
```

Position within the first large object to begin the comparison. The first byte/character is offset 1. The default is 1.

```
<offset_2>
```

Position within the second large object to begin the comparison. The first byte/character is offset 1. The default is 1.

```
<status>
```

Zero if both large objects are exactly the same for the specified length for the specified offsets. Non-zero, if the objects are not the same. <NULL> if <amount>, <offset_1>, or <offset_2> are less than zero.

3.6.3 CONVERTTOBLOB

The CONVERTIOBLOB procedure provides the capability to convert character data to binary.

Parameters

```
<dest lob>
```

BLOB large object locator to which the character data is to be converted.

<src clob>

CLOB large object locator of the character data to be converted.

<amount>

Number of characters of clob> to be converted.

```
<dest_offset> IN
```

Position in bytes in the destination BLOB where writing of the source CLOB should begin. The first byte is offset 1.

```
<dest_offset> OUT
```

Position in bytes in the destination BLOB after the write operation completes. The first byte is offset 1.

```
<src_offset> IN
```

Position in characters in the source CLOB where conversion to the destination BLOB should begin. The first character is offset 1.

```
<src_offset> OUT
```

Position in characters in the source CLOB after the conversion operation completes. The first character is offset 1.

```
<blob_csid>
```

Character set ID of the converted, destination BLOB.

```
<lang_context> IN
```

Language context for the conversion. The default value of 0 is typically used for this setting.

```
<lang_context> OUT
```

Language context after the conversion completes.

```
<warning>
```

0 if the conversion was successful, 1 if an inconvertible character was encountered.

3.6.4 CONVERTTOCLOB

The CONVERTICALOB procedure provides the capability to convert binary data to character.

Parameters

```
<dest lob>
```

CLOB large object locator to which the binary data is to be converted.

```
<src blob>
```

BLOB large object locator of the binary data to be converted.

<amount>

Number of bytes of src_blob> to be converted.

```
<dest_offset> IN
```

Position in characters in the destination CLOB where writing of the source BLOB should begin. The first character is offset 1.

```
<dest_offset> OUT
```

Position in characters in the destination CLOB after the write operation completes. The first character is offset 1.

```
<src_offset> IN
```

Position in bytes in the source BLOB where conversion to the destination CLOB should begin. The first byte is offset 1.

```
<src offset> OUT
```

Position in bytes in the source BLOB after the conversion operation completes. The first byte is offset 1.

```
<blob_csid>
```

Character set ID of the converted, destination CLOB.

```
<lang_context> IN
```

Language context for the conversion. The default value of 0 is typically used for this setting.

```
<lang_context> OUT
```

Language context after the conversion completes.

```
<warning>
```

0 if the conversion was successful, 1 if an inconvertible character was encountered.

3.6.5 COPY

The COPY procedure provides the capability to copy one large object to another. The source and destination large objects must be the same data type.

Parameters

```
<dest lob>
```

Large object locator of the large object to which src_lob> is to be copied. Must be the same data type
as src_lob>.

```
<src lob>
```

Large object locator of the large object to be copied to <dest_lob>. Must be the same data type as <dest_lob>.

```
<amount>
```

Number of bytes/characters of src_lob> to be copied.

```
<dest_offset>
```

Position in the destination large object where writing of the source large object should begin. The first position is offset 1. The default is 1.

```
<src_offset>
```

Position in the source large object where copying to the destination large object should begin. The first position is offset 1. The default is 1.

3.6.6 **ERASE**

The ERASE procedure provides the capability to erase a portion of a large object. To erase a large object means to replace the specified portion with zero-byte fillers for BLOBs or with spaces for CLOBs. The actual size of the large object is not altered.

```
ERASE( <lob_loc> IN OUT { BLOB | CLOB }, <amount> IN OUT INTEGER
[, <offset> INTEGER ])
```

Parameters

<lob_loc>

Large object locator of the large object to be erased.

```
<amount> IN
```

Number of bytes/characters to be erased.

```
<amount> OUT
```

Number of bytes/characters actually erased. This value can be smaller than the input value if the end of the large object is reached before <amount> bytes/characters have been erased.

```
<offset>
```

Position in the large object where erasing is to begin. The first byte/character is position 1. The default is

3.6.7 GET_STORAGE_LIMIT

The GET_STORAGE_LIMIT function returns the limit on the largest allowable large object.

```
<size> INTEGER GET_STORAGE_LIMIT(<lob_loc> BLOB)
<size> INTEGER GET_STORAGE_LIMIT(<lob_loc< CLOB)</pre>
```

Parameters

<size>

Maximum allowable size of a large object in this database.

<lob_loc>

This parameter is ignored, but is included for compatibility.

3.6.8 GETLENGTH

The GETLENGTH function returns the length of a large object.

```
<amount> INTEGER GETLENGTH(<lob_loc> BLOB)
<amount> INTEGER GETLENGTH(<lob_loc> CLOB)
```

Parameters

<lob_loc>

Large object locator of the large object whose length is to be obtained.

<amount>

Length of the large object in bytes for BLOBs or characters for CLOBs.

3.6.9 INSTR

The INSTR function returns the location of the nth occurrence of a given pattern within a large object.

```
<position> INTEGER INSTR(<lob_loc> { BLOB | CLOB },
<pattern> { RAW | VARCHAR2 } [, <offset> INTEGER [, <nth> INTEGER]])
```

Parameters

<lob_loc>

Large object locator of the large object in which to search for pattern.

<pattern>

Pattern of bytes or characters to match against the large object, lob. <pattern> must be RAW if <lob_loc> is a BLOB. pattern must be VARCHAR2 if <lob_loc> is a CLOB.

<offset>

Position within <lob_loc> to start search for <pattern>. The first byte/character is position 1. The default is 1.

<nth>

Search for cpattern>, <nth> number of times starting at the position given by <offset>. The
default is 1.

<position>

Position within the large object where <pattern< appears the nth time specified by <nth< starting from the position given by <offset>.

3.6.10 READ

The READ procedure provides the capability to read a portion of a large object into a buffer.

Parameters

<lob_loc>

Large object locator of the large object to be read.

<amount> IN

Number of bytes/characters to read.

<amount> OUT

Number of bytes/characters actually read. If there is no more data to be read, then <amount> returns 0 and a DATA NOT FOUND exception is thrown.

<offset>

Position to begin reading. The first byte/character is position 1.

huffer>

Variable to receive the large object. If $<lob_loc>$ is a BLOB, then <buffer> must be RAW. If $<lob_loc>$ is a CLOB, then <buffer> must be VARCHAR2.

3.6.11 SUBSTR

The SUBSTR function provides the capability to return a portion of a large object.

```
<data> { RAW | VARCHAR2 } SUBSTR(<lob_loc> { BLOB | CLOB }
   [, <amount> INTEGER [, <offset> INTEGER ]])
```

Parameters

<lob_loc>

Large object locator of the large object to be read.

<amount>

Number of bytes/characters to be returned. Default is 32,767.

<offset>

Position within the large object to begin returning data. The first byte/character is position 1. The default is 1.

<data>

Returned portion of the large object to be read. If $<lob_loc>$ is a BLOB, the return data type is RAW. If $<lob_loc>$ is a CLOB, the return data type is VARCHAR2.

3.6.12 TRIM

The TRIM procedure provides the capability to truncate a large object to the specified length.

```
TRIM(<lob_loc> IN OUT { BLOB | CLOB }, <newlen> INTEGER)
```

Parameters

<lob_loc>

Large object locator of the large object to be trimmed.

<newlen>

Number of bytes/characters to which the large object is to be trimmed.

3.6.13 WRITE

The WRITE procedure provides the capability to write data into a large object. Any existing data in the large object at the specified offset for the given length is overwritten by data given in the buffer.

Parameters

<lob_loc>

Large object locator of the large object to be written.

<amount>

The number of bytes/characters in <buffer> to be written to the large object.

<offset>

The offset in bytes/characters from the beginning of the large object (origin is 1) for the write operation to begin.

<buffer>

Contains data to be written to the large object. If <lob_loc> is a BLOB, then <buffer> must be RAW. If <lob_loc> is a CLOB, then <buffer> must be VARCHAR2.

3.6.14 WRITEAPPEND

The WRITEAPPEND procedure provides the capability to add data to the end of a large object.

Parameters

<lob_loc>

Large object locator of the large object to which data is to be appended.

<amount>

Number of bytes/characters from <buffer> to be appended the large object.

<buffer>

Data to be appended to the large object. If <lob_loc> is a BLOB, then <buffer> must be RAW. If <lob_loc> is a CLOB, then <buffer> must be VARCHAR2.

3.7 DBMS_LOCK

Advanced Server provides support for the DBMS_LOCK.SLEEP procedure.

Function/Procedure	Return Type	Description
SLEEP (<seconds>)</seconds>	n/a	Suspends a session for the specified number of <seconds>.</seconds>

Advanced Server's implementation of DBMS_LOCK is a partial implementation when compared to Oracle's version. Only DBMS_LOCK.SLEEP is supported.

3.7.1 SLEEP

The SLEEP procedure suspends the current session for the specified number of seconds.

SLEEP (<seconds> NUMBER)

Parameters

<seconds>

<seconds> specifies the number of seconds for which you wish to suspend the session. <seconds>
can be a fractional value; for example, enter 1.75 to specify one and three-fourths of a second.

3.7. DBMS_LOCK 92

3.8 DBMS_MVIEW

Use procedures in the DBMS_MVIEW package to manage and refresh materialized views and their dependencies. Advanced Server provides support for the following DBMS_MVIEW procedures:

Procedure	Re- turn Type	Description
<pre>GET_MV_DEPENDENCIES(<list> VARCHAR2, <deplist> VARCHAR2);</deplist></list></pre>	n/a	The GET_MV_DEPENDENCIES procedure returns a list of dependencies for a specified view.
REFRESH(<list> VARCHAR2, <method> VARCHAR2, <rollback_seg> VARCHAR2 , <push_deferred_rpc> BOOLEAN, <refresh_after_errors> BOOLEAN , <purge_option> NUMBER, <parallelism> NUMBER, <heap_size> NUMBER , <atomic_refresh> BOOLEAN , <nested> BOOLEAN);</nested></atomic_refresh></heap_size></parallelism></purge_option></refresh_after_errors></push_deferred_rpc></rollback_seg></method></list>	n/a	This variation of the REFRESH procedure refreshes all views named in a comma-separated list of view names.
REFRESH(<tab> dbms_utility.uncl_array, <method> VARCHAR2, <rollback_seg> VARCHAR2, <push_deferred_rpc> BOOLEAN, <refresh_after_errors> BOOLEAN, <purge_option> NUMBER, <parallelism> NUMBER, <heap_size> NUMBER, <atomic_refresh> BOOLEAN, <nested> BOOLEAN);</nested></atomic_refresh></heap_size></parallelism></purge_option></refresh_after_errors></push_deferred_rpc></rollback_seg></method></tab>	n/a	This variation of the REFRESH procedure refreshes all views named in a table of dbms_utility.uncl_array values.
REFRESH_ALL_MVIEWS(<number_of_failures> BINARY_INTEGER, <method> VARCHAR2, <rollback_seg> VARCHAR2, <refresh_after_errors> BOOLEAN, <atomic_refresh> BOOLEAN);</atomic_refresh></refresh_after_errors></rollback_seg></method></number_of_failures>	n/a	The REFRESH_ALL_MVIEWS procedure refreshes all materialized views.
REFRESH_DEPENDENT(<number_of_failures> BINARY_INTEGER, <list> VARCHAR2, <method< <rollback_seg="" varchar2,=""> VARCHAR2, <refresh_after_errors> BOOLEAN, <atomic_refresh> BOOLEAN, <nested> BOOLEAN);</nested></atomic_refresh></refresh_after_errors></method<></list></number_of_failures>	n/a	This variation of the REFRESH_DEPENDENT procedure refreshes all views that are dependent on the views listed in a comma-separated list.
REFRESH_DEPENDENT(<number_of_failures> BINARY_INTEGER, <tab> dbms_utility.uncl_array, <method> VARCHAR2, <rollback_seg> VARCHAR2, <refresh_after_errors> BOOLEAN, <atomic_refresh> BOOLEAN, <nested> BOOLEAN);</nested></atomic_refresh></refresh_after_errors></rollback_seg></method></tab></number_of_failures>	n/a	This variation of the REFRESH_DEPENDENT procedure refreshes all views that are dependent on the views listed in a table of dbms_utility.uncl_array values.

Advanced Server's implementation of $\texttt{DBMS_MVIEW}$ is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

3.8. DBMS_MVIEW 93

3.8.1 GET MV DEPENDENCIES

When given the name of a materialized view, GET_MV_DEPENDENCIES returns a list of items that depend on the specified view. The signature is:

Parameters

Examples

The following example:

value.

```
DECLARE

deplist VARCHAR2(1000);

BEGIN

DBMS_MVIEW.GET_MV_DEPENDENCIES('public.emp_view', deplist);

DBMS_OUTPUT.PUT_LINE('deplist: ' || deplist);

END;
```

Displays a list of the dependencies on a materialized view named public.emp_view.

3.8. DBMS_MVIEW 94

3.8.2 REFRESH

Use the REFRESH procedure to refresh all views specified in either a comma-separated list of view names, or a table of DBMS_UTILITY.UNCL_ARRAY values. The procedure has two signatures; use the first form when specifying a comma-separated list of view names:

```
REFRESH (
        IN VARCHAR2,
        <method> IN VARCHAR2 DEFAULT NULL,
        <rollback_seg> IN VARCHAR2 DEFAULT NULL,
        <push deferred rpc> IN BOOLEAN DEFAULT TRUE,
        <refresh after errors> IN BOOLEAN DEFAULT FALSE,
        <purge_option> IN NUMBER DEFAULT 1,
        <parallelism> IN NUMBER DEFAULT 0,
        <heap size> IN NUMBER DEFAULT 0,
        <atomic refresh> IN BOOLEAN DEFAULT TRUE,
        <nested> IN BOOLEAN DEFAULT FALSE);
Use the second form to specify view names in a table of DBMS_UTILITY.UNCL_ARRAY values:
    REFRESH (
        <tab> IN OUT DBMS_UTILITY.UNCL_ARRAY,
        <method> IN VARCHAR2 DEFAULT NULL,
        <rollback seg> IN VARCHAR2 DEFAULT NULL,
        <push_deferred_rpc> IN BOOLEAN DEFAULT TRUE,
        <refresh_after_errors> IN BOOLEAN DEFAULT FALSE,
        <purge_option> IN NUMBER DEFAULT 1,
        <parallelism> IN NUMBER DEFAULT 0,
        <heap size> IN NUMBER DEFAULT 0,
        <atomic_refresh> IN BOOLEAN DEFAULT TRUE,
        <nested> IN BOOLEAN DEFAULT FALSE);
Parameters
st>
    < list > is a VARCHAR2 value that specifies the name of a materialized view, or a comma-separated list
    of materialized view names. The names may be schema-qualified.
<tab>
    <tab> is a table of DBMS UTILITY. UNCL ARRAY values that specify the name (or names) of a ma-
    terialized view.
<method>
```

3.8. DBMS MVIEW 95

<method> is a VARCHAR2 value that specifies the refresh method that will be applied to the specified

view (or views). The only supported method is C; this performs a complete refresh of the view.

Examples

The following example uses DBMS_MVIEW.REFRESH to perform a COMPLETE refresh on the public.emp_view materialized view:

```
EXEC DBMS_MVIEW.REFRESH(list => 'public.emp_view', method => 'C');
```

3.8. DBMS_MVIEW 96

3.8.3 REFRESH ALL MVIEWS

Use the REFRESH_ALL_MVIEWS procedure to refresh any materialized views that have not been refreshed since the table or view on which the view depends has been modified. The signature is:

```
REFRESH_ALL_MVIEWS(

<number_of_failures> OUT BINARY_INTEGER,

<method< IN VARCHAR2 DEFAULT NULL,

<rollback_seg> IN VARCHAR2 DEFAULT NULL,

<refresh_after_errors> IN BOOLEAN DEFAULT FALSE,

<atomic_refresh> IN BOOLEAN DEFAULT TRUE);
```

Parameters

<atomic refresh> is accepted for compatibility and ignored. The default is TRUE.

Examples

The following example performs a COMPLETE refresh on all materialized views:

```
DECLARE
   errors INTEGER;
BEGIN
   DBMS_MVIEW.REFRESH_ALL_MVIEWS(errors, method => 'C');
END;
```

Upon completion, errors contains the number of failures.

3.8. DBMS MVIEW 97

3.8.4 REFRESH DEPENDENT

Use the REFRESH_DEPENDENT procedure to refresh all material views that are dependent on the views specified in the call to the procedure. You can specify a comma-separated list or provide the view names in a table of DBMS_UTILITY.UNCL_ARRAY values.

Use the first form of the procedure to refresh all material views that are dependent on the views specified in a commaseparated list:

```
REFRESH_DEPENDENT(

<number_of_failures> OUT BINARY_INTEGER,

IN VARCHAR2,

<method> IN VARCHAR2 DEFAULT NULL,

<rollback_seg> IN VARCHAR2 DEFAULT NULL

<refresh_after_errors> IN BOOLEAN DEFAULT FALSE,

<atomic_refresh> IN BOOLEAN DEFAULT TRUE,

<nested> IN BOOLEAN DEFAULT FALSE);
```

Use the second form of the procedure to refresh all material views that are dependent on the views specified in a table of DBMS_UTILITY.UNCL_ARRAY values:

```
REFRESH_DEPENDENT(

<number_of_failures> OUT BINARY_INTEGER,

<tab> IN DBMS_UTILITY.UNCL_ARRAY,

<method> IN VARCHAR2 DEFAULT NULL,

<rollback_seg> IN VARCHAR2 DEFAULT NULL,

<refresh_after_errors> IN BOOLEAN DEFAULT FALSE,

<atomic_refresh> IN BOOLEAN DEFAULT TRUE,

<nested> IN BOOLEAN DEFAULT FALSE);
```

Parameters

```
<number_of_failures>
  <number_of_failures> is a BINARY_INTEGER that contains the number of failures that occurred
  during the refresh operation.
```

<list>

<1ist> is a VARCHAR2 value that specifies the name of a materialized view, or a comma-separated list
of materialized view names. The names may be schema-qualified.

<tab>

<tab> is a table of DBMS_UTILITY.UNCL_ARRAY values that specify the name (or names) of a materialized view.

<method>

<method> is a VARCHAR2 value that specifies the refresh method that will be applied to the specified view (or views). The only supported method is C; this performs a complete refresh of the view.

```
<rollback_seg>
```

3.8. DBMS MVIEW 98

Examples

The following example performs a COMPLETE refresh on all materialized views dependent on a materialized view named emp_view that resides in the public schema:

```
DECLARE
  errors INTEGER;
BEGIN
  DBMS_MVIEW.REFRESH_DEPENDENT(errors, list => 'public.emp_view',
  method =>
'C');
END;
```

Upon completion, errors contains the number of failures.

3.8. DBMS_MVIEW 99

3.9 DBMS_OUTPUT

The DBMS_OUTPUT package provides the capability to send messages (lines of text) to a message buffer, or get messages from the message buffer. A message buffer is local to a single session. Use the DBMS_PIPE package to send messages between sessions.

The procedures and functions available in the DBMS_OUTPUT package are listed in the following table.

Function/Procedure	Return	Description
	Type	
DISABLE	n/a	Disable the capability to send and receive messages.
ENABLE(<buffer_size>)</buffer_size>	n/a	Enable the capability to send and receive messages.
GET_LINE(<line> OUT,</line>	n/a	Get a line from the message buffer.
<status> OUT)</status>		
GET_LINES(<lines> OUT,</lines>	n/a	Get multiple lines from the message buffer.
<numlines> IN OUT)</numlines>		
NEW_LINE	n/a	Puts an end-of-line character sequence.
PUT(<item>)</item>	n/a	Puts a partial line without an end-of-line character sequence.
PUT_LINE(<item>)</item>	n/a	Puts a complete line with an end-of-line character sequence.
SERVEROUTPUT(<stdout>)</stdout>	n/a	Direct messages from PUT, PUT_LINE, or NEW_LINE to
		either standard output or the message buffer.

The following table lists the public variables available in the DBMS_OUTPUT package.

Public Variables	Data Type	Value	Description
chararr	TABLE		For message lines.

3.9.1 CHARARR

The CHARARR is for storing multiple message lines.

TYPE chararr IS TABLE OF VARCHAR2 (32767) INDEX BY BINARY_INTEGER;

3.9. DBMS_OUTPUT 100

3.9.2 DISABLE

The DISABLE procedure clears out the message buffer. Any messages in the buffer at the time the DISABLE procedure is executed will no longer be accessible. Any messages subsequently sent with the PUT, PUT_LINE, or NEW_LINE procedures are discarded. No error is returned to the sender when the PUT, PUT_LINE, or NEW_LINE procedures are executed and messages have been disabled.

Use the ENABLE procedure or SERVEROUTPUT (TRUE) procedure to re-enable the sending and receiving of messages.

DISABLE

Examples

This anonymous block disables the sending and receiving messages in the current session.

BEGIN

DBMS_OUTPUT.DISABLE;

END;

3.9. DBMS_OUTPUT 101

3.9.3 ENABLE

The ENABLE procedure enables the capability to send messages to the message buffer or retrieve messages from the message buffer. Running SERVEROUTPUT (TRUE) also implicitly performs the ENABLE procedure.

The destination of a message sent with PUT, PUT_LINE, or NEW_LINE depends upon the state of SERVEROUTPUT.

- If the last state of SERVEROUTPUT is TRUE, the message goes to standard output of the command line.
- If the last state of SERVEROUTPUT is FALSE, the message goes to the message buffer.

```
ENABLE [ (<buffer_size> INTEGER) ]
```

Parameter

```
<buffer size>
```

Maximum length of the message buffer in bytes. If a <buffer_size> of less than 2000 is specified, the buffer size is set to 2000.

Examples

The following anonymous block enables messages. Setting SERVEROUTPUT (TRUE) forces them to standard output.

```
BEGIN

DBMS_OUTPUT.ENABLE;

DBMS_OUTPUT.SERVEROUTPUT(TRUE);

DBMS_OUTPUT.PUT_LINE('Messages enabled');

END;

Messages enabled
```

The same effect could have been achieved by simply using SERVEROUTPUT (TRUE).

```
BEGIN

DBMS_OUTPUT.SERVEROUTPUT(TRUE);

DBMS_OUTPUT.PUT_LINE('Messages enabled');

END;

Messages enabled
```

The following anonymous block enables messages, but setting SERVEROUTPUT (FALSE) directs messages to the message buffer.

```
BEGIN
    DBMS_OUTPUT.ENABLE;
    DBMS_OUTPUT.SERVEROUTPUT(FALSE);
    DBMS_OUTPUT.PUT_LINE('Message sent to buffer');
END;
```

3.9.4 GET LINE

The GET_LINE procedure provides the capability to retrieve a line of text from the message buffer. Only text that has been terminated by an end-of-line character sequence is retrieved – that is complete lines generated using PUT_LINE, or by a series of PUT calls followed by a NEW_LINE call.

```
GET_LINE(<line> OUT VARCHAR2, <status> OUT INTEGER)
```

Parameters

line>

Variable receiving the line of text from the message buffer.

<status>

0 if a line was returned from the message buffer, 1 if there was no line to return.

Examples

The following anonymous block writes the emp table out to the message buffer as a comma-delimited string for each row.

The following anonymous block reads the message buffer and inserts the messages written by the prior example into a table named messages. The rows in messages are then displayed.

```
CREATE TABLE messages (
   status
                   INTEGER,
   msq
                   VARCHAR2 (100)
);
DECLARE
   v_line
                   VARCHAR2 (100);
                   INTEGER := 0;
   v_status
BEGIN
   DBMS_OUTPUT.GET_LINE(v_line, v_status);
   WHILE v_status = 0 LOOP
       INSERT INTO messages VALUES(v_status, v_line);
       DBMS_OUTPUT.GET_LINE(v_line, v_status);
   END LOOP;
END;
SELECT msg FROM messages;
                               msq
```

```
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, ,30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, ,10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839, KING, PRESIDENT, ,17-NOV-81 00:00:00, 5000.00, 10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
(14 rows)
```

3.9.5 GET_LINES

The GET_LINES procedure provides the capability to retrieve one or more lines of text from the message buffer into a collection. Only text that has been terminated by an end-of-line character sequence is retrieved – that is complete lines generated using PUT_LINE, or by a series of PUT calls followed by a NEW_LINE call.

```
GET_LINES(<lines> OUT CHARARR, <numlines> IN OUT INTEGER)
```

Parameters

nes>

Table receiving the lines of text from the message buffer. See CHARARR for a description of 1 ines>.

```
<numlines> IN
```

Number of lines to be retrieved from the message buffer.

```
<numlines> OUT
```

Actual number of lines retrieved from the message buffer. If the output value of <numlines> is less than the input value, then there are no more lines left in the message buffer.

Examples

The following example uses the GET_LINES procedure to store all rows from the emp table that were placed on the message buffer, into an array.

```
EXEC DBMS_OUTPUT.SERVEROUTPUT(FALSE);
DECLARE
                   VARCHAR2(120);
    v_emprec
   CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
   DBMS_OUTPUT.ENABLE;
    FOR i IN emp_cur LOOP
        v_emprec := i.empno || ',' || i.ename || ',' || i.job || ',' ||
            NVL(LTRIM(TO_CHAR(i.mgr,'9999')),'') || ',' || i.hiredate ||
            ',' || i.sal || ',' ||
            NVL(LTRIM(TO_CHAR(i.comm, '9990.99')),'') || ',' || i.deptno;
        DBMS_OUTPUT.PUT_LINE(v_emprec);
   END LOOP;
END;
DECLARE
   v lines
                   DBMS OUTPUT.CHARARR;
   v_numlines
                  INTEGER := 14;
                  INTEGER := 0;
   v_status
BEGIN
   DBMS_OUTPUT.GET_LINES(v_lines, v_numlines);
    FOR i IN 1..v_numlines LOOP
        INSERT INTO messages VALUES(v numlines, v lines(i));
   END LOOP;
END;
SELECT msg FROM messages;
                               msa
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
```

```
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00,,20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00,30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00,,30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00,,10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00,,20
7839, KING, PRESIDENT,,17-NOV-81 00:00:00,5000.00,,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00,1500.00,0.00,30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00,1100.00,,20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00,950.00,,30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00,3000.00,,20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00,1300.00,,10
(14 rows)
```

3.9.6 NEW_LINE

The NEW_LINE procedure writes an end-of-line character sequence in the message buffer.

NEW_LINE

Parameter

The NEW_LINE procedure expects no parameters.

3.9.7 PUT

The PUT procedure writes a string to the message buffer. No end-of-line character sequence is written at the end of the string. Use the NEW_LINE procedure to add an end-of-line character sequence.

```
PUT (<item> VARCHAR2)
```

Parameter

<item>

Text written to the message buffer.

Examples

The following example uses the PUT procedure to display a comma-delimited list of employees from the emp table.

```
DECLARE
    CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
    FOR i IN emp_cur LOOP
        DBMS_OUTPUT.PUT(i.empno);
        DBMS_OUTPUT.PUT(',');
        DBMS_OUTPUT.PUT(i.ename);
        DBMS_OUTPUT.PUT(',');
        DBMS_OUTPUT.PUT(i.job);
        DBMS_OUTPUT.PUT(',');
        DBMS_OUTPUT.PUT(i.mgr);
        DBMS_OUTPUT.PUT(',');
        DBMS_OUTPUT.PUT(i.hiredate);
        DBMS_OUTPUT.PUT(',');
        DBMS_OUTPUT.PUT(i.sal);
        DBMS_OUTPUT.PUT(',');
        DBMS_OUTPUT.PUT(i.comm);
        DBMS_OUTPUT.PUT(',');
        DBMS_OUTPUT.PUT(i.deptno);
        DBMS_OUTPUT.NEW_LINE;
    END LOOP;
END;
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839, KING, PRESIDENT, , 17-NOV-81 00:00:00, 5000.00, , 10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00,,20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
```

3.9.8 PUT LINE

The PUT LINE procedure writes a single line to the message buffer including an end-of-line character sequence.

```
PUT_LINE(<item> VARCHAR2)
```

Parameter

<item>

Text to be written to the message buffer.

Examples

The following example uses the PUT_LINE procedure to display a comma-delimited list of employees from the emp

```
DECLARE
    v_emprec
                     VARCHAR2 (120);
    CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
    FOR i IN emp_cur LOOP
        v_emprec := i.empno || ',' || i.ename || ',' || i.job || ',' ||
             NVL(LTRIM(TO_CHAR(i.mgr,'9999')),'') || ',' || i.hiredate ||
             ',' || i.sal || ',' ||
            NVL(LTRIM(TO_CHAR(i.comm, '9990.99')),'') || ',' || i.deptno;
        DBMS_OUTPUT.PUT_LINE(v_emprec);
    END LOOP;
END;
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839, KING, PRESIDENT, ,17-NOV-81 00:00:00,5000.00,,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
```

3.9.9 SERVEROUTPUT

The SERVEROUTPUT procedure provides the capability to direct messages to standard output of the command line or to the message buffer. Setting SERVEROUTPUT (TRUE) also performs an implicit execution of ENABLE.

The default setting of SERVEROUTPUT is implementation dependent. For example, in Oracle SQL*Plus, SERVEROUTPUT (FALSE) is the default. In PSQL, SERVEROUTPUT (TRUE) is the default. Also note that in Oracle SQL*Plus, this setting is controlled using the SQL*Plus SET command, not by a stored procedure as implemented in Advanced Server.

```
SERVEROUTPUT (<stdout> BOOLEAN)
```

Parameter

<stdout>

Set to TRUE if subsequent PUT, PUT_LINE, or NEW_LINE commands are to send text directly to standard output of the command line. Set to FALSE if text is to be sent to the message buffer.

Examples

The following anonymous block sends the first message to the command line and the second message to the message buffer.

```
BEGIN

DBMS_OUTPUT.SERVEROUTPUT(TRUE);

DBMS_OUTPUT.PUT_LINE('This message goes to the command line');

DBMS_OUTPUT.SERVEROUTPUT(FALSE);

DBMS_OUTPUT.PUT_LINE('This message goes to the message buffer');

END;

This message goes to the command line
```

If within the same session, the following anonymous block is executed, the message stored in the message buffer from the prior example is flushed and displayed on the command line as well as the new message.

```
BEGIN

DBMS_OUTPUT.SERVEROUTPUT(TRUE);

DBMS_OUTPUT.PUT_LINE('Flush messages from the buffer');

END;

This message goes to the message buffer

Flush messages from the buffer
```

3.10 DBMS PIPE

The DBMS_PIPE package provides the capability to send messages through a pipe within or between sessions connected to the same database cluster.

The procedures and functions available in the DBMS_PIPE package are listed in the following table:

Function/Procedure	Return Type	Description				
CREATE_PIPE(<pipename> [,</pipename>	INTEGER	Explicitly create a private pipe if				
<maxpipesize>] [, <private></private></maxpipesize>		<pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre>				
])		a public pipe if <private> is "false".</private>				
NEXT_ITEM_TYPE	INTEGER	Determine the data type of the next item in				
		a received message.				
PACK_MESSAGE(<item>)</item>	n/a	Place <item> in the session's local mes-</item>				
		sage buffer.				
PURGE(<pipename>)</pipename>	n/a	Remove unreceived messages from the				
	specified pipe.					
<pre>RECEIVE_MESSAGE(<pipename> [,</pipename></pre>	INTEGER	Get a message from a specified pipe.				
<timeout>])</timeout>						
REMOVE_PIPE(<pipename>)</pipename>	INTEGER	Delete an explicitly created pipe.				
RESET_BUFFER	n/a	Reset the local message buffer.				
SEND_MESSAGE(<pipename> [,</pipename>	INTEGER	Send a message on a pipe.				
<timeout>] [, <maxpipesize></maxpipesize></timeout>						
])						
UNIQUE_SESSION_NAME VARCHAR2 Obtain a unique session name.						
UNPACK_MESSAGE(<item> OUT)</item>	n/a	Retrieve the next data item from a message				
		into a type-compatible variable, <item>.</item>				

Pipes are categorized as implicit or explicit. An *implicit pipe* is created if a reference is made to a pipe name that was not previously created by the CREATE_PIPE function. For example, if the SEND_MESSAGE function is executed using a non-existent pipe name, a new implicit pipe is created with that name. An *explicit pipe* is created using the CREATE_PIPE function whereby the first parameter specifies the pipe name for the new pipe.

Pipes are also categorized as private or public. A *private pipe* can only be accessed by the user who created the pipe. Even a superuser cannot access a private pipe that was created by another user. A *public pipe* can be accessed by any user who has access to the DBMS_PIPE package.

A public pipe can only be created by using the <code>CREATE_PIPE</code> function with the third parameter set to <code>FALSE</code>. The <code>CREATE_PIPE</code> function can be used to create a private pipe by setting the third parameter to <code>TRUE</code> or by omitting the third parameter. All implicit pipes are private.

The individual data items or "lines" of a message are first built-in a *local message buffer*, unique to the current session. The PACK_MESSAGE procedure builds the message in the session's local message buffer. The SEND_MESSAGE function is then used to send the message through the pipe.

Receipt of a message involves the reverse operation. The RECEIVE_MESSAGE function is used to get a message from the specified pipe. The message is written to the session's local message buffer. The UNPACK_MESSAGE procedure is then used to transfer the message data items from the message buffer to program variables. If a pipe contains multiple messages, RECEIVE_MESSAGE gets the messages in *FIFO* (first-in-first-out) order.

Each session maintains separate message buffers for messages created with the PACK_MESSAGE procedure and messages retrieved by the RECEIVE_MESSAGE function. Thus messages can be both built and received in the same session. However, if consecutive RECEIVE_MESSAGE calls are made, only the message from the last RECEIVE_MESSAGE call will be preserved in the local message buffer.

3.10.1 CREATE PIPE

The CREATE_PIPE function creates an explicit public pipe or an explicit private pipe with a specified name.

```
<status> INTEGER CREATE_PIPE(<pipename> VARCHAR2
   [, <maxpipesize> INTEGER ] [, <private> BOOLEAN ])
```

Parameters

<pipename>

Name of the pipe.

<maxpipesize>

Maximum capacity of the pipe in bytes. Default is 8192 bytes.

<private>

Create a public pipe if set to FALSE. Create a private pipe if set to TRUE. This is the default.

<status>

Status code returned by the operation. 0 indicates successful creation.

Examples

The following example creates a private pipe named messages:

The following example creates a public pipe named mailbox:

```
DECLARE

v_status INTEGER;

BEGIN

v_status := DBMS_PIPE.CREATE_PIPE('mailbox', 8192, FALSE);

DBMS_OUTPUT.PUT_LINE('CREATE_PIPE status: ' || v_status);

END;

CREATE_PIPE status: 0
```

3.10.2 NEXT ITEM TYPE

The NEXT_ITEM_TYPE function returns an integer code identifying the data type of the next data item in a message that has been retrieved into the session's local message buffer. As each item is moved off of the local message buffer with the UNPACK_MESSAGE procedure, the NEXT_ITEM_TYPE function will return the data type code for the next available item. A code of 0 is returned when there are no more items left in the message.

```
<typecode> INTEGER NEXT_ITEM_TYPE
```

Parameters

<typecode>

Code identifying the data type of the next data item as shown in the following table.

Type Code	Data Type
0	No more data items
9	NUMBER
11	VARCHAR2
13	DATE
23	RAW

Note: The type codes list in the table are not compatible with Oracle databases. Oracle assigns a different numbering sequence to the data types.

Examples

The following example shows a pipe packed with a NUMBER item, a VARCHAR2 item, a DATE item, and a RAW item. A second anonymous block then uses the NEXT_ITEM_TYPE function to display the type code of each item.

```
DECLARE
   v_number
                  NUMBER := 123;
   v_varchar
v_date
v_raw
                  VARCHAR2(20) := 'Character data';
                 DATE := SYSDATE;
                  RAW(4) := '21222324';
                   INTEGER;
   v_status
BEGIN
   DBMS_PIPE.PACK_MESSAGE(v_number);
   DBMS_PIPE.PACK_MESSAGE(v_varchar);
   DBMS_PIPE.PACK_MESSAGE(v_date);
   DBMS_PIPE.PACK_MESSAGE(v_raw);
   v_status := DBMS_PIPE.SEND_MESSAGE('datatypes');
   DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);
EXCEPTION
   WHEN OTHERS THEN
       DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
       DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
SEND_MESSAGE status: 0
DECLARE
   v_number
                  NUMBER;
   v_varchar
                   VARCHAR2 (20);
   v_date
                  DATE;
   v_timestamp
                  TIMESTAMP;
```

```
v_raw
                RAW (4);
   v_status
                INTEGER;
BEGIN
   v_status := DBMS_PIPE.RECEIVE_MESSAGE('datatypes');
   DBMS_OUTPUT.PUT_LINE('RECEIVE_MESSAGE status: ' || v_status);
   DBMS_OUTPUT.PUT_LINE('-----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
   DBMS_PIPE.UNPACK_MESSAGE(v_number);
   DBMS_OUTPUT.PUT_LINE('NUMBER Item : ' || v_number);
   DBMS_OUTPUT.PUT_LINE('-----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
   DBMS_PIPE.UNPACK_MESSAGE(v_varchar);
   DBMS_OUTPUT.PUT_LINE('VARCHAR2 Item : ' || v_varchar);
   DBMS_OUTPUT.PUT_LINE('-----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
   DBMS_PIPE.UNPACK_MESSAGE(v_date);
                                  : ' || v_date);
   DBMS_OUTPUT.PUT_LINE('DATE Item
   DBMS_OUTPUT.PUT_LINE('----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
   DBMS_PIPE.UNPACK_MESSAGE(v_raw);
   DBMS_OUTPUT.PUT_LINE('RAW Item : ' || v_raw);
   DBMS_OUTPUT.PUT_LINE('-----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
   DBMS_OUTPUT.PUT_LINE('-----');
EXCEPTION
   WHEN OTHERS THEN
      DBMS_OUTPUT_PUT_LINE('SQLERRM: ' || SQLERRM);
       DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
RECEIVE_MESSAGE status: 0
NEXT_ITEM_TYPE: 9
NUMBER Item : 123
NEXT_ITEM_TYPE: 11
VARCHAR2 Item : Character data
NEXT_ITEM_TYPE: 13
DATE Item : 02-OCT-07 11:11:43
NEXT_ITEM_TYPE: 23
RAW Item : 21222324
NEXT_ITEM_TYPE: 0
```

3.10.3 PACK_MESSAGE

The PACK_MESSAGE procedure places an item of data in the session's local message buffer. PACK_MESSAGE must be executed at least once before issuing a SEND_MESSAGE call.

```
PACK_MESSAGE(<item> { DATE | NUMBER | VARCHAR2 | RAW })
```

Use the UNPACK_MESSAGE procedure to obtain data items once the message is retrieved using a RECEIVE_MESSAGE call.

Parameters

<item>

An expression evaluating to any of the acceptable parameter data types. The value is added to the session's local message buffer.

3.10.4 PURGE

The PURGE procedure removes the unreceived messages from a specified implicit pipe.

```
PURGE(<pipename> VARCHAR2)
```

Use the REMOVE_PIPE function to delete an explicit pipe.

Parameter

```
<pipename>
```

Name of the pipe.

Examples

Two messages are sent on a pipe:

```
DECLARE

v_status INTEGER;

BEGIN

DBMS_PIPE.PACK_MESSAGE('Message #1');

v_status := DBMS_PIPE.SEND_MESSAGE('pipe');

DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);

DBMS_PIPE.PACK_MESSAGE('Message #2');

v_status := DBMS_PIPE.SEND_MESSAGE('pipe');

DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);

END;

SEND_MESSAGE status: 0

SEND_MESSAGE status: 0
```

Receive the first message and unpack it:

Purge the pipe:

```
EXEC DBMS_PIPE.PURGE('pipe');
```

Try to retrieve the next message. The RECEIVE_MESSAGE call returns status code 1 indicating it timed out because no message was available.

3.10.5 RECEIVE_MESSAGE

The RECEIVE_MESSAGE function obtains a message from a specified pipe.

```
<status> INTEGER RECEIVE_MESSAGE(<pipename> VARCHAR2
    [, <timeout> INTEGER ])
```

Parameters

<pipename>

Name of the pipe.

<timeout>

Wait time (seconds). Default is 86400000 (1000 days).

<status>

Status code returned by the operation.

The possible status codes are:

Status Code	Description
0	Success
1	Time out
2	Message too large .for the buffer

3.10.6 REMOVE PIPE

The REMOVE_PIPE function deletes an explicit private or explicit public pipe.

```
<status> INTEGER REMOVE_PIPE(<pipename> VARCHAR2)
```

Use the REMOVE_PIPE function to delete explicitly created pipes – i.e., pipes created with the CREATE_PIPE function.

Parameters

<pipename>

Name of the pipe.

<status>

Status code returned by the operation. A status code of 0 is returned even if the named pipe is non-existent.

Examples

Two messages are sent on a pipe:

```
DECLARE
   v_status
                    INTEGER:
BEGIN
   v_status := DBMS_PIPE.CREATE_PIPE('pipe');
   DBMS_OUTPUT.PUT_LINE('CREATE_PIPE status : ' || v_status);
   DBMS_PIPE.PACK_MESSAGE('Message #1');
   v_status := DBMS_PIPE.SEND_MESSAGE('pipe');
   DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);
   DBMS_PIPE.PACK_MESSAGE('Message #2');
   v_status := DBMS_PIPE.SEND_MESSAGE('pipe');
   DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);
END;
CREATE_PIPE status : 0
SEND_MESSAGE status: 0
SEND_MESSAGE status: 0
```

Receive the first message and unpack it:

Remove the pipe:

```
SELECT DBMS_PIPE.REMOVE_PIPE('pipe') FROM DUAL;

remove_pipe
-----
0
(1 row)
```

Try to retrieve the next message. The RECEIVE_MESSAGE call returns status code 1 indicating it timed out because the pipe had been deleted.

3.10.7 RESET BUFFER

The RESET_BUFFER procedure resets a "pointer" to the session's local message buffer back to the beginning of the buffer. This has the effect of causing subsequent PACK_MESSAGE calls to overwrite any data items that existed in the message buffer prior to the RESET_BUFFER call.

```
RESET BUFFER
```

Examples

A message to John is written to the local message buffer. It is replaced by a message to Bob by calling RESET_BUFFER. The message is sent on the pipe.

```
DECLARE

v_status INTEGER;

BEGIN

DBMS_PIPE.PACK_MESSAGE('Hi, John');

DBMS_PIPE.PACK_MESSAGE('Can you attend a meeting at 3:00, today?');

DBMS_PIPE.PACK_MESSAGE('If not, is tomorrow at 8:30 ok with you?');

DBMS_PIPE.RESET_BUFFER;

DBMS_PIPE.PACK_MESSAGE('Hi, Bob');

DBMS_PIPE.PACK_MESSAGE('Can you attend a meeting at 9:30, tomorrow?');

v_status := DBMS_PIPE.SEND_MESSAGE('pipe');

DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);

END;

SEND_MESSAGE status: 0
```

The message to Bob is in the received message.

```
DECLARE
   v_item
                   VARCHAR2(80);
                   INTEGER;
   v_status
BEGIN
   v_status := DBMS_PIPE.RECEIVE_MESSAGE('pipe',1);
   DBMS_OUTPUT.PUT_LINE('RECEIVE_MESSAGE status: ' || v_status);
   DBMS_PIPE.UNPACK_MESSAGE(v_item);
   DBMS_OUTPUT.PUT_LINE('Item: ' || v_item);
   DBMS_PIPE.UNPACK_MESSAGE(v_item);
   DBMS_OUTPUT.PUT_LINE('Item: ' || v_item);
END;
RECEIVE_MESSAGE status: 0
Item: Hi, Bob
Item: Can you attend a meeting at 9:30, tomorrow?
```

3.10.8 SEND_MESSAGE

The SEND_MESSAGE function sends a message from the session's local message buffer to the specified pipe.

```
<status> SEND_MESSAGE(<pipename> VARCHAR2 [, <timeout> INTEGER ]
    [, <maxpipesize> INTEGER ])
```

Parameters

<pipename>

Name of the pipe.

<timeout>

Wait time (seconds). Default is 86400000 (1000 days).

<maxpipesize>

Maximum capacity of the pipe in bytes. Default is 8192 bytes.

<status>

Status code returned by the operation.

The possible status codes are:

Status Code	Description
0	Success
1	Time out
3	Function interrupted

3.10.9 UNIQUE_SESSION_NAME

The UNIQUE_SESSION_NAME function returns a name, unique to the current session.

```
<name> VARCHAR2 UNIQUE_SESSION_NAME
```

Parameters

<name>

Unique session name.

Examples

The following anonymous block retrieves and displays a unique session name.

```
DECLARE
v_session VARCHAR2(30);

BEGIN
v_session := DBMS_PIPE.UNIQUE_SESSION_NAME;

DBMS_OUTPUT_LINE('Session Name: ' || v_session);

END;

Session Name: PG$PIPE$5$2752
```

3.10.10 UNPACK_MESSAGE

The UNPACK_MESSAGE procedure copies the data items of a message from the local message buffer to a specified program variable. The message must be placed in the local message buffer with the RECEIVE_MESSAGE function before using UNPACK_MESSAGE.

```
UNPACK_MESSAGE(<item> OUT { DATE | NUMBER | VARCHAR2 | RAW })
```

Parameter

<item>

Type-compatible variable that receives a data item from the local message buffer.

3.10.11 Comprehensive Example

The following example uses a pipe as a "mailbox". The procedures to create the mailbox, add a multi-item message to the mailbox (up to three items), and display the full contents of the mailbox are enclosed in a package named, mailbox.

```
CREATE OR REPLACE PACKAGE mailbox
   PROCEDURE create_mailbox;
   PROCEDURE add_message (
      p_mailbox VARCHAR2,
      p_item_1 VARCHAR2,
      p_item_2 VARCHAR2 DEFAULT 'END',
      );
   PROCEDURE empty_mailbox (
       p_mailbox VARCHAR2,
       p_waittime INTEGER DEFAULT 10
END mailbox;
CREATE OR REPLACE PACKAGE BODY mailbox
   PROCEDURE create_mailbox
       v_mailbox VARCHAR2(30);
      v_status INTEGER;
       v_mailbox := DBMS_PIPE.UNIQUE_SESSION_NAME;
       v_status := DBMS_PIPE.CREATE_PIPE(v_mailbox, 1000, FALSE);
       IF v_status = 0 THEN
          DBMS_OUTPUT.PUT_LINE('Created mailbox: ' || v_mailbox);
          DBMS_OUTPUT_LINE('CREATE_PIPE failed - status: ' ||
              v_status);
       END IF:
   END create_mailbox;
   PROCEDURE add_message (
       p_mailbox VARCHAR2,
       p_item_1 VARCHAR2,
       )
   TS
       v_item_cnt INTEGER := 0;
       v_status INTEGER;
   BEGIN
       DBMS_PIPE.PACK_MESSAGE(p_item_1);
       v_item_cnt := 1;
       IF p_item_2 != 'END' THEN
          DBMS_PIPE.PACK_MESSAGE(p_item_2);
          v_item_cnt := v_item_cnt + 1;
       END IF;
       IF p_item_3 != 'END' THEN
          DBMS_PIPE.PACK_MESSAGE(p_item_3);
          v_item_cnt := v_item_cnt + 1;
       END IF;
```

```
v_status := DBMS_PIPE.SEND_MESSAGE(p_mailbox);
       IF v_status = 0 THEN
            DBMS_OUTPUT.PUT_LINE('Added message with ' || v_item_cnt ||
               ' item(s) to mailbox ' || p_mailbox);
       ELSE
           DBMS_OUTPUT_LINE('SEND_MESSAGE in add_message failed - ' ||
                'status: ' || v_status);
       END IF;
   END add_message;
   PROCEDURE empty_mailbox (
       p_mailbox VARCHAR2,
       p_waittime INTEGER DEFAULT 10
    IS
                  INTEGER DEFAULT 0;
       v_msqno
       v_itemno INTEGER DEFAULT 0;
                  VARCHAR2 (100);
       v_item
       v_status INTEGER;
   BEGIN
       v_status := DBMS_PIPE.RECEIVE_MESSAGE(p_mailbox,p_waittime);
       WHILE v_status = 0 LOOP
           v_msgno := v_msgno + 1;
           DBMS_OUTPUT.PUT_LINE('***** Start message #' || v_msgno ||
               ' *****');
           BEGIN
               LOOP
                    v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
                   EXIT WHEN v_status = 0;
                   DBMS_PIPE.UNPACK_MESSAGE(v_item);
                   v_itemno := v_itemno + 1;
                    DBMS_OUTPUT.PUT_LINE('Item #' || v_itemno || ': ' ||
               END LOOP;
               DBMS_OUTPUT.PUT_LINE('***** End message #' || v_msgno ||
                    ' ******');
               DBMS_OUTPUT.PUT_LINE('*');
               v_{itemno} := 0;
               v_status := DBMS_PIPE.RECEIVE_MESSAGE(p_mailbox, 1);
           END;
       END LOOP;
       DBMS_OUTPUT_LINE('Number of messages received: ' || v_msgno);
       v_status := DBMS_PIPE.REMOVE_PIPE(p_mailbox);
       IF v_status = 0 THEN
            DBMS_OUTPUT.PUT_LINE('Deleted mailbox ' || p_mailbox);
       ELSE
            DBMS_OUTPUT.PUT_LINE('Could not delete mailbox - status: '
               || v_status);
       END IF;
   END empty_mailbox;
END mailbox;
```

The following demonstrates the execution of the procedures in mailbox. The first procedure creates a public pipe using a name generated by the UNIQUE_SESSION_NAME function.

```
EXEC mailbox.create_mailbox;
Created mailbox: PG$PIPE$13$3940
```

Using the mailbox name, any user in the same database with access to the mailbox package and DBMS_PIPE package can add messages:

```
EXEC mailbox.add_message('PG$PIPE$13$3940','Hi, John','Can you attend a meeting at_

3:00, today?','-- Mary');

Added message with 3 item(s) to mailbox PG$PIPE$13$3940

EXEC mailbox.add_message('PG$PIPE$13$3940','Don''t forget to submit your report',

'Thanks,','-- Joe');

Added message with 3 item(s) to mailbox PG$PIPE$13$3940
```

Finally, the contents of the mailbox can be emptied:

```
EXEC mailbox.empty_mailbox('PG$PIPE$13$3940');

****** Start message #1 ******
Item #1: Hi, John
Item #2: Can you attend a meeting at 3:00, today?
Item #3: -- Mary

******* End message #1 ******

*

****** Start message #2 ******
Item #1: Don't forget to submit your report
Item #2: Thanks,
Item #3: Joe

******* End message #2 ******

*

Number of messages received: 2
Deleted mailbox PG$PIPE$13$3940
```

3.11 DBMS_PROFILER

The DBMS_PROFILER package collects and stores performance information about the PL/pgSQL and SPL statements that are executed during a performance profiling session; use the functions and procedures listed below to control the profiling tool.

Function/Procedure	Return	Description
	Type	
FLUSH_DATA	Status	Flushes performance data collected in the current
	Code or	session without terminating the session (profiling
	Exception	continues).
<pre>GET_VERSION(<major> OUT,</major></pre>	n/a	Returns the version number of this package.
<minor> OUT)</minor>		
INTERNAL_VERSION_CHECK	Status	Confirms that the current version of the profiler
	Code	will work with the current database.
PAUSE_PROFILER	Status	Pause data collection.
	Code or	
	Exception	
RESUME_PROFILER	Status	Resume data collection.
	Code or	
	Exception	
START_PROFILER(<run_comment>,</run_comment>	Status	Start data collection.
<run_comment1> [, <run_number></run_number></run_comment1>	Code or	
OUT])	Exception	
STOP_PROFILER	Status	Stop data collection and flush performance data to
	Code or	the PLSQL_PROFILER_RAWDATA table.
	Exception	

The functions within the DBMS_PROFILER package return a status code to indicate success or failure; the DBMS_PROFILER procedures raise an exception only if they encounter a failure. The status codes and messages returned by the functions, and the exceptions raised by the procedures are listed in the table below.

Status Code	Message	Exception	Description
-1	error	version_mismatch	The profiler version and the database are incompat-
	version		ible.
0	success	n/a	The operation completed successfully.
1	error_param	profiler_error	The operation received an incorrect parameter.
2	error_io	profiler_error	The data flush operation has failed.

3.11.1 FLUSH DATA

The FLUSH_DATA function/procedure flushes the data collected in the current session without terminating the profiler session. The data is flushed to the tables described in the Advanced Server Performance Features Guide. The function and procedure signatures are:

```
<status> INTEGER FLUSH_DATA
FLUSH_DATA
```

Parameter

<status>

Status code returned by the operation.

3.11.2 GET_VERSION

The GET_VERSION procedure returns the version of DBMS_PROFILER. The procedure signature is:

```
GET_VERSION(<major> OUT INTEGER, <minor> OUT INTEGER)
```

Parameters

<major>

The major version number of DBMS_PROFILER.

<minor>

The minor version number of DBMS PROFILER.

3.11.3 INTERNAL_VERSION_CHECK

The INTERNAL_VERSION_CHECK function confirms that the current version of DBMS_PROFILER will work with the current database. The function signature is:

```
<status> INTEGER INTERNAL_VERSION_CHECK
```

Parameter

<status>

Status code returned by the operation.

3.11.4 PAUSE PROFILER

The PAUSE_PROFILER function/procedure pauses a profiling session. The function and procedure signatures are:

```
<status> INTEGER PAUSE_PROFILER
PAUSE_PROFILER
```

Parameter

<status>

Status code returned by the operation.

3.11.5 RESUME_PROFILER

The RESUME_PROFILER function/procedure pauses a profiling session. The function and procedure signatures are:

```
<status> INTEGER RESUME_PROFILER
RESUME_PROFILER
```

Parameter

<status>

Status code returned by the operation.

3.11.6 START_PROFILER

The START_PROFILER function/procedure starts a data collection session. The function and procedure signatures are:

Parameters

<run_comment>

A user-defined comment for the profiler session. The default value is SYSDATE.

<run comment1>

An additional user-defined comment for the profiler session. The default value is ".

<run_number>

The session number of the profiler session.

<status>

Status code returned by the operation.

3.11.7 STOP_PROFILER

The STOP_PROFILER function/procedure stops a profiling session and flushes the performance information to the DBMS_PROFILER tables and view. The function and procedure signatures are:

```
<status> INTEGER STOP_PROFILER
STOP_PROFILER
```

Parameter

<status>

Status code returned by the operation.

3.11.8 Using DBMS_PROFILER

The DBMS_PROFILER package collects and stores performance information about the PL/pgSQL and SPL statements that are executed during a profiling session; you can review the performance information in the tables and views provided by the profiler.

DBMS_PROFILER works by recording a set of performance-related counters and timers for each line of PL/pgSQL or SPL statement that executes within a profiling session. The counters and timers are stored in a table named SYS. PLSQL_PROFILER_DATA. When you complete a profiling session, DBMS_PROFILER will write a row to the performance statistics table for each line of PL/pgSQL or SPL code that executed within the session. For example, if you execute the following function:

```
1 - CREATE OR REPLACE FUNCTION getBalance(acctNumber INTEGER)
2 - RETURNS NUMERIC AS $$
3 - DECLARE
4 - result NUMERIC;
5 - BEGIN
6 - SELECT INTO result balance FROM acct WHERE id = acctNumber;
7 -
8 - IF (result IS NULL) THEN
9 - RAISE INFO 'Balance is null';
10- END IF;
11-
12- RETURN result;
13- END;
14- $$ LANGUAGE 'plpgsql';
```

DBMS_PROFILER adds one PLSQL_PROFILER_DATA entry for each line of code within the getBalance() function (including blank lines and comments). The entry corresponding to the SELECT statement executed exactly one time; and required a very small amount of time to execute. On the other hand, the entry corresponding to the RAISE INFO statement executed once or not at all (depending on the value for the balance column).

Some of the lines in this function contain no executable code so the performance statistics for those lines will always contain zero values.

To start a profiling session, invoke the DBMS_PROFILER.START_PROFILER function (or procedure). Once you've invoked START_PROFILER, Advanced Server will profile every PL/pgSQL or SPL function, procedure, trigger, or anonymous block that your session executes until you either stop or pause the profiler (by calling STOP_PROFILER or PAUSE PROFILER).

It is important to note that when you start (or resume) the profiler, the profiler will only gather performance statistics for functions/procedures/triggers that start after the call to START_PROFILER (or RESUME_PROFILER).

While the profiler is active, Advanced Server records a large set of timers and counters in memory; when you invoke the STOP_PROFILER (or FLUSH_DATA) function/procedure, DBMS_PROFILER writes those timers and counters to a set of three tables:

• SYS.PLSQL_PROFILER_RAWDATA

Contains the performance counters and timers for each statement executed within the session.

• SYS.PLSQL_PROFILER_RUNS

Contains a summary of each run (aggregating the information found in PLSQL_PROFILER_RAWDATA).

• SYS.PLSQL_PROFILER_UNITS

Contains a summary of each code unit (function, procedure, trigger, or anonymous block) executed within a session.

In addition, DBMS_PROFILER defines a view, SYS.PLSQL_PROFILER_DATA, which contains a subset of the PLSQL PROFILER RAWDATA table.

Please note that a non-superuser may gather profiling information, but may not view that profiling information unless a superuser grants specific privileges on the profiling tables (stored in the SYS schema). This permits a non-privileged user to gather performance statistics without exposing information that the administrator may want to keep secret.

3.11.8.1 Querying the DBMS_PROFILER Tables and View

The following step-by-step example uses DBMS_PROFILER to retrieve performance information for procedures, functions, and triggers included in the sample data distributed with Advanced Server.

1. Open the EDB-PSQL command line, and establish a connection to the Advanced Server database. Use an EXEC statement to start the profiling session:

```
acctg=# EXEC dbms_profiler.start_profiler('profile list_emp');
EDB-SPL Procedure successfully completed
```

Note: (The call to start_profiler() includes a comment that DBMS_PROFILER associates with the profiler session).

2. Then call the list emp function:

```
acctg=# SELECT list_emp();
INFO: EMPNO ENAME
INFO: ----
INFO: 7369
            SMITH
INFO: 7499
             ALLEN
INFO: 7521
             WARD
INFO: 7566
             JONES
INFO: 7654
             MARTIN
INFO: 7698
             BLAKE
INFO: 7782
             CLARK
INFO: 7788
             SCOTT
INFO: 7839
              KING
INFO: 7844
              TURNER
INFO: 7876
              ADAMS
INFO: 7900
              JAMES
INFO: 7902
              FORD
INFO: 7934
              MILLER
list_emp
(1 row)
```

3. Stop the profiling session with a call to dbms profiler.stop profiler:

```
acctg=# EXEC dbms_profiler.stop_profiler;
EDB-SPL Procedure successfully completed
```

4. Start a new session with the dbms_profiler.start_profiler function (followed by a new comment):

```
acctg=# EXEC dbms_profiler.start_profiler('profile get_dept_name and
emp_sal_trig');
EDB-SPL Procedure successfully completed
```

5. Invoke the get_dept_name function:

```
acctg=# SELECT get_dept_name(10);
get_dept_name
-----
ACCOUNTING
(1 row)
```

6. Execute an UPDATE statement that causes a trigger to execute:

```
acctg=# UPDATE memp SET sal = 500 WHERE empno = 7902;
INFO: Updating employee 7902
INFO: ..Old salary: 3000.00
INFO: ..New salary: 500.00
INFO: ..Raise: -2500.00
INFO: User enterprisedb updated employee(s) on 04-FEB-14
UPDATE 1
```

7. Terminate the profiling session and flush the performance information to the profiling tables:

```
acctg=# EXEC dbms_profiler.stop_profiler;

EDB-SPL Procedure successfully completed
```

8. Now, query the plsql_profiler_runs table to view a list of the profiling sessions, arranged by runid:

9. Query the plsql_profiler_units table to view the amount of time consumed by each unit (each function, procedure, or trigger):

```
acctg=# SELECT * FROM plsql_profiler_units;
runid | unit_number | unit_type | unit_owner |
                                        unit_name
→unit_timestamp | total_time | spare1 | spare2
-----+-----
       16999 | FUNCTION | enterprisedb | list_emp()
         4 | |
        17002 | FUNCTION | enterprisedb | user_audit_trig()
   2 |
         17000 | FUNCTION | enterprisedb | get_dept_name(p_deptno numeric) | _
   2 |
         1 | 1
   2 |
         17004 | FUNCTION | enterprisedb | emp_sal_trig()
                                                        | __
              1 |
                      1
(4 rows)
```

10. Query the plsql_profiler_rawdata table to view a list of the wait event counters and wait event times:

```
acctq=# SELECT runid, sourcecode, func_oid, line_number, exec_count, tuples_returned,...
→time total FROM plsql profiler rawdata;
runid |
                                                   | func_oid |_
                        sourcecode
→line_number | exec_count | tuples_returned | time_total
-----+
                                                      16999 |
      1 | 0 | v_empno NUMERIC(4);
2 | 0 | v ename VARCHAR(10);
                            0 | 0
                                                      16999 |
                            0 | 0
       v_ename
                                                      16999 |...
                             0 | 0
       emp_cur CURSOR FOR
                                                      16999 |
        4 | 0 | 0 | 0
                                                      16999 |_
       SELECT empno, ename FROM memp ORDER BY empno;
        5 | 0 |
                     0 | 0
  1 | BEGIN
                                                      16999 |
      6 | 0 |
                            0 | 0
  1 |
      OPEN emp_cur;
                                                      16999 |
                            0 | 0
       7 | 0 |
      RAISE INFO 'EMPNO ENAME';
                                                      16999 |_
  1 |
       8 | 1 |
                             0 | 0.001621
       RAISE INFO '----
  1 |
                                                      16999 |
                1 |
       9 |
                              0 | 0.000301
       LOOP
  1 |
                                                      16999 |_
                1 |
                            0 | 4.6e-05
       10 |
       FETCH emp_cur INTO v_empno, v_ename;
                                                      16999 |
       11 | 0 | 0.001114
       EXIT WHEN NOT FOUND;
                                                      16999 |_
  1 |
                             0 | 0.000206
       12 | 15 |
       RAISE INFO '% %', v_empno, v_ename;
13 | 15 | 0 | 8.3e-0
                                                      16999 |
                            0 | 8.3e-05
       13 | 15 |
       END LOOP;
                                                      16999 |
       14 | 14 |
                            0 | 0.000773
       CLOSE emp_cur;
                                                      16999 |...
       15 | 0 |
                            0 |
       RETURN;
                                                      16999 |
       16 | 1 |
                            0 | 1e-05
  1 | END;
                                                      16999 |
      17 | 1 |
                            0 | 0
                                                      16999 |
       18 I
           0 |
                            0 |
                                     Ω
  2 | DECLARE
                                                      17002 |_
       1 |
       1 | 0 | v_action VARCHAR(24);
                             0 |
                                     Ω
  2 |
                                                      17002 |...
       2 | 0 |
                             0 |
                                     Ω
      v_text 1E
  2 |
                TEXT;
                                                      17002 |
                             0 |
                                      0
                                                      17002 |
  2 | BEGIN
        4 |
                0 |
                             0 |
                                     0
        IF TG_OP = 'INSERT' THEN
                                                      17002 |_
        5 | 0 |
                             0 |
        v_action := ' added employee(s) on ';
                                                      17002 |...
        6 | 1 |
                            0 | 0.000143
        ELSIF TG_OP = 'UPDATE' THEN
                                                      17002 |
  2 |
        7 | 0 |
                             0 |
         v_action := ' updated employee(s) on ';
                                                   | 17002 |
                0 | 0 |
```

	2	ELSIF TG_OP = 'DELETE' THEN	1	17002
\hookrightarrow	_	9 1 0 3.2e-05	1	17002
→	2			17002
	2	· · · · · · · · · · · · · · · · · · ·	I	17002 _
\hookrightarrow	_	10 0 0		1.0000
	2	•	ı	17002 _
\hookrightarrow	_	11 0 0 0		
	2			17002 _
\hookrightarrow		12 0 0		
	2	, = ,	I	17002 _
\hookrightarrow		13 0 0.000383		
	2	•		17002 _
\hookrightarrow		14 0 6.3e-05		
	2	END;		17002 _
\hookrightarrow		15 1 0 3.6e-05		
	2			17002 _
\hookrightarrow		16 0 0		
	2	DECLARE	1	17000 _
\hookrightarrow		1 0 0		_
	2	v_dname VARCHAR(14);		17000 _
\hookrightarrow		2 0 0 0		
	2	BEGIN	1	17000 _
\hookrightarrow		3 0 0	·	
	2		1	17000 _
\hookrightarrow		4 0 0 0	'	
	2		1	17000
\hookrightarrow	_	5 1 0 0.000647	'	17000 1
	2		1	17000
\hookrightarrow	_	6 1 0 2.6e-05	ı	17000 1
	2		1	17000
	_	7 0 0 0	ı	17000
\hookrightarrow	2		1	17000
	2	8 0 0 0	I	17000 [
\hookrightarrow	2			17000
	2	•	I	17000
\hookrightarrow	0	9 0 0 0		17000
	2	END;	I	17000 _
\hookrightarrow	_	10 0 0		1.0000
	2		ı	17000 _
\hookrightarrow		11 0 0		
	2	DECLARE	I	17004 _
\hookrightarrow	_	1 0 0 0		1700
	2	sal_diff NUMERIC(7,2);	I	17004 _
\hookrightarrow		2 0 0 0		
	2	BEGIN		17004 _
\hookrightarrow		3 0 0 0		
	2	·	1	17004 _
\hookrightarrow		4 0 0		
	2		1	17004
\hookrightarrow		5 0 8.4e-05		
	2		1	17004 _
\hookrightarrow		6 0 0		
	2	RETURN NEW;	1	17004 _
\hookrightarrow		7 0 0		
	2	END IF;	1	17004 _
\hookrightarrow		8 0 0		
	2	IF TG_OP = 'UPDATE' THEN	1	17004
\hookrightarrow		9 0 0		
	2	sal_diff := NEW.sal - OLD.sal;	1	17004 _
\hookrightarrow		10 1 0 0.000355		

```
RAISE INFO 'Updating employee %', OLD.empno;
                                                                        17004 |
         11 |
                1 |
                                       0.000177
                                                                        17004 |_
              RAISE INFO '..Old salary: %', OLD.sal;
   2 |
                      1 |
                                       0 |
         12 |
              RAISE INFO '.. New salary: %', NEW.sal;
   2 |
                                                                        17004 |...
         13 |
                                       0 | 3.1e-05
                     1 |
   2 |
              RAISE INFO '..Raise
                                    : %', sal_diff;
                                                                        17004 |...
                      1 |
                                       0 | 2.8e-05
   2 |
              RETURN NEW;
                                                                        17004 |
                                       0 | 2.7e-05
         15 I
                      1 |
          END IF;
                                                                        17004 |_
   2 |
                                       0 |
         16 |
                     1 |
                                              1e-06
          IF TG_OP = 'DELETE' THEN
   2 |
                                                                        17004 |...
                     0 |
                                       0 |
                                                                        17004 |_
   2 |
            RAISE INFO 'Deleting employee %', OLD.empno;
         18 | 0 |
                                       0 |
             RAISE INFO '..Old salary: %', OLD.sal;
   2 |
                                                                        17004 |
         19 | 0 |
                                       0 |
                                                    0
             RETURN OLD;
                                                                        17004 |_
   2 |
         20 |
                                       0 |
                                                    0
                      0 |
   2 |
         END IF;
                                                                        17004 |_
         21 |
                      0 |
                                       0 |
                                                                        17004 |_
   2 | END;
         22 |
                      0 |
                                       0 |
                                                    0
\hookrightarrow
                                                                        17004 |_
   2 |
                       0 |
                                       0 |
         23 |
                                                    0
(68 rows)
```

11. Query the plsql_profiler_data view to review a subset of the information found in plsql_profiler_rawdata table:

acctg=# SELECT * FROM plsql_profiler_data;										
runid unit_			total_occur	to	otal_time	r	min_time	1	max_time	spare1_
		+		+		-+-		+-		·
1	16999	+ 1	0	1	0		0	I	0	u
1	16999	 2	0	1	0	I	0	I	0	ں ا
1	16999	 3	0	1	0	I	0	I	0	ں ا
1	16999	 4	0		0	I	0	I	0	ں ا
1	16999	 5	0		0	I	0		0	ں
1	16999	 6 	0	I	0	I	0	I	0	u
1	16999	, 7 	0	1	0	I	0		0	ں ا
1	16999	 8 	1	1	0.001621	I	0.001621		0.001621	ں ا
1	16999 I	 9 	1	1	0.000301		0.000301	I	0.000301	ں ا
1	16999 I	 10	1	1	4.6e-05		4.6e-05	I	4.6e-05	ں
1	16999 	11 	1		0.001114		0.001114	I	0.001114	ں ا

\hookrightarrow	1	16999	12	15	0.000206	5e-06	7.8e-05	u
\hookrightarrow	1	16999	13	15	8.3e-05	2e-06	4.7e-05	u
←	1	16999	14	14	0.000773	4.7e-05	0.000116	u u
	1	16999	15	0	0	0	0	u
\hookrightarrow	1	16999		1	1e-05	1e-05	1e-05	ت
\hookrightarrow	1	16999	17	1	0	0	0	u
\hookrightarrow	1	16999	18	0	0	0	0	u
	2	17002	1	0	0	0	0	u u
	2	17002		0	0	0	0	u
\hookrightarrow	2	17002	3	0	0	0	0	u
↔	2	17002		0	0	0	0	u
\hookrightarrow	2	17002	5	0	0	0	0	u
	2	17002	6	1	0.000143	0.000143	0.000143	u
	2	17002	7	0	0	0	0	u
\hookrightarrow	2	17002		0	0	0	0	ш
\hookrightarrow	2	17002	9	1	3.2e-05	3.2e-05	3.2e-05	u
\hookrightarrow	2	17002		0	0	0	0	u
\hookrightarrow	2	17002	11	0	0	0	0	u
↔	2	17002	12	0	0	0	0	u
\hookrightarrow	2	17002	13	1	0.000383	0.000383	0.000383	u
↔	2	17002	14	1	6.3e-05	6.3e-05	6.3e-05	u
	2	17002		1	3.6e-05	3.6e-05	3.6e-05	u
↔	2	17002		0	0	0	0	٦
\hookrightarrow	2	17000		0	0	0	0	u
\hookrightarrow	2	17000		0	0	0	0	u
↔	2	17000	3	0	0	0	0	u
\hookrightarrow	2	17000	4	0	0	0	0	u
\hookrightarrow	2	17000	5	1	0.000647	0.000647	0.000647	u
\hookrightarrow	2	17000		1	2.6e-05	2.6e-05	2.6e-05	u u
\hookrightarrow								

	2	17000	7	0	0	0	0	u
	2	17000	 8	0	0	0	0	u
↔	2	17000	 9	0	0	0	0	u
↔	2	17000	10	0	0	0	0	ш
↔	2	17000	11	0	0	0	0	u
	2	17004	 1	0	0	0	0	٦
	2	17004	 2	0	0	0	0	٦
↔	2	17004	3	0	0	0	0	u
↔	2	17004	 4	0	0	0	0	J
	2	17004	 5	1	8.4e-05	8.4e-05	8.4e-05	u
	2	17004	 6	0	0	0	0	u u
	2	17004	 7	0	0	0	0	u
	2	17004	 8	0	0	0	0	٦
	2	17004	 9	0	0	0	0	u
	2	17004	 10	1	0.000355	0.000355	0.000355	u u
	2	17004	 11	1	0.000177	0.000177	0.000177	u u
	2	17004	 12	1	5.5e-05	5.5e-05	5.5e-05	u
	2	17004	 13	1	3.1e-05	3.1e-05	3.1e-05	u u
	2	17004	 14	1	2.8e-05	2.8e-05	2.8e-05	u
	2	17004	 15	1	2.7e-05	2.7e-05	2.7e-05	u u
↔	2	17004	16	1	1e-06	l 1e-06	le-06	u u
	2	17004	17	0	0	0	0	u
↔	2	17004	18	0	0	0	0	u u
←	2	17004		0	0	0	0	u
	2	17004	20	0	0	0	0	u
	2	17004		0	0	0	0	u
	2	17004	 22	0	0	0	0	٦
	2	17004	23	0	0	0	0	u
	rows)		<u> </u>					

3.11.8.2 DBMS_PROFILER - Reference

The Advanced Server installer creates the following tables and views that you can query to review PL/SQL performance profile information:

Table Name	Description
PLSQL_PROFILER_RUNS	Table containing information about all profiler runs, organized by runid.
PLSQL_PROFILER_UNITS	Table containing information about all profiler runs, organized by unit.
PLSQL_PROFILER_DATA	View containing performance statistics.
PLSQL_PROFILER_RAWDATA	Table containing the performance statistics and the extended performance
	statistics for DRITA counters and timers.

3.11.8.2.1 PLSQL_PROFILER_RUNS

The $\protect\operatorname{PROFILER}_{\protect\operatorname{RUNS}}$ table contains the following columns:

Column	Data Type	Description
runid	INTEGER (NOT NULL)	Unique identifier
		(plsql_profiler_runnumber)
related_run	INTEGER	The runid of a related run.
run_owner	TEXT	The role that recorded the profiling session.
run_date	TIMESTAMP WITHOUT	The profiling session start time.
	TIME ZONE	
run_comment	TEXT	User comments relevant to this run
run_total_time	BIGINT	Run time (in microseconds)
run_system_info	TEXT	Currently Unused
run_comment1	TEXT	Additional user comments
spare1	TEXT	Currently Unused

3.11.8.2.2 PLSQL_PROFILER_UNITS

The PLSQL_PROFILER_UNITS table contains the following columns:

Column	Data Type	Description
runid	INTEGER	Unique identifier
		(plsql_profiler_runnumber)
unit_number	OID	Corresponds to the OID of the row in the
		pg_proc table that identifies the unit.
unit_type	TEXT	PL/SQL function, procedure, trigger or
		anonymous block
unit_owner	TEXT	The identity of the role that owns the unit.
unit_name	TEXT	The complete signature of the unit.
unit_timestamp	TIMESTAMP WITHOUT	Creation date of the unit (currently NULL).
	TIME ZONE	
total_time	BIGINT	Time spent within the unit (in milliseconds)
spare1	BIGINT	Currently Unused
spare2	BIGINT	Currently Unused

3.11.8.2.3 PLSQL_PROFILER_DATA

The PLSQL_PROFILER_DATA view contains the following columns:

Column	Data Type	Description
runid	INTEGER	Unique identifier
		(plsql_profiler_runnumber)
unit_number	OID	Object ID of the unit that contains the cur-
		rent line.
line#	INTEGER	Current line number of the profiled work-
		load.
total_occur	BIGINT	The number of times that the line was exe-
		cuted.
total_time	DOUBLE PRECISION	The amount of time spent executing the line
		(in seconds)
min_time	DOUBLE PRECISION	The minimum execution time for the line.
max_time	DOUBLE PRECISION	The maximum execution time for the line.
spare1	NUMBER	Currently Unused
spare2	NUMBER	Currently Unused
spare3	NUMBER	Currently Unused
spare4	NUMBER	Currently Unused

3.11.8.2.4 PLSQL_PROFILER_RAWDATA

The PLSQL_PROFILER_RAWDATA table contains the statistical and wait events information that is found in the PLSQL_PROFILER_DATA view, as well as the performance statistics returned by the DRITA counters and timers.

Column	Data Type	Description
runid	INTEGER	The run identifier
		(plsql_profiler_runnumber).
sourcecode	TEXT	The individual line of profiled code.
func_oid	OID	Object ID of the unit that contains the cur-
		rent line.
line_number	INTEGER	Current line number of the profiled work-
		load.
exec_count	BIGINT	The number of times that the line was exe-
		cuted.
tuples_returned	BIGINT	Currently Unused
time_total	DOUBLE PRECISION	The amount of time spent executing the line
		(in seconds)
time_shortest	DOUBLE PRECISION	The minimum execution time for the line.
time_longest	DOUBLE PRECISION	The maximum execution time for the line.
num_scans	BIGINT	Currently Unused
tuples_fetched	BIGINT	Currently Unused
tuples_inserted	BIGINT	Currently Unused
tuples_updated	BIGINT	Currently Unused
tuples_deleted	BIGINT	Currently Unused
blocks_fetched	BIGINT	Currently Unused
blocks_hit	BIGINT	Currently Unused

Table 3.2 – continued from previous page

Column	Table 3.2 – continued	Description
	Data Type	
wal_write	BIGINT	A server has waited for a write to the write-
		ahead log buffer (expect this value to be
	-	high).
wal_flush	BIGINT	A server has waited for the write-ahead log
		to flush to disk.
wal_file_sync	BIGINT	A server has waited for the write-ahead
		log to sync to disk (related to the
		wal_sync_method parameter which, by de-
		fault, is 'fsync' - better performance can
		be gained by changing this parameter to
		open_sync).
db_file_read	BIGINT	A server has waited for the completion of a
		read (from disk).
db_file_write	BIGINT	A server has waited for the completion of a
		write (to disk).
db_file_sync	BIGINT	A server has waited for the operating system
		to flush all changes to disk.
db_file_extend	BIGINT	A server has waited for the operating system
		while adding a new page to the end of a file.
sql_parse	BIGINT	Currently Unused.
query_plan	BIGINT	A server has generated a query plan.
other_lwlock_acquire	BIGINT	A server has waited for other light-weight
		lock to protect data.
shared_plan_cache_coll	Bilohi NT	A server has waited for
<u> </u>		the completion of the
		shared_plan_cache_collision
		event.
shared_plan_cache_inse	rtBIGINT	A server has waited for the completion
		of the shared_plan_cache_insert
		event.
shared_plan_cache_hit	BIGINT	A server has waited for the completion of
		the shared_plan_cache_hit event.
shared_plan_cache_miss	BIGINT	A server has waited for the completion of
onaroa_pran_oaono_mro	2101111	the shared_plan_cache_miss event.
shared_plan_cache_lock	BIGINT	A server has waited for the completion of
21121 24_p 1411_240112_100K	2101111	the shared_plan_cache_lock event.
shared_plan_cache_busy	BIGINT	A server has waited for the completion of
onarea_pran_cache_busy	D.T.O.T.IA.T.	the shared_plan_cache_busy event.
shmemindexlock	BIGINT	A server has waited to find or allocate space
SIMEMITIGEXTOCK	חזמזמז	in the shared memory.
oidgenlock	BIGINT	A server has waited to allocate or assign an
oragenrock	חות דמות ו	OID.
videonlos!	DICINT	
xidgenlock	BIGINT	A server has waited to allocate or assign a
7 7	DIGINE	transaction ID.
procarraylock	BIGINT	A server has waited to get a snapshot or
		clearing a transaction ID at transaction end.
sinvalreadlock	BIGINT	A server has waited to retrieve or remove
		messages from shared invalidation queue.
sinvalwritelock	BIGINT	A server has waited to add a message to the
		shared invalidation queue.

Table 3.2 – continued from previous page

Column	Data Type	Description
walbufmappinglock	BIGINT	A server has waited to replace a page in
		WAL buffers.
walwritelock	BIGINT	A server has waited for WAL buffers to be
		written to disk.
controlfilelock	BIGINT	A server has waited to read or update the
		control file or creation of a new WAL file.
checkpointlock	BIGINT	A server has waited to perform a check-
-		point.
clogcontrollock	BIGINT	A server has waited to read or update the
		transaction status.
subtranscontrollock	BIGINT	A server has waited to read or update the
Subclaiiscolicioliock	DIGINI	sub-transaction information.
	DIGINE	
multixactgenlock	BIGINT	A server has waited to read or update the
		shared multixact state.
multixactoffsetcontrol	lædgint	A server has waited to read or update multi-
		xact offset mappings.
multixactmembercontrol	lædgint	A server has waited to read or update multi-
		xact member mappings.
relcacheinitlock	BIGINT	A server has waited to read or write the re-
		lation cache initialization file.
checkpointercommlock	BIGINT	A server has waited to manage the fsync re-
one on point of the original of the	2101111	quests.
twophasestatelock	BIGINT	A server has waited to read or update the
twophasestaterock	DIGINI	
	D T G T 1 T D	state of prepared transactions.
tablespacecreatelock	BIGINT	A server has waited to create or drop the ta-
		blespace.
btreevacuumlock	BIGINT	A server has waited to read or update the
		vacuum related information for a B-tree in-
		dex.
addinshmeminitlock	BIGINT	A server has waited to manage space alloca-
		tion in shared memory.
autovacuumlock	BIGINT	The autovacuum launcher waiting to read
		or update the current state of autovacuum
		workers.
autovacuumschedulelock	BIGINT	A server has waited to ensure that the table
aaco vacaamooneaarereen	DIGINI	selected for a vacuum still needs vacuum-
	DICINE	A server has waited to get the start location
syncscanlock	BIGINT	
		of a scan on a table for synchronized scans.
relationmappinglock	BIGINT	A server has waited to update the relation
		map file used to store catalog to file node
		mapping.
asyncctllock	BIGINT	A server has waited to read or update shared
		notification state.
asyncqueuelock	BIGINT	A server has waited to read or update the
		notification messages.
serializablexacthashlo	C.kB.T.G.T.N.T	A server has waited to retrieve or store in-
		formation about serializable transactions.
serializablefinishedli		A server has waited to access the list of fin-
serrarranterfillsliedff	D CHICKTUN I	
		ished serializable transactions.

Table 3.2 – continued from previous page

Column	Data Type	Description
serializablepredicatel	7.	A server has waited to perform an operation
1 1 1		on a list of locks held by serializable trans-
		actions.
oldserxidlock	BIGINT	A server has waited to read or record the
Oldberhidioek	DIGINI	conflicting serializable transactions.
syncreplock	BIGINT	A server has waited to read or update infor-
Syncreprock	DIGINI	mation about synchronous replicas.
1 1	DIGINE	
backgroundworkerlock	BIGINT	A server has waited to read or update the
		background worker state.
dynamicsharedmemorycon	t moligionak	A server has waited to read or update the
		dynamic shared memory state.
autofilelock	BIGINT	A server has waited to update the
		postgresql.auto.conf file.
replicationslotallocat	OBNI GOLOWI	A server has waited to allocate or free a
		replication slot.
replicationslotcontrol.	ORENT .	A server has waited to read or update repli-
		cation slot state.
committscontrollock	BIGINT	A server has waited to read or update trans-
		action commit timestamps.
committslock	BIGINT	A server has waited to read or update the last
		value set for the transaction timestamp.
replicationoriginlock	BIGINT	A server has waited to set up, drop, or use
repriederonorrymioen	BIGINI	replication origin.
multixacttruncationloc	RICINT	A server has waited to read or truncate mul-
multixacttluncationioc.	Y DIGINI	tixact information.
oldsnapshottimemaplock	BIGINT	A server has waited to read or update old
ordshapshoccimemaprock	DIGINI	_
1 1 1 1 1	DIGINE	snapshot control information.
backendrandomlock	BIGINT	A server has waited to generate a random
		number.
logicalrepworkerlock	BIGINT	A server has waited for the action on logical
		replication worker to finish.
clogtruncationlock	BIGINT	A server has waited to truncate the write-
		ahead log or waiting for write-ahead log
		truncation to finish.
bulkloadlock	BIGINT	A server has waited for the
		bulkloadlock to bulk upload the
		data.
edbresourcemanagerlock	BIGINT	The edbresourcemanagerlock pro-
-		vides detail about edb resource manager
		lock module.
wal_write_time	BIGINT	The amount of time that the server has
		waited for a wal_write wait event to
		write to the write-ahead log buffer (expect
		this value to be high).
wal_flush_time	BIGINT	The amount of time that the server has
		waited for a wal_flush wait event to
		write-ahead log to flush to disk.
		write arread tog to much to disk.

Table 3.2 – continued from previous page

Column	Data Type	Description
wal_file_sync_time	BIGINT	The amount of time that the server has
war_rrrc_sync_cime	DIGINI	waited for a wal_file_sync wait event
		to write-ahead log to sync to disk (related
		to the wal_sync_method parameter which,
		by default, is 'fsync' - better performance
		can be gained by changing this parameter to
11 6'1	DIGINE.	open_sync).
db_file_read_time	BIGINT	The amount of time that the server has
		waited for the db_file_read wait event
		for completion of a read (from disk).
db_file_write_time	BIGINT	The amount of time that the server has
		waited for the db_file_write wait
		event for completion of a write (to disk).
db_file_sync_time	BIGINT	The amount of time that the server has
		waited for the db_file_sync wait event
		to sync all changes to disk.
db_file_extend_time	BIGINT	The amount of time that the server has
		<pre>waited for the db_file_extend wait</pre>
		event while adding a new page to the end
		of a file.
sql_parse_time	BIGINT	The amount of time that the server has
-		waited for the sql_parse wait event to
		parse a SQL statement.
query_plan_time	BIGINT	The amount of time that the server has
· · · · · ·		waited for the query_plan wait event to
		compute the execution plan for a SQL state-
		ment.
other_lwlock_acquire_	timbelGINT	The amount of time that the
	31111	server has waited for the
		other_lwlock_acquire wait event to
		protect data.
shared_plan_cache_col.	I desitasti Ntti ma	The amount of time that the
bilarca_prail_cacile_cor	T T GATEST IT FORTILLE	server has waited for the
		shared_plan_cache_collision
		wait event.
shared plan cashe in-	→ ++D T+C'17•N×T	The amount of time that the
shared_plan_cache_ins	ST COTATIONS	
	DICINE	event.
shared_plan_cache_hit	T TEMBER T N.T.	The amount of time that the
		server has waited for the
		shared_plan_cache_hit wait
		event.
shared_plan_cache_mis	s_tBin@INT	The amount of time that the
		server has waited for the
		shared_plan_cache_miss wait
		event.

Table 3.2 – continued from previous page

Column	Table 3.2 – continued from pre	Description
shared_plan_cache_lock		The amount of time that the
<u> </u>		server has waited for the
		shared_plan_cache_lock wait
		event.
shared_plan_cache_busy	tBince NT	The amount of time that the
		server has waited for the
		shared_plan_cache_busy wait
		event.
shmemindexlock_time	BIGINT	The amount of time that the server has
		waited for the shmemindexlock wait
		event to find or allocate space in the shared
		memory.
oidgenlock_time	BIGINT	The amount of time that the server has
		waited for the oidgenlock wait event to
		allocate or assign an OID.
xidgenlock_time	BIGINT	The amount of time that the server has
		waited for xidgenlock wait event to al-
		locate or assign a transaction ID.
procarraylock_time	BIGINT	The amount of time that the server has
produra, roon_ormo	210111	waited for a procarraylock wait event
		to clear a transaction ID at transaction end.
sinvalreadlock_time	BIGINT	The amount of time that the server has
binvarieaaroon_erme	BIGINI	waited for a sinvalreadlock wait event
		to retrieve or remove messages from shared
		invalidation queue.
sinvalwritelock_time	BIGINT	The amount of time that the server has
		waited for a sinvalwritelock wait
		event to add a message to the shared invali-
		dation queue.
walbufmappinglock_time	BIGINT	The amount of time that the server has
		waited for a walbufmappinglock wait
		event to replace a page in WAL buffers.
walwritelock_time	BIGINT	The amount of time that the server has
····		waited for a walwritelock wait event to
		write the WAL buffers to disk.
controlfilelock_time	BIGINT	The amount of time that the server has
		waited for a controlfilelock wait
		event to read or update the control file or to
		create a new WAL file.
checkpointlock_time	BIGINT	The amount of time that the server has
<u> </u>		waited for a checkpointlock wait event
		to perform a checkpoint.
clogcontrollock_time	BIGINT	The amount of time that the server has
		waited for a clogcontrollock wait
		event to read or update the transaction sta-
		tus.
subtranscontrollock_time	neBIGINT	The amount of time that the server has
		waited for the subtranscontrollock
		wait event to read or update the sub-
		transaction information.
		Continued on post page

Table 3.2 – continued from previous page

Column	Data Type	d from previous page Description
multixactgenlock_time	BIGINT	The amount of time that the server has
multixactgeniock_time	DIGINI	waited for the multixactgenlock wait
		event to read or update the shared multixact
		state.
multixactoffsetcontrol	and crains	The amount of time that the
multixactoffsetControl	T OBSTREETINITING	
		multixactoffsetcontrollock
		wait event to read or update multixact offset
multixactmembercontrol	1 AND THE	mappings. The amount of time that the
multixactmembercontrol	T OBCING TRAITING	
		server has waited for the multixactmembercontrollock
		wait event to read or update multixact
	DIGINE	member mappings. The amount of time that the server has
relcacheinitlock_time	BIGINT	
		waited for the releacheinitlock wait
		event to read or write the relation cache initialization file.
	DIGINE	
checkpointercommlock_t	1 matel GINI	The amount of time that the server has waited for the
		server has waited for the checkpointercommlock wait event to
	DIGINE	manage the fsync requests.
twophasestatelock_time	BIGINT	The amount of time that the server has
		waited for the twophasestatelock
		wait event to read or update the state of pre-
		pared transactions.
tablespacecreatelock_t	imbelGINT	The amount of time that the
		server has waited for the
		tablespacecreatelock wait event to
		create or drop the tablespace.
btreevacuumlock_time	BIGINT	The amount of time that the server has
		waited for the btreevacuumlock wait
		event to read or update the vacuum related
		information for a B-tree index.
addinshmeminitlock_tim	e BIGINT	The amount of time that the server has
		waited for the addinshmeminitlock
		wait event to manage space allocation in
	DIGINE	shared memory.
autovacuumlock_time	BIGINT	The amount of time that the server has
		waited for the autovacuumlock wait
		event to read or update the current state of
		autovacuum workers.
autovacuumschedulelock	_tbimeINT	The amount of time that the
		server has waited for the
		autovacuumschedulelock wait
		event to ensure that the table selected for a
		vacuum still needs vacuuming.
syncscanlock_time	BIGINT	The amount of time that the server has
		waited for the syncscanlock wait event
		to get the start location of a scan on a table
		for synchronized scans.

Table 3.2 – continued from previous page

Column	Data Type	Description
relationmappinglock_t:		The amount of time that the server has
		waited for the relationmappinglock
		wait event to update the relation map file
		used to store catalog to file node mapping.
asyncctllock_time	BIGINT	The amount of time that the server has
asyncectiock_cime	BIGINI	waited for the asyncctllock wait event
		_
1 - 1 - 1 - 1	DIGINE	to read or update shared notification state.
asyncqueuelock_time	BIGINT	The amount of time that the server has
		waited for the asyncqueuelock wait
		event to read or update the notification mes-
		sages.
serializablexacthashlo	o¢k <u>rigim</u> er	The amount of time that the
		server has waited for the
		serializablexacthashlock wait
		event to retrieve or store information about
		serializable transactions.
serializablefinishedl	istBIMATtime	The amount of time that the
		server has waited for the
		serializablefinishedlistlock
		wait event to access the list of finished
		serializable transactions.
serializablepredicate	lockIGISVIlock_time	The amount of time that the
-		server has waited for the
		serializablepredicatelocklistloc
		wait event to perform an operation on a list
		of locks held by serializable transactions.
oldserxidlock_time	BIGINT	The amount of time that the server has
orabernrareen_erme	D101111	waited for the oldserxidlock wait
		event to read or record the conflicting seri-
		alizable transactions.
syncreplock_time	BIGINT	The amount of time that the server has
syncreprock_cime	BIGINI	waited for the syncreplock wait event
		to read or update information about syn-
		chronous replicas.
backgroundworkerlock_t	CIMBELGINT	The amount of time that the
		server has waited for the
		backgroundworkerlock wait event to
		read or update the background worker state.
dynamicsharedmemorycom	nt:BolGloWik_time	The amount of time that the
		server has waited for the
		dynamicsharedmemorycontrollock
		wait event to read or update the dynamic
		shared memory state.
autofilelock_time	BIGINT	The amount of time that the server has
		waited for the autofilelock wait event
		to update the postgresql.auto.conf
		file.

Table 3.2 – continued from previous page

Column Data 1	ype Description
replicationslotallocation 1800	The amount of time that the server has waited for the
	replicationslotallocationlock wait event to allocate or free a replication slot.
replicationslotcontroll@HGLM	The amount of time that the server has waited for the replicationslotcontrollock wait event to read or update replication slot state.
committscontrollock_timeBIGIN	waited for the committscontrollock wait event to read or update transaction commit timestamps.
committslock_time BIGIN	waited for the committslock wait event to read or update the last value set for the transaction timestamp.
replicationoriginlock_tiBneGIN	server has waited for the replicationoriginlock wait event to set up, drop, or use replication origin.
multixacttruncationlock <u>BriGna</u>	The amount of time that the server has waited for the multixacttruncationlock wait event to read or truncate multixact information.
oldsnapshottimemaplock thine	The amount of time that the server has waited for the oldsnapshottimemaplock wait event to read or update old snapshot control information.
backendrandomlock_time BIGIN	The amount of time that the server has waited for the backendrandomlock wait event to generate a random number.
logicalrepworkerlock_timeGIN	server has waited for the logicalrepworkerlock wait event for an action on logical replication worker to finish.
clogtruncationlock_time BIGIN	waited for the clogtruncationlock wait event to truncate the write-ahead log or waiting for write-ahead log truncation to finish.
bulkloadlock_time BIGIN	The amount of time that the server has waited for the bulkloadlock wait event to bulk upload the data.

Table 3.2 – continued from previous page

Column	Data Type	Descr	ription				
edbresourcemanagerlock	tBiInGEINT	The	amount	of	time	that	the
		server	has	wa	nited	for	the
		edbr	esourcer	mana	gerlo	ck	wait
		event.					
totalwaits	BIGINT	The to	tal number	of ev	ent wait	s.	
totalwaittime	BIGINT	The to	tal time sp	ent wa	aiting fo	r an eve	ent.

3.12 DBMS_RANDOM

The DBMS_RANDOM package provides a number of methods to generate random values. The procedures and functions available in the DBMS_RANDOM package are listed in the following table.

Function/Procedure	Return Type	Description
INITIALIZE(<val>)</val>	n/a	Initializes the DBMS_RANDOM package with the spec-
		ified seed <value>. Deprecated, but supported for</value>
		backward compatibility.
NORMAL()	NUMBER	Returns a random NUMBER.
RANDOM	INTEGER	Returns a random INTEGER with a value greater than
		or equal to -2^31 and less than 2^31. Deprecated, but
		supported for backward compatibility
SEED(<val>)</val>	n/a	Resets the seed with the specified <value>.</value>
SEED(<val>)</val>	n/a	Resets the seed with the specified <value>.</value>
STRING(<opt>, <len>)</len></opt>	VARCHAR2	Returns a random string.
TERMINATE	n/a	TERMINATE has no effect. Deprecated, but supported
		for backward compatibility.
VALUE	NUMBER	Returns a random number with a value greater than or
		equal to 0 and less than 1, with 38 digit precision.
VALUE(<low>, <high>)</high></low>	NUMBER	Returns a random number with a value greater than or
		equal to <low> and less than <high>.</high></low>

3.12.1 INITIALIZE

The INITIALIZE procedure initializes the DBMS_RANDOM package with a seed value. The signature is:

```
INITIALIZE(<val> IN INTEGER)
```

This procedure should be considered deprecated; it is included for backward compatibility only.

Parameter

<val>

<val> is the seed value used by the DBMS_RANDOM package algorithm.

Example

The following code snippet demonstrates a call to the INITIALIZE procedure that initializes the DBMS_RANDOM package with the seed value, 6475.

DBMS_RANDOM.INITIALIZE(6475);

3.12.2 NORMAL

The NORMAL function returns a random number of type NUMBER. The signature is:

<result> NUMBER NORMAL()

Parameter

<result>

<result> is a random value of type NUMBER.

Example

The following code snippet demonstrates a call to the NORMAL function:

```
x:= DBMS_RANDOM.NORMAL();
```

3.12.3 **RANDOM**

The RANDOM function returns a random INTEGER value that is greater than or equal to -2 ^31 and less than 2 ^31. The signature is:

```
<result> INTEGER RANDOM()
```

This function should be considered deprecated; it is included for backward compatibility only.

Parameter

<result>

<result> is a random value of type INTEGER.

Example

The following code snippet demonstrates a call to the RANDOM function. The call returns a random number:

```
x := DBMS_RANDOM.RANDOM();
```

3.12.4 SEED

The first form of the SEED procedure resets the seed value for the DBMS_RANDOM package with an INTEGER value. The SEED procedure is available in two forms; the signature of the first form is:

```
SEED(<val> IN INTEGER)
```

Parameter

<val>

<val> is the seed value used by the DBMS_RANDOM package algorithm.

Example

The following code snippet demonstrates a call to the SEED procedure; the call sets the seed value at 8495.

```
DBMS_RANDOM.SEED(8495);
```

3.12.5 SEED

The second form of the SEED procedure resets the seed value for the DBMS_RANDOM package with a string value. The SEED procedure is available in two forms; the signature of the second form is:

```
SEED(<val> IN VARCHAR2)
```

Parameter

<val>

<val> is the seed value used by the DBMS_RANDOM package algorithm.

Example

The following code snippet demonstrates a call to the SEED procedure; the call sets the seed value to abc123.

```
DBMS_RANDOM.SEED('abc123');
```

3.12.6 **STRING**

The STRING function returns a random VARCHAR2 string in a user-specified format. The signature of the STRING function is:

```
<result> VARCHAR2 STRING(<opt> IN CHAR, <len> IN NUMBER)
```

Parameters

<opt>

Formatting option for the returned string. coption> may be:

Option	Specifies Formatting Option
u or U	Uppercase alpha string
l or L	Lowercase alpha string
a or A	Mixed case string
x or X	Uppercase alpha-numeric string
p or P	Any printable characters

<len>

The length of the returned string.

<result>

<result> is a random value of type VARCHAR2.

Example

The following code snippet demonstrates a call to the STRING function; the call returns a random alpha-numeric character string that is 10 characters long.

```
x := DBMS_RANDOM.STRING('X', 10);
```

3.12.7 TERMINATE

The TERMINATE procedure has no effect. The signature is:

TERMINATE

The TERMINATE procedure should be considered deprecated; the procedure is supported for compatibility only.

3.12.8 **VALUE**

The VALUE function returns a random NUMBER that is greater than or equal to 0, and less than 1, with 38 digit precision. The VALUE function has two forms; the signature of the first form is:

```
<result> NUMBER VALUE()
```

Parameter

<result>

<result> is a random value of type NUMBER.

Example

The following code snippet demonstrates a call to the VALUE function. The call returns a random NUMBER:

```
x := DBMS_RANDOM.VALUE();
```

3.12.9 **VALUE**

The VALUE function returns a random NUMBER with a value that is between user-specified boundaries. The VALUE function has two forms; the signature of the second form is:

```
<result> NUMBER VALUE(<low> IN NUMBER, <high> IN NUMBER)
```

Parameters

<low>

<low> specifies the lower boundary for the random value. The random value may be equal to <low>.

<high>

<high> specifies the upper boundary for the random value; the random value will be less than <high>.

<result>

<result> is a random value of type NUMBER.

Example

The following code snippet demonstrates a call to the VALUE function. The call returns a random NUMBER with a value that is greater than or equal to 1 and less than 100:

```
x := DBMS_RANDOM.VALUE(1, 100);
```

3.13 DBMS_REDACT

The DBMS_REDACT package enables the redacting or masking of data returned by a query. The DBMS_REDACT package provides a procedure to create policies, alter policies, enable policies, disable policies, and drop policies. The procedures available in the DBMS_REDACT package are listed in the following table.

Function/Procedure	Function or Pro- cedure	Return Type	Description
ADD_POLICY(<object_schema>, <object_name>, <policy_name>, <policy_description>, <column_name>, <column_description>, <function_type>, <function_parameters>, <expression>, <enable>, <regexp_pattern>, <regexp_replace_string>,</regexp_replace_string></regexp_pattern></enable></expression></function_parameters></function_type></column_description></column_name></policy_description></policy_name></object_name></object_schema>	Procedure	n/a	Adds a data redaction policy.
<pre><regexp_position>, <regexp_occurence>, <regexp_match_parameter>, <custom_function_expression>)</custom_function_expression></regexp_match_parameter></regexp_occurence></regexp_position></pre>			
ALTER_POLICY(<object_schema>, <object_name>, <policy_name>, <action>, <column_name>, <function_type>, <function_parameters>, <expression>, <regexp_pattern>, <regexp_replace_string>, <regexp_position>, <regexp_occurence>, <regexp_match_parameter>, <policy_description>, <column_description>, <custom_function_expression>)</custom_function_expression></column_description></policy_description></regexp_match_parameter></regexp_occurence></regexp_position></regexp_replace_string></regexp_pattern></expression></function_parameters></function_type></column_name></action></policy_name></object_name></object_schema>	Procedure		Alters the existing data redaction policy.
<pre>DISABLE_POLICY(<object_schema>,</object_schema></pre>	Procedure		Disables the existing data redaction policy.
<pre>ENABLE_POLICY(<object_schema,> <object_name>, <policy_name>)</policy_name></object_name></object_schema,></pre>	Procedure		Enables a previously disabled data redaction policy.
<pre>DROP_POLICY(<object_schema>, <object_name>, <policy_name>)</policy_name></object_name></object_schema></pre>	Procedure	n/a	Drops a data redaction policy.
<pre>UPDATE_FULL_REDACTION_VALUES(<number_val>,</number_val></pre>	Procedure	n/a	Updates the full redaction default values for the specified datatype.

The data redaction feature uses the DBMS_REDACT package to define policies or conditions to redact data in a column based on the table column type and redaction type.

Note that you must be the owner of the table to create or change the data redaction policies. The users are exempted from all the column redaction policies, which the table owner or super-user is by default.

3.13.1 Using DBMS_REDACT Constants and Function Parameters

The DBMS_REDACT package uses the constants and redacts the column data by using any one of the data redaction types. The redaction type can be decided based on the function_type parameter of dbms_redact.add_policy and dbms_redact.alter_policy procedure. The below table highlights the values for function_type parameters of dbms_redact.add_policy and dbms_redact.alter_policy.

Constant	Type	Value	Description
NONE	INTEGER	0	No redaction, zero effect on the result of a query against
			table.
FULL	INTEGER	1	Full redaction, redacts full values of the column data.
PARTIAL	INTEGER	2	Partial redaction, redacts a portion of the column data.
RANDOM	INTEGER	4	Random redaction, each query results in a different ran-
			dom value depending on the datatype of the column.
REGEXP	INTEGER	5	Regular Expression based redaction, searches for the
			pattern of data to redact.
CUSTOM	INTEGER	99	Custom redaction type.

The following table shows the values for the action parameter of dbms_redact.alter_policy.

Constant	Type	Value	Description
ADD_COLUMN	INTEGER	1	Adds a column to the redaction policy.
DROP_COLUMN	INTEGER	2	Drops a column from the redaction policy.
MODIFY_EXPRESSION	INTEGER	3	Modifies the expression of a redaction pol-
			icy. The redaction is applied when the ex-
			pression evaluates to the BOOLEAN value to
			TRUE.
MODIFY_COLUMN	INTEGER	4	Modifies a column in the redaction policy to
			change the redaction function type or func-
			tion parameter.
SET_POLICY_DESCRIPTION	INTEGER	5	Sets the redaction policy description.
SET_COLUMN_DESCRIPTION	INTEGER	6	Sets a description for the redaction per-
			formed on the column.

The partial data redaction enables you to redact only a portion of the column data. To use partial redaction, you must set the <code>dbms_redact.add_policy</code> procedure function_type parameter to <code>dbms_redact.partial</code> and use the function_parameters parameter to specify the partial redaction behavior.

The data redaction feature provides a predefined format to configure policies that use the following datatype:

- Character
- Number
- Datetime

The following table highlights the format descriptor for partial redaction with respect to datatype. The example described below shows how to perform a redaction for a string datatype (in this scenario, a Social Security Number (SSN)), a Number datatype, and a DATE datatype.

Datatype	Format Descriptor	Description	Examples
Character	REDACT_PARTIAL_INPUT_FORMAT	Specifies the in-	Consider 'VVVFVVFVVVV,
		put format. Enter	VVV-VV-VVVV, X, 1, 5' for
		∨ for each charac-	masking first 5 digits of SSN
		ter from the input	strings such as 123-45-6789,
		string to be possi-	adding hyphen to format it
		bly redacted. En-	and thereby resulting in strings
		ter F for each char-	such as XXX-6789. The
		acter from the in-	field value VVVFVVFVVVV for
		put string that can	matching SSN strings such as
		be considered as	123-45-6789.
		a separator such	
		as blank spaces or	
	REDACT_PARTIAL_OUTPUT_FORMAT	hyphens. Specifies the out-	The field value VVV-VV-VVVV
	REDACI_FARITAL_OUTFUI_FORMAI	put format. Enter	can be used to redact SSN
		V for each charac-	strings into XXX-XX-6789
		ter from the input	where X comes from
		string to be possi-	REDACT_PARTIAL_MASKCHAR
		bly redacted. Re-	field.
		place each F char-	
		acter from the in-	
		put format with a	
		character such as	
		a hyphen or any	
		other separator.	
	REDACT_PARTIAL_MASKCHAR	Specifies the char-	The value X for redacting SSN
		acter to be used for	strings into XXX-XX-6789.
	DEDICE DIDELL MICHEDON	redaction.	Til. 1 Committee
	REDACT_PARTIAL_MASKFROM	Specifies which V	The value 1 for redacting
		within the input format from which	SSN strings starting at the
		to start the redac-	first V of the input format of VVVFVVFVVVVVV into strings such
		tion.	as XXX-XX-6789.
	REDACT_PARTIAL_MASKTO	Specifies which V	The value 5 for redacting SSN
	1	within the input	strings up to and including the
		format at which to	fifth \vee within the input format of
		end the redaction.	VVVFVVFVVVV into strings such
			as XXX-XX-6789.
Number	REDACT_PARTIAL_MASKCHAR	Specifies the char-	'9, 1, 5' for redacting the
		acter to be dis-	first five digits of the Social Se-
		played in the range	curity Number 123456789 into
		between 0 and 9.	999996789.
	REDACT_PARTIAL_MASKFROM	Specifies the start	
		digit position for	
		redaction.	
	REDACT_PARTIAL_MASKTO	Specifies the end	
		digit position for	
		redaction.	

Table 3.3 – continued from previous page

	T	a nom previous page	
Datetime	REDACT_PARTIAL_DATE_MONTH	'm' redacts the	m3 displays as March.
		month. To mask	
		a specific month,	
		specify 'm#'	
		where # indicates	
		the month speci-	
		fied by its number	
		between 1 and 12.	
	REDACT_PARTIAL_DATE_DAY	'd' redacts the	d3 displays as 03.
		day of the month.	
		To mask with a	
		day of the month,	
		append 1-31 to a	
		lowercase d.	
	REDACT_PARTIAL_DATE_YEAR	'y' redacts the	y1960 displays as 60.
		year. To mask	
		with a year, ap-	
		pend 1-9999 to a	
		lowercase y.	
	REDACT_PARTIAL_DATE_HOUR	'h' redacts the	h18 displays as 18.
		hour. To mask	
		with an hour, ap-	
		pend 0-23 to a	
		lowercase h.	
	REDACT_PARTIAL_DATE_MINUTE	'm' redacts the	m20 displays as 20.
		minute. To mask	
		with a minute, ap-	
		pend 0-59 to a	
		lowercase m.	
	REDACT_PARTIAL_DATE_SECOND	's' redacts the	s40 displays as 40.
		second. To mask	
		with a second, ap-	
		pend 0-59 to a	
		lowercase s.	

The following table represents function_parameters values that can be used in partial redaction.

Function Parameter	Data Type	Value	Description
REDACT_US_SSN_F5	VARCHAR2	'VVVFVVFVVVV,	Redacts the first 5 numbers
		<pre>VVV-VV-VVVV, X, 1, 5'</pre>	of SSN.
			Example: The number
			123-45-6789 becomes
			XXX-XX-6789.
REDACT_US_SSN_L4	VARCHAR2	'VVVFVVFVVVV,	Redacts the last 4 numbers
		<pre>VVV-VV-VVVV, X, 6, 9'</pre>	of SSN.
			Example: The number
			123-45-6789 becomes
			123-45-XXXX.

Table 3.4 – continued from previous page

Idult		ued from previous page	
REDACT_US_SSN_ENTIRE	VARCHAR2	'VVVFVVFVVVV,	Redacts the entire SSN.
		VVV-VV-VVVV,X,1,9'	Example: The number
			123-45-6789 becomes
			XXX-XX-XXXX.
REDACT_NUM_US_SSN_F5	VARCHAR2	19 1 51	Redacts the first 5 numbers
KEDACI_NOFI_05_55N_F5	VARCHARZ	9,1,3	of SSN when the column is
			a number datatype.
			Example: The number
			123456789 becomes
			999996789.
REDACT_NUM_US_SSN_L4	VARCHAR2	'9,6,9'	Redacts the last four num-
			bers of SSN when the col-
			umn is a number datatype.
			Example: The number
			123456789 becomes
			123459999.
REDACT_NUM_US_SSN_ENTIRE	VARCHAR2	9,1,9'	Redacts the entire SSN
			when the column is a num-
			ber datatype.
			Example: The number
			123456789 becomes
			999999999.
REDACT_ZIP_CODE	VARCHAR2	'VVVVV, VVVVV, X, 1,	Redacts a 5 digit zip code.
		5 '	Example: 12345 becomes
			XXXXX.
REDACT_NUM_ZIP_CODE	VARCHAR2	'9,1,5'	Redacts a 5 digit zip code
1001_101_111_0011	VIIICOIIIICE	3,1,0	when the column is a num-
			ber datatype.
			Example: 12345 becomes
			99999.
REDACT_CCN16_F12	VARCHAR2	'VVVVFVVVVFVVVVFVVVV	
VEDUCT CONTO LIS	VARCHARZ		
		VVVV-VVVV-VVVV-VVVV,	1 2
		*,1,12'	only 4 digits.
			Example: 1234 5678
			9000 2358 becomes
			****-*****-2358.
REDACT_DATE_MILLENNIUM	VARCHAR2	'm1d1y2000'	Redacts a date that is in the
			DD-MM-YY format.
			Example: Redacts all date
			to 01-JAN-2000.
REDACT_DATE_EPOCH	VARCHAR2	'm1d1y1970'	Redacts all dates to
INDACI_DATE_EFOCII	VAICHARZ	mitary roll	01-JAN-70.
REDACT_AMEX_CCN_FORMATTED	VARCHAR2	• \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \	Redacts the Amercian Ex-
NEDACI_AMEA_CCN_FORMATIED	VARCHARZ	'VVVVFVVVVVVFVVVVV,	press credit card number
		VVVV-VVVVVV-VVVVV,	-
		*,1,10'	and replaces the digit with *
			except for the last 5 digits.
			Example: The credit card
			number 1234 567890
			34500 becomes ****
			***** 34500.
1	1		Continued on next need

Table 3.4 – continued from previous page

REDACT_AMEX_CCN_NUMBER		'0,1,10'	Redacts the Amercian Ex-
REDACI_AMEX_CCN_NUMBER	VARCHARZ	0,1,10	
			press credit card number
			and replaces the digit with 0
			except the last 5 digits.
			Example: The credit card
			number 1234 567890
			34500 becomes 0000
			000000 34500.
REDACT_SIN_FORMATTED	VARCHAR2	'VVVFVVVFVVV,	Redacts the Social Insur-
		VVV-VVV-VVV,*,1,6'	ance Number by replacing
			the first 6 digits by * Exam-
			ple: 123–456–789 be-
			comes $***-***-789$.
REDACT_SIN_NUMBER	VARCHAR2	'9,1,6'	Redacts the Social Insur-
			ance Number by replacing
			the first 6 digits by 9.
			Example: 123456789
			becomes 999999789.
REDACT_SIN_UNFORMATTED	VARCHAR2	'\\\\\	Redacts the Social Insur-
		VVVVVVVV, *, 1, 6'	ance Number by replacing
			the first 6 digits by *.
			Example: 123456789
			becomes *****789.
REDACT_CCN_FORMATTED	VARCHAR2	'VVVVFVVVVFVVVVFVVVV	
REDACI_CCN_FORMATIED	VARCHARZ	VVVV-VVVV-VVVV-VVVV,	ber by * and displays only 4
		1	
		*,1,12'	digits.
			Example: The
			credit card number
			1234-5678-9000-4671
			becomes
			****-****-4671.
REDACT_CCN_NUMBER	VARCHAR2	'9,1,12'	Redacts a credit card num-
			ber by 0 except the last 4
			digits.
			Example: The
			credit card number
			1234567890004671
			becomes
			0000000000004671.
REDACT_NA_PHONE_FORMATTED			
	VARCHAR2	'VVVFVVVFVVVV,	Redacts the North Amer-
	VARCHAR2	VVVFVVVFVVVV, VVV-VVV-VVVV,X,4,	Redacts the North American phone number by X
	VARCHAR2		
NBBNe1_IWL_I NOWB_I GRUITIEB	VARCHAR2	VVV-VVV-VVVV,X,4,	ican phone number by X
NBBNC1_W_1NOWB_1OWINT1BB	VARCHAR2	VVV-VVV-VVVV,X,4,	ican phone number by X leaving the area code.
NBBNC1_W_TNOWB_TOWNTTBB	VARCHAR2	VVV-VVV-VVVV,X,4,	ican phone number by X leaving the area code. Example:
		VVV-VVV-VVVV,X,4,	ican phone number by X leaving the area code. Example: 123-456-7890 becomes
REDACT_NA_PHONE_NUMBER	VARCHAR2	VVV-VVV-VVVV,X,4,	ican phone number by X leaving the area code. Example: 123-456-7890 becomes 123-XXX-XXXX. Redacts the North Amer-
		VVV-VVV-VVVV,X,4,	ican phone number by X leaving the area code. Example: 123-456-7890 becomes 123-XXX-XXXX. Redacts the North American phone number by 0
		VVV-VVV-VVVV,X,4,	ican phone number by X leaving the area code. Example: 123-456-7890 becomes 123-XXX-XXXX. Redacts the North American phone number by 0 leaving the area code.
		VVV-VVV-VVVV,X,4,	ican phone number by X leaving the area code. Example: 123-456-7890 becomes 123-XXX-XXXX. Redacts the North American phone number by 0

Table 3.4 – continued from previous page

			r
REDACT_NA_PHONE_UNFORMATTED	VARCHAR2	'\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\	Redacts the North Amer-
		<pre>VVVVVVVVVV, X, 4, 10'</pre>	ican phone number by X
			leaving the area code.
			Example: 1234567890
			becomes 123XXXXXXX.
REDACT_UK_NIN_FORMATTED	VARCHAR2	'VVFVVFVVFVVFV,VV	Redacts the UK National
		VV VV VV V,X,3,8'	Insurance Number by X but
			leaving the alphabetic char-
			acters.
			Example: NY 22 01 34
			D becomes NY XX XX XX
			D.
REDACT_UK_NIN_UNFORMATTED	VARCHAR2	'\\\\	Redacts the UK National
		<pre>VVVVVVVV, X, 3, 8'</pre>	Insurance Number by X but
			leaving the alphabetic char-
			acters.
			Example: NY220134D
			becomes NYXXXXXXD.

A regular expression-based redaction searches for patterns of data to redact. The regexp_pattern search the values in order for the regexp_replace_string to change the value. The following table illustrates the regexp_pattern values that you can use during REGEXP based redaction.

Data Type	Value
VARCHAR2	'(dddddd)(ddd*)(dddd)'

Table 3.5 – continued from previous page

Table 3.5 – continued from previous page			
Function Parameter and Descrip-	Data Type	Value	
tion			
	VARCHAR2	'd'	
RE_PATTERN_ANY_DIGITs:	7711101171112		
Searches for any digit and replaces the			
identified pattern with the characters			
specified by the following values of the			
regexp_replace_string parameter.			
regexp_replace_string=>			
RE_REDACT_WITH_SINGLE_X			
(replaces any matched digit with the X			
character).			
regexp_replace_string=>			
RE_REDACT_WITH_SINGLE_1			
(replaces any matched digit with the 1			
character).			
,			
	VARCHAR2	'((ddd)lddd)-(ddd)'	
RE_PATTERN_US_PHONE:		((223),000) (000)	
Searches for the U.S phone number and			
-			
replaces the identified pattern with the			
characters specified by the			
regexp_replace_string parameter.			
regexp_replace_string=>			
RE_REDACT_US_PHONE_L7			
(searches the phone number and then			
replaces the last 7 digits).			
	VARCHAR2	'([A-Za-z0-9%+-]+)@([A-Za-z0-9]+.[A-Za-	
RE_PATTERN_EMAIL_ADDRESS:	7 IKCHAKZ	$([A-2a-20-3/(T-]+) \otimes ([A-2a-20-3]+.[A-2a-20-$	
Searches for the email address and		LJ(2,7)	
replaces the identified pattern with the			
characters specified by the following			
values of the regexp_replace_string			
parameter.			
regexp_replace_string=>			
RE_REDACT_EMAIL_NAME			
(finds the email address and redacts the			
email username).			
·			
regexp_replace_string=>			
RE_REDACT_EMAIL_DOMAIN			
(finds the email address and redacts the			
email domain).			
regexp_replace_string=>			
RE_REDACT_EMAIL_ENTIRE			
(finds the email address and redacts the			
entire email address).			

Table 3.5 – continued from previous page

Function Parameter and Descrip- Data Type Value			
tion	-		
RE_PATTERN_IP_ADDRESS: Searches for an IP address and replaces the identified pattern with the characters specified by the regexp_replace_string parameter. The regexp_replace_string parameter to be used is RE_REDACT_IP_L3 that replaces the last section of an IP address with 999 and indicates it is redacted.	VARCHAR2	'(d{1,3}.d{1,3}.d{1,3}).d{1,3}'	
RE_PATTERN_AMEX_CCN: Searches for the American Express credit card number. The regexp_replace_string parameter to be used is RE_REDACT_AMEX_CCN that redacts all of the digits except the last 5.	VARCHAR2	'.*(ddddd)\$'	
RE_PATTERN_CCN: Searches for the credit card number other than American Express credit cards. The regexp_replace_string parameter to be used is RE_REDACT_CCN that redacts all of the digits except the last 4.	VARCHAR2	'.*(dddd)\$'	
RE_PATTERN_US_SSN: Searches the SSN number and replaces the identified pattern with the characters specified by the regexp_replace_string parameter. '1-XXX-XXXX' or 'XXX-XXX-3' will return 123-XXX-XXXX or XXX-XXX-6789 for the value '123-45-6789' respectively.	VARCHAR2	'(ddd)-(dd)-(dddd)'	

Table 3.5 – continued from previous page

Function Parameter and Descrip-	Data Type	Value
	Data Type	Value
tion		
	VARCHAR2	'1XXXXXX3'
RE_REDACT_CC_MIDDLE_DIGITS	:	
Redacts the middle digits of a credit		
card number according to the		
regexp_pattern parameter with the		
RE_PATTERN_CC_L6_T4 format and		
replaces each redacted character with		
an X.		
Example: The credit card number 1234		
5678 9000 2490 becomes 1234 56XX		
XXXX 2490.		
AAAA 2490.		
	WAD CHADA	(37)
	VARCHAR2	'X'
RE_REDACT_WITH_SINGLE_X:		
Replaces the data with a single X		
character for each matching pattern as		
specified by setting		
Specimen of securing		

The below table illustrates the regexp_replace_string values that you can use during REGEXP based redaction.

Function Parameter	Data Type	Value	Description
RE_REDACT_CC_MIDDLE_DIGITS	VARCHAR2	'1XXXXXX3'	Redacts the middle digits of a
			credit card number according to the
			regexp_pattern parameter with the
			RE_PATTERN_CC_L6_T4 format
			and replaces each redacted charac-
			ter with an X.
			Example: The credit card num-
			ber 1234 5678 9000 2490 becomes
			1234 56XX XXXX 2490.
RE_REDACT_WITH_SINGLE_X	VARCHAR2	'X'	Replaces the data with a single
			X character for each matching
			pattern as specified by setting the
			regexp_pattern parameter with
			the RE_PATTERN_ANY_DIGIT
			format.
			Example: The credit card num-
			ber 1234 5678 9000 2490 becomes
			XXXX XXXX XXXX XXXX.

Table 3.6 – continued from previous page

		i iroiii previous pa	<u> </u>
RE_REDACT_WITH_SINGLE_1	VARCHAR2		Replaces the data with a single 1 digit for each of the data digits as specified by setting the regexp_pattern parameter with the RE_PATTERN_ANY_DIGIT format. Example: The credit card number 1234 5678 9000 2490 becomes 1111 1111 1111 1111.
RE_REDACT_US_PHONE_L7	VARCHAR2		Redacts the last 7 digits of U.S
		XXXX	phone number according to the regexp_pattern parameter with the RE_PATTERN_US_PHONE format and replaces each redacted character with an X. Example: The phone number 123-444-5900 becomes 123-XXX-
			XXXX.
RE_REDACT_EMAIL_NAME	VARCHAR2		Redacts the email name according to the reg- exp_pattern parameter with the RE_PATTERN_EMAIL_ADDRESS format and replaces the email user- name with the four x characters. Example: The email address sjohn@example.com becomes xxxx@example.com.
RE_REDACT_EMAIL_DOMAIN	VARCHAR2	'1@xxxxx.com'	Redacts the email domain
			name according to the reg- exp_pattern parameter with the RE_PATTERN_EMAIL_ADDRESS format and replaces the domain with the five x characters. Example: The email address sjohn@example.com becomes sjohn@xxxxx.com.
RE_REDACT_EMAIL_ENTIRE	VARCHAR2	'xxxx@xxxxx.coi	nRedacts the entire email ad-
			dress according to the reg- exp_pattern parameter with the RE_PATTERN_EMAIL_ADDRESS format and replaces the email ad- dress with the x characters. Example: The email address sjohn@example.com becomes xxxx@xxxxx.com.

Table 3.6 – continued from previous page

/ARCHAR2	'1.999'	Redacts the last 3 digits of an
		IP address according to the reg-
		exp_pattern parameter with the
		RE_PATTERN_IP_ADDRESS for-
		mat.
		Example: The IP address
		172.0.1.258 becomes 172.0.1.999,
		which is an invalid IP address.
ARCHAR2	·*****1 [']	Redacts the first 10 digits of an
		American Express credit card
		number according to the reg-
		exp_pattern parameter with the
		RE_PATTERN_AMEX_CCN for-
		mat. Example: 123456789062816
		becomes ********62816.
ARCHAR2	·*******1 [,]	Redacts the first 12 digits of a credit
		card number as specified by the
		regexp_pattern parameter with the
		RE_PATTERN_CCN format.
		Example: 8749012678345671 be-
		comes **********5671.
7	ARCHAR2	ARCHARZ

The following tables show the $regexp_position$ value and $regexp_occurrence$ values that you can use during REGEXP based redaction.

Function Parameter	Data Type	Value	Description
RE_BEGINNING	INTEGER	1	Specifies the position of a character where search must
			begin. By default, the value is 1 that indicates the search
			begins at the first character of source_char.

Function Parameter	Data Type	Value	Description
RE_ALL	INTEGER	0	Specifies the replacement occurrence of a substring. If
			the value is 0, then the replacement of each matching
			substring occurs.
RE_FIRST	INTEGER	1	Specifies the replacement occurrence of a substring. If
			the value is 1, then the replacement of the first matching
			substring occurs.

The following table shows the $regexp_match_parameter$ values that you can use during REGEXP based redaction which lets you change the default matching behavior of a function.

Function Parameter	Data Type	Value	Description
RE_CASE_SENSITIVE	VARCHAR2	'c'	Specifies the case-sensitive matching.
RE_CASE_INSENSITIVE	VARCHAR2	ʻi'	Specifies the case-insensitive matching.
RE_MULTIPLE_LINES	VARCHAR2	'm'	Treats the source string as multiple lines but
			if you omit this parameter, then it indicates
			as a single line.
RE_NEWLINE_WILDCARD	VARCHAR2	'n'	Specifies the period (.), but if you omit this
			parameter, then the period does not match
			the newline character.
RE_IGNORE_WHITESPACE	VARCHAR2	'x'	Ignores the whitespace characters.

Note: If you create a redaction policy based on a numeric type column, then make sure that the result after redaction is a number and accordingly set the replacement string to avoid runtime errors.

Note: If you create a redaction policy based on a character type column, then make sure that a length of the result after redaction is compatible with the column type and accordingly set the replacement string to avoid runtime errors.

3.13.2 ADD POLICY

The add_policy procedure creates a new data redaction policy for a table.

```
PROCEDURE add_policy (
object_schema
                                        IN VARCHAR2 DEFAULT NULL,
object name
                                        IN VARCHAR2,
policy_name
                                        IN VARCHAR2,
policy_description
                                        IN VARCHAR2 DEFAULT NULL,
column_name
                                        IN VARCHAR2 DEFAULT NULL,
column_description IN VARCHAR2 DEFAULT NULL,
function_type IN INTEGER DEFAULT DBMS_REDACT.FULL,
function_parameters IN VARCHAR2 DEFAULT NULL,
expression IN VARCHAR2,
enable
                                        IN BOOLEAN DEFAULT TRUE,
                                        IN VARCHAR2 DEFAULT NULL,
regexp_pattern
regexp_replace_string IN VARCHAR2 DEFAULT NULL,
regexp_position IN INTEGER DEFAULT DBMS_REDACT.RE_BEGINNING,
regexp_occurrence IN INTEGER DEFAULT DBMS_REDACT.RE_ALL,
regexp_match_parameter IN VARCHAR2 DEFAULT NULL, custom_function_expression IN VARCHAR2 DEFAULT NULL
```

Parameters

```
<object_schema>
```

Specifies the name of the schema in which the object resides and on which the data redaction policy will be applied. If you specify NULL then the given object is searched by the order specified by search_path setting.

```
<object_name>
```

Name of the table on which the data redaction policy is created.

```
<policy_name>
```

Name of the policy to be added. Ensure that the policy_name is unique for the table on which the policy is created.

```
<policy_description>
```

Specify the description of a redaction policy.

```
<column_name>
```

Name of the column to which the redaction policy applies. To redact more than one column, use the alter_policy procedure to add additional columns.

```
<column_description>
```

Description of the column to be redacted. The column_description is not supported, but if you specify the description for a column then, you will get a warning message.

```
<function_type>
```

The type of redaction function to be used. The possible values are NONE, FULL, PARTIAL, RANDOM, REGEXP, and CUSTOM.

```
<function_parameters>
```

Specifies the function parameters for the partition redaction and is applicable only for partial redaction.

```
<expression>
```

Specifies the Boolean expression for the table and determines how the policy is to be applied. The redaction occurs if this policy expression is evaluated to TRUE.

```
<enable>
```

When set to TRUE, the policy is enabled upon creation. The default is set as TRUE. When set to FALSE, the policy is disabled but the policy can be enabled by calling the enable policy procedure.

```
<regexp_pattern>
```

Specifies the regular expression pattern to redact data. If the regexp_pattern does not match, then the NULL value is returned.

```
<regexp_replace_string>
```

Specifies the replacement string value.

```
<regexp_position>
```

Specifies the position of a character where search must begin. By default, the function parameter is RE BEGINNING.

```
<regexp_occurrence>
```

Specifies the replacement occurrence of a substring. If the constant is RE_ALL, then the replacement of each matching substring occurs. If the constant is RE_FIRST, then the replacement of the first matching substring occurs.

```
<regexp_match_parameter>
```

Changes the default matching behavior of a function. The possible regexp_match_parameter constants can be `RE_CASE_SENSITIVE', `RE_CASE_INSENSITIVE', `RE_MULTIPLE_LINES', `RE_NEWLINE_WILDCARD', `RE_IGNORE_WHITESPACE'.

Note: For more information on constants, function_parameters, or regexp (regular expressions) see, Using DBMS_REDACT Constants and Function Parameters.

```
<custom_function_expression>
```

The custom_function_expression is applicable only for the CUSTOM redaction type. The custom_function_expression is a function expression that is, schema-qualified function with a parameter such as schema_name.function_name (argument1, ...)that allows a user to use their redaction logic to redact the column data.

Example

The following example illustrates how to create a policy and use full redaction for values in the payment_details_tab table customer id column.

Redacted Result:

3.13.3 ALTER POLICY

The alter_policy procedure alters or modifies an existing data redaction policy for a table.

```
PROCEDURE alter_policy (
 object_schema
                                                                                                                                                      IN VARCHAR2 DEFAULT NULL,
 object_name
                                                                                                                                                      IN VARCHAR2,
 policy_name
                                                                                                                                                      IN VARCHAR2,
                                                                                               IN INTEGER DEFAULT DBMS_REDACT.ADD_COLUMN,
 action
 column_name
                                                                                                                                                     IN VARCHAR2 DEFAULT NULL,
                                                                                                                                                      IN INTEGER DEFAULT DBMS_REDACT.FULL,
 function_type
function_type

function_parameters

in VARCHAR2 DEFAULT NUL
expression

in VARCHAR2 DEFAULT
regexp_pattern

in VARCHAR2 DEFAULT
in VARCHAR2 DEFAUL
                                                                                                                          IN VARCHAR2 DEFAULT NULL,
                                                                                                                                                    IN VARCHAR2 DEFAULT NULL,
                                                                                                                                                 IN VARCHAR2 DEFAULT NULL,
 regexp_position IN INTEGER DEFAULT DBMS_REDACT.RE_BEGINNING,
 regexp_occurrence IN INTEGER DEFAULT DBMS_REDACT.RE_ALL,
 regexp_match_parameter IN VARCHAR2 DEFAULT NULL,
policy_description
column_description
                                                                                                                               IN VARCHAR2 DEFAULT NULL,
                                                                                                                                 IN VARCHAR2 DEFAULT NULL,
 custom_function_expression IN VARCHAR2 DEFAULT NULL
```

Parameters

```
<object_schema>
```

Specifies the name of the schema in which the object resides and on which the data redaction policy will be altered. If you specify NULL then the given object is searched by the order specified by search_path setting.

```
<object_name>
```

Name of the table to which to alter a data redaction policy.

```
<policy_name>
```

Name of the policy to be altered.

```
<action>
```

The action to perform. For more information about action parameters see, "DBMS_REDACT Constants and Function Parameters".

```
<column_name>
```

Name of the column to which the redaction policy applies.

```
<function_type>
```

The type of redaction function to be used. The possible values are NONE, FULL, PARTIAL, RANDOM, REGEXP, and CUSTOM.

```
<function_parameters>
```

Specifies the function parameters for the redaction function.

```
<expression>
```

Specifies the Boolean expression for the table and determines how the policy is to be applied. The redaction occurs if this policy expression is evaluated to TRUE.

```
<regexp_pattern>
```

Enables the use of regular expressions to redact data. If the regexp_pattern does not match the data, then the NULL value is returned.

```
<regexp_replace_string>
```

Specifies the replacement string value.

```
<regexp_position>
```

Specifies the position of a character where search must begin. By default, the function parameter is RE_BEGINNING.

```
<regexp_occurence>
```

Specifies the replacement occurrence of a substring. If the constant is RE_ALL, then the replacement of each matching substring occurs. If the constant is RE_FIRST, then the replacement of the first matching substring occurs.

```
<regexp_match_parameter>
```

Changes the default matching behavior of a function. The possible regexp_match_parameter constants can be `RE_CASE_SENSITIVE', `RE_CASE_INSENSITIVE', `RE_MULTIPLE_LINES', `RE_NEWLINE_WILDCARD', `RE_IGNORE_WHITESPACE'.

Note: For more information on constants, function_parameters, or regexp (regular expressions) see, Using DBMS_REDACT Constants and Function Parameters.

```
<policy_description>
```

Specify the description of a redaction policy.

```
<column_description>
```

Description of the column to be redacted. The column_description is not supported, but if you specify the description for a column then, you will get a warning message.

```
<custom_function_expression>
```

The custom_function_expression is applicable only for the CUSTOM redaction type. The custom_function_expression is a function expression that is, schema-qualified function with a parameter such as schema_name.function_name (argument1, ...)that allows a user to use their redaction logic to redact the column data.

Example

The following example illustrates to alter a policy partial redaction for values in the payment_details_tab table card_string (usually a credit card number) column.

```
function_parameters => DBMS_REDACT.REDACT_CCN16_F12);
END;
```

Redacted Result:

3.13.4 DISABLE POLICY

The disable_policy procedure disables an existing data redaction policy.

Parameters

```
<object schema>
```

Specifies the name of the schema in which the object resides and on which the data redaction policy will be applied. If you specify NULL then the given object is searched by the order specified by search_path setting.

```
<object_name>
```

Name of the table for which to disable a data redaction policy.

```
<policy_name>
```

Name of the policy to be disabled.

Example

The following example illustrates how to disable a policy.

```
BEGIN

DBMS_REDACT.disable_policy(
   object_schema => 'public',
   object_name => 'payment_details_tab',
   policy_name => 'redactPolicy_001');
END;
```

Redacted Result: Data is no longer redacted after disabling a policy.

3.13.5 ENABLE_POLICY

The enable_policy procedure enables the previously disabled data redaction policy.

Parameters

```
<object_schema>
```

Specifies the name of the schema in which the object resides and on which the data redaction policy will be applied. If you specify NULL then the given object is searched by the order specified by search_path setting.

```
<object_name>
```

Name of the table to which to enable a data redaction policy.

```
<policy_name>
```

Name of the policy to be enabled.

Example

The following example illustrates how to enable a policy.

```
BEGIN

DBMS_REDACT.enable_policy(
   object_schema => 'public',
   object_name => 'payment_details_tab',
   policy_name => 'redactPolicy_001');
END;
```

Redacted Result: Data is redacted after enabling a policy.

3.13.6 DROP POLICY

The drop_policy procedure drops a data redaction policy by removing the masking policy from a table.

Parameters

```
<object schema>
```

Specifies the name of the schema in which the object resides and on which the data redaction policy will be applied. If you specify NULL then the given object is searched by the order specified by search_path setting.

```
<object_name>
```

Name of the table from which to drop a data redaction policy.

```
<policy_name>
```

Name of the policy to be dropped.

Example

The following example illustrates how to drop a policy.

```
BEGIN

DBMS_REDACT.drop_policy(
   object_schema => 'public',
   object_name => 'payment_details_tab',
   policy_name => 'redactPolicy_001');
```

Redacted Result: The server drops the specified policy.

3.13.7 UPDATE FULL REDACTION VALUES

The update_full_redaction_values procedure updates the default displayed values for a data redaction policy and these default values can be viewed using the redaction_values_for_type_full view that use the full redaction type.

```
PROCEDURE update_full_redaction_values (
             IN NUMBER
number_val
                                          DEFAULT NULL,
bindouble_val IN FLOAT8
char_val IN CHAR
varchar_val
                                          DEFAULT NULL,
                 IN FLOAT8
                                         DEFAULT NULL,
                                         DEFAULT NULL,
varchar_val
                IN VARCHAR2
                                         DEFAULT NULL,
nchar_val
                 IN NCHAR
                                         DEFAULT NULL,
nvarchar_val IN NVARCHAR2
                                        DEFAULT NULL, DEFAULT NULL,
datecol_val
                 IN DATE
                 IN TIMESTAMP
ts_val
                                         DEFAULT NULL,
tswtz_val
                IN TIMESTAMPTZ
                                        DEFAULT NULL,
blob_val
clob_val
                 IN BLOB
                                         DEFAULT NULL,
                  IN CLOB
                                         DEFAULT NULL,
nclob_val
                  IN CLOB
                                          DEFAULT NULL
```

Parameters

```
<number_val>
```

Updates the default value for columns of the NUMBER datatype.

```
<br/>
<br/>
dinfloat_val>
```

The FLOAT4 datatype is a random value. The binary float datatype is not supported.

```
<br/>bindouble val>
```

The FLOAT8 datatype is a random value. The binary double datatype is not supported.

```
<char_val>
```

Updates the default value for columns of the CHAR datatype.

```
<varchar val>
```

Updates the default value for columns of the VARCHAR2 datatype.

```
<nchar_val>
```

The nchar_val is mapped to CHAR datatype and returns the CHAR value.

```
<nvarchar_val>
```

The nvarchar_val is mapped to VARCHAR2 datatype and returns the VARCHAR value.

```
<datecol_val>
```

Updates the default value for columns of the DATE datatype.

```
<ts val>
```

Updates the default value for columns of the TIMESTAMP datatype.

```
<tswtz val>
```

Updates the default value for columns of the TIMESTAMPTZ datatype.

```
<blob val>
```

Updates the default value for columns of the BLOB datatype.

```
<clob_val>
```

Updates the default value for columns of the CLOB datatype.

```
<nclob val>
```

The nclob val is mapped to CLOB datatype and returns the CLOB value.

Example

The following example illustrates how to update the full redaction values but before updating the values, you can:

1. View the default values using redaction_values_for_type_full view as shown below:

```
edb=\# \x
Expanded display is on.
edb=# SELECT number_value, char_value, varchar_value, date_value,
      timestamp_value, timestamp_with_time_zone_value, blob_value, clob_value
FROM redaction_values_for_type_full;
-[ RECORD 1 ]-------
number_value
char_value
varchar_value
date_value
                            | 01-JAN-01 00:00:00
timestamp_value | 01-JAN-01 01:00:00
timestamp_with_time_zone_value | 31-DEC-00 20:00:00 -05:00
blob_value
                           | \x5b72656461637465645d
clob_value
                             | [redacted]
(1 row)
```

2. Now, update the default values for full redaction type. The NULL values will be ignored. c edb base_user

```
edb=# BEGIN
    DBMS_REDACT.update_full_redaction_values (
    number_val => 9999999,
    char_val => 'Z',
    varchar_val => 'V',
    datecol_val => to_date('17/10/2018', 'DD/MM/YYYY'),
    ts_val => to_timestamp('17/10/2018 11:12:13', 'DD/MM/YYYY HH24:MI:SS'),
    tswtz_val => NULL,
    blob_val => 'NEW REDACTED VALUE',
    clob_val => 'NEW REDACTED VALUE');
END;
```

3. You can now see the updated values using redaction_values_for_type_full view.

```
blob_value | \x4e45572052454441435445442056414c5545 | NEW REDACTED VALUE (1 row)
```

Redacted Result:

3.14 DBMS_RLS

The DBMS_RLS package enables the implementation of Virtual Private Database on certain Advanced Server database objects.

Function/Procedure	Function or Proce-	Return	Description
	dure	Type	
ADD_POLICY(<object_schema>, <object_name>, <policy_name>, <function_schema>, <policy_function> [, <statement_types> [, <update_check> [, <enable> [, <static_policy> [, <policy_type> [, <long_predicate> [, <sec_relevant_cols> [, <sec_relevant_cols_opt>]]]]]]]])</sec_relevant_cols_opt></sec_relevant_cols></long_predicate></policy_type></static_policy></enable></update_check></statement_types></policy_function></function_schema></policy_name></object_name></object_schema>	Procedure	n/a	Add a security policy to a database object.
DROP_POLICY(<object_schema>, <object_name>, <policy_name>)</policy_name></object_name></object_schema>	Procedure	n/a	Remove a security policy from a database object.
ENABLE_POLICY(<object_schema>, <object_name>, <policy_name>, <en-able>)</en-able></policy_name></object_name></object_schema>	Procedure	n/a	Enable or disable a security policy.

Advanced Server's implementation of DBMS_RLS is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Virtual Private Database is a type of fine-grained access control using security policies. Fine-grained access control in Virtual Private Database means that access to data can be controlled down to specific rows as defined by the security policy.

The rules that encode a security policy are defined in a *policy function*, which is an SPL function with certain input parameters and return value. The *security policy* is the named association of the policy function to a particular database object, typically a table.

Note: In Advanced Server, the policy function can be written in any language supported by Advanced Server such as SQL, PL/pgSQL and SPL.

Note: The database objects currently supported by Advanced Server Virtual Private Database are tables. Policies cannot be applied to views or synonyms.

The advantages of using Virtual Private Database are the following:

- Provides a fine-grained level of security. Database object level privileges given by the GRANT command determine access privileges to the entire instance of a database object, while Virtual Private Database provides access control for the individual rows of a database object instance.
- A different security policy can be applied depending upon the type of SQL command (INSERT, UPDATE, DELETE, or SELECT).
- The security policy can vary dynamically for each applicable SQL command affecting the database object depending upon factors such as the session user of the application accessing the database object.
- Invocation of the security policy is transparent to all applications that access the database object and thus, individual applications do not have to be modified to apply the security policy.
- Once a security policy is enabled, it is not possible for any application (including new applications) to circumvent the security policy except by the system privilege noted by the following.

• Even superusers cannot circumvent the security policy except by the system privilege noted by the following.

Note: The only way security policies can be circumvented is if the EXEMPT ACCESS POLICY system privilege has been granted to a user. The EXEMPT ACCESS POLICY privilege should be granted with extreme care as a user with this privilege is exempted from all policies in the database.

The DBMS_RLS package provides procedures to create policies, remove policies, enable policies, and disable policies.

The process for implementing Virtual Private Database is as follows:

- Create a policy function. The function must have two input parameters of type VARCHAR2. The first input parameter is for the schema containing the database object to which the policy is to apply and the second input parameter is for the name of that database object. The function must have a VARCHAR2 return type. The function must return a string in the form of a WHERE clause predicate. This predicate is dynamically appended as an AND condition to the SQL command that acts upon the database object. Thus, rows that do not satisfy the policy function predicate are filtered out from the SQL command result set.
- Use the ADD_POLICY procedure to define a new policy, which is the association of a policy function with a database object. With the ADD_POLICY procedure, you can also specify the types of SQL commands (INSERT, UPDATE, DELETE, or SELECT) to which the policy is to apply, whether or not to enable the policy at the time of its creation, and if the policy should apply to newly inserted rows or the modified image of updated rows.
- Use the ENABLE_POLICY procedure to disable or enable an existing policy.
- Use the DROP_POLICY procedure to remove an existing policy. The DROP_POLICY procedure does not drop the policy function or the associated database object.

Once policies are created, they can be viewed in the catalog views, compatible with Oracle databases: ALL_POLICIES, DBA_POLICIES, or USER_POLICIES. The supported compatible views are listed in the Database Compatibility for Oracle Developers Reference Guide, available at the EnterpriseDB website at:

https://www.enterprisedb.com/edb-docs/

The SYS_CONTEXT function is often used with DBMS_RLS. The signature is:

```
SYS_CONTEXT(<namespace>, <attribute>)
```

Where:

<namespace> is a VARCHAR2; the only accepted value is USERENV. Any other value will return NULL.

<attribute> is a VARCHAR2. <attribute> may be:

attribute Value	Equivalent Value
SESSION_USER	pg_catalog.session_user
CURRENT_USER	pg_catalog.current_user
CURRENT_SCHEMA	pg_catalog.current_schema
HOST	pg_catalog.inet_host
IP_ADDRESS	pg_catalog.inet_client_addr
SERVER_HOST	pg_catalog.inet_server_addr

Note: The examples used to illustrate the DBMS_RLS package are based on a modified copy of the sample emp table provided with Advanced Server along with a role named salesmgr that is granted all privileges on the table. You can create the modified copy of the emp table named <code>vpemp</code> and the <code>salesmgr</code> role as shown by the following:

```
CREATE TABLE public.vpemp AS SELECT empno, ename, job, sal, comm, deptno FROM emp;
ALTER TABLE vpemp ADD authid VARCHAR2(12);
UPDATE vpemp SET authid = 'researchmgr' WHERE deptno = 20;
UPDATE vpemp SET authid = 'salesmgr' WHERE deptno = 30;
SELECT * FROM vpemp;
empno | ename | job | sal | comm | deptno | authid
7782 | CLARK | MANAGER | 2450.00 | 10 |
     7839 | KING | PRESIDENT | 5000.00 |
                                                                                                                                             10 I
    7934 | MILLER | CLERK | 1300.00 | | 10 | | 17369 | SMITH | CLERK | 800.00 | | 20 | researchmgr | 1566 | JONES | MANAGER | 2975.00 | | 20 | researchmgr | 1788 | SCOTT | ANALYST | 3000.00 | | 20 | researchmgr | 17876 | ADAMS | CLERK | 1100.00 | | 20 | researchmgr | 17902 | FORD | ANALYST | 3000.00 | | 20 | researchmgr | 17499 | ALLEN | SALESMAN | 1600.00 | 300.00 | 30 | salesmgr | 17521 | WARD | SALESMAN | 1250.00 | 500.00 | 30 | salesmgr | 17654 | MARTIN | CALESMAN | 1250.00 | 1400.00 | 30 | salesmgr | 17654 | MARTIN | CALESMAN | 1250.00 | 1400.00 | 30 | salesmgr | 17654 | MARTIN | CALESMAN | 1250.00 | 1400.00 | 30 | salesmgr | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 | 300.00 
     7934 | MILLER | CLERK | 1300.00 |
                                                                                                                                             10 I
     7654 | MARTIN | SALESMAN | 1250.00 | 1400.00 |
                                                                                                                                                               30 | salesmgr
     7698 | BLAKE | MANAGER | 2850.00 |
                                                                                                                                                                30 | salesmgr
    7844 | TURNER | SALESMAN | 1500.00 | 0.00 | 30 | salesmgr
7900 | JAMES | CLERK | 950.00 | 30 | salesmgr
 (14 rows)
CREATE ROLE salesmgr WITH LOGIN PASSWORD 'password';
GRANT ALL ON vpemp TO salesmgr;
```

3.14.1 ADD POLICY

The ADD_POLICY procedure creates a new policy by associating a policy function with a database object.

You must be a superuser to execute this procedure.

```
ADD_POLICY(<object_schema> VARCHAR2, <object_name> VARCHAR2, <policy_name> VARCHAR2, <function_schema> VARCHAR2, <policy_function> VARCHAR2

[, <statement_types> VARCHAR2

[, <update_check> BOOLEAN

[, <enable> BOOLEAN

[, <static_policy> BOOLEAN

[, <policy_type> INTEGER

[, <long_predicate> BOOLEAN

[, <sec_relevant_cols> VARCHAR2

[, <sec_relevant_cols_opt> INTEGER ]]]]]]]]))
```

Parameters

<object_schema>

Name of the schema containing the database object to which the policy is to be applied.

```
<object_name>
```

Name of the database object to which the policy is to be applied. A given database object may have more than one policy applied to it.

```
<policy_name>
```

Name assigned to the policy. The combination of database object (identified by <object_schema> and <object_name>) and policy name must be unique within the database.

```
<function schema>
```

Name of the schema containing the policy function.

Note: The policy function may belong to a package in which case <function_schema> must contain the name of the schema in which the package is defined.

```
<policy_function>
```

Name of the SPL function that defines the rules of the security policy. The same function may be specified in more than one policy.

Note: The policy function may belong to a package in which case <policy_function> must also contain the package name in dot notation (that is, <package name>.<function name>).

<statement_types>

Comma-separated list of SQL commands to which the policy applies. Valid SQL commands are INSERT, UPDATE, DELETE, and SELECT. The default is INSERT, UPDATE, DELETE, SELECT.

Note: Advanced Server accepts INDEX as a statement type, but it is ignored. Policies are not applied to index operations in Advanced Server.

<update_check>

Applies to INSERT and UPDATE SQL commands only.

When set to TRUE, the policy is applied to newly inserted rows and to the modified image of updated rows. If any of the new or modified rows do not qualify according to the policy function predicate, then the INSERT or UPDATE command throws an exception and no rows are inserted or modified by the INSERT or UPDATE command.

When set to FALSE, the policy is not applied to newly inserted rows or the modified image of updated rows. Thus, a newly inserted row may not appear in the result set of a subsequent SQL command that invokes the same policy. Similarly, rows which qualified according to the policy prior to an UPDATE command may not appear in the result set of a subsequent SQL command that invokes the same policy.

The default is FALSE.

<enable>

When set to TRUE, the policy is enabled and applied to the SQL commands given by the <statement_types> parameter. When set to FALSE the policy is disabled and not applied to any SQL commands. The policy can be enabled using the ENABLE_POLICY procedure. The default is TRUE.

<static_policy>

In Oracle, when set to TRUE, the policy is *static*, which means the policy function is evaluated once per database object the first time it is invoked by a policy on that database object. The resulting policy function predicate string is saved in memory and reused for all invocations of that policy on that database object while the database server instance is running.

When set to FALSE, the policy is *dynamic*, which means the policy function is re-evaluated and the policy function predicate string regenerated for all invocations of the policy.

The default is FALSE.

Note: In Oracle 10g, the <policy_type> parameter was introduced, which is intended to replace the <static_policy> parameter. In Oracle, if the <policy_type> parameter is not set to its default value of NULL, the <policy_type> parameter setting overrides the <static_policy> setting.

Note: The setting of <static_policy> is ignored by Advanced Server. Advanced Server implements only the dynamic policy, regardless of the setting of the <static_policy> parameter.

```
<policy_type>
```

In Oracle, determines when the policy function is re-evaluated, and hence, if and when the predicate string returned by the policy function changes. The default is NULL.

Note: The setting of this parameter is ignored by Advanced Server. Advanced Server always assumes a dynamic policy.

```
<long_predicate>
```

In Oracle, allows predicates up to 32K bytes if set to TRUE, otherwise predicates are limited to 4000 bytes. The default is FALSE.

Note: The setting of this parameter is ignored by Advanced Server. An Advanced Server policy function can return a predicate of unlimited length for all practical purposes.

```
<sec_relevant_cols>
```

Comma-separated list of columns of <object_name>. Provides column-level Virtual Private Database for the listed columns. The policy is enforced if any of the listed columns are referenced in a SQL command of a type listed in <statement_types>. The policy is not enforced if no such columns are referenced.

The default is NULL, which has the same effect as if all of the database object's columns were included in <sec relevant cols>.

```
<sec_relevant_cols_opt>
```

In Oracle, if <sec_relevant_cols_opt> is set to DBMS_RLS.ALL_ROWS (INTEGER constant of value 1), then the columns listed in <sec_relevant_cols> return NULL on all rows where the applied policy predicate is false. (If <sec_relevant_cols_opt> is not set to DBMS_RLS. ALL_ROWS, these rows would not be returned at all in the result set.) The default is NULL.

Note: Advanced Server does not support the DBMS_RLS.ALL_ROWS functionality. Advanced Server throws an error if sec_relevant_cols_opt is set to DBMS_RLS.ALL_ROWS (INTEGER value of 1).

Examples

This example uses the following policy function:

This function generates the predicate authid = SYS_CONTEXT('USERENV', 'SESSION_USER'), which is added to the WHERE clause of any SQL command of the type specified in the ADD_POLICY procedure.

This limits the effect of the SQL command to those rows where the content of the authid column is the same as the session user.

Note: This example uses the SYS_CONTEXT function to return the login user name. In Oracle the SYS_CONTEXT function is used to return attributes of an *application context*. The first parameter of the SYS_CONTEXT function is the name of an application context while the second parameter is the name of an attribute set within the application context. USERENV is a special built-in namespace that describes the current session. Advanced Server does not support application contexts, but only this specific usage of the SYS_CONTEXT function.

The following anonymous block calls the ADD_POLICY procedure to create a policy named secure_update to be applied to the vpemp table using function verify_session_user whenever an INSERT, UPDATE, or DELETE SQL command is given referencing the vpemp table.

```
DECLARE
                        v_object_schema
                                                                                                                                                                              VARCHAR2(30) := 'public';
                                                                                                                                                                              VARCHAR2(30) := 'vpemp';
                       v_object_name
v_policy_name
v_policy_name
v_function_schema
v_policy_function
v_policy_function
v_policy_function
v_statement_types
v_update_check
v_enable
VARCHAR2(30) := 'secure_update';
VARCHAR2(30) := 'enterprisedb';
VARCHAR2(30) := 'verify_session_user';
v_archar2(30) := 'INSERT, UPDATE, DELETE';
v_enable

ROOLEAN := TRUE;

v_policy_name
vARCHAR2(30) := 'secure_update';
verify_session_user';
varchar2(30) := 'TRUE;
v= TRUE;
v
                         v_object_name
                         v_enable
                                                                                                                                                                                 BOOLEAN
                                                                                                                                                                                                                                                                            := TRUE;
BEGIN
                         DBMS RLS.ADD POLICY(
                                                    v_object_schema,
                                                    v_object_name,
                                                    v_policy_name,
                                                    v_function_schema,
                                                    v_policy_function,
                                                     v_statement_types,
                                                     v_update_check,
                                                     v enable
                           );
END;
```

After successful creation of the policy, a terminal session is started by user salesmgr. The following query shows the content of the vpemp table:

```
edb=# \c edb salesmgr
Password for user salesmgr:
You are now connected to database "edb" as user "salesmgr".
edb=> SELECT * FROM vpemp;
empno | ename | job
                            comm
                                     | deptno |
                                                authid
                        sal
______
 7782 | CLARK | MANAGER | 2450.00 |
                                          10 |
 7839 | KING | PRESIDENT | 5000.00 |
                                    10 |
                                         10 I
 7934 | MILLER | CLERK | 1300.00 |
                                    20 | researchmgr
 7369 | SMITH | CLERK
                     | 800.00 |
                                    7566 | JONES | MANAGER | 2975.00 |
                                    20 | researchmgr
 7788 | SCOTT | ANALYST | 3000.00 |
                                    1
                                         20 | researchmgr
 20 | researchmgr
                                         20 | researchmgr
 7499 | ALLEN | SALESMAN | 1600.00 | 300.00 |
                                         30 | salesmgr
 7521 | WARD | SALESMAN | 1250.00 | 500.00 |
                                         30 | salesmgr
 7654 | MARTIN | SALESMAN | 1250.00 | 1400.00 |
                                         30 | salesmgr
 7698 | BLAKE | MANAGER | 2850.00 |
                                         30 | salesmgr
 7844 | TURNER | SALESMAN | 1500.00 |
                                0.00 |
                                          30 | salesmgr
 7900 | JAMES | CLERK | 950.00 |
                                 30 | salesmgr
(14 rows)
```

An unqualified UPDATE command (no WHERE clause) is issued by the salesmgr user:

```
edb=> UPDATE vpemp SET comm = sal * .75;
UPDATE 6
```

Instead of updating all rows in the table, the policy restricts the effect of the update to only those rows where the authid column contains the value salesmgr as specified by the policy function predicate authid = SYS_CONTEXT('USERENV', 'SESSION_USER').

The following query shows that the comm column has been changed only for those rows where authid contains salesmar. All other rows are unchanged.

```
edb=> SELECT * FROM vpemp;
empno | ename | job | sal | comm | deptno | authid
                    -----
 7782 | CLARK | MANAGER | 2450.00 |
                                              10 I
 7839 | KING | PRESIDENT | 5000.00 |
                                                    10 |
                                               7934 | MILLER | CLERK | 1300.00 | 7369 | SMITH | CLERK | 800.00 |
                                                     10 |
                                               20 | researchmgr
20 | researchmgr
                           | 800.00 |
                                              7566 | JONES | MANAGER | 2975.00 |
                                              20 | researchmgr
 7788 | SCOTT | ANALYST | 3000.00 |
                                              20 | researchmgr
 7876 | ADAMS | CLERK | 1100.00 |
                                              7902 | FORD | ANALYST | 3000.00 |
                                                    20 | researchmgr
 7499 | ALLEN | SALESMAN | 1600.00 | 1200.00 | 30 | salesmgr
 7521 | WARD | SALESMAN | 1250.00 | 937.50 |
                                                    30 | salesmgr
 7654 | MARTIN | SALESMAN | 1250.00 | 937.50 |
                                                    30 | salesmgr
 7698 | BLAKE | MANAGER | 2850.00 | 2137.50 | 30 | salesmgr
7844 | TURNER | SALESMAN | 1500.00 | 1125.00 | 30 | salesmgr
7900 | JAMES | CLERK | 950.00 | 712.50 | 30 | salesmgr
                                                    30 | salesmgr
 7900 | JAMES | CLERK | 950.00 | 712.50 |
(14 rows)
```

Furthermore, since the <update_check> parameter was set to TRUE in the ADD_POLICY procedure, the following INSERT command throws an exception since the value given for the authid column, researchmgr, does not match the session user, which is salesmgr, and hence, fails the policy.

```
edb=> INSERT INTO vpemp VALUES (9001, 'SMITH', 'ANALYST', 3200.00, NULL, 20, 'researchmgr \( \to '); \)
ERROR: policy with check option violation
DETAIL: Policy predicate was evaluated to FALSE with the updated values
```

If <update_check> was set to FALSE, the preceding INSERT command would have succeeded.

The following example illustrates the use of the <sec_relevant_cols> parameter to apply a policy only when certain columns are referenced in the SQL command. The following policy function is used for this example, which selects rows where the employee salary is less than 2000.

The policy is created so that it is enforced only if a SELECT command includes columns sal or comm:

```
DECLARE
                                       VARCHAR2(30) := 'public';
     v_object_schema
    v_object_name
v_policy_name
v_function_schema
v_policy_function
v_statement_types
v_soc_rol_sum_time
v_nobject_name
vARCHAR2(30) := 'vpemp';
vARCHAR2(30) := 'secure_salary'
vARCHAR2(30) := 'enterprisedb';
vARCHAR2(30) := 'sal_lt_2000';
vARCHAR2(30) := 'SELECT';
                                       VARCHAR2(30) := 'secure_salary';
     BEGIN
     DBMS_RLS.ADD_POLICY(
           v_object_schema,
           v_object_name,
           v_policy_name,
           v_function_schema,
           v_policy_function,
           v_statement_types,
           sec_relevant_cols => v_sec_relevant_cols
     );
END;
```

If a query does not reference columns sal or comm, then the policy is not applied. The following query returns all 14 rows of table vpemp:

```
edb=# SELECT empno, ename, job, deptno, authid FROM vpemp;
empno | ename | job | deptno | authid
----+----
 7782 | CLARK | MANAGER |
                            10 I
                           10 I
 7839 | KING | PRESIDENT |
                           10 |
 7934 | MILLER | CLERK |
                      | 20 | researchmgr
 7369 | SMITH | CLERK
 7566 | JONES | MANAGER | 20 | researchmgr
 7788 | SCOTT | ANALYST | 20 | researchmgr
 7876 | ADAMS | CLERK
                      | 20 | researchmgr
 7902 | FORD | ANALYST |
                           20 | researchmgr
 7499 | ALLEN | SALESMAN |
                           30 | salesmgr
 7521 | WARD | SALESMAN |
                           30 | salesmgr
 7654 | MARTIN | SALESMAN |
                            30 | salesmgr
                            30 | salesmgr
 7698 | BLAKE | MANAGER
                       7844 | TURNER | SALESMAN | 30 | salesmgr
 7900 | JAMES | CLERK |
                            30 | salesmgr
(14 rows)
```

If the query references the sal or comm columns, then the policy is applied to the query eliminating any rows where sal is greater than or equal to 2000 as shown by the following:

	-		_			•	FROM vpemp;
-	ename -+			sal 		-	authid
	MILLER	•				10	
7369	SMITH	CLERK		800.00		20	researchmgr
7876	ADAMS	CLERK		1100.00		20	researchmgr
7499	ALLEN	SALESMAN		1600.00	1200.00	30	salesmgr
7521	WARD	SALESMAN		1250.00	937.50	30	salesmgr
7654	MARTIN	SALESMAN		1250.00	937.50	30	salesmgr
7844	TURNER	SALESMAN		1500.00	1125.00	30	salesmgr
7900	JAMES	CLERK		950.00	712.50	30	salesmgr
(8 rows	3)						

3.14.2 DROP POLICY

The DROP_POLICY procedure deletes an existing policy. The policy function and database object associated with the policy are not deleted by the DROP_POLICY procedure.

You must be a superuser to execute this procedure.

```
DROP_POLICY(<object_schema> VARCHAR2, <object_name> VARCHAR2,
<policy_name> VARCHAR2)
```

Parameters

```
<object_schema>
```

Name of the schema containing the database object to which the policy applies.

```
<object_name>
```

Name of the database object to which the policy applies.

```
<policy_name>
```

Name of the policy to be deleted.

Examples

The following example deletes policy secure_update on table public.vpemp:

3.14.3 ENABLE_POLICY

The ENABLE_POLICY procedure enables or disables an existing policy on the specified database object.

You must be a superuser to execute this procedure.

```
ENABLE_POLICY(<object_schema> VARCHAR2, <object_name> VARCHAR2,
<policy_name> VARCHAR2, <enable> BOOLEAN)
```

Parameters

```
<object_schema>
```

Name of the schema containing the database object to which the policy applies.

```
<object_name>
```

Name of the database object to which the policy applies.

```
<policy_name>
```

Name of the policy to be enabled or disabled.

```
<enable>
```

When set to TRUE, the policy is enabled. When set to FALSE, the policy is disabled.

Examples

The following example disables policy secure_update on table public.vpemp:

```
DECLARE
   v_object_schema
                          VARCHAR2(30) := 'public';
   v_object_name
                          VARCHAR2(30) := 'vpemp';
   v_policy_name
                         VARCHAR2(30) := 'secure_update';
                         BOOLEAN := FALSE;
   v_enable
BEGIN
   DBMS_RLS.ENABLE_POLICY(
       v_object_schema,
       v_object_name,
       v_policy_name,
       v_enable
   );
END;
```

3.15 DBMS_SCHEDULER

The DBMS_SCHEDULER package provides a way to create and manage Oracle-styled jobs, programs and job schedules. The DBMS_SCHEDULER package implements the following functions and procedures:

Function/Procedure	Return Type	Description
CREATE_JOB(<job_name>, <job_type>, <job_action>, <number_of_arguments>, <start_date>, <repeat_interval>, <end_date>, <job_class>, <enabled>, <auto_drop>, <comments>)</comments></auto_drop></enabled></job_class></end_date></repeat_interval></start_date></number_of_arguments></job_action></job_type></job_name>	n/a	Use the first form of the CREATE_JOB procedure to create a job, specifying program and schedule details by means of parameters.
CREATE_JOB(<job_name>, <pre>gram_name>, <schedule_name>, <job_class>, <enabled>, <auto_drop>, <comments>)</comments></auto_drop></enabled></job_class></schedule_name></pre></job_name>	n/a	Use the second form of CREATE_JOB to create a job that uses a named program and named schedule.
CREATE_PROGRAM(<program_name>, <program_type>, <program_action>, <number_of_arguments>, <enabled>, <comments>)</comments></enabled></number_of_arguments></program_action></program_type></program_name>	n/a	Use CREATE_PROGRAM to create a program.
CREATE_SCHEDULE(<schedule_name>, <start_date>, <repeat_interval>, <end_date>, <comments>)</comments></end_date></repeat_interval></start_date></schedule_name>	n/a	Use the CREATE_SCHEDULE procedure to create a schedule.
DEFINE_PROGRAM_ARGUMENT(<pre></pre>	n/a	Use the first form of the DE-FINE_PROGRAM_ARGUMENT procedure to define a program argument that has a default value.
DEFINE_PROGRAM_ARGUMENT(<pre></pre>	n/a	Use the first form of the DE-FINE_PROGRAM_ARGUMENT procedure to define a program argument that does not have a default value.
DISABLE(<name>, <force>, <commit_semantics>)</commit_semantics></force></name>	n/a	Use the DISABLE procedure to disable a job or program.
DROP_JOB(<job_name>, <force>, <de-fer>, <commit_semantics>)</commit_semantics></de-fer></force></job_name>	n/a	Use the DROP_JOB procedure to drop a job.
DROP_PROGRAM(<pre>program_name>, <force>)</force></pre>	n/a	Use the DROP_PROGRAM procedure to drop a program.
DROP_PROGRAM_ARGUMENT(<pre>pro- gram_name>, <argument_position>)</argument_position></pre>	n/a	Use the first form of DROP_PROGRAM_ARGUMENT to drop a program argument by specifying the argument position.
DROP_PROGRAM_ARGUMENT(<pre>pro- gram_name>, <argument_name>)</argument_name></pre>	n/a	Use the second form of DROP_PROGRAM_ARGUMENT to drop a program argument by specifying the argument name.
DROP_SCHEDULE(<schedule_name>, <force>)</force></schedule_name>	n/a	Use the DROP SCHEDULE procedure to drop a schedule.
ENABLE(<name>, <commit_semantics>)</commit_semantics></name>	n/a	Use the ENABLE command to enable a program or job.
EVALUATE_CALENDAR_STRING(<calendar_string>, <start_date>, <re- turn_date_after="">, <next_run_date>)</next_run_date></re-></start_date></calendar_string>	n/a	Use EVALUATE_CALENDAR_STRING to review the execution date described by a user-defined calendar schedule.
RUN_JOB(<job_name>, <use_current_session>, <manually>)</manually></use_current_session></job_name>	n/a	Use the RUN_JOB procedure to execute a job immediately.

Continued on next page

Table 3.7 – continued from previous page

SET_JOB_ARGUMENT_VALUE(n/a	Use the first form of SET_JOB_ARGUMENT value to	
<pre><job_name>, <argument_position>,</argument_position></job_name></pre>		set the value of a job argument described by the argu-	
<argument_value>)</argument_value>		ment's position.	
SET_JOB_ARGUMENT_VALUE(n/a		Use the second form of SET_JOB_ARGUMENT value	
<pre><job_name>, <argument_name>, <ar-< pre=""></ar-<></argument_name></job_name></pre>		to set the value of a job argument described by the argu-	
gument_value>)		ment's name.	

Advanced Server's implementation of DBMS_SCHEDULER is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The DBMS_SCHEDULER package is dependent on the pgAgent service; you must have a pgAgent service installed and running on your server before using DBMS_SCHEDULER.

Before using DBMS_SCHEDULER, a database superuser must create the catalog tables in which the DBMS_SCHEDULER programs, schedules and jobs are stored. Use the psql client to connect to the database, and invoke the command:

CREATE EXTENSION dbms_scheduler;

By default, the dbms_scheduler extension resides in the contrib/dbms_scheduler_ext subdirectory (under the Advanced Server installation).

Note that after creating the DBMS_SCHEDULER tables, only a superuser will be able to perform a dump or reload of the database.

3.15.1 Using Calendar Syntax to Specify a Repeating Interval

The CREATE_JOB and CREATE_SCHEDULE procedures use Oracle-styled calendar syntax to define the interval with which a job or schedule is repeated. You should provide the scheduling information in the <repeat_interval> parameter of each procedure.

<repeat_interval> is a value (or series of values) that define the interval between the executions of the scheduled
job. Each value is composed of a token, followed by an equal sign, followed by the unit (or units) on which the schedule
will execute. Multiple token values must be separated by a semi-colon (;).

For example, the following value:

FREQ=DAILY; BYDAY=MON, TUE, WED, THU, FRI; BYHOUR=17; BYMINUTE=45

Defines a schedule that is executed each weeknight at 5:45.

The token types and syntax described in the table below are supported by Advanced Server:

Token type	Syntax	Valid Values
FREQ	FREQ= <pre>predefined_interval></pre>	Where <pre> <pre> <pre></pre></pre></pre>
		one of the following: YEARLY,
		MONTHLY, WEEKLY, DAILY,
		HOURLY, MINUTELY. The SEC-
		ONDLY keyword is not supported.
BYMONTH	BYMONTH= <month>(, <month>)</month></month>	Where <month> is the three-letter ab-</month>
		breviation of the month name: JAN
		FEB MAR APR MAY JUN JUL
		AUG SEP OCT NOV DEC
BYMONTH	BYMONTH= <month> (, <month>)</month></month>	Where <month> is the numeric value</month>
		representing the month: 1 2 3 4 5
		6 7 8 9 10 11 12
BYMONTHDAY	BYMONTHDAY= <day_of_month></day_of_month>	Where <day_of_month> is a value</day_of_month>
		from 1 through 31
BYDAY	BYDAY= <weekday></weekday>	Where <weekday> is a three-letter ab-</weekday>
		breviation or single-digit value repre-
		senting the day of the week.
		Monday MON 1
		Tuesday TUE 2
		Wednesday WED 3
		Thursday THU 4
		Friday FRI 5
		Saturday SAT 6
		Sunday SUN 7
BYDATE	BYDATE= <date>(, <date>)</date></date>	Where <date> is <yyyymmdd>.</yyyymmdd></date>
		VVVV is a foundisit year
		YYYY is a four-digit year
		representation of the year,
		MM is a two-digit representation of
		the month,
		and DD is a two-digit day
		representation of the day.
		Out in a day of the same

Continued on next page

Table 3.8 – continued from previous page

Token type	Syntax	Valid Values
BYDATE	BYDATE= <date> (, <date>)</date></date>	Where <date> is <mmdd>.</mmdd></date>
		MM is a two-digit representation of the month, and DD is a two-digit day representation of the day
BYHOUR	BYHOUR= <hour></hour>	Where <nour> is a value from 0 through 23.</nour>
BYMINUTE	BYMINUTE= <minute></minute>	Where <minute> is a value from 0 through 59.</minute>

3.15.2 CREATE JOB

Use the CREATE_JOB procedure to create a job. The procedure comes in two forms; the first form of the procedure specifies a schedule within the job definition, as well as a job action that will be invoked when the job executes:

The second form uses a job schedule to specify the schedule on which the job will execute, and specifies the name of a program that will execute when the job runs:

Parameters

```
<job_ame>
     <job_name> specifies the optionally schema-qualified name of the job being created.

<job_type>
     <job_type> specifies the type of job. The current implementation of CREATE_JOB supports a job type of PLSQL_BLOCK or STORED_PROCEDURE.

<job_action>
```

If <job_type> is PLSQL_BLOCK, <job_action> specifies the content of the PL/SQL block that will be invoked when the job executes. The block must be terminated with a semi-colon (;).

 $If \verb|<job_type>| is \verb| STORED_PROCEDURE|, \verb|<job_action>| specifies the optionally schema-qualified name of the procedure.$

```
<number_of_arguments>
```

<number_of_arguments> is an INTEGER value that specifies the number of arguments expected by
the job. The default is 0.

```
<start_date>
```

<start_date> is a TIMESTAMP WITH TIME ZONE value that specifies the first time that the job is scheduled to execute. The default value is NULL, indicating that the job should be scheduled to execute when the job is enabled.

```
<repeat_interval>
```

<repeat_interval> is a VARCHAR2 value that specifies how often the job will repeat. If a
<repeat_interval> is not specified, the job will execute only once. The default value is NULL.

```
<end date>
```

<end_date> is a TIMESTAMP WITH TIME ZONE value that specifies a time after which the job will
no longer execute. If a date is specified, the <end_date> must be after <start_date>. The default
value is NULL.

Please note that if an <end_date> is not specified and a <repeat_interval> is specified, the job will repeat indefinitely until it is disabled.

```
cprogram_name>
```

program_name> is the name of a program that will be executed by the job.

```
<schedule_name>
```

<schedule_name> is the name of the schedule associated with the job.

```
<iob class>
```

<job_class> is accepted for compatibility and ignored.

<enabled>

<enabled> is a BOOLEAN value that specifies if the job is enabled when created. By default, a job is
created in a disabled state, with <enabled> set to FALSE. To enable a job, specify a value of TRUE
when creating the job, or enable the job with the DBMS_SCHEDULER.ENABLE procedure.

```
<auto_drop>
```

The <auto_drop> parameter is accepted for compatibility and is ignored. By default, a job's status will be changed to DISABLED after the time specified in <end_date>.

```
<comments>
```

Use the <comments> parameter to specify a comment about the job.

Example

The following example demonstrates a call to the CREATE_JOB procedure:

The code fragment creates a job named update_log that executes each weeknight at 5:00. The job executes a PL/SQL block that inserts the current timestamp into a logfile (my_log). Since no end_date is specified, the job will execute until it is disabled by the DBMS_SCHEDULER.DISABLE procedure.

3.15.3 CREATE PROGRAM

Use the CREATE_PROGRAM procedure to create a DBMS_SCHEDULER program. The signature is:

Parameters

```
cprogram_name>
```

amanamespecifies the name of the program that is being created.

```
cprogram_type>
```

```
cprogram_action>
```

If contains the PL/SQL block that will execute when the program is invoked. The PL/SQL block must be terminated with a semi-colon (;).

If foram_type> is PROCEDURE, program_action> contains the name of the stored procedure.

```
<number_of_arguments>
```

If is PLSQL_BLOCK, this argument is ignored.

If $\operatorname{sprogram_type}$ is PROCEDURE, $\operatorname{snumber_of_arguments}$ specifies the number of arguments required by the procedure. The default value is 0.

<enabled>

<enabled> specifies if the program is created enabled or disabled:

- If <enabled> is TRUE, the program is created enabled.
- If <enabled> is FALSE, the program is created disabled; use the DBMS_SCHEDULER.ENABLE program to enable a disabled program.

The default value is FALSE.

```
<comments>
```

Use the <comments> parameter to specify a comment about the program; by default, this parameter is NULL.

Example

The following call to the CREATE_PROGRAM procedure creates a program named update_log:

```
EXEC
  DBMS_SCHEDULER.CREATE_PROGRAM (
program_name => 'update_log',
  program_type => 'PLSQL_BLOCK',
  program_action => 'BEGIN INSERT INTO my_log VALUES(current_timestamp);END;',
  enabled => TRUE,
  comment => 'This program adds a row to the my_log table.');
```

update_log is a PL/SQL block that adds a row containing the current date and time to the my_log table. The program will be enabled when the CREATE_PROGRAM procedure executes.

3.15.4 CREATE SCHEDULE

Use the CREATE_SCHEDULE procedure to create a job schedule. The signature of the CREATE_SCHEDULE procedure is:

```
create_schedule(
  <schedule_name> IN VARCHAR2,
  <start_date> IN TIMESTAMP WITH TIME ZONE DEFAULT NULL,
  <repeat_interval> IN VARCHAR2,
  <end_date> IN TIMESTAMP WITH TIME ZONE DEFAULT NULL,
  <comments> IN VARCHAR2 DEFAULT NULL)
```

Parameters

```
<schedule_name>
     <schedule_name> specifies the name of the schedule.
<start_date>
```

<start_date> is a TIMESTAMP WITH TIME ZONE value that specifies the date and time that the
schedule is eligible to execute. If a <start_date> is not specified, the date that the job is enabled is
used as the <start_date>. By default, <start_date> is NULL.

```
<repeat_interval>
```

<repeat_interval> is a VARCHAR2 value that specifies how often the job will repeat. If a
<repeat_interval> is not specified, the job will execute only once, on the date specified by
<start_date>.

Note: You must provide a value for either <start_date> or <repeat_interval>; if both <start_date> and <repeat_interval> are NULL, the server will return an error.

```
<end date> IN TIMESTAMP WITH TIME ZONE DEFAULT NULL
```

<end_date> is a TIMESTAMP WITH TIME ZONE value that specifies a time after which the schedule will no longer execute. If a date is specified, the <end_date> must be after the <start_date>.
The default value is NULL.

Please note that if a <repeat_interval> is specified and an <end_date> is not specified, the schedule will repeat indefinitely until it is disabled.

```
<comments> IN VARCHAR2 DEFAULT NULL)
```

Use the <comments> parameter to specify a comment about the schedule; by default, this parameter is NULL.

Example

The following code fragment calls CREATE_SCHEDULE to create a schedule named weeknights_at_5:

```
EXEC

DBMS_SCHEDULER.CREATE_SCHEDULE (
schedule_name => 'weeknights_at_5',
start_date => '01-JUN-13 09:00:00.000000'
repeat_interval => 'FREQ=DAILY;BYDAY=MON,TUE,WED,THU,FRI;BYHOUR=17;',
comments => 'This schedule executes each weeknight at 5:00');
```

The schedule executes each weeknight, at 5:00 pm, effective after June 1, 2013. Since no end_date is specified, the schedule will execute indefinitely until it is disabled with DBMS_SCHEDULER.DISABLE.

3.15.5 DEFINE PROGRAM ARGUMENT

DEFINE_PROGRAM_ARGUMENT procedure to define a program argument. DEFINE_PROGRAM_ARGUMENT procedure comes in two forms; the first form defines an argument with a default value:

```
DEFINE PROGRAM ARGUMENT (
program_name> IN VARCHAR2,
<argument_position> IN PLS_INTEGER,
<argument_name> IN VARCHAR2 DEFAULT NULL,
<argument type> IN VARCHAR2,
<default value> IN VARCHAR2,
<out_argument> IN BOOLEAN DEFAULT FALSE)
```

The second form defines an argument without a default value:

```
DEFINE_PROGRAM_ARGUMENT (
program_name> IN VARCHAR2,
<argument_position> IN PLS_INTEGER,
<argument_name> IN VARCHAR2 DEFAULT NULL,
<argument_type> IN VARCHAR2,
<out_argument> IN BOOLEAN DEFAULT FALSE)
```

Parameters

```
cprogram_name>
    <argument_position>
    <argument_position> specifies the position of the argument as it is passed to the program.
<argument_name>
    <argument_name> specifies the optional name of the argument. By default, <argument_name> is
    NULL.
<argument_type> IN VARCHAR2
    <argument_type> specifies the data type of the argument.
<default_value>
    <default value> specifies the default value assigned to the argument. <default value> will
    be overridden by a value specified by the job when the job executes.
```

```
<out_argument> IN BOOLEAN DEFAULT FALSE
```

<out_argument> is not currently used; if specified, the value must be FALSE.

Example

The following code fragment uses the DEFINE_PROGRAM_ARGUMENT procedure to define the first and second arguments in a program named add_emp:

The first argument is an INTEGER value named "dept_no" that has a default value of 20. The second argument is a VARCHAR2 value named emp_name; the second argument does not have a default value.

3.15.6 DISABLE

Use the DISABLE procedure to disable a program or a job. The signature of the DISABLE procedure is:

```
DISABLE(
<name> IN VARCHAR2,
<force> IN BOOLEAN DEFAULT FALSE,
<commit_semantics> IN VARCHAR2 DEFAULT 'STOP_ON_FIRST_ERROR')
```

Parameters

<commit_semantics>

<commit_semantics> instructs the server how to handle an error encountered while disabling a program or job. By default, <commit_semantics> is set to STOP_ON_FIRST_ERROR, instructing the
server to stop when it encounters an error. Any programs or jobs that were successfully disabled prior to
the error will be committed to disk.

The TRANSACTIONAL and ABSORB_ERRORS keywords are accepted for compatibility, and ignored.

Example

The following call to the DISABLE procedure disables a program named update_emp:

```
DBMS_SCHEDULER.DISABLE('update_emp');
```

3.15.7 DROP JOB

Use the DROP_JOB procedure to DROP a job, DROP any arguments that belong to the job, and eliminate any future job executions. The signature of the procedure is:

```
DROP_JOB(

<job_name> IN VARCHAR2,

<force> IN BOOLEAN DEFAULT FALSE,

<defer> IN BOOLEAN DEFAULT FALSE,

<commit_semantics> IN VARCHAR2 DEFAULT 'STOP_ON_FIRST_ERROR')
```

Parameters

The TRANSACTIONAL and ABSORB_ERRORS keywords are accepted for compatibility, and ignored.

Example

The following call to DROP_JOB drops a job named update_log:

server to stop when it encounters an error.

```
DBMS_SCHEDULER.DROP_JOB('update_log');
```

3.15.8 DROP PROGRAM

```
The DROP_PROGRAM procedure
```

The signature of the DROP_PROGRAM procedure is:

Parameters

```
program_name>
```

program_name> specifies the name of the program that is being dropped.

<force>

<force> is a BOOLEAN value that instructs the server how to handle programs with dependent jobs.

Specify FALSE to instruct the server to return an error if the program is referenced by a job.

Specify TRUE to instruct the server to disable any jobs that reference the program before dropping the program.

The default value is FALSE.

Example

The following call to DROP_PROGRAM drops a job named update_emp:

```
DBMS_SCHEDULER.DROP_PROGRAM('update_emp');
```

3.15.9 DROP PROGRAM ARGUMENT

Use the DROP_PROGRAM_ARGUMENT procedure to drop a program argument. The DROP_PROGRAM_ARGUMENT procedure comes in two forms; the first form uses an argument position to specify which argument to drop:

```
drop_program_argument(
cprogram_name> IN VARCHAR2,
<argument_position> IN PLS_INTEGER)
```

The second form takes the argument name:

```
drop_program_argument(
cprogram_name> IN VARCHAR2,
<argument_name> IN VARCHAR2)
```

Parameters

Examples

The following call to DROP_PROGRAM_ARGUMENT drops the first argument in the update_emp program:

```
DBMS_SCHEDULER.DROP_PROGRAM_ARGUMENT('update_emp', 1);
```

The following call to DROP_PROGRAM_ARGUMENT drops an argument named emp_name:

```
DBMS_SCHEDULER.DROP_PROGRAM_ARGUMENT(update_emp', 'emp_name');
```

3.15.10 DROP SCHEDULE

Use the DROP_SCHEDULE procedure to drop a schedule. The signature is:

Parameters

```
<schedule_name>
  <schedule_name> specifies the name of the schedule that is being dropped.
<force>
```

<force> specifies the behavior of the server if the specified schedule is referenced by any job:

- Specify FALSE to instruct the server to return an error if the specified schedule is referenced by a job. This is the default behavior.
- Specify TRUE to instruct the server to disable to any jobs that use the specified schedule before dropping the schedule. Any running jobs will be allowed to complete before the schedule is dropped.

Example

The following call to DROP_SCHEDULE drops a schedule named weeknights_at_5:

```
DBMS_SCHEDULER.DROP_SCHEDULE('weeknights_at_5', TRUE);
```

The server will disable any jobs that use the schedule before dropping the schedule.

3.15.11 **ENABLE**

Use the ENABLE procedure to enable a disabled program or job.

The signature of the ENABLE procedure is:

```
ENABLE(
  <name> IN VARCHAR2,
  <commit_semantics> IN VARCHAR2 DEFAULT 'STOP_ON_FIRST_ERROR')
```

Parameters

<name>

<name> specifies the name of the program or job that is being enabled.

```
<commit_semantics>
```

<commit_semantics> instructs the server how to handle an error encountered while enabling a program or job. By default, <commit_semantics> is set to STOP_ON_FIRST_ERROR, instructing the
server to stop when it encounters an error.

The TRANSACTIONAL and ABSORB_ERRORS keywords are accepted for compatibility, and ignored.

Example

The following call to ${\tt DBMS_SCHEDULER}$. ${\tt ENABLE}$ enables the ${\tt update_emp}$ program:

```
DBMS_SCHEDULER.ENABLE('update_emp');
```

3.15.12 EVALUATE_CALENDAR_STRING

Use the EVALUATE_CALENDAR_STRING procedure to evaluate the <repeat_interval> value specified when creating a schedule with the CREATE_SCHEDULE procedure. The EVALUATE_CALENDAR_STRING procedure will return the date and time that a specified schedule will execute without actually scheduling the job.

The signature of the EVALUATE_CALENDAR_STRING procedure is:

```
evaluate_calendar_string(
<calendar_string> IN VARCHAR2,
<start_date> IN TIMESTAMP WITH TIME ZONE,
<return_date_after> IN TIMESTAMP WITH TIME ZONE,
<next_run_date> OUT TIMESTAMP WITH TIME ZONE)
```

Parameters

```
<calendar_string>
```

<calendar_string> is the calendar string that describes a <repeat_interval> that is being
evaluated.

```
<start_date> IN TIMESTAMP WITH TIME ZONE
```

<start_date> is the date and time after which the <repeat_interval> will become valid.

```
<return date after>
```

Use the <return_date_after parameter> to specify the date and time that EVALUATE_CALENDAR_STRING should use as a starting date when evaluating the <repeat_interval>.

For example, if you specify a <return_date_after> value of 01-APR-13 09.00.00.00.0000000, EVALUATE_CALENDAR_STRING will return the date and time of the first iteration of the schedule after April 1st, 2013.

```
<next_run_date OUT TIMESTAMP WITH TIME ZONE</pre>
```

<next_run_date> is an OUT parameter that will contain the first occurrence of the schedule after the
date specified by the <return_date_after> parameter.

Example

The following example evaluates a calendar string and returns the first date and time that the schedule will be executed after June 15, 2013:

```
DECLARE
result TIMESTAMP;
BEGIN

DBMS_SCHEDULER.EVALUATE_CALENDAR_STRING
(
    'FREQ=DAILY; BYDAY=MON, TUE, WED, THU, FRI; BYHOUR=17;',
    '15-JUN-2013', NULL, result
);

DBMS_OUTPUT.PUT_LINE('next_run_date: ' || result);
END;
/
next_run_date: 17-JUN-13 05.00.00.000000 PM
```

June 15, 2013 is a Saturday; the schedule will not execute until Monday, June 17, 2013 at 5:00 pm.

3.15.13 RUN JOB

Use the RUN_JOB procedure to execute a job immediately. The signature of the RUN_JOB procedure is:

```
run_job(
<job_name> IN VARCHAR2,
<use_current_session> IN BOOLEAN DEFAULT TRUE
```

Parameters

```
<job_name>
     <job_name> specifies the name of the job that will execute.
<use_current_session>
```

By default, the job will execute in the current session. If specified, <use_current_session> must be set to TRUE; if <use_current_session> is set to FALSE, Advanced Server will return an error.

Example

The following call to RUN_JOB executes a job named update_log:

```
DBMS_SCHEDULER.RUN_JOB('update_log', TRUE);
```

Passing a value of TRUE as the second argument instructs the server to invoke the job in the current session.

3.15.14 SET_JOB_ARGUMENT_VALUE

Use the SET_JOB_ARGUMENT_VALUE procedure to specify a value for an argument. The SET_JOB_ARGUMENT_VALUE procedure comes in two forms; the first form specifies which argument should be modified by position:

```
set_job_argument_value(
<job_name> IN VARCHAR2,
<argument_position> IN PLS_INTEGER,
<argument_value> IN VARCHAR2)
```

The second form uses an argument name to specify which argument to modify:

```
set_job_argument_value(
<job_name> IN VARCHAR2,
<argument_name> IN VARCHAR2,
<argument_value> IN VARCHAR2)
```

Argument values set by the SET_JOB_ARGUMENT_VALUE procedure override any values set by default.

Parameters

```
<job_name>
     <job_name> specifies the name of the job to which the modified argument belongs.

<argument_position>
     Use <argument_position> to specify the argument position for which the value will be set.

<argument_name>
     Use <argument_name> to specify the argument by name for which the value will be set.

<argument_value>
     <argument_value> specifies the new value of the argument.
```

Examples

The following example assigns a value of 30 to the first argument in the update_emp job:

```
DBMS_SCHEDULER.SET_JOB_ARGUMENT_VALUE('update_emp', 1, '30');
```

The following example sets the emp_name argument to SMITH:

```
DBMS_SCHEDULER.SET_JOB_ARGUMENT_VALUE('update_emp', 'emp_name', 'SMITH');
```

3.16 DBMS_SESSION

Advanced Server provides support for the following DBMS_SESSION.SET_ROLE procedure:

Function/Procedure	Return	Description
	Type	
SET_ROLE(<role_cmd>)</role_cmd>	n/a	Executes a SET ROLE statement followed by the string value spec-
		ified in <role_cmd>.</role_cmd>

Advanced Server's implementation of DBMS_SESSION is a partial implementation when compared to Oracle's version. Only DBMS_SESSION.SET_ROLE is supported.

3.16.1 **SET_ROLE**

The SET_ROLE procedure sets the current session user to the role specified in <role_cmd>. After invoking the SET_ROLE procedure, the current session will use the permissions assigned to the specified role. The signature of the procedure is:

```
SET_ROLE(<role_cmd>)
```

The SET_ROLE procedure appends the value specified for <role_cmd> to the SET_ROLE statement, and then invokes the statement.

Parameters

<role_cmd>

<role_cmd> specifies a role name in the form of a string value.

Example

The following call to the SET_ROLE procedure invokes the SET_ROLE command to set the identity of the current session user to manager:

```
edb=# exec DBMS_SESSION.SET_ROLE('manager');
```

3.17 DBMS_SQL

The DBMS_SQL package provides an application interface compatible with Oracle databases to the EnterpriseDB dynamic SQL functionality. With DBMS_SQL you can construct queries and other commands at run time (rather than when you write the application). EnterpriseDB Advanced Server offers native support for dynamic SQL; DBMS_SQL provides a way to use dynamic SQL in a fashion compatible with Oracle databases without modifying your application.

DBMS_SQL assumes the privileges of the current user when executing dynamic SQL statements.

Function/Procedure	Function or Procedure	Return Type	Description
BIND_VARIABLE(c, name, value [, out_value_size])	Procedure	n/a	Bind a value to a variable.
BIND_VARIABLE_CHAR(c, name, value [, out_value_size])	Procedure	n/a	Bind a CHAR value to a variable.
BIND_VARIABLE_RAW(c, name, value [, out_value_size])	Procedure	n/a	Bind a RAW value to a variable.
CLOSE_CURSOR(c IN OUT)	Procedure	n/a	Close a cursor.
COLUMN_VALUE(c, position, value OUT [, column_error OUT [, actual_length OUT]])	Procedure	n/a	Return a column value into a variable.
COLUMN_VALUE_CHAR(c, position, value OUT [, column_error OUT [, actual_length OUT]])	Procedure	n/a	Return a CHAR column value into a variable.
COLUMN_VALUE_RAW(c, position, value OUT [, column_error OUT [, actual_length OUT]])	Procedure	n/a	Return a RAW column value into a variable.
DEFINE_COLUMN(c, position, column [, column_size])	Procedure	n/a	Define a column in the SELECT list.
DEFINE_COLUMN_CHAR(c, position, column, column_size)	Procedure	n/a	Define a CHAR column in the SELECT list.
DEFINE_COLUMN_RAW(c, position, column, column_size)	Procedure	n/a	Define a RAW column in the SELECT list.
DESCRIBE_COLUMNS	Procedure	n/a	Defines columns to hold a cursor result set.
EXECUTE(c)	Function	INTEGER	Execute a cursor.
EXECUTE_AND_FETCH(c [, exact])	Function	INTEGER	Execute a cursor and fetch a single row.
FETCH_ROWS(c)	Function	INTEGER	Fetch rows from the cursor.
IS_OPEN(c)	Function	BOOLEAN	Check if a cursor is open.
LAST_ROW_COUNT	Function	INTEGER	Return cumulative number of rows fetched.
OPEN_CURSOR	Function	INTEGER	Open a cursor.
PARSE(c, statement, language_flag)	Procedure	n/a	Parse a statement.

Database Compability for Oracle® Developers Built-in Package Guide, Release 12

Advanced Server's implementation of $DBMS_SQL$ is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The following table lists the public variable available in the DBMS_SQL package.

Public Variables	Data Type	Value	Description			
native	INTEGER	1	Provided for compatibility with Oracle syntax. S	See		
			DBMS_SQL.PARSE for more information.			
V6	INTEGER	2	Provided for compatibility with Oracle syntax. S	See		
			DBMS_SQL.PARSE for more information.			
V7	INTEGER	3	Provided for compatibility with Oracle syntax. S	See		
			DBMS_SQL.PARSE for more information			

3.17.1 BIND VARIABLE

The BIND_VARIABLE procedure provides the capability to associate a value with an IN or IN OUT bind variable in a SQL command.

Parameters

<c>

Cursor ID of the cursor for the SQL command with bind variables.

<name>

Name of the bind variable in the SQL command.

<value>

Value to be assigned.

```
<out_value_size>
```

If <name> is an IN OUT variable, defines the maximum length of the output value. If not specified, the length of <value> is assumed.

Examples

The following anonymous block uses bind variables to insert a row into the emp table.

```
curid
                  INTEGER;
   v_sql
                  VARCHAR2(150) := 'INSERT INTO emp VALUES ' ||
                      '(:p_empno, :p_ename, :p_job, :p_mgr, ' ||
                      ':p_hiredate, :p_sal, :p_comm, :p_deptno)';
   v_empno
                  emp.empno%TYPE;
                 emp.ename%TYPE;
   v_ename
   v_job
                 emp.job%TYPE;
   v_mqr
                 emp.mgr%TYPE;
   v comm
                 emp.comm%TYPE;
   v_deptno
                  emp.deptno%TYPE;
                  INTEGER:
   v_status
BEGIN
   curid := DBMS_SQL.OPEN_CURSOR;
   DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
   v_empno := 9001;
   v_ename := 'JONES';
   v_job := 'SALESMAN';
            := 7369;
   v_hiredate := TO_DATE('13-DEC-07','DD-MON-YY');
   v sal := 8500.00;
            := 1500.00;
   v_comm
   v deptno := 40;
   DBMS_SQL.BIND_VARIABLE(curid, ':p_empno', v_empno);
   DBMS_SQL.BIND_VARIABLE(curid,':p_ename',v_ename);
   DBMS_SQL.BIND_VARIABLE(curid,':p_job',v_job);
```

```
DBMS_SQL.BIND_VARIABLE(curid,':p_mgr',v_mgr);
DBMS_SQL.BIND_VARIABLE(curid,':p_hiredate',v_hiredate);
DBMS_SQL.BIND_VARIABLE(curid,':p_sal',v_sal);
DBMS_SQL.BIND_VARIABLE(curid,':p_comm',v_comm);
DBMS_SQL.BIND_VARIABLE(curid,':p_deptno',v_deptno);
v_status := DBMS_SQL.EXECUTE(curid);
DBMS_OUTPUT_PUT_LINE('Number of rows processed: ' || v_status);
DBMS_SQL.CLOSE_CURSOR(curid);
END;
Number of rows processed: 1
```

3.17.2 BIND_VARIABLE_CHAR

The $BIND_VARIABLE_CHAR$ procedure provides the capability to associate a CHAR value with an IN or IN OUT bind variable in a SQL command.

```
BIND_VARIABLE_CHAR(<c> INTEGER, <name> VARCHAR2, <value> CHAR
[, <out_value_size> INTEGER ])
```

Parameters

<c>

Cursor ID of the cursor for the SQL command with bind variables.

<name>

Name of the bind variable in the SQL command.

<value>

Value of type CHAR to be assigned.

```
<out_value_size>
```

If <name> is an IN OUT variable, defines the maximum length of the output value. If not specified, the length of <value> is assumed.

3.17.3 BIND VARIABLE RAW

The BIND_VARIABLE_RAW procedure provides the capability to associate a RAW value with an IN or IN OUT bind variable in a SQL command.

```
BIND_VARIABLE_RAW(<c> INTEGER, <name> VARCHAR2, <value> RAW
[, <out_value_size> INTEGER ])
```

Parameters

<c>

Cursor ID of the cursor for the SQL command with bind variables.

<name>

Name of the bind variable in the SQL command.

<value>

Value of type RAW to be assigned.

```
<out_value_size>
```

If <name> is an IN OUT variable, defines the maximum length of the output value. If not specified, the length of <value> is assumed.

3.17.4 CLOSE_CURSOR

The CLOSE_CURSOR procedure closes an open cursor. The resources allocated to the cursor are released and it can no longer be used.

```
CLOSE_CURSOR(<c> IN OUT INTEGER)
```

Parameters

<c>

Cursor ID of the cursor to be closed.

Examples

The following example closes a previously opened cursor:

3.17.5 COLUMN VALUE

The COLUMN_VALUE procedure defines a variable to receive a value from a cursor.

```
COLUMN_VALUE(<c> INTEGER, <position> INTEGER, <value> OUT { BLOB | CLOB | DATE | FLOAT | INTEGER | NUMBER | TIMESTAMP | VARCHAR2 } [, <column_error> OUT NUMBER [, <actual_length> OUT INTEGER ]])
```

Parameters

<c>

Cursor id of the cursor returning data to the variable being defined.

<position>

Position within the cursor of the returned data. The first value in the cursor is position 1.

<value>

Variable receiving the data returned in the cursor by a prior fetch call.

<column error>

Error number associated with the column, if any.

```
<actual_length>
```

Actual length of the data prior to any truncation.

Examples

The following example shows the portion of an anonymous block that receives the values from a cursor using the COLUMN_VALUE procedure.

```
DECLARE
   curid
                  INTEGER;
   v_empno
v_ename
                 NUMBER (4);
                 VARCHAR2(10);
   v_hiredate DATE;
v_sal NUMBER(7,2);
   v_comm
                                 'comm FROM emp';
              INTEGER;
   v_status
BEGIN
   LOOP
       v_status := DBMS_SQL.FETCH_ROWS(curid);
       EXIT WHEN v_status = 0;
       DBMS_SQL.COLUMN_VALUE(curid, 1, v_empno);
       DBMS_SQL.COLUMN_VALUE(curid, 2, v_ename);
       DBMS_SQL.COLUMN_VALUE(curid, 3, v_hiredate);
       DBMS_SQL.COLUMN_VALUE(curid, 4, v_sal);
       DBMS_SQL.COLUMN_VALUE(curid, 4, v_sal);
       DBMS_SQL.COLUMN_VALUE(curid, 5, v_comm);
       DBMS_OUTPUT_LINE(v_empno || ' ' || RPAD(v_ename,10) || ' ' ||
          TO_CHAR(v_hiredate,'yyyy-mm-dd') || ' ' ||
           TO_CHAR(v_sal, '9, 999.99') || ' ' ||
           TO_CHAR(NVL(v_comm, 0), '9, 999.99'));
```

```
END LOOP;
  DBMS_SQL.CLOSE_CURSOR(curid);
END;
```

3.17.6 COLUMN_VALUE_CHAR

```
The COLUMN_VALUE_CHAR procedure defines a variable to receive a CHAR value from a cursor.
```

```
COLUMN_VALUE_CHAR(<c> INTEGER, <position> INTEGER, <value> OUT CHAR
[, <column_error> OUT NUMBER [, <actual_length> OUT INTEGER ]])
```

Parameters

<c>

Cursor id of the cursor returning data to the variable being defined.

<position>

Position within the cursor of the returned data. The first value in the cursor is position 1.

<value>

Variable of data type CHAR receiving the data returned in the cursor by a prior fetch call.

<column_error>

Error number associated with the column, if any.

<actual_length>

Actual length of the data prior to any truncation.

3.17.7 COLUMN VALUE RAW

```
The COLUMN_VALUE_RAW procedure defines a variable to receive a RAW value from a cursor.
```

```
COLUMN_VALUE_RAW(<c> INTEGER, <position> INTEGER, <value> OUT RAW
[, <column_error> OUT NUMBER [, <actual_length> OUT INTEGER ]])
```

Parameters

<c>

Cursor id of the cursor returning data to the variable being defined.

<position>

Position within the cursor of the returned data. The first value in the cursor is position 1.

<value>

Variable of data type RAW receiving the data returned in the cursor by a prior fetch call.

<column_error>

Error number associated with the column, if any.

<actual_length>

Actual length of the data prior to any truncation.

3.17.8 DEFINE COLUMN

The DEFINE_COLUMN procedure defines a column or expression in the SELECT list that is to be returned and retrieved in a cursor.

```
DEFINE_COLUMN(<c> INTEGER, <position> INTEGER, <column> { BLOB |
    CLOB | DATE | FLOAT | INTEGER | NUMBER | TIMESTAMP | VARCHAR2 }
    [, <column_size> INTEGER ])
```

Parameters

<c>

Cursor id of the cursor associated with the SELECT command.

<position>

Position of the column or expression in the SELECT list that is being defined.

<column>

A variable that is of the same data type as the column or expression in position <position> of the SELECT list.

```
<column_size>
```

The maximum length of the returned data. <column_size> must be specified only if <column> is VARCHAR2. Returned data exceeding <column_size> is truncated to <column_size> characters.

Examples

The following shows how the empno, ename, hiredate, sal, and comm columns of the emp table are defined with the DEFINE_COLUMN procedure.

```
DECLARE
   curid
                   INTEGER;
   v_empno
                   NUMBER (4);
                   VARCHAR2(10);
   v_ename
   v_hiredate
                  DATE;
   v_sal
                  NUMBER (7,2);
                  NUMBER (7,2);
   v_comm
                   VARCHAR2(50) := 'SELECT empno, ename, hiredate, sal, ' ||
   v_sql
                                    'comm FROM emp';
   v_status INTEGER;
BEGIN
   curid := DBMS_SQL.OPEN_CURSOR;
   DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
   DBMS_SQL.DEFINE_COLUMN(curid, 1, v_empno);
   DBMS_SQL.DEFINE_COLUMN(curid, 2, v_ename, 10);
   DBMS_SQL.DEFINE_COLUMN(curid, 3, v_hiredate);
   DBMS_SQL.DEFINE_COLUMN(curid, 4, v_sal);
   DBMS_SQL.DEFINE_COLUMN(curid, 5, v_comm);
END:
```

The following shows an alternative to the prior example that produces the exact same results. Note that the lengths of the data types are irrelevant – the empno, sal, and comm columns will still return data equivalent to NUMBER (4) and NUMBER (7,2), respectively, even though v_num is defined as NUMBER (1) (assuming the declarations in the COLUMN_VALUE procedure are of the appropriate maximum sizes). The ename column will return data up to ten characters in length as defined by the <length> parameter in the DEFINE_COLUMN call, not by the data type declaration, VARCHAR2 (1) declared for v_varchar. The actual size of the returned data is dictated by the COLUMN_VALUE procedure.

```
DECLARE
   curid
                    INTEGER;
   v_num
                    NUMBER (1);
                    VARCHAR2(1);
   v_varchar
   v_date
                    DATE:
                    VARCHAR2(50) := 'SELECT empno, ename, hiredate, sal, ' ||
    v_sql
                                      'comm FROM emp';
    v_status
                    INTEGER;
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
    DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
   DBMS_SQL.DEFINE_COLUMN(curid,1,v_num);
   DBMS_SQL.DEFINE_COLUMN(curid, 2, v_varchar, 10);
   DBMS_SQL.DEFINE_COLUMN(curid, 3, v_date);
    DBMS_SQL.DEFINE_COLUMN(curid, 4, v_num);
    DBMS_SQL.DEFINE_COLUMN(curid, 5, v_num);
END;
```

3.17.9 DEFINE_COLUMN_CHAR

The DEFINE_COLUMN_CHAR procedure defines a CHAR column or expression in the SELECT list that is to be returned and retrieved in a cursor.

```
DEFINE_COLUMN_CHAR(<c> INTEGER, <position> INTEGER, <column> CHAR, <column_size> INTEGER)
```

Parameters

<c>

Cursor id of the cursor associated with the SELECT command.

<position>

Position of the column or expression in the SELECT list that is being defined.

<column>

A CHAR variable.

<column_size>

The maximum length of the returned data. Returned data exceeding <column_size> is truncated to <column_size> characters.

3.17.10 DEFINE_COLUMN_RAW

The DEFINE_COLUMN_RAW procedure defines a RAW column or expression in the SELECT list that is to be returned and retrieved in a cursor.

```
DEFINE_COLUMN_RAW(<c> INTEGER, <position> INTEGER, <column> RAW,
<column_size> INTEGER)
```

Parameters

<c>

Cursor id of the cursor associated with the SELECT command.

<position>

Position of the column or expression in the SELECT list that is being defined.

<column>

A RAW variable.

<column_size>

The maximum length of the returned data. Returned data exceeding <column_size> is truncated to <column_size> characters.

3.17.11 DESCRIBE COLUMNS

The DESCRIBE_COLUMNS procedure describes the columns returned by a cursor.

DESCRIBE_COLUMNS(c INTEGER, col_cnt OUT INTEGER, desc_t OUT
DESC_TAB);

Parameters

<c>

The cursor ID of the cursor.

<col_cnt>

The number of columns in cursor result set.

<desc_tab>

The table that contains a description of each column returned by the cursor. The descriptions are of type DESC_REC, and contain the following values:

Column Name	Туре
col_type	INTEGER
col_max_len	INTEGER
col_name	VARCHAR2(128)
col_name_len	INTEGER
col_schema_name	VARCHAR2(128)
col_schema_name_len	INTEGER
col_precision	INTEGER
col_scale	INTEGER
col_charsetid	INTEGER
col_charsetform	INTEGER
col_null_ok	BOOLEAN

3.17.12 EXECUTE

The EXECUTE function executes a parsed SQL command or SPL block.

```
<status> INTEGER EXECUTE(<c> INTEGER)
```

Parameters

<c>

Cursor ID of the parsed SQL command or SPL block to be executed.

```
<status>
```

Number of rows processed if the SQL command was DELETE, INSERT, or UPDATE. <status> is meaningless for all other commands.

Examples

The following anonymous block inserts a row into the dept table.

```
DECLARE

curid INTEGER;

v_sql VARCHAR2(50);

v_status INTEGER;

BEGIN

curid := DBMS_SQL.OPEN_CURSOR;

v_sql := 'INSERT INTO dept VALUES (50, ''HR'', ''LOS ANGELES'')';

DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);

v_status := DBMS_SQL.EXECUTE(curid);

DBMS_OUTPUT_LINE('Number of rows processed: ' || v_status);

DBMS_SQL.CLOSE_CURSOR(curid);

END;
```

3.17.13 EXECUTE_AND_FETCH

Function EXECUTE AND FETCH executes a parsed SELECT command and fetches one row.

```
<status> INTEGER EXECUTE_AND_FETCH(<c> INTEGER
[, <exact> BOOLEAN ])
```

Parameters

<c>

Cursor id of the cursor for the SELECT command to be executed.

<exact>

If set to TRUE, an exception is thrown if the number of rows in the result set is not exactly equal to 1. If set to FALSE, no exception is thrown. The default is FALSE. A NO_DATA_FOUND exception is thrown if <exact> is TRUE and there are no rows in the result set. A TOO_MANY_ROWS exception is thrown if <exact> is TRUE and there is more than one row in the result set.

<status>

Returns 1 if a row was successfully fetched, 0 if no rows to fetch. If an exception is thrown, no value is returned.

Examples

The following stored procedure uses the EXECUTE_AND_FETCH function to retrieve one employee using the employee's name. An exception will be thrown if the employee is not found, or there is more than one employee with the same name.

```
CREATE OR REPLACE PROCEDURE select_by_name(
    p_ename emp.ename%TYPE
IS
    curid
   curid INTEGER;

v_empno emp.empno%TYPE;

v_hiredate emp.hiredate%TYPE;

v_sal emp.sal%TYPE;

v_comm emp.comm%TYPE;

v_dname dept.dname%TYPE;

v_disp_date VARCHAR2(10);
                      INTEGER:
    v_sql
                       VARCHAR2(120) := 'SELECT empno, hiredate, sal, ' ||
                                            'NVL(comm, 0), dname ' ||
                                            'FROM emp e, dept d ' ||
                                            'WHERE ename = :p_ename ' ||
                                            'AND e.deptno = d.deptno';
                       INTEGER;
    v status
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
    DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
    DBMS_SQL.BIND_VARIABLE(curid,':p_ename',UPPER(p_ename));
    DBMS_SQL.DEFINE_COLUMN(curid, 1, v_empno);
    DBMS_SQL.DEFINE_COLUMN(curid, 2, v_hiredate);
    DBMS_SQL.DEFINE_COLUMN(curid, 3, v_sal);
    DBMS_SQL.DEFINE_COLUMN(curid, 4, v_comm);
    DBMS_SQL.DEFINE_COLUMN (curid, 5, v_dname, 14);
    v_status := DBMS_SQL.EXECUTE_AND_FETCH(curid,TRUE);
    DBMS_SQL.COLUMN_VALUE(curid, 1, v_empno);
    DBMS_SQL.COLUMN_VALUE(curid, 2, v_hiredate);
    DBMS_SQL.COLUMN_VALUE(curid, 3, v_sal);
```

```
DBMS_SQL.COLUMN_VALUE(curid, 4, v_comm);
   DBMS_SQL.COLUMN_VALUE(curid, 5, v_dname);
   v_disp_date := TO_CHAR(v_hiredate, 'MM/DD/YYYY');
   DBMS_OUTPUT.PUT_LINE('Number : ' || v_empno);
                                  : ' || UPPER(p_ename));
   DBMS_OUTPUT.PUT_LINE('Name
   DBMS_OUTPUT.PUT_LINE('Hire Date : ' || v_disp_date);
   DBMS_OUTPUT.PUT_LINE('Salary : ' || v_sal);
   DBMS_OUTPUT.PUT_LINE('Commission: ' || v_comm);
   DBMS_OUTPUT.PUT_LINE('Department: ' || v_dname);
   DBMS_SQL.CLOSE_CURSOR(curid);
EXCEPTION
   WHEN NO_DATA_FOUND THEN
       DBMS_OUTPUT.PUT_LINE('Employee ' || p_ename || ' not found');
       DBMS_SQL.CLOSE_CURSOR(curid);
   WHEN TOO_MANY_ROWS THEN
       DBMS_OUTPUT.PUT_LINE('Too many employees named, ' ||
           p_ename || ', found');
       DBMS_SQL.CLOSE_CURSOR(curid);
   WHEN OTHERS THEN
       DBMS_OUTPUT.PUT_LINE('The following is SQLERRM:');
       DBMS_OUTPUT.PUT_LINE(SQLERRM);
       DBMS_OUTPUT.PUT_LINE('The following is SQLCODE:');
       DBMS_OUTPUT.PUT_LINE(SQLCODE);
       DBMS_SQL.CLOSE_CURSOR(curid);
END;
EXEC select_by_name('MARTIN')
Number: 7654
Name
        : MARTIN
Hire Date : 09/28/1981
Salary: 1250
Commission: 1400
Department: SALES
```

3.17.14 FETCH ROWS

The FETCH ROWS function retrieves a row from a cursor.

```
<status> INTEGER FETCH_ROWS(<c> INTEGER)
```

Parameters

<c>

Cursor ID of the cursor from which to fetch a row.

<status>

Returns 1 if a row was successfully fetched, 0 if no more rows to fetch.

Examples

The following examples fetches the rows from the emp table and displays the results.

```
INTEGER;
   curid
   v_empno
                 NUMBER(4);
   v_ename
                  VARCHAR2(10);
   v_hiredate DATE;
                  NUMBER (7,2);
   v_sal
            NUMBER (7, 2);
   v comm
   v_sql
                  VARCHAR2(50) := 'SELECT empno, ename, hiredate, sal, ' ||
                                   'comm FROM emp';
   v_status
                 INTEGER;
BEGIN
   curid := DBMS_SQL.OPEN_CURSOR;
   DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
   DBMS_SQL.DEFINE_COLUMN(curid, 1, v_empno);
   DBMS_SQL.DEFINE_COLUMN(curid, 2, v_ename, 10);
   DBMS_SQL.DEFINE_COLUMN(curid, 3, v_hiredate);
   DBMS_SQL.DEFINE_COLUMN(curid, 4, v_sal);
   DBMS_SQL.DEFINE_COLUMN(curid, 5, v_comm);
   v_status := DBMS_SQL.EXECUTE(curid);
   DBMS_OUTPUT.PUT_LINE('EMPNO ENAME
                                          HIREDATE SAL
                                                                 COMM');
   DBMS OUTPUT.PUT LINE('---- ------
                                                                 ' 11
       '----'):
   LOOP
       v_status := DBMS_SQL.FETCH_ROWS(curid);
       EXIT WHEN v_status = 0;
       DBMS_SQL.COLUMN_VALUE(curid, 1, v_empno);
       DBMS_SQL.COLUMN_VALUE(curid, 2, v_ename);
       DBMS_SQL.COLUMN_VALUE(curid, 3, v_hiredate);
       DBMS_SQL.COLUMN_VALUE(curid, 4, v_sal);
       DBMS_SQL.COLUMN_VALUE(curid, 4, v_sal);
       DBMS_SQL.COLUMN_VALUE(curid, 5, v_comm);
       DBMS_OUTPUT_LINE(v_empno || ' ' || RPAD(v_ename, 10) || ' ' ||
           TO_CHAR(v_hiredate,'yyyy-mm-dd') || ' ' ||
           TO_CHAR(v_sal, '9, 999.99') || ' ' ||
           TO_CHAR(NVL(v_comm, 0), '9, 999.99'));
   END LOOP;
   DBMS_SQL.CLOSE_CURSOR(curid);
END;
EMPNO ENAME
                 HIREDATE
                             SAL
                                        COMM
```

7369	SMITH	1980-12-17	800.00	.00
7499	ALLEN	1981-02-20	1,600.00	300.00
7521	WARD	1981-02-22	1,250.00	500.00
7566	JONES	1981-04-02	2,975.00	.00
7654	MARTIN	1981-09-28	1,250.00	1,400.00
7698	BLAKE	1981-05-01	2,850.00	.00
7782	CLARK	1981-06-09	2,450.00	.00
7788	SCOTT	1987-04-19	3,000.00	.00
7839	KING	1981-11-17	5,000.00	.00
7844	TURNER	1981-09-08	1,500.00	.00
7876	ADAMS	1987-05-23	1,100.00	.00
7900	JAMES	1981-12-03	950.00	.00
7902	FORD	1981-12-03	3,000.00	.00
7934	MILLER	1982-01-23	1,300.00	.00

3.17.15 IS_OPEN

The IS_OPEN function provides the capability to test if the given cursor is open.

```
<status> BOOLEAN IS_OPEN(<c> INTEGER)
```

Parameters

<c>

Cursor ID of the cursor to be tested.

<status>

Set to TRUE if the cursor is open, set to FALSE if the cursor is not open.

3.17.16 LAST_ROW_COUNT

The LAST_ROW_COUNT function returns the number of rows that have been currently fetched.

```
<rowcnt> INTEGER LAST_ROW_COUNT
```

Parameters

<rowcnt>

Number of row fetched thus far.

Examples

The following example uses the LAST ROW COUNT function to display the total number of rows fetched in the query.

```
DECLARE
                 INTEGER;
  curid
   v_empno
v_ename
                 NUMBER(4);
                  VARCHAR2 (10);
   VARCHAR2(50) := 'SELECT empno, ename, hiredate, sal, ' ||
                                  'comm FROM emp';
   v_status INTEGER;
BEGIN
   curid := DBMS_SQL.OPEN_CURSOR;
   DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
   DBMS_SQL.DEFINE_COLUMN(curid, 1, v_empno);
   DBMS_SQL.DEFINE_COLUMN(curid, 2, v_ename, 10);
   DBMS_SQL.DEFINE_COLUMN(curid, 3, v_hiredate);
   DBMS_SQL.DEFINE_COLUMN(curid, 4, v_sal);
   DBMS_SQL.DEFINE_COLUMN(curid, 5, v_comm);
   v_status := DBMS_SQL.EXECUTE(curid);
   DBMS_OUTPUT.PUT_LINE('EMPNO ENAME HIREDATE SAL COMM');
   DBMS_OUTPUT.PUT_LINE('---- ------
                                                       ----- ' ||
       '----');
   LOOP
       v_status := DBMS_SQL.FETCH_ROWS(curid);
       EXIT WHEN v_status = 0;
       DBMS_SQL.COLUMN_VALUE(curid,1,v_empno);
       DBMS_SQL.COLUMN_VALUE(curid, 2, v_ename);
       DBMS_SQL.COLUMN_VALUE(curid, 3, v_hiredate);
       DBMS_SQL.COLUMN_VALUE(curid, 4, v_sal);
       DBMS_SQL.COLUMN_VALUE(curid, 4, v_sal);
       DBMS_SQL.COLUMN_VALUE(curid, 5, v_comm);
       DBMS_OUTPUT.PUT_LINE(v_empno || ' ' || RPAD(v_ename,10) || ' ' ||
           TO_CHAR(v_hiredate,'yyyy-mm-dd') || ' ' ||
           TO_CHAR(v_sal, '9,999.99') || ' ' ||
           TO_CHAR(NVL(v_comm, 0), '9, 999.99'));
   END LOOP;
   DBMS_OUTPUT.PUT_LINE('Number of rows: ' | DBMS_SQL.LAST_ROW_COUNT);
   DBMS_SQL.CLOSE_CURSOR(curid);
END;
EMPNO ENAME HIREDATE SAL COMM
7369 SMITH 1980-12-17 800.00 .00
7499 ALLEN 1981-02-20 1,600.00 300.00
```

7521	WARD	1981-02-22	1,250.00	500.00
7566	JONES	1981-04-02	2,975.00	.00
7654	MARTIN	1981-09-28	1,250.00	1,400.00
7698	BLAKE	1981-05-01	2,850.00	.00
7782	CLARK	1981-06-09	2,450.00	.00
7788	SCOTT	1987-04-19	3,000.00	.00
7839	KING	1981-11-17	5,000.00	.00
7844	TURNER	1981-09-08	1,500.00	.00
7876	ADAMS	1987-05-23	1,100.00	.00
7900	JAMES	1981-12-03	950.00	.00
7902	FORD	1981-12-03	3,000.00	.00
7934	MILLER	1982-01-23	1,300.00	.00
Number	of rows: 14			

3.17.17 OPEN_CURSOR

The OPEN_CURSOR function creates a new cursor. A cursor must be used to parse and execute any dynamic SQL statement. Once a cursor has been opened, it can be re-used with the same or different SQL statements. The cursor does not have to be closed and re-opened in order to be re-used.

```
<c> INTEGER OPEN_CURSOR
```

Parameters

<c>

Cursor ID number associated with the newly created cursor.

Examples

The following example creates a new cursor:

```
DECLARE
curid INTEGER;

BEGIN
curid := DBMS_SQL.OPEN_CURSOR;
.
.
.
END;
```

3.17.18 PARSE

The PARSE procedure parses a SQL command or SPL block. If the SQL command is a DDL command, it is immediately executed and does not require running the EXECUTE function.

```
PARSE(<c> INTEGER, <statement> VARCHAR2, <language_flag> INTEGER)
```

Parameters

<c>

Cursor ID of an open cursor.

```
<statement>
```

SQL command or SPL block to be parsed. A SQL command must not end with the semi-colon terminator, however an SPL block does require the semi-colon terminator.

```
<language_flag>
```

Language flag provided for compatibility with Oracle syntax. Use DBMS_SQL.V6, DBMS_SQL.V7 or DBMS_SQL.native. This flag is ignored, and all syntax is assumed to be in EnterpriseDB Advanced Server form.

Examples

The following anonymous block creates a table named, job. Note that DDL statements are executed immediately by the PARSE procedure and do not require a separate EXECUTE step.

The following inserts two rows into the job table.

```
DECLARE
   curid
                    INTEGER;
   v_sql
                    VARCHAR2 (50);
                    INTEGER;
   v_status
BEGIN
   curid := DBMS_SQL.OPEN_CURSOR;
   v_sql := 'INSERT INTO job VALUES (100, ''ANALYST'')';
   DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
   v_status := DBMS_SQL.EXECUTE(curid);
   DBMS_OUTPUT.PUT_LINE('Number of rows processed: ' || v_status);
   v_sql := 'INSERT INTO job VALUES (200, ''CLERK'')';
   DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
   v_status := DBMS_SQL.EXECUTE(curid);
   DBMS_OUTPUT.PUT_LINE('Number of rows processed: ' || v_status);
   DBMS_SQL.CLOSE_CURSOR(curid);
END;
Number of rows processed: 1
Number of rows processed: 1
```

The following anonymous block uses the DBMS_SQL package to execute a block containing two INSERT statements. Note that the end of the block contains a terminating semi-colon, while in the prior example, each individual INSERT statement does not have a terminating semi-colon.

```
DECLARE
   curid
                  INTEGER;
   v_sql
                   VARCHAR2(100);
   v_status
                   INTEGER;
BEGIN
   curid := DBMS_SQL.OPEN_CURSOR;
   v_sql := 'BEGIN ' ||
               'INSERT INTO job VALUES (300, ''MANAGER''); ' ||
               'INSERT INTO job VALUES (400, ''SALESMAN''); ' ||
             'END;';
   DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
   v_status := DBMS_SQL.EXECUTE(curid);
   DBMS_SQL.CLOSE_CURSOR(curid);
END;
```

3.18 DBMS_UTILITY

The DBMS_UTILITY package provides support for the following various utility programs:

Function/Procedure	Function	Return Type	Description
	or Pro-		F
	cedure		
ANALYZE_DATABASE(method [,	Procedure	n/a	Analyze database tables.
estimate_rows [, estimate_percent [,			
method_opt]]])			
ANALYZE_PART_OBJECT(schema, ob-	Procedure	n/a	Analyze a partitioned table.
ject_name [, object_type [, command_type			J 1
[, command_opt [, sample_clause]]]])			
ANALYZE_SCHEMA(schema, method	Procedure	n/a	Analyze schema tables.
[, estimate_rows [, estimate_percent [,			•
method_opt]]])			
CANONICALIZE(name, canon_name	Procedure	n/a	Canonicalizes a string – e.g.,
OUT, canon_len)			strips off white space.
COMMA_TO_TABLE(list, tablen OUT,	Procedure	n/a	Convert a comma-delimited list
tab OUT)			of names to a table of names.
DB_VERSION(version OUT, compatibility	Procedure	n/a	Get the database version.
OUT)			
EXEC_DDL_STATEMENT(parse_string)	Procedure	n/a	Execute a DDL statement.
FORMAT_CALL_STACK	Function	TEXT	Formats the current call stack.
GET_CPU_TIME	Function	NUMBER	Get the current CPU time.
GET_DEPENDENCY(type, schema,	Procedure	n/a	Get objects that are dependent
name)			upon the given object
GET_HASH_VALUE(name, base,	Function	NUMBER	Compute a hash value.
hash_size)			
GET_PARAMETER_VALUE(parnam, int-	Procedure	BINARY_INTEGER	Get database initialization pa-
val OUT, strval OUT)		rameter settings.	
GET_TIME	Function	NUMBER	Get the current time.
NAME_TOKENIZE(name, a OUT, b OUT,	Procedure	n/a	Parse the given name into its
c OUT, dblink OUT, nextpos OUT)			component parts.
TABLE_TO_COMMA(tab, tablen OUT,	Procedure	n/a	Convert a table of names to a
list OUT)			comma-delimited list.

Advanced Server's implementation of DBMS_UTILITY is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The following table lists the public variables available in the ${\tt DBMS_UTILITY}$ package.

Public Variables	Data Type	Value	Description
inv_error_on_restrictions	PLS_INTEGER	1	Used by the INVALIDATE pro-
			cedure.
lname_array	TABLE		For lists of long names.
uncl_array	TABLE		For lists of users and names.

3.18. DBMS_UTILITY 240

3.18.1 LNAME_ARRAY

The LNAME_ARRAY is for storing lists of long names including fully-qualified names.

TYPE lname_array IS `TABLE OF VARCHAR2(4000) INDEX BY BINARY_INTEGER;

3.18.2 UNCL_ARRAY

The UNCL_ARRAY is for storing lists of users and names.

TYPE uncl_array IS TABLE OF VARCHAR2(227) INDEX BY BINARY_INTEGER;

3.18.3 ANALYZE_DATABASE, ANALYZE SCHEMA and ANALYZE PART_OBJECT

The ANALYZE_DATABASE(), ANALYZE_SCHEMA() and ANALYZE_PART_OBJECT() procedures provide the capability to gather statistics on tables in the database. When you execute the ANALYZE statement, Postgres samples the data in a table and records distribution statistics in the pg_statistics system table.

ANALYZE_DATABASE, ANALYZE_SCHEMA, and ANALYZE_PART_OBJECT differ primarily in the number of tables that are processed:

- ANALYZE_DATABASE analyzes all tables in all schemas within the current database.
- ANALYZE_SCHEMA analyzes all tables in a given schema (within the current database).
- ANALYZE_PART_OBJECT analyzes a single table.

The syntax for the ANALYZE commands are:

Parameters - ANALYZE_DATABASE and ANALYZE_SCHEMA

<method>

method determines whether the ANALYZE procedure populates the pg_statistics table or removes entries from the pg_statistics table. If you specify a method of DELETE, the ANALYZE procedure removes the relevant rows from pg_statistics. If you specify a method of COMPUTE or ESTIMATE, the ANALYZE procedure analyzes a table (or multiple tables) and records the distribution information in pg_statistics. There is no difference between COMPUTE and ESTIMATE; both methods execute the Postgres ANALYZE statement. All other parameters are validated and then ignored.

```
<estimate_rows>
```

Number of rows upon which to base estimated statistics. One of <estimate_rows> or <estimate_percent> must be specified if method is ESTIMATE.

This argument is ignored, but is included for compatibility.

```
<estimate_percent>
```

Percentage of rows upon which to base estimated statistics. One of <estimate_rows> or <estimate_percent> must be specified if method is ESTIMATE.

This argument is ignored, but is included for compatibility.

<method opt>

Object types to be analyzed. Any combination of the following:

```
[FOR TABLE]
[FOR ALL [ INDEXED ] COLUMNS ] [ SIZE n]
[FOR ALL INDEXES]
```

This argument is ignored, but is included for compatibility.

```
Parameters - ANALYZE PART OBJECT
```

<schema>

Name of the schema whose objects are to be analyzed.

```
<object_name>
```

Name of the partitioned object to be analyzed.

```
<object_type>
```

Type of object to be analyzed. Valid values are: T – table, I – index.

This argument is ignored, but is included for compatibility.

```
<command_type>
```

Type of analyze functionality to perform. Valid values are: E - gather estimated statistics based upon on a specified number of rows or a percentage of rows in the $<sample_clause>$ clause; C - compute exact statistics; or V - validate the structure and integrity of the partitions.

This argument is ignored, but is included for compatibility.

```
<command_opt>
```

For <command_type> C or E, can be any combination of:

```
[FOR TABLE]
[FOR ALL COLUMNS]
[FOR ALL LOCAL INDEXES]
```

For <command_type> V, can be CASCADE if <object_type> is T.

This argument is ignored, but is included for compatibility.

```
<sample_clause>
```

If <command_type> is E, contains the following clause to specify the number of rows or percentage or rows on which to base the estimate.

```
SAMPLE <n> { ROWS | PERCENT }
```

This argument is ignored, but is included for compatibility.

3.18.4 CANONICALIZE

The CANONICALIZE procedure performs the following operations on an input string:

- If the string is not double-quoted, verifies that it uses the characters of a legal identifier. If not, an exception is thrown. If the string is double-quoted, all characters are allowed.
- If the string is not double-quoted and does not contain periods, uppercases all alphabetic characters and eliminates leading and trailing spaces.
- If the string is double-quoted and does not contain periods, strips off the double quotes.
- If the string contains periods and no portion of the string is double-quoted, uppercases each portion of the string and encloses each portion in double quotes.
- If the string contains periods and portions of the string are double-quoted, returns the double-quoted portions unchanged including the double quotes and returns the non-double-quoted portions uppercased and enclosed in double quotes.

```
CANONICALIZE(<name> VARCHAR2, <canon_name> OUT VARCHAR2,
<canon_len> BINARY_INTEGER)
```

Parameters

<name>

String to be canonicalized.

<canon_name>

The canonicalized string.

<canon_len>

Number of bytes in <name> to canonicalize starting from the first character.

Examples

The following procedure applies the CANONICALIZE procedure on its input parameter and displays the results.

```
CREATE OR REPLACE PROCEDURE canonicalize (
    p name
              VARCHAR2,
              BINARY_INTEGER DEFAULT 30
   p_length
TS
              VARCHAR2 (100);
    v_canon
BEGIN
    DBMS_UTILITY.CANONICALIZE(p_name, v_canon, p_length);
   DBMS_OUTPUT.PUT_LINE('Canonicalized name ==>' || v_canon || '<==');</pre>
   DBMS_OUTPUT.PUT_LINE('Length: ' | LENGTH(v_canon));
EXCEPTION
    WHEN OTHERS THEN
        DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
        DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
EXEC canonicalize('Identifier')
Canonicalized name ==>IDENTIFIER<==
Length: 10
EXEC canonicalize('"Identifier"')
Canonicalized name ==>Identifier<==
Length: 10
```

```
EXEC canonicalize('"_+142%"')
Canonicalized name ==>_+142%<==
Length: 6

EXEC canonicalize('abc.def.ghi')
Canonicalized name ==>"ABC"."DEF"."GHI"<==
Length: 17

EXEC canonicalize('"abc.def.ghi"')
Canonicalized name ==>abc.def.ghi<==
Length: 11

EXEC canonicalize('"abc".def."ghi"')
Canonicalized name ==>"abc"."DEF"."ghi"<==
Length: 17

EXEC canonicalize('"abc.def".ghi')
Canonicalized name ==>"abc.def"."GHI"<==
Length: 15
```

3.18.5 COMMA TO TABLE

The COMMA_TO_TABLE procedure converts a comma-delimited list of names into a table of names. Each entry in the list becomes a table entry. The names must be formatted as valid identifiers.

Examples

The following procedure uses the COMMA_TO_TABLE procedure to convert a list of names to a table. The table entries are then displayed.

```
CREATE OR REPLACE PROCEDURE comma_to_table (
   p_list VARCHAR2
IS
             DBMS_UTILITY.LNAME_ARRAY;
    r_lname
   v_length BINARY_INTEGER;
BEGIN
   DBMS_UTILITY.COMMA_TO_TABLE(p_list, v_length, r_lname);
   FOR i IN 1..v_length LOOP
       DBMS_OUTPUT.PUT_LINE(r_lname(i));
   END LOOP;
END;
EXEC comma_to_table('edb.dept, edb.emp, edb.jobhist')
edb.dept
edb.emp
edb.jobhist
```

3.18.6 DB VERSION

The DB_VERSION procedure returns the version number of the database.

```
DB_VERSION(<version> OUT VARCHAR2, <compatibility> OUT VARCHAR2)
```

Parameters

<version>

Database version number.

```
<compatibility>
```

Compatibility setting of the database. (To be implementation-defined as to its meaning.)

Examples

The following anonymous block displays the database version information.

```
DECLARE

v_version VARCHAR2(150);

v_compat VARCHAR2(150);

BEGIN

DBMS_UTILITY.DB_VERSION(v_version, v_compat);

DBMS_OUTPUT.PUT_LINE('Version: ' || v_version);

DBMS_OUTPUT.PUT_LINE('Compatibility: ' || v_compat);

END;

Version: EnterpriseDB 10.0.0 on i686-pc-linux-gnu, compiled by GCC gcc (GCC) 4.1.2_

-20080704 (Red Hat 4.1.2-48), 32-bit

Compatibility: EnterpriseDB 10.0.0 on i686-pc-linux-gnu, compiled by GCC gcc (GCC) 4.

-1.220080704 (Red Hat 4.1.2-48), 32-bit
```

3.18.7 EXEC DDL STATEMENT

The EXEC_DDL_STATEMENT provides the capability to execute a DDL command.

```
EXEC_DDL_STATEMENT(<parse_string> VARCHAR2)
```

Parameters

```
<parse_string>
```

The DDL command to be executed.

Examples

The following anonymous block creates the job table.

```
BEGIN

DBMS_UTILITY.EXEC_DDL_STATEMENT(

'CREATE TABLE job (' ||

'jobno NUMBER(3),' ||

'jname VARCHAR2(9))'

);

END;
```

If the <parse_string> does not include a valid DDL statement, Advanced Server returns the following error:

```
edb=# exec dbms_utility.exec_ddl_statement('select rownum from dual');
ERROR: EDB-20001: 'parse_string' must be a valid DDL statement
```

In this case, Advanced Server's behavior differs from Oracle's; Oracle accepts the invalid <parse_string> without complaint.

3.18.8 FORMAT_CALL_STACK

The FORMAT_CALL_STACK function returns the formatted contents of the current call stack.

DBMS_UTILITY.FORMAT_CALL_STACK return VARCHAR2

This function can be used in a stored procedure, function or package to return the current call stack in a readable format. This function is useful for debugging purposes.

3.18. DBMS_UTILITY 249

3.18.9 GET_CPU_TIME

The GET_CPU_TIME function returns the CPU time in hundredths of a second from some arbitrary point in time.

```
<cputime> NUMBER GET_CPU_TIME
```

Parameters

<cputime>

Number of hundredths of a second of CPU time.

Examples

The following SELECT command retrieves the current CPU time, which is 603 hundredths of a second or .0603 seconds.

3.18. DBMS_UTILITY

3.18.10 GET DEPENDENCY

The GET_DEPENDENCY procedure provides the capability to list the objects that are dependent upon the specified object. GET_DEPENDENCY does not show dependencies for functions or procedures.

Parameters

```
<type>
```

The object type of <name>. Valid values are INDEX, PACKAGE, PACKAGE BODY, SEQUENCE, TABLE, TRIGGER, TYPE and VIEW.

<schema>

Name of the schema in which <name> exists.

<name>

Name of the object for which dependencies are to be obtained.

Examples

The following anonymous block finds dependencies on the EMP table.

```
BEGIN
     DBMS_UTILITY.GET_DEPENDENCY('TABLE', 'public', 'EMP');
END;

DEPENDENCIES ON public.EMP

*TABLE public.EMP()

* CONSTRAINT c public.emp()

* CONSTRAINT f public.emp()

* CONSTRAINT p public.emp()

* TYPE public.emp()

* CONSTRAINT c public.emp()

* CONSTRAINT c public.emp()

* CONSTRAINT c public.emp()

* CONSTRAINT f public.emp()

* CONSTRAINT f public.emp()
```

3.18.11 GET_HASH_VALUE

The GET_HASH_VALUE function provides the capability to compute a hash value for a given string.

Parameters

<name>

The string for which a hash value is to be computed.

<base>

Starting value at which hash values are to be generated.

<hash_size>

The number of hash values for the desired hash table.

<hash>

The generated hash value.

Examples

The following anonymous block creates a table of hash values using the ename column of the emp table and then displays the key along with the hash value. The hash values start at 100 with a maximum of 1024 distinct values.

```
DECLARE
   v_hash
                   NUMBER;
   TYPE hash_tab IS TABLE OF NUMBER INDEX BY VARCHAR2(10);
   r_hash
                  HASH_TAB;
   CURSOR emp_cur IS SELECT ename FROM emp;
BEGIN
   FOR r_emp IN emp_cur LOOP
        r_hash(r_emp.ename.. code-block:: text) :=
           DBMS_UTILITY.GET_HASH_VALUE(r_emp.ename, 100, 1024);
   END LOOP;
   FOR r_emp IN emp_cur LOOP
        DBMS_OUTPUT.PUT_LINE(RPAD(r_emp.ename, 10) || ' ' ||
           r_hash(r_emp.ename));
   END LOOP;
END;
SMITH
          377
ALLEN
          740
          718.. code-block:: text
WARD
JONES
          131
MARTIN
          176
BLAKE
          568
          621
CLARK
SCOTT
          1097
          235
KING
TURNER
          850
ADAMS
          156
JAMES
          942
FORD
           775
MILLER
```

3.18.12 GET PARAMETER VALUE

The GET_PARAMETER_VALUE procedure provides the capability to retrieve database initialization parameter settings.

Parameters

<parnam>

Name of the parameter whose value is to be returned. The parameters are listed in the pg_settings system view.

<intval>

Value of an integer parameter or the length of <strval>.

<strval>

Value of a string parameter.

<status>

Returns 0 if the parameter value is INTEGER or BOOLEAN. Returns 1 if the parameter value is a string.

Examples

The following anonymous block shows the values of two initialization parameters.

```
DECLARE

v_intval INTEGER;
v_strval VARCHAR2(80);

BEGIN

DBMS_UTILITY.GET_PARAMETER_VALUE('max_fsm_pages', v_intval, v_strval);
DBMS_OUTPUT.PUT_LINE('max_fsm_pages' || ': ' || v_intval);
DBMS_UTILITY.GET_PARAMETER_VALUE('client_encoding', v_intval, v_strval);
DBMS_OUTPUT.PUT_LINE('client_encoding' || ': ' || v_strval);
END;

max_fsm_pages: 72625
client_encoding: SQL_ASCII
```

3.18.13 **GET_TIME**

The GET_TIME function provides the capability to return the current time in hundredths of a second.

```
<time> NUMBER GET_TIME
```

Parameters

<time>

Number of hundredths of a second from the time in which the program is started.

Examples

The following example shows calls to the GET_TIME function.

```
get_time
-----
1555860

SELECT DBMS_UTILITY.GET_TIME FROM DUAL;

get_time
------
1556037
```

3.18.14 NAME_TOKENIZE

The NAME_TOKENIZE procedure parses a name into its component parts. Names without double quotes are uppercased. The double quotes are stripped from names with double quotes.

```
NAME_TOKENIZE(<name> VARCHAR2, <a> OUT VARCHAR2, <b> OUT VARCHAR2, <c> OUT VARCHAR2, <dblink> OUT VARCHAR2, <nextpos> OUT BINARY_INTEGER)
```

Parameters

<name>

String containing a name in the following format:

```
<a> [.<b> [.<c>]][@<dblink> ]
```

<a>

Returns the leftmost component.

Returns the second component, if any.

<c>

Returns the third component, if any.

<dblink>

Returns the database link name.

<nextpos>

Position of the last character parsed in name.

Examples

The following stored procedure is used to display the returned parameter values of the NAME_TOKENIZE procedure for various names.

```
CREATE OR REPLACE PROCEDURE name_tokenize (
             VARCHAR2
    p_name
IS
                    VARCHAR2(30);
    v_a
   v_b
                    VARCHAR2 (30);
                    VARCHAR2(30);
    V_C
   v_dblink
                   VARCHAR2(30);
                    BINARY_INTEGER;
    v_nextpos
BEGIN
    DBMS_UTILITY.NAME_TOKENIZE(p_name,v_a,v_b,v_c,v_dblink,v_nextpos);
    DBMS_OUTPUT.PUT_LINE('name : ' || p_name);
   DBMS_OUTPUT_LINE('a : ' || v_a);
DBMS_OUTPUT_LINE('b : ' || v_b);
DBMS_OUTPUT_LINE('c : ' || v_c);
    DBMS_OUTPUT.PUT_LINE('dblink : ' || v_dblink);
    DBMS_OUTPUT.PUT_LINE('nextpos: ' || v_nextpos);
END;
```

Tokenize the name, emp:

```
BEGIN
name_tokenize('emp');
END;
name
: emp
a
: EMP
b
:
c
:
dblink :
nextpos: 3
```

Tokenize the name, edb.list_emp:

```
BEGIN
name_tokenize('edb.list_emp');
END;
name
:
a
:
b
:
c
:
dblink :
nextpos:
edb.list_emp
EDB
LIST_EMP
12
```

Tokenize the name, "edb"."Emp_Admin".update_emp_sal :

```
BEGIN
name_tokenize('"edb"."Emp_Admin".update_emp_sal');
END;
name
:
a
:
b
:
c
:
c
:
dblink :
nextpos:
"edb"."Emp_Admin".update_emp_sal
edb
Emp_Admin
UPDATE_EMP_SAL
32
```

Tokenize the name edb.emp@edb_dblink:

```
BEGIN
Copyright © 2007 - 2019 EnterpriseDB Corporation. All rights reserved.
255Database Compatibility for Oracle® Developers
Built-in Package Guide
name_tokenize('edb.emp@edb_dblink');
END;
name
:
a
:
b
:
c
c
:
dblink :
nextpos:
edb.emp@edb_dblink
EDB
EMP
EDB_DBLINK
18
```

3.18.15 TABLE TO COMMA

The TABLE_TO_COMMA procedure converts table of names into a comma-delimited list of names. Each table entry becomes a list entry. The names must be formatted as valid identifiers.

Comma-delimited list of names from <tab>.

Examples

The following example first uses the COMMA_TO_TABLE procedure to convert a comma-delimited list to a table. The TABLE_TO_COMMA procedure then converts the table back to a comma-delimited list that is displayed.

```
CREATE OR REPLACE PROCEDURE table_to_comma (
   p_list
           VARCHAR2
IS
   r_lname DBMS_UTILITY.LNAME_ARRAY;
   v_length BINARY_INTEGER;
   v_listlen BINARY_INTEGER;
   v_list
             VARCHAR2(80);
BEGIN
   DBMS_UTILITY.COMMA_TO_TABLE(p_list,v_length,r_lname);
   DBMS_OUTPUT.PUT_LINE('Table Entries');
   DBMS_OUTPUT.PUT_LINE('----');
   FOR i IN 1..v_length LOOP
       DBMS_OUTPUT.PUT_LINE(r_lname(i));
   END LOOP;
   DBMS_OUTPUT.PUT_LINE('----');
   DBMS_UTILITY.TABLE_TO_COMMA(r_lname, v_listlen, v_list);
   DBMS_OUTPUT.PUT_LINE('Comma-Delimited List: ' | | v_list);
END;
EXEC table_to_comma('edb.dept, edb.emp, edb.jobhist')
Table Entries
edb.dept
edb.emp
edb.jobhist
```

------Comma-Delimited List: edb.dept, edb.emp, edb.jobhist

3.19 UTL_ENCODE

The $\mathtt{UTL_ENCODE}$ package provides a way to encode and decode data. Advanced Serve supports the following functions and procedures:

Function/Procedure	Return Type	Description
BASE64_DECODE(r)	RAW	Use the BASE64_DECODE function to
		translate a Base64 encoded string to the
		original RAW value.
BASE64_ENCODE(r)	RAW	Use the BASE64_ENCODE function to
		translate a RAW string to an encoded
		Base64 value.
BASE64_ENCODE(loid)	TEXT	Use the BASE64_ENCODE function to
		translate a TEXT string to an encoded
IM THE LEFT PERCONNEL	TATA D CATA TO D	Base64 value.
MIMEHEADER_DECODE(buf)	VARCHAR2	Use the MIMEHEADER_DECODE func-
		tion to translate an encoded MIME-
		HEADER formatted string to it's original value.
MIMEHEADER_ENCODE(buf, en-	VARCHAR2	Use the MIMEHEADER ENCODE func-
code_charset, encoding)	VIRCIIIIC	tion to convert and encode a string in
code_charset, cheeding)		MIMEHEADER format.
QUOTED_PRINTABLE_DECODE(r)	RAW	Use the QUOTED_PRINTABLE_DECODE
		function to translate an encoded string to a
		RAW value.
QUOTED_PRINTABLE_ENCODE(r)	RAW	Use the QUOTED_PRINTABLE_ENCODE
		function to translate an input string to a
		quoted-printable formatted RAW value.
TEXT_DECODE(buf, encode_charset, en-	VARCHAR2	Use the TEXT_DECODE function to de-
coding)	***************************************	code a string encoded by TEXT_ENCODE.
TEXT_ENCODE(buf, encode_charset, en-	VARCHAR2	Use the TEXT_ENCODE function to trans-
coding)		late a string to a user-specified character set,
THIDECODE()	DAW	and then encode the string.
UUDECODE(r)	RAW	Use the UUDECODE function to translate a
LILIENCODE(a tama filamana a maria)	DAW	uuencode encoded string to a RAW value. Use the UUENCODE function to translate a
UUENCODE(r, type, filename, permission)	RAW	
		RAW string to an encoded uuencode value.

3.19.1 BASE64_DECODE

Use the BASE64_DECODE function to translate a Base64 encoded string to the original value originally encoded by BASE64_ENCODE. The signature is:

```
BASE64_DECODE (<r> IN RAW)
```

This function returns a RAW value.

Parameters

<r>

<r> is the string that contains the Base64 encoded data that will be translated to RAW form.

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example first encodes (using BASE64_ENCODE), and then decodes (using BASE64_DECODE) a string that contains the text abc:

```
edb=# SELECT UTL_ENCODE.BASE64_ENCODE(CAST ('abc' AS RAW));
base64_encode
------
YWJj
(1 row)
edb=# SELECT UTL_ENCODE.BASE64_DECODE(CAST ('YWJj' AS RAW));
base64_decode
-----------------
abc
(1 row)
```

3.19.2 BASE64_ENCODE

Use the BASE64_ENCODE function to translate and encode a string in Base64 format (as described in RFC 4648). This function can be useful when composing MIME email that you intend to send using the UTL_SMTP package. The BASE64_ENCODE function has two signatures:

```
BASE64_ENCODE(<r> IN RAW)
and
BASE64_ENCODE(<loid> IN OID)
```

This function returns a RAW value or an OID.

Parameters

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example first encodes (using BASE64_ENCODE), and then decodes (using BASE64_DECODE) a string that contains the text abc:

3.19.3 MIMEHEADER_DECODE

Use the MIMEHEADER_DECODE function to decode values that are encoded by the MIMEHEADER_ENCODE function. The signature is:

```
MIMEHEADER_DECODE (<buf> IN VARCHAR2)
```

This function returns a VARCHAR2 value.

Parameters

<buf>

<buf> contains the value (encoded by MIMEHEADER_ENCODE) that will be decoded.

Examples

The following examples use the MIMEHEADER_ENCODE and MIMEHEADER_DECODE functions to first encode, and then decode a string:

3.19.4 MIMEHEADER_ENCODE

Use the MIMEHEADER_ENCODE function to convert a string into mime header format, and then encode the string. The signature is:

```
MIMEHEADER_ENCODE(<buf> IN VARCHAR2, <encode_charset> IN VARCHAR2 DEFAULT NULL, <encoding> IN INTEGER DEFAULT NULL)
```

This function returns a VARCHAR2 value.

Parameters

<buf>

<bush
 <bush
 contains the string that will be formatted and encoded. The string is a VARCHAR2 value.

```
<encode_charset>
```

<encode_charset> specifies the character set to which the string will be converted before being
formatted and encoded. The default value is NULL.

<encoding>

<encoding> specifies the encoding type used when encoding the string. You can specify:

- Q to enable quoted-printable encoding. If you do not specify a value, MIMEHEADER_ENCODE will use quoted-printable encoding.
- B to enable base-64 encoding.

Examples

The following examples use the MIMEHEADER_ENCODE and MIMEHEADER_DECODE functions to first encode, and then decode a string:

3.19.5 QUOTED_PRINTABLE_DECODE

Use the QUOTED_PRINTABLE_DECODE function to translate an encoded quoted-printable string into a decoded RAW string.

The signature is:

```
QUOTED_PRINTABLE_DECODE (<r> IN RAW)
```

This function returns a RAW value.

Parameters

<r>

<r> contains the encoded string that will be decoded. The string is a RAW value, encoded by QUOTED PRINTABLE ENCODE.

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example first encodes and then decodes a string:

3.19.6 QUOTED_PRINTABLE_ENCODE

Use the QUOTED_PRINTABLE_ENCODE function to translate and encode a string in quoted-printable format. The signature is:

```
QUOTED_PRINTABLE_ENCODE(<r> IN RAW)
```

This function returns a RAW value.

Parameters

<r>

<r> contains the string (a RAW value) that will be encoded in a quoted-printable format.

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example first encodes and then decodes a string:

3.19.7 TEXT DECODE

Use the TEXT_DECODE function to translate and decode an encoded string to the VARCHAR2 value that was originally encoded by the TEXT_ENCODE function. The signature is:

```
TEXT_DECODE(<buf> IN VARCHAR2, <encode_charset> IN VARCHAR2 DEFAULT
NULL, <encoding> IN PLS_INTEGER DEFAULT NULL)
```

This function returns a VARCHAR2 value.

Parameters

```
<buf>
```

<buf> contains the encoded string that will be translated to the original value encoded by
TEXT ENCODE.

```
<encode_charset>
```

<encode_charset> specifies the character set to which the string will be translated before encoding.
The default value is NULL.

<encoding>

<encoding> specifies the encoding type used by TEXT_DECODE. Specify:

- UTL_ENCODE.BASE64 to specify base-64 encoding.
- UTL_ENCODE.QUOTED_PRINTABLE to specify quoted printable encoding. This is the default.

Examples

The following example uses the TEXT_ENCODE and TEXT_DECODE functions to first encode, and then decode a string:

3.19.8 TEXT ENCODE

Use the TEXT_ENCODE function to translate a string to a user-specified character set, and then encode the string. The signature is:

```
TEXT_DECODE(<buf> IN VARCHAR2, <encode_charset> IN VARCHAR2 DEFAULT
NULL, <encoding> IN PLS_INTEGER DEFAULT NULL)
```

This function returns a VARCHAR2 value.

Parameters

```
<buf>
```

<buf> contains the encoded string that will be translated to the specified character set and encoded by
TEXT_ENCODE.

```
<encode_charset>
```

<encode_charset> specifies the character set to which the value will be translated before encoding.
The default value is NULL.

<encoding>

<encoding> specifies the encoding type used by TEXT_ENCODE. Specify:

- UTL_ENCODE.BASE64 to specify base-64 encoding.
- UTL_ENCODE.QUOTED_PRINTABLE to specify quoted printable encoding. This is the default.

Examples

The following example uses the TEXT_ENCODE and TEXT_DECODE functions to first encode, and then decode a string:

3.19.9 UUDECODE

Use the UUDECODE function to translate and decode a uuencode encoded string to the RAW value that was originally encoded by the UUENCODE function. The signature is:

```
UUDECODE (<r> IN RAW)
```

This function returns a RAW value.

If you are using the Advanced Server UUDECODE function to decode uuencoded data that was created by the Oracle implementation of the UTL_ENCODE.UUENCODE function, then you must first set the Advanced Server configuration parameter utl_encode.uudecode_redwood to TRUE before invoking the Advanced Server UUDECODE function on the Oracle-created data. (For example, this situation may occur if you migrated Oracle tables containing uuencoded data to an Advanced Server database.)

The uuencoded data created by the Oracle version of the UUENCODE function results in a format that differs from the uuencoded data created by the Advanced Server UUENCODE function. As a result, attempting to use the Advanced Server UUDECODE function on the Oracle uuencoded data results in an error unless the configuration parameter utl encode.uudecode redwood is set to TRUE.

However, if you are using the Advanced Server UUDECODE function on uuencoded data created by the Advanced Server UUENCODE function, then utl_encode.uudecode_redwood must be set to FALSE, which is the default setting.

Parameters

<r>

<r> contains the uuencoded string that will be translated to RAW.

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example uses UUENCODE and UUDECODE to first encode and then decode a string:

```
edb=# SET bytea_output = escape;
SET
edb=# SELECT UTL_ENCODE.UUENCODE('What is the date?') FROM DUAL;
uuencode
_____
begin 0 uuencode.txt\01215VAA="!I<R!T:&4@9&%T93\\`\012`\012end\012
(1 row)
edb=# SELECT UTL_ENCODE.UUDECODE
edb-# ('begin 0 uuencode.txt\01215VAA="!I<R!T:&4@9&%T93\\`\012`\012end\012')
edb-# FROM DUAL;
uudecode
______
What is the date?
(1 row)</pre>
```

3.19.10 UUENCODE

Use the UUENCODE function to translate RAW data into a uuencode formatted encoded string. The signature is:

This function returns a RAW value.

Parameters

<r>

<r> contains the RAW string that will be translated to uuencode format.

<type>

<type> is an INTEGER value or constant that specifies the type of unencoded string that will be returned; the default value is 1. The possible values are:

Value	Constant	
1	complete	
2	header_piece	
3	middle_piece	
4	end_piece	

<filename>

<filename> is a VARCHAR2 value that specifies the file name that you want to embed in the encoded form; if you do not specify a file name, UUENCODE will include a filename of uuencode.txt in the encoded form.

<permission>

<permission> is a VARCHAR2 that specifies the permission mode; the default value is NULL.

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example uses UUENCODE and UUDECODE to first encode and then decode a string:

3.20 UTL_FILE

The UTL_FILE package provides the capability to read from, and write to files on the operating system's file system. Non-superusers must be granted EXECUTE privilege on the UTL_FILE package by a superuser before using any of the functions or procedures in the package. For example the following command grants the privilege to user mary:

```
GRANT EXECUTE ON PACKAGE SYS.UTL_FILE TO mary;
```

Also, the operating system username, enterprisedb, must have the appropriate read and/or write permissions on the directories and files to be accessed using the UTL_FILE functions and procedures. If the required file permissions are not in place, an exception is thrown in the UTL_FILE function or procedure.

A handle to the file to be written to, or read from is used to reference the file. The *file handle* is defined by a public variable in the UTL_FILE package named, UTL_FILE.FILE_TYPE. A variable of type FILE_TYPE must be declared to receive the file handle returned by calling the FOPEN function. The file handle is then used for all subsequent operations on the file.

References to directories on the file system are done using the directory name or alias that is assigned to the directory using the CREATE DIRECTORY command. The procedures and functions available in the UTL_FILE package are listed in the following table:

Function/Procedure	Return Type	Description
FCLOSE(file IN OUT)	n/a	Closes the specified file identified by file.
FCLOSE_ALL	n/a	Closes all open files.
FCOPY(location, filename, dest_dir,	n/a	Copies filename in the directory identified
<pre>dest_file [, start_line [, end_line]])</pre>		by location to file, dest_file, in directory,
		dest_dir, starting from line, start_line, to
		line, end_line.
FFLUSH(file)	n/a	Forces data in the buffer to be written to disk
		in the file identified by file.
FOPEN(location, filename, open_mode [,	FILE_TYPE	Opens file, filename, in the directory identi-
max_linesize])		fied by location.
FREMOVE(location, filename)	n/a	Removes the specified file from the file sys-
		tem.
FRENAME(location, filename, dest_dir,	n/a	Renames the specified file.
dest_file [, overwrite])		
GET_LINE(file, buffer OUT)	n/a	Reads a line of text into variable, buffer,
		from the file identified by file.
IS_OPEN(file)	BOOLEAN	Determines whether or not the given file is
		open.
NEW_LINE(file [, lines])	n/a	Writes an end-of-line character sequence
		into the file.
PUT(file, buffer)	n/a	Writes buffer to the given file. PUT does not
		write an end-of-line character sequence.
PUT_LINE(file, buffer)	n/a	Writes buffer to the given file. An end-
		of-line character sequence is added by the
		PUT_LINE procedure.
PUTF(file, format [, arg1] [,])	n/a	Writes a formatted string to the given
		file. Up to five substitution parameters,
		arg1,arg5 may be specified for replace-
		ment in format.

Advanced Server's implementation of UTL_FILE is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

UTL_FILE Exception Codes

If a call to a UTL_FILE procedure or function raises an exception, you can use the condition name to catch the exception. The UTL_FILE package reports the following exception codes compatible with Oracle databases:

Exception Code	Condition name
-29283	invalid_operation
-29285	write_error
-29284	read_error
-29282	invalid_filehandle
-29287	invalid_maxlinesize
-29281	invalid_mode
-29280	invalid_path

3.20.1 Setting File Permissions with utl_file.umask

When a UTL_FILE function or procedure creates a file, there are default file permissions as shown by the following.

```
-rw----- 1 enterprisedb enterprisedb 21 Jul 24 16:08 utlfile
```

Note that all permissions are denied on users belonging to the enterprised group as well as all other users. Only the enterprised user has read and write permissions on the created file.

If you wish to have a different set of file permissions on files created by the UTL_FILE functions and procedures, you can accomplish this by setting the utl_file.umask configuration parameter.

The utl_file.umask parameter sets the *file mode creation mask* or simply, the *mask*, in a manner similar to the Linux umask command. This is for usage only within the Advanced Server UTL_FILE package.

Note: The utl_file.umask parameter is not supported on Windows systems.

The value specified for utl_file.umask is a 3 or 4-character octal string that would be valid for the Linux umask command. The setting determines the permissions on files created by the UTL_FILE functions and procedures. (Refer to any information source regarding Linux or Unix systems for information on file permissions and the usage of the umask command.)

The following is an example of setting the file permissions with utl file.umask.

First, set up the directory in the file system to be used by the UTL_FILE package. Be sure the operating system account, enterprised or postgres, whichever is applicable, can read and write in the directory.

```
mkdir /tmp/utldir
chmod 777 /tmp/utldir
```

The CREATE DIRECTORY command is issued in psql to create the directory database object using the file system directory created in the preceding step.

```
CREATE DIRECTORY utldir AS '/tmp/utldir';
```

Set the utl_file.umask configuration parameter. The following setting allows the file owner any permission. Group users and other users are permitted any permission except for the execute permission.

```
SET utl_file.umask TO '0011';
```

In the same session during which the utl_file.umask parameter is set to the desired value, run the UTL_FILE functions and procedures.

```
DECLARE

v_utlfile    UTL_FILE.FILE_TYPE;
v_directory    VARCHAR2(50) := 'utldir';
v_filename    VARCHAR2(20) := 'utlfile';

BEGIN

v_utlfile := UTL_FILE.FOPEN(v_directory, v_filename, 'w');
UTL_FILE.PUT_LINE(v_utlfile, 'Simple one-line file');
DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
UTL_FILE.FCLOSE(v_utlfile);

END;
```

The permission settings on the resulting file show that group users and other users have read and write permissions on the file as well as the file owner.

```
$ pwd
/tmp/utldir
$ ls -l
total 4
-rw-rw-rw- 1 enterprisedb enterprisedb 21 Jul 24 16:04 utlfile
```

This parameter can also be set on a per role basis with the ALTER ROLE command, on a per database basis with the ALTER DATABASE command, or for the entire database server instance by setting it in the postgresql.conf file.

3.20.2 FCLOSE

The FCLOSE procedure closes an open file.

```
FCLOSE(<file> IN OUT FILE_TYPE)
```

Parameters

<file>

Variable of type FILE_TYPE containing a file handle of the file to be closed.

3.20.3 FCLOSE ALL

The FLCLOSE_ALL procedures closes all open files. The procedure executes successfully even if there are no open files to close.

```
FCLOSE ALL
```

3.20.4 FCOPY

The FCOPY procedure copies text from one file to another.

Parameters

```
<location>
```

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory containing the file to be copied.

```
<filename>
```

Name of the source file to be copied.

```
<dest dir>
```

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory to which the file is to be copied.

```
<dest_file>
```

Name of the destination file.

```
<start_line>
```

Line number in the source file from which copying will begin. The default is 1.

```
<end line>
```

Line number of the last line in the source file to be copied. If omitted or null, copying will go to the last line of the file.

Examples

The following makes a copy of a file, C:\TEMP\EMPDIR\empfile.csv, containing a comma-delimited list of employees from the emp table. The copy, empcopy.csv, is then listed.

```
CREATE DIRECTORY empdir AS 'C:/TEMP/EMPDIR';
DECLARE
   v_empfile UTL_FILE.FILE_TYPE;
v_src_dir VARCHAR2(50) := 'empdir';
v_src_file VARCHAR2(20) := 'empfile.csv';
v_dest_dir VARCHAR2(50) := 'empdir';
v_dest_file VARCHAR2(20) := 'empcopy.csv';
v_emprec VARCHAR2(120);
v_count INTEGER := 0;
    v_count
                         INTEGER := 0;
BEGIN
    UTL_FILE.FCOPY(v_src_dir,v_src_file,v_dest_dir,v_dest_file);
     v_empfile := UTL_FILE.FOPEN(v_dest_dir,v_dest_file,'r');
    DBMS_OUTPUT.PUT_LINE('The following is the destination file, ''' ||
         v_dest_file || '''');
    LOOP
          UTL_FILE.GET_LINE(v_empfile, v_emprec);
          DBMS_OUTPUT.PUT_LINE(v_emprec);
          v_count := v_count + 1;
    END LOOP;
     EXCEPTION
          WHEN NO_DATA_FOUND THEN
               UTL_FILE.FCLOSE(v_empfile);
               DBMS_OUTPUT.PUT_LINE(v_count || ' records retrieved');
          WHEN OTHERS THEN
               DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
               DBMS_OUTPUT.PUT_LINE('SQLCODE: ' | SQLCODE);
END;
```

```
The following is the destination file, 'empcopy.csv'
7369, SMITH, CLERK, 7902, 17-DEC-80, 800,, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81, 1600, 300, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81, 1250, 500, 30
7566, JONES, MANAGER, 7839, 02-APR-81, 2975, , 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81, 1250, 1400, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81, 2850, , 30
7782, CLARK, MANAGER, 7839, 09-JUN-81, 2450,, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87, 3000,,20
7839, KING, PRESIDENT, , 17-NOV-81, 5000, , 10
7844, TURNER, SALESMAN, 7698, 08-SEP-81, 1500, 0, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87, 1100,, 20
7900, JAMES, CLERK, 7698, 03-DEC-81, 950,, 30
7902, FORD, ANALYST, 7566, 03-DEC-81, 3000,, 20
7934, MILLER, CLERK, 7782, 23-JAN-82, 1300, , 10
14 records retrieved
```

3.20.5 FFLUSH

The FFLUSH procedure flushes unwritten data from the write buffer to the file.

```
FFLUSH(<file> FILE_TYPE)
```

Parameters

<file>

Variable of type FILE_TYPE containing a file handle.

Examples

Each line is flushed after the NEW_LINE procedure is called.

```
DECLARE
   v_empfile
                    UTL_FILE.FILE_TYPE;
   v_directory
                    VARCHAR2(50) := 'empdir';
                    VARCHAR2(20) := 'empfile.csv';
    v_filename
   CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
    v_empfile := UTL_FILE.FOPEN(v_directory, v_filename, 'w');
    FOR i IN emp_cur LOOP
        UTL_FILE.PUT(v_empfile,i.empno);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.ename);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.job);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.mgr);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.hiredate);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.sal);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.comm);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.deptno);
        UTL_FILE.NEW_LINE(v_empfile);
        UTL_FILE.FFLUSH(v_empfile);
```

```
END LOOP;
DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
UTL_FILE.FCLOSE(v_empfile);
END;
```

3.20.6 FOPEN

The FOPEN function opens a file for I/O.

```
<filetype> FILE_TYPE FOPEN(<location> VARCHAR2,
<filename> VARCHAR2,<open_mode> VARCHAR2
[,<max linesize> BINARY INTEGER ])
```

Parameters

<location>

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory containing the file to be opened.

<filename>

Name of the file to be opened.

<open_mode>

Mode in which the file will be opened. Modes are: a - append to file; r - read from file; w - write to file.

```
<max linesize>
```

Maximum size of a line in characters. In read mode, an exception is thrown if an attempt is made to read a line exceeding <max_linesize>. In write and append modes, an exception is thrown if an attempt is made to write a line exceeding <max_linesize>. The end-of-line character(s) are not included in determining if the maximum line size is exceeded. This behavior is not compatible with Oracle databases; Oracle does count the end-of-line character(s).

```
<filetype>
```

Variable of type FILE_TYPE containing the file handle of the opened file.

3.20.7 FREMOVE

The FREMOVE procedure removes a file from the system.

```
FREMOVE(<location> VARCHAR2, <filename> VARCHAR2)
```

An exception is thrown if the file to be removed does not exist.

Parameters

```
<location>
```

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory containing the file to be removed.

```
<filename>
```

Name of the file to be removed.

Examples

The following removes file empfile.csv.

3.20.8 FRENAME

The FRENAME procedure renames a given file. This effectively moves a file from one location to another.

```
FRENAME(<location> VARCHAR2, <filename> VARCHAR2,
<dest_dir> VARCHAR2, <dest_file> VARCHAR2,
[<overwrite> BOOLEAN])
```

Parameters

```
<location>
```

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory containing the file to be renamed.

```
<filename>
```

Name of the source file to be renamed.

```
<dest_dir>
```

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory to which the renamed file is to exist.

```
<dest_file>
```

New name of the original file.

```
<overwrite>
```

Replaces any existing file named <dest_file> in <dest_dir> if set to TRUE, otherwise an exception is thrown if set to FALSE. This is the default.

Examples

The following renames a file, C:\TEMP\EMPDIR\empfile.csv, containing a comma-delimited list of employees from the emp table. The renamed file, C:\TEMP\NEWDIR\newemp.csv, is then listed.

```
CREATE DIRECTORY "newdir" AS 'C:/TEMP/NEWDIR';
DECLARE
                  UTL_FILE.FILE_TYPE;
   v_empfile
   v_replace
                   BOOLEAN := FALSE;
   v_emprec
                   VARCHAR2(120);
   v_count
                   INTEGER := 0;
BEGIN
   UTL_FILE.FRENAME(v_src_dir, v_src_file, v_dest_dir,
       v_dest_file,v_replace);
    v empfile := UTL FILE.FOPEN(v dest dir, v dest file, 'r');
   DBMS_OUTPUT.PUT_LINE('The following is the renamed file, ''' ||
        v_dest_file || '''');
   LOOP
        UTL_FILE.GET_LINE(v_empfile, v_emprec);
        DBMS_OUTPUT.PUT_LINE(v_emprec);
        v_count := v_count + 1;
    END LOOP;
    EXCEPTION
        WHEN NO_DATA_FOUND THEN
            UTL_FILE.FCLOSE(v_empfile);
            DBMS_OUTPUT.PUT_LINE(v_count || ' records retrieved');
        WHEN OTHERS THEN
            DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
            DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
The following is the renamed file, 'newemp.csv'
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839, KING, PRESIDENT, , 17-NOV-81 00:00:00, 5000.00, , 10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
14 records retrieved
```

3.20.9 **GET_LINE**

The GET_LINE procedure reads a line of text from a given file up to, but not including the end-of-line terminator. A NO_DATA_FOUND exception is thrown when there are no more lines to read.

```
GET_LINE(<file> FILE_TYPE, <buffer> OUT VARCHAR2)
```

Parameters

<file>

Variable of type FILE_TYPE containing the file handle of the opened file.

<buffer>

Variable to receive a line from the file.

Examples

The following anonymous block reads through and displays the records in file empfile.csv.

```
DECLARE
                    VARCHAR2(50) := 'empdir';
    v_filename
                    VARCHAR2(20) := 'empfile.csv';
    v_emprec
                   VARCHAR2 (120);
    v_count
                   INTEGER := 0;
BEGIN
    v_empfile := UTL_FILE.FOPEN(v_directory, v_filename, 'r');
    LOOP
        UTL_FILE.GET_LINE(v_empfile,v_emprec);
        DBMS_OUTPUT.PUT_LINE(v_emprec);
        v_count := v_count + 1;
   END LOOP;
    EXCEPTION
        WHEN NO_DATA_FOUND THEN
            UTL_FILE.FCLOSE(v_empfile);
            DBMS_OUTPUT_LINE('End of file ' || v_filename || ' - ' ||
                v_count || ' records retrieved');
        WHEN OTHERS THEN
            DBMS_OUTPUT.PUT_LINE('SQLERRM: ' | SQLERRM);
            DBMS_OUTPUT.PUT_LINE('SQLCODE: ' | SQLCODE);
END;
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839, KING, PRESIDENT, ,17-NOV-81 00:00:00,5000.00,,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
End of file empfile.csv - 14 records retrieved
```

3.20.10 IS OPEN

The IS_OPEN function determines whether or not the given file is open.

```
<status> BOOLEAN IS_OPEN(<file> FILE_TYPE)
```

Parameters

```
<file>
```

Variable of type FILE_TYPE containing the file handle of the file to be tested.

<status>

TRUE if the given file is open, FALSE otherwise.

3.20.11 NEW LINE

The NEW_LINE procedure writes an end-of-line character sequence in the file.

```
NEW LINE(<file> FILE TYPE [, <lines> INTEGER ])
```

Parameters

<file>

Variable of type FILE_TYPE containing the file handle of the file to which end-of-line character sequences are to be written.

nes>

Number of end-of-line character sequences to be written. The default is one.

Examples

A file containing a double-spaced list of employee records is written.

```
DECLARE
   v_empfile     UTL_FILE.FILE_TYPE;
v_directory      VARCHAR2(50) := 'empdir';
    v_filename VARCHAR2(20) := 'empfile.csv';
    CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
    v_empfile := UTL_FILE.FOPEN(v_directory, v_filename, 'w');
    FOR i IN emp_cur LOOP
        UTL_FILE.PUT(v_empfile,i.empno);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.ename);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.job);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.mgr);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.hiredate);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.sal);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.comm);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.deptno);
        UTL_FILE.NEW_LINE(v_empfile,2);
    END LOOP;
```

```
DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
   UTL_FILE.FCLOSE(v_empfile);
END;
Created file: empfile.csv
```

This file is then displayed:

```
C:\TEMP\EMPDIR>TYPE empfile.csv
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00,, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00,, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00,, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00,, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00,, 20
7839, KING, PRESIDENT,, 17-NOV-81 00:00:00, 5000.00,, 10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1500.00,, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00,, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00,, 20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00,, 10
```

3.20.12 PUT

The PUT procedure writes a string to the given file. No end-of-line character sequence is written at the end of the string. Use the NEW_LINE procedure to add an end-of-line character sequence.

```
PUT(<file> FILE_TYPE, <buffer> { DATE | NUMBER | TIMESTAMP |
VARCHAR2 })
```

Parameters

<file>

Variable of type FILE_TYPE containing the file handle of the file to which the given string is to be written.

<buffer>

Text to be written to the specified file.

Examples

The following example uses the PUT procedure to create a comma-delimited file of employees from the emp table.

```
DECLARE
   v_empfile
                   UTL_FILE.FILE_TYPE;
   v_directory
                 VARCHAR2(50) := 'empdir';
   CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
   v_empfile := UTL_FILE.FOPEN(v_directory, v_filename, 'w');
   FOR i IN emp_cur LOOP
       UTL_FILE.PUT(v_empfile,i.empno);
       UTL_FILE.PUT(v_empfile,',');
       UTL_FILE.PUT(v_empfile,i.ename);
       UTL_FILE.PUT(v_empfile,',');
       UTL_FILE.PUT(v_empfile,i.job);
       UTL_FILE.PUT(v_empfile,',');
       UTL_FILE.PUT(v_empfile,i.mgr);
       UTL_FILE.PUT(v_empfile,',');
       UTL_FILE.PUT(v_empfile,i.hiredate);
       UTL_FILE.PUT(v_empfile,',');
       UTL_FILE.PUT(v_empfile,i.sal);
       UTL_FILE.PUT(v_empfile,',');
       UTL_FILE.PUT(v_empfile,i.comm);
       UTL_FILE.PUT(v_empfile,',');
       UTL_FILE.PUT(v_empfile,i.deptno);
       UTL_FILE.NEW_LINE(v_empfile);
   END LOOP;
   DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
   UTL_FILE.FCLOSE(v_empfile);
END;
Created file: empfile.csv
```

The following is the contents of empfile.csv created above:

```
C:\TEMP\EMPDIR>TYPE empfile.csv

7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, ,30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, ,10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, ,20
7839, KING, PRESIDENT, ,17-NOV-81 00:00:00, 5000.00, 10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, ,20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 3000.00, ,20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, ,10
```

3.20.13 PUT LINE

The PUT LINE procedure writes a single line to the given file including an end-of-line character sequence.

```
PUT_LINE(<file> FILE_TYPE,
<buffer> {DATE|NUMBER|TIMESTAMP|VARCHAR2})
```

Parameters

<file>

Variable of type FILE_TYPE containing the file handle of the file to which the given line is to be written.

<buffer>

Text to be written to the specified file.

Examples

The following example uses the PUT_LINE procedure to create a comma-delimited file of employees from the emp table.

```
DECLARE
   v_empfile
                 UTL_FILE.FILE_TYPE;
   v_directory
                 VARCHAR2(50) := 'empdir';
   VARCHAR2 (120);
   v_emprec
   CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
   v_empfile := UTL_FILE.FOPEN(v_directory, v_filename, 'w');
   FOR i IN emp_cur LOOP
       v_emprec := i.empno || ',' || i.ename || ',' || i.job || ',' ||
          NVL(LTRIM(TO_CHAR(i.mgr,'9999')),'') || ',' || i.hiredate ||
           ',' || i.sal || ',' ||
           NVL(LTRIM(TO_CHAR(i.comm, '9990.99')),'') || ',' || i.deptno;
       UTL_FILE.PUT_LINE(v_empfile, v_emprec);
   END LOOP:
   DBMS_OUTPUT.PUT_LINE('Created file: ' | | v_filename);
   UTL_FILE.FCLOSE(v_empfile);
END;
```

The following is the contents of empfile.csv created above:

```
C:\TEMP\EMPDIR>TYPE empfile.csv

7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839, KING, PRESIDENT, 17-NOV-81 00:00:00, 5000.00, 10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 3000.00, 20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
```

3.20.14 PUTF

The PUTF procedure writes a formatted string to the given file.

```
PUTF(<file> FILE_TYPE, <format> VARCHAR2 [, <arg1> VARCHAR2]
[, ...])
```

Parameters

<file>

Variable of type FILE_TYPE containing the file handle of the file to which the formatted line is to be written.

```
<format>
```

String to format the text written to the file. The special character sequence, %s, is substituted by the value of arg. The special character sequence, \n, indicates a new line. Note, however, in Advanced Server, a new line character must be specified with two consecutive backslashes instead of one - \\n. This characteristic is not compatible with Oracle databases.

```
<arg1>
```

Up to five arguments, <arg1>,...<arg5>, to be substituted in the format string for each occurrence of %s. The first arg is substituted for the first occurrence of %s, the second arg is substituted for the second occurrence of %s, etc.

Examples

The following anonymous block produces formatted output containing data from the emp table. Note the use of the E literal syntax and double backslashes for the new line character sequence in the format string which are not compatible with Oracle databases.

```
DECLARE
   v_filename
                  VARCHAR2(20) := 'empfile.csv';
   v format
                  VARCHAR2 (200);
   CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
   v_{format} := E'%s %s, %s\nSalary: $%s Commission: $%s\n\n';
   v_empfile := UTL_FILE.FOPEN(v_directory, v_filename, 'w');
   FOR i IN emp_cur LOOP
       UTL_FILE.PUTF(v_empfile,v_format,i.empno,i.ename,i.job,i.sal,
           NVL(i.comm, 0));
   END LOOP:
   DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
   UTL_FILE.FCLOSE(v_empfile);
EXCEPTION
   WHEN OTHERS THEN
       DBMS_OUTPUT.PUT_LINE('SQLERRM: ' | SQLERRM);
       DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
Created file: empfile.csv
```

The following is the contents of empfile.csv created above:

```
C:\TEMP\EMPDIR>TYPE empfile.csv
7369 SMITH, CLERK
Salary: $800.00 Commission: $0
```

```
7499 ALLEN, SALESMAN
Salary: $1600.00 Commission: $300.00
7521 WARD, SALESMAN
Salary: $1250.00 Commission: $500.00
7566 JONES, MANAGER
Salary: $2975.00 Commission: $0
7654 MARTIN, SALESMAN
Salary: $1250.00 Commission: $1400.00
7698 BLAKE, MANAGER
Salary: $2850.00 Commission: $0
7782 CLARK, MANAGER
Salary: $2450.00 Commission: $0
7788 SCOTT, ANALYST
Salary: $3000.00 Commission: $0
7839 KING, PRESIDENT
Salary: $5000.00 Commission: $0
7844 TURNER, SALESMAN
Salary: $1500.00 Commission: $0.00
7876 ADAMS, CLERK
Salary: $1100.00 Commission: $0
7900 JAMES, CLERK
Salary: $950.00 Commission: $0
7902 FORD, ANALYST
Salary: $3000.00 Commission: $0
7934 MILLER, CLERK
Salary: $1300.00 Commission: $0
```

3.21 UTL_HTTP

The UTL_HTTP package provides a way to use the HTTP or HTTPS protocol to retrieve information found at an URL. Advanced Server supports the following functions and procedures:

Function/Procedure	Return Type	Description
BEGIN_REQUEST(url, method,	UTL_HTTP.REQ	Initiates a new HTTP request.
http_version)		•
END_REQUEST(r IN OUT)	n/a	Ends an HTTP request before allowing it to
		complete.
END_RESPONSE(r IN OUT)	n/a	Ends the HTTP response.
GET_BODY_CHARSET	VARCHAR2	Returns the default character set of the body
		of future HTTP requests.
GET_BODY_CHARSET(charset OUT)	n/a	Returns the default character set of the body
		of future HTTP requests.
GET_FOLLOW_REDIRECT(max_redirects	n/a	Current setting for the maximum number of
OUT)		redirections allowed.
GET_HEADER(r IN OUT, n, name OUT,	n/a	Returns the nth header of the HTTP re-
value OUT)		sponse.
GET_HEADER_BY_NAME(r IN OUT,	n/a	Returns the HTTP response header for the
name, value OUT, n)		specified name.
GET_HEADER_COUNT(r IN OUT)	INTEGER	Returns the number of HTTP response
		headers.
GET_RESPONSE(r IN OUT)	UTL_HTTP.RESP	Returns the HTTP response.
GET_RESPONSE_ERROR_CHECK(enable		Returns whether or not response error check
OUT)		is set.
GET_TRANSFER_TIMEOUT(timeout	n/a	Returns the transfer timeout setting for
OUT)		HTTP requests.
(r IN OUT, data OUT, remove_crlf)	n/a	Returns the HTTP response body in text
/		form until the end of line.
READ_RAW(r IN OUT, data OUT, len)	n/a	Returns the HTTP response body in binary
		form for a specified number of bytes.
READ_TEXT(r IN OUT, data OUT, len)	n/a	Returns the HTTP response body in text
		form for a specified number of characters.
REQUEST(url)	VARCHAR2	Returns the content of a web page.
REQUEST_PIECES(url, max_pieces)	UTL_HTTP.	Returns a table of 2000-byte segments re-
	HTML_PIECES	trieved from an URL.
SET_BODY_CHARSET(charset)	n/a	Sets the default character set of the body of
		future HTTP requests.
SET_FOLLOW_REDIRECT(max_redirects)	n/a	Sets the maximum number of times to fol-
		low the redirect instruction.
SET_FOLLOW_REDIRECT(r IN OUT,	n/a	Sets the maximum number of times to fol-
max_redirects)		low the redirect instruction for an individual
		request.
SET_HEADER(r IN OUT, name, value)	n/a	Sets the HTTP request header.
SET_RESPONSE_ERROR_CHECK(enable)	n/a	Determines whether or not HTTP 4xx and
		5xx status codes are to be treated as errors.
SET_TRANSFER_TIMEOUT(timeout)	n/a	Sets the default, transfer timeout value for
		HTTP requests.
SET_TRANSFER_TIMEOUT(r IN OUT,	n/a	Sets the transfer timeout value for an indi-
timeout)		vidual HTTP request.
	1	Continued on next page

Continued on next page

Table 3.9 – continued from previous page

WRITE_LINE(r IN OUT, data)	n/a	Writes CRLF terminated data to the HTTP
		request body in TEXT form.
WRITE_RAW(r IN OUT, data)	n/a	Writes data to the HTTP request body in BI-
		NARY form.
WRITE_TEXT(r IN OUT, data)	n/a	Writes data to the HTTP request body in
		TEXT form.

Advanced Server's implementation of UTL_HTTP is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Note: In Advanced Server, an HTTP 4xx or HTTP 5xx response produces a database error; in Oracle, this is configurable but FALSE by default.

In Advanced Server, the UTL_HTTP text interfaces expect the downloaded data to be in the database encoding. All currently-available interfaces are text interfaces. In Oracle, the encoding is detected from HTTP headers; in the absence of the header, the default is configurable and defaults to ISO-8859-1.

Advanced Server ignores all cookies it receives.

The UTL_HTTP exceptions that can be raised in Oracle are not recognized by Advanced Server. In addition, the error codes returned by Advanced Server are not the same as those returned by Oracle.

There are various public constants available with UTL_HTTP. These are listed in the following tables.

The following table contains UTL_HTTP public constants defining HTTP versions and port assignments.

HTTP VERSIONS				
HTTP_VERSION_1_0	CONSTANT VARCHAR2(64) := 'HTTP/1.0';			
HTTP_VERSION_1_1	CONSTANT VARCHAR2(64) := 'HTTP/1.1';			
STANDARD PORT ASSIGNMENTS				
DEFAULT_HTTP_PORT	CONSTANT INTEGER := 80;			
DEFAULT_HTTPS_PORT	CONSTANT INTEGER := 443;			

The following table contains UTL_HTTP public status code constants.

1XX INFORMATIONAL		
HTTP_CONTINUE	CONSTANT INTEGER := 100;	
HTTP_SWITCHING_PROTOCOLS	CONSTANT INTEGER := 101;	
HTTP_PROCESSING	CONSTANT INTEGER := 102;	
2XX SUCCESS		
HTTP_OK	CONSTANT INTEGER := 200;	
HTTP_CREATED	CONSTANT INTEGER := 201;	
HTTP_ACCEPTED	CONSTANT INTEGER := 202;	
HTTP_NON_AUTHORITATIVE_INFO	CONSTANT INTEGER := 203;	
HTTP_NO_CONTENT	CONSTANT INTEGER := 204;	
HTTP_RESET_CONTENT	CONSTANT INTEGER := 205;	
HTTP_PARTIAL_CONTENT	CONSTANT INTEGER := 206;	
HTTP_MULTI_STATUS	CONSTANT INTEGER := 207;	
HTTP_ALREADY_REPORTED	CONSTANT INTEGER := 208;	
HTTP_IM_USED	CONSTANT INTEGER := 226;	
3XX REDIRECTION		
HTTP_MULTIPLE_CHOICES	CONSTANT INTEGER := 300;	
HTTP_MOVED_PERMANENTLY	CONSTANT INTEGER := 301;	
HTTP_FOUND	CONSTANT INTEGER := 302;	
HTTP_SEE_OTHER	CONSTANT INTEGER := 303;	
HTTP_NOT_MODIFIED	CONSTANT INTEGER := 304;	
HTTP_USE_PROXY	CONSTANT INTEGER := 305;	
HTTP_SWITCH_PROXY	CONSTANT INTEGER := 306;	
HTTP_TEMPORARY_REDIRECT	CONSTANT INTEGER := 307;	
HTTP_PERMANENT_REDIRECT	CONSTANT INTEGER := 308;	

4XX CLIENT ERROR	
HTTP_BAD_REQUEST	CONSTANT INTEGER := 400;
HTTP_UNAUTHORIZED	CONSTANT INTEGER := 401;
HTTP_PAYMENT_REQUIRED	CONSTANT INTEGER := 402;
HTTP_FORBIDDEN	CONSTANT INTEGER := 403;
HTTP_NOT_FOUND	CONSTANT INTEGER := 404;
HTTP_METHOD_NOT_ALLOWED	CONSTANT INTEGER := 405;
HTTP_NOT_ACCEPTABLE	CONSTANT INTEGER := 406;
HTTP_PROXY_AUTH_REQUIRED	CONSTANT INTEGER := 407;
HTTP_REQUEST_TIME_OUT	CONSTANT INTEGER := 408;
HTTP_CONFLICT	CONSTANT INTEGER := 409;
HTTP_GONE	CONSTANT INTEGER := 410;
HTTP_LENGTH_REQUIRED	CONSTANT INTEGER := 411;
HTTP_PRECONDITION_FAILED	CONSTANT INTEGER := 412;
HTTP_REQUEST_ENTITY_TOO_LARGE	CONSTANT INTEGER := 413;
HTTP_REQUEST_URI_TOO_LARGE	CONSTANT INTEGER := 414;
HTTP_UNSUPPORTED_MEDIA_TYPE	CONSTANT INTEGER := 415;
HTTP_REQ_RANGE_NOT_SATISFIABLE	CONSTANT INTEGER := 416;
HTTP_EXPECTATION_FAILED	CONSTANT INTEGER := 417;
HTTP_I_AM_A_TEAPOT	CONSTANT INTEGER := 418;
HTTP_AUTHENTICATION_TIME_OUT	CONSTANT INTEGER := 419;
HTTP_ENHANCE_YOUR_CALM	CONSTANT INTEGER := 420;
HTTP_UNPROCESSABLE_ENTITY	CONSTANT INTEGER := 422;
HTTP_LOCKED	CONSTANT INTEGER := 423;
HTTP_FAILED_DEPENDENCY	CONSTANT INTEGER := 424;
HTTP_UNORDERED_COLLECTION	CONSTANT INTEGER := 425;
HTTP_UPGRADE_REQUIRED	CONSTANT INTEGER := 426;
HTTP_PRECONDITION_REQUIRED	CONSTANT INTEGER := 428;
HTTP_TOO_MANY_REQUESTS	CONSTANT INTEGER := 429;
HTTP_REQUEST_HEADER_FIELDS_TOO_LARGE	CONSTANT INTEGER := 431;
HTTP_NO_RESPONSE	CONSTANT INTEGER := 444;
HTTP_RETRY_WITH	CONSTANT INTEGER := 449;
HTTP_BLOCKED_BY_WINDOWS_PARENTAL_CONTROLS	CONSTANT INTEGER := 450;
HTTP_REDIRECT	CONSTANT INTEGER := 451;
HTTP_REQUEST_HEADER_TOO_LARGE	CONSTANT INTEGER := 494;
HTTP_CERT_ERROR	CONSTANT INTEGER := 495;
HTTP_NO_CERT	CONSTANT INTEGER := 496;
HTTP_HTTP_TO_HTTPS	CONSTANT INTEGER := 497;
HTTP_CLIENT_CLOSED_REQUEST	CONSTANT INTEGER := 499;

5XX SERVER ERROR	
HTTP_INTERNAL_SERVER_ERROR	CONSTANT INTEGER := 500;
HTTP_NOT_IMPLEMENTED	CONSTANT INTEGER := 501;
HTTP_BAD_GATEWAY	CONSTANT INTEGER := 502;
HTTP_SERVICE_UNAVAILABLE	CONSTANT INTEGER := 503;
HTTP_GATEWAY_TIME_OUT	CONSTANT INTEGER := 504;
HTTP_VERSION_NOT_SUPPORTED	CONSTANT INTEGER := 505;
HTTP_VARIANT_ALSO_NEGOTIATES	CONSTANT INTEGER := 506;
HTTP_INSUFFICIENT_STORAGE	CONSTANT INTEGER := 507;
HTTP_LOOP_DETECTED	CONSTANT INTEGER := 508;
HTTP_BANDWIDTH_LIMIT_EXCEEDED	CONSTANT INTEGER := 509;
HTTP_NOT_EXTENDED	CONSTANT INTEGER := 510;
HTTP_NETWORK_AUTHENTICATION_REQUIRED	CONSTANT INTEGER := 511;
HTTP_NETWORK_READ_TIME_OUT_ERROR	CONSTANT INTEGER := 598;
HTTP_NETWORK_CONNECT_TIME_OUT_ERROR	CONSTANT INTEGER := 599;

3.21.1 HTML_PIECES

The UTL_HTTP package declares a type named HTML_PIECES, which is a table of type VARCHAR2 (2000) indexed by BINARY INTEGER. A value of this type is returned by the REQUEST_PIECES function.

```
TYPE html_pieces IS TABLE OF VARCHAR2(2000) INDEX BY BINARY_INTEGER;
```

3.21.2 REQ

The REQ record type holds information about each HTTP request.

```
TYPE req IS RECORD (
url VARCHAR2(32767), -- URL to be accessed
method VARCHAR2(64), -- HTTP method
http_version VARCHAR2(64), -- HTTP version
private_hndl INTEGER -- Holds handle for this request
);
```

3.21.3 RESP

The RESP record type holds information about the response from each HTTP request.

```
TYPE resp IS RECORD (
status_code INTEGER, -- HTTP status code
reason_phrase VARCHAR2(256), -- HTTP response reason phrase
http_version VARCHAR2(64), -- HTTP version
private_hndl INTEGER -- Holds handle for this response
);
```

3.21.4 BEGIN REQUEST

The BEGIN_REQUEST function initiates a new HTTP request. A network connection is established to the web server with the specified URL. The signature is:

```
BEGIN_REQUEST(<url> IN VARCHAR2, <method> IN VARCHAR2 DEFAULT
'GET ', <http_version> IN VARCHAR2 DEFAULT NULL) RETURN
UTL_HTTP.REQ
```

The BEGIN REQUEST function returns a record of type UTL HTTP.REQ.

Parameters

```
<url>
```

<url>
 is the Uniform Resource Locator from which UTL HTTP will return content.

<met.hod>

<method> is the HTTP method to be used. The default is GET.

<http_version>

>a>a<a href="http-vers

3.21.5 END REQUEST

The END_REQUEST procedure terminates an HTTP request. Use the END_REQUEST procedure to terminate an HTTP request without completing it and waiting for the response. The normal process is to begin the request, get the response, then close the response. The signature is:

```
END_REQUEST(<r> IN OUT UTL_HTTP.REQ)
```

Parameters

<r>

<r> is the HTTP request record.

3.21.6 END RESPONSE

The END_RESPONSE procedure terminates the HTTP response. The END_RESPONSE procedure completes the HTTP request and response. This is the normal method to end the request and response process. The signature is:

```
END_RESPONSE(<r> IN OUT UTL_HTTP.RESP)
```

Parameters

<r>

<r> is the HTTP response record.

3.21.7 GET_BODY_CHARSET

The GET_BODY_CHARSET program is available in the form of both a procedure and a function. A call to GET_BODY_CHARSET returns the default character set of the body of future HTTP requests.

The procedure signature is:

```
GET_BODY_CHARSET(<charset> OUT VARCHAR2)
```

The function signature is:

```
GET_BODY_CHARSET() RETURN VARCHAR2
```

This function returns a VARCHAR2 value.

Parameters

```
<charset>
```

<charset> is the character set of the body.

Examples

The following is an example of the GET_BODY_CHARSET function.

```
edb=# SELECT UTL_HTTP.GET_BODY_CHARSET() FROM DUAL;
get_body_charset
------
ISO-8859-1
(1 row)
```

3.21.8 GET_FOLLOW_REDIRECT

The GET_FOLLOW_REDIRECT procedure returns the current setting for the maximum number of redirections allowed. The signature is:

```
GET_FOLLOW_REDIRECT(<max_redirects> OUT INTEGER)
```

Parameters

```
<max_redirects>
```

<max_redirects> is maximum number of redirections allowed.

3.21.9 GET_HEADER

The GET_HEADER procedure returns the nth header of the HTTP response. The signature is:

```
GET_HEADER(<r> IN OUT UTL_HTTP.RESP, <n> INTEGER, <name> OUT
VARCHAR2, <value> OUT VARCHAR2)
```

Parameters

<value> is the value of the response header.

Examples

The following example retrieves the header count, then the headers.

```
DECLARE
                   UTL_HTTP.REQ;
   v_req
                  UTL_HTTP.RESP;
   v_resp
                   VARCHAR2(30);
   v_name
   v_value
                   VARCHAR2 (200);
   v_header_cnt INTEGER;
BEGIN
-- Initiate request and get response
   v_req := UTL_HTTP.BEGIN_REQUEST('www.enterprisedb.com');
   v_resp := UTL_HTTP.GET_RESPONSE(v_req);
-- Get header count
   v_header_cnt := UTL_HTTP.GET_HEADER_COUNT(v_resp);
   DBMS_OUTPUT.PUT_LINE('Header Count: ' || v_header_cnt);
-- Get all headers
   FOR i IN 1 .. v_header_cnt LOOP
        UTL_HTTP.GET_HEADER(v_resp, i, v_name, v_value);
       DBMS_OUTPUT.PUT_LINE(v_name || ': ' || v_value);
   END LOOP;
-- Terminate request
   UTL_HTTP.END_RESPONSE(v_resp);
END;
```

The following is the output from the example.

```
Header Count: 23
Age: 570
Cache-Control: must-revalidate
Content-Type: text/html; charset=utf-8
Date: Wed, 30 Apr 2015 14:57:52 GMT
ETag: "aab02f2bd2d696eed817ca89ef411dda"
Expires: Sun, 19 Nov 1978 05:00:00 GMT
Last-Modified: Wed, 30 Apr 2015 14:15:49 GMT
RTSS: 1-1307-3
Server: Apache/2.2.3 (Red Hat)
Set-Cookie: SESS2771d0952de2a1a84d322a262e0c173c=jn1u1j1etmdi5gg4lh8hakvs01;
→expires=Fri, 23-May-2015 18:21:43 GMT; path=/; domain=.enterprisedb.com
Vary: Accept-Encoding
Via: 1.1 varnish
X-EDB-Backend: ec
X-EDB-Cache: HIT
X-EDB-Cache-Address: 10.31.162.212
X-EDB-Cache-Server: ip-10-31-162-212
X-EDB-Cache-TTL: 600.000
X-EDB-Cacheable: MAYBE: The user has a cookie of some sort. Maybe it's double choc-
⇔chip!
X-EDB-Do-GZIP: false
X-Powered-By: PHP/5.2.17
X-Varnish: 484508634 484506789
transfer-encoding: chunked
Connection: keep-alive
```

3.21.10 GET HEADER BY NAME

The GET_HEADER_BY_NAME procedure returns the header of the HTTP response according to the specified name. The signature is:

```
GET_HEADER_BY_NAME(<r> IN OUT UTL_HTTP.RESP, <name> VARCHAR2,
<value> OUT VARCHAR2, <n> INTEGER DEFAULT 1)
```

Parameters

Examples

The following example retrieves the header for Content-Type.

```
DECLARE
   v_req
                  UTL_HTTP.REQ;
                  UTL_HTTP.RESP;
   v_resp
                   VARCHAR2(30) := 'Content-Type';
   v name
   v_value
                   VARCHAR2 (200);
BEGIN
   v_req := UTL_HTTP.BEGIN_REQUEST('www.enterprisedb.com');
   v_resp := UTL_HTTP.GET_RESPONSE(v_req);
   UTL_HTTP.GET_HEADER_BY_NAME(v_resp, v_name, v_value);
   DBMS_OUTPUT.PUT_LINE(v_name || ': ' || v_value);
   UTL HTTP.END RESPONSE (v resp);
END;
Content-Type: text/html; charset=utf-8
```

3.21.11 GET HEADER COUNT

The GET_HEADER_COUNT function returns the number of HTTP response headers. The signature is:

```
GET HEADER COUNT (<r> IN OUT UTL HTTP.RESP) RETURN INTEGER
```

This function returns an INTEGER value.

Parameters

<r>

<r> is the HTTP response record.

3.21.12 GET_RESPONSE

The GET_RESPONSE function sends the network request and returns any HTTP response. The signature is:

```
GET_RESPONSE(<r> IN OUT UTL_HTTP.REQ) RETURN UTL_HTTP.RESP
```

This function returns a UTL_HTTP.RESP record.

Parameters

<r>

<r> is the HTTP request record.

3.21.13 GET_RESPONSE_ERROR_CHECK

The GET_RESPONSE_ERROR_CHECK procedure returns whether or not response error check is set. The signature is:

```
GET_RESPONSE_ERROR_CHECK(<enable> OUT BOOLEAN)
```

Parameters

<enable>

<enable> returns TRUE if response error check is set, otherwise it returns FALSE.

3.21.14 GET_TRANSFER_TIMEOUT

The GET_TRANSFER_TIMEOUT procedure returns the current, default transfer timeout setting for HTTP requests. The signature is:

```
GET_TRANSFER_TIMEOUT (<timeout> OUT INTEGER)
```

Parameters

<timeout>

<timeout> is the transfer timeout setting in seconds.

3.21.15 READ LINE

The READ_LINE procedure returns the data from the HTTP response body in text form until the end of line is reached. A CR character, a LF character, a CR LF sequence, or the end of the response body constitutes the end of line. The signature is:

```
READ_LINE(<r> IN OUT UTL_HTTP.RESP, <data> OUT VARCHAR2, <remove_crlf>
BOOLEAN DEFAULT FALSE)
```

Parameters

Set <remove_crlf> to TRUE to remove new line characters, otherwise set to FALSE. The default is FALSE.

Examples

The following example retrieves and displays the body of the specified website.

```
DECLARE
                UTL_HTTP.REQ;
   v_req
   v_resp
                 UTL_HTTP.RESP;
               VARCHAR2(1024);
   v_value
   v_req := UTL_HTTP.BEGIN_REQUEST('http://www.enterprisedb.com');
   v_resp := UTL_HTTP.GET_RESPONSE(v_req);
   LOOP
       UTL_HTTP.READ_LINE(v_resp, v_value, TRUE);
       DBMS_OUTPUT.PUT_LINE(v_value);
   END LOOP;
   EXCEPTION
       WHEN OTHERS THEN
           UTL_HTTP.END_RESPONSE(v_resp);
END;
```

The following is the output.

→documentation, and tutorials." />

```
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"
   "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/xhtml" xml:lang="en" lang="en" dir="ltr">
   <!-- HEAD --->
   <head>
<meta http-equiv="Content-Type" content="text/html; charset=utf-8" />
   <title>EnterpriseDB | The Postgres Database Company</title>
   <meta http-equiv="Content-Type" content="text/html; charset=utf-8" />
   <meta name="keywords" content="postgres, postgresql, postgresql installer, mysql, migration, open source database, training, replication" />
   <meta name="description" content="The leader in open source database products, services, support, training and expertise based on PostgreSQL. Free downloads, services.</pre>
```

```
<meta name="abstract" content="The Enterprise PostgreSQL Company" />
<link rel="EditURI" type="application/rsd+xml" title="RSD" href="http://www.</pre>
→enterprisedb.com/blogapi/rsd" />
<link rel="alternate" type="application/rss+xml" title="EnterpriseDB RSS" href="http:/</pre>
→/www.enterprisedb.com/rss.xml" />
<link rel="shortcut icon" href="/sites/all/themes/edb_pixelcrayons/favicon.ico" type=</pre>
→ "image/x-icon" />
   <link type="text/css" rel="stylesheet" media="all" href="/sites/default/files/css/</pre>
⇒css_db11adabae0aed6b79a2c3c52def4754.css" />
<!--[if IE 6]>
<link type="text/css" rel="stylesheet" media="all" href="/sites/all/themes/oho_basic/</pre>
⇔css/ie6.css?q" />
<![endif]-->
<!--[if IE 7]>
<link type="text/css" rel="stylesheet" media="all" href="/sites/all/themes/oho_basic/</pre>
⇔css/ie7.css?g" />
<![endif]-->
    <script type="text/javascript" src="/sites/default/files/js/js_</pre>
→74d97b1176812e2fd6e43d62503a5204.js"></script>
<script type="text/javascript">
<!--//--><! [CDATA[//><!--
```

3.21.16 READ_RAW

The READ_RAW procedure returns the data from the HTTP response body in binary form. The number of bytes returned is specified by the <len> parameter. The signature is:

```
READ_RAW(<r> IN OUT UTL_HTTP.RESP, <data> OUT RAW, <len> INTEGER)
```

Parameters

Set <len> to the number of bytes of data to be returned.

Examples

The following example retrieves and displays the first 150 bytes in binary form.

The following is the output from the example.

```
\x3c21444f43545950452068746d6c205055424c494320222d2f2f5733432f2f4454442058485
44d4c20312e30205374726963742f2f454e220d0a202022687474703a2f2f7777772e77332e6f
72672f54522f7868746d6c312f4454442f7868746d6c312d7374726963742e647464223e0d0a3
c68746d6c20786d6c6e733d22687474703a2f2f7777772e77332e6f72672f313939392f
```

3.21.17 READ TEXT

The READ_TEXT procedure returns the data from the HTTP response body in text form. The maximum number of characters returned is specified by the <len> parameter. The signature is:

```
READ_TEXT(<r> IN OUT UTL_HTTP.RESP, <data> OUT VARCHAR2, <len>
INTEGER)
```

Parameters

Set <len> to the maximum number of characters to be returned.

Examples

The following example retrieves the first 150 characters.

The following is the output.

```
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"
  "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/"</pre>
```

3.21.18 REQUEST

The REQUEST function returns the first 2000 bytes retrieved from a user-specified URL. The signature is:

```
REQUEST (<url> IN VARCHAR2) RETURN VARCHAR2
```

If the data found at the given URL is longer than 2000 bytes, the remainder will be discarded. If the data found at the given URL is shorter than 2000 bytes, the result will be shorter than 2000 bytes.

Parameters

<url>

<ur><url> is the Uniform Resource Locator from which UTL_HTTP will return content.

Example

The following command returns the first 2000 bytes retrieved from the EnterpriseDB website:

```
SELECT UTL_HTTP.REQUEST('http://www.enterprisedb.com/') FROM DUAL;
```

3.21.19 REQUEST PIECES

The REQUEST_PIECES function returns a table of 2000-byte segments retrieved from an URL. The signature is:

```
REQUEST_PIECES(<url> IN VARCHAR2, <max_pieces> NUMBER IN DEFAULT 32767) RETURN UTL_HTTP.HTML_PIECES
```

Parameters

```
<url>
```

<url> is the Uniform Resource Locator from which UTL_HTTP will return content.

```
<max_pieces>
```

<max_pieces> specifies the maximum number of 2000-byte segments that the REQUEST_PIECES
function will return. If <max_pieces> specifies more units than are available at the specified <url>,
the final unit will contain fewer bytes.

Example

The following example returns the first four 2000 byte segments retrieved from the EnterpriseDB website:

```
DECLARE

result UTL_HTTP.HTML_PIECES;

BEGIN

result := UTL_HTTP.REQUEST_PIECES('http://www.enterprisedb.com/', 4);

END
```

3.21.20 SET BODY CHARSET

The SET_BODY_CHARSET procedure sets the default character set of the body of future HTTP requests. The signature is:

```
SET BODY CHARSET (<charset> VARCHAR2 DEFAULT NULL)
```

Parameters

<charset>

<charset> is the character set of the body of future requests. The default is null in which case the
database character set is assumed.

3.21.21 SET FOLLOW REDIRECT

The SET_FOLLOW_REDIRECT procedure sets the maximum number of times the HTTP redirect instruction is to be followed in the response to this request or future requests. This procedures has two signatures:

```
SET_FOLLOW_REDIRECT(<max_redirects> IN INTEGER DEFAULT 3)
and
SET_FOLLOW_REDIRECT(<r> IN OUT UTL_HTTP.REQ, <max_redirects> IN INTEGER DEFAULT 3)
```

Use the second form to change the maximum number of redirections for an individual request that a request inherits from the session default settings.

Parameters

<r>

```
<r> is the HTTP request record.
```

```
<max_redirects>
```

<max_redirects> is maximum number of redirections allowed. Set to 0 to disable redirections. The default is 3.

3.21.22 SET HEADER

The SET_HEADER procedure sets the HTTP request header. The signature is:

```
SET_HEADER(<r> IN OUT UTL_HTTP.REQ, <name> IN VARCHAR2, <value>
IN VARCHAR2 DEFAULT NULL)
```

Parameters

```
\langle r \rangle
```

<r> is the HTTP request record.

<name>

<name> is the name of the request header.

<value>

<value> is the value of the request header. The default is null.

3.21.23 SET RESPONSE ERROR CHECK

The SET_RESPONSE_ERROR_CHECK procedure determines whether or not HTTP 4xx and 5xx status codes returned by the GET_RESPONSE function should be interpreted as errors. The signature is:

```
SET RESPONSE ERROR CHECK (<enable> IN BOOLEAN DEFAULT FALSE)
```

Parameters

<enable>

Set <enable> to TRUE if HTTP 4xx and 5xx status codes are to be treated as errors, otherwise set to FALSE. The default is FALSE.

3.21.24 SET TRANSFER TIMEOUT

The SET_TRANSFER_TIMEOUT procedure sets the default, transfer timeout setting for waiting for a response from an HTTP request. This procedure has two signatures:

```
SET_TRANSFER_TIMEOUT(<timeout> IN INTEGER DEFAULT 60)

and

SET_TRANSFER_TIMEOUT(<r> IN OUT UTL_HTTP.REQ, <timeout> IN INTEGER DEFAULT 60)
```

Use the second form to change the transfer timeout setting for an individual request that a request inherits from the session default settings.

Parameters

3.21.25 WRITE LINE

The WRITE_LINE procedure writes data to the HTTP request body in text form; the text is terminated with a CRLF character pair. The signature is:

```
\label{eq:write_line} \mbox{WRITE\_LINE(<r> IN OUT UTL\_HTTP.REQ, <data> IN VARCHAR2)}
```

Parameters

Example

The following example writes data (Account balance \$500.00) in text form to the request body to be sent using the HTTP POST method. The data is sent to a hypothetical web application (post.php) that accepts and processes data.

Assuming the web application successfully processed the POST method, the following output would be displayed:

```
Status Code: 200
Reason Phrase: OK
```

3.21.26 WRITE RAW

The WRITE_RAW procedure writes data to the HTTP request body in binary form. The signature is:

```
WRITE_RAW(<r> IN OUT UTL_HTTP.REQ, <data> IN RAW)
```

Parameters

```
<r>
  <r>  is the HTTP request record.
<data>
```

<data> is the request body in binary form.

Example

The following example writes data in binary form to the request body to be sent using the HTTP POST method to a hypothetical web application that accepts and processes such data.

```
DECLARE
                    UTL_HTTP.REQ;
    v_req
   v_resp
                    UTL_HTTP.RESP;
BEGIN
   v_req := UTL_HTTP.BEGIN_REQUEST('http://www.example.com/post.php',
       'POST');
   UTL_HTTP.SET_HEADER(v_req, 'Content-Length', '23');
   UTL_HTTP.WRITE_RAW(v_req, HEXTORAW
('54657374696e6720504f5354206d6574686f6420696e20485454502072657175657374'));
   v_resp := UTL_HTTP.GET_RESPONSE(v_req);
   DBMS_OUTPUT.PUT_LINE('Status Code: ' || v_resp.status_code);
   DBMS_OUTPUT.PUT_LINE('Reason Phrase: ' || v_resp.reason_phrase);
   UTL_HTTP.END_RESPONSE(v_resp);
END;
```

The text string shown in the HEXTORAW function is the hexadecimal translation of the text Testing POST method in HTTP request.

Assuming the web application successfully processed the POST method, the following output would be displayed:

```
Status Code: 200
Reason Phrase: OK
```

3.21.27 WRITE TEXT

The WRITE_TEXT procedure writes data to the HTTP request body in text form. The signature is:

```
WRITE_TEXT(<r> IN OUT UTL_HTTP.REQ, <data> IN VARCHAR2)
```

Parameters

Example

The following example writes data (Account balance \$500.00) in text form to the request body to be sent using the HTTP POST method. The data is sent to a hypothetical web application (post.php) that accepts and processes data.

Assuming the web application successfully processed the POST method, the following output would be displayed:

```
Status Code: 200
Reason Phrase: OK
```

3.22 UTL_MAIL

The $\mathtt{UTL_MAIL}$ package provides the capability to manage e-mail. Advanced Server supports the following procedures:

Function/Procedure	Re-	Description
	turn	
	Type	
SEND(<sender>, <recipients>, <cc>, <bcc>, <subject>, <message> [,</message></subject></bcc></cc></recipients></sender>	n/a	Packages and sends an e-mail
<mime_type> [, <priority>]])</priority></mime_type>		to an SMTP server.
SEND_ATTACH_RAW(<sender>, <recipients>, <cc>, <bcc>, <subject>,</subject></bcc></cc></recipients></sender>	n/a	Same as the SEND proce-
<pre><message>, <mime_type>, <priority>, <attachment> [, <att_inline> [,</att_inline></attachment></priority></mime_type></message></pre>		dure, but with BYTEA or
<att_mime_type> [, <att_filename>]]])</att_filename></att_mime_type>		large object attachments.
SEND_ATTACH_VARCHAR2(<sender>, <recipients>, <cc>, <bcc>,</bcc></cc></recipients></sender>	n/a	Same as the SEND proce-
<pre><subject>, <message>, <mime_type>, <priority>, <attachment> [,</attachment></priority></mime_type></message></subject></pre>		dure, but with VARCHAR2
<att_inline>[, <att_mime_type>[, <att_filename>]]])</att_filename></att_mime_type></att_inline>		attachments.

Note: An administrator must grant execute privileges to each user or group before they can use this package.

3.22. UTL_MAIL 306

3.22.1 SEND

```
The SEND procedure provides the capability to send an e-mail to an SMTP server.
```

```
SEND(<sender> VARCHAR2, <recipients> VARCHAR2, <cc> VARCHAR2, <bc> VARCHAR2, <subject> VARCHAR2, <message> VARCHAR2 [, <mime_type> VARCHAR2 [, <pri>PLS_INTEGER ]])
```

Parameters

```
<sender>
```

E-mail address of the sender.

```
<recipients>
```

Comma-separated e-mail addresses of the recipients.

<cc>

Comma-separated e-mail addresses of copy recipients.

<bcc>

Comma-separated e-mail addresses of blind copy recipients.

<subject>

Subject line of the e-mail.

<message>

Body of the e-mail.

<mime_type>

Mime type of the message. The default is text/plain; charset=us-ascii.

<priority>

Priority of the e-mail The default is 3.

Examples

The following anonymous block sends a simple e-mail message.

```
DECLARE
   v_sender
                  VARCHAR2(30);
   v_recipients VARCHAR2(60);
   v_subj
                   VARCHAR2 (20);
                  VARCHAR2 (200);
   v_msg
BEGIN
   v_sender := 'jsmith@enterprisedb.com';
   v_recipients := 'ajones@enterprisedb.com,rrogers@enterprisedb.com';
   v_subj := 'Holiday Party';
   v_msg := 'This year''s party is scheduled for Friday, Dec. 21 at ' ||
            '6:00 PM. Please RSVP by Dec. 15th.';
   UTL_MAIL.SEND(v_sender,v_recipients,NULL,NULL,v_subj,v_msg);
END;
```

3.22. UTL MAIL 307

3.22.2 SEND ATTACH RAW

The SEND_ATTACH_RAW procedure provides the capability to send an e-mail to an SMTP server with an attachment containing either BYTEA data or a large object (identified by the large object's OID). The call to SEND_ATTACH_RAW can be written in two ways:

```
SEND_ATTACH_RAW(<sender> VARCHAR2, <recipients> VARCHAR2, <cc> VARCHAR2,
<bcc> VARCHAR2, <subject> VARCHAR2, <message> VARCHAR2, <mime_type> VARCHAR2,
<priority> PLS_INTEGER, <attachment> BYTEA[, <att_inline> BOOLEAN [,
<att_mime_type> VARCHAR2[, <att_filename> VARCHAR2 ]]])
SEND ATTACH RAW(<sender> VARCHAR2, <recipients> VARCHAR2, <cc> VARCHAR2,
<bcc> VARCHAR2, <subject> VARCHAR2, <message> VARCHAR2, <mime_type>
VARCHAR2, <priority> PLS_INTEGER, <attachment> OID [, <att_inline> BOOLEAN
[, <att_mime_type> VARCHAR2 [, <att_filename> VARCHAR2 ]]])
Parameters
<sender>
    E-mail address of the sender.
<recipients>
    Comma-separated e-mail addresses of the recipients.
<cc>
    Comma-separated e-mail addresses of copy recipients.
    Comma-separated e-mail addresses of blind copy recipients.
<subject>
    Subject line of the e-mail.
<message>
    Body of the e-mail.
<mime_type>
    Mime type of the message. The default is text/plain; charset=us-ascii.
```

3.22. UTL MAIL 308

<priority>

Priority of the e-mail. The default is 3.

<attachment>

The attachment.

<att_inline>

If set to TRUE, then the attachment is viewable inline, FALSE otherwise. The default is TRUE.

<att_mime_type>

Mime type of the attachment. The default is application/octet.

<att_filename>

The file name containing the attachment. The default is null.

3.22. UTL_MAIL 309

3.22.3 SEND ATTACH VARCHAR2

The SEND_ATTACH_VARCHAR2 procedure provides the capability to send an e-mail to an SMTP server with a text attachment.

```
SEND_ATTACH_VARCHAR2(<sender> VARCHAR2, <recipients> VARCHAR2, <cc> VARCHAR2, <bc> VARCHAR2, <mime_type> VARCHAR2, <priority> PLS_INTEGER, <attachment> VARCHAR2 [, <att_inline> BOOLEAN [, <att_mime_type> VARCHAR2 [, <att_filename> VARCHAR2 ]]])
```

Parameters

```
<sender>
```

E-mail address of the sender.

<recipients>

Comma-separated e-mail addresses of the recipients.

<cc>

Comma-separated e-mail addresses of copy recipients.

<bcc>

Comma-separated e-mail addresses of blind copy recipients.

<subject>

Subject line of the e-mail.

<message>

Body of the e-mail.

<mime_type>

Mime type of the message. The default is text/plain; charset=us-ascii.

<priority>

Priority of the e-mail The default is 3.

<attachment>

The VARCHAR2 attachment.

<att_inline>

If set to TRUE, then the attachment is viewable inline, FALSE otherwise. The default is TRUE.

<att_mime_type>

Mime type of the attachment. The default is text/plain; charset=us-ascii.

<att_filename>

The file name containing the attachment. The default is null.

3.22. UTL MAIL 310

3.23 UTL_RAW

The UTL_RAW package allows you to manipulate or retrieve the length of raw data types.

Note: An administrator must grant execute privileges to each user or group before they can use this package.

Function/Procedure	Function or Proce-	Return Type	Description
	dure		
CAST_TO_RAW(c IN VAR-	Function	RAW	Converts a VARCHAR2 string
CHAR2)			to a RAW value.
CAST_TO_VARCHAR2(r IN	Function	VARCHAR2	Converts a RAW value to a
RAW)			VARCHAR2 string.
CONCAT(r1 IN RAW, r2 IN	Function	RAW	Concatenate multiple RAW val-
RAW, r3 IN RAW,)			ues into a single RAW value.
CONVERT(r IN RAW,	Function	RAW	Converts encoded data from one
to_charset IN VARCHAR2,			encoding to another, and returns
from_charset IN VARCHAR2			the result as a RAW value.
LENGTH(r IN RAW)	Function	NUMBER	Returns the length of a RAW
			value.
SUBSTR(r IN RAW, pos IN IN-	Function	RAW	Returns a portion of a RAW
TEGER, len IN INTEGER)			value.

Advanced Server's implementation of UTL_RAW is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

3.23.1 CAST_TO_RAW

The CAST_TO_RAW function converts a VARCHAR2 string to a RAW value. The signature is:

```
CAST_TO_RAW(<c> VARCHAR2)
```

The function returns a RAW value if you pass a non-NULL value; if you pass a NULL value, the function will return NULL.

Parameters

<c>

The VARCHAR2 value that will be converted to RAW.

Example

The following example uses the CAST_TO_RAW function to convert a VARCHAR2 string to a RAW value:

```
DECLARE
  v VARCHAR2;
  r RAW;
BEGIN
  v := 'Accounts';
  dbms_output.put_line(v);
  r := UTL_RAW.CAST_TO_RAW(v);
  dbms_output.put_line(r);
END;
```

3.23. UTL RAW 311

The result set includes the content of the original string and the converted RAW value:

```
Accounts
\x4163636f756e7473
```

3.23.2 CAST_TO_VARCHAR2

The CAST_TO_VARCHAR2 function converts RAW data to VARCHAR2 data. The signature is:

```
CAST_TO_VARCHAR2(<r> RAW)
```

The function returns a VARCHAR2 value if you pass a non-NULL value; if you pass a NULL value, the function will return NULL.

Parameters

<r>

The RAW value that will be converted to a VARCHAR2 value.

Example

The following example uses the CAST_TO_VARCHAR2 function to convert a RAW value to a VARCHAR2 string:

```
DECLARE
    r RAW;
    v VARCHAR2;
BEGIN
    r := '\x4163636f756e7473'
    dbms_output.put_line(v);
    v := UTL_RAW.CAST_TO_VARCHAR2(r);
    dbms_output.put_line(r);
END;
```

The result set includes the content of the original string and the converted RAW value:

```
\x4163636f756e7473
Accounts
```

3.23. UTL_RAW 312

3.23.3 **CONCAT**

The CONCAT function concatenates multiple RAW values into a single RAW value. The signature is:

```
CONCAT(<r1> RAW, <r2> RAW, <r3> RAW,...)
```

The function returns a RAW value. Unlike the Oracle implementation, the Advanced Server implementation is a variadic function, and does not place a restriction on the number of values that can be concatenated.

Parameters

```
<r1, r2, r3,...>
```

The RAW values that CONCAT will concatenate.

Example

The following example uses the CONCAT function to concatenate multiple RAW values into a single RAW value:

```
| SELECT UTL_RAW.CAST_TO_VARCHAR2(UTL_RAW.CONCAT('\x61', '\x62', | '\x63')) FROM DUAL;
| concat
| ------
| abc
| (1 row)
```

The result (the concatenated values) is then converted to VARCHAR2 format by the CAST_TO_VARCHAR2 function.

3.23. UTL_RAW 313

3.23.4 CONVERT

The CONVERT function converts a string from one encoding to another encoding and returns the result as a RAW value. The signature is:

```
CONVERT(<r> RAW, <to_charset> VARCHAR2, <from_charset> VARCHAR2)
```

The function returns a RAW value.

Parameters

```
<r>
```

The RAW value that will be converted.

```
<to charset>
```

The name of the encoding to which <r> will be converted.

```
<from charset>
```

The name of the encoding from which <r> will be converted.

Example

The following example uses the UTL_RAW.CAST_TO_RAW function to convert a VARCHAR2 string (Accounts) to a raw value, and then convert the value from UTF8 to LATIN7, and then from LATIN7 to UTF8:

```
DECLARE
    r RAW;
    v VARCHAR2;
BEGIN
    v:= 'Accounts';
    dbms_output.put_line(v);
    r:= UTL_RAW.CAST_TO_RAW(v);
    dbms_output.put_line(r);
    r:= UTL_RAW.CONVERT(r, 'UTF8', 'LATIN7');
    dbms_output.put_line(r);
    r:= UTL_RAW.CONVERT(r, 'LATIN7', 'UTF8');
    dbms_output.put_line(r);
```

The example returns the VARCHAR2 value, the RAW value, and the converted values:

```
Accounts
\x4163636f756e7473
\x4163636f756e7473
\x4163636f756e7473
```

3.23. UTL RAW 314

3.23.5 LENGTH

The LENGTH function returns the length of a RAW value. The signature is:

```
LENGTH (<r> RAW)
```

The function returns a RAW value.

Parameters

<r>

The RAW value that LENGTH will evaluate.

Example

The following example uses the LENGTH function to return the length of a RAW value:

```
SELECT UTL_RAW.LENGTH(UTL_RAW.CAST_TO_RAW('Accounts')) FROM DUAL;
length
-----
8
(1 row)
```

The following example uses the LENGTH function to return the length of a RAW value that includes multi-byte characters:

```
SELECT UTL_RAW.LENGTH(UTL_RAW.CAST_TO_RAW('hello'));
length
-----
5
(1 row)
```

3.23. UTL_RAW 315

3.23.6 SUBSTR

The SUBSTR function returns a substring of a RAW value. The signature is:

```
SUBSTR (<r> RAW, <pos> INTEGER, <len> INTEGER)
```

This function returns a RAW value.

Parameters

<r>

The RAW value from which the substring will be returned.

<pos>

The position within the RAW value of the first byte of the returned substring.

- If <pos> is 0 or 1, the substring begins at the first byte of the RAW value.
- If <pos> is greater than one, the substring begins at the first byte specified by <pos>. For example, if <pos> is 3, the substring begins at the third byte of the value.
- If <pos> is negative, the substring begins at <pos> bytes from the end of the source value. For example, if <pos> is -3, the substring begins at the third byte from the end of the value.

<len>

The maximum number of bytes that will be returned.

Example

The following example uses the SUBSTR function to select a substring that begins 3 bytes from the start of a RAW value:

```
SELECT UTL_RAW.SUBSTR(UTL_RAW.CAST_TO_RAW('Accounts'), 3, 5) FROM DUAL;
substr
-----
count
(1 row)
```

The following example uses the SUBSTR function to select a substring that starts 5 bytes from the end of a RAW value:

```
SELECT UTL_RAW.SUBSTR(UTL_RAW.CAST_TO_RAW('Accounts'), -5 , 3) FROM DUAL; substr -------- oun (1 row)
```

3.23. UTL RAW 316

3.24 UTL_SMTP

The UTL_SMTP package provides the capability to send e-mails over the Simple Mail Transfer Protocol (SMTP).

Note: An administrator must grant execute privileges to each user or group before they can use this package.

Function/Procedure	Function or Proce-	Return Type	Description
	dure		
CLOSE_DATA(c IN OUT)	Procedure	n/a	Ends an e-mail message.
COMMAND(c IN OUT, cmd [,	Both	REPLY	Execute an SMTP command.
arg])			
COMMAND_REPLIES(c IN	Function	REPLIES	Execute an SMTP command
OUT, cmd [, arg])			where multiple reply lines are expected.
DATA(c IN OUT, body VAR-	Procedure	n/a	Specify the body of an e-mail
CHAR2)			message.
EHLO(c IN OUT, domain)	Procedure	n/a	Perform initial handshaking
			with an SMTP server and return
THE COLUMN TO TH			extended information.
HELO(c IN OUT, domain)	Procedure	n/a	Perform initial handshaking
HELD, DIOLET	F .:	DEDITIES	with an SMTP server
HELP(c IN OUT [, command])	Function	REPLIES	Send the HELP command.
MAIL(c IN OUT, sender [, parameters])	Procedure	n/a	Start a mail transaction.
NOOP(c IN OUT)	Both	REPLY	Send the null command.
OPEN_CONNECTION(host [,	Function	CONNECTION	Open a connection.
port [, tx_timeout]])			_
OPEN_DATA(c IN OUT)	Both	REPLY	Send the DATA command.
QUIT(c IN OUT)	Procedure	n/a	Terminate the SMTP session and disconnect.
RCPT(c IN OUT, recipient [,	Procedure	n/a	Specify the recipient of an e-
parameters])			mail message.
RSET(c IN OUT)	Procedure	n/a	Terminate the current mail
			transaction.
VRFY(c IN OUT, recipient)	Function	REPLY	Validate an e-mail address.
WRITE_DATA(c IN OUT, data)	Procedure	n/a	Write a portion of the e-mail
			message.

Advanced Server's implementation of UTL_SMTP is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The following table lists the public variables available in the ${\tt UTL_SMTP}$ package.

Public Variables	Data Type	Value	Description
connection	RECORD		Description of an SMTP connection.
reply	RECORD		SMTP reply line.

3.24. UTL_SMTP 317

3.24.1 CONNECTION

The CONNECTION record type provides a description of an SMTP connection.

```
TYPE connection IS RECORD (
host VARCHAR2(255),
port PLS_INTEGER,
tx_timeout PLS_INTEGER
);
```

3.24.2 REPLY/REPLIES

The REPLY record type provides a description of an SMTP reply line. REPLIES is a table of multiple SMTP reply lines.

```
TYPE reply IS RECORD (
code INTEGER,
text VARCHAR2(508)
);
TYPE replies IS TABLE OF reply INDEX BY BINARY_INTEGER;
```

3.24.3 CLOSE_DATA

The CLOSE_DATA procedure terminates an e-mail message by sending the following sequence:

```
<CR><LF>.<CR><LF>
```

This is a single period at the beginning of a line.

```
CLOSE_DATA(<c> IN OUT CONNECTION)
```

Parameters

<c>

The SMTP connection to be closed.

3.24.4 COMMAND

The COMMAND procedure provides the capability to execute an SMTP command. If you are expecting multiple reply lines, use COMMAND_REPLIES.

```
<reply> REPLY COMMAND(<c> IN OUT CONNECTION, <cmd> VARCHAR2
[, <arg> VARCHAR2 ])
COMMAND(<c> IN OUT CONNECTION, <cmd> VARCHAR2 [, <arg> VARCHAR2 ])
```

Parameters

<c>

The SMTP connection to which the command is to be sent.

<cmd>

The SMTP command to be processed.

```
<arg>
```

An argument to the SMTP command. The default is null.

```
<reply>
```

SMTP reply to the command. If SMTP returns multiple replies, only the last one is returned in <reply>.

See *Reply/Replies* for a description of REPLY and REPLIES.

3.24.5 COMMAND REPLIES

The COMMAND_REPLIES function processes an SMTP command that returns multiple reply lines. Use COMMAND if only a single reply line is expected.

```
<replies> REPLIES COMMAND(<c> IN OUT CONNECTION, <cmd> VARCHAR2
[, <arg> VARCHAR2 ])
```

Parameters

<c>

The SMTP connection to which the command is to be sent.

<cmd>

The SMTP command to be processed.

<arg>

An argument to the SMTP command. The default is null.

<replies>

SMTP reply lines to the command. See *Reply/Replies* for a description of REPLY and REPLIES.

3.24.6 DATA

The DATA procedure provides the capability to specify the body of the e-mail message. The message is terminated with a <CR><LF>.<CR><LF> sequence.

```
DATA(<c> IN OUT CONNECTION, <body> VARCHAR2)
```

Parameters

<c>

The SMTP connection to which the command is to be sent.

<body>

Body of the e-mail message to be sent.

3.24.7 EHLO

The EHLO procedure performs initial handshaking with the SMTP server after establishing the connection. The EHLO procedure allows the client to identify itself to the SMTP server according to RFC 821. RFC 1869 specifies the format of the information returned in the server's reply. The *HELO* procedure performs the equivalent functionality, but returns less information about the server.

```
EHLO(<c> IN OUT CONNECTION, <domain> VARCHAR2)
```

Parameters

<c>

The connection to the SMTP server over which to perform handshaking.

<domain>

Domain name of the sending host.

3.24.8 HELO

The HELO procedure performs initial handshaking with the SMTP server after establishing the connection. The HELO procedure allows the client to identify itself to the SMTP server according to RFC 821. The *EHLO* procedure performs the equivalent functionality, but returns more information about the server.

```
HELO(<c> IN OUT, <domain*> VARCHAR2)
```

Parameters

<c>

The connection to the SMTP server over which to perform handshaking.

<domain>

Domain name of the sending host.

3.24.9 HELP

The HELP function provides the capability to send the HELP command to the SMTP server.

```
<replies> REPLIES HELP(<c> IN OUT CONNECTION [, <command> VARCHAR2])
```

Parameters

<c>

The SMTP connection to which the command is to be sent.

<command>

Command on which help is requested.

<replies>

SMTP reply lines to the command. See *Reply/Replies* for a description of REPLY and REPLIES.

3.24.10 MAIL

The MAIL procedure initiates a mail transaction.

Parameters

<c>

Connection to SMTP server on which to start a mail transaction.

<sender>

The sender's e-mail address.

<parameters>

Mail command parameters in the format, key=value as defined in RFC 1869.

3.24.11 NOOP

The NOOP function/procedure sends the null command to the SMTP server. The NOOP has no effect upon the server except to obtain a successful response.

```
<reply> REPLY NOOP(<c> IN OUT CONNECTION)
NOOP(<c> IN OUT CONNECTION)
```

Parameters

<c>

The SMTP connection on which to send the command.

<reply>

SMTP reply to the command. If SMTP returns multiple replies, only the last one is returned in <peply>. See *Reply/Replies* for a description of REPLY and REPLIES.

3.24.12 OPEN CONNECTION

The OPEN_CONNECTION functions open a connection to an SMTP server.

```
<c> CONNECTION OPEN_CONNECTION(<host> VARCHAR2 [, <port>
PLS_INTEGER [, <tx_timeout> PLS_INTEGER DEFAULT NULL]])
```

Parameters

<host>

Name of the SMTP server.

<port>

Port number on which the SMTP server is listening. The default is 25.

```
<tx_timeout>
```

Time out value in seconds. Do not wait is indicated by specifying 0. Wait indefinitely is indicated by setting timeout to null. The default is null.

<c>

Connection handle returned by the SMTP server.

3.24.13 OPEN DATA

The OPEN_DATA procedure sends the DATA command to the SMTP server.

```
OPEN_DATA(<c> IN OUT CONNECTION)
```

Parameters

<c>

SMTP connection on which to send the command.

3.24.14 QUIT

The QUIT procedure closes the session with an SMTP server.

```
QUIT(<c> IN OUT CONNECTION)
```

Parameters

<c>

SMTP connection to be terminated.

3.24.15 RCPT

The RCPT procedure provides the e-mail address of the recipient. To schedule multiple recipients, invoke RCPT multiple times.

```
RCPT(<c> IN OUT CONNECTION, <recipient> VARCHAR2
[, parameters> VARCHAR2 ])
```

Parameters

<C>

Connection to SMTP server on which to add a recipient.

<recipient>

The recipient's e-mail address.

<parameters>

Mail command parameters in the format, key=value as defined in RFC 1869.

3.24.16 RSET

The RSET procedure provides the capability to terminate the current mail transaction.

```
RSET(<c> IN OUT CONNECTION)
```

Parameters

<c>

SMTP connection on which to cancel the mail transaction.

3.24.17 VRFY

The VRFY function provides the capability to validate and verify the recipient's e-mail address. If valid, the recipient's full name and fully qualified mailbox is returned.

```
<reply> REPLY VRFY(<c> IN OUT CONNECTION, <recipient> VARCHAR2)
```

Parameters

<c>

The SMTP connection on which to verify the e-mail address.

<recipient>

The recipient's e-mail address to be verified.

<reply>

SMTP reply to the command. If SMTP returns multiple replies, only the last one is returned in *reply*. See *Reply/Replies* for a description of REPLY and REPLIES.

3.24.18 **WRITE_DATA**

The WRITE_DATA procedure provides the capability to add VARCHAR2 data to an e-mail message. The WRITE_DATA procedure may be repetitively called to add data.

```
WRITE_DATA(<c> IN OUT CONNECTION, <data> VARCHAR2)
```

Parameters

<c>

The SMTP connection on which to add data.

<data>

Data to be added to the e-mail message. The data must conform to the RFC 822 specification.

3.24.19 Comprehensive Example

The following procedure constructs and sends a text e-mail message using the UTL_SMTP package.

```
CREATE OR REPLACE PROCEDURE send_mail (
   p_sender VARCHAR2,
   p_recipient
                 VARCHAR2,
   p_subj
                  VARCHAR2,
                  VARCHAR2,
   p_msg
   p_mailhost
                  VARCHAR2
IS
                 UTL SMTP.CONNECTION;
   v conn
   v_crlf
                  CONSTANT VARCHAR2(2) := CHR(13) \mid CHR(10);
                  CONSTANT PLS_INTEGER := 25;
   v_port
BEGIN
   v_conn := UTL_SMTP.OPEN_CONNECTION(p_mailhost, v_port);
   UTL_SMTP.HELO(v_conn,p_mailhost);
   UTL_SMTP.MAIL(v_conn,p_sender);
   UTL_SMTP.RCPT(v_conn,p_recipient);
   UTL_SMTP.DATA(v_conn, SUBSTR(
        'Date: ' || TO_CHAR(SYSDATE,
```

The following example uses the OPEN_DATA, WRITE_DATA, and CLOSE_DATA procedures instead of the DATA procedure.

```
CREATE OR REPLACE PROCEDURE send_mail_2 (
   p_sender
                 VARCHAR2,
   p_recipient
                  VARCHAR2,
   p_subj
                   VARCHAR2,
   p_msg
                   VARCHAR2,
                   VARCHAR2
   p_mailhost
IS
   v conn
                   UTL SMTP.CONNECTION;
                   CONSTANT VARCHAR2(2) := CHR(13) \mid \mid CHR(10);
   v_crlf
   v_port
                  CONSTANT PLS_INTEGER := 25;
BEGIN
   v_conn := UTL_SMTP.OPEN_CONNECTION(p_mailhost, v_port);
   UTL_SMTP.HELO(v_conn,p_mailhost);
   UTL_SMTP.MAIL(v_conn,p_sender);
   UTL_SMTP.RCPT(v_conn,p_recipient);
   UTL_SMTP.OPEN_DATA(v_conn);
   UTL_SMTP.WRITE_DATA(v_conn,'From: ' || p_sender || v_crlf);
   UTL_SMTP.WRITE_DATA(v_conn,'To: ' || p_recipient || v_crlf);
   UTL_SMTP.WRITE_DATA(v_conn,'Subject: ' || p_subj || v_crlf);
   UTL_SMTP.WRITE_DATA(v_conn, v_crlf || p_msg);
   UTL SMTP.CLOSE DATA(v conn);
   UTL_SMTP.QUIT(v_conn);
END;
EXEC send_mail_2('asmith@enterprisedb.com', 'pjones@enterprisedb.com', 'Holiday Party',
→ 'Are you planning to attend?', 'smtp.enterprisedb.com');
```

3.25 UTL_URL

The UTL_URL	package provides a	a way to escape	illegal and reserved	l characters with	in an URL.

Function/Procedure	Return	Description
	Type	
ESCAPE(url, es-	VAR-	Use the ESCAPE function to escape any illegal and reserved
cape_reserved_chars, url_charset) CHAR2		characters in a URL.
UNESCAPE(url, url_charset)	VAR-	The UNESCAPE function to convert an URL to it's original
	CHAR2	form.

The UTL_URL package will return the BAD_URL exception if the call to a function includes an incorrectly-formed URL.

3.25.1 **ESCAPE**

Use the ESCAPE function to escape illegal and reserved characters within an URL. The signature is:

Reserved characters are replaced with a percent sign, followed by the two-digit hex code of the ascii value for the escaped character.

Parameters

<url>

<url> specifies the Uniform Resource Locator that UTL_URL will escape.

```
<escape_reserved_chars>
```

<escape_reserved_chars> is a BOOLEAN value that instructs the ESCAPE function to escape
reserved characters as well as illegal characters:

- If <escaped_reserved_chars> is FALSE, ESCAPE will escape only the illegal characters in the specified URL.
- If <escape_reserved_chars> is TRUE, ESCAPE will escape both the illegal characters and the reserved characters in the specified URL.

By default, <escape_reserved_chars> is FALSE.

Within an URL, legal characters are:

Uppercase A through Z	Lowercase a through z	0 through 9	
asterisk (*)	exclamation point (!)	hyphen (-)	
left parenthesis (()	period (.)	right parenthesis ())	
single-quote (')	tilde (~)	underscore (_)	

Some characters are legal in some parts of an URL, while illegal in others; to review comprehensive rules about illegal characters, please refer to RFC 2396. Some *examples* of characters that are considered illegal in any part of an URL are:

3.25. UTL URL 325

Illegal Character	Escape Sequence	
a blank space ()	%20	
curly braces ({ or })	%7b and %7d	
hash mark (#)	%23	

The ESCAPE function considers the following characters to be reserved, and will escape them if <escape_reserved_chars> is set to TRUE:

Reserved Character	Escape Sequence
ampersand (&)	%5C
at sign (@)	%25
colon (:)	%3a
comma (,)	%2c
dollar sign (\$)	%24
equal sign (=)	%3d
plus sign (+)	%2b
question mark (?)	%3f
semi-colon (;)	%3b
slash (/)	%2f

<url_charset>

<url_charset> specifies a character set to which a given character will be converted before it is
escaped. If <url_charset> is NULL, the character will not be converted. The default value of
<url_charset> is ISO-8859-1.

Examples

The following anonymous block uses the ESCAPE function to escape the blank spaces in the URL:

```
DECLARE
result varchar2(400);
BEGIN
result := UTL_URL.ESCAPE('http://www.example.com/Using the ESCAPE function.html');
DBMS_OUTPUT.PUT_LINE(result);
END;
```

The resulting (escaped) URL is:

```
http://www.example.com/Using%20the%20ESCAPE%20function.html
```

If you include a value of TRUE for the <escape_reserved_chars> parameter when invoking the function:

```
DECLARE
result varchar2(400);
BEGIN
result := UTL_URL.ESCAPE('http://www.example.com/Using the ESCAPE function.html',____
TRUE);
DBMS_OUTPUT.PUT_LINE(result);
END;
```

The ESCAPE function escapes the reserved characters as well as the illegal characters in the URL:

```
http%3A%2F%2Fwww.example.com%2FUsing%20the%20ESCAPE%20function.html
```

3.25. UTL URL 326

3.25.2 UNESCAPE

The UNESCAPE function removes escape characters added to an URL by the ESCAPE function, converting the URL to it's original form.

The signature is:

<url charset>

```
UNESCAPE(<url> VARCHAR2, <url_charset> VARCHAR2)
```

Parameters

```
\verb| <url>| <url>| <url| <url|
```

After unescaping a character, the character is assumed to be in <url_charset> encoding, and will be converted from that encoding to database encoding before being returned. If <url_charset> is NULL, the character will not be converted. The default value of <url_charset> is ISO-8859-1.

Examples

The following anonymous block uses the ESCAPE function to escape the blank spaces in the URL:

The resulting (unescaped) URL is:

```
http://www.example.com/Using the UNESCAPE function.htm
```

3.25. UTL_URL 327

CHAPTER 4

Acknowledgements

The PostgreSQL 8.3, 8.4, 9.0, 9.1, 9.2, 9.3, 9.4, 9.5, 9.6, 10, 11, and 12 Documentation provided the baseline for the portions of this guide that are common to PostgreSQL, and is hereby acknowledged:

Portions of this EnterpriseDB Software and Documentation may utilize the following copyrighted material, the use of which is hereby acknowledged.

PostgreSQL Documentation, Database Management System

PostgreSQL is Copyright © 1996-2020 by the PostgreSQL Global Development Group and is distributed under the terms of the license of the University of California below.

Postgres95 is Copyright © 1994-5 by the Regents of the University of California.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose, without fee, and without a written agreement is hereby granted, provided that the above copyright notice and this paragraph and the following two paragraphs appear in all copies.

IN NO EVENT SHALL THE UNIVERSITY OF CALIFORNIA BE LIABLE TO ANY PARTY FOR DIRECT, INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES, INCLUDING LOST PROFITS, ARISING OUT OF THE USE OF THIS SOFTWARE AND ITS DOCUMENTATION, EVEN IF THE UNIVERSITY OF CALIFORNIA HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

THE UNIVERSITY OF CALIFORNIA SPECIFICALLY DISCLAIMS ANY WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE SOFTWARE PROVIDED HEREUNDER IS ON AN "AS-IS" BASIS, AND THE UNIVERSITY OF CALIFORNIA HAS NO OBLIGATIONS TO PROVIDE MAINTENANCE, SUPPORT, UPDATES, ENHANCEMENTS, OR MODIFICATIONS.

CHAPTER 5

Conclusion

Database Compatibility for Oracle® Developers Built-in Packages Guide

Copyright © 2007 - 2020 EnterpriseDB Corporation. All rights reserved.

EnterpriseDB® Corporation 34 Crosby Drive, Suite 201, Bedford, MA 01730, USA

T +1 781 357 3390 F +1 978 467 1307 E info@enterprisedb.com www.enterprisedb.com

- EnterpriseDB and Postgres Enterprise Manager are registered trademarks of EnterpriseDB Corporation. EDB and EDB Postgres are trademarks of EnterpriseDB Corporation. Oracle is a registered trademark of Oracle, Inc. Other trademarks may be trademarks of their respective owners.
- EDB designs, establishes coding best practices, reviews, and verifies input validation for the logon UI for EDB Postgres Enterprise Manager where present. EDB follows the same approach for additional input components, however the nature of the product may require that it accepts freeform SQL, WMI or other strings to be entered and submitted by trusted users for which limited validation is possible. In such cases it is not possible to prevent users from entering incorrect or otherwise dangerous inputs.
- EDB reserves the right to add features to products that accept freeform SQL, WMI or other potentially dangerous inputs from authenticated, trusted users in the future, but will ensure all such features are designed and tested to ensure they provide the minimum possible risk, and where possible, require superuser or equivalent privileges.
- EDB does not warrant that we can or will anticipate all potential threats and therefore our process cannot fully guarantee that all potential vulnerabilities have been addressed or considered.

ALTER_POLICY, 171 ALTER_QUEUE, 45 ALTER_QUEUE TABLE, 46 ANALYZE_DATABASE, ANALYZE_SCHEMA ANALYZE PART_OBJECT, 242 APPEND, 78 B BASE64_DECODE, 261 BASE64_ENCODE, 262 BEGIN_REQUEST, 291 BIND VARIABLE RAW, 218 BIND_VARIABLE, 215 BIND_VARIABLE_CHAR, 217 BROKEN, 68 Built-In Packages, 21 C C CANONICALIZE, 244 CAST_TO_RAW, 311 CAST_TO_VARCHAR2, 312 CHANGE, 69 CHARARR, 100 CLOSE_CURSOR, 219 CLOSE_DATA, 318 COLUMN_VALUE_CHAR, 222 COLUMN_VALUE_RAW, 223 COMMA_TO_TABLE, 246 COMMAND, 318 COMMAND_REPLIES, 319 COMPARE, 79 CONCAT, 313 CONCETTON, 318 CONVERT, 314 CONVERTITOBLOB, 80	and	COPY, 82 CREATE_JOB, 196 CREATE_PIPE, 112 CREATE_PROGRAM, 198 CREATE_QUEUE, 47 CREATE_QUEUE_TABLE, 49 CREATE_SCHEDULE, 200 Creating Packages, 12 Creating the Package Body, 13 Creating the Package Specification, 12 D DATA, 319 DB_VERSION, 247 DBMS_ALERT, 22 DBMS_ALERT_Comprehensive_example, 27 DBMS_ALERT_Register, 22 DBMS_ALERT_Remove, 23 DBMS_AQ_Register, 39 DBMS_AQ_Register, 39 DBMS_AQ_Register, 39 DBMS_AQADM, 43 DBMS_CRYPTO, 56 DBMS_JOB_REmove, 72 DBMS_LOB_SUBSTR, 88 DBMS_LOB_SUBSTR, 88 DBMS_LOB_SUBSTR, 88 DBMS_LOCK, 92 DBMS_MVIEW, 93 DBMS_OUTPUT_DISABLE, 101 DBMS_OUTPUT_ENABLE, 102 DBMS_OUTPUT_PUT, 108 DBMS_OUTPUT_PUT, 108 DBMS_OUTPUT_PUT, 108 DBMS_OUTPUT_PUT_LINE, 109 DBMS_PIPE, 111 DBMS_PIPE_Comprehensive_example, 125 DBMS_PROFILER, 128 DBMS_PROFILER - Reference, 140 DBMS_RANDOM_VALUE_FIRST_FORM, 153
CONVERTTOCLOB, 81		DBMS_RANDOM_VALUE_FIRST_FORM, 153 DBMS_RANDOM_VALUE_SECOND_FORM, 154

DBMS_REDACT, 155	G
DBMS_REDACT_ADD_POLICY, 168	GET BODY CHARSET, 292
DBMS_REDACT_DROP_POLICY, 176	GET_CPU_TIME, 250
DBMS_REDACT_ENABLE_POLICY, 175	GET_DEPENDENCY, 251
DBMS_RLS, 180	GET_FOLLOW_REDIRECT, 293
DBMS_RLS_DROP_POLICY, 190	GET_HASH_VALUE, 252
DBMS_RLS_ENABLE_POLICY, 191	GET_HEADER, 293
DBMS_RLSADD_POLICY:, 183	GET_HEADER_BY_NAME, 295
DBMS_SCHEDULER, 192	GET_HEADER_COUNT, 295
DBMS_SCHEDULER_DISABLE, 203	GET_LINE, 103, 280
DBMS_SCHEDULER_ENABLE, 208	GET_LINES, 105, 280 GET_LINES, 105
DBMS_SESSION, 212	GET_MV_DEPENDENCIES, 94
DBMS_SQL, 213	
DBMS_UTILITY, 240	GET_PARAMETER_VALUE, 253
DECRYPT, 57	GET_RESPONSE, 296
DEFINE_COLUMN, 224	GET_RESPONSE_ERROR_CHECK, 296
DEFINE_COLUMN_CHAR, 226	GET_STORAGE_LIMIT, 84
DEFINE_COLUMN_RAW, 227	GET_TIME, 254
DEFINE_PROGRAM_ARGUMENT, 201	GET_TRANSFER_TIMEOUT, 296
DEQUEUE, 35	GET_VERSION, 129
DESCRIBE COLUMNS, 228	GETLENGTH, 85
DISABLE_POLICY, 174	Н
DROP JOB, 204	
DROP PROGRAM, 205	HASH, 61
DROP_PROGRAM_ARGUMENT, 206	HELO, 320
DROP_QUEUE, 51	HELP, 320
_ •	HTML_PIECES, 291
DROP_QUEUE_TABLE, 52	1
DROP_SCHEDULE, 207	I
Dropping a Package, 20	INITIALIZE, 151
E	INSTR, 86
	INTERNAL_VERSION_CHECK, 129
EHLO, 320	INTERVAL, 70
ENCRYPT, 59	Introduction, 1
END_REQUEST, 292	IS_OPEN, 234, 281
END_RESPONSE, 292	
ENQUEUE, 32	L
ERASE, 83	LAST ROW COUNT, 235
ESCAPE, 325	LENGTH, 315
EVALUATE_CALENDAR_STRING, 209	LNAME_ARRAY, 241
EXEC_DDL_STATEMENT, 248	
EXECUTE, 229	M
EXECUTE_AND_FETCH, 230	MAC, 62
_	MAIL, 321
F	MIMEHEADER_DECODE, 263
FCLOSE, 274	MIMEHEADER_ENCODE, 264
FCLOSE_ALL, 274	WIIWIETEADER_ENCODE, 204
FCOPY, 274	N
FETCH_ROWS, 232	
FFLUSH, 276	NAME_TOKENIZE, 255
FLUSH_DATA, 129	NEW_LINE, 107, 281
FOPEN, 277	NEXT_DATE, 71
FORMAT_CALL_STACK, 249	NEXT_ITEM_TYPE, 113
FREMOVE, 277	NOOP, 321
FRENAME, 278	NORMAL, 151
I INDI WANTE, 470	

0	S
OPEN_CONNECTION, 321	SEED, 152
OPEN_CURSOR, 237	SEND, 307
OPEN_DATA, 322	SEND_ATTACH_RAW, 308
D	SEND_ATTACH_VARCHAR2, 310
P	SEND_MESSAGE, 122
PACK_MESSAGE, 115	SERVEROUTPUT, 110
Package Body Syntax, 7	SET_BODY_CHARSET, 301
Package Components, 4	SET_FOLLOW_REDIRECT, 301
Package Specification Syntax, 4	SET_HEADER, 302
Packages, 3	SET_JOB_ARGUMENT_VALUE, 211
PARSE, 238	SET_RESPONSE_ERROR_CHECK, 302
PAUSE_PROFILER, 129	SET_ROLE, 212
PLSQL_PROFILER_DATA, 141	SET_TRANSFER_TIMEOUT, 302
PLSQL_PROFILER_RAWDATA, 141	Setting File Permissions with utl_file.umask, 273
PLSQL_PROFILER_RUNS, 140	SIGNAL, 23
PLSQL_PROFILER_UNITS, 140	SLEEP, 92
PURGE, 116	START_PROFILER, 130
PURGE_QUEUE_TABLE, 53	START_QUEUE, 54
PUTF, 285	STOP_PROFILER, 130
_	STOP_QUEUE, 55
Q	STRING, 153
QUIT, 322	SUBMIT, 74
QUOTED_PRINTABLE_DECODE, 265	T
QUOTED_PRINTABLE_ENCODE, 266	T
(0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 	TABLE_TO_COMMA, 258
R	TERMINATE, 153
RANDOM, 152	TEXT_DECODE, 267
RANDOMBYTES, 63	TEXT_ENCODE, 268
RANDOMINTEGER, 64	TRIM, 89
RANDOMNUMBER, 65	11
RCPT, 322	U
READ, 87	UNCL_ARRAY, 241
READ_LINE, 297	UNESCAPE, 327
READ RAW, 299	UNIQUE_SESSION_NAME, 123
READ_TEXT, 299	UNPACK_MESSAGE, 124
RECEIVE_MESSAGE, 118	UNREGISTER, 41
Referencing a Package, 15	UPDATE_FULL_REDACTION_VALUES, 177
REFRESH, 95	Using Calendar Syntax to Specify a Repeating Interval,
REFRESH_ALL_MVIEWS, 97	194
REFRESH_DEPENDENT, 98	Using DBMS_PROFILER, 131
REMOVE_PIPE, 119	Using DBMS_REDACT Constants and Function Param-
REMOVEALL, 23	eters, 156
REPLY/REPLIES, 318	Using Packages With User Defined Types, 16
REQ, 291	UTL_ENCODE, 260
REQUEST, 300	UTL_FILE, 272
REQUEST_PIECES, 301	UTL_FILE_PUT, 282
RESET_BUFFER, 121	UTL_FILE_PUT_LINE, 284
RESP, 291	UTL_HTTP, 287
RESUME_PROFILER, 130	UTL_MAIL, 306
RSET, 322	UTL_RAW, 311
RUN, 73	UTL_RAW_SUBSTR, 316
RUN_JOB, 210	UTL_SMTP, 317
	UTL_SMTP_Comprehensive_example, 323

UTL_URL, 325 UUDECODE, 269 UUENCODE, 270

VRFY, 323

W

WAITANY, 24 WAITONE, 25 WHAT, 75 What's New, 2

WRITE, 90

WRITE_DATA, 323

WRITE_LINE, 303 WRITE_RAW, 304

WRITE_TEXT, 305

WRITEAPPEND, 91