Contents

1 Database Compatibility for Oracle Developers Built-in Packages
Guide navTitle: Built-in Package Guide
2 Introduction
What's New
3.1 Packages
3.2 Package Components
Package Specification Syntax
Package Body Syntax
3.3 Creating Packages
Creating the Package Specification
Creating the Package Body
3.4 Referencing a Package
3.5 Using Packages With User Defined Types
3.6 Dropping a Package
4.1 Built-In Packages
4.2 DBMS_ALERT
REGISTER
REMOVE
REMOVEALL
SIGNAL
WAITANY
WAITONE
Comprehensive Example
4.3.1 DBMS_AQ
4.3.2 'ENQUEUE'
4.3.3 'DEQUEUE'
4.3.4 REGISTER
4.3.5 'UNREGISTER'
4.4.1 DBMS_AQADM
4.4.2 ALTER_QUEUE
4.4.3 ALTER_QUEUE_TABLE
4.4.4 CREATE_QUEUE
4.4.6 DROP_QUEUE
4.4.7 DROP_QUEUE_TABLE
4.4.8 PURGE_QUEUE_TABLE
4.4.9 START_QUEUE
4.4.10 STOP QUEUE
4.5.1 DBMS_CRYPTO
4.5.2 DECRYPT
4.5.3 ENCRYPT
4.5.4 HASH
4.5.5 MAC
4 5 6 PANDOMRVTES

4.5.7 RANDOMINTEGER	61
4.5.8 RANDOMNUMBER	61
4.6.1 DBMS_JOB	61
4.6.2 BROKEN	63
4.6.3 CHANGE	64
4.6.4 INTERVAL	65
4.6.5 NEXT_DATE	65
4.6.6 REMOVE	66
4.6.7 RUN	66
4.6.8 SUBMIT	67
4.6.9 WHAT	68
4.7.1 DBMS_LOB	68
4.7.2 APPEND	70
4.7.3 COMPARE	70
4.7.4 CONVERTTOBLOB	71
4.7.5 CONVERTTOCLOB	72
4.7.6 COPY	73
4.7.7 ERASE	74
4.7.8 GET_STORAGE_LIMIT	75
4.7.9 GETLENGTH	75 75
4.7.10 INSTR	76
4.7.11 READ	76
4.7.11 READ	77
4.7.13 TRIM	78
4.7.14 WRITE	78 70
4.7.15 WRITEAPPEND	79 70
4.8 DBMS_LOCK	79 70
SLEEP	79
4.9.1 DBMS_MVIEW	80
4.9.2 GET_MV_DEPENDENCIES	80
4.9.3 REFRESH	81
4.9.4 REFRESH_ALL_MVIEWS	83
4.9.5 REFRESH_DEPENDENT	84
4.10 DBMS_OUTPUT	86
CHARARR	87
DISABLE	87
ENABLE	87
GET_LINE	88
GET_LINES	90
NEW_LINE	92
PUT	92
PUT_LINE	93
SERVEROUTPUT	94
4.11.1 DBMS_PIPE	95
4.11.2 CREATE_PIPE	96
4.11.3 NEXT_ITEM_TYPE	97

4.11.4 PACK_MESSAGE
4.11.5 PURGE
4.11.6 RECEIVE_MESSAGE
4.11.7 REMOVE_PIPE
4.11.8 RESET_BUFFER
4.11.9 SEND_MESSAGE
4.11.10 UNIQUE_SESSION_NAME
4.11.11 UNPACK_MESSAGE
4.11.12 Comprehensive Example
4.12 DBMS_PROFILER
FLUSH_DATA
GET_VERSION
INTERNAL_VERSION_CHECK
PAUSE_PROFILER
RESUME_PROFILER
START_PROFILER
STOP_PROFILER
Using DBMS_PROFILER
Querying the DBMS_PROFILER Tables and View 114
DBMS_PROFILER - Reference
4.13 DBMS_RANDOM
INITIALIZE
NORMAL
RANDOM
SEED
SEED
STRING
TERMINATE
VALUE
VALUE
4.14 DBMS_REDACT
Using DBMS_REDACT Constants and Function Parameters 129
ADD_POLICY
ALTER POLICY
DISABLE_POLICY
ENABLE_POLICY
DROP_POLICY
UPDATE_FULL_REDACTION_VALUES
4.15 DBMS_RLS
ADD_POLICY
DROP_POLICY
ENABLE_POLICY
4.16.1 DBMS SCHEDULER
4.16.2 'Using Calendar Syntax to Specify a Repeating Interval' 157
4.16.3 CREATE_JOB
4.16.4 CDEATE DDOCDAM 160

4.16.5 CREATE_SCHEDULE	
4.16.6 DEFINE_PROGRAM_ARGUMENT	3
4.16.7 DISABLE	4
4.16.8 DROP_JOB	5
4.16.9 DROP_PROGRAM	6
4.16.10 DROP_PROGRAM_ARGUMENT	7
4.16.11 DROP SCHEDULE	8
4.16.12 ENABLE	8
4.16.13 EVALUATE_CALENDAR_STRING	9
4.16.14 RUN_JOB	
4.16.15 SET_JOB_ARGUMENT_VALUE	1
4.17 DBMS_SESSION	2
SET ROLE	2
4.18.1 DBMS SQL	3
4.18.2 BIND_VARIABLE	
4.18.3 BIND_VARIABLE_CHAR	
4.18.4 BIND VARIABLE RAW	
4.18.5 CLOSE CURSOR	
4.18.6 COLUMN VALUE	
4.18.7 COLUMN VALUE CHAR	
4.18.8 COLUMN VALUE RAW	
4.18.9 DEFINE COLUMN	
4.18.10 DEFINE_COLUMN_CHAR	
4.18.11 DEFINE COLUMN RAW	
4.18.12 DESCRIBE COLUMNS	
4.18.13 EXECUTE	
4.18.14 EXECUTE AND FETCH	
4.18.15 FETCH ROWS	
4.18.16 IS OPEN	
4.18.17 LAST ROW COUNT	
4.18.18 OPEN CURSOR	
4.18.19 PARSE	
4.19 DBMS UTILITY	
LNAME ARRAY	
UNCL ARRAY	
ANALYZE DATABASE, ANALYZE SCHEMA and ANALYZE	
PART OBJECT	3
CANONICALIZE	
COMMA TO TABLE	
DB VERSION	
EXEC DDL STATEMENT	
FORMAT CALL STACK	
GET CPU TIME	
GET DEPENDENCY	
GET HASH VALUE	
GET PARAMETER VALUE	

GET_TIME	203
NAME TOKENIZE	204
TABLE TO COMMA	
4.20.1 UTL ENCODE	
4.20.2 BASE64 DECODE	
4.20.3 BASE64 ENCODE	
4.20.4 MIMEHEADER DECODE	
4.20.5 MIMEHEADER ENCODE	
4.20.6 QUOTED_PRINTABLE_DECODE	
4.20.7 QUOTED PRINTABLE ENCODE	
4.20.8 TEXT DECODE	
4.20.9 TEXT_ENCODE	
4.20.10 UUDECODE	
4.20.11 UUENCODE	
4.21 UTL FILE	
Setting File Permissions with utl file.umask	
FCLOSE	
FCLOSE ALL	
FCOPY	
FFLUSH	
FOPEN	
FREMOVE	
FRENAME	
GET LINE	
IS OPEN	
NEW LINE	
PUT	
PUT LINE	
PUTF	
4.22 UTL HTTP	
HTML PIECES	
REQ	
RESP	
BEGIN REQUEST	
END REQUEST	
END RESPONSE	
GET BODY CHARSET	
GET FOLLOW REDIRECT	
GET HEADER	
GET HEADER BY NAME	
GET HEADER COUNT	
GET RESPONSE	
GET RESPONSE ERROR CHECK	
GET TRANSFER TIMEOUT	
READ LINE	
READ RAW	

READ_TEXT	248
REQUEST	249
REQUEST PIECES	249
SET BODY CHARSET	
SET FOLLOW REDIRECT	
SET HEADER	
SET RESPONSE ERROR CHECK	
SET_TRANSFER_TIMEOUT	
WRITE LINE	
WRITE RAW	
WRITE TEXT	
4.23 UTL MAIL	
SEND	
SEND ATTACH RAW	
SEND_ATTACH_VARCHAR2	
4.24 UTL_RAW	
CAST_TO_RAW	
CAST_TO_VARCHAR2	
CONCAT	
CONVERT	
LENGTH	
SUBSTR	
4.25 UTL_SMTP	
CONNECTION	
REPLY/REPLIES	
CLOSE_DATA	
COMMAND	
COMMAND_REPLIES	266
DATA	266
EHLO	267
HELO	267
HELP	267
MAIL	268
NOOP	268
OPEN_CONNECTION	269
OPEN_DATA	269
QUIT	269
RCPT	270
RSET	270
VRFY	270
WRITE DATA	271
_	271
	272
	273
	275
	276

6	Conclusion																	27	76

1 Database Compatibility for Oracle Developers Built-in Packages Guide navTitle: Built-in Package Guide

introduction packages built-in_packages acknowledgements conclusion

2 Introduction

Database Compatibility for Oracle means that an application runs in an Oracle environment as well as in the EDB Postgres Advanced Server (Advanced Server) environment with minimal or no changes to the application code. This guide focuses solely on the features that are related to the package support provided by Advanced Server.

For more information about using other compatibility features offered by Advanced Server, please see the complete set of Advanced Server guides, available at:

https://www.enterprisedb.com/edb-docs/

What's New

The following database compatibility for Oracle features have been added to Advanced Server 11 to create Advanced Server 12:

- Advanced Server introduces COMPOUND TRIGGERS, which are stored as a PL block that executes in response to a specified triggering event. For information, see the *Database Compatibility for Oracle Developer's Guide*.
- Advanced Server now supports new DATA DICTIONARY VIEWS that provide information compatible with the Oracle data dictionary views. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has added the LISTAGG function to support string aggregation that concatenates data from multiple rows into a single row in an ordered manner. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server now supports CAST(MULTISET) function, allowing subquery output to be CAST to a nested table type. For information, see the Database Compatibility for Oracle Developer's Reference Guide.
- Advanced Server has added the MEDIAN function to calculate a median value from the set of provided values. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.

- Advanced Server has added the SYS_GUID function to generate and return a globally unique identifier in the form of 16-bytes of RAW data. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server now supports an Oracle-compatible SELECT UNIQUE clause in addition to an existing SELECT DISTINCT clause. For information, see the *Database Compatibility for Oracle Developer's Reference Guide*.
- Advanced Server has re-implemented default_with_rowids to create a
 table that includes a ROWID column in the newly created table. For information, see the EDB Postgres Advanced Server Guide.
- Advanced Server now supports logical decoding on the standby server, which allows creating a logical replication slot on a standby, independently of a primary server. For information, see the *EDB Postgres Advanced Server Guide*.
- Advanced Server introduces INTERVAL PARTITIONING, which allows a
 database to automatically create partitions of a specified interval as
 new data is inserted into a table. For information, see the *Database*Compatibility for Oracle Developer's Guide.

Note

Database Compatibility for Oracle Developer's Guide, Database Compatibility for Oracle Developer's Reference Guide, and EDB Postgres Advanced Server Guides are available at:

nttps:/	/www.ent	terprised	0.com/	edb-d	locs/	

3.1 Packages

This chapter discusses the concept of packages in Advanced Server. A *package* is a named collection of functions, procedures, variables, cursors, user-defined record types, and records that are referenced using a common qualifier – the package identifier. Packages have the following characteristics:

- Packages provide a convenient means of organizing the functions and procedures that perform a related purpose. Permission to use the package functions and procedures is dependent upon one privilege granted to the entire package. All of the package programs must be referenced with a common name.
- Certain functions, procedures, variables, types, etc. in the package can be declared as *public*. Public entities are visible and can be referenced by other programs that are given EXECUTE privilege on the package. For public functions and procedures, only their signatures are visible the program names, parameters if any, and return types of functions. The SPL code of these functions and procedures is not accessible to others,

- therefore applications that utilize a package are dependent only upon the information available in the signature not in the procedural logic itself.
- Other functions, procedures, variables, types, etc. in the package can be declared as *private*. Private entities can be referenced and used by function and procedures within the package, but not by other external applications. Private entities are for use only by programs within the package.
- Function and procedure names can be overloaded within a package. One or more functions/procedures can be defined with the same name, but with different signatures. This provides the capability to create identically named programs that perform the same job, but on different types of input.

 $package_components\ creating_packages\ referencing_a_package\ using_packages_with_user_defined_types\ dropping_a_package$

3.2 Package Components

Packages consist of two main components:

- The package specification: This is the public interface, (these are the elements which can be referenced outside the package). We declare all database objects that are to be a part of our package within the specification.
- The *package body*: This contains the actual implementation of all the database objects declared within the package specification.

The package body implements the specifications in the package specification. It contains implementation details and private declarations which are invisible to the application. You can debug, enhance or replace a package body without changing the specifications. Similarly, you can change the body without recompiling the calling programs because the implementation details are invisible to the application.

Package Specification Syntax

The package specification defines the user interface for a package (the API). The specification lists the functions, procedures, types, exceptions and cursors that are visible to a user of the package.

The syntax used to define the interface for a package is:

```
CREATE [ OR REPLACE ] PACKAGE <package_name>
[ <authorization_clause> ]
{ IS | AS }
[ <declaration>; ] ...
[ <procedure_or_function_declaration> ] ...
END [ <package_name> ] ;
```

```
Where <authorization_clause> :=
     { AUTHID DEFINER } | { AUTHID CURRENT_USER }
Where cedure_or_function_declaration> :=
     cprocedure_declaration> | <function_declaration>
Where cdure_declaration> :=
     PROCEDURE  proc_name > [ <argument_list > ]; [ <restriction_pragma >;
     1
Where <function_declaration> :=
     FUNCTION <func_name> [ <argument_list> ]
    RETURN <rettype> [ DETERMINISTIC ]; [ <restriction_pragma>;
Where <argument_list> :=
     ( <argument_declaration> [, ...] )
Where <argument_declaration> :=
     <argname> [ IN | IN OUT | OUT ] <argtype> [ DEFAULT
     <value> ]
Where <restriction_pragma> :=
     PRAGMA RESTRICT_REFERENCES ( <name>, <restrictions>)
Where <restrictions> :=
     <restriction>[, ...]
Parameters
<package name>
     <package_name> is an identifier assigned to the package - each pack-
     age must have a name unique within the schema.
AUTHID DEFINER
     If you omit the AUTHID clause or specify AUTHID DEFINER, the priv-
     ileges of the package owner are used to determine access privileges
     to database objects.
AUTHID CURRENT_USER
     If you specify AUTHID CURRENT_USER, the privileges of the current
     user executing a program in the package are used to determine access
     privileges.
```

<declaration>

<declaration> is an identifier of a public variable. A public variable can be accessed from outside of the package using the syntax
<package_name.variable>. There can be zero, one, or more public variables. Public variable definitions must come before procedure or function declarations.

<declaration> can be any of the following:

- Variable Declaration
- Record Declaration
- Collection Declaration
- REF CURSOR and Cursor Variable Declaration
- TYPE Definitions for Records, Collections, and REF CURSORs
- Exception
- Object Variable Declaration

c_name>

The name of a public procedure.

<argname>

The name of an argument. The argument is referenced by this name within the function or procedure body.

IN | IN OUT | OUT

The argument mode. IN declares the argument for input only. This is the default. IN OUT allows the argument to receive a value as well as return a value. OUT specifies the argument is for output only.

<argtype>

The data type(s) of an argument. An argument type may be a base data type, a copy of the type of an existing column using %TYPE, or a user-defined type such as a nested table or an object type. A length must not be specified for any base type - for example, specify VARCHAR2, not VARCHAR2(10).

The type of a column is referenced by writing <tablename.columnname> %TYPE; using this can sometimes help make a procedure independent from changes to the definition of a table.

DEFAULT <value>

The DEFAULT clause supplies a default value for an input argument if one is not supplied in the invocation. DEFAULT may not be specified for arguments with modes IN OUT or OUT.

<func_name>

The name of a public function.

<rettype>

The return data type.

DETERMINISTIC

DETERMINISTIC is a synonym for IMMUTABLE. A DETERMINISTIC function cannot modify the database and always reaches the same result when given the same argument values; it does not do database lookups or otherwise use information not directly present in its argument list. If you include this clause, any call of the function with all-constant arguments can be immediately replaced with the function value.

<restriction>

The following keywords are accepted for compatibility and ignored:

RNDS

RNPS

TRUST

WNDS

WNPS

Package Body Syntax

Package implementation details reside in the package body; the package body may contain objects that are not visible to the package user. Advanced Server supports the following syntax for the package body:

```
[ PRAGMA AUTONOMOUS_TRANSACTION; ]
     [ <declaration>; ] [, ...]
     BEGIN
         <statement>; [...]
         [ EXCEPTION
             {WHEN <exception> [OR <exception>]
             [...]] THEN <statement>; }
         [...]
Where <function_definition> :=
     FUNCTION <func_name> [ <argument_list> ]
         RETURN <rettype> [ DETERMINISTIC ]
         [ <options_list> ]
         { IS | AS }
         <function_body>
         END [ <func_name> ];
Where <function_body> :=
     [ PRAGMA AUTONOMOUS_TRANSACTION; ]
     [ <declaration>; ] [, ...]
    BEGIN
         <statement>; [...]
     [ EXCEPTION
         { WHEN <exception> [ OR <exception> ] [...] THEN
         <statement>; }
         [...]
Where <argument_list> :=
     ( <argument_declaration> [, ...] )
Where \argument_declaration > :=
     <argname> [ IN | IN OUT | OUT ] <argtype> [ DEFAULT <value>
Where options_list> :=
```

Parameters

<package_name>

<package_name> is the name of the package for which this is the
package body. There must be an existing package specification with
this name.

<private_declaration>

<private_declaration> is an identifier of a private variable
that can be accessed by any procedure or function within the
package. There can be zero, one, or more private variables.
<private_declaration> can be any of the following:

- Variable Declaration
- Record Declaration
- Collection Declaration
- REF CURSOR and Cursor Variable Declaration
- TYPE Definitions for Records, Collections, and REF CURSORs
- Exception
- Object Variable Declaration

c_name>

The name of the procedure being created.

PRAGMA AUTONOMOUS_TRANSACTION

PRAGMA AUTONOMOUS_TRANSACTION is the directive that sets the procedure as an autonomous transaction.

<declaration>

A variable, type, REF CURSOR, or subprogram declaration. If subprogram declarations are included, they must be declared after all other variable, type, and REF CURSOR declarations.

<statement>

An SPL program statement. Note that a DECLARE - BEGIN - END block is considered an SPL statement unto itself. Thus, the function body may contain nested blocks.

<exception>

An exception condition name such as NO_DATA_FOUND, OTHERS, etc.

<func name>

The name of the function being created.

<rettype>

The return data type, which may be any of the types listed for <argtype>. As for <argtype>, a length must not be specified for <rettype>.

DETERMINISTIC

Include DETERMINISTIC to specify that the function will always return the same result when given the same argument values. A DETERMINISTIC function must not modify the database.

Note

The DETERMINISTIC keyword is equivalent to the PostgreSQL IMMUTABLE option.

Note

If DETERMINISTIC is specified for a public function in the package body, it must also be specified for the function declaration in the package specification. (For private functions, there is no function declaration in the package specification.)

PRAGMA AUTONOMOUS_TRANSACTION

PRAGMA AUTONOMOUS_TRANSACTION is the directive that sets the function as an autonomous transaction.

<declaration>

A variable, type, REF CURSOR, or subprogram declaration. If subprogram declarations are included, they must be declared after all other variable, type, and REF CURSOR declarations.

<argname>

The name of a formal argument. The argument is referenced by this name within the procedure body.

IN | IN OUT | OUT

The argument mode. IN declares the argument for input only. This is the default. IN OUT allows the argument to receive a value as well as return a value. OUT specifies the argument is for output only.

<argtype>

The data type(s) of an argument. An argument type may be a base data type, a copy of the type of an existing column using %TYPE, or a user-defined type such as a nested table or an object type. A length must not be specified for any base type - for example, specify VARCHAR2, not VARCHAR2(10).

The type of a column is referenced by writing <tablename>. <columnname>`%TYPE; using this can sometimes help make a procedure independent from changes to the definition of a table.

DEFAULT <value>

The DEFAULT clause supplies a default value for an input argument if one is not supplied in the procedure call. DEFAULT may not be specified for arguments with modes IN OUT or OUT.

Please note: the following options are not compatible with Oracle databases; they are extensions to Oracle package syntax provided by Advanced Server only.

STRICT

The STRICT keyword specifies that the function will not be executed if called with a NULL argument; instead the function will return NULL.

LEAKPROOF

The LEAKPROOF keyword specifies that the function will not reveal any information about arguments, other than through a return value.

PARALLEL { UNSAFE | RESTRICTED | SAFE }

The PARALLEL clause enables the use of parallel sequential scans (parallel mode). A parallel sequential scan uses multiple workers to scan a relation in parallel during a query in contrast to a serial sequential scan.

When set to UNSAFE, the procedure or function cannot be executed in parallel mode. The presence of such a procedure or function forces a serial execution plan. This is the default setting if the PARALLEL clause is omitted.

When set to RESTRICTED, the procedure or function can be executed in parallel mode, but the execution is restricted to the parallel group leader. If the qualification for any particular relation has anything that is parallel restricted, that relation won't be chosen for parallelism.

When set to SAFE, the procedure or function can be executed in parallel mode with no restriction.

<execution_cost>

<execution_cost> specifies a positive number giving the estimated
execution cost for the function, in units of cpu_operator_cost. If
the function returns a set, this is the cost per returned row. The
default is 0.0025.

`<result_rows>

<result_rows> is the estimated number of rows that the query planner should expect the function to return. The default is 1000.

SET

Use the SET clause to specify a parameter value for the duration of the function:

<config_param> specifies the parameter name.

<value> specifies the parameter value.

FROM CURRENT guarantees that the parameter value is restored when the function ends.

<package_initializer>

The statements in the <package_initializer> are executed once per user's session when the package is first referenced.

Note

The STRICT, LEAKPROOF, PARALLEL, COST, ROWS and SET keywords provide extended functionality for Advanced Server and are not supported by Oracle.

3.3 Creating Packages

A package is not an executable piece of code; rather it is a repository of code. When you use a package, you actually execute or make reference to an element within a package.

Creating the Package Specification

The package specification contains the definition of all the elements in the package that can be referenced from outside of the package. These are called the public elements of the package, and they act as the package interface. The following code sample is a package specification:

```
-- Package specification for the 'emp admin' package.
CREATE OR REPLACE PACKAGE emp admin
IS
   FUNCTION get_dept_name (
     p_deptno NUMBER DEFAULT 10
)
   RETURN VARCHAR2;
   FUNCTION update_emp_sal (
     p_empno NUMBER,
     p_raise NUMBER
)
   RETURN NUMBER;
   PROCEDURE hire emp (
     p_empno
                        NUMBER,
                        VARCHAR2,
     p_ename
     p_job
                        VARCHAR2,
     p sal
                        NUMBER,
     p_hiredate
                        DATE
                                  DEFAULT
                                             sysdate,
     p_comm
                        NUMBER
                                  DEFAULT
                                             0,
                        NUMBER,
     p_mgr
     p_deptno
                        NUMBER
                                  DEFAULT
                                             10
    );
   PROCEDURE fire_emp (
     p_empno NUMBER
);
END emp_admin;
```

This code sample creates the emp_admin package specification. This package specification consists of two functions and two stored procedures. We can also add the OR REPLACE clause to the CREATE PACKAGE statement for convenience.

Creating the Package Body

The body of the package contains the actual implementation behind the package specification. For the above emp_admin package specification, we shall now create a package body which will implement the specifications. The body will contain the implementation of the functions and stored procedures in the specification.

```
-- Package body for the 'emp_admin' package.
CREATE OR REPLACE PACKAGE BODY emp_admin
IS
    -- Function that queries the 'dept' table based on the department
    -- number and returns the corresponding department name.
    FUNCTION get_dept_name (
       p_deptno IN NUMBER DEFAULT 10
   RETURN VARCHAR2
       v_dname VARCHAR2(14);
   BEGIN
        SELECT dname INTO v_dname FROM dept WHERE deptno = p_deptno;
        RETURN v_dname;
    EXCEPTION
        WHEN NO_DATA_FOUND THEN
            DBMS_OUTPUT.PUT_LINE('Invalid department number ' || p_deptno);
            RETURN '';
   END;
    -- Function that updates an employee's salary based on the
    -- employee number and salary increment/decrement passed
    -- as IN parameters. Upon successful completion the function
    -- returns the new updated salary.
   FUNCTION update_emp_sal (
       p_empno
                    IN NUMBER,
                     IN NUMBER
       p_raise
    )
   RETURN NUMBER
                       NUMBER := 0;
       v_sal
    BEGIN
        SELECT sal INTO v_sal FROM emp WHERE empno = p_empno;
        v_sal := v_sal + p_raise;
        UPDATE emp SET sal = v_sal WHERE empno = p_empno;
       RETURN v_sal;
   EXCEPTION
      WHEN NO DATA FOUND THEN
         DBMS_OUTPUT.PUT_LINE('Employee ' || p_empno || ' not found');
          RETURN -1;
      WHEN OTHERS THEN
```

```
DBMS_OUTPUT.PUT_LINE('The following is SQLERRM:');
        DBMS_OUTPUT.PUT_LINE(SQLERRM);
        DBMS_OUTPUT.PUT_LINE('The following is SQLCODE:');
        DBMS_OUTPUT.PUT_LINE(SQLCODE);
        RETURN -1;
 END;
  -- Procedure that inserts a new employee record into the 'emp' table.
    PROCEDURE hire_emp (
    p_empno
                       NUMBER,
    p_ename
                        VARCHAR2,
    p_job
                       VARCHAR2,
                      NUMBER,
    p sal
                   DATE DEFAULT sysdate, NUMBER DEFAULT 0,
    p_hiredate
    p_comm
                       NUMBER,
    p_mgr
    p_deptno
                      NUMBER DEFAULT 10
  )
  AS
  BEGIN
     INSERT INTO emp(empno, ename, job, sal, hiredate, comm, mgr, deptno)
        VALUES(p_empno, p_ename, p_job, p_sal,
               p_hiredate, p_comm, p_mgr, p_deptno);
  END;
  -- Procedure that deletes an employee record from the 'emp' table based
  -- on the employee number.
 PROCEDURE fire_emp (
      p empno NUMBER
  )
  AS
      DELETE FROM emp WHERE empno = p_empno;
  END;
END;
```

3.4 Referencing a Package

To reference the types, items and subprograms that are declared within a package specification, we use the dot notation. For example:

```
<package_name>.<type_name>
```

```
<package_name>.<item_name>
<package_name.<subprogram_name</pre>
```

To invoke a function from the emp_admin package specification, we will execute the following SQL command.

```
SELECT emp_admin.get_dept_name(10) FROM DUAL;
```

Here we are invoking the get_dept_name function declared within the package emp_admin. We are passing the department number as an argument to the function, which will return the name of the department. Here the value returned should be ACCOUNTING, which corresponds to department number 10.

3.5 Using Packages With User Defined Types

The following example incorporates the various user-defined types discussed in earlier chapters within the context of a package.

The package specification of emp_rpt shows the declaration of a record type, emprec_typ, and a weakly-typed REF CURSOR, emp_refcur, as publicly accessible along with two functions and two procedures. Function, open_emp_by_dept, returns the REF CURSOR type, EMP_REFCUR. Procedures, fetch_emp and close_refcur, both declare a weakly-typed REF CURSOR as a formal parameter.

```
CREATE OR REPLACE PACKAGE emp_rpt
IS
   TYPE emprec_typ IS RECORD (
                NUMBER(4),
       empno
       ename
                   VARCHAR(10)
   TYPE emp_refcur IS REF CURSOR;
   FUNCTION get_dept_name (
       p_deptno
                   IN NUMBER
   ) RETURN VARCHAR2;
   FUNCTION open_emp_by_dept (
                   IN emp.deptno%TYPE
       p_deptno
   ) RETURN EMP_REFCUR;
   PROCEDURE fetch_emp (
       p_refcur
                   IN OUT SYS_REFCURSOR
   );
   PROCEDURE close_refcur (
                   IN OUT SYS_REFCURSOR
       p_refcur
   );
   END emp_rpt;
```

The package body shows the declaration of several private variables - a static cursor, dept_cur, a table type, depttab_typ, a table variable, t_dept, an integer variable, t_dept_max, and a record variable, r_emp.

```
CREATE OR REPLACE PACKAGE BODY emp_rpt
IS
    CURSOR dept_cur IS SELECT * FROM dept;
   TYPE depttab_typ IS TABLE of dept%ROWTYPE
       INDEX BY BINARY INTEGER;
   t_dept
                  DEPTTAB_TYP;
    t_dept_max
                  INTEGER := 1;
                   EMPREC_TYP;
   r_emp
   FUNCTION get_dept_name (
       p_deptno IN NUMBER
    ) RETURN VARCHAR2
    IS
    BEGIN
        FOR i IN 1..t_dept_max LOOP
            IF p_deptno = t_dept(i).deptno THEN
               RETURN t_dept(i).dname;
           END IF;
       END LOOP;
        RETURN 'Unknown';
 END;
 FUNCTION open_emp_by_dept(
   p_deptno
                   IN emp.deptno%TYPE
 ) RETURN EMP REFCUR
    emp_by_dept EMP_REFCUR;
 BEGIN
    OPEN emp_by_dept FOR SELECT empno, ename FROM emp
       WHERE deptno = p_deptno;
    RETURN emp_by_dept;
 END;
 PROCEDURE fetch_emp (
               IN OUT SYS_REFCURSOR
     p_refcur
  )
 IS
 BEGIN
      DBMS_OUTPUT.PUT_LINE('EMPNO ENAME');
     DBMS_OUTPUT.PUT_LINE('----');
     LOOP
         FETCH p_refcur INTO r_emp;
         EXIT WHEN p_refcur%NOTFOUND;
```

```
END LOOP;
  END;
  PROCEDURE close_refcur (
                    IN OUT SYS_REFCURSOR
      p_refcur
  IS
 BEGIN
      CLOSE p_refcur;
 END:
BEGIN
  OPEN dept_cur;
 LOOP
      FETCH dept_cur INTO t_dept(t_dept_max);
      EXIT WHEN dept cur%NOTFOUND;
      t_dept_max := t_dept_max + 1;
 END LOOP;
 CLOSE dept_cur;
  t_dept_max := t_dept_max - 1;
END emp_rpt;
```

DBMS_OUTPUT.PUT_LINE(r_emp.empno || ' ' || r_emp.ename);

This package contains an initialization section that loads the private table variable, t_dept, using the private static cursor, dept_cur.t_dept serves as a department name lookup table in function, get_dept_name.

Function, open_emp_by_dept returns a REF CURSOR variable for a result set of employee numbers and names for a given department. This REF CURSOR variable can then be passed to procedure, fetch_emp, to retrieve and list the individual rows of the result set. Finally, procedure, close_refcur, can be used to close the REF CURSOR variable associated with this result set.

The following anonymous block runs the package function and procedures. In the anonymous block's declaration section, note the declaration of cursor variable, <code>v_emp_cur</code>, using the package's public REF CURSOR type, EMP_REFCUR. <code>v_emp_cur</code> contains the pointer to the result set that is passed between the package function and procedures.

DECLARE

The following anonymous block illustrates another means of achieving the same result. Instead of using the package procedures, fetch_emp and close_refcur, the logic of these programs is coded directly into the anonymous block. In the anonymous block's declaration section, note the addition of record variable, r_emp, declared using the package's public record type, EMPREC_TYP.

```
DECLARE
```

EMPNO ENAME

```
dept.deptno%TYPE DEFAULT 30;
   v_deptno
               emp_rpt.EMP_REFCUR;
   v_emp_cur
   r_emp
               emp_rpt.EMPREC_TYP;
BEGIN
  v_emp_cur := emp_rpt.open_emp_by_dept(v_deptno);
  DBMS_OUTPUT.PUT_LINE('EMPLOYEES IN DEPT #' || v_deptno ||
      ': ' || emp_rpt.get_dept_name(v_deptno));
  DBMS_OUTPUT.PUT_LINE('EMPNO ENAME');
  DBMS_OUTPUT.PUT_LINE('----');
  LOOP
      FETCH v_emp_cur INTO r_emp;
      EXIT WHEN v_emp_cur%NOTFOUND;
      DBMS_OUTPUT.PUT_LINE(r_emp.empno || ' ' ||
      r_emp.ename);
  END LOOP;
  DBMS_OUTPUT.PUT_LINE(v_emp_cur%ROWCOUNT || ' rows were retrieved');
  CLOSE v_emp_cur;
END;
The following is the result of this anonymous block.
EMPLOYEES IN DEPT #30: SALES
```

7499 ALLEN

7521 WARD

7654 MARTIN

7698 BLAKE

7844 TURNER

7900 JAMES

6 rows were retrieved

3.6 Dropping a Package

The syntax for deleting an entire package or just the package body is as follows:

If the keyword, BODY, is omitted, both the package specification and the package body are deleted - i.e., the entire package is dropped. If the keyword, BODY, is specified, then only the package body is dropped. The package specification remains intact. cpackage_name> is the identifier of the package to be dropped.

Following statement will destroy only the package body of <emp_admin>:

DROP PACKAGE BODY emp_admin;

The following statement will drop the entire <emp_admin> package:

DROP PACKAGE emp_admin;

4.1 Built-In Packages

This chapter describes the built-in packages that are provided with Advanced Server. For certain packages, non-superusers must be explicitly granted the EXECUTE privilege on the package before using any of the package's functions or procedures. For most of the built-in packages, EXECUTE privilege has been granted to PUBLIC by default.

For information about using the GRANT command to provide access to a package, please see the *Database Compatibility for Oracle Developers Reference Guide*, available at:

https://www.enterprisedb.com/edb-docs

All built-in packages are owned by the special sys user which must be specified when granting or revoking privileges on built-in packages:

GRANT EXECUTE ON PACKAGE SYS.UTL_FILE TO john;

dbms_alert dbms_aq dbms_aqadm dbms_crypto dbms_job dbms_lob dbms_lock dbms_mview dbms_output dbms_pipe dbms_profiler dbms_random dbms_redact dbms_rls dbms_scheduler dbms_session dbms_sql dbms_utility utl_encode utl_file utl_http utl_mail_utl_raw_utl_smtp_utl_url

4.2 DBMS ALERT

The DBMS_ALERT package provides the capability to register for, send, and receive alerts. The following table lists the supported procedures:

Function/Procedure	Return Type	Description
REGISTER(<name>)</name>	n/a	Register to be able t
REMOVE(<name>)</name>	n/a	Remove registration
REMOVEALL	n/a	Remove registration
SIGNAL(<name>, <message>)</message></name>	n/a	Signals the alert nan
WAITANY(<name> OUT, <message> OUT, <status> OUT, <timeout>)</timeout></status></message></name>	n/a	Wait for any register
WAITONE(<name>, <message. <status="" out,=""> OUT, <timeout>)</timeout></message.></name>	n/a	Wait for the specified

Advanced Server's implementation of DBMS_ALERT is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Advanced Server allows a maximum of 500 concurrent alerts. You can use the dbms_alert.max_alerts GUC variable (located in the postgresql.conf file) to specify the maximum number of concurrent alerts allowed on a system.

To set a value for the dbms_alert.max_alerts variable, open the postgresql.conf file (located by default in /opt/PostgresPlus/10AS/data) with your choice of editor, and edit the dbms_alert.max_alerts parameter as shown:

```
dbms alert.max alerts = <alert count>
```

<alert_count>

alert_count specifies the maximum number of concurrent alerts. By default,
the value of dbms_alert.max_alerts is 100. To disable this feature, set
dbms_alert.max_alerts to 0.

For the dbms_alert.max_alerts GUC to function correctly, the custom_variable_classes parameter must contain dbms_alerts:

```
custom_variable_classes = 'dbms_alert, ...'
```

After editing the postgresql.conf file parameters, you must restart the server for the changes to take effect.

 $DBMS_ALERT_Register$

REGISTER

The REGISTER procedure enables the current session to be notified of the specified alert.

```
REGISTER(<name> VARCHAR2)
```

Parameters

<name>

Name of the alert to be registered.

Examples

The following anonymous block registers for an alert named, alert_test, then waits for the signal.

```
DECLARE
```

```
v_name
                   VARCHAR2(30) := 'alert_test';
                   VARCHAR2(80);
   v_msg
                   INTEGER;
   v_status
                   NUMBER(3) := 120;
   v_timeout
BEGIN
   DBMS_ALERT.REGISTER(v_name);
   DBMS_OUTPUT.PUT_LINE('Registered for alert ' || v_name);
   DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
   DBMS_ALERT.WAITONE(v_name,v_msg,v_status,v_timeout);
   DBMS OUTPUT.PUT LINE('Alert name : ' || v name);
   DBMS_OUTPUT.PUT_LINE('Alert msg : ' || v_msg);
   DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
   DBMS_OUTPUT.PUT_LINE('Alert timeout: ' || v_timeout || ' seconds');
   DBMS_ALERT.REMOVE(v_name);
END;
Registered for alert alert_test
Waiting for signal...
DBMS ALERT Remove
```

REMOVE

The REMOVE procedure unregisters the session for the named alert.

```
REMOVE(<name> VARCHAR2)
```

Parameters

<name>

Name of the alert to be unregistered.

REMOVEALL

The REMOVEALL procedure unregisters the session for all alerts.

REMOVEALL

SIGNAL

The SIGNAL procedure signals the occurrence of the named alert.

SIGNAL(<name> VARCHAR2, <message> VARCHAR2)

Parameters

<name>

Name of the alert.

<message>

Information to pass with this alert.

Examples

The following anonymous block signals an alert for alert_test.

```
DECLARE
```

```
v_name VARCHAR2(30) := 'alert_test';
BEGIN
    DBMS_ALERT.SIGNAL(v_name,'This is the message from ' || v_name);
    DBMS_OUTPUT.PUT_LINE('Issued alert for ' || v_name);
END;
Issued alert for alert_test
```

WAITANY

The WAITANY procedure waits for any of the registered alerts to occur.

```
{\tt WAITANY(< name>\ OUT\ VARCHAR2,\ < message>\ OUT\ VARCHAR2,}
```

```
<status> OUT INTEGER, <timeout> NUMBER)
```

Parameters

<name>

Variable receiving the name of the alert.

<message>

Variable receiving the message sent by the SIGNAL procedure.

<status>

Status code returned by the operation. Possible values are: 0 – alert occurred; 1 – timeout occurred.

<timeout>

Time to wait for an alert in seconds.

Examples

The following anonymous block uses the WAITANY procedure to receive an alert named, alert_test or any_alert:

```
DECLARE
                     VARCHAR2(30);
   v name
                    VARCHAR2(80);
   v_msg
   v_status
                    INTEGER:
                     NUMBER(3) := 120;
   v_timeout
BEGIN
   DBMS ALERT.REGISTER('alert test');
   DBMS_ALERT.REGISTER('any_alert');
   DBMS OUTPUT.PUT LINE('Registered for alert alert test and any alert');
   DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
   DBMS_ALERT.WAITANY(v_name,v_msg,v_status,v_timeout);
   DBMS_OUTPUT.PUT_LINE('Alert name : ' || v_name);
                                     : ' || v_msg);
   DBMS_OUTPUT.PUT_LINE('Alert msg
   DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
   DBMS_OUTPUT.PUT_LINE('Alert timeout: ' || v_timeout || ' seconds');
   DBMS_ALERT.REMOVEALL;
END;
Registered for alert alert_test and any_alert
Waiting for signal...
An anonymous block in a second session issues a signal for any_alert:
DECLARE
   v_name
           VARCHAR2(30) := 'any_alert';
BEGIN
   DBMS ALERT.SIGNAL(v name, 'This is the message from ' | | v name);
   DBMS_OUTPUT.PUT_LINE('Issued alert for ' || v_name);
Issued alert for any_alert
Control returns to the first anonymous block and the remainder of the code is
executed:
Registered for alert alert_test and any_alert
Waiting for signal...
Alert name : any alert
Alert msg : This is the message from any_alert
Alert status: 0
Alert timeout: 120 seconds
```

WAITONE

The WAITONE procedure waits for the specified registered alert to occur.

```
WAITONE(<name> VARCHAR2, <message> OUT VARCHAR2,
```

```
<status> OUT INTEGER, <timeout> NUMBER)
```

Parameters

<name>

Name of the alert.

<message>

Variable receiving the message sent by the SIGNAL procedure.

<status>

Status code returned by the operation. Possible values are: 0 – alert occurred; 1 – timeout occurred.

<timeout>

Time to wait for an alert in seconds.

Examples

The following anonymous block is similar to the one used in the WAITANY example except the WAITONE procedure is used to receive the alert named, alert_test.

DECLARE

```
v name
                     VARCHAR2(30) := 'alert_test';
   v_{msg}
                     VARCHAR2(80);
   v_status
                     INTEGER;
                     NUMBER(3) := 120;
    v_timeout
BEGIN
   DBMS_ALERT.REGISTER(v_name);
   DBMS_OUTPUT.PUT_ DBMS_ALERT.REGISTER(v_name);
   DBMS_OUTPUT.PUT_LINE('Registered for alert ' || v_name);
   DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
   DBMS_ALERT.WAITONE(v_name,v_msg,v_status,v_timeout);
   DBMS_OUTPUT.PUT_LINE('Alert name : ' || v_name);
                                      : ' || v_msg);
   DBMS_OUTPUT.PUT_LINE('Alert msg
   DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
   DBMS_OUTPUT.PUT_LINE('Alert timeout: ' || v_timeout || ' seconds');
   DBMS_ALERT.REMOVE(v_name);LINE('Registered for alert ' || v_name);
   DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
   DBMS_ALERT.WAITONE(v_name,v_msg,v_status,v_timeout);
   DBMS OUTPUT.PUT LINE('Alert name : ' || v name);
   DBMS_OUTPUT.PUT_LINE('Alert msg
                                      : ' || v_msg);
   DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
```

```
DBMS_OUTPUT.PUT_LINE('Alert timeout: ' || v_timeout || ' seconds');
   DBMS_ALERT.REMOVE(v_name);
   END;
   Registered for alert alert_test
   Waiting for signal...
Signal sent for alert_test sent by an anonymous block in a second session:
DECLARE
             VARCHAR2(30) := 'alert_test';
    v_name
BEGIN
   DBMS_ALERT.SIGNAL(v_name, 'This is the message from ' || v_name);
   DBMS_OUTPUT.PUT_LINE('Issued alert for ' || v_name);
END;
Issued alert for alert_test
First session is alerted, control returns to the anonymous block, and the remain-
der of the code is executed:
Registered for alert alert_test
Waiting for signal...
            : alert_test
Alert name
             : This is the message from alert_test
Alert msg
Alert status: 0
Alert timeout: 120 seconds
DBMS_ALERT_Comprehensive_example
```

Comprehensive Example

The following example uses two triggers to send alerts when the dept table or the emp table is changed. An anonymous block listens for these alerts and displays messages when an alert is received.

The following are the triggers on the dept and emp tables:

```
CREATE OR REPLACE TRIGGER dept_alert_trig

AFTER INSERT OR UPDATE OR DELETE ON dept

DECLARE

v_action VARCHAR2(25);

BEGIN

IF INSERTING THEN

v_action := ' added department(s) ';

ELSIF UPDATING THEN

v_action := ' updated department(s) ';

ELSIF DELETING THEN

v_action := ' deleted department(s) ';
```

```
END IF;
  DBMS_ALERT.SIGNAL('dept_alert', USER || v_action || 'on ' ||
      SYSDATE);
END;
CREATE OR REPLACE TRIGGER emp_alert_trig
    AFTER INSERT OR UPDATE OR DELETE ON emp
DECLARE
                    VARCHAR2(25);
    v_action
BEGIN
  IF INSERTING THEN
      v_action := ' added employee(s) ';
  ELSIF UPDATING THEN
      v action := ' updated employee(s) ';
  ELSIF DELETING THEN
      v_action := ' deleted employee(s) ';
  END IF;
  DBMS_ALERT.SIGNAL('emp_alert', USER || v_action || 'on ' ||
      SYSDATE);
END;
The following anonymous block is executed in a session while updates to the
dept and emp tables occur in other sessions:
DECLARE
    v_dept_alert
                     VARCHAR2(30) := 'dept_alert';
    v_emp_alert
                     VARCHAR2(30) := 'emp alert';
    v_name
                     VARCHAR2(30);
    v_msg
                     VARCHAR2(80);
    v_status
                     INTEGER;
                     NUMBER(3) := 60;
    v_timeout
BEGIN
    DBMS_ALERT.REGISTER(v_dept_alert);
    DBMS ALERT.REGISTER(v emp alert);
    DBMS_OUTPUT.PUT_LINE('Registered for alerts dept_alert and emp_alert');
    DBMS_OUTPUT.PUT_LINE('Waiting for signal...');
    LOOP
        DBMS_ALERT.WAITANY(v_name, v_msg, v_status, v_timeout);
        EXIT WHEN v_status != 0;
        DBMS_OUTPUT.PUT_LINE('Alert name : ' || v_name);
        DBMS_OUTPUT.PUT_LINE('Alert msg : ' || v_msg);
        DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
        DBMS_OUTPUT.PUT_LINE('-----' ||
       '----');
    END LOOP;
    DBMS_OUTPUT.PUT_LINE('Alert status : ' || v_status);
    DBMS_ALERT.REMOVEALL;
```

```
END;
```

Registered for alerts dept_alert and emp_alert Waiting for signal...

The following changes are made by user, mary:

```
INSERT INTO dept VALUES (50,'FINANCE','CHICAGO');
INSERT INTO emp (empno,ename,deptno) VALUES (9001,'JONES',50);
INSERT INTO emp (empno,ename,deptno) VALUES (9002,'ALICE',50);
```

The following change is made by user, john:

```
INSERT INTO dept VALUES (60, 'HR', 'LOS ANGELES');
```

The following is the output displayed by the anonymous block receiving the signals from the triggers:

```
Registered for alerts dept_alert and emp_alert
Waiting for signal...
Alert name : dept_alert
Alert msg : mary added department(s) on 25-OCT-07 16:41:01
Alert status : 0

Alert name : emp_alert
Alert msg : mary added employee(s) on 25-OCT-07 16:41:02
Alert status : 0

Alert name : dept_alert
Alert msg : john added department(s) on 25-OCT-07 16:41:22
Alert status : 0
```

$4.3.1 DBMS_AQ$

Alert status : 1

EDB Postgres Advanced Server Advanced Queueing provides message queueing and message processing for the Advanced Server database. User-defined messages are stored in a queue; a collection of queues is stored in a queue table. Procedures in the DBMS_AQADM package create and manage message queues and queue tables. Use the DBMS_AQ package to add messages to a queue or remove messages from a queue, or register or unregister a PL/SQL callback procedure.

Advanced Server also provides extended (non-compatible) functionality for the DBMS_AQ package with SQL commands. Please see the *Database Compatibility for Oracle Developers Reference Guide* for detailed information about the following SQL commands:

• ALTER QUEUE

- ALTER QUEUE TABLE
- CREATE QUEUE
- CREATE QUEUE TABLE
- DROP QUEUE
- DROP QUEUE TABLE

The DBMS_AQ package provides procedures that allow you to enqueue a message, dequeue a message, and manage callback procedures. The supported procedures are:

Function/Procedure	Return Type	Description
ENQUEUE	n/a	Post a message to a queue.
DEQUEUE	n/a	Retrieve a message from a queue if or when a message is available.
REGISTER	n/a	Register a callback procedure.
UNREGISTER	n/a	Unregister a callback procedure.

Advanced Server's implementation of DBMS_AQ is a partial implementation when compared to Oracle's version. Only those procedures listed in the table above are supported.

Advanced Server supports use of the constants listed below:

Constant	Description
$DBMS_AQ.BROWSE(0)$	Read the message without locking.
$DBMS_AQ.LOCKED$ (1)	This constant is defined, but will return an error if used.
DBMS_AQ.REMOVE (2)	Delete the message after reading; the default.
DBMS_AQ.REMOVE_NODATA (3)	This constant is defined, but will return an error if used.
DBMS_AQ.FIRST_MESSAGE (0)	Return the first available message that matches the search
DBMS_AQ.NEXT_MESSAGE (1)	Return the next available message that matches the search
DBMS_AQ.NEXT_TRANSACTION (2)	This constant is defined, but will return an error if used.
DBMS_AQ.FOREVER (-1)	Wait forever if a message that matches the search term is r
DBMS_AQ.NO_WAIT (0)	Do not wait if a message that matches the search term is n
$DBMS_AQ.ON_COMMIT(0)$	The dequeue is part of the current transaction.
$DBMS_AQ.IMMEDIATE(1)$	This constant is defined, but will return an error if used.
DBMS_AQ.PERSISTENT (0)	The message should be stored in a table.
DBMS_AQ.BUFFERED (1)	This constant is defined, but will return an error if used.
$DBMS_AQ.READY(0)$	Specifies that the message is ready to process.
DBMS_AQ.WAITING (1)	Specifies that the message is waiting to be processed.
DBMS_AQ.PROCESSED (2)	Specifies that the message has been processed.
DBMS_AQ.EXPIRED (3)	Specifies that the message is in the exception queue.
$DBMS_AQ.NO_DELAY(0)$	This constant is defined, but will return an error if used
DBMS_AQ.NEVER (NULL)	This constant is defined, but will return an error if used
$DBMS_AQ.NAMESPACE_AQ$ (0)	Accept notifications from DBMS_AQ queues.
DBMS_AQ.NAMESPACE_ANONYMOUS (1)	This constant is defined, but will return an error if used

The DBMS_AQ configuration parameters listed in the following table can be defined in the postgresql.conf file. After the configuration parameters are defined, you can invoke the DBMS_AQ package to use and manage messages held in queues and queue tables.

Parameter	Description
dbms_aq.max_workers	The maximum number of workers to run.
dbms_aq.max_idle_time	The idle time a worker must wait before exiting.
dbms_aq.min_work_time	The minimum time a worker can run before exiting.
dbms_aq.launch_delay	The minimum time between creating workers.
dbms_aq.batch_size	The maximum number of messages to process in a single transaction. The
dbms_aq.max_databases	The size of DBMS_AQ's hash table of databases. The default value is 102
dbms_aq.max_pending_retries	The size of DBMS_AQ's hash table of pending retries. The default value

enqueue dequeue register unregister

4.3.2 'ENQUEUE'

The ENQUEUE procedure adds an entry to a queue. The signature is:

ENQUEUE (

```
<queue_name> IN VARCHAR2,
<enqueue_options> IN DBMS_AQ.ENQUEUE_OPTIONS_T,
<message_properties> IN DBMS_AQ.MESSAGE_PROPERTIES_T,
<payload IN <type_name>,
<msgid> OUT RAW)
```

Parameters

<queue_name>

The name (optionally schema-qualified) of an existing queue. If you omit the schema name, the server will use the schema specified in the SEARCH_PATH. Please note that unlike Oracle, unquoted identifiers are converted to lower case before storing. To include special characters or use a case-sensitive name, enclose the name in double quotes.

For detailed information about creating a queue, please see DBMS_AQADM.CREATE_QUEUE.

<enqueue_options>

<enqueue_options> is a value of the type, enqueue_options_t:

```
DBMS_AQ.ENQUEUE_OPTIONS_T IS RECORD(
    visibility BINARY_INTEGER DEFAULT ON_COMMIT,
    relative_msgid RAW(16) DEFAULT NULL,
    sequence_deviation BINARY INTEGER DEFAULT NULL,
    transformation VARCHAR2(61) DEFAULT NULL,
    delivery_mode PLS_INTEGER NOT NULL DEFAULT PERSISTENT);
```

Currently, the only supported parameter values for enqueue_options_t are:

visibility	ON_COMMIT.
delivery_mode	PERSISTENT
sequence_deviation	NULL
transformation	NULL
relative_msgid	NULL

<message_properties>

<message_properties> is a value of the type, message_properties_t:

```
message_properties_t IS RECORD(
    priority INTEGER,
    delay INTEGER,
    expiration INTEGER,
    correlation CHARACTER VARYING(128) COLLATE pg_catalog."C",
    attempts INTEGER,
    recipient_list "AQ$_RECIPIENT_LIST_T",
    exception_queue CHARACTER VARYING(61) COLLATE pg_catalog."C",
    enqueue_time TIMESTAMP WITHOUT TIME ZONE,
    state INTEGER,
    original_msgid BYTEA,
    transaction_group CHARACTER VARYING(30) COLLATE pg_catalog."C",
    delivery_mode INTEGER

DBMS AQ.PERSISTENT);
```

The supported values for message_properties_t are:

<payload>

Use the <payload> parameter to provide the data that will be associated with the queue entry. The payload type must match the type specified when creating the corresponding queue table (see DBMS_AQADM.CREATE_QUEUE_TABLE).

<msgid>

Use the <msgid> parameter to retrieve a unique (system-generated) message identifier.

Example

The following anonymous block calls DBMS_AQ.ENQUEUE, adding a message to a queue named work_order:

```
DECLARE
 enqueue_options
                    DBMS_AQ.ENQUEUE_OPTIONS_T;
 message_properties DBMS_AQ.MESSAGE_PROPERTIES_T;
                    raw(16);
message_handle
 payload
                    work_order;
BEGIN
payload := work_order('Smith', 'system upgrade');
DBMS_AQ.ENQUEUE(
 queue name
                    => 'work order',
 enqueue_options
                  => enqueue_options,
message_properties => message_properties,
 payload
                    => payload,
msgid
                    => message_handle
   );
END;
```

4.3.3 'DEQUEUE'

The DEQUEUE procedure dequeues a message. The signature is:

```
DEQUEUE (
```

```
<queue_name> IN VARCHAR2,
<dequeue_options> IN DBMS_AQ.DEQUEUE_OPTIONS_T,
<message_properties> OUT DBMS_AQ.MESSAGE_PROPERTIES_T,
<payload> OUT type_name,
<msgid> OUT RAW)
```

Parameters

<queue_name>

The name (optionally schema-qualified) of an existing queue. If you omit the schema name, the server will use the schema specified in the SEARCH_PATH. Please note that unlike Oracle, unquoted identifiers are converted to lower case before storing. To include special characters or use a case-sensitive name, enclose the name in double quotes.

```
For detailed information about creating a queue, please see
    DBMS_AQADM.CREATE_QUEUE.
<dequeue_options>
     <dequeue_options> is a value of the type, dequeue_options_t:
DEQUEUE_OPTIONS_T IS RECORD(
  consumer_name CHARACTER VARYING(30),
  dequeue mode INTEGER,
 navigation INTEGER,
  visibility INTEGER,
  wait INTEGER,
 msgid BYTEA,
  correlation CHARACTER VARYING(128),
  deq_condition CHARACTER VARYING(4000),
  transformation CHARACTER VARYING(61),
  delivery_mode INTEGER);
Currently, the supported parameter values for dequeue_options_t are:
<message_properties>
<message_properties> is a value of the type, message_properties_t:
message_properties_t IS RECORD(
 priority INTEGER,
  delay INTEGER,
  expiration INTEGER,
  correlation CHARACTER VARYING(128) COLLATE pg_catalog."C",
  attempts INTEGER,
 recipient_list "AQ$_RECIPIENT_LIST_T",
  exception_queue CHARACTER VARYING(61) COLLATE pg_catalog."C",
  enqueue_time TIMESTAMP WITHOUT TIME ZONE,
  state INTEGER,
  original_msgid BYTEA,
  transaction_group CHARACTER VARYING(30) COLLATE pg_catalog."C",
  delivery_mode INTEGER
DBMS_AQ.PERSISTENT);
```

priority

delay

Specify the number of seconds that will pass before a message is available for dequeue
expiration

Correlation

Use the expiration parameter to specify the number of seconds until a message expires
Use correlation to specify a message that will be associated with the entry; the default
attempts

This is a system-maintained value that specifies the number of attempts to dequeue the
recipient_list

exception_queue

Use the exception_queue parameter to specify the name of an exception queue to wh

The supported values for message_properties_t are:

enqueue_time is the time the record was added to the queue; this value is provided by enqueue_time This parameter is maintained by DBMS_AQ; state can be: DBMS_AQ.WAITING - the delay state This parameter is accepted for compatibility and ignored. original_msgid transaction_group This parameter is accepted for compatibility and ignored. delivery_mode This parameter is not supported; specify a value of DBMS_AQ.PERSISTENT.

<payload>

Use the <payload> parameter to retrieve the payload of a message with a dequeue operation. The payload type must match the type specified when creating the queue table.

<msgid>

Use the <msgid> parameter to retrieve a unique message identifier.

Example

The following anonymous block calls DBMS_AQ.DEQUEUE, retrieving a message from the queue and a payload:

DECLARE

```
DBMS_AQ.DEQUEUE_OPTIONS_T;
 dequeue_options
 message_properties DBMS_AQ.MESSAGE_PROPERTIES_T;
 message_handle
                     raw(16);
 payload
                     work_order;
BEGIN
  dequeue_options.dequeue_mode := DBMS_AQ.BROWSE;
 DBMS_AQ.DEQUEUE(
    queue_name
                       => 'work_queue',
    dequeue_options
                       => dequeue_options,
    message_properties => message_properties,
    payload
                       => payload,
    msgid
                       => message_handle
 );
 DBMS_OUTPUT.PUT_LINE(
  'The next work order is [' || payload.subject || '].'
  );
END;
The payload is displayed by DBMS_OUTPUT.PUT_LINE.
```

4.3.4 REGISTER

Use the REGISTER procedure to register an email address, procedure or URL that will be notified when an item is enqueued or dequeued. The signature is:

<count> is the number of entries in <reg_list>.

Example

The following anonymous block calls DBMS_AQ.REGISTER, registering procedures that will be notified when an item is added to or removed from a queue. A set of attributes (of sys.aq\$_reg_info type) is provided for each subscription identified in the DECLARE section:

```
DECLARE
```

```
subscription1 sys.aq$_reg_info;
   subscription2 sys.aq$_reg_info;
   subscription3 sys.aq$_reg_info;
   subscriptionlist sys.aq$_reg_info_list;
BEGIN
  subscription1 := sys.aq\_reg_info('q', DBMS_AQ.NAMESPACE_AQ,
'plsql://assign_worker?PR=0',HEXTORAW('FFFF'));
  subscription2 := sys.aq$_reg_info('q', DBMS_AQ.NAMESPACE_AQ,
'plsql://add_to_history?PR=1',HEXTORAW('FFFF'));
  subscription3 := sys.aq$_reg_info('q', DBMS_AQ.NAMESPACE_AQ,
'plsql://reserve_parts?PR=2',HEXTORAW('FFFF'));
  subscriptionlist := sys.aq$_reg_info_list(subscription1,
subscription2, subscription3);
  dbms aq.register(subscriptionlist, 3);
commit;
   END;
```

/

The subscriptionlist is of type sys.aq\$_reg_info_list, and contains the previously described sys.aq\$_reg_info objects. The list name and an object count are passed to dbms_aq.register.

4.3.5 'UNREGISTER'

Use the UNREGISTER procedure to turn off notifications related to enqueueing and dequeueing. The signature is:

```
UNREGISTER(
```

```
<reg_list> IN SYS.AQ$_REG_INFO_LIST,
<count> IN NUMBER)
```

Parameter

```
<reg_list>
```

<reg_list> is a list of type AQ\$_REG_INFO_LIST; that provides information about each subscription that you would like to register. Each entry within the list is of the type AQ\$_REG_INFO, and may contain:

<count>

<count> is the number of entries in <reg_list>.

Example

The following anonymous block calls DBMS_AQ.UNREGISTER, disabling the notifications specified in the example for DBMS_AQ.REGISTER:

DECLARE

```
subscription1 sys.aq$_reg_info;
subscription2 sys.aq$_reg_info;
subscription3 sys.aq$_reg_info;
subscriptionlist sys.aq$_reg_info_list;

BEGIN

subscription1 := sys.aq$_reg_info('q', DBMS_AQ.NAMESPACE_AQ, 'plsql://assign_worker?PR=0',HEXTORAW('FFFF'));
subscription2 := sys.aq$_reg_info('q', DBMS_AQ.NAMESPACE_AQ, 'plsql://add_to_history?PR=1',HEXTORAW('FFFF'));
subscription3 := sys.aq$_reg_info('q', DBMS_AQ.NAMESPACE_AQ, 'plsql://add_to_sistory?PR=1',HEXTORAW('FFFF'));
```

'plsql://reserve_parts?PR=2',HEXTORAW('FFFF'));

```
subscriptionlist := sys.aq$_reg_info_list(subscription1,
subscription2, subscription3);

dbms_aq.unregister(subscriptionlist, 3);
commit;
END;
//
```

The subscriptionlist is of type sys.aq\$_reg_info_list, and contains the previously described sys.aq\$_reg_info objects. The list name and an object count are passed to dbms_aq.unregister.

4.4.1 DBMS_AQADM

EDB Postgres Advanced Server Advanced Queueing provides message queueing and message processing for the Advanced Server database. User-defined messages are stored in a queue; a collection of queues is stored in a queue table. Procedures in the DBMS_AQADM package create and manage message queues and queue tables. Use the DBMS_AQ package to add messages to a queue or remove messages from a queue, or register or unregister a PL/SQL callback procedure.

Advanced Server also provides extended (non-compatible) functionality for the DBMS_AQ package with SQL commands. Please see the *Database Compatibility for Oracle Developers Reference Guide* for detailed information about the following SQL commands:

- ALTER QUEUE
- ALTER QUEUE TABLE
- CREATE QUEUE
- CREATE QUEUE TABLE
- DROP QUEUE
- DROP QUEUE TABLE

The DBMS_AQADM package provides procedures that allow you to create and manage queues and queue tables.

Function/Procedure	Return Type	Description
ALTER_QUEUE	n/a	Modify an existing queue.
ALTER_QUEUE_TABLE	n/a	Modify an existing queue table.
CREATE_QUEUE	n/a	Create a queue.
CREATE_QUEUE_TABLE	n/a	Create a queue table.
DROP_QUEUE	n/a	Drop an existing queue.
DROP_QUEUE_TABLE	n/a	Drop an existing queue table.
PURGE_QUEUE_TABLE	n/a	Remove one or more messages from a queue table.

Function/Procedure	Return Type	Description
START_QUEUE STOP_QUEUE	n/a n/a	Make a queue available for enqueueing and dequeueing procedures. Make a queue unavailable for enqueueing and dequeueing procedures

Advanced Server's implementation of DBMS_AQADM is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Advanced Server supports use of the arguments listed below:

Constant	Description	For
DBMS_AQADM.TRANSACTIONAL(1)	This constant is defined, but will return an error if used.	mes
DBMS_AQADM.NONE(0)	Use to specify message grouping for a queue table.	mes
DBMS_AQADM.NORMAL_QUEUE(0)	Use with create_queue to specify queue_type.	que
DBMS_AQADM.EXCEPTION_QUEUE (1)	Use with create_queue to specify queue_type.	que
DBMS_AQADM.INFINITE(-1)	Use with create_queue to specify retention_time.	ret
DBMS_AQADM.PERSISTENT (0)	The message should be stored in a table.	enc
DBMS_AQADM.BUFFERED (1)	This constant is defined, but will return an error if used.	enc
DBMS_AQADM.PERSISTENT_OR_BUFFERED (2)	This constant is defined, but will return an error if used.	enc

alter_queue alter_queue_table create_queue create_queue_table drop_queue drop_queue_table purge_queue_table start_queue stop_queue

4.4.2 ALTER_QUEUE

Use the ALTER_QUEUE procedure to modify an existing queue. The signature is:

ALTER_QUEUE(

```
<max_retries> IN NUMBER DEFAULT NULL,
<retry_delay> IN NUMBER DEFAULT 0
<retention_time> IN NUMBER DEFAULT 0,
<auto_commit> IN BOOLEAN DEFAULT TRUE)
<comment> IN VARCHAR2 DEFAULT NULL,
```

Parameters

<queue_name>

The name of the new queue.

<max_retries>

<max_retries> specifies the maximum number of attempts to
remove a message with a dequeue statement. The value of
<max_retries> is incremented with each ROLLBACK statement.
When the number of failed attempts reaches the value specified
by <max_retries>, the message is moved to the exception queue.
Specify 0 to indicate that no retries are allowed.

<retry_delay>

<retry_delay> specifies the number of seconds until a message is
scheduled for re-processing after a ROLLBACK. Specify 0 to indicate
that the message should be retried immediately (the default).

<retention_time>

<retention_time> specifies the length of time (in seconds) that a
message will be stored after being dequeued. You can also specify
0 (the default) to indicate the message should not be retained after
dequeueing, or INFINITE to retain the message forever.

<auto_commit>

This parameter is accepted for compatibility and ignored.

<comment>

<comment> specifies a comment associated with the queue.

Example

The following command alters a queue named work_order, setting the retry_delay parameter to 5 seconds:

EXEC DBMS_AQADM.ALTER_QUEUE(queue_name => 'work_order', retry_delay
=> 5);

4.4.3 ALTER_QUEUE_TABLE

Use the ALTER_QUEUE_TABLE procedure to modify an existing queue table.

The signature is:

Parameters

<queue_table>

The (optionally schema-qualified) name of the queue table.

<comment>

Use the **<comment>** parameter to provide a comment about the queue table.

primary_instance>

<primary_instance> is accepted for compatibility and stored, but
is ignored.

<secondary_instance>

<secondary_instance> is accepted for compatibility, but is ignored.

Example

The following command modifies a queue table named work_order_table:

```
EXEC DBMS_AQADM.ALTER_QUEUE_TABLE
```

(queue_table => 'work_order_table', comment => 'This queue table
contains work orders for the shipping department.');

The queue table is named work_order_table; the command adds a comment to the definition of the queue table.

4.4.4 CREATE_QUEUE

Use the CREATE_QUEUE procedure to create a queue in an existing queue table. The signature is:

CREATE_QUEUE(

<queue_name> IN VARCHAR2
<queue_table> IN VARCHAR2,
<queue_type> IN BINARY_INTEGER DEFAULT NORMAL_QUEUE,
<max_retries> IN NUMBER DEFAULT 5,
<retry_delay> IN NUMBER DEFAULT 0
<retention_time> IN NUMBER DEFAULT 0,
<dependency_tracking> IN BOOLEAN DEFAULT FALSE,
<comment> IN VARCHAR2 DEFAULT NULL,
<auto_commit> IN BOOLEAN DEFAULT TRUE)

Parameters

<queue_name>

The name of the new queue.

<queue_table>

The name of the table in which the new queue will reside.

<queue_type>

The type of the new queue. The valid values for <queue_type> are:

 ${\tt DBMS_AQADM.NORMAL_QUEUE}$ — This value specifies a normal queue (the default).

DBMS_AQADM.EXCEPTION_QUEUE – This value specifies that the new queue is an exception queue. An exception queue will support only dequeue operations.

<max_retries>

<max_retries> specifies the maximum number of attempts to
remove a message with a dequeue statement. The value of
<max_retries> is incremented with each ROLLBACK statement.
When the number of failed attempts reaches the value specified by
<max_retries>, the message is moved to the exception queue. The
default value for a system table is 0; the default value for a user
created table is 5.

<retry_delay>

<retry_delay> specifies the number of seconds until a message is
scheduled for re-processing after a ROLLBACK. Specify 0 to indicate
that the message should be retried immediately (the default).

<retention time>

<retention_time> specifies the length of time (in seconds) that a
message will be stored after being dequeued. You can also specify
0 (the default) to indicate the message should not be retained after
dequeueing, or INFINITE to retain the message forever.

<dependency_tracking>

This parameter is accepted for compatibility and ignored.

<comment>

<comment> specifies a comment associated with the queue.

<auto_commit>

This parameter is accepted for compatibility and ignored.

Example

The following anonymous block creates a queue named work_order in the work_order_table table:

BEGIN

```
DBMS_AQADM.CREATE_QUEUE ( queue_name => 'work_order', queue_table
=> 'work_order_table', comment => 'This queue contains pending work
orders.');
END;
```

4.4.5 CREATE_QUEUE_TABLE

Use the ${\tt CREATE_QUEUE_TABLE}$ procedure to create a queue table. The signature is:

Parameters

```
<queue_table>
```

The (optionally schema-qualified) name of the queue table. <queue_payload_type>

The user-defined type of the data that will be stored in the queue table. Please note that to specify a RAW data type, you must create a user-defined type that identifies a RAW type.

<storage_clause>

Use the <storage_clause> parameter to specify attributes for the queue table. Please note that only the TABLESPACE option is enforced; all others are accepted for compatibility and ignored. Use the TABLESPACE clause to specify the name of a tablespace in which the table will be created.

<storage_clause> may be one or more of the following:

TABLESPACE <tablespace_name>, PCTFREE integer, PCTUSED integer,

INITRANS integer, MAXTRANS integer or STORAGE <storage_option>.

<storage_option> may be one or more of the following:

MINEXTENTS integer, MAXEXTENTS integer, PCTINCREASE integer,

INITIAL <size_clause>, NEXT, FREELISTS integer, OPTIMAL
<size_clause>, BUFFER_POOL {KEEP|RECYCLE|DEFAULT}.

<sort_list>

<sort_list> controls the dequeueing order of the queue; specify
the names of the column(s) that will be used to sort the queue (in
ascending order). The currently accepted values are the following
combinations of enq_time and priority:

```
enq_time, priority
priority, enq_time
priority
enq_time
```

<multiple_consumers>

<multiple_consumers> queue tables is not supported.

<message_grouping>

If specified, <message_grouping> must be NONE.

<comment>

Use the **<comment>** parameter to provide a comment about the queue table.

<auto_commit>

<secure> is accepted for compatibility, but is ignored.

Example

The following anonymous block first creates a type (work_order) with attributes that hold a name (a VARCHAR2), and a project description (a TEXT). The block then uses that type to create a queue table:

BEGIN

```
CREATE TYPE work_order AS (name VARCHAR2, project TEXT, completed BOOLEAN);

EXEC DBMS_AQADM.CREATE_QUEUE_TABLE
          (queue_table => 'work_order_table',
                queue_payload_type => 'work_order',
                comment => 'Work order message queue table');

END;
```

The queue table is named work_order_table, and contains a payload of a type work_order. A comment notes that this is the Work order message queue table.

4.4.6 DROP_QUEUE

Use the DROP_QUEUE procedure to delete a queue. The signature is:

Parameters

<queue_name>

The name of the queue that you wish to drop.

```
<auto_commit>
```

<auto_commit> is accepted for compatibility, but is ignored.

Example

The following anonymous block drops the queue named work_order:

```
BEGIN
```

```
DBMS_AQADM.DROP_QUEUE(queue_name => 'work_order');
END;
```

4.4.7 DROP_QUEUE_TABLE

Use the DROP_QUEUE_TABLE procedure to delete a queue table. The signature is:

Parameters

<queue_table>

The (optionally schema-qualified) name of the queue table.

<force>

The <force> keyword determines the behavior of the DROP_QUEUE_TABLE command when dropping a table that contain entries:

If the target table contains entries and force is FALSE, the command will fail, and the server will issue an error.

If the target table contains entries and force is TRUE, the command will drop the table and any dependent objects.

<auto_commit>

<auto_commit> is accepted for compatibility, but is ignored.

Example

The following anonymous block drops a table named work_order_table:

```
DBMS_AQADM.DROP_QUEUE_TABLE ('work_order_table', force => TRUE);
END;
```

4.4.8 PURGE_QUEUE_TABLE

Use the PURGE_QUEUE_TABLE procedure to delete messages from a queue table. The signature is:

```
PURGE_QUEUE_TABLE(
    <queue_table> IN VARCHAR2,
    <purge_condition> IN VARCHAR2,
    <purge_options> IN aq$_purge_options_t)
```

Parameters

```
<queue_table>
```

<queue_table> specifies the name of the queue table from which
you are deleting a message.

<purge_condition>

Use <purge_condition> to specify a condition (a SQL WHERE clause)
that the server will evaluate when deciding which messages to purge.

<purge_options>

<purge_options> is an object of the type aq\$_purge_options_t.
An aq\$_purge_options_t object contains:

Attribute	Type	Description
Block	Boolean	Specify TRUE if an exclusive lock should be held on all queues within the table
delivery_mode	INTEGER	<pre><delivery_mode> specifies the type of message that will be purged. The only</delivery_mode></pre>

Example

The following anonymous block removes any messages from the work_order_table with a value in the completed column of YES:

DECLARE

```
purge_options dbms_aqadm.aq$_purge_options_t;
BEGIN
   dbms_aqadm.purge_queue_table('work_order_table', 'completed = YES',
purge_options);
   END;
```

4.4.9 START_QUEUE

Use the START_QUEUE procedure to make a queue available for enqueuing and dequeueing.

The signature is:

```
START_QUEUE(
    <queue_name> IN VARCHAR2,
    <enqueue> IN BOOLEAN DEFAULT TRUE,
    <dequeue> IN BOOLEAN DEFAULT TRUE)
```

Parameters

```
<queue_name>
```

<queue_name> specifies the name of the queue that you are starting.

<enqueue>

Specify TRUE to enable enqueueing (the default), or FALSE to leave the current setting unchanged.

<dequeue>

Specify TRUE to enable dequeueing (the default), or FALSE to leave the current setting unchanged.

Example

The following anonymous block makes a queue named work_order available for enqueueing:

```
BEGIN
DBMS_AQADM.START_QUEUE
(queue_name => 'work_order);
END;
```

4.4.10 STOP_QUEUE

Use the STOP_QUEUE procedure to disable enqueuing or dequeueing on a specified queue.

The signature is:

```
STOP_QUEUE(
    <queue_name> IN VARCHAR2,
    <enqueue> IN BOOLEAN DEFAULT TRUE,
    <dequeue> IN BOOLEAN DEFAULT TRUE,
    <wait> IN BOOLEAN DEFAULT TRUE)
```

Parameters

<queue_name>

<queue_name> specifies the name of the queue that you are stopping.

<enqueu>

Specify TRUE to disable enqueueing (the default), or FALSE to leave the current setting unchanged.

<dequeue>

Specify TRUE to disable dequeueing (the default), or FALSE to leave the current setting unchanged.

<wait>

Specify TRUE to instruct the server to wait for any uncompleted transactions to complete before applying the specified changes; while waiting to stop the queue, no transactions are allowed to enqueue or dequeue from the specified queue. Specify FALSE to stop the queue immediately.

Example

The following anonymous block disables enqueueing and dequeueing from the queue named work_order:

BEGIN

```
DBMS_AQADM.STOP_QUEUE(queue_name =>'work_order', enqueue=>TRUE,
dequeue=>TRUE, wait=>TRUE);
END;
```

Enqueueing and dequeueing will stop after any outstanding transactions complete.

4.5.1 DBMS CRYPTO

The DBMS_CRYPTO package provides functions and procedures that allow you to encrypt or decrypt RAW, BLOB or CLOB data. You can also use DBMS_CRYPTO functions to generate cryptographically strong random values.

The following table lists the DBMS_CRYPTO Functions and Procedures.

Function/Procedure	Return Type	Description
DECRYPT(src, typ, key, iv)	RAW	Decrypts RAW data.
DECRYPT(dst INOUT, src, typ, key, iv)	N/A	Decrypts BLOB data.
DECRYPT(dst INOUT, src, typ, key, iv)	N/A	Decrypts CLOB data.
<pre>ENCRYPT(src, typ, key, iv)</pre>	RAW	Encrypts RAW data.
<pre>ENCRYPT(dst INOUT, src, typ, key, iv)</pre>	N/A	Encrypts BLOB data.

ENCRYPT(dst INOUT, src, typ, key, iv)	N/A	Encrypts CLOB data.
HASH(src, typ)	RAW	Applies a hash algorithm to RAW data.
HASH(src)	RAW	Applies a hash algorithm to CLOB data.
MAC(src, typ, key)	RAW	Returns the hashed MAC value of the given RAW
MAC(src, typ, key)	RAW	Returns the hashed MAC value of the given CLO
RANDOMBYTES(number_bytes)	RAW	Returns a specified number of cryptographicall
RANDOMINTEGER()	INTEGER	Returns a random INTEGER.
RANDOMNUMBER()	NUMBER	Returns a random NUMBER.

DBMS_CRYPTO functions and procedures support the following error messages:

```
ORA-28239 - DBMS_CRYPTO.KeyNull
ORA-28829 - DBMS_CRYPTO.CipherSuiteNull
ORA-28827 - DBMS_CRYPTO.CipherSuiteInvalid
```

Unlike Oracle, Advanced Server will not return error ORA-28233 if you reencrypt previously encrypted information.

Please note that RAW and BLOB are synonyms for the PostgreSQL BYTEA data type, and CLOB is a synonym for TEXT.

decrypt encrypt hash mac randombytes randominteger randomnumber

4.5.2 DECRYPT

The DECRYPT function or procedure decrypts data using a user-specified cipher algorithm, key and optional initialization vector. The signature of the DECRYPT function is:

```
DECRYPT
(<src> IN RAW, <typ> IN INTEGER, <key> IN RAW, <iv> IN RAW
DEFAULT NULL) RETURN RAW
```

The signature of the DECRYPT procedure is:

```
DECRYPT

(<dst> INOUT BLOB, <src> IN BLOB, <typ> IN INTEGER,
<key> IN RAW,
<iv> IN RAW DEFAULT NULL)

Or

DECRYPT

(<dst> INOUT CLOB, <src> IN CLOB, <typ> IN INTEGER,
```

```
<key> IN RAW,
 <iv> IN RAW DEFAULT NULL)
```

When invoked as a procedure, DECRYPT returns BLOB or CLOB data to a user-specified BLOB.

Parameters

<dst>

<dst> specifies the name of a BLOB to which the output of the
DECRYPT procedure will be written. The DECRYPT procedure will
overwrite any existing data currently in <dst>.

<src>

<src> specifies the source data that will be decrypted. If you are invoking DECRYPT as a function, specify RAW data; if invoking DECRYPT
as a procedure, specify BLOB or CLOB data.

<typ>

<typ> specifies the block cipher type and any modifiers. This should
match the type specified when the <src> was encrypted. Advanced
Server supports the following block cipher algorithms, modifiers and
cipher suites:

Block Cipher Algorithms

```
ENCRYPT_DES
                                  CONSTANT INTEGER := 1;
ENCRYPT_3DES
                                  CONSTANT INTEGER := 3;
ENCRYPT_AES
                                  CONSTANT INTEGER := 4;
ENCRYPT_AES128
                                  CONSTANT INTEGER := 6;
Block Cipher Modifiers
CHAIN CBC
                                  CONSTANT INTEGER := 256;
CHAIN ECB
                                  CONSTANT INTEGER := 768;
Block Cipher Padding Modifiers
PAD_PKCS5
                                  CONSTANT INTEGER := 4096;
PAD_NONE
                                  CONSTANT INTEGER := 8192;
Block Cipher Suites
DES CBC PKCS5
                                  CONSTANT INTEGER := ENCRYPT DES + CHAIN CBC + PAD PKCS5;
                                  CONSTANT INTEGER := ENCRYPT_3DES + CHAIN_CBC + PAD_PKCS5;
DES3_CBC_PKCS5
AES_CBC_PKCS5
                                  CONSTANT INTEGER := ENCRYPT_AES + CHAIN_CBC + PAD_PKCS5;
```

<key>

<key> specifies the user-defined decryption key. This should match
the key specified when the <src> was encrypted.

<iv>

<iv> (optional) specifies an initialization vector. If an initialization
vector was specified when the <src> was encrypted, you must specify
an initialization vector when decrypting the <src>. The default is
NULL.

Examples

The following example uses the DBMS_CRYPTO.DECRYPT function to decrypt an encrypted password retrieved from the passwords table:

```
CREATE TABLE passwords
   principal VARCHAR2(90) PRIMARY KEY, -- username
   ciphertext RAW(9) -- encrypted password
);
CREATE FUNCTION get_password(username VARCHAR2) RETURN RAW AS
           INTEGER := DBMS CRYPTO.DES CBC PKCS5;
 typ
           RAW(128) := 'my secret key';
 key
           RAW(100) := 'my initialization vector';
 password RAW(2048);
 BEGIN
   SELECT ciphertext INTO password FROM passwords WHERE principal =
   username;
   RETURN dbms_crypto.decrypt(password, typ, key, iv);
 END;
```

Note that when calling <code>DECRYPT</code>, you must pass the same cipher type, key value and initialization vector that was used when <code>ENCRYPTING</code> the target.

4.5.3 ENCRYPT

ENCRYPT

or

The ENCRYPT function or procedure uses a user-specified algorithm, key, and optional initialization vector to encrypt RAW, BLOB or CLOB data. The signature of the ENCRYPT function is:

```
ENCRYPT
  (<dst> INOUT BLOB, <src> IN CLOB, <typ> IN INTEGER,
  <key> IN RAW,
  <iv> IN RAW DEFAULT NULL)
```

When invoked as a procedure, ENCRYPT returns BLOB or CLOB data to a user-specified BLOB.

Parameters

<dst>

<dst> specifies the name of a BLOB to which the output of the
ENCRYPT procedure will be written. The ENCRYPT procedure will
overwrite any existing data currently in <dst>.

<src>

<src> specifies the source data that will be encrypted. If you are invoking ENCRYPT as a function, specify RAW data; if invoking ENCRYPT
as a procedure, specify BLOB or CLOB data.

<typ>

<typ> specifies the block cipher type that will be used by ENCRYPT, and any modifiers. Advanced Server supports the block cipher algorithms, modifiers and cipher suites listed below:

Block Cipher Algorithms				
ENCRYPT_DES	CONSTANT	INTEGER	:=	1;
ENCRYPT_3DES	CONSTANT	INTEGER	:=	3;
ENCRYPT_AES	CONSTANT	INTEGER	:=	4;
ENCRYPT_AES128	CONSTANT	INTEGER	:=	6;
Block Cipher Modifiers				
CHAIN_CBC	CONSTANT	INTEGER	:=	256;
CHAIN_ECB	CONSTANT	INTEGER	:=	768;
Block Cipher Padding Modifiers				
PAD_PKCS5	CONSTANT	INTEGER	:=	4096;
PAD_NONE	CONSTANT	INTEGER	:=	8192;
Block Cipher Suites				
DES_CBC_PKCS5	CONSTANT	INTEGER	:=	<pre>ENCRYPT_DES + CHAIN_CBC + PAD_PKCS5;</pre>
DES3_CBC_PKCS5	CONSTANT	INTEGER	:=	<pre>ENCRYPT_3DES + CHAIN_CBC + PAD_PKCS5;</pre>
AES_CBC_PKCS5	CONSTANT	INTEGER	:=	<pre>ENCRYPT_AES + CHAIN_CBC + PAD_PKCS5;</pre>

<key>

<key> specifies the encryption key.

<iv>

<iv> (optional) specifies an initialization vector. By default, <iv> is NULL.

Examples

The following example uses the DBMS_CRYPTO.DES_CBC_PKCS5 Block Cipher Suite (a pre-defined set of algorithms and modifiers) to encrypt a value retrieved from the passwords table:

```
CREATE TABLE passwords
             VARCHAR2(90) PRIMARY KEY, -- username
ciphertext RAW(9) -- encrypted password
);
CREATE PROCEDURE set_password(username VARCHAR2, cleartext RAW) AS
             INTEGER := DBMS CRYPTO.DES CBC PKCS5;
typ
             RAW(128) := 'my secret key';
key
             RAW(100) := 'my initialization vector';
 iv
            RAW(2048);
 encrypted
BEGIN
 encrypted := dbms_crypto.encrypt(cleartext, typ, key, iv);
UPDATE passwords SET ciphertext = encrypted WHERE principal =
 username;
END;
```

ENCRYPT uses a key value of my secret key and an initialization vector of my initialization vector when encrypting the password; specify the same key and initialization vector when decrypting the password.

4.5.4 HASH

The HASH function uses a user-specified algorithm to return the hash value of a RAW or CLOB value. The HASH function is available in three forms:

```
HASH
(<src> IN RAW, <typ> IN INTEGER) RETURN RAW

HASH
(<src> IN CLOB, <typ> IN INTEGER) RETURN RAW

Parameters
```

<src>

<src> specifies the value for which the hash value will be generated.
You can specify a RAW, a BLOB, or a CLOB value.

<typ>

<typ> specifies the HASH function type. Advanced Server supports the HASH function types listed below:

HASH Functions			
HASH_MD4	CONSTANT	INTEGER	:= 1;
HASH_MD5	CONSTANT	INTEGER	:= 2;
HASH_SH1	CONSTANT	INTEGER	:= 3;

Examples

The following example uses DBMS_CRYPTO.HASH to find the md5 hash value of the string, cleartext source:

```
DECLARE
  typ INTEGER := DBMS_CRYPTO.HASH_MD5;
  hash_value RAW(100);
BEGIN
  hash_value := DBMS_CRYPTO.HASH('cleartext source', typ);
END;
```

4.5.5 MAC

The MAC function uses a user-specified MAC function to return the hashed MAC value of a RAW or CLOB value. The MAC function is available in three forms:

```
MAC
(<src> IN RAW, <typ> IN INTEGER, <key> IN RAW) RETURN
RAW

MAC
(<src> IN CLOB, <typ> IN INTEGER, <key> IN RAW) RETURN
RAW
```

Parameters

<src>

<src> specifies the value for which the MAC value will be generated.
Specify a RAW, BLOB, or CLOB value.

<typ>

 $<\!$ specifies the MAC function used. Advanced Server supports the MAC functions listed below.

MAC Functions				
HMAC_MD5	CONSTANT	INTEGER	:=	1;
HMAC_SH1	CONSTANT	INTEGER	:=	2;

<key>

<key> specifies the key that will be used to calculate the hashed MAC value.

Examples

The following example finds the hashed MAC value of the string cleartext source:

DECLARE

```
typ INTEGER := DBMS_CRYPTO.HMAC_MD5;
key RAW(100) := 'my secret key';
mac_value RAW(100);
BEGIN

mac_value := DBMS_CRYPTO.MAC('cleartext source', typ, key);
END;
```

DBMS_CRYPTO.MAC uses a key value of my secret key when calculating the MAC value of cleartext source.

4.5.6 RANDOMBYTES

The RANDOMBYTES function returns a RAW value of the specified length, containing cryptographically random bytes. The signature is:

```
RANDOMBYTES
(<number_bytes> IN INTEGER) RETURNS RAW
```

Parameter

```
<number_bytes>
```

<number_bytes> specifies the number of random bytes to be returned

Examples

BEGIN

The following example uses RANDOMBYTES to return a value that is 1024 bytes long:

DECLARE result RAW(1024);

```
result := DBMS_CRYPTO.RANDOMBYTES(1024);
END;
```

4.5.7 RANDOMINTEGER

The RANDOMINTEGER() function returns a random INTEGER between 0 and 268,435,455. The signature is:

RANDOMINTEGER() RETURNS INTEGER

Examples

The following example uses the RANDOMINTEGER function to return a cryptographically strong random INTEGER value:

```
DECLARE
  result INTEGER;
BEGIN
  result := DBMS_CRYPTO.RANDOMINTEGER();
  DBMS_OUTPUT.PUT_LINE(result);
END;
```

4.5.8 RANDOMNUMBER

The RANDOMNUMBER() function returns a random NUMBER between 0 and 268,435,455. The signature is:

RANDOMNUMBER() RETURNS NUMBER

Examples

The following example uses the ${\tt RANDOMNUMBER}$ function to return a cryptographically strong random number:

```
DECLARE
  result NUMBER;
BEGIN
  result := DBMS_CRYPTO.RANDOMNUMBER();
  DBMS_OUTPUT.PUT_LINE(result);
END;
```

4.6.1 DBMS JOB

The DBMS_JOB package provides for the creation, scheduling, and managing of jobs. A job runs a stored procedure which has been previously stored in the

database. The SUBMIT procedure is used to create and store a job definition. A job identifier is assigned to a job along with its associated stored procedure and the attributes describing when and how often the job is to be run.

This package relies on the pgAgent scheduler. By default, the Advanced Server installer installs pgAgent, but you must start the pgAgent service manually prior to using DBMS_JOB. If you attempt to use this package to schedule a job after un-installing pgAgent, DBMS_JOB will throw an error. DBMS_JOB verifies that pgAgent is installed, but does not verify that the service is running.

The following table lists the supported <code>DBMS_JOB</code> procedures:

Function/Procedure	Return Type	Dε
<pre>BROKEN(<job>, <broken> [, <next_date>])</next_date></broken></job></pre>	n/a	Sp
<pre>CHANGE(<job, <what="">, <next_date>, <interval, force="" instance,="">)</interval,></next_date></job,></pre>	n/a	Ch
<pre>INTERVAL(<job>, <interval>)</interval></job></pre>	n/a	Set
<pre>NEXT_DATE(<job>, <next_date>)</next_date></job></pre>	n/a	Set
REMOVE(<job>)</job>	n/a	De
RUN(<job>)</job>	n/a	For
SUBMIT(<job> OUT, <what> [, <next_date> [, <interval> [, <no_parse>]]])</no_parse></interval></next_date></what></job>	n/a	Cre
WHAT(<job>, <what>)</what></job>	n/a	Ch

Advanced Server's implementation of DBMS_JOB is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Before using DBMS_JOB, a database superuser must create the pgAgent extension. Use the psql client to connect to a database and invoke the command:

CREATE EXTENSION pgagent;

When and how often a job is run is dependent upon two interacting parameters – <next_date> and <interval>. The <next_date> parameter is a date/time value that specifies the next date/time when the job is to be executed. The <interval> parameter is a string that contains a date function that evaluates to a date/time value.

Just prior to any execution of the job, the expression in the <interval> parameter is evaluated. The resulting value replaces the <next_date> value stored with the job. The job is then executed. In this manner, the expression in <interval> is repeatedly re-evaluated prior to each job execution, supplying the <next_date> date/time for the next execution.

The following examples use the following stored procedure, job_proc, which simply inserts a timestamp into table, jobrun, containing a single VARCHAR2 column.

```
CREATE TABLE jobrun (
runtime VARCHAR2(40)
```

4.6.2 BROKEN

The BROKEN procedure sets the state of a job to either broken or not broken. A broken job cannot be executed except by using the RUN procedure.

```
BROKEN(<job> BINARY_INTEGER, <broken> BOOLEAN [, <next_date> DATE
])
```

Parameters

<job>

Identifier of the job to be set as broken or not broken.

broken>

If set to TRUE the job's state is set to broken. If set to FALSE the job's state is set to not broken. Broken jobs cannot be run except by using the RUN procedure.

<next_date>

Date/time when the job is to be run. The default is SYSDATE.

Examples

Set the state of a job with job identifier 104 to broken:

```
BEGIN
```

```
DBMS_JOB.BROKEN(104,true);
END;
```

Change the state back to not broken:

```
DBMS_JOB.BROKEN(104,false);
END;
```

4.6.3 CHANGE

The CHANGE procedure modifies certain job attributes including the stored procedure to be run, the next date/time the job is to be run, and how often it is to be run.

Parameters

<job>

Identifier of the job to modify.

<what>

Stored procedure name. Set this parameter to null if the existing value is to remain unchanged.

<next_date>

Date/time when the job is to be run next. Set this parameter to null if the existing value is to remain unchanged.

<interval>

Date function that when evaluated, provides the next date/time the job is to run. Set this parameter to null if the existing value is to remain unchanged.

<instance>

This argument is ignored, but is included for compatibility.

<force>

This argument is ignored, but is included for compatibility.

Examples

Change the job to run next on December 13, 2007. Leave other parameters unchanged.

```
DBMS_JOB.CHANGE(104,NULL,TO_DATE('13-DEC-07','DD-MON-YY'),NULL, NULL,
NULL);
END;
```

4.6.4 INTERVAL

The INTERVAL procedure sets the frequency of how often a job is to be run.

```
INTERVAL(<job> BINARY_INTEGER, <interval> VARCHAR2)
```

Parameters

```
<job>
```

Identifier of the job to modify.

<interval>

Date function that when evaluated, provides the next date/time the job is to be run. If <interval> is NULL and the job is complete, the job is removed from the queue.

Examples

Change the job to run once a week:

BEGIN

```
DBMS_JOB.INTERVAL(104,'SYSDATE + 7');
END;
```

4.6.5 **NEXT_DATE**

The NEXT_DATE procedure sets the date/time of when the job is to be run next.

```
NEXT_DATE(<job> BINARY_INTEGER, <next_date> DATE)
```

Parameters

```
<job>
```

Identifier of the job whose next run date is to be set.

<next_date>

Date/time when the job is to be run next.

Examples

Change the job to run next on December 14, 2007:

```
DBMS_JOB.NEXT_DATE(104, TO_DATE('14-DEC-07','DD-MON-YY'));
END;
```

4.6.6 REMOVE

The REMOVE procedure deletes the specified job from the database. The job must be resubmitted using the SUBMIT procedure in order to have it executed again. Note that the stored procedure that was associated with the job is not deleted.

```
REMOVE(<job> BINARY_INTEGER)
```

Parameter

<job>

Identifier of the job that is to be removed from the database.

Examples

Remove a job from the database:

BEGIN

```
DBMS_JOB.REMOVE(104);
END;
```

4.6.7 RUN

The RUN procedure forces the job to be run, even if its state is broken.

```
RUN(<job> BINARY_INTEGER)
```

Parameter

<job>

Identifier of the job to be run.

Examples

Force a job to be run.

BEGIN

```
DBMS_JOB.RUN(104);
```

END;

4.6.8 SUBMIT

The SUBMIT procedure creates a job definition and stores it in the database. A job consists of a job identifier, the stored procedure to be executed, when the job is to be first run, and a date function that calculates the next date/time the job is to be run.

```
SUBMIT(<job> OUT BINARY_INTEGER, <what> VARCHAR2
```

```
[, <next_date> DATE [, <interval> VARCHAR2 [, <no_parse> BOOLEAN
]]])
```

Parameters

<job>

Identifier assigned to the job.

<what>

Name of the stored procedure to be executed by the job.

<next_date>

Date/time when the job is to be run next. The default is SYSDATE.

<interval>

Date function that when evaluated, provides the next date/time the job is to run. If <interval> is set to null, then the job is run only once. Null is the default.

<no_parse>

If set to TRUE, do not syntax-check the stored procedure upon job creation – check only when the job first executes. If set to FALSE, check the procedure upon job creation. The default is FALSE.

Note

The <no_parse> option is not supported in this implementation of SUBMIT(). It is included for compatibility only.

Examples

The following example creates a job using stored procedure, job_proc. The job will execute immediately and run once a day thereafter as set by the <interval> parameter, SYSDATE + 1.

```
END;
jobid: 104
The job immediately executes procedure, job_proc, populating table, jobrun,
with a row:
SELECT * FROM jobrun;
               runtime
_____
  job_proc run at 2007-12-11 11:43:25
  (1 row)
4.6.9 WHAT
The WHAT procedure changes the stored procedure that the job will execute.
WHAT(<job> BINARY_INTEGER, <what> VARCHAR2)
Parameters
<job>
    Identifier of the job for which the stored procedure is to be changed.
<what>
    Name of the stored procedure to be executed.
Examples
Change the job to run the list_emp procedure:
BEGIN
   DBMS_JOB.WHAT(104,'list_emp;');
END;
```

4.7.1 DBMS_LOB

The DBMS_LOB package provides the capability to operate on large objects. The following table lists the supported functions and procedures:

```
Function/Procedure
APPEND(<dest_lob> IN OUT, <src_lob>)
```

```
COMPARE(<lob_1>, <lob_2> [, <amount> [, <offset_1> [, <offset_2> ]]])
CONVERTOBLOB(<dest_lob> IN OUT, <src_clob>, <amount>, <dest_offset> IN OUT, <src_offset> IN
CONVERTTOCLOB(<dest_lob> IN OUT, <src_blob>, <amount>, <dest_offset> IN OUT, <src_offset> IN
COPY(<dest_lob> IN OUT, <src_lob>, <amount> [, <dest_offset> [, <src_offset> ]])
ERASE(lob_loc IN OUT, <amount> IN OUT [, <offset> ])
GET_STORAGE_LIMIT(<lob_loc>)
GETLENGTH(<lob_loc>)
INSTR(<lob_loc>, <pattern> [, <offset> [, <nth> ]])
READ(<lob_loc>, <amount> IN OUT, <offset>, <buffer> OUT)
SUBSTR(<lob_loc> [, <amount> [, <offset> ]])
TRIM(<lob_loc> IN OUT, <amount>, <offset>, <buffer>)
WRITE(<lob_loc> IN OUT, <amount>, <offset>, <buffer>)
WRITEAPPEND(<lob_loc> IN OUT, <amount>, <buffer>)
```

Advanced Server's implementation of DBMS_LOB is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The following table lists the public variables available in the package.

Public Variables	Data Type	Value
compress off	INTEGER	0
compress_on	INTEGER	1
deduplicate_off	INTEGER	0
deduplicate_on	INTEGER	4
default_csid	INTEGER	0
default_lang_ctx	INTEGER	0
encrypt_off	INTEGER	0
encrypt_on	INTEGER	1
file_readonly	INTEGER	0
lobmaxsize	INTEGER	1073741823
lob_readonly	INTEGER	0
lob_readwrite	INTEGER	1
no_warning	INTEGER	0
opt_compress	INTEGER	1
opt_deduplicate	INTEGER	4
opt_encrypt	INTEGER	2
warn_inconvertible_char	INTEGER	1

In the following sections, lengths and offsets are measured in bytes if the large objects are BLOBs. Lengths and offsets are measured in characters if the large objects are CLOBs.

append compare convert toblob convert toclob copy erase get_storage_limit

4.7.2 APPEND

The APPEND procedure provides the capability to append one large object to another. Both large objects must be of the same type.

```
APPEND(<dest_lob> IN OUT { BLOB | CLOB }, <src_lob> { BLOB | CLOB })
```

Parameters

```
<dest_lob>
```

Large object locator for the destination object. Must be the same data type as <src_lob>.

<src_lob>

Large object locator for the source object. Must be the same data type as <dest_lob>.

4.7.3 COMPARE

The COMPARE procedure performs an exact byte-by-byte comparison of two large objects for a given length at given offsets. The large objects being compared must be the same data type.

Parameters

<lob_1>

Large object locator of the first large object to be compared. Must be the same data type as <lob_2>.

<lob_2>

Large object locator of the second large object to be compared. Must be the same data type as <lob_1>.

<amount>

If the data type of the large objects is BLOB, then the comparison is made for <amount> bytes. If the data type of the large objects is CLOB, then the comparison is made for <amount> characters. The default is the maximum size of a large object.

<offset_1>

Position within the first large object to begin the comparison. The first byte/character is offset 1. The default is 1.

<offset_2>

Position within the second large object to begin the comparison. The first byte/character is offset 1. The default is 1.

<status>

Zero if both large objects are exactly the same for the specified length for the specified offsets. Non-zero, if the objects are not the same. <NULL> if <amount>, <offset_1>, or <offset_2> are less than zero.

4.7.4 CONVERTTOBLOB

The CONVERTTOBLOB procedure provides the capability to convert character data to binary.

Parameters

<dest_lob>

BLOB large object locator to which the character data is to be converted.

<src_clob>

CLOB large object locator of the character data to be converted.

<amount>

Number of characters of <src_clob> to be converted.

<dest_offset> IN

Position in bytes in the destination BLOB where writing of the source CLOB should begin. The first byte is offset 1.

<dest_offset> OUT

Position in bytes in the destination BLOB after the write operation completes. The first byte is offset 1.

<src_offset> IN

Position in characters in the source CLOB where conversion to the destination BLOB should begin. The first character is offset 1.

<src_offset> OUT

Position in characters in the source CLOB after the conversion operation completes. The first character is offset 1.

<blob_csid>

Character set ID of the converted, destination BLOB.

<lang_context> IN

Language context for the conversion. The default value of 0 is typically used for this setting.

<lang_context> OUT

Language context after the conversion completes.

<warning>

0 if the conversion was successful, 1 if an inconvertible character was encountered.

4.7.5 CONVERTTOCLOB

The CONVERTTOCLOB procedure provides the capability to convert binary data to character.

Parameters

<dest lob>

 $\tt CLOB$ large object locator to which the binary data is to be converted. $\tt <src_blob>$ BLOB large object locator of the binary data to be converted.

<amount>

Number of bytes of <src_blob> to be converted.

<dest_offset> IN

Position in characters in the destination CLOB where writing of the source BLOB should begin. The first character is offset 1.

<dest_offset> OUT

Position in characters in the destination CLOB after the write operation completes. The first character is offset 1.

<src_offset> IN

Position in bytes in the source BLOB where conversion to the destination CLOB should begin. The first byte is offset 1.

<src_offset> OUT

Position in bytes in the source BLOB after the conversion operation completes. The first byte is offset 1.

<blob_csid>

Character set ID of the converted, destination CLOB.

<lang_context> IN

Language context for the conversion. The default value of 0 is typically used for this setting.

<lang_context> OUT

Language context after the conversion completes.

<warning>

0 if the conversion was successful, 1 if an inconvertible character was encountered.

4.7.6 COPY

The COPY procedure provides the capability to copy one large object to another. The source and destination large objects must be the same data type.

```
COPY(<dest_lob> IN OUT { BLOB | CLOB }, <src_lob>
{ BLOB | CLOB },
```

<amount> INTEGER

```
[, <dest_offset> INTEGER [, <src_offset> INTEGER
]])
```

Parameters

<dest_lob>

Large object locator of the large object to which src_lob> is to be copied. Must be the same data type as src_lob>.

<src lob>

Large object locator of the large object to be copied to <dest_lob>. Must be the same data type as <dest_lob>.

<amount>

Number of bytes/characters of <src_lob> to be copied.

<dest_offset>

Position in the destination large object where writing of the source large object should begin. The first position is offset 1. The default is 1.

<src_offset>

Position in the source large object where copying to the destination large object should begin. The first position is offset 1. The default is 1.

4.7.7 ERASE

The ERASE procedure provides the capability to erase a portion of a large object. To erase a large object means to replace the specified portion with zero-byte fillers for BLOBs or with spaces for CLOBs. The actual size of the large object is not altered.

```
ERASE( <lob_loc> IN OUT { BLOB | CLOB }, <amount> IN OUT
INTEGER
```

```
[, <offset> INTEGER ])
```

Parameters

<lob_loc>

Large object locator of the large object to be erased.

<amount> IN

Number of bytes/characters to be erased.

<amount> OUT

Number of bytes/characters actually erased. This value can be smaller than the input value if the end of the large object is reached before <amount> bytes/characters have been erased.

<offset>

Position in the large object where erasing is to begin. The first byte/character is position 1. The default is 1.

4.7.8 GET STORAGE LIMIT

The GET_STORAGE_LIMIT function returns the limit on the largest allowable large object.

```
<size> INTEGER GET_STORAGE_LIMIT(<lob_loc> BLOB)
<size> INTEGER GET_STORAGE_LIMIT(<lob_loc< CLOB)</pre>
```

Parameters

<size>

Maximum allowable size of a large object in this database.

<lob_loc>

This parameter is ignored, but is included for compatibility.

4.7.9 GETLENGTH

The GETLENGTH function returns the length of a large object.

```
<amount> INTEGER GETLENGTH(<lob_loc> BLOB)
<amount> INTEGER GETLENGTH(<lob_loc> CLOB)
```

Parameters

<lob_loc>

Large object locator of the large object whose length is to be obtained.

<amount>

Length of the large object in bytes for BLOBs or characters for CLOBs.

4.7.10 INSTR

The INSTR function returns the location of the nth occurrence of a given pattern within a large object.

```
<position> INTEGER INSTR(<lob_loc> { BLOB | CLOB },
<pattern> { RAW | VARCHAR2 } [, <offset> INTEGER [,
<nth> INTEGER]])
```

Parameters

<lob loc>

Large object locator of the large object in which to search for pattern.

<pattern>

Pattern of bytes or characters to match against the large object, lob. pattern> must be RAW if <lob_loc> is a BLOB. pattern must be VARCHAR2 if <lob_loc> is a CLOB.

<offset>

Position within <lob_loc> to start search for <pattern>. The first byte/character is position 1. The default is 1.

<nth>

Search for <pattern>, <nth> number of times starting at the position given by <offset>. The default is 1.

<position>

Position within the large object where <pattern< appears the nth time specified by <nth< starting from the position given by <offset>.

4.7.11 READ

The READ procedure provides the capability to read a portion of a large object into a buffer.

Parameters

<lob_loc>

Large object locator of the large object to be read.

<amount> IN

Number of bytes/characters to read.

<amount> OUT

Number of bytes/characters actually read. If there is no more data to be read, then <amount> returns 0 and a DATA_NOT_FOUND exception is thrown.

<offset>

Position to begin reading. The first byte/character is position 1.

<buffer>

Variable to receive the large object. If <lob_loc> is a BLOB, then <buffer> must be RAW. If <lob_loc> is a CLOB, then <buffer> must be VARCHAR2.

4.7.12 SUBSTR

The SUBSTR function provides the capability to return a portion of a large object.

```
<data> { RAW | VARCHAR2 } SUBSTR(<lob_loc> { BLOB | CLOB
}
```

[, <amount> INTEGER [, <offset> INTEGER]])

Parameters

<lob_loc>

Large object locator of the large object to be read.

<amount>

Number of bytes/characters to be returned. Default is 32,767.

<offset>

Position within the large object to begin returning data. The first byte/character is position 1. The default is 1.

<data>

Returned portion of the large object to be read. If <lob_loc> is a BLOB, the return data type is RAW. If <lob_loc> is a CLOB, the return data type is VARCHAR2.

4.7.13 TRIM

The TRIM procedure provides the capability to truncate a large object to the specified length.

```
TRIM(<lob_loc> IN OUT { BLOB | CLOB }, <newlen> INTEGER)
```

Parameters

<lob_loc>

Large object locator of the large object to be trimmed.

<newlen>

Number of bytes/characters to which the large object is to be trimmed.

4.7.14 WRITE

The WRITE procedure provides the capability to write data into a large object. Any existing data in the large object at the specified offset for the given length is overwritten by data given in the buffer.

Parameters

<lob_loc>

Large object locator of the large object to be written.

<amount>

The number of bytes/characters in **<buffer>** to be written to the large object.

<offset>

The offset in bytes/characters from the beginning of the large object (origin is 1) for the write operation to begin.

<buffer>

Contains data to be written to the large object. If <lob_loc> is a BLOB, then <buffer> must be RAW. If <lob_loc> is a CLOB, then <buffer> must be VARCHAR2.

4.7.15 WRITEAPPEND

The WRITEAPPEND procedure provides the capability to add data to the end of a large object.

Parameters

<lob_loc>

Large object locator of the large object to which data is to be appended.

<amount>

Number of bytes/characters from **<buffer>** to be appended the large object.

<buffer>

Data to be appended to the large object. If <lob_loc> is a BLOB, then <buffer> must be RAW. If <lob_loc> is a CLOB, then <buffer> must be VARCHAR2.

4.8 DBMS_LOCK

Advanced Server provides support for the DBMS_LOCK.SLEEP procedure.

Function/Procedure	Return Type	Description
SLEEP(<seconds>)</seconds>	n/a	Suspends a session for the specified number of <seconds>.</seconds>

Advanced Server's implementation of DBMS_LOCK is a partial implementation when compared to Oracle's version. Only DBMS_LOCK.SLEEP is supported.

SLEEP

The SLEEP procedure suspends the current session for the specified number of seconds.

SLEEP(<seconds> NUMBER)

Parameters

<seconds>

<seconds> specifies the number of seconds for which you wish to suspend the session. <seconds> can be a fractional value; for example, enter 1.75 to specify one and three-fourths of a second.

4.9.1 DBMS_MVIEW

Use procedures in the DBMS_MVIEW package to manage and refresh materialized views and their dependencies. Advanced Server provides support for the following DBMS_MVIEW procedures:

Procedure

GET_MV_DEPENDENCIES(<list> VARCHAR2, <deplist> VARCHAR2);

REFRESH(<list> VARCHAR2, <method> VARCHAR2, <rollback_seg> VARCHAR2, <push_deferred_rpc> BC REFRESH(<tab> dbms_utility.uncl_array, <method> VARCHAR2, <rollback_seg> VARCHAR2, <push_deferred_rpc> BC REFRESH_ALL_MVIEWS(<number_of_failures> BINARY_INTEGER, <method> VARCHAR2, <rollback_seg> VARCHAR2, <method< VARCHAR2, <method< VARCHAR2, <method< VARCHAR2, <method< VARCHAR2, <method< VARCHAR2, <method</method> VARCHAR2, <method</method</method> VARCHAR2, <method</method> VARCHAR2, <method> VARCHAR2, <method> VARCHAR2, <method> VARCHAR2, <method> VARCHAR2, <method> VARCHAR2, <method> VARCHAR2, <method</method> VARCHAR2, <method> VARCHAR2, <metho

Advanced Server's implementation of DBMS_MVIEW is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

get_mv_dependencies refresh_all_mviews refresh_dependent

4.9.2 GET MV DEPENDENCIES

When given the name of a materialized view, GET_MV_DEPENDENCIES returns a list of items that depend on the specified view. The signature is:

```
GET_MV_DEPENDENCIES(
```

t> IN VARCHAR2,

<deplist> OUT VARCHAR2);

Parameters

t>

specifies the name of a materialized view, or a commaseparated list of materialized view names.

<deplist>

<deplist> is a comma-separated list of schema-qualified dependencies. <deplist> is a VARCHAR2 value.

Examples

The following example:

```
DECLARE
  deplist VARCHAR2(1000);
BEGIN
  DBMS_MVIEW.GET_MV_DEPENDENCIES('public.emp_view', deplist);
  DBMS_OUTPUT.PUT_LINE('deplist: ' || deplist);
END;
```

Displays a list of the dependencies on a materialized view named public.emp_view.

4.9.3 REFRESH

Use the REFRESH procedure to refresh all views specified in either a commaseparated list of view names, or a table of DBMS_UTILITY.UNCL_ARRAY values. The procedure has two signatures; use the first form when specifying a commaseparated list of view names:

REFRESH(

```
IN VARCHAR2,
<method> IN VARCHAR2 DEFAULT NULL,
<rollback_seg> IN VARCHAR2 DEFAULT NULL,
<push_deferred_rpc> IN BOOLEAN DEFAULT TRUE,
<refresh_after_errors> IN BOOLEAN DEFAULT FALSE,
<purge_option> IN NUMBER DEFAULT 1,
<parallelism> IN NUMBER DEFAULT 0,
<heap_size> IN NUMBER DEFAULT 0,
<atomic_refresh> IN BOOLEAN DEFAULT TRUE,
<nested> IN BOOLEAN DEFAULT FALSE);
```

Use the second form to specify view names in a table of ${\tt DBMS_UTILITY.UNCL_ARRAY}$ values:

```
REFRESH(
```

```
<tab> IN OUT DBMS_UTILITY.UNCL_ARRAY,
<method> IN VARCHAR2 DEFAULT NULL,
<rollback_seg> IN VARCHAR2 DEFAULT NULL,
<push_deferred_rpc> IN BOOLEAN DEFAULT TRUE,
```

<refresh_after_errors> IN BOOLEAN DEFAULT
FALSE,

<purge_option> IN NUMBER DEFAULT 1,

<parallelism> IN NUMBER DEFAULT 0,

<heap_size> IN NUMBER DEFAULT 0,

<atomic_refresh> IN BOOLEAN DEFAULT TRUE,

<nested> IN BOOLEAN DEFAULT FALSE);

Parameters

st>

is a VARCHAR2 value that specifies the name of a materialized view, or a comma-separated list of materialized view names. The names may be schema-qualified.

<tab>

<tab> is a table of DBMS_UTILITY.UNCL_ARRAY values that specify
the name (or names) of a materialized view.

<method>

<method> is a VARCHAR2 value that specifies the refresh method that will be applied to the specified view (or views). The only supported method is C; this performs a complete refresh of the view.

<rollback_seg>

<rollback_seg> is accepted for compatibility and ignored. The
default is NULL.

<push_deferred_rpc>

<push_deferred_rpc> is accepted for compatibility and ignored.
The default is TRUE.

<refresh_after_errors>

<refresh_after_errors> is accepted for compatibility and ignored.
The default is FALSE.

<purge_option>

<purge_option> is accepted for compatibility and ignored. The
default is 1.

<parallelism>

 $\operatorname{sparallelism}$ is accepted for compatibility and ignored. The default is 0.

<heap_size> IN NUMBER DEFAULT 0,

<heap_size> is accepted for compatibility and ignored. The default
is 0.

<atomic_refresh>

<atomic_refresh> is accepted for compatibility and ignored. The
default is TRUE.

<nested>

<nested> is accepted for compatibility and ignored. The default is FALSE.

Examples

The following example uses DBMS_MVIEW.REFRESH to perform a COMPLETE refresh on the public.emp_view materialized view:

EXEC DBMS_MVIEW.REFRESH(list => 'public.emp_view', method => 'C');

4.9.4 REFRESH_ALL_MVIEWS

Use the REFRESH_ALL_MVIEWS procedure to refresh any materialized views that have not been refreshed since the table or view on which the view depends has been modified. The signature is:

REFRESH_ALL_MVIEWS(

<number_of_failures> OUT BINARY_INTEGER,

<method< IN VARCHAR2 DEFAULT NULL,</pre>

<rollback_seg> IN VARCHAR2 DEFAULT NULL,

<refresh_after_errors> IN BOOLEAN DEFAULT
FALSE,

<atomic_refresh> IN BOOLEAN DEFAULT TRUE);

Parameters

<number_of_failures>

<number_of_failures> is a BINARY_INTEGER that specifies the number of failures that occurred during the refresh operation.

<method>

<method> is a VARCHAR2 value that specifies the refresh method that will be applied to the specified view (or views). The only supported method is C; this performs a complete refresh of the view.

```
<rollback_seg>
```

<rollback_seg> is accepted for compatibility and ignored. The
default is NULL.

<refresh_after_errors>

<refresh_after_errors> is accepted for compatibility and ignored.
The default is FALSE.

<atomic_refresh>

<atomic_refresh> is accepted for compatibility and ignored. The
default is TRUE.

Examples

The following example performs a COMPLETE refresh on all materialized views:

DECLARE

```
errors INTEGER;
```

BEGIN

DBMS_MVIEW.REFRESH_ALL_MVIEWS(errors, method => 'C');
END;

Upon completion, errors contains the number of failures.

4.9.5 REFRESH DEPENDENT

Use the REFRESH_DEPENDENT procedure to refresh all material views that are dependent on the views specified in the call to the procedure. You can specify a comma-separated list or provide the view names in a table of DBMS_UTILITY.UNCL_ARRAY values.

Use the first form of the procedure to refresh all material views that are dependent on the views specified in a comma-separated list:

REFRESH_DEPENDENT(

```
<number_of_failures> OUT BINARY_INTEGER,
IN VARCHAR2,
<method> IN VARCHAR2 DEFAULT NULL,
<rollback_seg> IN VARCHAR2 DEFAULT NULL
<refresh_after_errors> IN BOOLEAN DEFAULT
FALSE,
<atomic_refresh> IN BOOLEAN DEFAULT TRUE,
<nested> IN BOOLEAN DEFAULT FALSE);
```

Use the second form of the procedure to refresh all material views that are dependent on the views specified in a table of DBMS_UTILITY.UNCL_ARRAY values:

REFRESH_DEPENDENT(

```
<number_of_failures> OUT BINARY_INTEGER,
<tab> IN DBMS_UTILITY.UNCL_ARRAY,
<method> IN VARCHAR2 DEFAULT NULL,
<rollback_seg> IN VARCHAR2 DEFAULT NULL,
<refresh_after_errors> IN BOOLEAN DEFAULT
FALSE,
<atomic_refresh> IN BOOLEAN DEFAULT TRUE,
<nested> IN BOOLEAN DEFAULT FALSE);
```

Parameters

<number_of_failures>

<number_of_failures> is a BINARY_INTEGER that contains the number of failures that occurred during the refresh operation.

st>

is a VARCHAR2 value that specifies the name of a materialized view, or a comma-separated list of materialized view names. The names may be schema-qualified.

<tab>

<tab> is a table of DBMS_UTILITY.UNCL_ARRAY values that specify
the name (or names) of a materialized view.

<method>

 ${\bf method}$ is a VARCHAR2 value that specifies the refresh method that will be applied to the specified view (or views). The only supported method is C; this performs a complete refresh of the view.

<rollback_seg>

<rollback_seg> is accepted for compatibility and ignored. The
default is NULL.

<refresh_after_errors>

<refresh_after_errors> is accepted for compatibility and ignored.
The default is FALSE.

<atomic_refresh>

<atomic_refresh> is accepted for compatibility and ignored. The default is TRUE.

<nested>

<nested> is accepted for compatibility and ignored. The default is FALSE.

Examples

The following example performs a COMPLETE refresh on all materialized views dependent on a materialized view named emp_view that resides in the public schema:

```
DECLARE
  errors INTEGER;
BEGIN
  DBMS_MVIEW.REFRESH_DEPENDENT(errors, list => 'public.emp_view',
  method =>
'C');
END;
```

Upon completion, errors contains the number of failures.

4.10 DBMS_OUTPUT

The DBMS_OUTPUT package provides the capability to send messages (lines of text) to a message buffer, or get messages from the message buffer. A message buffer is local to a single session. Use the DBMS_PIPE package to send messages between sessions.

The procedures and functions available in the DBMS_OUTPUT package are listed in the following table.

Function/Procedure	Return Type	Description
DISABLE	n/a	Disable the capability to send and receive
<pre>ENABLE(<buffer_size>)</buffer_size></pre>	n/a	Enable the capability to send and receiv
<pre>GET_LINE(<line> OUT, <status> OUT)</status></line></pre>	n/a	Get a line from the message buffer.
<pre>GET_LINES(<lines> OUT, <numlines> IN OUT)</numlines></lines></pre>	n/a	Get multiple lines from the message buf
NEW_LINE	n/a	Puts an end-of-line character sequence.
PUT(<item>)</item>	n/a	Puts a partial line without an end-of-lin
<pre>PUT_LINE(<item>)</item></pre>	n/a	Puts a complete line with an end-of-line
SERVEROUTPUT(<stdout>)</stdout>	n/a	Direct messages from PUT, PUT_LINE, or

The following table lists the public variables available in the DBMS_OUTPUT package.

Public Variables	Data Type	Value	Description
chararr	TABLE		For message lines.

CHARARR

The CHARARR is for storing multiple message lines.

TYPE chararr IS TABLE OF VARCHAR2(32767) INDEX BY BINARY_INTEGER; DBMS_OUTPUT_DISABLE

DISABLE

The DISABLE procedure clears out the message buffer. Any messages in the buffer at the time the DISABLE procedure is executed will no longer be accessible. Any messages subsequently sent with the PUT, PUT_LINE, or NEW_LINE procedures are discarded. No error is returned to the sender when the PUT, PUT_LINE, or NEW_LINE procedures are executed and messages have been disabled.

Use the ENABLE procedure or SERVEROUTPUT (TRUE) procedure to re-enable the sending and receiving of messages.

DISABLE

Examples

This anonymous block disables the sending and receiving messages in the current session.

BEGIN

DBMS_OUTPUT.DISABLE;

END;

DBMS OUTPUT ENABLE

ENABLE

The ENABLE procedure enables the capability to send messages to the message buffer or retrieve messages from the message buffer. Running SERVEROUTPUT (TRUE) also implicitly performs the ENABLE procedure.

The destination of a message sent with PUT, PUT_LINE, or NEW_LINE depends upon the state of SERVEROUTPUT.

• If the last state of SERVEROUTPUT is TRUE, the message goes to standard output of the command line.

• If the last state of SERVEROUTPUT is FALSE, the message goes to the message buffer.

```
ENABLE [ (<buffer_size> INTEGER) ]
```

Parameter

```
<buffer_size>
```

Maximum length of the message buffer in bytes. If a <buffer_size> of less than 2000 is specified, the buffer size is set to 2000.

Examples

The following anonymous block enables messages. Setting SERVEROUTPUT (TRUE) forces them to standard output.

```
BEGIN
```

```
DBMS_OUTPUT.ENABLE;
DBMS_OUTPUT.SERVEROUTPUT(TRUE);
DBMS_OUTPUT.PUT_LINE('Messages enabled');
END;
```

Messages enabled

The same effect could have been achieved by simply using SERVEROUTPUT (TRUE).

```
BEGIN
```

```
DBMS_OUTPUT.SERVEROUTPUT(TRUE);
DBMS_OUTPUT.PUT_LINE('Messages enabled');
END;
```

Messages enabled

The following anonymous block enables messages, but setting SERVEROUTPUT (FALSE) directs messages to the message buffer.

BEGIN

```
DBMS_OUTPUT.ENABLE;
DBMS_OUTPUT.SERVEROUTPUT(FALSE);
DBMS_OUTPUT.PUT_LINE('Message sent to buffer');
END;
```

GET_LINE

The GET_LINE procedure provides the capability to retrieve a line of text from the message buffer. Only text that has been terminated by an end-of-line character sequence is retrieved – that is complete lines generated using PUT_LINE, or by a series of PUT calls followed by a NEW_LINE call.

```
GET_LINE(<line> OUT VARCHAR2, <status> OUT INTEGER)
```

Parameters

line>

Variable receiving the line of text from the message buffer.

<status>

0 if a line was returned from the message buffer, 1 if there was no line to return.

Examples

The following anonymous block writes the emp table out to the message buffer as a comma-delimited string for each row.

```
EXEC DBMS_OUTPUT.SERVEROUTPUT(FALSE);
```

The following anonymous block reads the message buffer and inserts the messages written by the prior example into a table named messages. The rows in messages are then displayed.

```
CREATE TABLE messages (
    status
                    INTEGER,
                    VARCHAR2(100)
    msg
);
DECLARE
    v_line
                    VARCHAR2(100);
    v_status
                    INTEGER := 0;
BEGIN
    DBMS_OUTPUT.GET_LINE(v_line,v_status);
    WHILE v_status = 0 LOOP
        INSERT INTO messages VALUES(v_status, v_line);
        DBMS OUTPUT.GET LINE(v line, v status);
    END LOOP;
```

END;

SELECT msg FROM messages;

```
msg
```

7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, ,20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, ,30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, ,10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, ,20
7839, KING, PRESIDENT, ,17-NOV-81 00:00:00, 5000.00, ,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, ,20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 3000.00, ,20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, ,10
(14 rows)

GET LINES

The GET_LINES procedure provides the capability to retrieve one or more lines of text from the message buffer into a collection. Only text that has been terminated by an end-of-line character sequence is retrieved – that is complete lines generated using PUT_LINE, or by a series of PUT calls followed by a NEW_LINE call.

GET LINES(<lines> OUT CHARARR, <numlines> IN OUT INTEGER)

Parameters

nes>

<numlines> IN

Number of lines to be retrieved from the message buffer.

<numlines> OUT

Actual number of lines retrieved from the message buffer. If the output value of <numlines> is less than the input value, then there are no more lines left in the message buffer.

Examples

The following example uses the GET_LINES procedure to store all rows from the emp table that were placed on the message buffer, into an array.

EXEC DBMS_OUTPUT.SERVEROUTPUT(FALSE);

```
DECLARE
    v_emprec
                     VARCHAR2(120);
    CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
    DBMS OUTPUT. ENABLE;
    FOR i IN emp cur LOOP
        v_emprec := i.empno || ',' || i.ename || ',' || i.job || ',' ||
            NVL(LTRIM(TO_CHAR(i.mgr,'9999')),'') || ',' || i.hiredate ||
            ',' || i.sal || ',' ||
            NVL(LTRIM(TO_CHAR(i.comm, '9990.99')), '') || ',' || i.deptno;
        DBMS_OUTPUT.PUT_LINE(v_emprec);
    END LOOP;
END;
DECLARE
    v_lines
                     DBMS_OUTPUT.CHARARR;
    v_numlines
                     INTEGER := 14;
    v_status
                     INTEGER := 0;
BEGIN
    DBMS_OUTPUT.GET_LINES(v_lines,v_numlines);
    FOR i IN 1..v_numlines LOOP
        INSERT INTO messages VALUES(v_numlines, v_lines(i));
    END LOOP;
END;
SELECT msg FROM messages;
 7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
 7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
 7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
 7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
 7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
 7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
 7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
 7788,SCOTT,ANALYST,7566,19-APR-87 00:00:00,3000.00,,20
 7839, KING, PRESIDENT, ,17-NOV-81 00:00:00,5000.00,,10
 7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
 7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
 7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
```

```
7902,FORD,ANALYST,7566,03-DEC-81 00:00:00,3000.00,,20 7934,MILLER,CLERK,7782,23-JAN-82 00:00:00,1300.00,,10 (14 rows)
```

NEW_LINE

The NEW_LINE procedure writes an end-of-line character sequence in the message buffer.

NEW_LINE

Parameter

The NEW_LINE procedure expects no parameters.

DBMS_OUTPUT_PUT

PUT

The PUT procedure writes a string to the message buffer. No end-of-line character sequence is written at the end of the string. Use the NEW_LINE procedure to add an end-of-line character sequence.

```
PUT(<item> VARCHAR2)
```

Parameter

<item>

Text written to the message buffer.

Examples

The following example uses the PUT procedure to display a comma-delimited list of employees from the emp table.

DECLARE

```
CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;

BEGIN

FOR i IN emp_cur LOOP

DBMS_OUTPUT.PUT(i.empno);

DBMS_OUTPUT.PUT(',');

DBMS_OUTPUT.PUT(i.ename);

DBMS_OUTPUT.PUT(',');

DBMS_OUTPUT.PUT(i.job);

DBMS_OUTPUT.PUT(i.mgr);

DBMS_OUTPUT.PUT(i.mgr);

DBMS_OUTPUT.PUT(i.hiredate);

DBMS_OUTPUT.PUT(i.hiredate);

DBMS_OUTPUT.PUT(i.sal);

DBMS_OUTPUT.PUT(i.sal);

DBMS_OUTPUT.PUT(',');
```

```
DBMS_OUTPUT.PUT(i.comm);
        DBMS_OUTPUT.PUT(',');
        DBMS OUTPUT.PUT(i.deptno);
        DBMS_OUTPUT.NEW_LINE;
    END LOOP;
END;
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839, KING, PRESIDENT, ,17-NOV-81 00:00:00,5000.00,,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
DBMS OUTPUT PUT LINE
```

PUT LINE

The PUT_LINE procedure writes a single line to the message buffer including an end-of-line character sequence.

```
PUT_LINE(<item> VARCHAR2)
```

Parameter

<item>

Text to be written to the message buffer.

Examples

The following example uses the PUT_LINE procedure to display a commadelimited list of employees from the emp table.

DECLARE

```
NVL(LTRIM(TO_CHAR(i.comm, '9990.99')), '') || ',' || i.deptno;
        DBMS_OUTPUT.PUT_LINE(v_emprec);
    END LOOP;
END;
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839, KING, PRESIDENT, ,17-NOV-81 00:00:00,5000.00,,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
```

SERVEROUTPUT

The SERVEROUTPUT procedure provides the capability to direct messages to standard output of the command line or to the message buffer. Setting SERVEROUTPUT(TRUE) also performs an implicit execution of ENABLE.

The default setting of SERVEROUTPUT is implementation dependent. For example, in Oracle SQLPlus, SERVEROUTPUT (FALSE) is the default. In PSQL, SERVEROUTPUT (TRUE) is the default. Also note that in Oracle SQLPlus, this setting is controlled using the SQL*Plus SET command, not by a stored procedure as implemented in Advanced Server.

```
SERVEROUTPUT(<stdout> BOOLEAN)
```

Parameter

<stdout>

Set to TRUE if subsequent PUT, PUT_LINE, or NEW_LINE commands are to send text directly to standard output of the command line. Set to FALSE if text is to be sent to the message buffer.

Examples

The following anonymous block sends the first message to the command line and the second message to the message buffer.

```
BEGIN
```

```
DBMS_OUTPUT.SERVEROUTPUT(TRUE);
DBMS_OUTPUT.PUT_LINE('This message goes to the command line');
```

```
DBMS_OUTPUT.SERVEROUTPUT(FALSE);
   DBMS_OUTPUT.PUT_LINE('This message goes to the message buffer');
END;
```

This message goes to the command line

If within the same session, the following anonymous block is executed, the message stored in the message buffer from the prior example is flushed and displayed on the command line as well as the new message.

```
BEGIN
```

```
DBMS_OUTPUT.SERVEROUTPUT(TRUE);
DBMS_OUTPUT.PUT_LINE('Flush messages from the buffer');
END;
```

This message goes to the message buffer Flush messages from the buffer

4.11.1 DBMS_PIPE

The DBMS_PIPE package provides the capability to send messages through a pipe within or between sessions connected to the same database cluster.

The procedures and functions available in the DBMS_PIPE package are listed in the following table:

Function/Procedure	Return Type	Description
<pre>CREATE_PIPE(<pipename> [, <maxpipesize>] [, <private>])</private></maxpipesize></pipename></pre>	INTEGER	Explicitly create a p
NEXT_ITEM_TYPE	INTEGER	Determine the data
PACK_MESSAGE(<item>)</item>	n/a	Place <item> in the</item>
<pre>PURGE(<pipename>)</pipename></pre>	n/a	Remove unreceived
<pre>RECEIVE_MESSAGE(<pipename> [, <timeout>])</timeout></pipename></pre>	INTEGER	Get a message from
REMOVE_PIPE(<pipename>)</pipename>	INTEGER	Delete an explicitly
RESET_BUFFER	n/a	Reset the local mess
<pre>SEND_MESSAGE(<pipename> [, <timeout>] [, <maxpipesize>])</maxpipesize></timeout></pipename></pre>	INTEGER	Send a message on a
UNIQUE_SESSION_NAME	VARCHAR2	Obtain a unique ses
UNPACK_MESSAGE(<item> OUT)</item>	n/a	Retrieve the next de

Pipes are categorized as implicit or explicit. An *implicit pipe* is created if a reference is made to a pipe name that was not previously created by the CREATE_PIPE function. For example, if the SEND_MESSAGE function is executed using a non-existent pipe name, a new implicit pipe is created with that name. An *explicit pipe* is created using the CREATE_PIPE function whereby the first parameter specifies the pipe name for the new pipe.

Pipes are also categorized as private or public. A *private pipe* can only be accessed by the user who created the pipe. Even a superuser cannot access a private pipe that was created by another user. A *public pipe* can be accessed by any user who has access to the DBMS_PIPE package.

A public pipe can only be created by using the CREATE_PIPE function with the third parameter set to FALSE. The CREATE_PIPE function can be used to create a private pipe by setting the third parameter to TRUE or by omitting the third parameter. All implicit pipes are private.

The individual data items or "lines" of a message are first built-in a *local message buffer*, unique to the current session. The PACK_MESSAGE procedure builds the message in the session's local message buffer. The SEND_MESSAGE function is then used to send the message through the pipe.

Receipt of a message involves the reverse operation. The RECEIVE_MESSAGE function is used to get a message from the specified pipe. The message is written to the session's local message buffer. The UNPACK_MESSAGE procedure is then used to transfer the message data items from the message buffer to program variables. If a pipe contains multiple messages, RECEIVE_MESSAGE gets the messages in FIFO (first-in-first-out) order.

Each session maintains separate message buffers for messages created with the PACK_MESSAGE procedure and messages retrieved by the RECEIVE_MESSAGE function. Thus messages can be both built and received in the same session. However, if consecutive RECEIVE_MESSAGE calls are made, only the message from the last RECEIVE_MESSAGE call will be preserved in the local message buffer.

 $\label{lem:create_pipe} create_pipe next_item_pipe pack_message purge receive_message remove_pipe reset_buffer send_message unique_session_name unpack_message comprehensive_example$

4.11.2 CREATE PIPE

The CREATE_PIPE function creates an explicit public pipe or an explicit private pipe with a specified name.

```
<status> INTEGER CREATE_PIPE(<pipename> VARCHAR2
```

```
[, <maxpipesize> INTEGER ] [, <private> BOOLEAN ])
```

Parameters

<pipename>

Name of the pipe.

<maxpipesize>

Maximum capacity of the pipe in bytes. Default is 8192 bytes.

vate>

Create a public pipe if set to FALSE. Create a private pipe if set to TRUE. This is the default.

<status>

Status code returned by the operation. 0 indicates successful creation.

Examples

The following example creates a private pipe named messages:

```
DECLARE
                    INTEGER;
    v_status
BEGIN
    v_status := DBMS_PIPE.CREATE_PIPE('messages');
    DBMS_OUTPUT.PUT_LINE('CREATE_PIPE status: ' || v_status);
END;
CREATE_PIPE status: 0
The following example creates a public pipe named mailbox:
DECLARE
    v_status
                    INTEGER;
BEGIN
    v status := DBMS PIPE.CREATE PIPE('mailbox',8192,FALSE);
    DBMS_OUTPUT.PUT_LINE('CREATE_PIPE status: ' || v_status);
END;
CREATE_PIPE status: 0
```

4.11.3 NEXT_ITEM_TYPE

The NEXT_ITEM_TYPE function returns an integer code identifying the data type of the next data item in a message that has been retrieved into the session's local message buffer. As each item is moved off of the local message buffer with the UNPACK_MESSAGE procedure, the NEXT_ITEM_TYPE function will return the data type code for the next available item. A code of 0 is returned when there are no more items left in the message.

```
<typecode> INTEGER NEXT_ITEM_TYPE
```

Parameters

<typecode>

Code identifying the data type of the next data item as shown in the following table.

Type Code	Data Type
0	No more data items
9	NUMBER
11	VARCHAR2
13	DATE
23	RAW

Note

The type codes list in the table are not compatible with Oracle databases. Oracle assigns a different numbering sequence to the data types.

Examples

The following example shows a pipe packed with a NUMBER item, a VARCHAR2 item, a DATE item, and a RAW item. A second anonymous block then uses the NEXT_ITEM_TYPE function to display the type code of each item.

DECLARE

```
v number
                    NUMBER := 123;
    v_varchar
                    VARCHAR2(20) := 'Character data';
   v_date
                    DATE := SYSDATE;
                    RAW(4) := '21222324';
   v_raw
                    INTEGER;
    v_status
BEGIN
   DBMS_PIPE.PACK_MESSAGE(v_number);
   DBMS_PIPE.PACK_MESSAGE(v_varchar);
    DBMS_PIPE.PACK_MESSAGE(v_date);
    DBMS_PIPE.PACK_MESSAGE(v_raw);
    v_status := DBMS_PIPE.SEND_MESSAGE('datatypes');
    DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);
EXCEPTION
   WHEN OTHERS THEN
        DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
        DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
SEND_MESSAGE status: 0
DECLARE
   v_number
                    NUMBER;
    v_varchar
                    VARCHAR2(20);
   v_{date}
                    DATE;
                    TIMESTAMP;
    v_timestamp
   v_raw
                    RAW(4);
                    INTEGER;
    v_status
```

```
BEGIN
   v_status := DBMS_PIPE.RECEIVE_MESSAGE('datatypes');
   DBMS_OUTPUT.PUT_LINE('RECEIVE_MESSAGE status: ' || v_status);
   DBMS_OUTPUT.PUT_LINE('-----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
   DBMS_PIPE.UNPACK_MESSAGE(v_number);
   DBMS_OUTPUT.PUT_LINE('NUMBER Item : ' || v_number);
   DBMS_OUTPUT.PUT_LINE('-----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
   DBMS PIPE.UNPACK MESSAGE(v varchar);
   DBMS_OUTPUT.PUT_LINE('VARCHAR2 Item : ' || v_varchar);
   DBMS_OUTPUT.PUT_LINE('-----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
   DBMS_PIPE.UNPACK_MESSAGE(v_date);
   DBMS_OUTPUT.PUT_LINE('DATE Item : ' || v_date);
   DBMS_OUTPUT.PUT_LINE('-----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
   DBMS_PIPE.UNPACK_MESSAGE(v_raw);
   DBMS_OUTPUT.PUT_LINE('RAW Item : ' || v_raw);
   DBMS_OUTPUT.PUT_LINE('-----');
   v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
   DBMS_OUTPUT.PUT_LINE('NEXT_ITEM_TYPE: ' || v_status);
   DBMS_OUTPUT.PUT_LINE('-----');
EXCEPTION
   WHEN OTHERS THEN
       DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
       DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
RECEIVE_MESSAGE status: 0
NEXT_ITEM_TYPE: 9
NUMBER Item : 123
-----
NEXT_ITEM_TYPE: 11
VARCHAR2 Item : Character data
```

NEXT_ITEM_TYPE: 13

DATE Item : 02-0CT-07 11:11:43

NEXT_ITEM_TYPE: 23

RAW Item : 21222324

NEXT_ITEM_TYPE: 0

4.11.4 PACK MESSAGE

The PACK_MESSAGE procedure places an item of data in the session's local message buffer. PACK_MESSAGE must be executed at least once before issuing a SEND_MESSAGE call.

```
PACK_MESSAGE(<item> { DATE | NUMBER | VARCHAR2 | RAW })
```

Use the UNPACK_MESSAGE procedure to obtain data items once the message is retrieved using a RECEIVE_MESSAGE call.

Parameters

<item>

An expression evaluating to any of the acceptable parameter data types. The value is added to the session's local message buffer.

4.11.5 PURGE

The PURGE procedure removes the unreceived messages from a specified implicit pipe.

PURGE(<pipename> VARCHAR2)

Use the REMOVE_PIPE function to delete an explicit pipe.

Parameter

<pipename>

Name of the pipe.

Examples

Two messages are sent on a pipe:

DECLARE

v_status

INTEGER;

BEGIN

DBMS_PIPE.PACK_MESSAGE('Message #1');

```
v_status := DBMS_PIPE.SEND_MESSAGE('pipe');
    DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);
    DBMS_PIPE.PACK_MESSAGE('Message #2');
    v_status := DBMS_PIPE.SEND_MESSAGE('pipe');
    DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);
END;
SEND MESSAGE status: 0
SEND_MESSAGE status: 0
Receive the first message and unpack it:
DECLARE
   v item
                    VARCHAR2(80);
    v_status
                    INTEGER;
BEGIN
    v_status := DBMS_PIPE.RECEIVE_MESSAGE('pipe',1);
    DBMS_OUTPUT.PUT_LINE('RECEIVE_MESSAGE status: ' || v_status);
    DBMS_PIPE.UNPACK_MESSAGE(v_item);
    DBMS_OUTPUT.PUT_LINE('Item: ' || v_item);
END;
RECEIVE_MESSAGE status: 0
Item: Message #1
Purge the pipe:
EXEC DBMS_PIPE.PURGE('pipe');
Try to retrieve the next message. The RECEIVE_MESSAGE call returns status
code 1 indicating it timed out because no message was available.
DECLARE
                    VARCHAR2(80);
    v_{item}
    v status
                    INTEGER;
BEGIN
    v_status := DBMS_PIPE.RECEIVE_MESSAGE('pipe',1);
    DBMS_OUTPUT.PUT_LINE('RECEIVE_MESSAGE status: ' || v_status);
END;
RECEIVE_MESSAGE status: 1
```

4.11.6 RECEIVE MESSAGE

The RECEIVE_MESSAGE function obtains a message from a specified pipe.

<status> INTEGER RECEIVE_MESSAGE(cpipename> VARCHAR2

```
[, <timeout> INTEGER ])
```

Parameters

<pipename>

Name of the pipe.

<timeout>

Wait time (seconds). Default is 86400000 (1000 days).

<status>

Status code returned by the operation.

The possible status codes are:

Status Code	Description
0	Success
1	Time out
2	Message too large . for the buffer

4.11.7 REMOVE_PIPE

The REMOVE_PIPE function deletes an explicit private or explicit public pipe.

```
<status> INTEGER REMOVE_PIPE(<pipename> VARCHAR2)
```

Use the REMOVE_PIPE function to delete explicitly created pipes – i.e., pipes created with the CREATE_PIPE function.

Parameters

<pipename>

Name of the pipe.

<status>

Status code returned by the operation. A status code of 0 is returned even if the named pipe is non-existent.

Examples

Two messages are sent on a pipe:

DECLARE

```
v_status INTEGER;
BEGIN
v_status := DBMS_PIPE.CREATE_PIPE('pipe');
DBMS_OUTPUT.PUT_LINE('CREATE_PIPE status : ' || v_status);
```

```
DBMS_PIPE.PACK_MESSAGE('Message #1');
    v_status := DBMS_PIPE.SEND_MESSAGE('pipe');
    DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);
   DBMS_PIPE.PACK_MESSAGE('Message #2');
    v_status := DBMS_PIPE.SEND_MESSAGE('pipe');
   DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);
END;
CREATE_PIPE status : 0
SEND_MESSAGE status: 0
SEND_MESSAGE status: 0
Receive the first message and unpack it:
DECLARE
   BEGIN
    v_status := DBMS_PIPE.RECEIVE_MESSAGE('pipe',1);
   DBMS_OUTPUT.PUT_LINE('RECEIVE_MESSAGE status: ' || v_status);
   DBMS_PIPE.UNPACK_MESSAGE(v_item);
    DBMS_OUTPUT.PUT_LINE('Item: ' || v_item);
END;
RECEIVE MESSAGE status: 0
Item: Message #1
Remove the pipe:
SELECT DBMS_PIPE.REMOVE_PIPE('pipe') FROM DUAL;
remove_pipe
         0
(1 row)
Try to retrieve the next message. The RECEIVE_MESSAGE call returns status
code 1 indicating it timed out because the pipe had been deleted.
DECLARE
                  VARCHAR2(80);
   v_item
   v_status INTEGER;
BEGIN
```

```
v_status := DBMS_PIPE.RECEIVE_MESSAGE('pipe',1);
   DBMS_OUTPUT.PUT_LINE('RECEIVE_MESSAGE status: ' || v_status);
END;

RECEIVE_MESSAGE status: 1
```

4.11.8 RESET_BUFFER

The RESET_BUFFER procedure resets a "pointer" to the session's local message buffer back to the beginning of the buffer. This has the effect of causing subsequent PACK_MESSAGE calls to overwrite any data items that existed in the message buffer prior to the RESET_BUFFER call.

```
RESET_BUFFER
```

Examples

A message to John is written to the local message buffer. It is replaced by a message to Bob by calling RESET_BUFFER. The message is sent on the pipe.

```
DECLARE
                    INTEGER;
    v_status
BEGIN
    DBMS_PIPE.PACK_MESSAGE('Hi, John');
    DBMS_PIPE.PACK_MESSAGE('Can you attend a meeting at 3:00, today?');
   DBMS_PIPE.PACK_MESSAGE('If not, is tomorrow at 8:30 ok with you?');
   DBMS_PIPE.RESET_BUFFER;
   DBMS_PIPE.PACK_MESSAGE('Hi, Bob');
   DBMS PIPE.PACK MESSAGE('Can you attend a meeting at 9:30, tomorrow?');
    v_status := DBMS_PIPE.SEND_MESSAGE('pipe');
    DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE status: ' || v_status);
END;
SEND_MESSAGE status: 0
The message to Bob is in the received message.
DECLARE
                    VARCHAR2(80);
    v_item
   v_status
                    INTEGER;
BEGIN
    v_status := DBMS_PIPE.RECEIVE_MESSAGE('pipe',1);
   DBMS_OUTPUT.PUT_LINE('RECEIVE_MESSAGE status: ' || v_status);
    DBMS_PIPE.UNPACK_MESSAGE(v_item);
    DBMS_OUTPUT.PUT_LINE('Item: ' || v_item);
   DBMS_PIPE.UNPACK_MESSAGE(v_item);
    DBMS_OUTPUT.PUT_LINE('Item: ' || v_item);
```

END;

RECEIVE_MESSAGE status: 0

Item: Hi, Bob

Item: Can you attend a meeting at 9:30, tomorrow?

4.11.9 SEND_MESSAGE

The SEND_MESSAGE function sends a message from the session's local message buffer to the specified pipe.

<status> SEND_MESSAGE(<pipename> VARCHAR2 [, <timeout>
INTEGER]

[, <maxpipesize> INTEGER])

Parameters

<pipename>

Name of the pipe.

<timeout>

Wait time (seconds). Default is 86400000 (1000 days).

<maxpipesize>

Maximum capacity of the pipe in bytes. Default is 8192 bytes.

<status>

Status code returned by the operation.

The possible status codes are:

Status Code	Description
0	Success
1	Time out
3	Function interrupted

4.11.10 UNIQUE_SESSION_NAME

The UNIQUE_SESSION_NAME function returns a name, unique to the current session.

<name> VARCHAR2 UNIQUE_SESSION_NAME

Parameters

<name>

Unique session name.

Examples

The following anonymous block retrieves and displays a unique session name.

4.11.11 UNPACK_MESSAGE

The UNPACK_MESSAGE procedure copies the data items of a message from the local message buffer to a specified program variable. The message must be placed in the local message buffer with the RECEIVE_MESSAGE function before using UNPACK_MESSAGE.

```
UNPACK_MESSAGE(<item> OUT { DATE | NUMBER | VARCHAR2 |
RAW })
```

Parameter

<item>

Type-compatible variable that receives a data item from the local message buffer.

4.11.12 Comprehensive Example

The following example uses a pipe as a "mailbox". The procedures to create the mailbox, add a multi-item message to the mailbox (up to three items), and display the full contents of the mailbox are enclosed in a package named, mailbox.

```
VARCHAR2 DEFAULT 'END'
        p_item_3
    );
   PROCEDURE empty_mailbox (
        p_mailbox
                   VARCHAR2,
        p_waittime INTEGER DEFAULT 10
    );
END mailbox;
CREATE OR REPLACE PACKAGE BODY mailbox
IS
   PROCEDURE create_mailbox
        v_mailbox VARCHAR2(30);
        v status
                    INTEGER;
    BEGIN
        v_mailbox := DBMS_PIPE.UNIQUE_SESSION_NAME;
        v_status := DBMS_PIPE.CREATE_PIPE(v_mailbox,1000,FALSE);
        IF v_status = 0 THEN
            DBMS_OUTPUT.PUT_LINE('Created mailbox: ' || v_mailbox);
        ELSE
            DBMS_OUTPUT.PUT_LINE('CREATE_PIPE failed - status: ' ||
                v_status);
        END IF;
   END create_mailbox;
   PROCEDURE add_message (
        p_mailbox VARCHAR2,
        p_item_1
                    VARCHAR2,
                    VARCHAR2 DEFAULT 'END',
        p_item_2
                    VARCHAR2 DEFAULT 'END'
        p_item_3
    )
    IS
        v_item_cnt INTEGER := 0;
        v_status
                    INTEGER;
    BEGIN
        DBMS_PIPE.PACK_MESSAGE(p_item_1);
        v_item_cnt := 1;
        IF p_item_2 != 'END' THEN
            DBMS_PIPE.PACK_MESSAGE(p_item_2);
            v_item_cnt := v_item_cnt + 1;
        END IF;
        IF p_item_3 != 'END' THEN
            DBMS_PIPE.PACK_MESSAGE(p_item_3);
            v_item_cnt := v_item_cnt + 1;
        END IF;
        v_status := DBMS_PIPE.SEND_MESSAGE(p_mailbox);
```

```
IF v_status = 0 THEN
        DBMS_OUTPUT.PUT_LINE('Added message with ' || v_item_cnt ||
            ' item(s) to mailbox ' || p_mailbox);
    ELSE
        DBMS_OUTPUT.PUT_LINE('SEND_MESSAGE in add_message failed - ' ||
            'status: ' || v_status);
    END IF;
END add_message;
PROCEDURE empty_mailbox (
    p_mailbox VARCHAR2,
    p_waittime INTEGER DEFAULT 10
)
IS
    v_msgno
                INTEGER DEFAULT 0;
    v itemno
                INTEGER DEFAULT 0;
    v_item
                VARCHAR2(100);
    v_{\tt}status
                INTEGER;
BEGIN
    v_status := DBMS_PIPE.RECEIVE_MESSAGE(p_mailbox,p_waittime);
    WHILE v_status = 0 LOOP
        v_msgno := v_msgno + 1;
        DBMS_OUTPUT.PUT_LINE('***** Start message #' || v_msgno ||
            ' ******');
        BEGIN
            LOOP
                v_status := DBMS_PIPE.NEXT_ITEM_TYPE;
                EXIT WHEN v_status = 0;
                DBMS_PIPE.UNPACK_MESSAGE(v_item);
                v_itemno := v_itemno + 1;
                DBMS_OUTPUT.PUT_LINE('Item #' || v_itemno || ': ' ||
                    v_item);
            END LOOP;
            DBMS_OUTPUT.PUT_LINE('****** End message #' || v_msgno ||
                ' ******');
            DBMS_OUTPUT.PUT_LINE('*');
            v_{itemno} := 0;
            v_status := DBMS_PIPE.RECEIVE_MESSAGE(p_mailbox,1);
        END;
    END LOOP;
    DBMS_OUTPUT.PUT_LINE('Number of messages received: ' || v_msgno);
    v_status := DBMS_PIPE.REMOVE_PIPE(p_mailbox);
    IF v status = 0 THEN
        DBMS_OUTPUT.PUT_LINE('Deleted mailbox ' || p_mailbox);
    ELSE
        DBMS_OUTPUT.PUT_LINE('Could not delete mailbox - status: '
```

```
|| v_status);
        END IF;
    END empty_mailbox;
END mailbox;
The following demonstrates the execution of the procedures in mailbox.
The first procedure creates a public pipe using a name generated by the
UNIQUE_SESSION_NAME function.
EXEC mailbox.create mailbox;
Created mailbox: PG$PIPE$13$3940
Using the mailbox name, any user in the same database with access to the
mailbox package and DBMS_PIPE package can add messages:
EXEC mailbox.add_message('PG$PIPE$13$3940','Hi, John','Can you attend a meeting at 3:00, too
Added message with 3 item(s) to mailbox PG$PIPE$13$3940
EXEC mailbox.add_message('PG$PIPE$13$3940','Don''t forget to submit your report','Thanks,',
Added message with 3 item(s) to mailbox PG$PIPE$13$3940
Finally, the contents of the mailbox can be emptied:
EXEC mailbox.empty_mailbox('PG$PIPE$13$3940');
***** Start message #1 *****
Item #1: Hi, John
Item #2: Can you attend a meeting at 3:00, today?
Item #3: -- Mary
***** End message #1 *****
***** Start message #2 *****
Item #1: Don't forget to submit your report
Item #2: Thanks,
Item #3: Joe
***** End message #2 *****
Number of messages received: 2
Deleted mailbox PG$PIPE$13$3940
```

4.12 DBMS PROFILER

The DBMS_PROFILER package collects and stores performance information about the PL/pgSQL and SPL statements that are executed during a performance profiling session; use the functions and procedures listed below to control the profiling tool.

Function/Procedure	Return Type
FLUSH_DATA	Status Code or Exception
<pre>GET_VERSION(<major> OUT, <minor> OUT)</minor></major></pre>	n/a
INTERNAL_VERSION_CHECK	Status Code
PAUSE_PROFILER	Status Code or Exception
RESUME_PROFILER	Status Code or Exception
<pre>START_PROFILER(<run_comment>, <run_comment1> [, <run_number> OUT])</run_number></run_comment1></run_comment></pre>	Status Code or Exception
STOP_PROFILER	Status Code or Exception

The functions within the DBMS_PROFILER package return a status code to indicate success or failure; the DBMS_PROFILER procedures raise an exception only if they encounter a failure. The status codes and messages returned by the functions, and the exceptions raised by the procedures are listed in the table below.

Status Code	Message	Exception	Description
-1	error version	version_mismatch	The profiler version and the database are incompatible
0	success	n/a	The operation completed successfully.
1	error_param	<pre>profiler_error</pre>	The operation received an incorrect parameter.
2	error_io	<pre>profiler_error</pre>	The data flush operation has failed.

FLUSH_DATA

The FLUSH_DATA function/procedure flushes the data collected in the current session without terminating the profiler session. The data is flushed to the tables described in the Advanced Server Performance Features Guide. The function and procedure signatures are:

<status> INTEGER FLUSH_DATA
FLUSH_DATA

Parameter

<status>

Status code returned by the operation.

GET_VERSION

The GET_VERSION procedure returns the version of DBMS_PROFILER. The procedure signature is:

GET_VERSION(<major> OUT INTEGER, <minor> OUT INTEGER)

Parameters

<major>

The major version number of DBMS_PROFILER.

<minor>

The minor version number of DBMS_PROFILER.

INTERNAL_VERSION_CHECK

The INTERNAL_VERSION_CHECK function confirms that the current version of DBMS_PROFILER will work with the current database. The function signature is:

<status> INTEGER INTERNAL_VERSION_CHECK

Parameter

<status>

Status code returned by the operation.

PAUSE_PROFILER

The PAUSE_PROFILER function/procedure pauses a profiling session. The function and procedure signatures are:

<status> INTEGER PAUSE_PROFILER
PAUSE_PROFILER

Parameter

<status>

Status code returned by the operation.

RESUME_PROFILER

The RESUME_PROFILER function/procedure pauses a profiling session. The function and procedure signatures are:

<status> INTEGER RESUME_PROFILER
RESUME_PROFILER

Parameter

<status>

Status code returned by the operation.

START_PROFILER

The START_PROFILER function/procedure starts a data collection session. The function and procedure signatures are:

Parameters

<run_comment>

A user-defined comment for the profiler session. The default value is SYSDATE.

```
<run comment1>
```

An additional user-defined comment for the profiler session. The default value is ".

<run_number>

The session number of the profiler session.

<status>

Status code returned by the operation.

STOP PROFILER

The STOP_PROFILER function/procedure stops a profiling session and flushes the performance information to the DBMS_PROFILER tables and view. The function and procedure signatures are:

```
<status> INTEGER STOP_PROFILER
STOP_PROFILER
```

Parameter

<status>

Status code returned by the operation.

Using DBMS_PROFILER

The DBMS_PROFILER package collects and stores performance information about the PL/pgSQL and SPL statements that are executed during a profiling session; you can review the performance information in the tables and views provided by the profiler.

DBMS_PROFILER works by recording a set of performance-related counters and timers for each line of PL/pgSQL or SPL statement that executes within a profiling session. The counters and timers are stored in a table named SYS.PLSQL_PROFILER_DATA. When you complete a profiling session, DBMS_PROFILER will write a row to the performance statistics table for each line of PL/pgSQL or SPL code that executed within the session. For example, if you execute the following function:

```
1 - CREATE OR REPLACE FUNCTION getBalance(acctNumber INTEGER)
2 - RETURNS NUMERIC AS $$
3 - DECLARE
4 - result NUMERIC;
5 - BEGIN
6 - SELECT INTO result balance FROM acct WHERE id = acctNumber;
7 -
8 - IF (result IS NULL) THEN
9 - RAISE INFO 'Balance is null';
10- END IF;
11-
12- RETURN result;
13- END;
14- $$ LANGUAGE 'plpgsql';
```

DBMS_PROFILER adds one PLSQL_PROFILER_DATA entry for each line of code within the getBalance() function (including blank lines and comments). The entry corresponding to the SELECT statement executed exactly one time; and required a very small amount of time to execute. On the other hand, the entry corresponding to the RAISE INFO statement executed once or not at all (depending on the value for the balance column).

Some of the lines in this function contain no executable code so the performance statistics for those lines will always contain zero values.

To start a profiling session, invoke the DBMS_PROFILER.START_PROFILER function (or procedure). Once you've invoked START_PROFILER, Advanced Server

will profile every PL/pgSQL or SPL function, procedure, trigger, or anonymous block that your session executes until you either stop or pause the profiler (by calling STOP PROFILER or PAUSE PROFILER).

It is important to note that when you start (or resume) the profiler, the profiler will only gather performance statistics for functions/procedures/triggers that start after the call to START_PROFILER (or RESUME_PROFILER).

While the profiler is active, Advanced Server records a large set of timers and counters in memory; when you invoke the STOP_PROFILER (or FLUSH_DATA) function/procedure, DBMS_PROFILER writes those timers and counters to a set of three tables:

• SYS.PLSQL_PROFILER_RAWDATA

Contains the performance counters and timers for each statement executed within the session.

• SYS.PLSQL PROFILER RUNS

Contains a summary of each run (aggregating the information found in PLSQL_PROFILER_RAWDATA).

• SYS.PLSQL_PROFILER_UNITS

Contains a summary of each code unit (function, procedure, trigger, or anonymous block) executed within a session.

In addition, DBMS_PROFILER defines a view, SYS.PLSQL_PROFILER_DATA, which contains a subset of the PLSQL_PROFILER_RAWDATA table.

Please note that a non-superuser may gather profiling information, but may not view that profiling information unless a superuser grants specific privileges on the profiling tables (stored in the SYS schema). This permits a non-privileged user to gather performance statistics without exposing information that the administrator may want to keep secret.

Querying the DBMS_PROFILER Tables and View

The following step-by-step example uses DBMS_PROFILER to retrieve performance information for procedures, functions, and triggers included in the sample data distributed with Advanced Server.

1. Open the EDB-PSQL command line, and establish a connection to the Advanced Server database. Use an EXEC statement to start the profiling session:

```
acctg=# EXEC dbms_profiler.start_profiler('profile list_emp');
```

EDB-SPL Procedure successfully completed

Note

(The call to start_profiler() includes a comment that DBMS_PROFILER associates with the profiler session).

2. Then call the list_emp function:

```
acctg=# SELECT list_emp();
INFO: EMPNO
               ENAME
INFO: ----
INFO: 7369
                SMITH
INFO: 7499
               ALLEN
INFO: 7521
               WARD
INFO: 7566
               JONES
INFO: 7654
              MARTIN
INFO: 7698
             BLAKE
INFO: 7782
            CLARK
INFO: 7788
             SCOTT
INFO: 7839
               KING
INFO: 7844
               TURNER
INFO: 7876
              ADAMS
INFO: 7900
               JAMES
INFO: 7902
               FORD
INFO: 7934
               MILLER
list_emp
(1 row)
  3. Stop the profiling session with a call to dbms_profiler.stop_profiler:
acctg=# EXEC dbms_profiler.stop_profiler;
EDB-SPL Procedure successfully completed
  4. Start a new session with the dbms_profiler.start_profiler function
    (followed by a new comment):
acctg=# EXEC dbms_profiler.start_profiler('profile get_dept_name and
emp_sal_trig');
EDB-SPL Procedure successfully completed
  5. Invoke the get_dept_name function:
acctg=# SELECT get_dept_name(10);
{\tt get\_dept\_name}
_____
ACCOUNTING
```

6. Execute an UPDATE statement that causes a trigger to execute:

(1 row)

```
UPDATE 1
    7. Terminate the profiling session and flush the performance information to
         the profiling tables:
acctg=# EXEC dbms_profiler.stop_profiler;
EDB-SPL Procedure successfully completed
    8. Now, query the plsql_profiler_runs table to view a list of the profiling
         sessions, arranged by runid:
acctg=# SELECT * FROM plsql_profiler_runs;
 runid | related_run | run_owner | run_date
                                                                                                                            - 1
                                                                                                                                                         run_comment
|run_total_time | run_system_info | run_comment1 | spare1
| enterprisedb | 04-FEB-14 09:32:48.874315 | profile list_emp
         2 |
                                       | enterprisedb | 04-FEB-14 09:41:30.546503 | profile get_dept_name and
(2 rows)
    9. Query the plsql_profiler_units table to view the amount of time con-
         sumed by each unit (each function, procedure, or trigger):
acctg=# SELECT * FROM plsql_profiler_units;
 runid | unit_number | unit_type | unit_owner | unit_name | unit_time | unit_ti
_____
         1 | 16999 | FUNCTION | enterprisedb | list_emp()
                          17002 | FUNCTION | enterprisedb | user audit trig() |
         2 |
         2 |
                         17000 | FUNCTION | enterprisedb | get_dept_name(p_deptno numeric) |
                            17004 | FUNCTION | enterprisedb | emp_sal_trig()
         2 |
(4 rows)
  10. Query the plsql_profiler_rawdata table to view a list of the wait event
         counters and wait event times:
acctg=# SELECT runid, sourcecode, func_oid, line_number, exec_count, tuples_returned, time_
 runid |
                                                                    sourcecode
                                                                                                                                                | func_oid | line_n
______
                                                                                                                                             | 16999 |
       1 | DECLARE
       1 | v_empno NUMERIC(4);
1 | v_ename VARCHAR(10);
1 | emp_cur CURSOR FOR
1 | SELECT empno, ename FROM
                                                                                                                                               | 16999 |
                                                                                                                                              l 16999 l
                                                                                                                                              l 16999 l
                                                                                                                            | 16999 |
                               SELECT empno, ename FROM memp ORDER BY empno;
```

acctg=# UPDATE memp SET sal = 500 WHERE empno = 7902;

INFO: User enterprisedb updated employee(s) on 04-FEB-14

INFO: Updating employee 7902 INFO: ..Old salary: 3000.00 INFO: ..New salary: 500.00 INFO: ..Raise: -2500.00

```
1 | BEGIN
                                                                              16999 |
1 |
                                                                              16999 |
        OPEN emp_cur;
1 |
        RAISE INFO 'EMPNO
                              ENAME';
                                                                              16999 |
        RAISE INFO '----
1 |
                              -----';
                                                                              16999 |
1 |
        LOOP
                                                                              16999 |
                                                                              16999 |
1 |
            FETCH emp_cur INTO v_empno, v_ename;
            EXIT WHEN NOT FOUND;
1 |
                                                                              16999 |
            RAISE INFO '%
1 |
                               %', v_empno, v_ename;
                                                                              16999 |
        END LOOP;
1 |
                                                                              16999 |
1 |
        CLOSE emp_cur;
                                                                              16999 |
        RETURN;
1 |
                                                                              16999
1 | END;
                                                                              16999 |
1 |
                                                                              16999 I
2 | DECLARE
                                                                              17002
2 |
        v_action
                         VARCHAR(24);
                                                                              17002 I
2 |
        v_text
                         TEXT;
                                                                              17002 I
2 | BEGIN
                                                                              17002 |
2 |
        IF TG_OP = 'INSERT' THEN
                                                                              17002 |
2 |
            v_action := ' added employee(s) on ';
                                                                              17002 |
2 |
        ELSIF TG_OP = 'UPDATE' THEN
                                                                              17002 |
2 |
            v_action := ' updated employee(s) on ';
                                                                              17002 |
2 |
        ELSIF TG_OP = 'DELETE' THEN
                                                                              17002 |
2 |
            v_action := ' deleted employee(s) on ';
                                                                              17002 |
2 |
        END IF;
                                                                              17002 |
2 |
        v_text := 'User ' || USER || v_action || CURRENT_DATE;
                                                                              17002 |
        RAISE INFO ' %', v_text;
                                                                              17002 |
2 |
        RETURN NULL;
                                                                              17002 I
2 | END;
                                                                              17002 I
2 |
                                                                              17002 |
2 | DECLARE
                                                                              17000 I
2 |
        v dname
                         VARCHAR(14);
                                                                              17000
2 | BEGIN
                                                                              17000 I
2 |
        SELECT INTO v_dname dname FROM dept WHERE deptno = p_deptno; |
                                                                              17000
2 |
        RETURN v_dname;
                                                                              17000 |
2 |
        IF NOT FOUND THEN
                                                                              17000
2 |
            RAISE INFO 'Invalid department number %', p_deptno;
                                                                              17000 I
2 |
            RETURN '';
                                                                              17000 I
2 |
        END IF;
                                                                              17000 |
2 | END;
                                                                              17000 |
2 |
                                                                              17000 |
2 | DECLARE
                                                                              17004 |
2 |
        sal_diff
                        NUMERIC(7,2);
                                                                              17004 |
2 | BEGIN
                                                                              17004 |
2 |
        IF TG OP = 'INSERT' THEN
                                                                              17004 I
2 |
            RAISE INFO 'Inserting employee %', NEW.empno;
                                                                              17004 I
            RAISE INFO '.. New salary: %', NEW.sal;
                                                                              17004 |
```

```
2 |
               RETURN NEW;
                                                                                17004 |
   2 |
           END IF;
                                                                                17004 |
   2 |
           IF TG_OP = 'UPDATE' THEN
                                                                                17004 |
   2 |
               sal_diff := NEW.sal - OLD.sal;
                                                                                17004 |
   2 |
               RAISE INFO 'Updating employee %', OLD.empno;
                                                                                17004 |
   2 |
               RAISE INFO '..Old salary: %', OLD.sal;
                                                                                17004 |
               RAISE INFO '.. New salary: %', NEW.sal;
   2 |
                                                                                17004 |
   2 |
               RAISE INFO '..Raise : %', sal_diff;
                                                                                17004 |
   2 |
               RETURN NEW;
                                                                                17004 I
   2 |
           END IF;
                                                                                17004 |
   2 |
           IF TG_OP = 'DELETE' THEN
                                                                                17004 |
   2 |
               RAISE INFO 'Deleting employee %', OLD.empno;
                                                                                17004 |
   2 |
               RAISE INFO '..Old salary: %', OLD.sal;
                                                                                17004 |
   2 |
               RETURN OLD;
                                                                                17004 |
   2 |
           END IF;
                                                                                17004 |
   2 | END;
                                                                                17004 |
   2 |
                                                                                17004 |
(68 rows)
```

11. Query the plsql_profiler_data view to review a subset of the information found in plsql_profiler_rawdata table:

tion found in prsqr_proffrer_rawdata table.				
acctg=# SELECT * FRO	M plsql_profiler_data;			

runid	unit_number	line#	total_occur	total_time	min_time	max_time	spare1 s	;]
1	16999	1	l 0	l 0	l 0	l 0	+ 	
1	16999	1 2	1 0	0	0	Ι 0	1	
1	16999	3	1 0	0	0	0	1	
1	16999	4	1 0	0	0	0	1	
1	16999	1 5	0	0	0	0	1	
1	16999	1 6	0	0	0	0	1	
1	16999	7	1 0	0	0	1 0	1	
1	16999	8	1	0.001621	0.001621	0.001621	1	
1	16999	9	1	0.000301	0.000301	0.000301	1	
1	16999	10	1	4.6e-05	4.6e-05	4.6e-05	1	
1	16999	11	1	0.001114	0.001114	0.001114	1	
1	16999	12	l 15	0.000206	l 5e-06	7.8e-05	1	
1	16999	13	15	8.3e-05	l 2e-06	4.7e-05	1	
1	16999	14	l 14	0.000773	4.7e-05	0.000116	1	
1	16999	15	0	0	0	1 0	1	
1	16999	16	1	l 1e-05	l 1e-05	l 1e-05	1	
1	16999	17	1	0	0	1 0	1	
1	16999	18	0	0	0	1 0	1	
2	17002	1	1 0	0	0	1 0	1	
2	17002	1 2	1 0	0	0	0	1	
2	17002	3	1 0	1 0	0	0	1	

2	17002	4	0	I 0	I 0	0 1
2	17002		0	0	0	0
2	17002	l 6 l	1	0.000143	0.000143	0.000143
2	17002	7	0	1 0	0	0 1
2	17002	8	0	1 0	0	0 1
2	17002	9	1	3.2e-05	3.2e-05	3.2e-05
2	17002	l 10 l	0	0	0	0
2	17002	11	0	0	0	0
2	17002	12	0	0	0	0
2	17002		1	0.000383	-	
2	17002		1	6.3e-05		6.3e-05
2	17002		1	3.6e-05	3.6e-05	3.6e-05
2	17002		0	0	0	0 1
2	17000		0	0	0	0 1
2	17000	2	0	0	0	0 1
2		3	0	0	0	0
2			0	0	0	0
2					0.000647	
2				2.6e-05		
2				0	-	
2			0	0	0	
2			0	0	0	0
2			0	0	0	0
2			0	0	0	0
2			0	0	0	0
2			0	0	0	0
2			0	0	0	0
2			0	0	0	0
2				8.4e-05		•
2				0	-	
2				0	0	0 1
2			0	0	0	0
2			0	0	0	0
2			1	•	-	0.000355
2			1	•		
2	17004		1			
2			1			
2						
2						
2						
2 2						
2						
2						
2						
2	17004	22	0	0	0	0 1

2 | 17004 | 23 | 0 | 0 | 0 | 0 | | (68 rows)

DBMS_PROFILER - Reference

The Advanced Server installer creates the following tables and views that you can query to review PL/SQL performance profile information:

Table Name	Description
PLSQL_PROFILER_RUNS	Table containing information about all profiler runs, organized by runid.
PLSQL_PROFILER_UNITS	Table containing information about all profiler runs, organized by unit.
PLSQL_PROFILER_DATA	View containing performance statistics.
PLSQL_PROFILER_RAWDATA	Table containing the performance statistics and the extended performance statis

${\bf PLSQL_PROFILER_RUNS}$ The PLSQL_PROFILER_RUNS table contains the following columns:

Column	Data Type	Description
runid	INTEGER (NOT NULL)	Unique identifier (plsql_profiler_runnumber)
related_run	INTEGER	The runid of a related run.
run_owner	TEXT	The role that recorded the profiling session.
run_date	TIMESTAMP WITHOUT TIME ZONE	The profiling session start time.
run_comment	TEXT	User comments relevant to this run
run_total_time	BIGINT	Run time (in microseconds)
run_system_info	TEXT	Currently Unused
run_comment1	TEXT	Additional user comments
spare1	TEXT	Currently Unused

${\bf PLSQL_PROFILER_UNITS}$ The ${\tt PLSQL_PROFILER_UNITS}$ table contains the following columns:

Column	Data Type	Description
runid	INTEGER	Unique identifier (plsql_profiler_runnumber)
unit_number	OID	Corresponds to the OID of the row in the pg_proc tab
unit_type	TEXT	PL/SQL function, procedure, trigger or anonymous blo
unit_owner	TEXT	The identity of the role that owns the unit.
unit_name	TEXT	The complete signature of the unit.
unit_timestamp	TIMESTAMP WITHOUT TIME ZONE	Creation date of the unit (currently NULL).
total_time	BIGINT	Time spent within the unit (in milliseconds)
spare1	BIGINT	Currently Unused
spare2	BIGINT	Currently Unused

PLSQL_PROFILER_DATA The PLSQL_PROFILER_DATA view contains the following columns:

Column	Data Type	Description
runid	INTEGER	Unique identifier (plsql_profiler_runnumber)
unit_number	OID	Object ID of the unit that contains the current line.
line#	INTEGER	Current line number of the profiled workload.
total_occur	BIGINT	The number of times that the line was executed.
total_time	DOUBLE PRECISION	The amount of time spent executing the line (in seconds)
min_time	DOUBLE PRECISION	The minimum execution time for the line.
max_time	DOUBLE PRECISION	The maximum execution time for the line.
spare1	NUMBER	Currently Unused
spare2	NUMBER	Currently Unused
spare3	NUMBER	Currently Unused
spare4	NUMBER	Currently Unused

PLSQL_PROFILER_RAWDATA The PLSQL_PROFILER_RAWDATA table contains the statistical and wait events information that is found in the PLSQL_PROFILER_DATA view, as well as the performance statistics returned by the DRITA counters and timers.

Column	Data Type	Description
runid	INTEGER	The run identifier (plsql_profiler_runn
sourcecode	TEXT	The individual line of profiled code.
func_oid	OID	Object ID of the unit that contains the
line_number	INTEGER	Current line number of the profiled wor
exec_count	BIGINT	The number of times that the line was
tuples_returned	BIGINT	Currently Unused
time_total	DOUBLE PRECISION	The amount of time spent executing the
time_shortest	DOUBLE PRECISION	The minimum execution time for the lin
time_longest	DOUBLE PRECISION	The maximum execution time for the li
num_scans	BIGINT	Currently Unused
tuples_fetched	BIGINT	Currently Unused
tuples_inserted	BIGINT	Currently Unused
tuples_updated	BIGINT	Currently Unused
tuples_deleted	BIGINT	Currently Unused
blocks_fetched	BIGINT	Currently Unused
blocks_hit	BIGINT	Currently Unused
wal_write	BIGINT	A server has waited for a write to the v
wal_flush	BIGINT	A server has waited for the write-ahead
wal_file_sync	BIGINT	A server has waited for the write-ahead
db_file_read	BIGINT	A server has waited for the completion
db_file_write	BIGINT	A server has waited for the completion
db_file_sync	BIGINT	A server has waited for the operating s

Column	Data Type	Description
db_file_extend	BIGINT	A server has waited for the operating s
sql_parse	BIGINT	Currently Unused.
query_plan	BIGINT	A server has generated a query plan.
other_lwlock_acquire	BIGINT	A server has waited for other light-weig
shared_plan_cache_collision	BIGINT	A server has waited for the completion
shared_plan_cache_insert	BIGINT	A server has waited for the completion
shared_plan_cache_hit	BIGINT	A server has waited for the completion
shared_plan_cache_miss	BIGINT	A server has waited for the completion
shared_plan_cache_lock	BIGINT	A server has waited for the completion
shared_plan_cache_busy	BIGINT	A server has waited for the completion
shmemindexlock	BIGINT	A server has waited to find or allocate s
oidgenlock	BIGINT	A server has waited to allocate or assig
xidgenlock	BIGINT	A server has waited to allocate or assig
procarraylock	BIGINT	A server has waited to get a snapshot of
sinvalreadlock	BIGINT	A server has waited to retrieve or remo
sinvalwritelock	BIGINT	A server has waited to add a message t
walbufmappinglock	BIGINT	A server has waited to replace a page in
walwritelock	BIGINT	A server has waited for WAL buffers to
controlfilelock	BIGINT	A server has waited to read or update t
checkpointlock	BIGINT	A server has waited to perform a check
clogcontrollock	BIGINT	A server has waited to read or update t
subtranscontrollock	BIGINT	A server has waited to read or update t
multixactgenlock	BIGINT	A server has waited to read or update t
multixactoffsetcontrollock	BIGINT	A server has waited to read or update i
multixactmembercontrollock	BIGINT	A server has waited to read or update i
relcacheinitlock	BIGINT	A server has waited to read or write the
checkpointercommlock	BIGINT	A server has waited to manage the fsyn
twophasestatelock	BIGINT	A server has waited to read or update t
tablespacecreatelock	BIGINT	A server has waited to create or drop to
btreevacuumlock	BIGINT	A server has waited to read or update t
addinshmeminitlock	BIGINT	A server has waited to manage space al
autovacuumlock	BIGINT	The autovacuum launcher waiting to re
autovacuumschedulelock	BIGINT	A server has waited to ensure that the
syncscanlock	BIGINT	A server has waited to get the start loc
relationmappinglock	BIGINT	A server has waited to update the relat
asyncctllock	BIGINT	A server has waited to read or update s
asyncqueuelock	BIGINT	A server has waited to read or update to
serializablexacthashlock	BIGINT	A server has waited to retrieve or store
serializablefinishedlistlock	BIGINT	A server has waited to access the list of
serializablepredicatelocklistlock	BIGINT	A server has waited to perform an oper
oldserxidlock	BIGINT	A server has waited to read or record to
syncreplock	BIGINT	A server has waited to read or update i
backgroundworkerlock	BIGINT	A server has waited to read or update to A server has waited to read or update to
dynamicsharedmemorycontrollock	BIGINT	A server has waited to read or update to A server has waited to read or update to
aynamicsnareumemory Controlition	DIGINI	11 server has warred to read or apdate

Column	Data Type	Description
autofilelock	BIGINT	A server has waited to update the post
replications lotal location lock	BIGINT	A server has waited to allocate or free
replicationslotcontrollock	BIGINT	A server has waited to read or update:
committscontrollock	BIGINT	A server has waited to read or update
committslock	BIGINT	A server has waited to read or update
replicationoriginlock	BIGINT	A server has waited to set up, drop, or
multixacttruncationlock	BIGINT	A server has waited to read or truncate
oldsnapshottimemaplock	BIGINT	A server has waited to read or update
backendrandomlock	BIGINT	A server has waited to generate a rand-
logicalrepworkerlock	BIGINT	A server has waited for the action on lo
clogtruncationlock	BIGINT	A server has waited to truncate the wr
bulkloadlock	BIGINT	A server has waited for the bulkloadle
edbresourcemanagerlock	BIGINT	The edbresourcemanagerlock provide
wal_write_time	BIGINT	The amount of time that the server has
wal_flush_time	BIGINT	The amount of time that the server has
wal_file_sync_time	BIGINT	The amount of time that the server has
db_file_read_time	BIGINT	The amount of time that the server has
db_file_write_time	BIGINT	The amount of time that the server has
db_file_sync_time	BIGINT	The amount of time that the server has
db_file_extend_time	BIGINT	The amount of time that the server has
sql_parse_time	BIGINT	The amount of time that the server has
query_plan_time	BIGINT	The amount of time that the server has
other_lwlock_acquire_time	BIGINT	The amount of time that the server has
shared_plan_cache_collision_time	BIGINT	The amount of time that the server has
shared_plan_cache_insert_time	BIGINT	The amount of time that the server has
shared_plan_cache_hit_time	BIGINT	The amount of time that the server has
shared_plan_cache_miss_time	BIGINT	The amount of time that the server has
shared_plan_cache_lock_time	BIGINT	The amount of time that the server has
shared_plan_cache_busy_time	BIGINT	The amount of time that the server has
shmemindexlock_time	BIGINT	The amount of time that the server has
oidgenlock_time	BIGINT	The amount of time that the server has
xidgenlock_time	BIGINT	The amount of time that the server has
procarraylock_time	BIGINT	The amount of time that the server has
sinvalreadlock_time	BIGINT	The amount of time that the server has
sinvalwritelock_time	BIGINT	The amount of time that the server has
walbufmappinglock_time	BIGINT	The amount of time that the server has
walwritelock_time	BIGINT	The amount of time that the server has
controlfilelock_time	BIGINT	The amount of time that the server has
checkpointlock_time	BIGINT	The amount of time that the server has
clogcontrollock_time	BIGINT	The amount of time that the server has
subtranscontrollock_time	BIGINT	The amount of time that the server has
multixactgenlock_time	BIGINT	The amount of time that the server has
multixactoffsetcontrollock_time	BIGINT	The amount of time that the server has
multixactmembercontrollock_time	BIGINT	The amount of time that the server has

Column	Data Type	Description
relcacheinitlock_time	BIGINT	The amount of time that the server has
checkpointercommlock_time	BIGINT	The amount of time that the server has
twophasestatelock_time	BIGINT	The amount of time that the server has
tablespacecreatelock_time	BIGINT	The amount of time that the server has
btreevacuumlock_time	BIGINT	The amount of time that the server has
addinshmeminitlock_time	BIGINT	The amount of time that the server has
autovacuumlock_time	BIGINT	The amount of time that the server has
autovacuumschedulelock_time	BIGINT	The amount of time that the server has
syncscanlock_time	BIGINT	The amount of time that the server has
relationmappinglock_time	BIGINT	The amount of time that the server has
asyncctllock_time	BIGINT	The amount of time that the server has
asyncqueuelock_time	BIGINT	The amount of time that the server has
serializablexacthashlock_time	BIGINT	The amount of time that the server has
serializablefinishedlistlock_time	BIGINT	The amount of time that the server has
serializablepredicatelocklistlock_time	BIGINT	The amount of time that the server has
oldserxidlock_time	BIGINT	The amount of time that the server has
syncreplock_time	BIGINT	The amount of time that the server has
backgroundworkerlock_time	BIGINT	The amount of time that the server has
dynamicsharedmemorycontrollock_time	BIGINT	The amount of time that the server has
autofilelock_time	BIGINT	The amount of time that the server has
replicationslotallocationlock_time	BIGINT	The amount of time that the server has
replicationslotcontrollock_time	BIGINT	The amount of time that the server has
committscontrollock_time	BIGINT	The amount of time that the server has
committslock_time	BIGINT	The amount of time that the server has
replicationoriginlock_time	BIGINT	The amount of time that the server has
multixacttruncationlock_time	BIGINT	The amount of time that the server has
oldsnapshottimemaplock_time	BIGINT	The amount of time that the server has
backendrandomlock_time	BIGINT	The amount of time that the server has
logicalrepworkerlock_time	BIGINT	The amount of time that the server has
clogtruncationlock_time	BIGINT	The amount of time that the server has
bulkloadlock_time	BIGINT	The amount of time that the server has
edbresourcemanagerlock_time	BIGINT	The amount of time that the server has
totalwaits	BIGINT	The total number of event waits.
totalwaittime	BIGINT	The total time spent waiting for an eve
		· · ·

4.13 DBMS_RANDOM

The $\tt DBMS_RANDOM$ package provides a number of methods to generate random values. The procedures and functions available in the <code>DBMS_RANDOM</code> package are listed in the following table.

Function/Procedure	Return Type	Description
<pre>INITIALIZE(<val>)</val></pre>	n/a	Initializes the DBMS_RANDOM package with the specified seed <value< td=""></value<>
NORMAL()	NUMBER	Returns a random NUMBER.
RANDOM	INTEGER	Returns a random INTEGER with a value greater than or equal to -2
SEED(<val>)</val>	n/a	Resets the seed with the specified <value>.</value>
SEED(<val>)</val>	n/a	Resets the seed with the specified <value>.</value>
STRING(<opt>, <len>)</len></opt>	VARCHAR2	Returns a random string.
TERMINATE	n/a	TERMINATE has no effect. Deprecated, but supported for backward
VALUE	NUMBER	Returns a random number with a value greater than or equal to 0 a
<pre>VALUE(<low>, <high>)</high></low></pre>	NUMBER	Returns a random number with a value greater than or equal to <1

INITIALIZE

The INITIALIZE procedure initializes the DBMS_RANDOM package with a seed value. The signature is:

```
INITIALIZE(<val> IN INTEGER)
```

This procedure should be considered deprecated; it is included for backward compatibility only.

Parameter

<val>

<val> is the seed value used by the DBMS_RANDOM package algorithm.

Example

The following code snippet demonstrates a call to the INITIALIZE procedure that initializes the DBMS_RANDOM package with the seed value, 6475.

DBMS_RANDOM.INITIALIZE(6475);

NORMAL

The NORMAL function returns a random number of type NUMBER. The signature is:

```
<result> NUMBER NORMAL()
```

Parameter

<result>

<result> is a random value of type NUMBER.

Example

The following code snippet demonstrates a call to the NORMAL function:

```
x:= DBMS_RANDOM.NORMAL();
```

RANDOM

The RANDOM function returns a random INTEGER value that is greater than or equal to -2 ^31 and less than 2 ^31. The signature is:

```
<result> INTEGER RANDOM()
```

This function should be considered deprecated; it is included for backward compatibility only.

Parameter

<result>

<result> is a random value of type INTEGER.

Example

The following code snippet demonstrates a call to the RANDOM function. The call returns a random number:

```
x := DBMS_RANDOM.RANDOM();
```

SEED

The first form of the SEED procedure resets the seed value for the DBMS_RANDOM package with an INTEGER value. The SEED procedure is available in two forms; the signature of the first form is:

```
SEED(<val> IN INTEGER)
```

Parameter

<val>

<val> is the seed value used by the DBMS_RANDOM package algorithm.

Example

The following code snippet demonstrates a call to the SEED procedure; the call sets the seed value at 8495.

```
DBMS_RANDOM.SEED(8495);
```

SEED

The second form of the SEED procedure resets the seed value for the DBMS_RANDOM package with a string value. The SEED procedure is available in two forms; the signature of the second form is:

```
SEED(<val> IN VARCHAR2)
```

Parameter

<val>

<val> is the seed value used by the DBMS_RANDOM package algorithm.

Example

The following code snippet demonstrates a call to the SEED procedure; the call sets the seed value to abc123.

```
DBMS_RANDOM.SEED('abc123');
```

STRING

The STRING function returns a random VARCHAR2 string in a user-specified format. The signature of the STRING function is:

<result> VARCHAR2 STRING(<opt> IN CHAR, <len> IN NUMBER)

Parameters

<opt>

Formatting option for the returned string. <option> may be:

 $Y\{0.6\}$

Option	Specifies Formatting Option
u or U	Uppercase alpha string
1 or L	Lowercase alpha string
a or A	Mixed case string
$\mathbf{x} \text{ or } \mathbf{X}$	Uppercase alpha-numeric string
p or P	Any printable characters

<len>

The length of the returned string.

<result>

<result> is a random value of type VARCHAR2.

Example

The following code snippet demonstrates a call to the STRING function; the call returns a random alpha-numeric character string that is 10 characters long.

```
x := DBMS_RANDOM.STRING('X', 10);
```

TERMINATE

The TERMINATE procedure has no effect. The signature is:

TERMINATE

The TERMINATE procedure should be considered deprecated; the procedure is supported for compatibility only.

DBMS RANDOM VALUE FIRST FORM

VALUE

The VALUE function returns a random NUMBER that is greater than or equal to 0, and less than 1, with 38 digit precision. The VALUE function has two forms; the signature of the first form is:

<result> NUMBER VALUE()

Parameter

<result>

<result> is a random value of type NUMBER.

Example

The following code snippet demonstrates a call to the VALUE function. The call returns a random NUMBER:

x := DBMS_RANDOM.VALUE();

DBMS_RANDOM_VALUE_SECOND_FORM

VALUE

The VALUE function returns a random NUMBER with a value that is between user-specified boundaries. The VALUE function has two forms; the signature of the second form is:

<result> NUMBER VALUE(<low> IN NUMBER, <high> IN NUMBER)

Parameters

<low>

<low> specifies the lower boundary for the random value. The random value may be equal to <low>.

<high>

<high> specifies the upper boundary for the random value; the random value will be less than <high>.

<result>

<result> is a random value of type NUMBER.

Example

The following code snippet demonstrates a call to the VALUE function. The call returns a random NUMBER with a value that is greater than or equal to 1 and less than 100:

x := DBMS_RANDOM.VALUE(1, 100);

4.14 DBMS REDACT

The DBMS_REDACT package enables the redacting or masking of data returned by a query. The DBMS_REDACT package provides a procedure to create policies, alter policies, enable policies, disable policies, and drop policies. The procedures available in the DBMS_REDACT package are listed in the following table.

Function/Procedure

```
ADD_POLICY(<object_schema>, <object_name>, <policy_name>, <policy_description>, <column_name
ALTER_POLICY(<object_schema>, <object_name>, <policy_name>, <action>, <column_name>, <funct:
DISABLE_POLICY(<object_schema>, <object_name>, <policy_name>)
ENABLE_POLICY(<object_schema,> <object_name>, <policy_name>)
DROP_POLICY(<object_schema>, <object_name>, <policy_name>)
UPDATE_FULL_REDACTION_VALUES(<number_val>, <binfloat_val>, <binfloat_val>, <binfloat_val>, <var.
```

The data redaction feature uses the DBMS_REDACT package to define policies or conditions to redact data in a column based on the table column type and redaction type.

Note that you must be the owner of the table to create or change the data redaction policies. The users are exempted from all the column redaction policies, which the table owner or super-user is by default.

Using DBMS_REDACT Constants and Function Parameters

The DBMS_REDACT package uses the constants and redacts the column data by using any one of the data redaction types. The redaction type can be decided based on the function_type parameter of dbms_redact.add_policy and dbms_redact.alter_policy procedure. The below table highlights the values for function_type parameters of dbms_redact.add_policy and dbms_redact.alter_policy.

Constant	Type	Value	Description
NONE	INTEGER	0	No redaction, zero effect on the result of a query against table.
FULL	INTEGER	1	Full redaction, redacts full values of the column data.
PARTIAL	INTEGER	2	Partial redaction, redacts a portion of the column data.
RANDOM	INTEGER	4	Random redaction, each query results in a different random value depending
REGEXP	INTEGER	5	Regular Expression based redaction, searches for the pattern of data to reda

CUSTOM INTE		Custom redaction type.	
-------------	--	------------------------	--

The following table shows the values for the action parameter of dbms_redact.alter_policy.

Constant	Type	Value	Description
ADD_COLUMN	INTEGER	1	Adds a column to the redaction policy.
DROP_COLUMN	INTEGER	2	Drops a column from the redaction policy.
MODIFY_EXPRESSION	INTEGER	3	Modifies the expression of a redaction policy. The redaction
MODIFY_COLUMN	INTEGER	4	Modifies a column in the redaction policy to change the reda
SET_POLICY_DESCRIPTION	INTEGER	5	Sets the redaction policy description.
SET_COLUMN_DESCRIPTION	INTEGER	6	Sets a description for the redaction performed on the column

The partial data redaction enables you to redact only a portion of the column data. To use partial redaction, you must set the dbms_redact.add_policy procedure function_type parameter to dbms_redact.partial and use the function_parameters parameter to specify the partial redaction behavior.

The data redaction feature provides a predefined format to configure policies that use the following datatype:

- Character
- Number
- Datetime

The following table highlights the format descriptor for partial redaction with respect to datatype. The example described below shows how to perform a redaction for a string datatype (in this scenario, a Social Security Number (SSN)), a Number datatype, and a DATE datatype.

Datatype	Format Descriptor	Description
Character	REDACT_PARTIAL_INPUT_FORMAT	Specifies the input format. Enter V for each character from t
	REDACT_PARTIAL_OUTPUT_FORMAT	Specifies the output format. Enter V for each character from
	REDACT_PARTIAL_MASKCHAR	Specifies the character to be used for redaction.
	REDACT_PARTIAL_MASKFROM	Specifies which V within the input format from which to star
	REDACT_PARTIAL_MASKTO	Specifies which V within the input format at which to end th
Number	REDACT_PARTIAL_MASKCHAR	Specifies the character to be displayed in the range between
	REDACT_PARTIAL_MASKFROM	Specifies the start digit position for redaction.
	REDACT_PARTIAL_MASKTO	Specifies the end digit position for redaction.
Datetime	REDACT_PARTIAL_DATE_MONTH	'm' redacts the month. To mask a specific month, specify 'm
	REDACT_PARTIAL_DATE_DAY	'd' redacts the day of the month. To mask with a day of the
	REDACT_PARTIAL_DATE_YEAR	'y' redacts the year. To mask with a year, append 1-9999 t
	REDACT_PARTIAL_DATE_HOUR	$^{\circ}h^{\circ}$ redacts the hour. To mask with an hour, append 0-23 t
	REDACT_PARTIAL_DATE_MINUTE	'm' redacts the minute. To mask with a minute, append $0-5$

The following table represents function_parameters values that can be used in partial redaction.

A regular expression-based redaction searches for patterns of data to redact. The regexp_pattern search the values in order for the regexp_replace_string to change the value. The following table illustrates the regexp_pattern values that you can use during REGEXP based redaction.

Function Parameter and Description	Data Type
	RE PATTERN CC L6 T4: Searches for the middle digits
	RE_PATTERN_ANY_DIGITs: Searches for any digit and
	RE_PATTERN_US_PHONE: Searches for the U.S phone
	RE_PATTERN_EMAIL_ADDRESS: Searches for the em
	RE_PATTERN_IP_ADDRESS: Searches for an IP address
	RE_PATTERN_AMEX_CCN: Searches for the American
	RE_PATTERN_CCN: Searches for the credit card number of
	RE_PATTERN_US_SSN: Searches the SSN number and re-
	RE_REDACT_CC_MIDDLE_DIGITS: Redacts the mid
	RE_REDACT_WITH_SINGLE_X: Replaces the data wi

The below table illustrates the regexp_replace_string values that you can use during REGEXP based redaction.

The following tables show the regexp_position value and regexp_occurence values that you can use during REGEXP based redaction.

Function Parameter RE_BEGINNING	Data Type INTEGER	Value 1	Description Specifies the position of a character where search must begin. By
Function Parameter	Data Type	Value	Description
RE_ALL	INTEGER	0	Specifies the replacement occurrence of a substring. If the value i
RE_FIRST	INTEGER	1	Specifies the replacement occurrence of a substring. If the value i

The following table shows the regexp_match_parameter values that you can use during REGEXP based redaction which lets you change the default matching behavior of a function.

Function Parameter	Data Type	Value	Description
RE_CASE_SENSITIVE	VARCHAR2	c'	Specifies the case-sensitive matching.

RE_CASE_INSENSITIVE	VARCHAR2	i',	Specifies the case-insensitive matching.
RE_MULTIPLE_LINES	VARCHAR2	'n,	Treats the source string as multiple lines but if you
RE_NEWLINE_WILDCARD	VARCHAR2	'n,	Specifies the period (.), but if you omit this parame
RE_IGNORE_WHITESPACE	VARCHAR2	'x'	Ignores the whitespace characters.

Note

If you create a redaction policy based on a numeric type column, then make sure that the result after redaction is a number and accordingly set the replacement string to avoid runtime errors.

Note

If you create a redaction policy based on a character type column, then make sure that a length of the result after redaction is compatible with the column type and accordingly set the replacement string to avoid runtime errors.

DBMS REDACT ADD POLICY

ADD_POLICY

The add_policy procedure creates a new data redaction policy for a table.

```
PROCEDURE add policy (
object_schema
                      IN VARCHAR2 DEFAULT NULL,
object_name
                      IN VARCHAR2,
                      IN VARCHAR2,
policy_name
policy_description
                          IN VARCHAR2 DEFAULT NULL,
column_name
                      IN VARCHAR2 DEFAULT NULL,
column_description
                          IN VARCHAR2 DEFAULT NULL,
                  IN INTEGER DEFAULT DBMS_REDACT.FULL,
function_type
                          IN VARCHAR2 DEFAULT NULL,
function_parameters
expression
                      IN VARCHAR2,
enable
                      IN BOOLEAN DEFAULT TRUE,
                          IN VARCHAR2 DEFAULT NULL,
regexp_pattern
regexp_replace_string
                          IN VARCHAR2 DEFAULT NULL,
regexp_position
                   IN INTEGER DEFAULT DBMS_REDACT.RE_BEGINNING,
regexp_occurrence IN INTEGER DEFAULT
                                       DBMS_REDACT.RE_ALL,
regexp_match_parameter
                              IN VARCHAR2 DEFAULT NULL,
custom_function_expression
                              IN VARCHAR2 DEFAULT NULL
```

Parameters

<object_schema>

Specifies the name of the schema in which the object resides and on which the data redaction policy will be applied. If you specify NULL then the given object is searched by the order specified by search_path setting.

<object_name>

Name of the table on which the data reduction policy is created.

<policy_name>

Name of the policy to be added. Ensure that the policy_name is unique for the table on which the policy is created.

<policy_description>

Specify the description of a redaction policy.

<column_name>

Name of the column to which the redaction policy applies. To redact more than one column, use the alter_policy procedure to add additional columns.

<column_description>

Description of the column to be redacted. The column_description is not supported, but if you specify the description for a column then, you will get a warning message.

<function_type>

The type of redaction function to be used. The possible values are NONE, FULL, PARTIAL, RANDOM, REGEXP, and CUSTOM.

<function_parameters>

Specifies the function parameters for the partition redaction and is applicable only for partial redaction.

<expression>

Specifies the Boolean expression for the table and determines how the policy is to be applied. The redaction occurs if this policy expression is evaluated to TRUE.

<enable>

When set to TRUE, the policy is enabled upon creation. The default is set as TRUE. When set to FALSE, the policy is disabled but the policy can be enabled by calling the enable_policy procedure.

<regexp_pattern>

Specifies the regular expression pattern to redact data. If the regexp_pattern does not match, then the NULL value is returned.

<regexp_replace_string>

Specifies the replacement string value.

<regexp_position>

Specifies the position of a character where search must begin. By default, the function parameter is RE_BEGINNING.

<regexp_occurrence>

Specifies the replacement occurrence of a substring. If the constant is RE_ALL, then the replacement of each matching substring occurs. If the constant is RE_FIRST, then the replacement of the first matching substring occurs.

<regexp_match_parameter>

```
Changes the default matching behavior of a function. The possible regexp_match_parameter constants can be 'RE_CASE_SENSITIVE', 'RE_CASE_INSENSITIVE', 'RE_MULTIPLE_LINES', 'RE_NEWLINE_WILDCARD', 'RE_IGNORE_WHITESPACE'.
```

Note

For more information on constants, function_parameters, or regexp (regular expressions) see, Using DBMS_REDACT Constants and Function Parameters.

<custom_function_expression>

The custom_function_expression is applicable only for the CUSTOM redaction type. The custom_function_expression is a function expression that is, schema-qualified function with a parameter such as schema_name.function_name (argument1, ...)that allows a user to use their redaction logic to redact the column data.

Example

The following example illustrates how to create a policy and use full redaction for values in the payment_details_tab table customer id column.

EDB-SPL Procedure successfully completed

```
edb=# CREATE USER redact_user;
CREATE ROLE
edb=# GRANT SELECT ON payment_details_tab TO redact_user;
GRANT
\c edb base_user
BEGIN
 DBMS_REDACT.add_policy(
    object_schema
                              => 'public',
                            => 'payment_details_tab',
    object_name
                            => 'redactPolicy_001',
   policy_name
   policy_description => 'redactPolicy_001 for payment_details_tab table',
    column_name
                             => 'customer_id',
                        => DBMS REDACT.full,
    function_type
                             => '1=1',
    expression
                              => TRUE);
    enable
END;
Redacted Result:
edb=# \c edb redact_user
You are now connected to database "edb" as user "redact_user".
edb=> select customer_id from payment_details_tab order by 1;
customer id
_____
          0
          0
(2 rows)
ALTER_POLICY
The alter_policy procedure alters or modifies an existing data redaction policy
for a table.
PROCEDURE alter_policy (
object_schema
                              IN VARCHAR2 DEFAULT NULL,
object_name
                              IN VARCHAR2,
policy_name
                             IN VARCHAR2,
                 IN INTEGER DEFAULT DBMS_REDACT.ADD_COLUMN,
action
column_name
                              IN VARCHAR2 DEFAULT NULL,
                              IN INTEGER DEFAULT DBMS_REDACT.FULL,
function_type
function_parameters
                          IN VARCHAR2 DEFAULT NULL,
expression
                              IN VARCHAR2 DEFAULT NULL,
                     IN VARCHAR2 DEFAULT NULL,
regexp_pattern
```

```
regexp_replace_string IN VARCHAR2 DEFAULT NULL,
regexp_position IN INTEGER DEFAULT DBMS_REDACT.RE_BEGINNING,
regexp_occurrence IN INTEGER DEFAULT DBMS_REDACT.RE_ALL,
regexp_match_parameter IN VARCHAR2 DEFAULT NULL,
policy_description IN VARCHAR2 DEFAULT NULL,
column_description IN VARCHAR2 DEFAULT NULL,
custom_function_expression IN VARCHAR2 DEFAULT NULL
)
```

Parameters

<object_schema>

Specifies the name of the schema in which the object resides and on which the data redaction policy will be altered. If you specify NULL then the given object is searched by the order specified by search_path setting.

<object_name>

Name of the table to which to alter a data redaction policy.

<policy_name>

Name of the policy to be altered.

<action>

The action to perform. For more information about action parameters see, DBMS_REDACT Constants and Function Parameters.

<column_name>

Name of the column to which the redaction policy applies.

<function_type>

The type of redaction function to be used. The possible values are NONE, FULL, PARTIAL, RANDOM, REGEXP, and CUSTOM.

<function_parameters>

Specifies the function parameters for the redaction function.

<expression>

Specifies the Boolean expression for the table and determines how the policy is to be applied. The redaction occurs if this policy expression is evaluated to TRUE.

<regexp_pattern>

Enables the use of regular expressions to redact data. If the regexp_pattern does not match the data, then the NULL value is returned.

<regexp_replace_string>

Specifies the replacement string value.

<regexp_position>

Specifies the position of a character where search must begin. By default, the function parameter is RE_BEGINNING.

<regexp_occurence>

Specifies the replacement occurrence of a substring. If the constant is RE_ALL, then the replacement of each matching substring occurs. If the constant is RE_FIRST, then the replacement of the first matching substring occurs.

<regexp_match_parameter>

Changes the default matching behavior of a function. The possible regexp_match_parameter constants can be 'RE_CASE_SENSITIVE', 'RE_CASE_INSENSITIVE', 'RE_MULTIPLE_LINES', 'RE_NEWLINE_WILDCARD', 'RE_IGNORE_WHITESPACE'.

Note

For more information on constants, function_parameters, or regexp (regular expressions) see, Using DBMS_REDACT Constants and Function Parameters.

<policy_description>

Specify the description of a redaction policy.

<column_description>

Description of the column to be redacted. The column_description is not supported, but if you specify the description for a column then, you will get a warning message.

<custom_function_expression>

The custom_function_expression is applicable only for the CUSTOM redaction type. The custom_function_expression is a function expression that is, schema-qualified function with a parameter such as schema_name.function_name (argument1, ...)that allows a user to use their redaction logic to redact the column data.

Example

The following example illustrates to alter a policy partial redaction for values in the payment_details_tab table card_string (usually a credit card number) column.

\c edb base _user

```
BEGIN
     DBMS_REDACT.alter_policy (
       object_schema
                                  => 'public',
                                  => 'payment_details_tab',
       object_name
       policy_name
                                  => 'redactPolicy_001',
                                  => DBMS_REDACT.ADD_COLUMN,
       action
                                  => 'card_string',
       column_name
                                  => DBMS_REDACT.partial,
       function_type
       function_parameters
                                  => DBMS REDACT.REDACT CCN16 F12);
   END;
Redacted Result:
edb=# \c - redact_user
You are now connected to database "edb" as user "redact user".
edb=> SELECT * FROM payment_details_tab;
customer_id |
                  card_string
-----
          0 | ****-****-1234
          0 | ****-****-2345
(2 rows)
DISABLE_POLICY
The disable_policy procedure disables an existing data reduction policy.
PROCEDURE disable_policy (
```

```
<object_schema>
                    IN VARCHAR2 DEFAULT NULL,
<object_name>
                    IN VARCHAR2,
<policy_name>
                    IN VARCHAR2
```

Parameters

```
<object_schema>
```

Specifies the name of the schema in which the object resides and on which the data redaction policy will be applied. If you specify NULL then the given object is searched by the order specified by search_path setting.

```
<object_name>
```

Name of the table for which to disable a data redaction policy.

<policy_name>

Name of the policy to be disabled.

Example

The following example illustrates how to disable a policy.

```
\c edb base_user

BEGIN

DBMS_REDACT.disable_policy(
   object_schema => 'public',
   object_name => 'payment_details_tab',
   policy_name => 'redactPolicy_001');
END;
```

Redacted Result: Data is no longer redacted after disabling a policy.

```
DBMS REDACT ENABLE POLICY
```

ENABLE_POLICY

The enable_policy procedure enables the previously disabled data redaction policy.

Parameters

```
<object_schema>
```

Specifies the name of the schema in which the object resides and on which the data redaction policy will be applied. If you specify NULL then the given object is searched by the order specified by search_path setting.

```
<object_name>
```

Name of the table to which to enable a data redaction policy.

```
<policy_name>
```

Name of the policy to be enabled.

Example

The following example illustrates how to enable a policy.

```
\c edb base_user
```

```
BEGIN
   DBMS_REDACT.enable_policy(
    object_schema => 'public',
    object_name => 'payment_details_tab',
    policy_name => 'redactPolicy_001');
END;
Redacted Result: Data is redacted after enabling a policy.
DBMS_REDACT_DROP_POLICY
```

DROP_POLICY

The drop_policy procedure drops a data redaction policy by removing the masking policy from a table.

Parameters

```
<object_schema>
```

Specifies the name of the schema in which the object resides and on which the data redaction policy will be applied. If you specify NULL then the given object is searched by the order specified by search_path setting.

```
<object_name>
```

Name of the table from which to drop a data redaction policy.

```
<policy_name>
```

Name of the policy to be dropped.

Example

The following example illustrates how to drop a policy.

```
\c edb base_user

BEGIN

DBMS_REDACT.drop_policy(
   object_schema => 'public',
   object_name => 'payment_details_tab',
   policy_name => 'redactPolicy_001');
```

Redacted Result: The server drops the specified policy.

UPDATE_FULL_REDACTION_VALUES

The update_full_redaction_values procedure updates the default displayed values for a data redaction policy and these default values can be viewed using the redaction_values_for_type_full view that use the full redaction type.

```
PROCEDURE update_full_redaction_values (
               IN NUMBER
number_val
                               DEFAULT NULL,
binfloat_val
               IN FLOAT4
                               DEFAULT NULL,
                               DEFAULT NULL,
bindouble_val IN FLOAT8
char_val
              IN CHAR
                                   DEFAULT NULL,
varchar_val
                   IN VARCHAR2
                                       DEFAULT NULL,
nchar_val
               IN NCHAR DEFAULT NULL,
nvarchar_val
              IN NVARCHAR2
                                       DEFAULT NULL,
             IN DATE
datecol_val
                                   DEFAULT NULL,
         IN TIMESTAMP
ts_val
                                   DEFAULT NULL,
tswtz_val
               IN TIMESTAMPTZ
                                       DEFAULT NULL,
blob_val
               IN BLOB
                                   DEFAULT NULL,
clob val
               IN CLOB
                                   DEFAULT NULL,
nclob_val
               IN CLOB
                                   DEFAULT NULL
```

Parameters

<number_val>

Updates the default value for columns of the NUMBER datatype.

<binfloat_val>

The FLOAT4 datatype is a random value. The binary float datatype is not supported.

 double_val>

The FLOAT8 datatype is a random value. The binary double datatype is not supported.

<char_val>

Updates the default value for columns of the CHAR datatype.

<varchar_val>

Updates the default value for columns of the VARCHAR2 datatype.

<nchar_val>

The nchar_val is mapped to CHAR datatype and returns the CHAR value.

```
<nvarchar_val>
```

The nvarchar_val is mapped to VARCHAR2 datatype and returns the VARCHAR value.

<datecol_val>

Updates the default value for columns of the DATE datatype.

<ts_val>

Updates the default value for columns of the TIMESTAMP datatype.

<tswtz_val>

Updates the default value for columns of the TIMESTAMPTZ datatype.

<blob val>

Updates the default value for columns of the BLOB datatype.

<clob_val>

Updates the default value for columns of the CLOB datatype.

<nclob_val>

The ${\tt nclob_val}$ is mapped to CLOB datatype and returns the CLOB value.

Example

The following example illustrates how to update the full redaction values but before updating the values, you can:

1. View the default values using redaction_values_for_type_full view as shown below:

```
edb=# \x
Expanded display is on.
edb=# SELECT number_value, char_value, varchar_value, date_value,
      timestamp_value, timestamp_with_time_zone_value, blob_value, clob_value
FROM redaction_values_for_type_full;
-[ RECORD 1 ]-----
number_value
                           1 0
char_value
                           varchar_value
date_value
                          | 01-JAN-01 00:00:00
                       O1-JAN-01 01:00:00
timestamp_value
timestamp_with_time_zone_value | 31-DEC-00 20:00:00 -05:00
blob_value
                     | \x5b72656461637465645d
clob_value
                           | [redacted]
(1 row)
```

2. Now, update the default values for full redaction type. The NULL values will be ignored. c edb base_user edb=# BEGIN DBMS_REDACT.update_full_redaction_values (number_val => 9999999, char_val => 'Z', varchar_val => 'V', datecol val => to date('17/10/2018', 'DD/MM/YYYY'), ts_val => to_timestamp('17/10/2018 11:12:13', 'DD/MM/YYYY HH24:MI:SS'), tswtz val => NULL, blob_val => 'NEW REDACTED VALUE', clob_val => 'NEW REDACTED VALUE'); END; 3. You can now see the updated values using redaction_values_for_type_full EDB-SPL Procedure successfully completed edb=# SELECT number_value, char_value, varchar_value, date_value, timestamp_value, timestamp_with_time_zone_value, blob_value, clob_value FROM redaction_values_for_type_full; -[RECORD 1]----number_value | 9999999 char_value ΙZ l V varchar_value | 17-0CT-18 00:00:00 date value timestamp_value | 17-0CT-18 11:12:13 timestamp_with_time_zone_value | 31-DEC-00 20:00:00 -05:00 | \x4e45572052454441435445442056414c5545 blob_value clob value | NEW REDACTED VALUE (1 row) Redacted Result: edb=# \c edb redact_user You are now connected to database "edb" as user "redact_user". edb=> select * from payment_details_tab order by 1; customer_id | card_string -----9999999 | V 9999999 | V

(2 rows)

4.15 DBMS RLS

The DBMS_RLS package enables the implementation of Virtual Private Database on certain Advanced Server database objects.

Function/Procedure

ADD_POLICY(<object_schema>, <object_name>, <policy_name>, <function_schema>, <policy_function_property(<object_schema>, <object_name>, <policy_name>)

ENABLE POLICY(<object_schema>, <object_name>, <policy_name>, <enable>)

Advanced Server's implementation of DBMS_RLS is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Virtual Private Database is a type of fine-grained access control using security policies. Fine-grained access control in Virtual Private Database means that access to data can be controlled down to specific rows as defined by the security policy.

The rules that encode a security policy are defined in a *policy function*, which is an SPL function with certain input parameters and return value. The *security policy* is the named association of the policy function to a particular database object, typically a table.

Note

In Advanced Server, the policy function can be written in any language supported by Advanced Server such as SQL, PL/pgSQL and SPL.

Note

The database objects currently supported by Advanced Server Virtual Private Database are tables. Policies cannot be applied to views or synonyms.

The advantages of using Virtual Private Database are the following:

- Provides a fine-grained level of security. Database object level privileges
 given by the GRANT command determine access privileges to the entire
 instance of a database object, while Virtual Private Database provides
 access control for the individual rows of a database object instance.
- A different security policy can be applied depending upon the type of SQL command (INSERT, UPDATE, DELETE, or SELECT).
- The security policy can vary dynamically for each applicable SQL command affecting the database object depending upon factors such as the session user of the application accessing the database object.
- Invocation of the security policy is transparent to all applications that access the database object and thus, individual applications do not have to be modified to apply the security policy.

- Once a security policy is enabled, it is not possible for any application (including new applications) to circumvent the security policy except by the system privilege noted by the following.
- Even superusers cannot circumvent the security policy except by the system privilege noted by the following.

Note

The only way security policies can be circumvented is if the EXEMPT ACCESS POLICY system privilege has been granted to a user. The EXEMPT ACCESS POLICY privilege should be granted with extreme care as a user with this privilege is exempted from all policies in the database.

The DBMS_RLS package provides procedures to create policies, remove policies, enable policies, and disable policies.

The process for implementing Virtual Private Database is as follows:

- Create a policy function. The function must have two input parameters of type VARCHAR2. The first input parameter is for the schema containing the database object to which the policy is to apply and the second input parameter is for the name of that database object. The function must have a VARCHAR2 return type. The function must return a string in the form of a WHERE clause predicate. This predicate is dynamically appended as an AND condition to the SQL command that acts upon the database object. Thus, rows that do not satisfy the policy function predicate are filtered out from the SQL command result set.
- Use the ADD_POLICY procedure to define a new policy, which is the association of a policy function with a database object. With the ADD_POLICY procedure, you can also specify the types of SQL commands (INSERT, UPDATE, DELETE, or SELECT) to which the policy is to apply, whether or not to enable the policy at the time of its creation, and if the policy should apply to newly inserted rows or the modified image of updated rows.
- Use the ENABLE POLICY procedure to disable or enable an existing policy.
- Use the DROP_POLICY procedure to remove an existing policy. The DROP_POLICY procedure does not drop the policy function or the associated database object.

Once policies are created, they can be viewed in the catalog views, compatible with Oracle databases: ALL_POLICIES, DBA_POLICIES, or USER_POLICIES. The supported compatible views are listed in the *Database Compatibility for Oracle Developers Reference Guide*, available at the EnterpriseDB website at:

https://www.enterprisedb.com/edb-docs/

The SYS_CONTEXT function is often used with DBMS_RLS. The signature is:

SYS_CONTEXT(<namespace>, <attribute>)

Where:

<namespace> is a VARCHAR2; the only accepted value is USERENV. Any
other value will return NULL.

<attribute> is a VARCHAR2. <attribute> may be:

attribute Value	Equivalent Value
SESSION_USER CURRENT_USER CURRENT_SCHEMA HOST IP_ADDRESS SERVER_HOST	pg_catalog.session_user pg_catalog.current_user pg_catalog.current_schema pg_catalog.inet_host pg_catalog.inet_client_addr pg_catalog.inet_server_addr

Note

The examples used to illustrate the DBMS_RLS package are based on a modified copy of the sample emp table provided with Advanced Server along with a role named salesmgr that is granted all privileges on the table. You can create the modified copy of the emp table named vpemp and the salesmgr role as shown by the following:

```
CREATE TABLE public.vpemp AS SELECT empno, ename, job, sal, comm, deptno FROM emp; ALTER TABLE vpemp ADD authid VARCHAR2(12);
UPDATE vpemp SET authid = 'researchmgr' WHERE deptno = 20;
UPDATE vpemp SET authid = 'salesmgr' WHERE deptno = 30;
SELECT * FROM vpemp;
```

empno ename		job	١.	sal	١.	comm	dept	no	authid
7782 CLARK	1	MANAGER	-+·	2450.00	-+		·+	10	+
7839 KING	i	PRESIDENT	i	5000.00			i	10	I
7934 MILLER	I	CLERK	1	1300.00			1	10	I
7369 SMITH	1	CLERK	1	800.00				20	researchmgr
7566 JONES		MANAGER		2975.00			1	20	researchmgr
7788 SCOTT		ANALYST		3000.00			1	20	researchmgr
7876 ADAMS		CLERK		1100.00			1	20	researchmgr
7902 FORD		ANALYST		3000.00			1	20	researchmgr
7499 ALLEN		SALESMAN		1600.00		300.00	1	30	salesmgr
7521 WARD		SALESMAN	-	1250.00		500.00	1	30	salesmgr
7654 MARTIN		SALESMAN		1250.00		1400.00	1	30	salesmgr
7698 BLAKE		MANAGER		2850.00			1	30	salesmgr
7844 TURNER		SALESMAN		1500.00		0.00	1	30	salesmgr
7900 JAMES	1	CLERK	-	950.00				30	salesmgr
(14 rows)									

CREATE ROLE salesmgr WITH LOGIN PASSWORD 'password';

```
GRANT ALL ON vpemp TO salesmgr; DBMS RLSADD POLICY:
```

ADD_POLICY

The ADD_POLICY procedure creates a new policy by associating a policy function with a database object.

You must be a superuser to execute this procedure.

```
ADD_POLICY(<object_schema> VARCHAR2, <object_name> VARCHAR2,
```

<policy_name> VARCHAR2, <function_schema>
VARCHAR2,

<policy_function> VARCHAR2

- [, <statement_types> VARCHAR2
- [, <update_check> BOOLEAN
- [, <enable> BOOLEAN
- [, <static_policy> BOOLEAN
- [, <policy_type> INTEGER
- [, <long_predicate> BOOLEAN
- [, <sec_relevant_cols> VARCHAR2
- [, <sec_relevant_cols_opt> INTEGER]]]]]]])

Parameters

<object schema>

Name of the schema containing the database object to which the policy is to be applied.

<object_name>

Name of the database object to which the policy is to be applied. A given database object may have more than one policy applied to it.

<policy_name>

Name assigned to the policy. The combination of database object (identified by <object_schema> and <object_name>) and policy name must be unique within the database.

<function_schema>

Name of the schema containing the policy function.

Note

The policy function may belong to a package in which case <function_schema> must contain the name of the schema in which the package is defined.

<policy_function>

Name of the SPL function that defines the rules of the security policy. The same function may be specified in more than one policy.

Note

The policy function may belong to a package in which case <policy_function> must also contain the package name in dot notation (that is, <package_name>.<function_name>).

<statement_types>

Comma-separated list of SQL commands to which the policy applies. Valid SQL commands are INSERT, UPDATE, DELETE, and SELECT. The default is INSERT, UPDATE, DELETE, SELECT.

Note

Advanced Server accepts INDEX as a statement type, but it is ignored. Policies are not applied to index operations in Advanced Server.

<update_check>

Applies to INSERT and UPDATE SQL commands only.

When set to TRUE, the policy is applied to newly inserted rows and to the modified image of updated rows. If any of the new or modified rows do not qualify according to the policy function predicate, then the INSERT or UPDATE command throws an exception and no rows are inserted or modified by the INSERT or UPDATE command.

When set to FALSE, the policy is not applied to newly inserted rows or the modified image of updated rows. Thus, a newly inserted row may not appear in the result set of a subsequent SQL command that invokes the same policy. Similarly, rows which qualified according to the policy prior to an UPDATE command may not appear in the result set of a subsequent SQL command that invokes the same policy.

The default is FALSE.

<enable>

When set to TRUE, the policy is enabled and applied to the SQL commands given by the <statement_types> parameter. When set to FALSE the policy is disabled and not applied to any SQL commands. The policy can be enabled using the ENABLE_POLICY procedure. The default is TRUE.

<static_policy>

In Oracle, when set to TRUE, the policy is *static*, which means the policy function is evaluated once per database object the first time it is invoked by a policy on that database object. The resulting policy function predicate string is saved in memory and reused for all invocations of that policy on that database object while the database server instance is running.

When set to FALSE, the policy is *dynamic*, which means the policy function is re-evaluated and the policy function predicate string regenerated for all invocations of the policy.

The default is FALSE.

Note

In Oracle 10g, the <policy_type> parameter was introduced, which is intended to replace the <static_policy> parameter. In Oracle, if the <policy_type> parameter is not set to its default value of NULL, the <policy_type> parameter setting overrides the <static_policy> setting.

Note

The setting of <static_policy> is ignored by Advanced Server. Advanced Server implements only the dynamic policy, regardless of the setting of the <static_policy> parameter.

<policy_type>

In Oracle, determines when the policy function is re-evaluated, and hence, if and when the predicate string returned by the policy function changes. The default is NULL.

Note

The setting of this parameter is ignored by Advanced Server. Advanced Server always assumes a dynamic policy.

<long_predicate>

In Oracle, allows predicates up to 32K bytes if set to TRUE, otherwise predicates are limited to 4000 bytes. The default is FALSE.

Note

The setting of this parameter is ignored by Advanced Server. An Advanced Server policy function can return a predicate of unlimited length for all practical purposes.

<sec_relevant_cols>

Comma-separated list of columns of <object_name>. Provides column-level Virtual Private Database for the listed columns. The policy is enforced if any of the listed columns are referenced in a SQL command of a type listed in <statement_types>. The policy is not enforced if no such columns are referenced.

The default is NULL, which has the same effect as if all of the database object's columns were included in <sec_relevant_cols>.

```
<sec_relevant_cols_opt>
```

In Oracle, if <sec_relevant_cols_opt> is set to DBMS_RLS.ALL_ROWS (INTEGER constant of value 1), then the columns listed in <sec_relevant_cols> return NULL on all rows where the applied policy predicate is false. (If <sec_relevant_cols_opt> is not set to DBMS_RLS.ALL_ROWS, these rows would not be returned at all in the result set.) The default is NULL.

Note

Advanced Server does not support the DBMS_RLS.ALL_ROWS functionality. Advanced Server throws an error if sec_relevant_cols_opt is set to DBMS_RLS.ALL_ROWS (INTEGER value of 1).

Examples

This example uses the following policy function:

This function generates the predicate authid = SYS_CONTEXT('USERENV', 'SESSION_USER'), which is added to the WHERE clause of any SQL command of the type specified in the ADD_POLICY procedure.

This limits the effect of the SQL command to those rows where the content of the authid column is the same as the session user.

Note

This example uses the SYS_CONTEXT function to return the login user name. In Oracle the SYS_CONTEXT function is used to return attributes of an *application context*. The first parameter of the SYS_CONTEXT function is the name of an application context while the second parameter is the name of an attribute set within the application context. USERENV is a special built-in namespace that

describes the current session. Advanced Server does not support application contexts, but only this specific usage of the SYS_CONTEXT function.

The following anonymous block calls the ADD_POLICY procedure to create a policy named secure_update to be applied to the vpemp table using function verify_session_user whenever an INSERT, UPDATE, or DELETE SQL command is given referencing the vpemp table.

DECLARE

```
v_object_schema
                            VARCHAR2(30) := 'public';
    v_object_name
                            VARCHAR2(30) := 'vpemp';
    v_policy_name
                            VARCHAR2(30) := 'secure_update';
    v_function_schema
                            VARCHAR2(30) := 'enterprisedb';
    v_policy_function
                            VARCHAR2(30) := 'verify_session_user';
                            VARCHAR2(30) := 'INSERT, UPDATE, DELETE';
   v statement types
                            BOOLEAN := TRUE:
    v_update_check
                                         := TRUE;
    v_enable
                            BOOLEAN
BEGIN
   DBMS_RLS.ADD_POLICY(
        v_object_schema,
        v_object_name,
        v_policy_name,
        v_function_schema,
        v_policy_function,
        v_statement_types,
        v_update_check,
        v enable
    );
END:
```

After successful creation of the policy, a terminal session is started by user salesmgr. The following query shows the content of the vpemp table:

```
edb=# \c edb salesmgr
Password for user salesmgr:
```

You are now connected to database "edb" as user "salesmgr". edb=> SELECT * FROM vpemp;

empno	I	ename	1	job	I	sal	1	comm	dep	tno	authid
7782 7839 7934 7369 7566 7788 7876	+	CLARK KING MILLER SMITH JONES SCOTT ADAMS FORD	- +	MANAGER PRESIDENT CLERK CLERK MANAGER ANALYST CLERK ANALYST	- +- 	2450.00 5000.00 1300.00 800.00 2975.00 3000.00 1100.00 3000.00	+-		+ 	10 10 10 20 20 20 20 20	researchmgr researchmgr researchmgr
7499	i	ALLEN	i	SALESMAN	i	1600.00	i	300.00	İ	30	salesmgr

```
7521 | WARD
                | SALESMAN
                           | 1250.00 | 500.00 |
                                                      30 | salesmgr
                            | 1250.00 | 1400.00 |
 7654 | MARTIN | SALESMAN
                                                      30 | salesmgr
 7698 | BLAKE
              | MANAGER
                            | 2850.00 |
                                                      30 | salesmgr
 7844 | TURNER | SALESMAN
                           | 1500.00 |
                                           0.00 |
                                                      30 | salesmgr
 7900 | JAMES | CLERK
                              950.00 l
                                                      30 | salesmgr
(14 rows)
```

An unqualified UPDATE command (no WHERE clause) is issued by the salesmgr user:

```
edb=> UPDATE vpemp SET comm = sal * .75;
UPDATE 6
```

Instead of updating all rows in the table, the policy restricts the effect of the update to only those rows where the authid column contains the value salesmgr as specified by the policy function predicate authid = SYS_CONTEXT('USERENV', 'SESSION_USER').

The following query shows that the comm column has been changed only for those rows where authid contains salesmgr. All other rows are unchanged.

edb=> SELECT * FROM vpemp;

empno	١	ename		job	١	sal	I	comm	١	deptno	authid
	+-		+-		-+-		+-		+		+
7782	1	CLARK		MANAGER		2450.00				10	
7839	1	KING		PRESIDENT		5000.00	1			10	
7934	1	MILLER	1	CLERK	1	1300.00	1		1	10	
7369	1	SMITH	1	CLERK	1	800.00	1		1	20	researchmgr
7566	1	JONES	Ι	MANAGER	Ι	2975.00	١		١	20	researchmgr
7788	1	SCOTT	1	ANALYST	1	3000.00	I		1	20	researchmgr
7876	1	ADAMS	1	CLERK	1	1100.00	1		1	20	researchmgr
7902	1	FORD	1	ANALYST	1	3000.00	1		1	20	researchmgr
7499	1	ALLEN	1	SALESMAN	1	1600.00	1	1200.00	1	30	salesmgr
7521	1	WARD	Ι	SALESMAN	Ι	1250.00	١	937.50	١	30	salesmgr
7654	1	MARTIN	Ι	SALESMAN	Ι	1250.00	١	937.50	١	30	salesmgr
7698	1	BLAKE	1	MANAGER	1	2850.00	1	2137.50	1	30	salesmgr
7844	1	TURNER	Ι	SALESMAN	Ι	1500.00	١	1125.00	١	30	salesmgr
7900	1	JAMES	Ι	CLERK	Ι	950.00	I	712.50	١	30	salesmgr
(14 row	s))									

Furthermore, since the <update_check> parameter was set to TRUE in the ADD_POLICY procedure, the following INSERT command throws an exception since the value given for the authid column, researchmgr, does not match the session user, which is salesmgr, and hence, fails the policy.

```
edb=> INSERT INTO vpemp VALUES (9001, 'SMITH', 'ANALYST', 3200.00, NULL, 20, 'researchmgr'); ERROR: policy with check option violation
```

DETAIL: Policy predicate was evaluated to FALSE with the updated values

If <update_check> was set to FALSE, the preceding INSERT command would have succeeded.

The following example illustrates the use of the <code>sec_relevant_cols></code> parameter to apply a policy only when certain columns are referenced in the SQL command. The following policy function is used for this example, which selects rows where the employee salary is less than 2000.

The policy is created so that it is enforced only if a SELECT command includes columns sal or comm:

DECLARE

```
{\tt v\_object\_schema}
                             VARCHAR2(30) := 'public';
                             VARCHAR2(30) := 'vpemp';
    v_object_name
                             VARCHAR2(30) := 'secure_salary';
    v_policy_name
                            VARCHAR2(30) := 'enterprisedb';
    v_function_schema
                            VARCHAR2(30) := 'sal_lt_2000';
    v_policy_function
    v_statement_types
                             VARCHAR2(30) := 'SELECT';
    v_sec_relevant_cols
                             VARCHAR2(30) := 'sal,comm';
BEGIN
    DBMS_RLS.ADD_POLICY(
        v_object_schema,
        v object name,
        v_policy_name,
        v function schema,
        v_policy_function,
        v_statement_types,
        sec_relevant_cols => v_sec_relevant_cols
    );
END;
```

If a query does not reference columns sal or comm, then the policy is not applied. The following query returns all 14 rows of table vpemp:

```
10 |
 7934 | MILLER | CLERK
 7369 | SMITH
                                  20 | researchmgr
               | CLERK
 7566 | JONES
                | MANAGER
                                  20 | researchmgr
 7788 | SCOTT
                | ANALYST
                                  20 | researchmgr
 7876 | ADAMS
                | CLERK
                                  20 | researchmgr
 7902 | FORD
                                  20 | researchmgr
                | ANALYST
 7499 | ALLEN
                | SALESMAN
                                  30 | salesmgr
 7521 | WARD
                | SALESMAN
                                  30 | salesmgr
 7654 | MARTIN | SALESMAN
                                  30 | salesmgr
 7698 | BLAKE
              | MANAGER
                                  30 | salesmgr
 7844 | TURNER | SALESMAN
                            1
                                  30 | salesmgr
 7900 | JAMES
               | CLERK
                            1
                                  30 | salesmgr
(14 rows)
```

If the query references the sal or comm columns, then the policy is applied to the query eliminating any rows where sal is greater than or equal to 2000 as shown by the following:

edb=# SELECT empno, enam	e, job, sal,	comm, deptno	, authid FROM vpemp;
empno ename job	sal	comm c	leptno authid
	+	-+	
7934 MILLER CLERK	1300.00	1	10
7369 SMITH CLERK	800.00	1	20 researchmgr
7876 ADAMS CLERK	1100.00	1	20 researchmgr
7499 ALLEN SALESM	AN 1600.00	1200.00	30 salesmgr
7521 WARD SALESM	AN 1250.00	937.50	30 salesmgr
7654 MARTIN SALESM	AN 1250.00	937.50	30 salesmgr
7844 TURNER SALESM	AN 1500.00	1125.00	30 salesmgr
7900 JAMES CLERK	950.00	712.50	30 salesmgr
(8 rows)			

DBMS_RLS_DROP_POLICY

DROP_POLICY

The DROP_POLICY procedure deletes an existing policy. The policy function and database object associated with the policy are not deleted by the DROP_POLICY procedure.

You must be a superuser to execute this procedure.

```
DROP_POLICY(<object_schema> VARCHAR2, <object_name>
VARCHAR2,
```

<policy_name> VARCHAR2)

Parameters

<object_schema>

Name of the schema containing the database object to which the policy applies.

```
<object_name>
```

Name of the database object to which the policy applies.

```
<policy_name>
```

Name of the policy to be deleted.

Examples

The following example deletes policy secure_update on table public.vpemp:

DECLARE

ENABLE_POLICY

The ENABLE_POLICY procedure enables or disables an existing policy on the specified database object.

You must be a superuser to execute this procedure.

```
ENABLE_POLICY(<object_schema> VARCHAR2, <object_name>
VARCHAR2,
<policy_name> VARCHAR2, <enable> BOOLEAN)
```

Parameters

```
<object_schema>
```

Name of the schema containing the database object to which the policy applies.

```
<object_name>
```

Name of the database object to which the policy applies.

```
<policy_name>
```

Name of the policy to be enabled or disabled.

<enable>

When set to TRUE, the policy is enabled. When set to FALSE, the policy is disabled.

Examples

The following example disables policy secure_update on table public.vpemp:

```
DECLARE
                             VARCHAR2(30) := 'public';
    v_object_schema
    v_object_name
                             VARCHAR2(30) := 'vpemp';
    v_policy_name
                             VARCHAR2(30) := 'secure_update';
                             BOOLEAN := FALSE;
    v_enable
BEGIN
    DBMS RLS.ENABLE POLICY(
        v_object_schema,
        v_object_name,
        v_policy_name,
        v_{enable}
    );
END;
```

4.16.1 DBMS SCHEDULER

The DBMS_SCHEDULER package provides a way to create and manage Oracle-styled jobs, programs and job schedules. The DBMS_SCHEDULER package implements the following functions and procedures:

```
Function/Procedure
CREATE JOB(<job name>, <job type>, <job action>, <number of arguments>, <start date>, <re
CREATE_JOB(<job_name>, , , <schedule_name>, <job_class>, <enabled>, <auto_dr</pre>
CREATE PROGRAM(cprogram name>, cprogram action>, <number of argument
CREATE_SCHEDULE( <schedule_name>, <start_date>, <repeat_interval>, <end_date>, <comments>
\label{lem:define_program_name} DEFINE\_PROGRAM\_ARGUMENT(\ program\_name>, <argument\_position>, <argument\_name>, <argume
DEFINE_PROGRAM_ARGUMENT( cprogram_name>, <argument_position>, <argument_name>
DISABLE(<name>, <force>, <commit_semantics>)
DROP_JOB(<job_name>, <force>, <defer>, <commit_semantics>)
DROP_PROGRAM(program_name>, <force>)
DROP_PROGRAM_ARGUMENT( cprogram_name>, <argument_position>)
DROP_PROGRAM_ARGUMENT( cprogram_name>, <argument_name>)
DROP_SCHEDULE(<schedule_name>, <force>)
ENABLE(<name>, <commit semantics>)
EVALUATE _CALENDAR_STRING( <calendar_string>, <start_date>, <return_date_after>, <next_ru
RUN_JOB(<job_name>, <use_current_session>, <manually>)
SET_JOB_ARGUMENT_VALUE( < job_name>, < argument_position>, < argument_value>)
```

Advanced Server's implementation of DBMS_SCHEDULER is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The DBMS_SCHEDULER package is dependent on the pgAgent service; you must have a pgAgent service installed and running on your server before using DBMS_SCHEDULER.

Before using DBMS_SCHEDULER, a database superuser must create the catalog tables in which the DBMS_SCHEDULER programs, schedules and jobs are stored. Use the psql client to connect to the database, and invoke the command:

CREATE EXTENSION dbms_scheduler;

By default, the dbms_scheduler extension resides in the contrib/dbms_scheduler_ext subdirectory (under the Advanced Server installation).

Note that after creating the DBMS_SCHEDULER tables, only a superuser will be able to perform a dump or reload of the database.

using_calendar_syntax_to_specify_a_repeating_interval create_job create_program create_schedule define_program_argument dbms_scheduler_disable drop_job drop_program drop_program_argument drop_schedule dbms_scheduler_enable evaluate calendar string run job set job argument value

4.16.2 'Using Calendar Syntax to Specify a Repeating Interval'

The CREATE_JOB and CREATE_SCHEDULE procedures use Oracle-styled calendar syntax to define the interval with which a job or schedule is repeated. You should provide the scheduling information in the <repeat_interval> parameter of each procedure.

<repeat_interval> is a value (or series of values) that define the interval between the executions of the scheduled job. Each value is composed of a token,
followed by an equal sign, followed by the unit (or units) on which the schedule
will execute. Multiple token values must be separated by a semi-colon (;).

For example, the following value:

FREQ=DAILY; BYDAY=MON, TUE, WED, THU, FRI; BYHOUR=17; BYMINUTE=45

Defines a schedule that is executed each weeknight at 5:45.

The token types and syntax described in the table below are supported by Advanced Server:

4.16.3 CREATE_JOB

Use the CREATE_JOB procedure to create a job. The procedure comes in two forms; the first form of the procedure specifies a schedule within the job definition, as well as a job action that will be invoked when the job executes:

The second form uses a job schedule to specify the schedule on which the job will execute, and specifies the name of a program that will execute when the job runs:

```
create_job(
<job_name> IN VARCHAR2,
cprogram_name> IN VARCHAR2,
<schedule_name> IN VARCHAR2,
<job_class> IN VARCHAR2 DEFAULT 'DEFAULT_JOB_CLASS',
<enabled> IN BOOLEAN DEFAULT FALSE,
<auto_drop> IN BOOLEAN DEFAULT TRUE,
<comments> IN VARCHAR2 DEFAULT NULL)
```

Parameters

<job_ame>

<job_name> specifies the optionally schema-qualified name of the
job being created.

<job_type>

<job_type> specifies the type of job. The current implementation of CREATE_JOB supports a job type of PLSQL_BLOCK or STORED_PROCEDURE.

<job_action>

If <job_type> is PLSQL_BLOCK, <job_action> specifies the content of the PL/SQL block that will be invoked when the job executes.

The block must be terminated with a semi-colon (;).

If <job_type> is STORED_PROCEDURE, <job_action> specifies the optionally schema-qualified name of the procedure.

<number_of_arguments>

<number_of_arguments> is an INTEGER value that specifies the number of arguments expected by the job. The default is 0.

<start date>

<start_date> is a TIMESTAMP WITH TIME ZONE value that specifies
the first time that the job is scheduled to execute. The default value
is NULL, indicating that the job should be scheduled to execute when
the job is enabled.

<repeat_interval>

<repeat_interval> is a VARCHAR2 value that specifies how often
the job will repeat. If a <repeat_interval> is not specified, the job
will execute only once. The default value is NULL.

<end_date>

<end_date> is a TIMESTAMP WITH TIME ZONE value that specifies a
time after which the job will no longer execute. If a date is specified,
the <end_date> must be after <start_date>. The default value is
NULL.

Please note that if an <end_date> is not specified and a <repeat_interval> is specified, the job will repeat indefinitely until it is disabled.

cprogram_name>

program_name> is the name of a program that will be executed by
the job.

<schedule_name>

<schedule_name> is the name of the schedule associated with the job.

<job_class>

<job_class> is accepted for compatibility and ignored.

<enabled>

<enabled> is a BOOLEAN value that specifies if the job is enabled when created. By default, a job is created in a disabled
state, with <enabled> set to FALSE. To enable a job, specify a
value of TRUE when creating the job, or enable the job with the
DBMS_SCHEDULER.ENABLE procedure.

<auto_drop>

The <auto_drop> parameter is accepted for compatibility and is ignored. By default, a job's status will be changed to DISABLED after the time specified in <end_date>.

<comments>

Use the <comments> parameter to specify a comment about the job.

Example

The following example demonstrates a call to the CREATE JOB procedure:

EXEC

The code fragment creates a job named update_log that executes each weeknight at 5:00. The job executes a PL/SQL block that inserts the current timestamp into a logfile (my_log). Since no end_date is specified, the job will execute until it is disabled by the DBMS SCHEDULER.DISABLE procedure.

4.16.4 CREATE PROGRAM

Use the CREATE_PROGRAM procedure to create a DBMS_SCHEDULER program. The signature is:

Parameters

cprogram_name>

am_name> specifies the name of the program that is being
created.

cprogram_type>

cprogram_action>

If cprogram_type> is PLSQL_BLOCK, cprogram_action> contains
the PL/SQL block that will execute when the program is invoked.
The PL/SQL block must be terminated with a semi-colon (;).

If is PROCEDURE, contains the
 name of the stored procedure.

<number_of_arguments>

If is PLSQL_BLOCK, this argument is ignored.

If is PROCEDURE, <number_of_arguments> specifies
 the number of arguments required by the procedure. The default
 value is 0.

<enabled>

<enabled> specifies if the program is created enabled or disabled:

- If <enabled> is TRUE, the program is created enabled.
- If <enabled> is FALSE, the program is created disabled; use the DBMS_SCHEDULER.ENABLE program to enable a disabled program.

The default value is FALSE.

<comments>

Use the <comments> parameter to specify a comment about the program; by default, this parameter is NULL.

Example

The following call to the CREATE_PROGRAM procedure creates a program named update_log:

EXEC

```
DBMS_SCHEDULER.CREATE_PROGRAM (    program_name => 'update_log',
    program_type => 'PLSQL_BLOCK',
    program_action => 'BEGIN INSERT INTO my_log VALUES(current_timestamp); END;',
    enabled => TRUE,
    comment => 'This program adds a row to the my_log table.');
```

update_log is a PL/SQL block that adds a row containing the current date and time to the my_log table. The program will be enabled when the CREATE_PROGRAM procedure executes.

4.16.5 CREATE_SCHEDULE

Use the CREATE_SCHEDULE procedure to create a job schedule. The signature of the CREATE_SCHEDULE procedure is:

Parameters

<schedule name>

<schedule_name> specifies the name of the schedule.

<start_date>

<start_date> is a TIMESTAMP WITH TIME ZONE value that specifies the date and time that the schedule is eligible to execute. If
a <start_date> is not specified, the date that the job is enabled is
used as the <start_date>. By default, <start_date> is NULL.

<repeat_interval>

<repeat_interval> is a VARCHAR2 value that specifies how often
the job will repeat. If a <repeat_interval> is not specified, the job
will execute only once, on the date specified by <start_date>.

Note

You must provide a value for either <start_date> or <repeat_interval>; if both <start_date> and <repeat_interval> are NULL, the server will return an error.

<end_date> IN TIMESTAMP WITH TIME ZONE DEFAULT NULL

<end_date> is a TIMESTAMP WITH TIME ZONE value that specifies a
time after which the schedule will no longer execute. If a date is
specified, the <end_date> must be after the <start_date>. The
default value is NULL.

Please note that if a <repeat_interval> is specified and an <end_date> is not specified, the schedule will repeat indefinitely until it is disabled.

<comments> IN VARCHAR2 DEFAULT NULL)

Use the <comments> parameter to specify a comment about the schedule; by default, this parameter is NULL.

Example

The following code fragment calls $\texttt{CREATE_SCHEDULE}$ to create a schedule named weeknights at 5:

EXEC

The schedule executes each weeknight, at 5:00 pm, effective after June 1, 2013. Since no end_date is specified, the schedule will execute indefinitely until it is disabled with DBMS_SCHEDULER.DISABLE.

4.16.6 DEFINE_PROGRAM_ARGUMENT

Use the DEFINE_PROGRAM_ARGUMENT procedure to define a program argument. The DEFINE_PROGRAM_ARGUMENT procedure comes in two forms; the first form defines an argument with a default value:

The second form defines an argument without a default value:

Parameters

```
cprogram_name>
```

rogram_name> is the name of the program to which the arguments
belong.

```
<argument_position>
```

<argument_position> specifies the position of the argument as it is passed to the program.

<argument_name>

<argument_name> specifies the optional name of the argument. By
default, <argument_name> is NULL.

```
<argument_type> IN VARCHAR2
```

<argument_type> specifies the data type of the argument.

```
<default value>
```

<default_value> specifies the default value assigned to the argument. <default_value> will be overridden by a value specified by
the job when the job executes.

```
<out_argument> IN BOOLEAN DEFAULT FALSE
```

<out_argument> is not currently used; if specified, the value must
be FALSE.

Example

The following code fragment uses the DEFINE_PROGRAM_ARGUMENT procedure to define the first and second arguments in a program named add_emp:

EXEC

```
DBMS_SCHEDULER.DEFINE_PROGRAM_ARGUMENT(
   program_name => 'add_emp',
   argument_position => 1,
   argument_name => 'dept_no',
   argument_type
                      => 'INTEGER,
   default_value
                      => '20');
EXEC
 DBMS SCHEDULER.DEFINE PROGRAM ARGUMENT(
   program_name => 'add_emp',
                      => 2,
   argument_position
   argument_name => 'emp_name',
                      => 'VARCHAR2');
   argument_type
```

The first argument is an INTEGER value nameddept_no that has a default value of 20. The second argument is a VARCHAR2 value named emp_name; the second argument does not have a default value.

4.16.7 **DISABLE**

Use the DISABLE procedure to disable a program or a job. The signature of the DISABLE procedure is:

```
DISABLE(
<name> IN VARCHAR2,
<force> IN BOOLEAN DEFAULT FALSE,
<commit_semantics> IN VARCHAR2 DEFAULT 'STOP_ON_FIRST_ERROR')
```

Parameters

<name>

<name> specifies the name of the program or job that is being disabled.

<force>

<force> is accepted for compatibility, and ignored.

<commit semantics>

<commit_semantics> instructs the server how to handle an error encountered while disabling a program or job. By default,
<commit_semantics> is set to STOP_ON_FIRST_ERROR, instructing
the server to stop when it encounters an error. Any programs
or jobs that were successfully disabled prior to the error will be
committed to disk.

The TRANSACTIONAL and ABSORB_ERRORS keywords are accepted for compatibility, and ignored.

Example

The following call to the DISABLE procedure disables a program named update_emp:

```
DBMS_SCHEDULER.DISABLE('update_emp');
```

4.16.8 DROP_JOB

Use the DROP_JOB procedure to DROP a job, DROP any arguments that belong to the job, and eliminate any future job executions. The signature of the procedure is:

```
DROP_JOB(
<job_name> IN VARCHAR2,
<force> IN BOOLEAN DEFAULT FALSE,
<defer> IN BOOLEAN DEFAULT FALSE,
<commit_semantics> IN VARCHAR2 DEFAULT 'STOP_ON_FIRST_ERROR')
```

Parameters

```
<job_name>
```

<job_name> specifies the name of the job that is being dropped.

<force>

<force> is accepted for compatibility, and ignored.

<defer>

<defer> is accepted for compatibility, and ignored.

<commit_semantics>

<commit_semantics> instructs the server how to handle an error encountered while dropping a program or job. By default,
<commit_semantics> is set to STOP_ON_FIRST_ERROR, instructing
the server to stop when it encounters an error.

The TRANSACTIONAL and ABSORB_ERRORS keywords are accepted for compatibility, and ignored.

Example

The following call to ${\tt DROP_JOB}$ drops a job named ${\tt update_log:}$

DBMS_SCHEDULER.DROP_JOB('update_log');

4.16.9 DROP PROGRAM

The $\mathtt{DROP_PROGRAM}$ procedure

The signature of the DROP_PROGRAM procedure is:

Parameters

cprogram_name>

cprogram_name> specifies the name of the program that is being
dropped.

<force>

<force> is a BOOLEAN value that instructs the server how to handle programs with dependent jobs.

Specify FALSE to instruct the server to return an error if the program is referenced by a job.

Specify TRUE to instruct the server to disable any jobs that reference the program before dropping the program.

The default value is FALSE.

Example

The following call to DROP_PROGRAM drops a job named update_emp: DBMS_SCHEDULER.DROP_PROGRAM('update_emp');

4.16.10 DROP_PROGRAM_ARGUMENT

Use the DROP_PROGRAM_ARGUMENT procedure to drop a program argument. The DROP_PROGRAM_ARGUMENT procedure comes in two forms; the first form uses an argument position to specify which argument to drop:

```
drop_program_argument(
cargument_position> IN PLS_INTEGER)
```

The second form takes the argument name:

```
drop_program_argument(
cprogram_name> IN VARCHAR2,
<argument_name> IN VARCHAR2)
```

Parameters

```
program_name>
```

cprogram_name> specifies the name of the program that is being
modified.

```
<argument_position>
```

<argument_position> specifies the position of the argument that is being dropped.

```
<argument_name>
```

<argument_name> specifies the name of the argument that is being dropped.

Examples

The following call to DROP_PROGRAM_ARGUMENT drops the first argument in the update_emp program:

```
DBMS_SCHEDULER.DROP_PROGRAM_ARGUMENT('update_emp', 1);
```

The following call to $\mathtt{DROP_PROGRAM_ARGUMENT}$ drops an argument named $\mathtt{emp_name}$:

```
DBMS_SCHEDULER.DROP_PROGRAM_ARGUMENT(update_emp', 'emp_name');
```

4.16.11 DROP SCHEDULE

Use the DROP SCHEDULE procedure to drop a schedule. The signature is:

```
DROP_SCHEDULE(
<schedule_name IN VARCHAR2,
<force> IN BOOLEAN DEFAULT FALSE)
```

Parameters

<schedule name>

<schedule_name> specifies the name of the schedule that is being dropped.

<force>

<force> specifies the behavior of the server if the specified schedule is referenced by any job:

- Specify FALSE to instruct the server to return an error if the specified schedule is referenced by a job. This is the default behavior.
- Specify TRUE to instruct the server to disable to any jobs that
 use the specified schedule before dropping the schedule. Any
 running jobs will be allowed to complete before the schedule is
 dropped.

Example

The following call to DROP_SCHEDULE drops a schedule named weeknights_at_5: DBMS_SCHEDULER.DROP_SCHEDULE('weeknights_at_5', TRUE);

The server will disable any jobs that use the schedule before dropping the schedule.

4.16.12 ENABLE

Use the ENABLE procedure to enable a disabled program or job.

The signature of the ENABLE procedure is:

```
ENABLE(
<name> IN VARCHAR2,
<commit_semantics> IN VARCHAR2 DEFAULT 'STOP_ON_FIRST_ERROR')
```

Parameters

<name>

<name> specifies the name of the program or job that is being enabled.

<commit_semantics>

<commit_semantics> instructs the server how to handle an error encountered while enabling a program or job. By default,
<commit_semantics> is set to STOP_ON_FIRST_ERROR, instructing
the server to stop when it encounters an error.

The TRANSACTIONAL and ABSORB_ERRORS keywords are accepted for compatibility, and ignored.

Example

The following call to DBMS_SCHEDULER.ENABLE enables the update_emp program:

DBMS_SCHEDULER.ENABLE('update_emp');

4.16.13 EVALUATE CALENDAR STRING

Use the EVALUATE_CALENDAR_STRING procedure to evaluate the <repeat_interval> value specified when creating a schedule with the CREATE_SCHEDULE procedure. The EVALUATE_CALENDAR_STRING procedure will return the date and time that a specified schedule will execute without actually scheduling the job.

The signature of the EVALUATE_CALENDAR_STRING procedure is:

```
evaluate_calendar_string(
<calendar_string> IN VARCHAR2,
<start_date> IN TIMESTAMP WITH TIME ZONE,
<return_date_after> IN TIMESTAMP WITH TIME ZONE,
<next_run_date> OUT TIMESTAMP WITH TIME ZONE)
```

Parameters

<calendar_string>

<calendar_string> is the calendar string that describes a
<repeat_interval> that is being evaluated.

<start_date> IN TIMESTAMP WITH TIME ZONE

<start_date> is the date and time after which the <repeat_interval>
will become valid.

<return_date_after>

Use the <return_date_after parameter> to specify the date and time that EVALUATE_CALENDAR_STRING should use as a starting date when evaluating the <repeat_interval>.

For example, if you specify a <return_date_after> value of O1-APR-13 09.00.00.000000, EVALUATE_CALENDAR_STRING will

return the date and time of the first iteration of the schedule after April 1st, 2013.

```
<next_run_date OUT TIMESTAMP WITH TIME ZONE</pre>
```

<next_run_date> is an OUT parameter that will contain the
first occurrence of the schedule after the date specified by the
<return_date_after> parameter.

Example

The following example evaluates a calendar string and returns the first date and time that the schedule will be executed after June 15, 2013:

```
DECLARE
  result    TIMESTAMP;
BEGIN

DBMS_SCHEDULER.EVALUATE_CALENDAR_STRING
  (
    'FREQ=DAILY;BYDAY=MON,TUE,WED,THU,FRI;BYHOUR=17;',
    '15-JUN-2013', NULL, result
);

DBMS_OUTPUT.PUT_LINE('next_run_date: ' || result);
END;
//
next_run_date: 17-JUN-13 05.00.00.000000 PM
```

June 15, 2013 is a Saturday; the schedule will not execute until Monday, June 17, 2013 at 5:00 pm.

4.16.14 RUN_JOB

Use the RUN_JOB procedure to execute a job immediately. The signature of the RUN_JOB procedure is:

```
run_job(
<job_name> IN VARCHAR2,
<use_current_session> IN BOOLEAN DEFAULT TRUE
```

Parameters

```
<job_name>
     <job_name> specifies the name of the job that will execute.
<use_current_session>
```

By default, the job will execute in the current session. If specified, <use_current_session> must be set to TRUE; if <use_current_session> is set to FALSE, Advanced Server will return an error.

Example

The following call to RUN_JOB executes a job named update_log:

```
DBMS_SCHEDULER.RUN_JOB('update_log', TRUE);
```

Passing a value of TRUE as the second argument instructs the server to invoke the job in the current session.

4.16.15 SET_JOB_ARGUMENT_VALUE

Use the SET_JOB_ARGUMENT_VALUE procedure to specify a value for an argument. The SET_JOB_ARGUMENT_VALUE procedure comes in two forms; the first form specifies which argument should be modified by position:

```
set_job_argument_value(
<job_name> IN VARCHAR2,
<argument_position> IN PLS_INTEGER,
<argument_value> IN VARCHAR2)
```

The second form uses an argument name to specify which argument to modify:

```
set_job_argument_value(
<job_name> IN VARCHAR2,
<argument_name> IN VARCHAR2,
<argument_value> IN VARCHAR2)
```

Argument values set by the SET_JOB_ARGUMENT_VALUE procedure override any values set by default.

Parameters

<job_name>

<job_name> specifies the name of the job to which the modified
argument belongs.

<argument_position>

Use <argument_position> to specify the argument position for which the value will be set.

<argument_name>

Use <argument_name> to specify the argument by name for which the value will be set.

```
<argument_value>
```

<argument_value> specifies the new value of the argument.

Examples

The following example assigns a value of 30 to the first argument in the update_emp job:

```
DBMS_SCHEDULER.SET_JOB_ARGUMENT_VALUE('update_emp', 1, '30');
```

The following example sets the emp_name argument to SMITH:

```
DBMS_SCHEDULER.SET_JOB_ARGUMENT_VALUE('update_emp', 'emp_name',
'SMITH');
```

4.17 DBMS_SESSION

Advanced Server provides support for the following DBMS_SESSION.SET_ROLE procedure:

Function/Procedure	Return Type	Description
$SET_ROLE(< role_cmd >)$	n/a	Executes a SET ROLE statement followed by the string value s

Advanced Server's implementation of DBMS_SESSION is a partial implementation when compared to Oracle's version. Only DBMS_SESSION.SET_ROLE is supported.

SET_ROLE

The SET_ROLE procedure sets the current session user to the role specified in <role_cmd>. After invoking the SET_ROLE procedure, the current session will use the permissions assigned to the specified role. The signature of the procedure is:

```
SET_ROLE(<role_cmd>)
```

The SET_ROLE procedure appends the value specified for <role_cmd> to the SET ROLE statement, and then invokes the statement.

Parameters

<role_cmd>

<role_cmd> specifies a role name in the form of a string value.

Example

The following call to the SET_ROLE procedure invokes the SET_ROLE command to set the identity of the current session user to manager:

```
edb=# exec DBMS_SESSION.SET_ROLE('manager');
```

4.18.1 DBMS SQL

The DBMS_SQL package provides an application interface compatible with Oracle databases to the EnterpriseDB dynamic SQL functionality. With DBMS_SQL you can construct queries and other commands at run time (rather than when you write the application). EnterpriseDB Advanced Server offers native support for dynamic SQL; DBMS_SQL provides a way to use dynamic SQL in a fashion compatible with Oracle databases without modifying your application.

DBMS_SQL assumes the privileges of the current user when executing dynamic SQL statements.

```
Function/Procedure
                                                                                         Function
BIND_VARIABLE(c, name, value [, out_value_size ])
                                                                                         Proced
BIND_VARIABLE_CHAR(c, name, value [, out_value_size ])
                                                                                         Proced
BIND_VARIABLE_RAW(c, name, value [, out_value_size])
                                                                                         Proced
CLOSE CURSOR(c IN OUT)
                                                                                         Proced
COLUMN_VALUE(c, position, value OUT [, column_error OUT [, actual_length OUT ]])
                                                                                         Proced
COLUMN_VALUE_CHAR(c, position, value OUT [, column_error OUT [, actual_length OUT ]])
                                                                                         Proced
COLUMN_VALUE_RAW(c, position, value OUT [, column_error OUT [, actual_length OUT ]])
                                                                                         Proced
DEFINE_COLUMN(c, position, column [, column_size])
                                                                                         Proced
DEFINE COLUMN CHAR(c, position, column, column size)
                                                                                         Proced
DEFINE COLUMN RAW(c, position, column, column size)
                                                                                         Proced
DESCRIBE COLUMNS
                                                                                         Proced
EXECUTE(c)
                                                                                         Function
EXECUTE AND FETCH(c [, exact ])
                                                                                         Function
FETCH_ROWS(c)
                                                                                         Function
IS OPEN(c)
                                                                                         Function
LAST ROW COUNT
                                                                                         Function
OPEN CURSOR
                                                                                         Function
PARSE(c, statement, language_flag)
                                                                                         Proced
```

Advanced Server's implementation of DBMS_SQL is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The following table lists the public variable available in the DBMS_SQL package.

Public Variables	Data Type	Value	Description
native	INTEGER	1	Provided for compatibility with Oracle syntax. See DBMS_SQL.PA
V6	INTEGER	2	Provided for compatibility with Oracle syntax. See DBMS_SQL.PA
V7	INTEGER	3	Provided for compatibility with Oracle syntax. See DBMS_SQL.PA

bind_variable bind_variable_char bind_variable_raw close_cursor column_value column_value_char column_value_raw define_column define_column_char define_column_raw describe_columns execute execute and fetch fetch rows is open last row count open cursor parse

4.18.2 BIND VARIABLE

The BIND_VARIABLE procedure provides the capability to associate a value with an IN or IN OUT bind variable in a SQL command.

Parameters

<c>

Cursor ID of the cursor for the SQL command with bind variables.

<name>

Name of the bind variable in the SQL command.

<value>

Value to be assigned.

```
<out_value_size>
```

If <name> is an IN OUT variable, defines the maximum length of the output value. If not specified, the length of <value> is assumed.

Examples

The following anonymous block uses bind variables to insert a row into the emp table.

DECLARE

```
v_hiredate
                    emp.hiredate%TYPE;
                    emp.sal%TYPE;
    v_sal
    v_{comm}
                    emp.comm%TYPE;
                    emp.deptno%TYPE;
    v_deptno
   v_status
                    INTEGER;
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
    DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
               := 9001;
    v empno
               := 'JONES';
    v_ename
               := 'SALESMAN';
    v_job
               := 7369;
   v_mgr
    v_hiredate := TO_DATE('13-DEC-07','DD-MON-YY');
             := 8500.00;
    v_comm
               := 1500.00;
   v deptno := 40;
    DBMS_SQL.BIND_VARIABLE(curid,':p_empno',v_empno);
   DBMS_SQL.BIND_VARIABLE(curid,':p_ename',v_ename);
    DBMS_SQL.BIND_VARIABLE(curid,':p_job',v_job);
    DBMS_SQL.BIND_VARIABLE(curid,':p_mgr',v_mgr);
   DBMS_SQL.BIND_VARIABLE(curid,':p_hiredate',v_hiredate);
    DBMS_SQL.BIND_VARIABLE(curid,':p_sal',v_sal);
    DBMS_SQL.BIND_VARIABLE(curid, ':p_comm', v_comm);
    DBMS_SQL.BIND_VARIABLE(curid,':p_deptno',v_deptno);
    v_status := DBMS_SQL.EXECUTE(curid);
   DBMS OUTPUT.PUT LINE('Number of rows processed: ' | | v status);
    DBMS_SQL.CLOSE_CURSOR(curid);
END:
Number of rows processed: 1
```

4.18.3 BIND VARIABLE CHAR

[, <out_value_size> INTEGER])

The BIND_VARIABLE_CHAR procedure provides the capability to associate a CHAR value with an IN or IN OUT bind variable in a SQL command.

```
BIND_VARIABLE_CHAR(<c> INTEGER, <name> VARCHAR2, <value> CHAR
```

Parameters

<c>

Cursor ID of the cursor for the SQL command with bind variables.

<name>

Name of the bind variable in the SQL command.

<value>

Value of type CHAR to be assigned.

<out_value_size>

If <name> is an IN OUT variable, defines the maximum length of the output value. If not specified, the length of <value> is assumed.

4.18.4 BIND VARIABLE RAW

The BIND_VARIABLE_RAW procedure provides the capability to associate a RAW value with an IN or IN OUT bind variable in a SQL command.

```
BIND_VARIABLE_RAW(<c> INTEGER, <name> VARCHAR2, <value> RAW
```

```
[, <out_value_size> INTEGER ])
```

Parameters

<c>

Cursor ID of the cursor for the SQL command with bind variables.

<name>

Name of the bind variable in the SQL command.

<value>

Value of type RAW to be assigned.

<out_value_size>

If <name> is an IN OUT variable, defines the maximum length of the output value. If not specified, the length of <value> is assumed.

4.18.5 CLOSE_CURSOR

The CLOSE_CURSOR procedure closes an open cursor. The resources allocated to the cursor are released and it can no longer be used.

```
CLOSE_CURSOR(<c> IN OUT INTEGER)
```

Parameters

<c>

Cursor ID of the cursor to be closed.

Examples

The following example closes a previously opened cursor:

4.18.6 COLUMN_VALUE

The COLUMN_VALUE procedure defines a variable to receive a value from a cursor.

Parameters

<c>

Cursor id of the cursor returning data to the variable being defined.

<position>

Position within the cursor of the returned data. The first value in the cursor is position 1.

<value>

Variable receiving the data returned in the cursor by a prior fetch call.

<column_error>

Error number associated with the column, if any.

<actual_length>

Actual length of the data prior to any truncation.

Examples

The following example shows the portion of an anonymous block that receives the values from a cursor using the COLUMN_VALUE procedure.

```
DECLARE
    curid
                    INTEGER;
                    NUMBER(4);
    v_empno
                    VARCHAR2(10);
    v_{ename}
    v hiredate
                    DATE;
                    NUMBER(7,2);
    v_sal
    v_comm
                    NUMBER(7,2);
                    VARCHAR2(50) := 'SELECT empno, ename, hiredate, sal, ' ||
    v_sql
                                     'comm FROM emp';
    v status
                    INTEGER;
BEGIN
   LOOP
        v_status := DBMS_SQL.FETCH_ROWS(curid);
        EXIT WHEN v_status = 0;
        DBMS_SQL.COLUMN_VALUE(curid,1,v_empno);
        DBMS_SQL.COLUMN_VALUE(curid,2,v_ename);
        DBMS_SQL.COLUMN_VALUE(curid,3,v_hiredate);
        DBMS_SQL.COLUMN_VALUE(curid,4,v_sal);
        DBMS_SQL.COLUMN_VALUE(curid,4,v_sal);
        DBMS_SQL.COLUMN_VALUE(curid,5,v_comm);
        DBMS_OUTPUT.PUT_LINE(v_empno || ' ' || RPAD(v_ename,10) || ' ' ||
            TO_CHAR(v_hiredate,'yyyy-mm-dd') || ' ' ||
            TO_CHAR(v_sal,'9,999.99') || ' ' ||
            TO_CHAR(NVL(v_comm,0),'9,999.99'));
   END LOOP;
    DBMS_SQL.CLOSE_CURSOR(curid);
END;
```

4.18.7 COLUMN_VALUE_CHAR

The COLUMN_VALUE_CHAR procedure defines a variable to receive a CHAR value from a cursor.

```
[, <column_error> OUT NUMBER [, <actual_length> OUT
INTEGER ]])
```

Parameters

<c>

Cursor id of the cursor returning data to the variable being defined.

<position>

Position within the cursor of the returned data. The first value in the cursor is position 1.

<value>

Variable of data type CHAR receiving the data returned in the cursor by a prior fetch call.

<column_error>

Error number associated with the column, if any.

<actual_length>

Actual length of the data prior to any truncation.

4.18.8 COLUMN_VALUE_RAW

The COLUMN_VALUE_RAW procedure defines a variable to receive a RAW value from a cursor.

 ${\tt COLUMN_VALUE_RAW(<c>\ INTEGER,\ <position>\ INTEGER,\ <value>\ OUT\ RAW}$

[, <column_error> OUT NUMBER [, <actual_length> OUT INTEGER]])

Parameters

<c>

Cursor id of the cursor returning data to the variable being defined.

<position>

Position within the cursor of the returned data. The first value in the cursor is position 1.

<value>

Variable of data type RAW receiving the data returned in the cursor by a prior fetch call.

<column_error>

Error number associated with the column, if any.

<actual_length>

Actual length of the data prior to any truncation.

4.18.9 DEFINE_COLUMN

The DEFINE_COLUMN procedure defines a column or expression in the SELECT list that is to be returned and retrieved in a cursor.

```
DEFINE_COLUMN(<c> INTEGER, <position> INTEGER, <column> { BLOB |
    CLOB | DATE | FLOAT | INTEGER | NUMBER | TIMESTAMP |
    VARCHAR2 }
    [, <column_size> INTEGER ])
```

Parameters

<c>

Cursor id of the cursor associated with the SELECT command.

<position>

Position of the column or expression in the SELECT list that is being defined.

<column>

<column_size>

The maximum length of the returned data. <column_size> must be specified only if <column> is VARCHAR2. Returned data exceeding <column_size> is truncated to <column_size> characters.

Examples

The following shows how the empno, ename, hiredate, sal, and comm columns of the emp table are defined with the DEFINE_COLUMN procedure.

DECLARE

```
curid
                     INTEGER;
    v_empno
                    NUMBER(4);
                    VARCHAR2(10);
    v_{ename}
    v_hiredate
                    DATE;
    v_sal
                    NUMBER(7,2);
    v_comm
                    NUMBER(7,2);
                    VARCHAR2(50) := 'SELECT empno, ename, hiredate, sal, ' ||
    v_sql
                                      'comm FROM emp';
    v_status
                    INTEGER;
BEGIN
```

```
curid := DBMS_SQL.OPEN_CURSOR;
DBMS_SQL.PARSE(curid,v_sql,DBMS_SQL.native);
DBMS_SQL.DEFINE_COLUMN(curid,1,v_empno);
DBMS_SQL.DEFINE_COLUMN(curid,2,v_ename,10);
DBMS_SQL.DEFINE_COLUMN(curid,3,v_hiredate);
DBMS_SQL.DEFINE_COLUMN(curid,4,v_sal);
DBMS_SQL.DEFINE_COLUMN(curid,5,v_comm);
...
...
END;
```

The following shows an alternative to the prior example that produces the exact same results. Note that the lengths of the data types are irrelevant — the empno, sal, and comm columns will still return data equivalent to NUMBER(4) and NUMBER(7,2), respectively, even though v_num is defined as NUMBER(1) (assuming the declarations in the COLUMN_VALUE procedure are of the appropriate maximum sizes). The ename column will return data up to ten characters in length as defined by the <length> parameter in the DEFINE_COLUMN call, not by the data type declaration, VARCHAR2(1) declared for v_varchar. The actual size of the returned data is dictated by the COLUMN_VALUE procedure.

```
DECLARE
```

```
INTEGER;
    curid
    v_num
                    NUMBER(1);
    v_varchar
                    VARCHAR2(1);
    v_date
                    DATE;
                    VARCHAR2(50) := 'SELECT empno, ename, hiredate, sal, ' ||
    v_sql
                                     'comm FROM emp';
    v_status
                    INTEGER;
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
    DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
    DBMS SQL.DEFINE COLUMN(curid,1,v num);
    DBMS_SQL.DEFINE_COLUMN(curid,2,v_varchar,10);
    DBMS_SQL.DEFINE_COLUMN(curid,3,v_date);
    DBMS_SQL.DEFINE_COLUMN(curid,4,v_num);
    DBMS_SQL.DEFINE_COLUMN(curid,5,v_num);
END;
```

4.18.10 DEFINE_COLUMN_CHAR

The DEFINE_COLUMN_CHAR procedure defines a CHAR column or expression in the SELECT list that is to be returned and retrieved in a cursor.

DEFINE_COLUMN_CHAR(<c> INTEGER, <position> INTEGER,
<column> CHAR, <column_size> INTEGER)

Parameters

<c>

Cursor id of the cursor associated with the SELECT command.

<position>

Position of the column or expression in the SELECT list that is being defined.

<column>

A CHAR variable.

<column_size>

The maximum length of the returned data. Returned data exceeding <column_size> is truncated to <column_size> characters.

4.18.11 DEFINE_COLUMN_RAW

The DEFINE_COLUMN_RAW procedure defines a RAW column or expression in the SELECT list that is to be returned and retrieved in a cursor.

```
DEFINE_COLUMN_RAW(<c> INTEGER, <position> INTEGER, <column> RAW,
```

<column_size> INTEGER)

Parameters

<c>

Cursor id of the cursor associated with the SELECT command.

<position>

Position of the column or expression in the SELECT list that is being defined.

<column>

A RAW variable.

<column_size>

The maximum length of the returned data. Returned data exceeding <column_size> is truncated to <column_size> characters.

4.18.12 DESCRIBE COLUMNS

The DESCRIBE_COLUMNS procedure describes the columns returned by a cursor.

DESCRIBE_COLUMNS(c INTEGER, col_cnt OUT INTEGER, desc_t OUT DESC_TAB);

Parameters

<c>

The cursor ID of the cursor.

<col_cnt>

The number of columns in cursor result set.

<desc_tab>

The table that contains a description of each column returned by the cursor. The descriptions are of type DESC_REC, and contain the following values:

Column Name	Type
col_type	INTEGER
col_max_len	INTEGER
col_name	VARCHAR2(128)
col_name_len	INTEGER
col_schema_name	VARCHAR2(128)
col_schema_name_len	INTEGER
col_precision	INTEGER
col_scale	INTEGER
col_charsetid	INTEGER
col_charsetform	INTEGER
col_null_ok	BOOLEAN

4.18.13 EXECUTE

The EXECUTE function executes a parsed SQL command or SPL block.

<status> INTEGER EXECUTE(<c> INTEGER)

Parameters

<c>

Cursor ID of the parsed SQL command or SPL block to be executed.

<status>

Number of rows processed if the SQL command was DELETE, INSERT, or UPDATE. <status> is meaningless for all other commands.

Examples

The following anonymous block inserts a row into the dept table.

DECLARE

```
curid INTEGER;
v_sql VARCHAR2(50);
v_status INTEGER;

BEGIN
curid := DBMS_SQL.OPEN_CURSOR;
v_sql := 'INSERT INTO dept VALUES (50, ''HR'', ''LOS ANGELES'')';
DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
v_status := DBMS_SQL.EXECUTE(curid);
DBMS_OUTPUT.PUT_LINE('Number of rows processed: ' || v_status);
DBMS_SQL.CLOSE_CURSOR(curid);
END;
```

4.18.14 EXECUTE AND FETCH

Function EXECUTE_AND_FETCH executes a parsed SELECT command and fetches one row.

```
<status> INTEGER EXECUTE_AND_FETCH(<c> INTEGER
[, <exact> BOOLEAN ])
```

Parameters

<c>

Cursor id of the cursor for the SELECT command to be executed.

<exact>

If set to TRUE, an exception is thrown if the number of rows in the result set is not exactly equal to 1. If set to FALSE, no exception is thrown. The default is FALSE. A NO_DATA_FOUND exception is thrown if <exact> is TRUE and there are no rows in the result set. A TOO_MANY_ROWS exception is thrown if <exact> is TRUE and there is more than one row in the result set.

<status>

Returns 1 if a row was successfully fetched, 0 if no rows to fetch. If an exception is thrown, no value is returned.

Examples

The following stored procedure uses the EXECUTE_AND_FETCH function to retrieve one employee using the employee's name. An exception will be thrown if the employee is not found, or there is more than one employee with the same name.

```
CREATE OR REPLACE PROCEDURE select_by_name(
   p_ename
                    emp.ename%TYPE
)
IS
    curid
                    INTEGER;
    v_empno
                    emp.empno%TYPE;
    v hiredate
                    emp.hiredate%TYPE;
    v_sal
                    emp.sal%TYPE;
    v_{comm}
                    emp.comm%TYPE;
    v_{dname}
                    dept.dname%TYPE;
   v_disp_date
                    VARCHAR2(10);
                    VARCHAR2(120) := 'SELECT empno, hiredate, sal, ' ||
   v_sql
                                      'NVL(comm, 0), dname ' ||
                                      'FROM emp e, dept d ' ||
                                      'WHERE ename = :p_ename ' ||
                                      'AND e.deptno = d.deptno';
    v status
                    INTEGER;
BEGIN
    curid := DBMS SQL.OPEN CURSOR;
    DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
    DBMS_SQL.BIND_VARIABLE(curid,':p_ename',UPPER(p_ename));
    DBMS_SQL.DEFINE_COLUMN(curid,1,v_empno);
   DBMS_SQL.DEFINE_COLUMN(curid,2,v_hiredate);
    DBMS SQL.DEFINE COLUMN(curid,3,v sal);
   DBMS_SQL.DEFINE_COLUMN(curid,4,v_comm);
    DBMS_SQL.DEFINE_COLUMN(curid,5,v_dname,14);
    v_status := DBMS_SQL.EXECUTE_AND_FETCH(curid,TRUE);
    DBMS_SQL.COLUMN_VALUE(curid,1,v_empno);
    DBMS_SQL.COLUMN_VALUE(curid,2,v_hiredate);
    DBMS_SQL.COLUMN_VALUE(curid,3,v_sal);
    DBMS_SQL.COLUMN_VALUE(curid,4,v_comm);
    DBMS_SQL.COLUMN_VALUE(curid,5,v_dname);
    v_disp_date := TO_CHAR(v_hiredate, 'MM/DD/YYYY');
    DBMS OUTPUT.PUT LINE('Number
                                  : ' || v empno);
                                    : ' || UPPER(p ename));
   DBMS OUTPUT.PUT LINE('Name
    DBMS_OUTPUT.PUT_LINE('Hire Date : ' || v_disp_date);
    DBMS_OUTPUT.PUT_LINE('Salary
                                  : ' || v_sal);
```

```
DBMS_OUTPUT.PUT_LINE('Commission: ' || v_comm);
    DBMS_OUTPUT.PUT_LINE('Department: ' || v_dname);
    DBMS_SQL.CLOSE_CURSOR(curid);
EXCEPTION
   WHEN NO_DATA_FOUND THEN
        DBMS_OUTPUT.PUT_LINE('Employee ' || p_ename || ' not found');
        DBMS_SQL.CLOSE_CURSOR(curid);
   WHEN TOO_MANY_ROWS THEN
        DBMS_OUTPUT.PUT_LINE('Too many employees named, ' ||
            p_ename || ', found');
        DBMS_SQL.CLOSE_CURSOR(curid);
    WHEN OTHERS THEN
        DBMS_OUTPUT.PUT_LINE('The following is SQLERRM:');
        DBMS OUTPUT.PUT LINE(SQLERRM);
        DBMS_OUTPUT.PUT_LINE('The following is SQLCODE:');
        DBMS OUTPUT.PUT LINE(SQLCODE);
        DBMS_SQL.CLOSE_CURSOR(curid);
END;
EXEC select_by_name('MARTIN')
Number
          : 7654
Name
          : MARTIN
Hire Date : 09/28/1981
Salary: 1250
Commission: 1400
Department: SALES
```

4.18.15 FETCH_ROWS

The FETCH_ROWS function retrieves a row from a cursor.

```
<status> INTEGER FETCH_ROWS(<c> INTEGER)
```

Parameters

<c>

Cursor ID of the cursor from which to fetch a row.

<status>

Returns ${\tt 1}$ if a row was successfully fetched, ${\tt 0}$ if no more rows to fetch.

Examples

The following examples fetches the rows from the emp table and displays the results.

```
DECLARE
   curid
                  INTEGER;
   v_empno
                  NUMBER(4);
   v_{\mathtt{ename}}
                  VARCHAR2(10);
   v_hiredate
                  DATE;
   v sal
                  NUMBER(7,2);
                  NUMBER(7,2);
   v_comm
   v_sql
                  VARCHAR2(50) := 'SELECT empno, ename, hiredate, sal, ' ||
                                  'comm FROM emp';
   v_status
                  INTEGER;
BEGIN
   curid := DBMS SQL.OPEN CURSOR;
   DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
   DBMS_SQL.DEFINE_COLUMN(curid,1,v_empno);
   DBMS_SQL.DEFINE_COLUMN(curid,2,v_ename,10);
   DBMS_SQL.DEFINE_COLUMN(curid,3,v_hiredate);
   DBMS_SQL.DEFINE_COLUMN(curid,4,v_sal);
   DBMS_SQL.DEFINE_COLUMN(curid,5,v_comm);
   v_status := DBMS_SQL.EXECUTE(curid);
   DBMS_OUTPUT.PUT_LINE('EMPNO ENAME
                                          HIREDATE
                                                      SAL
                                                                COMM');
   DBMS_OUTPUT.PUT_LINE('---- ------
                                                      ----- ' ||
       '----');
   LOOP
       v status := DBMS SQL.FETCH ROWS(curid);
       EXIT WHEN v_status = 0;
       DBMS_SQL.COLUMN_VALUE(curid,1,v_empno);
       DBMS_SQL.COLUMN_VALUE(curid,2,v_ename);
       DBMS_SQL.COLUMN_VALUE(curid,3,v_hiredate);
       DBMS_SQL.COLUMN_VALUE(curid,4,v_sal);
       DBMS_SQL.COLUMN_VALUE(curid,4,v_sal);
       DBMS_SQL.COLUMN_VALUE(curid,5,v_comm);
       DBMS_OUTPUT.PUT_LINE(v_empno || ' ' || RPAD(v_ename,10) || ' ' ||
           TO_CHAR(v_hiredate,'yyyy-mm-dd') || ' ' ||
           TO_CHAR(v_sal,'9,999.99') || ' ' ||
           TO_CHAR(NVL(v_comm,0),'9,999.99'));
   END LOOP;
   DBMS_SQL.CLOSE_CURSOR(curid);
END;
EMPNO ENAME
              HIREDATE
                                       COMM
                             SAI.
----- ------
                1980-12-17 800.00
7369
      SMITH
                                            .00
```

7499	ALLEN	1981-02-20	1,600.00	300.00
7521	WARD	1981-02-22	1,250.00	500.00
7566	JONES	1981-04-02	2,975.00	.00
7654	MARTIN	1981-09-28	1,250.00	1,400.00
7698	BLAKE	1981-05-01	2,850.00	.00
7782	CLARK	1981-06-09	2,450.00	.00
7788	SCOTT	1987-04-19	3,000.00	.00
7839	KING	1981-11-17	5,000.00	.00
7844	TURNER	1981-09-08	1,500.00	.00
7876	ADAMS	1987-05-23	1,100.00	.00
7900	JAMES	1981-12-03	950.00	.00
7902	FORD	1981-12-03	3,000.00	.00
7934	MILLER	1982-01-23	1,300.00	.00

4.18.16 IS_OPEN

The IS_OPEN function provides the capability to test if the given cursor is open.

<status> BOOLEAN IS_OPEN(<c> INTEGER)

Parameters

<c>

Cursor ID of the cursor to be tested.

<status>

Set to TRUE if the cursor is open, set to FALSE if the cursor is not open.

$4.18.17~LAST_ROW_COUNT$

The LAST_ROW_COUNT function returns the number of rows that have been currently fetched.

<rowcnt> INTEGER LAST_ROW_COUNT

Parameters

<rowcnt>

Number of row fetched thus far.

Examples

The following example uses the LAST_ROW_COUNT function to display the total number of rows fetched in the query.

```
DECLARE
                   INTEGER;
   curid
                   NUMBER(4);
   v_{empno}
   v_{ename}
                   VARCHAR2(10);
   v_hiredate
                   DATE;
                   NUMBER(7,2);
   v_sal
                   NUMBER(7,2);
   v\_{comm}
                   VARCHAR2(50) := 'SELECT empno, ename, hiredate, sal, ' ||
   v_sql
                                    'comm FROM emp';
                   INTEGER;
   v_status
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
   DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
   DBMS SQL.DEFINE COLUMN(curid,1,v empno);
   DBMS_SQL.DEFINE_COLUMN(curid,2,v_ename,10);
   DBMS_SQL.DEFINE_COLUMN(curid,3,v_hiredate);
   DBMS_SQL.DEFINE_COLUMN(curid,4,v_sal);
   DBMS_SQL.DEFINE_COLUMN(curid,5,v_comm);
   v_status := DBMS_SQL.EXECUTE(curid);
   DBMS_OUTPUT.PUT_LINE('EMPNO ENAME
                                            HIREDATE
                                                        SAL
                                                                  COMM');
    DBMS_OUTPUT.PUT_LINE('---- ------
                                                        ----- ' ||
        '----');
   LOOP
       v_status := DBMS_SQL.FETCH_ROWS(curid);
       EXIT WHEN v_status = 0;
       DBMS_SQL.COLUMN_VALUE(curid,1,v_empno);
       DBMS_SQL.COLUMN_VALUE(curid,2,v_ename);
       DBMS_SQL.COLUMN_VALUE(curid,3,v_hiredate);
       DBMS_SQL.COLUMN_VALUE(curid,4,v_sal);
       DBMS_SQL.COLUMN_VALUE(curid,4,v_sal);
       DBMS_SQL.COLUMN_VALUE(curid,5,v_comm);
       DBMS_OUTPUT.PUT_LINE(v_empno || ' ' || RPAD(v_ename,10) || ' ' ||
           TO_CHAR(v_hiredate,'yyyy-mm-dd') || ' ' ||
           TO_CHAR(v_sal,'9,999.99') || ' ' ||
           TO_CHAR(NVL(v_comm,0),'9,999.99'));
   DBMS_OUTPUT.PUT_LINE('Number of rows: ' || DBMS_SQL.LAST_ROW_COUNT);
   DBMS_SQL.CLOSE_CURSOR(curid);
END;
EMPNO ENAME
                 HIREDATE
                              SAL
                                        COMM
                                          .00
7369
      SMITH
                1980-12-17 800.00
     ALLEN 1981-02-20 1,600.00
WARD 1981-02-22 1,250.00
7499
                                          300.00
7521
                                          500.00
```

```
7566
       JONES
                    1981-04-02
                                 2,975.00
                                                  .00
7654
       MARTIN
                    1981-09-28
                                 1,250.00
                                            1,400.00
7698
       BLAKE
                    1981-05-01
                                 2,850.00
                                                  .00
7782
       CLARK
                    1981-06-09
                                 2,450.00
                                                  .00
7788
       SCOTT
                    1987-04-19
                                 3,000.00
                                                  .00
                                 5,000.00
7839
       KING
                    1981-11-17
                                                  .00
       TURNER
                    1981-09-08
                                 1,500.00
7844
                                                  .00
7876
       ADAMS
                    1987-05-23
                                 1,100.00
                                                  .00
7900
       JAMES
                    1981-12-03
                                   950.00
                                                  .00
7902
       FORD
                    1981-12-03
                                 3,000.00
                                                  .00
7934
       MILLER
                                 1,300.00
                    1982-01-23
                                                  .00
Number of rows: 14
```

.......

4.18.18 OPEN_CURSOR

The OPEN_CURSOR function creates a new cursor. A cursor must be used to parse and execute any dynamic SQL statement. Once a cursor has been opened, it can be re-used with the same or different SQL statements. The cursor does not have to be closed and re-opened in order to be re-used.

```
<c> INTEGER OPEN_CURSOR
```

Parameters

<c>

Cursor ID number associated with the newly created cursor.

Examples

The following example creates a new cursor:

4.18.19 PARSE

The PARSE procedure parses a SQL command or SPL block. If the SQL command is a DDL command, it is immediately executed and does not require running the EXECUTE function.

```
PARSE(<c> INTEGER, <statement> VARCHAR2, <language_flag> INTEGER)
```

Parameters

<c>

Cursor ID of an open cursor.

<statement>

SQL command or SPL block to be parsed. A SQL command must not end with the semi-colon terminator, however an SPL block does require the semi-colon terminator.

<language_flag>

Language flag provided for compatibility with Oracle syntax. Use DBMS_SQL.V6, DBMS_SQL.V7 or DBMS_SQL.native. This flag is ignored, and all syntax is assumed to be in EnterpriseDB Advanced Server form.

Examples

The following anonymous block creates a table named, job. Note that DDL statements are executed immediately by the PARSE procedure and do not require a separate EXECUTE step.

```
DECLARE
    curid
                    INTEGER;
BEGIN
    curid := DBMS SQL.OPEN CURSOR;
    DBMS_SQL.PARSE(curid, 'CREATE TABLE job (jobno NUMBER(3), ' ||
        'jname VARCHAR2(9))', DBMS_SQL.native);
    DBMS_SQL.CLOSE_CURSOR(curid);
END;
The following inserts two rows into the job table.
DECLARE
    curid
                    INTEGER;
    v_sql
                    VARCHAR2(50);
    v_status
                    INTEGER;
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
    v_sql := 'INSERT INTO job VALUES (100, ''ANALYST'')';
    DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
    v_status := DBMS_SQL.EXECUTE(curid);
    DBMS_OUTPUT.PUT_LINE('Number of rows processed: ' || v_status);
    v_sql := 'INSERT INTO job VALUES (200, ''CLERK'')';
    DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
    v_status := DBMS_SQL.EXECUTE(curid);
```

```
DBMS_OUTPUT.PUT_LINE('Number of rows processed: ' || v_status);
    DBMS_SQL.CLOSE_CURSOR(curid);
END;

Number of rows processed: 1
Number of rows processed: 1
```

The following anonymous block uses the DBMS_SQL package to execute a block containing two INSERT statements. Note that the end of the block contains a terminating semi-colon, while in the prior example, each individual INSERT statement does not have a terminating semi-colon.

DECLARE

```
INTEGER;
    curid
    v sql
                    VARCHAR2(100);
    v_status
                    INTEGER;
BEGIN
    curid := DBMS_SQL.OPEN_CURSOR;
    v_sql := 'BEGIN ' ||
               'INSERT INTO job VALUES (300, ''MANAGER''); ' ||
               'INSERT INTO job VALUES (400, ''SALESMAN''); ' ||
             'END;';
    DBMS_SQL.PARSE(curid, v_sql, DBMS_SQL.native);
    v_status := DBMS_SQL.EXECUTE(curid);
   DBMS_SQL.CLOSE_CURSOR(curid);
END;
```

4.19 DBMS UTILITY

The DBMS_UTILITY package provides support for the following various utility programs:

```
Function/Procedure
ANALYZE_DATABASE(method [, estimate_rows [, estimate_percent [, method_opt ]]])
ANALYZE_PART_OBJECT(schema, object_name [, object_type [, command_type [, command_opt [, san ANALYZE_SCHEMA(schema, method [, estimate_rows [, estimate_percent [, method_opt ]]])
CANONICALIZE(name, canon_name OUT, canon_len)
COMMA_TO_TABLE(list, tablen OUT, tab OUT)
DB_VERSION(version OUT, compatibility OUT)
EXEC_DDL_STATEMENT(parse_string)
FORMAT_CALL_STACK
GET_CPU_TIME
GET_DEPENDENCY(type, schema, name)
GET_HASH_VALUE(name, base, hash_size)
GET_PARAMETER_VALUE(parnam, intval OUT, strval OUT)
```

GET TIME

NAME_TOKENIZE(name, a OUT, b OUT, c OUT, dblink OUT, nextpos OUT) TABLE TO COMMA(tab, tablen OUT, list OUT)

Advanced Server's implementation of DBMS_UTILITY is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The following table lists the public variables available in the DBMS_UTILITY package.

Public Variables	Data Type	Value	Description
$inv_error_on_restrictions$	PLS_INTEGER	1	Used by the INVALIDATE procedure.
lname_array	TABLE		For lists of long names.
uncl_array	TABLE		For lists of users and names.

LNAME ARRAY

The LNAME_ARRAY is for storing lists of long names including fully-qualified names.

TYPE lname_array IS `TABLE OF VARCHAR2(4000) INDEX BY BINARY_INTEGER;

UNCL_ARRAY

The UNCL_ARRAY is for storing lists of users and names.

TYPE uncl_array IS TABLE OF VARCHAR2(227) INDEX BY BINARY_INTEGER;

ANALYZE_DATABASE, ANALYZE SCHEMA and ANALYZE PART_OBJECT

The ANALYZE_DATABASE(), ANALYZE_SCHEMA() and ANALYZE_PART_OBJECT() procedures provide the capability to gather statistics on tables in the database. When you execute the ANALYZE statement, Postgres samples the data in a table and records distribution statistics in the pg_statistics system table.

ANALYZE_DATABASE, ANALYZE_SCHEMA, and ANALYZE_PART_OBJECT differ primarily in the number of tables that are processed:

- ANALYZE_DATABASE analyzes all tables in all schemas within the current database.
- ANALYZE_SCHEMA analyzes all tables in a given schema (within the current database).
- ANALYZE_PART_OBJECT analyzes a single table.

The syntax for the ANALYZE commands are:

ANALYZE_DATABASE(<method> VARCHAR2 [, <estimate_rows> NUMBER

[, <estimate_percent> NUMBER [, <method_opt> VARCHAR2]]])

ANALYZE_SCHEMA(<schema> VARCHAR2, <method> VARCHAR2

- [, <estimate_rows> NUMBER [, <estimate_percent> NUMBER
- [, <method opt> VARCHAR2]]])

ANALYZE_PART_OBJECT(<schema> VARCHAR2, <object_name> VARCHAR2

- [, <object_type> CHAR [, <command_type> CHAR
- [, <command_opt> VARCHAR2 [, <sample_clause>
]]]])

Parameters - ANALYZE_DATABASE and ANALYZE_SCHEMA

<method>

method determines whether the ANALYZE procedure populates the pg_statistics table or removes entries from the pg_statistics table. If you specify a method of DELETE, the ANALYZE procedure removes the relevant rows from pg_statistics. If you specify a method of COMPUTE or ESTIMATE, the ANALYZE procedure analyzes a table (or multiple tables) and records the distribution information in pg_statistics. There is no difference between COMPUTE and ESTIMATE; both methods execute the Postgres ANALYZE statement. All other parameters are validated and then ignored.

<estimate rows>

Number of rows upon which to base estimated statistics. One of <estimate_rows> or <estimate_percent> must be specified if method is ESTIMATE.

This argument is ignored, but is included for compatibility.

<estimate_percent>

Percentage of rows upon which to base estimated statistics. One of <estimate_rows> or <estimate_percent> must be specified if method is ESTIMATE.

This argument is ignored, but is included for compatibility.

<method opt>

Object types to be analyzed. Any combination of the following:

```
[ FOR TABLE ]
[ FOR ALL [ INDEXED ] COLUMNS ] [ SIZE n ]
[ FOR ALL INDEXES ]
```

This argument is ignored, but is included for compatibility.

Parameters - ANALYZE_PART_OBJECT

<schema>

Name of the schema whose objects are to be analyzed.

<object_name>

Name of the partitioned object to be analyzed.

<object_type>

Type of object to be analyzed. Valid values are: $\mathtt{T}-\mathtt{table},\ \mathtt{I}-\mathtt{index}.$

This argument is ignored, but is included for compatibility.

<command_type>

Type of analyze functionality to perform. Valid values are: E-gather estimated statistics based upon on a specified number of rows or a percentage of rows in the <code><sample_clause></code> clause; C-compute exact statistics; or V-validate the structure and integrity of the partitions.

This argument is ignored, but is included for compatibility.

<command_opt>

For <command_type> C or E, can be any combination of:

```
[ FOR TABLE ]
[ FOR ALL COLUMNS ]
[ FOR ALL LOCAL INDEXES ]
```

For <command_type> V, can be CASCADE if <object_type> is T.

This argument is ignored, but is included for compatibility.

<sample_clause>

If <command_type> is E, contains the following clause to specify the number of rows or percentage or rows on which to base the estimate.

```
SAMPLE <n> { ROWS | PERCENT }
```

This argument is ignored, but is included for compatibility.

CANONICALIZE

The CANONICALIZE procedure performs the following operations on an input string:

- If the string is not double-quoted, verifies that it uses the characters of a legal identifier. If not, an exception is thrown. If the string is double-quoted, all characters are allowed.
- If the string is not double-quoted and does not contain periods, uppercases all alphabetic characters and eliminates leading and trailing spaces.
- If the string is double-quoted and does not contain periods, strips off the double quotes.
- If the string contains periods and no portion of the string is double-quoted, uppercases each portion of the string and encloses each portion in double quotes.
- If the string contains periods and portions of the string are double-quoted, returns the double-quoted portions unchanged including the double quotes and returns the non-double-quoted portions uppercased and enclosed in double quotes.

```
CANONICALIZE(<name> VARCHAR2, <canon_name> OUT VARCHAR2,
<canon_len> BINARY_INTEGER)
```

Parameters

<name>

String to be canonicalized.

<canon_name>

The canonicalized string.

<canon_len>

Number of bytes in <name> to canonicalize starting from the first character.

Examples

The following procedure applies the CANONICALIZE procedure on its input parameter and displays the results.

```
BEGIN
    DBMS_UTILITY.CANONICALIZE(p_name,v_canon,p_length);
    DBMS_OUTPUT.PUT_LINE('Canonicalized name ==>' || v_canon || '<==');</pre>
    DBMS_OUTPUT.PUT_LINE('Length: ' || LENGTH(v_canon));
EXCEPTION
    WHEN OTHERS THEN
        DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
        DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
EXEC canonicalize('Identifier')
Canonicalized name ==>IDENTIFIER<==
Length: 10
EXEC canonicalize('"Identifier"')
Canonicalized name ==>Identifier<==
Length: 10
EXEC canonicalize('"_+142%"')
Canonicalized name ==>_+142%<==
Length: 6
EXEC canonicalize('abc.def.ghi')
Canonicalized name ==>"ABC"."DEF"."GHI"<==
Length: 17
EXEC canonicalize('"abc.def.ghi"')
Canonicalized name ==>abc.def.ghi<==
Length: 11
EXEC canonicalize('"abc".def."ghi"')
Canonicalized name ==>"abc"."DEF"."ghi"<==
Length: 17
EXEC canonicalize('"abc.def".ghi')
Canonicalized name ==>"abc.def"."GHI"<==
Length: 15
```

COMMA_TO_TABLE

The COMMA_TO_TABLE procedure converts a comma-delimited list of names into a table of names. Each entry in the list becomes a table entry. The names must be formatted as valid identifiers.

Parameters

```
t>
```

Comma-delimited list of names.

<tablen>

Number of entries in <tab>.

<tab>

Table containing the individual names in t>.

LNAME_ARRAY

```
A DBMS_UTILITY LNAME_ARRAY (as described in the LNAME_ARRAY <\! lname_array> section).
```

<UNCL_ARRAY>

```
A DBMS_UTILITY UNCL_ARRAY (as described in the UNCL_ARRAY <uncl_array> section).
```

Examples

The following procedure uses the COMMA_TO_TABLE procedure to convert a list of names to a table. The table entries are then displayed.

```
CREATE OR REPLACE PROCEDURE comma_to_table (
                VARCHAR2
   p_list
)
IS
                DBMS UTILITY.LNAME ARRAY;
   r lname
   v_length
                BINARY_INTEGER;
BEGIN
   DBMS_UTILITY.COMMA_TO_TABLE(p_list,v_length,r_lname);
   FOR i IN 1..v length LOOP
        DBMS_OUTPUT.PUT_LINE(r_lname(i));
    END LOOP;
END;
EXEC comma_to_table('edb.dept, edb.emp, edb.jobhist')
edb.dept
edb.emp
edb.jobhist
```

DB_VERSION

The DB_VERSION procedure returns the version number of the database.

```
DB_VERSION(<version> OUT VARCHAR2, <compatibility> OUT
    VARCHAR2)
Parameters
<version>
     Database version number.
<compatibility>
     Compatibility setting of the database. (To be implementation-
     defined as to its meaning.)
Examples
The following anonymous block displays the database version information.
DECLARE
    v_version
                    VARCHAR2(150);
    v_compat
                    VARCHAR2(150);
BEGIN
    DBMS_UTILITY.DB_VERSION(v_version,v_compat);
    DBMS_OUTPUT.PUT_LINE('Version: '
                                       || v_version);
    DBMS_OUTPUT.PUT_LINE('Compatibility: ' || v_compat);
END;
Version: EnterpriseDB 10.0.0 on i686-pc-linux-gnu, compiled by GCC gcc (GCC) 4.1.2 20080704
Compatibility: EnterpriseDB 10.0.0 on i686-pc-linux-gnu, compiled by GCC gcc (GCC) 4.1.22008
EXEC_DDL_STATEMENT
The EXEC_DDL_STATEMENT provides the capability to execute a DDL command.
```

```
EXEC_DDL_STATEMENT(<parse_string> VARCHAR2)
```

Parameters

```
<parse_string>
```

The DDL command to be executed.

Examples

The following anonymous block creates the job table.

```
BEGIN
```

```
DBMS_UTILITY.EXEC_DDL_STATEMENT(
        'CREATE TABLE job (' ||
          'jobno NUMBER(3),' ||
          'jname VARCHAR2(9))'
    );
END;
```

```
edb=# exec dbms_utility.exec_ddl_statement('select rownum from dual');
ERROR: EDB-20001: 'parse_string' must be a valid DDL statement
```

In this case, Advanced Server's behavior differs from Oracle's; Oracle accepts the invalid cprse_string> without complaint.

FORMAT CALL STACK

The FORMAT_CALL_STACK function returns the formatted contents of the current call stack.

```
DBMS_UTILITY.FORMAT_CALL_STACK return VARCHAR2
```

This function can be used in a stored procedure, function or package to return the current call stack in a readable format. This function is useful for debugging purposes.

GET_CPU_TIME

The GET_CPU_TIME function returns the CPU time in hundredths of a second from some arbitrary point in time.

```
<cputime> NUMBER GET_CPU_TIME
```

Parameters

<cputime>

Number of hundredths of a second of CPU time.

Examples

The following SELECT command retrieves the current CPU time, which is 603 hundredths of a second or .0603 seconds.

```
SELECT DBMS_UTILITY.GET_CPU_TIME FROM DUAL;
```

```
get_cpu_time
```

603

GET_DEPENDENCY

The GET_DEPENDENCY procedure provides the capability to list the objects that are dependent upon the specified object. GET_DEPENDENCY does not show dependencies for functions or procedures.

Parameters

<type>

The object type of <name>. Valid values are INDEX, PACKAGE, PACKAGE BODY, SEQUENCE, TABLE, TRIGGER, TYPE and VIEW.

<schema>

Name of the schema in which <name> exists.

<name>

Name of the object for which dependencies are to be obtained.

Examples

The following anonymous block finds dependencies on the EMP table.

BEGIN

```
DBMS_UTILITY.GET_DEPENDENCY('TABLE','public','EMP');
END;
```

DEPENDENCIES ON public.EMP

*TABLE public.EMP()

- * CONSTRAINT c public.emp()
- * CONSTRAINT f public.emp()
- * CONSTRAINT p public.emp()
- * TYPE public.emp()
- * CONSTRAINT c public.emp()
- * CONSTRAINT f public.jobhist()
- * VIEW .empname_view()

GET_HASH_VALUE

The GET_HASH_VALUE function provides the capability to compute a hash value for a given string.

```
<hash> NUMBER GET_HASH_VALUE(<name> VARCHAR2, <base>
NUMBER,
```

<hash_size> NUMBER)

Parameters

<name>

The string for which a hash value is to be computed.

<base>

Starting value at which hash values are to be generated.

<hash_size>

The number of hash values for the desired hash table.

<hash>

The generated hash value.

Examples

The following anonymous block creates a table of hash values using the ename column of the emp table and then displays the key along with the hash value. The hash values start at 100 with a maximum of 1024 distinct values.

DECLARE

```
v hash
                    NUMBER;
    TYPE hash_tab IS TABLE OF NUMBER INDEX BY VARCHAR2(10);
                    HASH_TAB;
    CURSOR emp_cur IS SELECT ename FROM emp;
BEGIN
    FOR r_emp IN emp_cur LOOP
        r_hash(r_emp.ename.. code-block:: text) :=
            DBMS_UTILITY.GET_HASH_VALUE(r_emp.ename,100,1024);
    END LOOP;
    FOR r_emp IN emp_cur LOOP
        DBMS_OUTPUT.PUT_LINE(RPAD(r_emp.ename,10) || ' ' ||
            r_hash(r_emp.ename));
    END LOOP;
END;
           377
SMITH
ALLEN
           740
WARD
           718.. code-block:: text
JONES
           131
           176
MARTIN
BLAKE
           568
CLARK
           621
SCOTT
           1097
KING
           235
TURNER
           850
ADAMS
           156
           942
JAMES
FORD
           775
MILLER
           148
```

GET_PARAMETER_VALUE

The GET_PARAMETER_VALUE procedure provides the capability to retrieve database initialization parameter settings.

```
<status> BINARY_INTEGER GET_PARAMETER_VALUE(varchar2,
```

```
<intval> OUT INTEGER, <strval> OUT VARCHAR2)
```

Parameters

<parnam>

Name of the parameter whose value is to be returned. The parameters are listed in the pg_settings system view.

<intval>

Value of an integer parameter or the length of <strval>.

<strval>

Value of a string parameter.

<status>

Returns 0 if the parameter value is INTEGER or BOOLEAN. Returns 1 if the parameter value is a string.

Examples

The following anonymous block shows the values of two initialization parameters.

DECLARE

```
v_intval INTEGER;
v_strval VARCHAR2(80);

BEGIN

DBMS_UTILITY.GET_PARAMETER_VALUE('max_fsm_pages', v_intval, v_strval);
DBMS_OUTPUT.PUT_LINE('max_fsm_pages' || ': ' || v_intval);
DBMS_UTILITY.GET_PARAMETER_VALUE('client_encoding', v_intval, v_strval);
DBMS_OUTPUT.PUT_LINE('client_encoding' || ': ' || v_strval);
END;

max_fsm_pages: 72625
client_encoding: SQL_ASCII
```

GET_TIME

The GET_TIME function provides the capability to return the current time in hundredths of a second.

```
<time> NUMBER GET TIME
```

Parameters

```
<time>
```

Number of hundredths of a second from the time in which the program is started.

Examples

```
The following example shows calls to the GET_TIME function.
```

```
SELECT DBMS_UTILITY.GET_TIME FROM DUAL;
```

```
get_time
-----
1555860

SELECT DBMS_UTILITY.GET_TIME FROM DUAL;
get_time
----------
1556037
```

NAME_TOKENIZE

The NAME_TOKENIZE procedure parses a name into its component parts. Names without double quotes are uppercased. The double quotes are stripped from names with double quotes.

```
NAME_TOKENIZE(<name> VARCHAR2, <a> OUT VARCHAR2, <b> OUT VARCHAR2, <c> OUT VARCHAR2, <dblink> OUT VARCHAR2, <nextpos> OUT BINARY_INTEGER)
```

Parameters

```
<name>
```

String containing a name in the following format:

```
<a> [.<b> [.<c>]][@<dblink> ]
```

<a>

Returns the leftmost component.

Returns the second component, if any.

<c>

Returns the third component, if any.

<dblink>

Returns the database link name.

<nextpos>

Position of the last character parsed in name.

Examples

The following stored procedure is used to display the returned parameter values of the NAME_TOKENIZE procedure for various names.

```
CREATE OR REPLACE PROCEDURE name_tokenize (
   p_name
                   VARCHAR2
)
IS
                VARCHAR2(30);
   v_a
                  VARCHAR2(30);
   v_b
                   VARCHAR2(30);
   v_c
   v_dblink
                   VARCHAR2(30);
   v_nextpos
                   BINARY_INTEGER;
BEGIN
   DBMS_UTILITY.NAME_TOKENIZE(p_name,v_a,v_b,v_c,v_dblink,v_nextpos);
   DBMS_OUTPUT.PUT_LINE('name : ' || p_name);
   DBMS_OUTPUT.PUT_LINE('a
                              : ' || v_a);
                               : ' || v_b);
   DBMS_OUTPUT.PUT_LINE('b
                             : ' || v_c);
    DBMS_OUTPUT.PUT_LINE('c
    DBMS_OUTPUT.PUT_LINE('dblink : ' || v_dblink);
   DBMS_OUTPUT.PUT_LINE('nextpos: ' || v_nextpos);
END;
Tokenize the name, emp:
BEGIN
name_tokenize('emp');
END;
name
: emp
: EMP
b
С
dblink:
nextpos: 3
Tokenize the name, edb.list_emp:
BEGIN
name_tokenize('edb.list_emp');
```

```
END;
name
a
b
С
dblink :
nextpos:
edb.list_emp
EDB
LIST_EMP
12
Tokenize the name, "edb"."Emp_Admin".update_emp_sal :
name_tokenize('"edb"."Emp_Admin".update_emp_sal');
END;
name
a
b
С
dblink :
nextpos:
"edb"."Emp_Admin".update_emp_sal
edb
Emp_Admin
UPDATE_EMP_SAL
Tokenize the name edb.emp@edb_dblink :
BEGIN
Copyright \ensuremath{\texttt{©}} 2007 - 2019 EnterpriseDB Corporation. All rights reserved.
255Database Compatibility for Oracle Developers
Built-in Package Guide
name_tokenize('edb.emp@edb_dblink');
END;
name
:
a
```

```
:
b
:
c
c
:
dblink :
nextpos:
edb.emp@edb_dblink
EDB
EMP
EDB_DBLINK
18
```

TABLE_TO_COMMA

The TABLE_TO_COMMA procedure converts table of names into a comma-delimited list of names. Each table entry becomes a list entry. The names must be formatted as valid identifiers.

Parameters

<tab>

Table containing names.

LNAME_ARRAY

A ${\tt DBMS_UTILITY}$ ${\tt LNAME_ARRAY}$ (as described in the LNAME ARRAY section.

UNCL_ARRAY

A DBMS_UTILITY UNCL_ARRAY (as described the UNCL_ARRAY <uncl_array> section).

<tablen>

Number of entries in t>.

t>

Comma-delimited list of names from <tab>.

Examples

The following example first uses the COMMA_TO_TABLE procedure to convert a comma-delimited list to a table. The TABLE_TO_COMMA procedure then converts the table back to a comma-delimited list that is displayed.

```
CREATE OR REPLACE PROCEDURE table_to_comma (
   p_list
               VARCHAR2
)
IS
   r_{lname}
               DBMS_UTILITY.LNAME_ARRAY;
   v_length
               BINARY_INTEGER;
   v_listlen BINARY_INTEGER;
   v_list
               VARCHAR2(80);
BEGIN
   DBMS_UTILITY.COMMA_TO_TABLE(p_list,v_length,r_lname);
   DBMS_OUTPUT.PUT_LINE('Table Entries');
   DBMS_OUTPUT.PUT_LINE('----');
   FOR i IN 1..v_length LOOP
       DBMS_OUTPUT.PUT_LINE(r_lname(i));
   END LOOP;
   DBMS_OUTPUT.PUT_LINE('----');
   DBMS_UTILITY.TABLE_TO_COMMA(r_lname,v_listlen,v_list);
   DBMS_OUTPUT.PUT_LINE('Comma-Delimited List: ' || v_list);
END;
EXEC table_to_comma('edb.dept, edb.emp, edb.jobhist')
Table Entries
edb.dept
edb.emp
edb.jobhist
_____
Comma-Delimited List: edb.dept, edb.emp, edb.jobhist
```

4.20.1 UTL_ENCODE

The UTL_ENCODE package provides a way to encode and decode data. Advanced Serve supports the following functions and procedures:

Function/Procedure	Return Type	Description
$BASE64_DECODE(r)$	RAW	Use the BASE64_DECODE fu
BASE64_ENCODE(r)	RAW	Use the BASE64_ENCODE fu
BASE64_ENCODE(loid)	TEXT	Use the BASE64_ENCODE fu
MIMEHEADER_DECODE(buf)	VARCHAR2	Use the MIMEHEADER_DEC
MIMEHEADER_ENCODE(buf, encode_charset, encoding)	VARCHAR2	Use the MIMEHEADER_ENC
$QUOTED_PRINTABLE_DECODE(r)$	RAW	Use the QUOTED_PRINTAB
$QUOTED_PRINTABLE_ENCODE(r)$	RAW	Use the QUOTED_PRINTAB
TEXT_DECODE(buf, encode_charset, encoding)	VARCHAR2	Use the TEXT_DECODE fund

TEXT_ENCODE(buf, encode_charset, encoding)	VARCHAR2	Use the TEXT_ENCODE fund
UUDECODE(r)	RAW	Use the UUDECODE function
UUENCODE(r, type, filename, permission)	RAW	Use the UUENCODE function

 $base 64_decode \quad base 64_encode \quad mimeheader_decode \quad mimeheader_encode \\ quoted_printable_decode \quad quoted_printable_encode \quad text_decode \quad text_encode \\ uudecode \quad uuencode \\$

4.20.2 BASE64 DECODE

Use the BASE64_DECODE function to translate a Base64 encoded string to the original value originally encoded by BASE64_ENCODE. The signature is:

```
BASE64_DECODE (<r> IN RAW)
```

This function returns a RAW value.

Parameters

<r>

<r> is the string that contains the Base64 encoded data that will be
translated to RAW form.

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example first encodes (using BASE64_ENCODE), and then decodes (using BASE64_DECODE) a string that contains the text abc:

(1 row)

4.20.3 BASE64 ENCODE

Use the BASE64_ENCODE function to translate and encode a string in Base64 format (as described in RFC 4648). This function can be useful when composing MIME email that you intend to send using the UTL_SMTP package. The BASE64_ENCODE function has two signatures:

```
BASE64_ENCODE(<r> IN RAW)
and
BASE64_ENCODE(<loid> IN OID)
```

This function returns a RAW value or an OID.

Parameters

<r>

<r> specifies the RAW string that will be translated to Base64.</ri>

<loid>

<loid> specifies the object ID of a large object that will be translated to Base64.

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example first encodes (using BASE64_ENCODE), and then decodes (using BASE64_DECODE) a string that contains the text abc:

```
abc (1 row)
```

4.20.4 MIMEHEADER DECODE

Use the MIMEHEADER_DECODE function to decode values that are encoded by the MIMEHEADER_ENCODE function. The signature is:

MIMEHEADER_DECODE(<buf> IN VARCHAR2)

This function returns a VARCHAR2 value.

Parameters

<buf>

<buf> contains the value (encoded by MIMEHEADER_ENCODE) that
will be decoded.

Examples

The following examples use the MIMEHEADER_ENCODE and MIMEHEADER_DECODE functions to first encode, and then decode a string:

4.20.5 MIMEHEADER_ENCODE

Use the MIMEHEADER_ENCODE function to convert a string into mime header format, and then encode the string. The signature is:

```
MIMEHEADER_ENCODE(<buf> IN VARCHAR2, <encode_charset> IN VARCHAR2 DEFAULT NULL, <encoding> IN INTEGER DEFAULT NULL)
```

This function returns a VARCHAR2 value.

Parameters

<buf>

<buf> contains the string that will be formatted and encoded. The string is a VARCHAR2 value.

<encode_charset>

<encode_charset> specifies the character set to which the string
will be converted before being formatted and encoded. The default
value is NULL.

<encoding>

<encoding> specifies the encoding type used when encoding the
string. You can specify:

- Q to enable quoted-printable encoding. If you do not specify a value, MIMEHEADER_ENCODE will use quoted-printable encoding.
- B to enable base-64 encoding.

Examples

The following examples use the MIMEHEADER_ENCODE and MIMEHEADER_DECODE functions to first encode, and then decode a string:

4.20.6 QUOTED_PRINTABLE_DECODE

Use the QUOTED_PRINTABLE_DECODE function to translate an encoded quoted-printable string into a decoded RAW string.

The signature is:

```
QUOTED_PRINTABLE_DECODE(<r> IN RAW)
```

This function returns a RAW value.

Parameters

<r>

<r> contains the encoded string that will be decoded. The string is
a RAW value, encoded by QUOTED_PRINTABLE_ENCODE.

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example first encodes and then decodes a string:

4.20.7 QUOTED PRINTABLE ENCODE

Use the QUOTED_PRINTABLE_ENCODE function to translate and encode a string in quoted-printable format. The signature is:

```
QUOTED_PRINTABLE_ENCODE(<r> IN RAW)
```

This function returns a RAW value.

Parameters

<r>

<r> contains the string (a RAW value) that will be encoded in a
quoted-printable format.

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example first encodes and then decodes a string:

4.20.8 TEXT_DECODE

Use the TEXT_DECODE function to translate and decode an encoded string to the VARCHAR2 value that was originally encoded by the TEXT_ENCODE function. The signature is:

TEXT_DECODE(<buf> IN VARCHAR2, <encode_charset> IN VARCHAR2 DEFAULT NULL, <encoding> IN PLS_INTEGER DEFAULT NULL)

This function returns a VARCHAR2 value.

Parameters

<buf>

 <buf> contains the encoded string that will be translated to the original value encoded by TEXT_ENCODE.

<encode_charset>

<encode_charset> specifies the character set to which the string
will be translated before encoding. The default value is NULL.

<encoding>

<encoding> specifies the encoding type used by TEXT_DECODE. Specify:

- UTL_ENCODE.BASE64 to specify base-64 encoding.
- UTL_ENCODE.QUOTED_PRINTABLE to specify quoted printable encoding. This is the default.

Examples

The following example uses the TEXT_ENCODE and TEXT_DECODE functions to first encode, and then decode a string:

4.20.9 TEXT_ENCODE

Use the TEXT_ENCODE function to translate a string to a user-specified character set, and then encode the string. The signature is:

TEXT_DECODE(<buf> IN VARCHAR2, <encode_charset> IN
VARCHAR2 DEFAULT NULL, <encoding> IN PLS_INTEGER DEFAULT
NULL)

This function returns a VARCHAR2 value.

Parameters

<buf>

 <buf> contains the encoded string that will be translated to the specified character set and encoded by TEXT_ENCODE.

<encode_charset>

<encode_charset> specifies the character set to which the value will
be translated before encoding. The default value is NULL.

<encoding>

<encoding> specifies the encoding type used by TEXT_ENCODE. Specify:

- \bullet UTL_ENCODE.BASE64 to specify base-64 encoding.
- UTL_ENCODE.QUOTED_PRINTABLE to specify quoted printable encoding.
 This is the default.

Examples

The following example uses the TEXT_ENCODE and TEXT_DECODE functions to first encode, and then decode a string:

4.20.10 UUDECODE

Use the UUDECODE function to translate and decode a uuencode encoded string to the RAW value that was originally encoded by the UUENCODE function. The signature is:

```
UUDECODE(<r> IN RAW)
```

This function returns a RAW value.

If you are using the Advanced Server UUDECODE function to decode uuencoded data that was created by the Oracle implementation of the UTL_ENCODE.UUENCODE function, then you must first set the Advanced Server configuration parameter utl_encode.uudecode_redwood to TRUE before invoking the Advanced Server UUDECODE function on the Oracle-created data. (For example, this situation may occur if you migrated Oracle tables containing uuencoded data to an Advanced Server database.)

The uuencoded data created by the Oracle version of the UUENCODE function results in a format that differs from the uuencoded data created by the Advanced Server UUENCODE function. As a result, attempting to use the Advanced Server UUDECODE function on the Oracle uuencoded data results in an error unless the configuration parameter utl_encode.uudecode_redwood is set to TRUE.

However, if you are using the Advanced Server UUDECODE function on uuencoded data created by the Advanced Server UUENCODE function, then utl_encode.uudecode_redwood must be set to FALSE, which is the default setting.

Parameters

<r>

<r> contains the uuencoded string that will be translated to RAW.

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example uses UUENCODE and UUDECODE to first encode and then decode a string:

4.20.11 UUENCODE

Use the UUENCODE function to translate RAW data into a uuencode formatted encoded string. The signature is:

This function returns a RAW value.

Parameters

<r>

<r> contains the RAW string that will be translated to uuencode format.

<type>

<type> is an INTEGER value or constant that specifies the type of
uuencoded string that will be returned; the default value is 1. The
possible values are:

Value	Constant
1	complete
2	header_piece
3	$middle_piece$
4	end_piece

<filename>

<filename> is a VARCHAR2 value that specifies the file name that you
want to embed in the encoded form; if you do not specify a file name,
UUENCODE will include a filename of uuencode.txt in the encoded
form.

<permission>

<permission> is a VARCHAR2 that specifies the permission mode; the
default value is NULL.

Examples

Before executing the following example, invoke the command:

```
SET bytea_output = escape;
```

This command instructs the server to escape any non-printable characters, and to display BYTEA or RAW values onscreen in readable form. For more information, please refer to the Postgres Core Documentation available at:

https://www.postgresql.org/docs/12/static/datatype-binary.html

The following example uses UUENCODE and UUDECODE to first encode and then decode a string:

```
uudecode
-----
What is the date?
(1 row)
```

4.21 UTL FILE

The UTL_FILE package provides the capability to read from, and write to files on the operating system's file system. Non-superusers must be granted EXECUTE privilege on the UTL_FILE package by a superuser before using any of the functions or procedures in the package. For example the following command grants the privilege to user mary:

GRANT EXECUTE ON PACKAGE SYS.UTL_FILE TO mary;

Also, the operating system username, enterprisedb, must have the appropriate read and/or write permissions on the directories and files to be accessed using the UTL_FILE functions and procedures. If the required file permissions are not in place, an exception is thrown in the UTL_FILE function or procedure.

A handle to the file to be written to, or read from is used to reference the file. The *file handle* is defined by a public variable in the UTL_FILE package named, UTL_FILE.FILE_TYPE. A variable of type FILE_TYPE must be declared to receive the file handle returned by calling the FOPEN function. The file handle is then used for all subsequent operations on the file.

References to directories on the file system are done using the directory name or alias that is assigned to the directory using the CREATE DIRECTORY command. The procedures and functions available in the UTL_FILE package are listed in the following table:

Function/Procedure	Return Type	Description
FCLOSE(file IN OUT)	n/a	Closes the speci
FCLOSE_ALL	n/a	Closes all open
FCOPY(location, filename, dest_dir, dest_file [, start_line [, end_line]])	n/a	Copies filename
FFLUSH(file)	n/a	Forces data in t
FOPEN(location, filename, open_mode [, max_linesize])	FILE_TYPE	Opens file, filena
FREMOVE(location, filename)	n/a	Removes the spe
FRENAME(location, filename, dest_dir, dest_file [, overwrite])	n/a	Renames the sp
GET_LINE(file, buffer OUT)	n/a	Reads a line of t
IS_OPEN(file)	BOOLEAN	Determines whe
NEW_LINE(file [, lines])	n/a	Writes an end-o
PUT(file, buffer)	n/a	Writes buffer to
PUT_LINE(file, buffer)	n/a	Writes buffer to
PUTF(file, format [, arg1] [,])	n/a	Writes a format

Advanced Server's implementation of UTL_FILE is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

UTL_FILE Exception Codes

If a call to a UTL_FILE procedure or function raises an exception, you can use the condition name to catch the exception. The UTL_FILE package reports the following exception codes compatible with Oracle databases:

Exception Code	Condition name
-29283	invalid_operation
-29285	write_error
-29284	$read_error$
-29282	$invalid_filehandle$
-29287	$invalid_maxlinesize$
-29281	$invalid_mode$
-29280	$invalid_path$

Setting File Permissions with utl_file.umask

When a UTL_FILE function or procedure creates a file, there are default file permissions as shown by the following.

-rw----- 1 enterprisedb enterprisedb 21 Jul 24 16:08 utlfile

Note that all permissions are denied on users belonging to the enterprisedb group as well as all other users. Only the enterprisedb user has read and write permissions on the created file.

If you wish to have a different set of file permissions on files created by the UTL_FILE functions and procedures, you can accomplish this by setting the utl_file.umask configuration parameter.

The utl_file.umask parameter sets the *file mode creation mask* or simply, the *mask*, in a manner similar to the Linux umask command. This is for usage only within the Advanced Server UTL_FILE package.

Note

The utl_file.umask parameter is not supported on Windows systems.

The value specified for utl_file.umask is a 3 or 4-character octal string that would be valid for the Linux umask command. The setting determines the permissions on files created by the UTL_FILE functions and procedures. (Refer to any information source regarding Linux or Unix systems for information on file permissions and the usage of the umask command.)

The following is an example of setting the file permissions with utl_file.umask.

First, set up the directory in the file system to be used by the UTL_FILE package. Be sure the operating system account, enterprised or postgres, whichever is applicable, can read and write in the directory.

```
mkdir /tmp/utldir
chmod 777 /tmp/utldir
```

The CREATE DIRECTORY command is issued in psql to create the directory database object using the file system directory created in the preceding step.

```
CREATE DIRECTORY utldir AS '/tmp/utldir';
```

Set the utl_file.umask configuration parameter. The following setting allows the file owner any permission. Group users and other users are permitted any permission except for the execute permission.

```
SET utl file.umask TO '0011';
```

In the same session during which the utl_file.umask parameter is set to the desired value, run the UTL_FILE functions and procedures.

DECLARE

```
v_utlfile    UTL_FILE.FILE_TYPE;
v_directory    VARCHAR2(50) := 'utldir';
v_filename    VARCHAR2(20) := 'utlfile';

BEGIN
    v_utlfile := UTL_FILE.FOPEN(v_directory, v_filename, 'w');
    UTL_FILE.PUT_LINE(v_utlfile, 'Simple one-line file');
    DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
    UTL_FILE.FCLOSE(v_utlfile);

END;
```

The permission settings on the resulting file show that group users and other users have read and write permissions on the file as well as the file owner.

```
$ pwd
/tmp/utldir
$ ls -l
total 4
-rw-rw-rw- 1 enterprisedb enterprisedb 21 Jul 24 16:04 utlfile
```

This parameter can also be set on a per role basis with the ALTER ROLE command, on a per database basis with the ALTER DATABASE command, or for the entire database server instance by setting it in the postgresql.conf file.

FCLOSE

The FCLOSE procedure closes an open file.

```
FCLOSE(<file> IN OUT FILE_TYPE)
```

Parameters

<file>

Variable of type FILE_TYPE containing a file handle of the file to be closed.

FCLOSE_ALL

The FLCLOSE_ALL procedures closes all open files. The procedure executes successfully even if there are no open files to close.

FCLOSE_ALL

FCOPY

The FCOPY procedure copies text from one file to another.

Parameters

<location>

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory containing the file to be copied.

<filename>

Name of the source file to be copied.

<dest_dir>

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory to which the file is to be copied.

<dest_file>

Name of the destination file.

<start_line>

Line number in the source file from which copying will begin. The default is 1.

<end_line>

Line number of the last line in the source file to be copied. If omitted or null, copying will go to the last line of the file.

Examples

The following makes a copy of a file, C:\TEMP\EMPDIR\empfile.csv, containing a comma-delimited list of employees from the emp table. The copy, empcopy.csv, is then listed.

CREATE DIRECTORY empdir AS 'C:/TEMP/EMPDIR';

```
DECLARE
    v empfile
                     UTL FILE.FILE TYPE;
    v_src_dir
                     VARCHAR2(50) := 'empdir';
                     VARCHAR2(20) := 'empfile.csv';
    v_src_file
    v_dest_dir
                     VARCHAR2(50) := 'empdir';
    v_dest_file
                     VARCHAR2(20) := 'empcopy.csv';
    v emprec
                     VARCHAR2(120);
    v_count
                     INTEGER := 0;
BEGIN
    UTL_FILE.FCOPY(v_src_dir,v_src_file,v_dest_dir,v_dest_file);
    v_empfile := UTL_FILE.FOPEN(v_dest_dir,v_dest_file,'r');
    DBMS_OUTPUT.PUT_LINE('The following is the destination file, ''' ||
        v_dest_file || '''');
    LOOP
        UTL_FILE.GET_LINE(v_empfile,v_emprec);
        DBMS_OUTPUT.PUT_LINE(v_emprec);
        v_{count} := v_{count} + 1;
    END LOOP;
    EXCEPTION
        WHEN NO_DATA_FOUND THEN
            UTL_FILE.FCLOSE(v_empfile);
            DBMS_OUTPUT.PUT_LINE(v_count || ' records retrieved');
        WHEN OTHERS THEN
            DBMS OUTPUT.PUT LINE('SQLERRM: ' || SQLERRM);
            DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
The following is the destination file, 'empcopy.csv'
7369, SMITH, CLERK, 7902, 17-DEC-80, 800, ,20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81, 1600, 300, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81, 1250, 500, 30
7566, JONES, MANAGER, 7839, 02-APR-81, 2975, ,20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81, 1250, 1400, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81, 2850, ,30
7782, CLARK, MANAGER, 7839, 09-JUN-81, 2450, ,10
7788, SCOTT, ANALYST, 7566, 19-APR-87, 3000, ,20
7839, KING, PRESIDENT, ,17-NOV-81,5000, ,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81, 1500, 0, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87, 1100, ,20
```

```
7900, JAMES, CLERK, 7698, 03-DEC-81, 950, ,30
7902, FORD, ANALYST, 7566, 03-DEC-81, 3000, ,20
7934, MILLER, CLERK, 7782, 23-JAN-82, 1300, ,10
14 records retrieved
```

FFLUSH

The FFLUSH procedure flushes unwritten data from the write buffer to the file.

```
FFLUSH(<file> FILE_TYPE)
```

Parameters

<file>

Variable of type FILE_TYPE containing a file handle.

Examples

Each line is flushed after the NEW_LINE procedure is called.

DECLARE

```
v_empfile
                    UTL_FILE.FILE_TYPE;
    v_directory
                    VARCHAR2(50) := 'empdir';
                    VARCHAR2(20) := 'empfile.csv';
    v_filename
    CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
    v_empfile := UTL_FILE.FOPEN(v_directory,v_filename,'w');
    FOR i IN emp_cur LOOP
        UTL_FILE.PUT(v_empfile,i.empno);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.ename);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.job);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.mgr);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.hiredate);
        UTL FILE.PUT(v empfile,',');
        UTL_FILE.PUT(v_empfile,i.sal);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.comm);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.deptno);
        UTL_FILE.NEW_LINE(v_empfile);
        UTL_FILE.FFLUSH(v_empfile);
    END LOOP;
    DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
    UTL_FILE.FCLOSE(v_empfile);
```

END;

FOPEN

The FOPEN function opens a file for I/O.

```
<filetype> FILE_TYPE FOPEN(<location> VARCHAR2,
<filename> VARCHAR2,<open_mode> VARCHAR2
[, <max_linesize> BINARY_INTEGER ])
```

Parameters

<location>

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory containing the file to be opened.

<filename>

Name of the file to be opened.

<open mode>

Mode in which the file will be opened. Modes are: a - append to file; r - read from file; w - write to file.

<max_linesize>

Maximum size of a line in characters. In read mode, an exception is thrown if an attempt is made to read a line exceeding <max_linesize>. In write and append modes, an exception is thrown if an attempt is made to write a line exceeding <max_linesize>. The end-of-line character(s) are not included in determining if the maximum line size is exceeded. This behavior is not compatible with Oracle databases; Oracle does count the end-of-line character(s).

<filetype>

Variable of type FILE_TYPE containing the file handle of the opened file.

FREMOVE

The FREMOVE procedure removes a file from the system.

```
FREMOVE(<location> VARCHAR2, <filename> VARCHAR2)
```

An exception is thrown if the file to be removed does not exist.

Parameters

<location>

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory containing the file to be removed.

<filename>

Name of the file to be removed.

Examples

The following removes file empfile.csv.

DECLARE

```
v_directory VARCHAR2(50) := 'empdir';
v_filename VARCHAR2(20) := 'empfile.csv';

BEGIN
   UTL_FILE.FREMOVE(v_directory,v_filename);
   DBMS_OUTPUT.PUT_LINE('Removed file: ' || v_filename);
   EXCEPTION
      WHEN OTHERS THEN
            DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
            DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);

END;
```

Removed file: empfile.csv

FRENAME

The FRENAME procedure renames a given file. This effectively moves a file from one location to another.

```
FRENAME(<location> VARCHAR2, <filename> VARCHAR2,
<dest_dir> VARCHAR2, <dest_file> VARCHAR2,
[ <overwrite> BOOLEAN ])
```

Parameters

<location>

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory containing the file to be renamed.

<filename>

Name of the source file to be renamed.

<dest_dir>

Directory name, as stored in pg_catalog.edb_dir.dirname, of the directory to which the renamed file is to exist.

```
<dest_file>
```

New name of the original file.

<overwrite>

Replaces any existing file named <dest_file> in <dest_dir> if set to TRUE, otherwise an exception is thrown if set to FALSE. This is the default.

Examples

The following renames a file, C:\TEMP\EMPDIR\empfile.csv, containing a comma-delimited list of employees from the emp table. The renamed file, C:\TEMP\NEWDIR\newemp.csv, is then listed.

CREATE DIRECTORY "newdir" AS 'C:/TEMP/NEWDIR';

```
DECLARE
   v_empfile
                    UTL_FILE.FILE_TYPE;
                    VARCHAR2(50) := 'empdir';
   v_src_dir
                    VARCHAR2(20) := 'empfile.csv';
   v_src_file
    v_dest_dir
                    VARCHAR2(50) := 'newdir';
                    VARCHAR2(50) := 'newemp.csv';
    v_dest_file
    v_replace
                    BOOLEAN := FALSE;
    v_emprec
                    VARCHAR2(120);
   v_count
                    INTEGER := 0;
BEGIN
   UTL_FILE.FRENAME(v_src_dir,v_src_file,v_dest_dir,
        v_dest_file,v_replace);
    v_empfile := UTL_FILE.FOPEN(v_dest_dir,v_dest_file,'r');
    DBMS OUTPUT.PUT LINE('The following is the renamed file, ''' ||
        v_dest_file || '''');
    LOOP
        UTL_FILE.GET_LINE(v_empfile,v_emprec);
        DBMS OUTPUT.PUT LINE(v emprec);
        v_count := v_count + 1;
    END LOOP;
    EXCEPTION
        WHEN NO_DATA_FOUND THEN
            UTL_FILE.FCLOSE(v_empfile);
            DBMS_OUTPUT.PUT_LINE(v_count || ' records retrieved');
        WHEN OTHERS THEN
            DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
            DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
The following is the renamed file, 'newemp.csv'
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
```

```
7521,WARD,SALESMAN,7698,22-FEB-81 00:00:00,1250.00,500.00,30
7566,JONES,MANAGER,7839,02-APR-81 00:00:00,2975.00,,20
7654,MARTIN,SALESMAN,7698,28-SEP-81 00:00:00,1250.00,1400.00,30
7698,BLAKE,MANAGER,7839,01-MAY-81 00:00:00,2850.00,,30
7782,CLARK,MANAGER,7839,09-JUN-81 00:00:00,2450.00,,10
7788,SCOTT,ANALYST,7566,19-APR-87 00:00:00,3000.00,,20
7839,KING,PRESIDENT,,17-NOV-81 00:00:00,5000.00,,10
7844,TURNER,SALESMAN,7698,08-SEP-81 00:00:00,1500.00,0.00,30
7876,ADAMS,CLERK,7788,23-MAY-87 00:00:00,1100.00,,20
7900,JAMES,CLERK,7698,03-DEC-81 00:00:00,950.00,,30
7902,FORD,ANALYST,7566,03-DEC-81 00:00:00,3000.00,,20
7934,MILLER,CLERK,7782,23-JAN-82 00:00:00,1300.00,,10
```

GET_LINE

The GET_LINE procedure reads a line of text from a given file up to, but not including the end-of-line terminator. A NO_DATA_FOUND exception is thrown when there are no more lines to read.

```
GET LINE(<file> FILE TYPE, <buffer> OUT VARCHAR2)
```

Parameters

<file>

Variable of type FILE_TYPE containing the file handle of the opened file.

<buffer>

Variable to receive a line from the file.

Examples

The following anonymous block reads through and displays the records in file empfile.csv.

DECLARE

```
v_empfile    UTL_FILE.FILE_TYPE;
v_directory    VARCHAR2(50) := 'empdir';
v_filename    VARCHAR2(20) := 'empfile.csv';
v_emprec    VARCHAR2(120);
v_count    INTEGER := 0;
BEGIN
v_empfile := UTL_FILE.FOPEN(v_directory,v_filename,'r');
LOOP
    UTL_FILE.GET_LINE(v_empfile,v_emprec);
    DBMS_OUTPUT.PUT_LINE(v_emprec);
    v_count := v_count + 1;
```

```
END LOOP;
    EXCEPTION
        WHEN NO_DATA_FOUND THEN
             UTL_FILE.FCLOSE(v_empfile);
             DBMS_OUTPUT.PUT_LINE('End of file ' || v_filename || ' - ' ||
                 v_count || ' records retrieved');
        WHEN OTHERS THEN
             DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
             DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788,SCOTT,ANALYST,7566,19-APR-87 00:00:00,3000.00,,20
7839, KING, PRESIDENT, ,17-NOV-81 00:00:00,5000.00,,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
End of file empfile.csv - 14 records retrieved
IS OPEN
The IS_OPEN function determines whether or not the given file is open.
     <status> BOOLEAN IS_OPEN(<file> FILE_TYPE)
Parameters
<file>
     Variable of type FILE TYPE containing the file handle of the file to
     be tested.
<status>
     TRUE if the given file is open, FALSE otherwise.
NEW LINE
```

The NEW_LINE procedure writes an end-of-line character sequence in the file.

NEW_LINE(<file> FILE_TYPE [, <lines> INTEGER])

Parameters

<file>

Variable of type FILE_TYPE containing the file handle of the file to which end-of-line character sequences are to be written.

lines>

Number of end-of-line character sequences to be written. The default is one.

Examples

A file containing a double-spaced list of employee records is written.

DECLARE

```
UTL_FILE.FILE_TYPE;
    v empfile
   v_directory
                    VARCHAR2(50) := 'empdir';
   v filename
                    VARCHAR2(20) := 'empfile.csv';
    CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
    v_empfile := UTL_FILE.FOPEN(v_directory,v_filename,'w');
   FOR i IN emp_cur LOOP
        UTL_FILE.PUT(v_empfile,i.empno);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.ename);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.job);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.mgr);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.hiredate);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.sal);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.comm);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.deptno);
        UTL_FILE.NEW_LINE(v_empfile,2);
    END LOOP;
   DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
    UTL_FILE.FCLOSE(v_empfile);
END;
Created file: empfile.csv
This file is then displayed:
C:\TEMP\EMPDIR>TYPE empfile.csv
```

```
7369,SMITH,CLERK,7902,17-DEC-80 00:00:00,800.00,,20
7499,ALLEN,SALESMAN,7698,20-FEB-81 00:00:00,1600.00,300.00,30
7521,WARD,SALESMAN,7698,22-FEB-81 00:00:00,1250.00,500.00,30
7566,JONES,MANAGER,7839,02-APR-81 00:00:00,2975.00,,20
7654,MARTIN,SALESMAN,7698,28-SEP-81 00:00:00,1250.00,1400.00,30
7698,BLAKE,MANAGER,7839,01-MAY-81 00:00:00,2850.00,,30
7782,CLARK,MANAGER,7839,09-JUN-81 00:00:00,2450.00,,10
7788,SCOTT,ANALYST,7566,19-APR-87 00:00:00,3000.00,,20
7839,KING,PRESIDENT,,17-NOV-81 00:00:00,5000.00,,10
7844,TURNER,SALESMAN,7698,08-SEP-81 00:00:00,1500.00,0.00,30
7876,ADAMS,CLERK,7788,23-MAY-87 00:00:00,1100.00,,20
7900,JAMES,CLERK,7698,03-DEC-81 00:00:00,950.00,,30
7902,FORD,ANALYST,7566,03-DEC-81 00:00:00,3000.00,,20
7934,MILLER,CLERK,7782,23-JAN-82 00:00:00,1300.00,,10
UTL_FILE_PUT
```

PUT

The PUT procedure writes a string to the given file. No end-of-line character sequence is written at the end of the string. Use the NEW_LINE procedure to add an end-of-line character sequence.

```
PUT(<file> FILE_TYPE, <buffer> { DATE | NUMBER | TIMESTAMP |
VARCHAR2 })
```

Parameters

<file>

Variable of type FILE_TYPE containing the file handle of the file to which the given string is to be written.

<buffer>

Text to be written to the specified file.

Examples

The following example uses the PUT procedure to create a comma-delimited file of employees from the emp table.

```
DECLARE
                    UTL FILE.FILE TYPE;
    v empfile
    v directory
                    VARCHAR2(50) := 'empdir';
                    VARCHAR2(20) := 'empfile.csv';
    v filename
    CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
    v empfile := UTL FILE.FOPEN(v directory, v filename, 'w');
    FOR i IN emp_cur LOOP
        UTL_FILE.PUT(v_empfile,i.empno);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.ename);
        UTL_FILE.PUT(v_empfile,',');
        UTL FILE.PUT(v empfile,i.job);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.mgr);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.hiredate);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.sal);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.comm);
        UTL_FILE.PUT(v_empfile,',');
        UTL_FILE.PUT(v_empfile,i.deptno);
        UTL_FILE.NEW_LINE(v_empfile);
    END LOOP:
    DBMS OUTPUT.PUT LINE('Created file: ' | | v filename);
    UTL_FILE.FCLOSE(v_empfile);
END;
Created file: empfile.csv
The following is the contents of empfile.csv created above:
C:\TEMP\EMPDIR>TYPE empfile.csv
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
```

```
7698,BLAKE,MANAGER,7839,01-MAY-81 00:00:00,2850.00,,30 7782,CLARK,MANAGER,7839,09-JUN-81 00:00:00,2450.00,,10 7788,SCOTT,ANALYST,7566,19-APR-87 00:00:00,3000.00,,20 7839,KING,PRESIDENT,,17-NOV-81 00:00:00,5000.00,,10 7844,TURNER,SALESMAN,7698,08-SEP-81 00:00:00,1500.00,0.00,30 7876,ADAMS,CLERK,7788,23-MAY-87 00:00:00,1100.00,,20 7900,JAMES,CLERK,7698,03-DEC-81 00:00:00,950.00,,30 7902,FORD,ANALYST,7566,03-DEC-81 00:00:00,3000.00,,20 7934,MILLER,CLERK,7782,23-JAN-82 00:00:00,1300.00,,10 UTL_FILE_PUT_LINE
```

PUT LINE

The PUT_LINE procedure writes a single line to the given file including an end-of-line character sequence.

```
PUT_LINE(<file> FILE_TYPE,
<buffer> {DATE|NUMBER|TIMESTAMP|VARCHAR2})
```

Parameters

<file>

Variable of type FILE_TYPE containing the file handle of the file to which the given line is to be written.

<buffer>

Text to be written to the specified file.

Examples

The following example uses the PUT_LINE procedure to create a commadelimited file of employees from the emp table.

DECLARE

```
UTL_FILE.FILE_TYPE;
   v_empfile
    v_directory
                    VARCHAR2(50) := 'empdir';
                    VARCHAR2(20) := 'empfile.csv';
    v filename
    v emprec
                    VARCHAR2(120);
   CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
    v_empfile := UTL_FILE.FOPEN(v_directory,v_filename,'w');
   FOR i IN emp_cur LOOP
        v_emprec := i.empno || ',' || i.ename || ',' || i.job || ',' ||
            NVL(LTRIM(TO_CHAR(i.mgr,'9999')),'') || ',' || i.hiredate ||
            ',' || i.sal || ',' ||
            NVL(LTRIM(TO_CHAR(i.comm, '9990.99')), '') || ',' || i.deptno;
        UTL_FILE.PUT_LINE(v_empfile,v_emprec);
    END LOOP;
```

```
DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
    UTL_FILE.FCLOSE(v_empfile);
END;
The following is the contents of empfile.csv created above:
C:\TEMP\EMPDIR>TYPE empfile.csv
7369, SMITH, CLERK, 7902, 17-DEC-80 00:00:00, 800.00, 20
7499, ALLEN, SALESMAN, 7698, 20-FEB-81 00:00:00, 1600.00, 300.00, 30
7521, WARD, SALESMAN, 7698, 22-FEB-81 00:00:00, 1250.00, 500.00, 30
7566, JONES, MANAGER, 7839, 02-APR-81 00:00:00, 2975.00, 20
7654, MARTIN, SALESMAN, 7698, 28-SEP-81 00:00:00, 1250.00, 1400.00, 30
7698, BLAKE, MANAGER, 7839, 01-MAY-81 00:00:00, 2850.00, 30
7782, CLARK, MANAGER, 7839, 09-JUN-81 00:00:00, 2450.00, 10
7788, SCOTT, ANALYST, 7566, 19-APR-87 00:00:00, 3000.00, 20
7839, KING, PRESIDENT, ,17-NOV-81 00:00:00,5000.00,,10
7844, TURNER, SALESMAN, 7698, 08-SEP-81 00:00:00, 1500.00, 0.00, 30
7876, ADAMS, CLERK, 7788, 23-MAY-87 00:00:00, 1100.00, 20
7900, JAMES, CLERK, 7698, 03-DEC-81 00:00:00, 950.00, 30
7902, FORD, ANALYST, 7566, 03-DEC-81 00:00:00, 3000.00, 20
7934, MILLER, CLERK, 7782, 23-JAN-82 00:00:00, 1300.00, 10
```

PUTF

The PUTF procedure writes a formatted string to the given file.

```
PUTF(<file> FILE_TYPE, <format> VARCHAR2 [, <arg1>
VARCHAR2]
[, ...])
```

Parameters

<file>

Variable of type FILE_TYPE containing the file handle of the file to which the formatted line is to be written.

<format>

String to format the text written to the file. The special character sequence, %s, is substituted by the value of arg. The special character sequence, \n, indicates a new line. Note, however, in Advanced Server, a new line character must be specified with two consecutive backslashes instead of one - \\n. This characteristic is not compatible with Oracle databases.

<arg1>

Up to five arguments, <arg1>,...<arg5>, to be substituted in the format string for each occurrence of %s. The first arg is substituted for the first occurrence of %s, the second arg is substituted for the second occurrence of %s, etc.

Examples

The following anonymous block produces formatted output containing data from the emp table. Note the use of the E literal syntax and double backslashes for the new line character sequence in the format string which are not compatible with Oracle databases.

```
DECLARE
    v empfile
                    UTL_FILE.FILE_TYPE;
    v_directory
                    VARCHAR2(50) := 'empdir';
    v filename
                    VARCHAR2(20) := 'empfile.csv';
   v format
                    VARCHAR2(200);
   CURSOR emp_cur IS SELECT * FROM emp ORDER BY empno;
BEGIN
    v_format := E'%s %s, %s\\nSalary: $%s Commission: $%s\\n\\n';
    v_empfile := UTL_FILE.FOPEN(v_directory,v_filename,'w');
    FOR i IN emp_cur LOOP
        UTL_FILE.PUTF(v_empfile,v_format,i.empno,i.ename,i.job,i.sal,
            NVL(i.comm,0));
   END LOOP;
    DBMS_OUTPUT.PUT_LINE('Created file: ' || v_filename);
    UTL_FILE.FCLOSE(v_empfile);
EXCEPTION
    WHEN OTHERS THEN
        DBMS_OUTPUT.PUT_LINE('SQLERRM: ' || SQLERRM);
        DBMS_OUTPUT.PUT_LINE('SQLCODE: ' || SQLCODE);
END;
Created file: empfile.csv
The following is the contents of empfile.csv created above:
C:\TEMP\EMPDIR>TYPE empfile.csv
7369 SMITH, CLERK
Salary: $800.00 Commission: $0
7499 ALLEN, SALESMAN
Salary: $1600.00 Commission: $300.00
7521 WARD, SALESMAN
Salary: $1250.00 Commission: $500.00
7566 JONES, MANAGER
Salary: $2975.00 Commission: $0
7654 MARTIN, SALESMAN
Salary: $1250.00 Commission: $1400.00
```

7698 BLAKE, MANAGER

Salary: \$2850.00 Commission: \$0

7782 CLARK, MANAGER

Salary: \$2450.00 Commission: \$0

7788 SCOTT, ANALYST

Salary: \$3000.00 Commission: \$0

7839 KING, PRESIDENT

Salary: \$5000.00 Commission: \$0

7844 TURNER, SALESMAN

Salary: \$1500.00 Commission: \$0.00

7876 ADAMS, CLERK

Salary: \$1100.00 Commission: \$0

7900 JAMES, CLERK

Salary: \$950.00 Commission: \$0

7902 FORD, ANALYST

Salary: \$3000.00 Commission: \$0

7934 MILLER, CLERK

Salary: \$1300.00 Commission: \$0

4.22 UTL_HTTP

The UTL_HTTP package provides a way to use the HTTP or HTTPS protocol to retrieve information found at an URL. Advanced Server supports the following functions and procedures:

Function/Procedure	Return Type	Descripti
BEGIN_REQUEST(url, method, http_version)	$\mathrm{UTL_HTTP.REQ}$	Initiates
END_REQUEST(r IN OUT)	n/a	Ends an
END_RESPONSE(r IN OUT)	n/a	Ends the
GET_BODY_CHARSET	VARCHAR2	Returns
GET_BODY_CHARSET(charset OUT)	n/a	Returns
$GET_FOLLOW_REDIRECT(max_redirects\ OUT)$	n/a	Current
GET_HEADER(r IN OUT, n, name OUT, value OUT)	n/a	Returns
GET_HEADER_BY_NAME(r IN OUT, name, value OUT, n)	n/a	Returns
GET_HEADER_COUNT(r IN OUT)	INTEGER	Returns
GET_RESPONSE(r IN OUT)	UTL_HTTP.RESP	Returns
GET_RESPONSE_ERROR_CHECK(enable OUT)	n/a	Returns
GET_TRANSFER_TIMEOUT(timeout OUT)	n/a	Returns
(r IN OUT, data OUT, remove_crlf)	n/a	Returns
READ_RAW(r IN OUT, data OUT, len)	n/a	Returns
READ_TEXT(r IN OUT, data OUT, len)	n/a	Returns
REQUEST(url)	VARCHAR2	Returns
REQUEST_PIECES(url, max_pieces)	UTL_HTTP. HTML_PIECES	Returns
SET_BODY_CHARSET(charset)	n/a	Sets the

SET_FOLLOW_REDIRECT(max_redirects)	n/a	Sets the
SET_FOLLOW_REDIRECT(r IN OUT, max_redirects)	n/a	Sets the
SET_HEADER(r IN OUT, name, value)	n/a	Sets the
SET_RESPONSE_ERROR_CHECK(enable)	n/a	Determin
SET_TRANSFER_TIMEOUT(timeout)	n/a	Sets the
SET_TRANSFER_TIMEOUT(r IN OUT, timeout)	n/a	Sets the
WRITE_LINE(r IN OUT, data)	n/a	Writes C
WRITE_RAW(r IN OUT, data)	n/a	Writes d
WRITE_TEXT(r IN OUT, data)	n/a	Writes d

Advanced Server's implementation of UTL_HTTP is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

Note

In Advanced Server, an HTTP 4xx or HTTP 5xx response produces a database error; in Oracle, this is configurable but FALSE by default.

In Advanced Server, the UTL_HTTP text interfaces expect the downloaded data to be in the database encoding. All currently-available interfaces are text interfaces. In Oracle, the encoding is detected from HTTP headers; in the absence of the header, the default is configurable and defaults to ISO-8859-1.

Advanced Server ignores all cookies it receives.

The UTL_HTTP exceptions that can be raised in Oracle are not recognized by Advanced Server. In addition, the error codes returned by Advanced Server are not the same as those returned by Oracle.

There are various public constants available with UTL_HTTP. These are listed in the following tables.

The following table contains UTL_HTTP public constants defining HTTP versions and port assignments.

HTTP VERSIONS	
HTTP_VERSION_1_0	CONSTANT VARCHAR2 $(64) := 'HTTP/1.0';$
HTTP_VERSION_1_1	CONSTANT VARCHAR2 $(64) := 'HTTP/1.1';$
STANDARD PORT ASSIGNMENTS	
DEFAULT_HTTP_PORT	CONSTANT INTEGER := 80 ;
DEFAULT_HTTPS_PORT	CONSTANT INTEGER := 443 ;

The following table contains UTL_HTTP public status code constants.

1XX INFORMATIONAL	
HTTP_CONTINUE	CONSTANT INTEGER := 100 ;
HTTP_SWITCHING_PROTOCOLS	CONSTANT INTEGER := 101 ;
HTTP_PROCESSING	CONSTANT INTEGER := 102 ;
2XX SUCCESS	
HTTP_OK	CONSTANT INTEGER := 200 ;
HTTP_CREATED	CONSTANT INTEGER := 201 ;
HTTP_ACCEPTED	CONSTANT INTEGER := 202 ;
HTTP_NON_AUTHORITATIVE_INFO	CONSTANT INTEGER := 203 ;
HTTP_NO_CONTENT	CONSTANT INTEGER := 204 ;
HTTP_RESET_CONTENT	CONSTANT INTEGER := 205 ;
HTTP_PARTIAL_CONTENT	CONSTANT INTEGER := 206 ;
HTTP_MULTI_STATUS	CONSTANT INTEGER := 207 ;
HTTP_ALREADY_REPORTED	CONSTANT INTEGER := 208 ;
HTTP_IM_USED	CONSTANT INTEGER := 226 ;
3XX REDIRECTION	
HTTP_MULTIPLE_CHOICES	CONSTANT INTEGER := 300 ;
HTTP_MOVED_PERMANENTLY	CONSTANT INTEGER := 301 ;
HTTP_FOUND	CONSTANT INTEGER := 302 ;
HTTP_SEE_OTHER	CONSTANT INTEGER := 303 ;
HTTP_NOT_MODIFIED	CONSTANT INTEGER := 304 ;
HTTP_USE_PROXY	CONSTANT INTEGER := 305 ;
HTTP_SWITCH_PROXY	CONSTANT INTEGER := 306 ;
HTTP_TEMPORARY_REDIRECT	CONSTANT INTEGER := 307 ;
HTTP_PERMANENT_REDIRECT	CONSTANT INTEGER := 308 ;

4XX CLIENT ERROR

HTTP_BAD_REQUEST	CONSTANT INTEGER := 400 ;
HTTP_UNAUTHORIZED	CONSTANT INTEGER := 401 ;
HTTP_PAYMENT_REQUIRED	CONSTANT INTEGER := 402 ;
HTTP_FORBIDDEN	CONSTANT INTEGER := 403 ;
HTTP_NOT_FOUND	CONSTANT INTEGER := 404 ;
HTTP_METHOD_NOT_ALLOWED	CONSTANT INTEGER := 405 ;
HTTP_NOT_ACCEPTABLE	CONSTANT INTEGER := 406 ;
HTTP_PROXY_AUTH_REQUIRED	CONSTANT INTEGER := 407 ;
HTTP_REQUEST_TIME_OUT	CONSTANT INTEGER := 408 ;
HTTP_CONFLICT	CONSTANT INTEGER := 409 ;
HTTP_GONE	CONSTANT INTEGER := 410 ;
HTTP_LENGTH_REQUIRED	CONSTANT INTEGER := 411 ;
HTTP_PRECONDITION_FAILED	CONSTANT INTEGER := 412 ;
HTTP_REQUEST_ENTITY_TOO_LARGE	CONSTANT INTEGER := 413 ;
HTTP_REQUEST_URI_TOO_LARGE	CONSTANT INTEGER := 414 ;
HTTP_UNSUPPORTED_MEDIA_TYPE	CONSTANT INTEGER := 415 ;

4XX CLIENT ERROR	
HTTP_REQ_RANGE_NOT_SATISFIABLE	CONSTANT INTEGER := 416 ;
HTTP_EXPECTATION_FAILED	CONSTANT INTEGER := 417 ;
HTTP_I_AM_A_TEAPOT	CONSTANT INTEGER := 418 ;
HTTP_AUTHENTICATION_TIME_OUT	CONSTANT INTEGER := 419 ;
HTTP_ENHANCE_YOUR_CALM	CONSTANT INTEGER := 420 ;
HTTP_UNPROCESSABLE_ENTITY	CONSTANT INTEGER := 422 ;
HTTP_LOCKED	CONSTANT INTEGER := 423 ;
HTTP_FAILED_DEPENDENCY	CONSTANT INTEGER := 424 ;
HTTP_UNORDERED_COLLECTION	CONSTANT INTEGER := 425 ;
HTTP_UPGRADE_REQUIRED	CONSTANT INTEGER := 426 ;
HTTP_PRECONDITION_REQUIRED	CONSTANT INTEGER := 428 ;
HTTP_TOO_MANY_REQUESTS	CONSTANT INTEGER := 429 ;
HTTP_REQUEST_HEADER_FIELDS_TOO_LARGE	CONSTANT INTEGER := 431 ;
HTTP_NO_RESPONSE	CONSTANT INTEGER := 444 ;
HTTP_RETRY_WITH	CONSTANT INTEGER := 449 ;
HTTP_BLOCKED_BY_WINDOWS_PARENTAL_CONTROLS	CONSTANT INTEGER := 450 ;
HTTP_REDIRECT	CONSTANT INTEGER := 451 ;
HTTP_REQUEST_HEADER_TOO_LARGE	CONSTANT INTEGER := 494 ;
HTTP_CERT_ERROR	CONSTANT INTEGER := 495 ;
HTTP_NO_CERT	CONSTANT INTEGER := 496 ;
HTTP_HTTP_TO_HTTPS	CONSTANT INTEGER := 497 ;
HTTP_CLIENT_CLOSED_REQUEST	CONSTANT INTEGER := 499 ;

5XX SERVER ERROR

HTTP_INTERNAL_SERVER_ERROR	CONSTANT INTEGER := 500 ;
HTTP_NOT_IMPLEMENTED	CONSTANT INTEGER := 501 ;
HTTP_BAD_GATEWAY	CONSTANT INTEGER := 502 ;
HTTP_SERVICE_UNAVAILABLE	CONSTANT INTEGER := 503 ;
HTTP_GATEWAY_TIME_OUT	CONSTANT INTEGER := 504 ;
HTTP_VERSION_NOT_SUPPORTED	CONSTANT INTEGER := 505 ;
HTTP_VARIANT_ALSO_NEGOTIATES	CONSTANT INTEGER := 506 ;
HTTP_INSUFFICIENT_STORAGE	CONSTANT INTEGER := 507 ;
HTTP_LOOP_DETECTED	CONSTANT INTEGER := 508 ;
HTTP_BANDWIDTH_LIMIT_EXCEEDED	CONSTANT INTEGER := 509 ;
HTTP_NOT_EXTENDED	CONSTANT INTEGER := 510 ;
HTTP_NETWORK_AUTHENTICATION_REQUIRED	CONSTANT INTEGER := 511 ;
HTTP_NETWORK_READ_TIME_OUT_ERROR	CONSTANT INTEGER := 598 ;
HTTP_NETWORK_CONNECT_TIME_OUT_ERROR	CONSTANT INTEGER := 599 ;

HTML_PIECES

The UTL_HTTP package declares a type named HTML_PIECES, which is a table of type VARCHAR2 (2000) indexed by BINARY INTEGER. A value of this type is returned by the REQUEST_PIECES function.

TYPE html_pieces IS TABLE OF VARCHAR2(2000) INDEX BY BINARY_INTEGER;

REQ

The REQ record type holds information about each HTTP request.

```
TYPE req IS RECORD (

url VARCHAR2(32767), -- URL to be accessed

method VARCHAR2(64), -- HTTP method

http_version VARCHAR2(64), -- HTTP version

private_hndl INTEGER -- Holds handle for this request
);
```

RESP

The RESP record type holds information about the response from each HTTP request.

```
TYPE resp IS RECORD (
status_code INTEGER, -- HTTP status code
reason_phrase VARCHAR2(256), -- HTTP response reason phrase
http_version VARCHAR2(64), -- HTTP version
private_hndl INTEGER -- Holds handle for this response
);
```

BEGIN_REQUEST

The BEGIN_REQUEST function initiates a new HTTP request. A network connection is established to the web server with the specified URL. The signature is:

```
BEGIN_REQUEST(<url> IN VARCHAR2, <method> IN VARCHAR2
DEFAULT
'GET ', <http_version> IN VARCHAR2 DEFAULT NULL) RETURN
UTL HTTP.REQ
```

The BEGIN_REQUEST function returns a record of type UTL_HTTP.REQ.

Parameters

<url>

<url> is the Uniform Resource Locator from which UTL_HTTP will
return content.

<method>

<method> is the HTTP method to be used. The default is GET.

<http_version>

<http_version> is the HTTP protocol version sending the request.
The specified values should be either HTTP/1.0 or HTTP/1.1. The
default is null in which case the latest HTTP protocol version supported by the UTL HTTP package is used which is 1.1.

END_REQUEST

The END_REQUEST procedure terminates an HTTP request. Use the END_REQUEST procedure to terminate an HTTP request without completing it and waiting for the response. The normal process is to begin the request, get the response, then close the response. The signature is:

```
END_REQUEST(<r> IN OUT UTL_HTTP.REQ)
```

Parameters

<r>

<r> is the HTTP request record.

END_RESPONSE

The END_RESPONSE procedure terminates the HTTP response. The END_RESPONSE procedure completes the HTTP request and response. This is the normal method to end the request and response process. The signature is:

```
END_RESPONSE(<r> IN OUT UTL_HTTP.RESP)
```

Parameters

<r>

<r> is the HTTP response record.

GET_BODY_CHARSET

The GET_BODY_CHARSET program is available in the form of both a procedure and a function. A call to GET_BODY_CHARSET returns the default character set of the body of future HTTP requests.

The procedure signature is:

```
GET BODY CHARSET(<charset> OUT VARCHAR2)
```

The function signature is:

GET_BODY_CHARSET() RETURN VARCHAR2

This function returns a VARCHAR2 value.

Parameters

```
<charset>
```

<charset> is the character set of the body.

Examples

The following is an example of the GET_BODY_CHARSET function.

```
edb=# SELECT UTL_HTTP.GET_BODY_CHARSET() FROM DUAL;
get_body_charset
------
ISO-8859-1
(1 row)
```

${\bf GET_FOLLOW_REDIRECT}$

The GET_FOLLOW_REDIRECT procedure returns the current setting for the maximum number of redirections allowed. The signature is:

```
GET_FOLLOW_REDIRECT(<max_redirects> OUT INTEGER)
```

Parameters

```
<max_redirects>
```

<max_redirects> is maximum number of redirections allowed.

GET_HEADER

The GET_HEADER procedure returns the nth header of the HTTP response. The signature is:

```
GET_HEADER(<r> IN OUT UTL_HTTP.RESP, <n> INTEGER, <name>
OUT
VARCHAR2, <value> OUT VARCHAR2)
```

Parameters

<r>

<r> is the HTTP response record.

<n>

<n> is the nth header of the HTTP response record to retrieve.

<name>

<name> is the name of the response header.

<value>

<value> is the value of the response header.

Examples

The following example retrieves the header count, then the headers.

```
DECLARE
   v_req
                UTL_HTTP.REQ;
                UTL_HTTP.RESP;
   v_resp
                 VARCHAR2(30);
   v name
                VARCHAR2(200);
   v_value
   v_header_cnt INTEGER;
BEGIN
 -- Initiate request and get response
   v_req := UTL_HTTP.BEGIN_REQUEST('www.enterprisedb.com');
   v_resp := UTL_HTTP.GET_RESPONSE(v_req);
 -- Get header count
   v_header_cnt := UTL_HTTP.GET_HEADER_COUNT(v_resp);
   DBMS_OUTPUT.PUT_LINE('Header Count: ' || v_header_cnt);
 -- Get all headers
   FOR i IN 1 .. v_header_cnt LOOP
       UTL_HTTP.GET_HEADER(v_resp, i, v_name, v_value);
       DBMS_OUTPUT.PUT_LINE(v_name || ': ' || v_value);
   END LOOP;
 -- Terminate request
   UTL_HTTP.END_RESPONSE(v_resp);
END;
The following is the output from the example.
Header Count: 23
Age: 570
Cache-Control: must-revalidate
Content-Type: text/html; charset=utf-8
Date: Wed, 30 Apr 2015 14:57:52 GMT
ETag: "aab02f2bd2d696eed817ca89ef411dda"
Expires: Sun, 19 Nov 1978 05:00:00 GMT
Last-Modified: Wed, 30 Apr 2015 14:15:49 GMT
RTSS: 1-1307-3
Server: Apache/2.2.3 (Red Hat)
Vary: Accept-Encoding
Via: 1.1 varnish
X-EDB-Backend: ec
X-EDB-Cache: HIT
```

```
X-EDB-Cache-Address: 10.31.162.212
X-EDB-Cache-Server: ip-10-31-162-212
X-EDB-Cache-TTL: 600.000
X-EDB-Cacheable: MAYBE: The user has a cookie of some sort. Maybe it's double choc-chip!
X-EDB-Do-GZIP: false
X-Powered-By: PHP/5.2.17
X-Varnish: 484508634 484506789
transfer-encoding: chunked
Connection: keep-alive
GET_HEADER_BY_NAME
The GET_HEADER_BY_NAME procedure returns the header of the HTTP response
according to the specified name. The signature is:
     GET_HEADER_BY_NAME(<r> IN OUT UTL_HTTP.RESP, <name>
     VARCHAR2,
     <value> OUT VARCHAR2, <n> INTEGER DEFAULT 1)
Parameters
<r>
     <r> is the HTTP response record.
<name>
     <name> is the name of the response header to retrieve.
<value>
     <value> is the value of the response header.
<n>
     <n> is the nth header of the HTTP response record to retrieve ac-
     cording to the values specified by <name>. The default is 1.
Examples
The following example retrieves the header for Content-Type.
DECLARE
    v req
                     UTL HTTP.REQ;
    v_resp
                     UTL_HTTP.RESP;
    v_name
                     VARCHAR2(30) := 'Content-Type';
                     VARCHAR2(200);
    v_value
BEGIN
    v_req := UTL_HTTP.BEGIN_REQUEST('www.enterprisedb.com');
    v_resp := UTL_HTTP.GET_RESPONSE(v_req);
    UTL_HTTP.GET_HEADER_BY_NAME(v_resp, v_name, v_value);
```

DBMS_OUTPUT.PUT_LINE(v_name || ': ' || v_value);

```
UTL_HTTP.END_RESPONSE(v_resp);
END;
```

Content-Type: text/html; charset=utf-8

GET_HEADER_COUNT

The GET_HEADER_COUNT function returns the number of HTTP response headers. The signature is:

```
GET_HEADER_COUNT(<r> IN OUT UTL_HTTP.RESP) RETURN
INTEGER
```

This function returns an INTEGER value.

Parameters

<r>

<r> is the HTTP response record.

GET_RESPONSE

The GET_RESPONSE function sends the network request and returns any HTTP response. The signature is:

GET_RESPONSE(<r> IN OUT UTL_HTTP.REQ) RETURN UTL_HTTP.RESP

This function returns a UTL_HTTP.RESP record.

Parameters

<r>

<r> is the HTTP request record.

GET_RESPONSE_ERROR_CHECK

The <code>GET_RESPONSE_ERROR_CHECK</code> procedure returns whether or not response error check is set. The signature is:

GET_RESPONSE_ERROR_CHECK(<enable> OUT BOOLEAN)

Parameters

<enable>

 \leq enable> returns TRUE if response error check is set, otherwise it returns FALSE.

GET_TRANSFER_TIMEOUT

The GET_TRANSFER_TIMEOUT procedure returns the current, default transfer timeout setting for HTTP requests. The signature is:

```
GET_TRANSFER_TIMEOUT(<timeout> OUT INTEGER)
```

Parameters

<timeout>

<timeout> is the transfer timeout setting in seconds.

READ_LINE

The READ_LINE procedure returns the data from the HTTP response body in text form until the end of line is reached. A CR character, a LF character, a CR LF sequence, or the end of the response body constitutes the end of line. The signature is:

```
READ_LINE(<r> IN OUT UTL_HTTP.RESP, <data> OUT VARCHAR2,
<remove_crlf> BOOLEAN DEFAULT FALSE)
```

Parameters

<r>

 $\langle r \rangle$ is the HTTP response record.

<data>

<data> is the response body in text form.

<remove_crlf>

Set <remove_crlf> to TRUE to remove new line characters, otherwise set to FALSE. The default is FALSE.

Examples

The following example retrieves and displays the body of the specified website.

DECLARE

```
v_req     UTL_HTTP.REQ;
v_resp     UTL_HTTP.RESP;
v_value     VARCHAR2(1024);

BEGIN

v_req := UTL_HTTP.BEGIN_REQUEST('http://www.enterprisedb.com');
v_resp := UTL_HTTP.GET_RESPONSE(v_req);
LOOP
     UTL_HTTP.READ_LINE(v_resp, v_value, TRUE);
     DBMS_OUTPUT.PUT_LINE(v_value);
END LOOP;
EXCEPTION
```

```
WHEN OTHERS THEN
            UTL_HTTP.END_RESPONSE(v_resp);
END;
The following is the output.
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"</pre>
  "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/xhtml" xml:lang="en" lang="en" dir="ltr">
  <!-- HEAD _____
  <head>
<meta http-equiv="Content-Type" content="text/html; charset=utf-8" />
    <title>EnterpriseDB | The Postgres Database Company</title>
    <meta http-equiv="Content-Type" content="text/html; charset=utf-8" />
<meta name="keywords" content="postgres, postgresql, postgresql installer, mysql migration,</pre>
<meta name="description" content="The leader in open source database products, services, su
<meta name="abstract" content="The Enterprise PostgreSQL Company" />
<link rel="EditURI" type="application/rsd+xml" title="RSD" href="http://www.enterprisedb.com</pre>
<link rel="alternate" type="application/rss+xml" title="EnterpriseDB RSS" href="http://www.o</pre>
<link rel="shortcut icon" href="/sites/all/themes/edb_pixelcrayons/favicon.ico" type="image,</pre>
    <link type="text/css" rel="stylesheet" media="all" href="/sites/default/files/css/css_di</pre>
<!--[if IE 6]>
<link type="text/css" rel="stylesheet" media="all" href="/sites/all/themes/oho_basic/css/iee</pre>
<![endif]-->
<!--[if IE 7]>
<link type="text/css" rel="stylesheet" media="all" href="/sites/all/themes/oho_basic/css/ie"</pre>
<![endif]-->
    <script type="text/javascript" src="/sites/default/files/js/js_74d97b1176812e2fd6e43d62!</pre>
<script type="text/javascript">
<!--//--><! [CDATA [//><!--
READ_RAW
```

The READ_RAW procedure returns the data from the HTTP response body in binary form. The number of bytes returned is specified by the <len> parameter. The signature is:

```
READ_RAW(<r> IN OUT UTL_HTTP.RESP, <data> OUT RAW, <len>
INTEGER)
```

Parameters

<r>

<r> is the HTTP response record.

<data>

<data> is the response body in binary form.

<len>

Set <len> to the number of bytes of data to be returned.

Examples

The following example retrieves and displays the first 150 bytes in binary form.

DECLARE

```
v_req     UTL_HTTP.REQ;
v_resp     UTL_HTTP.RESP;
v_data     RAW;

BEGIN

v_req := UTL_HTTP.BEGIN_REQUEST('http://www.enterprisedb.com');
v_resp := UTL_HTTP.GET_RESPONSE(v_req);
UTL_HTTP.READ_RAW(v_resp, v_data, 150);
DBMS_OUTPUT.PUT_LINE(v_data);
UTL_HTTP.END_RESPONSE(v_resp);
END;
```

The following is the output from the example.

 $\label{eq:constraint} $$ x3c21444f43545950452068746d6c205055424c494320222d2f2f5733432f2f445444205848544d4c20312e30205374726963742f2f454e220d0a202022687474703a2f2f7777772e77332e6f72672f54522f7868746d6c312f4454442f7868746d6c312d7374726963742e647464223e0d0a3c68746d6c20786d6c6e733d22687474703a2f2f7777772e77332e6f72672f313939392f$

$READ_TEXT$

The READ_TEXT procedure returns the data from the HTTP response body in text form. The maximum number of characters returned is specified by the <le>> parameter. The signature is:

```
READ_TEXT(<r> IN OUT UTL_HTTP.RESP, <data> OUT VARCHAR2,
<len> INTEGER)
```

Parameters

<r>

<r> is the HTTP response record.

<data>

<data> is the response body in text form.

<len>

Set <len> to the maximum number of characters to be returned.

Examples

The following example retrieves the first 150 characters.

```
DECLARE
    v_req
                    UTL_HTTP.REQ;
                    UTL_HTTP.RESP;
    v_resp
                    VARCHAR2(150);
    v data
BEGIN
    v req := UTL HTTP.BEGIN REQUEST('http://www.enterprisedb.com');
    v_resp := UTL_HTTP.GET_RESPONSE(v_req);
    UTL_HTTP.READ_TEXT(v_resp, v_data, 150);
    DBMS_OUTPUT.PUT_LINE(v_data);
    UTL HTTP.END RESPONSE(v resp);
END;
The following is the output.
<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"</pre>
  "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/</pre>
```

REQUEST

The REQUEST function returns the first 2000 bytes retrieved from a user-specified URL. The signature is:

```
REQUEST(<url> IN VARCHAR2) RETURN VARCHAR2
```

If the data found at the given URL is longer than 2000 bytes, the remainder will be discarded. If the data found at the given URL is shorter than 2000 bytes, the result will be shorter than 2000 bytes.

Parameters

<url>

<ur>
is the Uniform Resource Locator from which UTL_HTTP will return content.

Example

The following command returns the first 2000 bytes retrieved from the EnterpriseDB website:

```
SELECT UTL_HTTP.REQUEST('http://www.enterprisedb.com/') FROM DUAL;
```

REQUEST_PIECES

The REQUEST_PIECES function returns a table of 2000-byte segments retrieved from an URL. The signature is:

REQUEST_PIECES(<url> IN VARCHAR2, <max_pieces> NUMBER IN DEFAULT 32767) RETURN UTL_HTTP.HTML_PIECES

Parameters

<url>

<ur><url> is the Uniform Resource Locator from which UTL_HTTP will return content.

<max_pieces>

<max_pieces> specifies the maximum number of 2000-byte segments
that the REQUEST_PIECES function will return. If <max_pieces>
specifies more units than are available at the specified <url>, the
final unit will contain fewer bytes.

Example

The following example returns the first four 2000 byte segments retrieved from the EnterpriseDB website:

DECLARE

```
result UTL_HTTP.HTML_PIECES;
BEGIN
result := UTL_HTTP.REQUEST_PIECES('http://www.enterprisedb.com/', 4);
END
```

SET_BODY_CHARSET

The SET_BODY_CHARSET procedure sets the default character set of the body of future HTTP requests. The signature is:

```
SET_BODY_CHARSET(<charset> VARCHAR2 DEFAULT NULL)
```

Parameters

<charset>

<charset> is the character set of the body of future requests. The
default is null in which case the database character set is assumed.

SET_FOLLOW_REDIRECT

The SET_FOLLOW_REDIRECT procedure sets the maximum number of times the HTTP redirect instruction is to be followed in the response to this request or future requests. This procedures has two signatures:

```
SET_FOLLOW_REDIRECT(<max_redirects> IN INTEGER DEFAULT
3)
```

and

```
SET_FOLLOW_REDIRECT(<r> IN OUT UTL_HTTP.REQ, <max_redirects>
IN INTEGER DEFAULT 3)
```

Use the second form to change the maximum number of redirections for an individual request that a request inherits from the session default settings.

Parameters

<r>

<r> is the HTTP request record.

<max redirects>

<max_redirects> is maximum number of redirections allowed. Set to 0 to disable redirections. The default is 3.

SET_HEADER

The SET_HEADER procedure sets the HTTP request header. The signature is:

```
SET_HEADER(<r> IN OUT UTL_HTTP.REQ, <name> IN VARCHAR2,
<value>
IN VARCHAR2 DEFAULT NULL)
```

Parameters

<r>

<r> is the HTTP request record.

<name>

<name> is the name of the request header.

<value>

<value> is the value of the request header. The default is null.

SET_RESPONSE_ERROR_CHECK

The SET_RESPONSE_ERROR_CHECK procedure determines whether or not HTTP 4xx and 5xx status codes returned by the GET_RESPONSE function should be interpreted as errors. The signature is:

SET_RESPONSE_ERROR_CHECK(<enable> IN BOOLEAN DEFAULT
FALSE)

Parameters

<enable>

Set <enable> to TRUE if HTTP 4xx and 5xx status codes are to be treated as errors, otherwise set to FALSE. The default is FALSE.

SET_TRANSFER_TIMEOUT

The SET_TRANSFER_TIMEOUT procedure sets the default, transfer timeout setting for waiting for a response from an HTTP request. This procedure has two signatures:

```
SET_TRANSFER_TIMEOUT(<timeout> IN INTEGER DEFAULT 60)
```

and

```
SET_TRANSFER_TIMEOUT(<r> IN OUT UTL_HTTP.REQ, <timeout>
IN INTEGER DEFAULT 60)
```

Use the second form to change the transfer timeout setting for an individual request that a request inherits from the session default settings.

Parameters

<r>

<r> is the HTTP request record.

<timeout>

<timeout> is the transfer timeout setting in seconds for HTTP requests. The default is 60 seconds.

WRITE_LINE

The WRITE_LINE procedure writes data to the HTTP request body in text form; the text is terminated with a CRLF character pair. The signature is:

```
WRITE_LINE(<r> IN OUT UTL_HTTP.REQ, <data> IN VARCHAR2)
```

Parameters

<r>

<r> is the HTTP request record.

<data>

<data> is the request body in TEXT form.

Example

The following example writes data (Account balance \$500.00) in text form to the request body to be sent using the HTTP POST method. The data is sent to a hypothetical web application (post.php) that accepts and processes data.

DECLARE

```
v_req     UTL_HTTP.REQ;
v_resp     UTL_HTTP.RESP;
BEGIN
v_req := UTL_HTTP.BEGIN_REQUEST('http://www.example.com/post.php',
```

```
'POST');
UTL_HTTP.SET_HEADER(v_req, 'Content-Length', '23');
UTL_HTTP.WRITE_LINE(v_req, 'Account balance $500.00');
v_resp := UTL_HTTP.GET_RESPONSE(v_req);
DBMS_OUTPUT.PUT_LINE('Status Code: ' || v_resp.status_code);
DBMS_OUTPUT.PUT_LINE('Reason Phrase: ' || v_resp.reason_phrase);
UTL_HTTP.END_RESPONSE(v_resp);
END;
```

Assuming the web application successfully processed the POST method, the following output would be displayed:

Status Code: 200 Reason Phrase: OK

$WRITE_RAW$

The WRITE_RAW procedure writes data to the HTTP request body in binary form. The signature is:

```
WRITE_RAW(<r> IN OUT UTL_HTTP.REQ, <data> IN RAW)
```

Parameters

<r>

<r> is the HTTP request record.

<data>

<data> is the request body in binary form.

Example

The following example writes data in binary form to the request body to be sent using the HTTP POST method to a hypothetical web application that accepts and processes such data.

```
DECLARE
```

END;

The text string shown in the HEXTORAW function is the hexadecimal translation of the text Testing POST method in HTTP request.

Assuming the web application successfully processed the POST method, the following output would be displayed:

Status Code: 200 Reason Phrase: OK

WRITE TEXT

The WRITE_TEXT procedure writes data to the HTTP request body in text form. The signature is:

```
WRITE TEXT(<r> IN OUT UTL HTTP.REQ, <data> IN VARCHAR2)
```

Parameters

<r>

<r> is the HTTP request record.

<data>

<data> is the request body in text form.

Example

The following example writes data (Account balance \$500.00) in text form to the request body to be sent using the HTTP POST method. The data is sent to a hypothetical web application (post.php) that accepts and processes data.

DECLARE

Assuming the web application successfully processed the POST method, the following output would be displayed:

Status Code: 200 Reason Phrase: OK

4.23 UTL_MAIL

The UTL_MAIL package provides the capability to manage e-mail. Advanced Server supports the following procedures:

Function/Procedure

```
SEND(<sender>, <recipients>, <cc>, <bcc>, <subject>, <message> [, <mime_type> [, <priority> ]]) \\ SEND_ATTACH_RAW(<sender>, <recipients>, <cc>, <bcc>, <subject>, <message>, <mime_type>, < SEND_ATTACH_VARCHAR2(<sender>, <message>, <mime_type>, < SEND_ATTACH_VARCHAR2(<sender), <message>, <mime_type>, < SEND_ATTACH_VARCHAR2(<sender), <message>, <mime_type>, < SEND_ATTACH_VARCHAR2(<sender), <message>, <mime_type>, < SEND_ATTACH_VARCHAR2(<sender), <message>, <mime_type>, <mime_type>, <message>, <mime_type>, <mime_type>, <mime_type>
```

Note

An administrator must grant execute privileges to each user or group before they can use this package.

SEND

The SEND procedure provides the capability to send an e-mail to an SMTP server.

```
SEND(<sender> VARCHAR2, <recipients> VARCHAR2, <cc> VARCHAR2,
<bcc> VARCHAR2, <subject> VARCHAR2, <message> VARCHAR2 [, <mime_type>
VARCHAR2 [, <priority> PLS_INTEGER ]])
```

Parameters

<sender>

E-mail address of the sender.

<recipients>

Comma-separated e-mail addresses of the recipients.

<cc>

Comma-separated e-mail addresses of copy recipients.

<bcc>

Comma-separated e-mail addresses of blind copy recipients.

<subject>

Subject line of the e-mail.

<message>

Body of the e-mail.

<mime_type>

```
Mime type of the message. The default is text/plain; charset=us-ascii.
```

<priority>

Priority of the e-mail The default is 3.

Examples

The following anonymous block sends a simple e-mail message.

DECLARE

```
v sender
                    VARCHAR2(30);
                    VARCHAR2(60);
    v_recipients
   v_subj
                    VARCHAR2(20);
                    VARCHAR2(200);
    v_msg
BEGIN
    v_sender := 'jsmith@enterprisedb.com';
    v_recipients := 'ajones@enterprisedb.com,rrogers@enterprisedb.com';
    v_subj := 'Holiday Party';
    v_msg := 'This year''s party is scheduled for Friday, Dec. 21 at ' ||
             '6:00 PM. Please RSVP by Dec. 15th.';
    UTL_MAIL.SEND(v_sender,v_recipients,NULL,NULL,v_subj,v_msg);
END;
```

SEND ATTACH RAW

The SEND_ATTACH_RAW procedure provides the capability to send an e-mail to an SMTP server with an attachment containing either BYTEA data or a large object (identified by the large object's OID). The call to SEND_ATTACH_RAW can be written in two ways:

```
SEND_ATTACH_RAW(<sender> VARCHAR2, <recipients> VARCHAR2, <cc> VARCHAR2, <bcc> VARCHAR2, <subject> VARCHAR2, <message> VARCHAR2, <mime_type> VARCHAR2, <priority> PLS_INTEGER, <attachment> BYTEA[, <att_inline> BOOLEAN [, <att_mime_type> VARCHAR2[, <att_filename> VARCHAR2]]])
```

or

```
SEND_ATTACH_RAW(<sender> VARCHAR2, <recipients> VARCHAR2, <cc> VARCHAR2, <bcc> VARCHAR2, <subject> VARCHAR2, <message> VARCHAR2, <mime_type> VARCHAR2, <priority> PLS_INTEGER, <attachment> OID [, <att_inline> BOOLEAN [, <att_mime_type> VARCHAR2 [, <att_filename> VARCHAR2 ]]])
```

Parameters

<sender>

E-mail address of the sender.

<recipients>

Comma-separated e-mail addresses of the recipients.

<cc>

Comma-separated e-mail addresses of copy recipients.

<bcc>

Comma-separated e-mail addresses of blind copy recipients.

<subject>

Subject line of the e-mail.

<message>

Body of the e-mail.

<mime_type>

Mime type of the message. The default is text/plain; charset=us-ascii.

<priority>

Priority of the e-mail. The default is 3.

<attachment>

The attachment.

<att inline>

If set to TRUE, then the attachment is viewable inline, FALSE otherwise. The default is TRUE.

<att_mime_type>

Mime type of the attachment. The default is application/octet.

<att filename>

The file name containing the attachment. The default is null.

SEND_ATTACH_VARCHAR2

The SEND_ATTACH_VARCHAR2 procedure provides the capability to send an e-mail to an SMTP server with a text attachment.

SEND_ATTACH_VARCHAR2(<sender> VARCHAR2, <recipients> VARCHAR2, <cc> VARCHAR2,

VARCHAR2,

VARCHAR2, <mime_type> VARCHAR2, <priority> PLS_INTEGER, <attachment> VARCHAR2 [, <att_inline> BOOLEAN [, <att_mime_type> VARCHAR2 [, <att_filename> VARCHAR2]]])

Parameters

<sender>

E-mail address of the sender.

<recipients>

Comma-separated e-mail addresses of the recipients.

<cc>

Comma-separated e-mail addresses of copy recipients.

<bcc>

Comma-separated e-mail addresses of blind copy recipients.

<subject>

Subject line of the e-mail.

<message>

Body of the e-mail.

<mime_type>

Mime type of the message. The default is text/plain; charset=us-ascii.

<priority>

Priority of the e-mail The default is 3.

<attachment>

The VARCHAR2 attachment.

<att_inline>

If set to TRUE, then the attachment is viewable inline, FALSE otherwise. The default is TRUE.

<att_mime_type>

Mime type of the attachment. The default is text/plain; charset=us-ascii.

<att_filename>

The file name containing the attachment. The default is $\verb"null"$.

4.24 UTL RAW

The UTL_RAW package allows you to manipulate or retrieve the length of raw data types.

Note

An administrator must grant execute privileges to each user or group before they can use this package.

Function/Procedure	Function or Procedure
CAST_TO_RAW(c IN VARCHAR2)	Function
CAST_TO_VARCHAR2(r IN RAW)	Function
CONCAT(r1 IN RAW, r2 IN RAW, r3 IN RAW,)	Function
CONVERT(r IN RAW, to_charset IN VARCHAR2, from_charset IN VARCHAR2	Function
LENGTH(r IN RAW)	Function
SUBSTR(r IN RAW, pos IN INTEGER, len IN INTEGER)	Function

Advanced Server's implementation of UTL_RAW is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

CAST_TO_RAW

The CAST_TO_RAW function converts a VARCHAR2 string to a RAW value. The signature is:

```
CAST_TO_RAW(<c> VARCHAR2)
```

The function returns a RAW value if you pass a non-NULL value; if you pass a NULL value, the function will return NULL.

Parameters

<c>

The VARCHAR2 value that will be converted to RAW.

Example

The following example uses the CAST_TO_RAW function to convert a VARCHAR2 string to a RAW value:

```
DECLARE
  v VARCHAR2;
  r RAW;
BEGIN
  v := 'Accounts';
  dbms_output.put_line(v);
  r := UTL_RAW.CAST_TO_RAW(v);
```

```
dbms_output.put_line(r);
END;
```

The result set includes the content of the original string and the converted RAW value:

Accounts

\x4163636f756e7473

CAST TO VARCHAR2

The CAST_TO_VARCHAR2 function converts RAW data to VARCHAR2 data. The signature is:

```
CAST_TO_VARCHAR2(<r> RAW)
```

The function returns a VARCHAR2 value if you pass a non-NULL value; if you pass a NULL value, the function will return NULL.

Parameters

<r>

The RAW value that will be converted to a VARCHAR2 value.

Example

The following example uses the CAST_TO_VARCHAR2 function to convert a RAW value to a VARCHAR2 string:

```
DECLARE
  r RAW;
  v VARCHAR2;
BEGIN
  r := '\x4163636f756e7473'
  dbms_output.put_line(v);
  v := UTL_RAW.CAST_TO_VARCHAR2(r);
  dbms_output.put_line(r);
FND:
```

The result set includes the content of the original string and the converted RAW value:

```
\x4163636f756e7473
Accounts
```

CONCAT

The ${\tt CONCAT}$ function concatenates multiple ${\tt RAW}$ values into a single ${\tt RAW}$ value. The signature is:

```
CONCAT(<r1> RAW, <r2> RAW, <r3> RAW,...)
```

The function returns a RAW value. Unlike the Oracle implementation, the Advanced Server implementation is a variadic function, and does not place a restriction on the number of values that can be concatenated.

Parameters

```
<r1, r2, r3,...>
```

The RAW values that CONCAT will concatenate.

Example

The following example uses the CONCAT function to concatenate multiple RAW values into a single RAW value:

```
| SELECT UTL_RAW.CAST_TO_VARCHAR2(UTL_RAW.CONCAT('\x61', '\x62', | '\x63')) FROM DUAL;
| concat
| -------
| abc
| (1 row)
```

The result (the concatenated values) is then converted to VARCHAR2 format by the CAST_TO_VARCHAR2 function.

CONVERT

The CONVERT function converts a string from one encoding to another encoding and returns the result as a RAW value. The signature is:

```
CONVERT(<r> RAW, <to_charset> VARCHAR2, <from_charset>
VARCHAR2)
```

The function returns a RAW value.

Parameters

<r>

The RAW value that will be converted.

```
<to_charset>
```

The name of the encoding to which <r> will be converted.

```
<from_charset>
```

The name of the encoding from which <r> will be converted.

Example

The following example uses the UTL_RAW.CAST_TO_RAW function to convert a VARCHAR2 string (Accounts) to a raw value, and then convert the value from UTF8 to LATIN7, and then from LATIN7 to UTF8:

```
DECLARE
 r RAW;
 v VARCHAR2;
BEGIN
 v:= 'Accounts';
 dbms_output.put_line(v);
 r:= UTL_RAW.CAST_TO_RAW(v);
 dbms_output.put_line(r);
 r:= UTL_RAW.CONVERT(r, 'UTF8', 'LATIN7');
 dbms_output.put_line(r);
 r:= UTL_RAW.CONVERT(r, 'LATIN7', 'UTF8');
 dbms_output.put_line(r);
values:
```

The example returns the VARCHAR2 value, the RAW value, and the converted

Accounts

\x4163636f756e7473 \x4163636f756e7473 \x4163636f756e7473

LENGTH

The LENGTH function returns the length of a RAW value. The signature is:

```
LENGTH(<r> RAW)
```

The function returns a RAW value.

Parameters

<r>

The RAW value that LENGTH will evaluate.

Example

The following example uses the LENGTH function to return the length of a RAW value:

```
SELECT UTL_RAW.LENGTH(UTL_RAW.CAST_TO_RAW('Accounts')) FROM DUAL;
length
-----
```

(1 row)

The following example uses the LENGTH function to return the length of a RAW value that includes multi-byte characters:

```
SELECT UTL_RAW.LENGTH(UTL_RAW.CAST_TO_RAW('hello'));
length
```

```
5
(1 row)
UTL_RAW_SUBSTR
```

SUBSTR

The SUBSTR function returns a substring of a RAW value. The signature is:

```
SUBSTR (<r> RAW, <pos> INTEGER, <len> INTEGER)
```

This function returns a RAW value.

Parameters

<r>

The RAW value from which the substring will be returned.

<pos>

The position within the RAW value of the first byte of the returned substring.

- If <pos> is 0 or 1, the substring begins at the first byte of the RAW value.
- If <pos> is greater than one, the substring begins at the first byte specified by <pos>. For example, if <pos> is 3, the substring begins at the third byte of the value.
- If <pos> is negative, the substring begins at <pos> bytes from the end of the source value. For example, if <pos> is -3, the substring begins at the third byte from the end of the value.

<len>

The maximum number of bytes that will be returned.

Example

The following example uses the SUBSTR function to select a substring that begins 3 bytes from the start of a RAW value:

```
SELECT UTL_RAW.SUBSTR(UTL_RAW.CAST_TO_RAW('Accounts'), 3, 5) FROM DUAL;
substr
-----
count
(1 row)
```

The following example uses the SUBSTR function to select a substring that starts 5 bytes from the end of a RAW value:

```
SELECT UTL_RAW.SUBSTR(UTL_RAW.CAST_TO_RAW('Accounts'), -5 , 3) FROM DUAL; substr
```

oun (1 row)

4.25 UTL SMTP

The UTL_SMTP package provides the capability to send e-mails over the Simple Mail Transfer Protocol (SMTP).

Note

An administrator must grant execute privileges to each user or group before they can use this package.

Function/Procedure	Function or Procedure	Return Type	Descripti
CLOSE_DATA(c IN OUT)	Procedure	n/a	Ends an
COMMAND(c IN OUT, cmd [, arg])	Both	REPLY	Execute
COMMAND_REPLIES(c IN OUT, cmd [, arg])	Function	REPLIES	Execute
DATA(c IN OUT, body VARCHAR2)	Procedure	n/a	Specify t
EHLO(c IN OUT, domain)	Procedure	n/a	Perform
HELO(c IN OUT, domain)	Procedure	n/a	Perform
HELP(c IN OUT [, command])	Function	REPLIES	Send the
MAIL(c IN OUT, sender [, parameters])	Procedure	n/a	Start a n
NOOP(c IN OUT)	Both	REPLY	Send the
OPEN_CONNECTION(host [, port [, tx_timeout]])	Function	CONNECTION	Open a c
OPEN_DATA(c IN OUT)	Both	REPLY	Send the
QUIT(c IN OUT)	Procedure	n/a	Terminat
RCPT(c IN OUT, recipient [, parameters])	Procedure	n/a	Specify t
RSET(c IN OUT)	Procedure	n/a	Terminat
VRFY(c IN OUT, recipient)	Function	REPLY	Validate
WRITE_DATA(c IN OUT, data)	Procedure	n/a	Write a p

Advanced Server's implementation of UTL_SMTP is a partial implementation when compared to Oracle's version. Only those functions and procedures listed in the table above are supported.

The following table lists the public variables available in the UTL_SMTP package.

Public Variables	Data Type	Value	Description
connection	RECORD		Description of an SMTP connection.
reply	RECORD		SMTP reply line.

CONNECTION

The CONNECTION record type provides a description of an SMTP connection.

REPLY/REPLIES

The REPLY record type provides a description of an SMTP reply line. REPLIES is a table of multiple SMTP reply lines.

CLOSE_DATA

The CLOSE_DATA procedure terminates an e-mail message by sending the following sequence:

```
<CR><LF>. <CR><LF>
```

This is a single period at the beginning of a line.

```
CLOSE DATA(<c> IN OUT CONNECTION)
```

Parameters

<c>

The SMTP connection to be closed.

COMMAND

The COMMAND procedure provides the capability to execute an SMTP command. If you are expecting multiple reply lines, use COMMAND_REPLIES.

```
<reply> REPLY COMMAND(<c> IN OUT CONNECTION, <cmd>
VARCHAR2
[, <arg> VARCHAR2 ])
COMMAND(<c> IN OUT CONNECTION, <cmd> VARCHAR2 [, <arg> VARCHAR2 ])
```

Parameters

<c>

The SMTP connection to which the command is to be sent.

<cmd>

The SMTP command to be processed.

<arg>

An argument to the SMTP command. The default is null.

<reply>

SMTP reply to the command. If SMTP returns multiple replies, only the last one is returned in <reply>.

See Reply/Replies <reply/replies> for a description of REPLY and REPLIES.

COMMAND_REPLIES

The COMMAND_REPLIES function processes an SMTP command that returns multiple reply lines. Use COMMAND if only a single reply line is expected.

<replies> REPLIES COMMAND(<c> IN OUT CONNECTION, <cmd>
VARCHAR2

[, <arg> VARCHAR2])

Parameters

<c>

The SMTP connection to which the command is to be sent.

<cmd>

The SMTP command to be processed.

<arg>

An argument to the SMTP command. The default is null.

<replies>

SMTP reply lines to the command. See Reply/Replies <reply/replies> for a description of REPLY and REPLIES.

DATA

The DATA procedure provides the capability to specify the body of the e-mail message. The message is terminated with a <CR><LF>.<CR><LF> sequence.

DATA(<c> IN OUT CONNECTION, <body> VARCHAR2)

Parameters

<c>

The SMTP connection to which the command is to be sent.

<body>

Body of the e-mail message to be sent.

EHLO

The EHLO procedure performs initial handshaking with the SMTP server after establishing the connection. The EHLO procedure allows the client to identify itself to the SMTP server according to RFC 821. RFC 1869 specifies the format of the information returned in the server's reply. The *HELO* procedure performs the equivalent functionality, but returns less information about the server.

```
EHLO(<c> IN OUT CONNECTION, <domain> VARCHAR2)
```

Parameters

<c>

The connection to the SMTP server over which to perform hand-shaking.

<domain>

Domain name of the sending host.

HELO

The HELO procedure performs initial handshaking with the SMTP server after establishing the connection. The HELO procedure allows the client to identify itself to the SMTP server according to RFC 821. The *EHLO* procedure performs the equivalent functionality, but returns more information about the server.

```
HELO(<c> IN OUT, <domain*> VARCHAR2)
```

Parameters

<c>

The connection to the SMTP server over which to perform hand-shaking.

<domain>

Domain name of the sending host.

HELP

The HELP function provides the capability to send the HELP command to the SMTP server.

```
<replies> REPLIES HELP(<c> IN OUT CONNECTION [, <command>
VARCHAR2])
```

Parameters

<c>

The SMTP connection to which the command is to be sent.

<command>

Command on which help is requested.

<replies>

SMTP reply lines to the command. See Reply/Replies <reply/replies> for a description of REPLY and REPLIES.

MAIL

The MAIL procedure initiates a mail transaction.

Parameters

<c>

Connection to SMTP server on which to start a mail transaction.

<sender>

The sender's e-mail address.

<parameters>

Mail command parameters in the format, key=value as defined in RFC 1869.

NOOP

The NOOP function/procedure sends the null command to the SMTP server. The NOOP has no effect upon the server except to obtain a successful response.

```
<reply> REPLY NOOP(<c> IN OUT CONNECTION)
NOOP(<c> IN OUT CONNECTION)
```

Parameters

<c>

The SMTP connection on which to send the command.

<reply>

SMTP reply to the command. If SMTP returns multiple replies, only the last one is returned in <reply>. See Reply/Replies <reply/replies> for a description of REPLY and REPLIES.

OPEN_CONNECTION

The OPEN_CONNECTION functions open a connection to an SMTP server.

```
<c> CONNECTION OPEN_CONNECTION(<host> VARCHAR2 [, <port>
PLS_INTEGER [, <tx_timeout> PLS_INTEGER DEFAULT NULL]])
```

Parameters

<host>

Name of the SMTP server.

<port>

Port number on which the SMTP server is listening. The default is 25

<tx_timeout>

Time out value in seconds. Do not wait is indicated by specifying 0. Wait indefinitely is indicated by setting timeout to null. The default is null.

<c>

Connection handle returned by the SMTP server.

OPEN_DATA

The OPEN_DATA procedure sends the DATA command to the SMTP server.

```
OPEN_DATA(<c> IN OUT CONNECTION)
```

Parameters

<c>

SMTP connection on which to send the command.

QUIT

The QUIT procedure closes the session with an SMTP server.

```
QUIT(<c> IN OUT CONNECTION)
```

Parameters

<c>

SMTP connection to be terminated.

RCPT

The RCPT procedure provides the e-mail address of the recipient. To schedule multiple recipients, invoke RCPT multiple times.

```
RCPT(<c> IN OUT CONNECTION, <recipient> VARCHAR2
[, parameters> VARCHAR2 ])
```

Parameters

<c>

Connection to SMTP server on which to add a recipient.

<recipient>

The recipient's e-mail address.

<parameters>

Mail command parameters in the format, key=value as defined in RFC 1869.

RSET

The RSET procedure provides the capability to terminate the current mail transaction.

```
RSET(<c> IN OUT CONNECTION)
```

Parameters

<c>

SMTP connection on which to cancel the mail transaction.

VRFY

The VRFY function provides the capability to validate and verify the recipient's e-mail address. If valid, the recipient's full name and fully qualified mailbox is returned.

```
<reply> REPLY VRFY(<c> IN OUT CONNECTION, <recipient>
VARCHAR2)
```

Parameters

<c>

The SMTP connection on which to verify the e-mail address.

<recipient>

The recipient's e-mail address to be verified.

<reply>

SMTP reply to the command. If SMTP returns multiple replies, only the last one is returned in *reply*. See Reply/Replies < reply/replies > for a description of REPLY and REPLIES.

WRITE DATA

The WRITE_DATA procedure provides the capability to add VARCHAR2 data to an e-mail message. The WRITE_DATA procedure may be repetitively called to add data.

```
WRITE_DATA(<c> IN OUT CONNECTION, <data> VARCHAR2)
```

Parameters

<c>

The SMTP connection on which to add data.

<data>

Data to be added to the e-mail message. The data must conform to the RFC 822 specification.

UTL SMTP Comprehensive example

Comprehensive Example

The following procedure constructs and sends a text e-mail message using the UTL_SMTP package.

```
CREATE OR REPLACE PROCEDURE send mail (
                    VARCHAR2,
   p_sender
                    VARCHAR2,
   p_recipient
   p_subj
                    VARCHAR2,
                    VARCHAR2,
   p_msg
                    VARCHAR2
   p_mailhost
)
IS
    v_conn
                    UTL_SMTP.CONNECTION;
    v_crlf
                    CONSTANT VARCHAR2(2) := CHR(13) || CHR(10);
    v_port
                    CONSTANT PLS_INTEGER := 25;
BEGIN
    v_conn := UTL_SMTP.OPEN_CONNECTION(p_mailhost,v_port);
    UTL SMTP.HELO(v conn,p mailhost);
   UTL_SMTP.MAIL(v_conn,p_sender);
    UTL_SMTP.RCPT(v_conn,p_recipient);
   UTL_SMTP.DATA(v_conn, SUBSTR(
        'Date: ' || TO_CHAR(SYSDATE,
        'Dy, DD Mon YYYY HH24:MI:SS') || v_crlf
        || 'From: ' || p_sender || v_crlf
```

```
|| 'To: ' || p_recipient || v_crlf
        || 'Subject: ' || p_subj || v_crlf
        || p_msg
        , 1, 32767));
    UTL_SMTP.QUIT(v_conn);
END;
EXEC send_mail('asmith@enterprisedb.com', 'pjones@enterprisedb.com', 'Holiday Party', 'Are you
The following example uses the OPEN_DATA, WRITE_DATA, and
CLOSE_DATA procedures instead of the DATA procedure.
CREATE OR REPLACE PROCEDURE send_mail_2 (
                    VARCHAR2,
   p_sender
   p_recipient
                    VARCHAR2,
                    VARCHAR2,
   p_subj
   p_msg
                    VARCHAR2,
   p_mailhost
                    VARCHAR2
)
IS
    v_{conn}
                    UTL_SMTP.CONNECTION;
                    CONSTANT VARCHAR2(2) := CHR(13) || CHR(10);
    v_crlf
   v_port
                    CONSTANT PLS_INTEGER := 25;
BEGIN
    v_conn := UTL_SMTP.OPEN_CONNECTION(p_mailhost,v_port);
   UTL_SMTP.HELO(v_conn,p_mailhost);
   UTL_SMTP.MAIL(v_conn,p_sender);
    UTL_SMTP.RCPT(v_conn,p_recipient);
   UTL_SMTP.OPEN_DATA(v_conn);
   UTL_SMTP.WRITE_DATA(v_conn, 'From: ' || p_sender || v_crlf);
    UTL_SMTP.WRITE_DATA(v_conn, 'To: ' || p_recipient || v_crlf);
    UTL_SMTP.WRITE_DATA(v_conn, 'Subject: ' || p_subj || v_crlf);
    UTL_SMTP.WRITE_DATA(v_conn,v_crlf || p_msg);
    UTL_SMTP.CLOSE_DATA(v_conn);
   UTL_SMTP.QUIT(v_conn);
END;
EXEC send_mail_2('asmith@enterprisedb.com', 'pjones@enterprisedb.com', 'Holiday Party', 'Are yo
```

4.26 UTL_URL

The UTL_URL package provides a way to escape illegal and reserved characters within an URL.

Function/Procedure

Return Type Description

ESCAPE(url, escape_reserved_chars, url_charset)	VARCHAR2	Use the ESCAPE function to escape an
UNESCAPE(url, url_charset)	VARCHAR2	The UNESCAPE function to convert ar

The UTL_URL package will return the BAD_URL exception if the call to a function includes an incorrectly-formed URL.

ESCAPE

Use the ESCAPE function to escape illegal and reserved characters within an URL. The signature is:

Reserved characters are replaced with a percent sign, followed by the two-digit hex code of the ascii value for the escaped character.

Parameters

<url>

<ur><url> specifies the Uniform Resource Locator that UTL_URL will escape.

<escape_reserved_chars>

<escape_reserved_chars> is a BOOLEAN value that instructs the
ESCAPE function to escape reserved characters as well as illegal characters:

- If <escaped_reserved_chars> is FALSE, ESCAPE will escape only the illegal characters in the specified URL.
- If <escape_reserved_chars> is TRUE, ESCAPE will escape both the illegal characters and the reserved characters in the specified URL.

By default, <escape_reserved_chars> is FALSE.

Within an URL, legal characters are:

Uppercase A through Z	Lowercase a through z	0 through 9
asterisk (*) left parenthesis (() single-quote (')	exclamation point (!) period (.) tilde (~)	hyphen (-) right parenthesis ()) underscore (_)

Some characters are legal in some parts of an URL, while illegal in others; to review comprehensive rules about illegal characters, please refer to RFC 2396. Some *examples* of characters that are considered

illegal in any part of an URL are:

Illegal Character	Escape Sequence
a blank space () curly braces ({ or }) hash mark (#)	%20 %7b and %7d %23

The ESCAPE function considers the following characters to be reserved, and will escape them if <escape_reserved_chars> is set to TRUE:

Reserved Character	Escape Sequence
ampersand (&)	%5C
at sign (@)	%25
colon (:)	%3a
comma (,)	%2c
dollar sign (\$)	%24
equal sign $(=)$	%3d
plus sign (+)	%2b
question mark (?)	%3f
semi-colon (;)	%3b
slash (/)	$\%2\mathrm{f}$

<url_charset>

<url_charset> specifies a character set to which a given character
will be converted before it is escaped. If <url_charset> is NULL, the
character will not be converted. The default value of <url_charset>
is ISO-8859-1.

Examples

The following anonymous block uses the ESCAPE function to escape the blank spaces in the URL:

```
DECLARE
result varchar2(400);
BEGIN
result := UTL_URL.ESCAPE('http://www.example.com/Using the ESCAPE function.html');
DBMS_OUTPUT.PUT_LINE(result);
END;
The resulting (escaped) URL is:
```

http://www.example.com/Using%20the%20ESCAPE%20function.html

If you include a value of TRUE for the <escape_reserved_chars> parameter when invoking the function:

```
DECLARE
result varchar2(400);
BEGIN
result := UTL_URL.ESCAPE('http://www.example.com/Using the ESCAPE function.html', TRUE);
DBMS_OUTPUT.PUT_LINE(result);
END;
```

The ESCAPE function escapes the reserved characters as well as the illegal characters in the URL:

http%3A%2F%2Fwww.example.com%2FUsing%2Othe%20ESCAPE%2Ofunction.html

UNESCAPE

The UNESCAPE function removes escape characters added to an URL by the ESCAPE function, converting the URL to it's original form.

The signature is:

```
UNESCAPE(<url> VARCHAR2, <url_charset> VARCHAR2)
```

Parameters

<url>

<ur><url> specifies the Uniform Resource Locator that UTL_URL will unescape.

```
<url_charset>
```

After unescaping a character, the character is assumed to be in <url_charset> encoding, and will be converted from that encoding to database encoding before being returned. If <url_charset> is NULL, the character will not be converted. The default value of <url_charset> is ISO-8859-1.

Examples

The following anonymous block uses the ESCAPE function to escape the blank spaces in the URL:

```
DECLARE
```

```
result varchar2(400);
```

BEGIN result := UTL_URL.UNESCAPE('http://www.example.com/Using%20the%20UNESCAPE%20function.
DBMS_OUTPUT.PUT_LINE(result);
END;

The resulting (unescaped) URL is:

http://www.example.com/Using the UNESCAPE function.htm

5 Acknowledgements

The PostgreSQL 8.3, 8.4, 9.0, 9.1, 9.2, 9.3, 9.4, 9.5, 9.6, 10, 11, and 12 Documentation provided the baseline for the portions of this guide that are common to PostgreSQL, and is hereby acknowledged:

Portions of this EnterpriseDB Software and Documentation may utilize the following copyrighted material, the use of which is hereby acknowledged.

PostgreSQL Documentation, Database Management System

PostgreSQL is Copyright © 1996-2020 by the PostgreSQL Global Development Group and is distributed under the terms of the license of the University of California below.

Postgres95 is Copyright © 1994-5 by the Regents of the University of California.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose, without fee, and without a written agreement is hereby granted, provided that the above copyright notice and this paragraph and the following two paragraphs appear in all copies.

IN NO EVENT SHALL THE UNIVERSITY OF CALIFORNIA BE LIABLE TO ANY PARTY FOR DIRECT, INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES, INCLUDING LOST PROFITS, ARISING OUT OF THE USE OF THIS SOFTWARE AND ITS DOCUMENTATION, EVEN IF THE UNIVERSITY OF CALIFORNIA HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

THE UNIVERSITY OF CALIFORNIA SPECIFICALLY DISCLAIMS ANY WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE SOFTWARE PROVIDED HEREUNDER IS ON AN "AS-IS" BASIS, AND THE UNIVERSITY OF CALIFORNIA HAS NO OBLIGATIONS TO PROVIDE MAINTENANCE, SUPPORT, UPDATES, ENHANCEMENTS, OR MODIFICATIONS.

6 Conclusion

Database Compatibility for Oracle Developers Built-in Packages Guide

Copyright © 2007 - 2020 EnterpriseDB Corporation. All rights reserved.

Enterprise
DB Corporation 34 Crosby Drive, Suite 201, Bedford, MA 01730, USA

T +1 781 357 3390 F +1 978 467 1307 E info@enterprisedb.com www.enterprisedb.com

- EnterpriseDB and Postgres Enterprise Manager are registered trademarks of EnterpriseDB Corporation. EDB and EDB Postgres are trademarks of EnterpriseDB Corporation. Oracle is a registered trademark of Oracle, Inc. Other trademarks may be trademarks of their respective owners.
- EDB designs, establishes coding best practices, reviews, and verifies input validation for the logon UI for EDB Postgres products where present. EDB follows the same approach for additional input components, however the nature of the product may require that it accepts freeform SQL, WMI or other strings to be entered and submitted by trusted users for which limited validation is possible. In such cases it is not possible to prevent users from entering incorrect or otherwise dangerous inputs.
- EDB reserves the right to add features to products that accept freeform SQL, WMI or other potentially dangerous inputs from authenticated, trusted users in the future, but will ensure all such features are designed and tested to ensure they provide the minimum possible risk, and where possible, require superuser or equivalent privileges.
- EDB does not warrant that we can or will anticipate all potential threats
 and therefore our process cannot fully guarantee that all potential vulnerabilities have been addressed or considered.