

Print stations

Send kitchen and bar tickets to the right printer automatically, by what was ordered.

What a print station is

A print station is a named destination, like Kitchen or Bar, with one printer attached. Route a product to a station and every order for it prints a ticket for just that station, to that printer.

Anything not routed to a station falls back to the single Kitchen ticket printer, set in Settings → Print → Printer selection.

Setting one up

It takes two steps, on two different screens.

- Management → Print stations: create the station and give it a name.
- Settings → Print → Print stations: pick that station from the list and choose which printer it prints to.

A station created but never given a printer looks finished on the Management screen. It is not. Nothing routed to it will print until you choose a printer for it in Settings.

Once a station has a printer, click the gear icon next to it. This opens the same settings panel a receipt or kitchen printer gets: paper size, header and footer text, and a Print test page button to check it before relying on it. See the Printer setup guide for what each setting does.

Routing products to a station

Open a product or a category and look for its Print stations tab. Pick a station there, and every order for that item goes to it.

Routing a category routes everything in it. Give a product its own station and that choice wins over the category's.

Send an item to more than one station at once, if it needs a ticket in two places.

The warning to watch for

In Settings → Print → Print stations, a station missing its printer shows a small red warning mark, saying it won't print until you choose one. That is the only warning you get. A station in this state does not fall back to any other printer; it simply drops whatever is routed to it.

Check for that warning after any change to your printers or stations, before it costs you a lost order.

Worth knowing

- Settings → Print → Customize receipt has a Kitchen item text size setting (Normal, Large, Extra large). It only affects kitchen tickets, not the customer's receipt.
- There is no reprint button for a kitchen ticket once it has gone to the printer.

EPos 365, Print stations.