# **Linux System Administration**

**Paul Cobbaut** 

#### **Linux System Administration**

Paul Cobbaut

Publication date 2015-05-24 CEST

#### **Abstract**

This book is meant to be used in an instructor-led training. For self-study, the intent is to read this book next to a working Linux computer so you can immediately do every subject, practicing each command.

This book is aimed at novice Linux system administrators (and might be interesting and useful for home users that want to know a bit more about their Linux system). However, this book is not meant as an introduction to Linux desktop applications like text editors, browsers, mail clients, multimedia or office applications.

More information and free .pdf available at http://linux-training.be .

Feel free to contact the author:

• Paul Cobbaut: paul.cobbaut@gmail.com, http://www.linkedin.com/in/cobbaut

Contributors to the Linux Training project are:

- Serge van Ginderachter: serge@ginsys.eu, build scripts and infrastructure setup
- Ywein Van den Brande: ywein@crealaw.eu, license and legal sections
- Hendrik De Vloed: hendrik.devloed@ugent.be, buildheader.pl script

We'd also like to thank our reviewers:

- Wouter Verhelst: wo@uter.be, http://grep.be
- Geert Goossens: mail.goossens.geert@gmail.com, http://www.linkedin.com/in/geertgoossens
- Elie De Brauwer: elie@de-brauwer.be, http://www.de-brauwer.be
- Christophe Vandeplas: christophe@vandeplas.com, http://christophe.vandeplas.com
- Bert Desmet: bert@devnox.be, http://blog.bdesmet.be
- Rich Yonts: richyonts@gmail.com,

Copyright 2007-2015 Paul Cobbaut

Permission is granted to copy, distribute and/or modify this document under the terms of the **GNU Free Documentation License**, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled 'GNU Free Documentation License'.

## **Table of Contents**

| I. process management                     |      |
|---|------|
| 1. introduction to processes              | 3    |
| 1.1. terminology                          | 4    |
| 1.2. basic process management             | 5    |
| 1.3. signalling processes                 | 9    |
| 1.4. practice : basic process management  | . 12 |
| 1.5. solution : basic process management  | 13   |
| 2. process priorities                     | . 15 |
| 2.1. priority and nice values             | 16   |
| 2.2. practice : process priorities        | 19   |
| 2.3. solution : process priorities        |      |
| 3. background jobs                        |      |
| 3.1. background processes                 |      |
| 3.2. practice: background processes       |      |
| 3.3. solution : background processes      |      |
| II. disk management                       |      |
| 4. disk devices                           |      |
| 4.1. terminology                          |      |
| 4.2. device naming                        |      |
| 4.3. discovering disk devices             |      |
| 4.4. erasing a hard disk                  |      |
| 4.5. advanced hard disk settings          |      |
| 4.6. practice: hard disk devices          |      |
| 4.7. solution: hard disk devices          |      |
| 5. disk partitions                        |      |
| 5.1. about partitions                     |      |
| 5.2. discovering partitions               |      |
| 5.3. partitioning new disks               |      |
| 5.4. about the partition table            |      |
| 5.5. GUID partition table                 |      |
| 5.6. labeling with parted                 |      |
|   |      |
| 5.7. practice: partitions                 |      |
| 6. file systems                           |      |
| 6.1. about file systems                   |      |
| 6.2. common file systems                  |      |
| ·   |      |
| 6.3. putting a file system on a partition |      |
|   |      |
| 6.5. checking a file system               |      |
| 6.6. practice: file systems               |      |
| 6.7. solution: file systems               |      |
| 7. mounting                               |      |
| 7.1. mounting local file systems          |      |
| 7.2. displaying mounted file systems      |      |
| 7.3. from start to finish                 |      |
| 7.4. permanent mounts                     |      |
| 7.5. securing mounts                      |      |
| 7.6. mounting remote file systems         |      |
| 7.7. practice: mounting file systems      |      |
| 7.8. solution: mounting file systems      |      |
| 8. troubleshooting tools                  |      |
| 8.1. lsof                                 |      |
| 8.2. fuser                                |      |
| 8.3. chroot                               |      |
| 8.4. iostat                               | 81   |

| 8.5. iotop   | 82  |
|--|-----|
| 8.6. vmstat  | 83  |
| 8.7. practice: troubleshooting tools                     | 84  |
| 8.8. solution: troubleshooting tools                     | 85  |
| 9. introduction to uuid's                                |     |
| 9.1. about unique objects                                |     |
| 9.2. tune2fs   |     |
| 9.3. uuid  |     |
| 9.4. uuid in /etc/fstab                                  |     |
| 9.5. uuid as a boot device                               |     |
| 9.6. practice: uuid and filesystems                      |     |
| 9.7. solution: uuid and filesystems                      |     |
| 10. introduction to raid                                 |     |
| 10.1. hardware or software                               |     |
| 10.2. raid levels  |     |
|  |     |
| 10.3. building a software raid5 array                    |     |
| 10.4. practice: raid                                     |     |
| 10.5. solution: raid                                     |     |
| 11. logical volume management                            |     |
| 11.1. introduction to lvm                                |     |
| 11.2. lvm terminology                                    |     |
| 11.3. example: using lvm                                 |     |
| 11.4. example: extend a logical volume                   |     |
| 11.5. example: resize a physical Volume                  |     |
| 11.6. example: mirror a logical volume                   |     |
| 11.7. example: snapshot a logical volume                 |     |
| 11.8. verifying existing physical volumes                |     |
| 11.9. verifying existing volume groups                   |     |
| 11.10. verifying existing logical volumes                |     |
| 11.11. manage physical volumes                           |     |
| 11.12. manage volume groups                              |     |
| 11.13. manage logical volumes                            |     |
| 11.14. practice: lvm                                     |     |
| 11.15. solution: lvm                                     |     |
| 12. iSCSI devices  |     |
| 12.1. iSCSI terminology                                  | 127 |
| 12.2. iSCSI Target in RHEL/CentOS                        | 127 |
| 12.3. iSCSI Initiator in RHEL/CentOS                     | 129 |
| 12.4. iSCSI target on Debian                             | 131 |
| 12.5. iSCSI target setup with dd files                   | 132 |
| 12.6. ISCSI initiator on ubuntu                          | 134 |
| 12.7. using iSCSI devices                                | 136 |
| 12.8. iSCSI Target RHEL7/CentOS7                         | 137 |
| 12.9. iSCSI Initiator RHEL7/CentOS7                      |     |
| 12.10. practice: iSCSI devices                           | 141 |
| 12.11. solution: iSCSI devices                           |     |
| 13. introduction to multipathing                         |     |
| 13.1. install multipath                                  |     |
| 13.2. configure multipath                                |     |
| 13.3. network  |     |
| 13.4. start multipathd and iscsi                         |     |
| 13.5. multipath list                                     |     |
| 13.6. using the device                                   |     |
| 13.7. practice: multipathing                             |     |
| 13.8. solution: multipathing                             |     |
| boot managementboot management                           |     |
| 14. bootloader   |     |
| 14.1. boot terminology                                   |     |
| 1 111 000t WIHHIOOG   1111111111111111111111111111111111 | 100 |

III.

| 14.2. grub  |   |
|---|---|
| 14.3. grub2   | 166   |
| 14.4. lilo  | 167   |
| 14.5. practice: bootloader  | 168   |
| 14.6. solution: bootloader  | 169   |
| 15. init and runlevels  | 170   |
| 15.1. system init(ialization)   | 171   |
| 15.2. daemon or demon ?   | 176   |
| 15.3. starting and stopping daemons   | 176   |
| 15.4. chkconfig   | 177   |
| 15.5. update-rc.d   | 179   |
| 15.6. bum   | 180   |
| 15.7. runlevels   | 181   |
| 15.8. systemd   | 183   |
| 15.9. practice: init  | 189   |
| 15.10. solution : init  | 190   |
| IV. system management   | 192   |
| 16. scheduling  | 194   |
| 16.1. one time jobs with at   | 195   |
| 16.2. cron  | 197   |
| 16.3. practice: scheduling  | 199   |
| 16.4. solution: scheduling  | 200   |
| 17. logging   | 201   |
| 17.1. login logging   | 202   |
| 17.2. syslogd   | 205   |
| 17.3. logger  | 208   |
| 17.4. watching logs   | 208   |
| 17.5. rotating logs   | 209   |
|   | 210   |
| 17.6. practice: logging   | 210   |
| 17.6. practice: logging   |   |
|   | 211   |
| 17.7. solution: logging   | 211   |
| 17.7. solution : logging  | 211 213 214   |
| 17.7. solution: logging   | 211 213 214 215   |
| 17.7. solution: logging   | 211 213 214 215 217   |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat   | 211 213 214 215 217 218   |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory   | 211 213 214 215 217 218 219   |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory   | 211 213 214 215 217 218 219   |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  | 211 213 214 215 217 218 219 220 221   |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  | 211 213 214 215 217 218 219 220 221   |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  19.2. top   | 211 213 214 215 217 218 219 220 221 221   |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  19.2. top  19.3. free   | 211 213 214 215 217 218 219 220 221 221 221   |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  19.2. top  19.3. free  19.4. watch  19.5. vmstat  19.6. iostat  | 211 213 214 215 217 218 219 220 221 221 222 222 222                                     |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  19.2. top  19.3. free  19.4. watch  19.5. vmstat  | 211 213 214 215 217 218 219 220 221 221 222 222 222                                     |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  19.2. top  19.3. free  19.4. watch  19.5. vmstat  19.6. iostat  | 211 213 214 215 217 218 219 220 221 221 222 222 223 224                                 |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  19.2. top  19.3. free  19.4. watch  19.5. vmstat  19.6. iostat  19.7. mpstat  | 211 213 214 215 217 218 219 220 221 221 222 222 222 224 224                             |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  19.2. top  19.3. free  19.4. watch  19.5. vmstat  19.6. iostat  19.7. mpstat  19.8. sadc and sar  | 211 213 214 215 217 218 219 220 221 221 222 222 223 224 224                             |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  19.2. top  19.3. free  19.4. watch  19.5. vmstat  19.6. iostat  19.7. mpstat  19.8. sadc and sar  19.9. ntop  | 211 213 214 215 217 218 219 221 221 221 222 222 224 224 225 225                         |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  19.2. top  19.3. free  19.4. watch  19.5. vmstat  19.6. iostat  19.7. mpstat  19.8. sadc and sar  19.9. ntop  19.10. iftop  | 211 213 214 215 217 218 219 220 221 221 222 222 223 224 225 225 225                     |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  19.2. top  19.3. free  19.4. watch  19.5. vmstat  19.6. iostat  19.7. mpstat  19.8. sadc and sar  19.9. ntop  19.10. iftop  19.11. iptraf  19.12. nmon  19.13. htop   | 211 213 214 215 217 218 219 220 221 221 222 222 223 224 225 225 226 226                 |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  19.2. top  19.3. free  19.4. watch  19.5. vmstat  19.6. iostat  19.7. mpstat  19.8. sadc and sar  19.9. ntop  19.10. iftop  19.11. iptraf  19.12. nmon  19.13. htop  20. package management   | 211 213 214 215 217 218 219 220 221 221 222 222 224 225 225 226 226 226                 |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  19.2. top  19.3. free  19.4. watch  19.5. vmstat  19.6. iostat  19.7. mpstat  19.8. sadc and sar  19.9. ntop  19.10. iftop  19.11. iptraf  19.12. nmon  19.13. htop   | 211 213 214 215 217 218 219 220 221 221 222 222 224 225 225 226 226 226                 |
| 17.7. solution: logging  18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  19.2. top  19.3. free  19.4. watch  19.5. vmstat  19.6. iostat  19.7. mpstat  19.8. sadc and sar  19.9. ntop  19.10. iftop  19.11. iptraf  19.12. nmon  19.13. htop  20. package management  20.1. package terminology  20.2. deb package management                    | 211 213 214 215 217 218 219 220 221 221 222 222 224 225 225 226 226 228 230             |
| 18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice: memory  18.5. solution: memory  19. resource monitoring  19.1. four basic resources  19.2. top  19.3. free  19.4. watch  19.5. vmstat  19.6. iostat  19.7. mpstat  19.8. sadc and sar  19.9. ntop  19.10. iftop  19.11. iptraf  19.12. nmon  19.13. htop  20. package management  20.1. package terminology  20.2. deb package management  20.3. apt-get                              | 211 213 214 215 217 218 219 221 221 222 222 224 225 225 226 228 230 232                 |
| 18. memory management  18.1. displaying memory and cache 18.2. managing swap space 18.3. monitoring memory with vmstat 18.4. practice : memory 18.5. solution : memory 19. resource monitoring 19.1. four basic resources 19.2. top 19.3. free 19.4. watch 19.5. vmstat 19.6. iostat 19.7. mpstat 19.8. sadc and sar 19.9. ntop 19.10. iftop 19.11. iptraf 19.12. nmon 19.13. htop 20. package management 20.1. package terminology 20.2. deb package management 20.3. apt-get 20.4. aptitude                                   | 211 213 214 215 217 218 219 221 221 221 222 222 224 225 226 226 226 230 232 233         |
| 18. memory management  18.1. displaying memory and cache  18.2. managing swap space  18.3. monitoring memory with vmstat  18.4. practice : memory  18.5. solution : memory  19. resource monitoring  19.1. four basic resources  19.2. top  19.3. free  19.4. watch  19.5. vmstat  19.6. iostat  19.7. mpstat  19.8. sadc and sar  19.9. ntop  19.10. iftop  19.11. iptraf  19.12. nmon  19.13. htop  20. package management  20.1. package terminology  20.2. deb package management  20.3. apt-get  20.4. aptitude  20.5. apt | 211 213 214 215 217 218 219 220 221 221 222 222 223 225 225 226 226 230 230 231         |
| 18. memory management  18.1. displaying memory and cache 18.2. managing swap space 18.3. monitoring memory with vmstat 18.4. practice : memory 18.5. solution : memory 19. resource monitoring 19.1. four basic resources 19.2. top 19.3. free 19.4. watch 19.5. vmstat 19.6. iostat 19.7. mpstat 19.8. sadc and sar 19.9. ntop 19.10. iftop 19.11. iptraf 19.12. nmon 19.13. htop 20. package management 20.1. package terminology 20.2. deb package management 20.3. apt-get 20.4. aptitude                                   | 211 213 214 215 217 218 219 220 221 221 222 222 223 225 226 226 226 230 232 235 236 237 |

| 20.8. alien                                       |     |
|---|-----|
| 20.9. downloading software outside the repository |     |
| 20.10. compiling software                         | 247 |
| 20.11. practice: package management               | 248 |
| 20.12. solution: package management               | 249 |
| V. network management                             | 250 |
| 21. general networking                            | 253 |
| 21.1. network layers                              | 254 |
| 21.2. unicast, multicast, broadcast, anycast      | 257 |
| 21.3. lan-wan-man                                 |     |
| 21.4. internet - intranet - extranet              |     |
| 21.5. tcp/ip                                      |     |
| 22. interface configuration                       |     |
| 22.1. to gui or not to gui                        |     |
| 22.2. Debian nic configuration                    |     |
| 22.3. RHEL nic configuration                      |     |
| 22.4. ifconfig                                    |     |
| 22.5. ip  |     |
| 22.6. dhclient                                    |     |
| 22.7. hostname                                    |     |
|   |     |
| 22.8. arp   |     |
| 22.9. route                                       |     |
| 22.10. ping                                       |     |
| 22.11. optional: ethtool                          |     |
| 22.12. practice: interface configuration          |     |
| 22.13. solution: interface configuration          |     |
| 23. network sniffing                              |     |
| 23.1. wireshark                                   |     |
| 23.2. tcpdump                                     |     |
| 23.3. practice: network sniffing                  |     |
| 23.4. solution: network sniffing                  |     |
| 24. binding and bonding                           |     |
| 24.1. binding on Redhat/Fedora                    |     |
| 24.2. binding on Debian/Ubuntu                    |     |
| 24.3. bonding on Redhat/Fedora                    | 290 |
| 24.4. bonding on Debian/Ubuntu                    | 292 |
| 24.5. practice: binding and bonding               |     |
| 24.6. solution: binding and bonding               | 295 |
| 25. ssh client and server                         | 296 |
| 25.1. about ssh                                   | 297 |
| 25.2. log on to a remote server                   | 299 |
| 25.3. executing a command in remote               |     |
| 25.4. scp   |     |
| 25.5. setting up passwordless ssh                 |     |
| 25.6. X forwarding via ssh                        |     |
| 25.7. troubleshooting ssh                         |     |
| 25.8. sshd  |     |
| 25.9. sshd keys                                   |     |
| 25.10. ssh-agent                                  |     |
| 25.11. practice: ssh                              |     |
| 25.12. solution: ssh                              |     |
| 26. introduction to nfs                           |     |
| 26.1. nfs protocol versions                       |     |
|   |     |
| 26.2. rpcinfo                                     |     |
| 26.3. server configuration                        |     |
| 26.4. /etc/exports                                |     |
| 26.5. exportfs                                    |     |
| 26.6. client configuration                        |     |

| 26.7. practice: introduction to nfs | 312 |
|-------------------------------------|-----|
| 27. introduction to networking      |     |
| 27.1. introduction to iptables      |     |
| 27.2. practice: iptables            |     |
| 27.3. solution: iptables            |     |
| 27.4. xinetd and inetd              |     |
| 27.5. practice: inetd and xinetd    |     |
| 27.6. network file system           |     |
| 27.7. practice: network file system |     |
| VI. kernel management               |     |
| 28. the Linux kernel                |     |
| 28.1. about the Linux kernel        |     |
| 28.2. Linux kernel source           |     |
| 28.3. kernel boot files             |     |
| 28.4. Linux kernel modules          |     |
| 28.5. compiling a kernel            |     |
| 28.6. compiling one module          |     |
| 29. library management              |     |
| 29.1. introduction                  |     |
| 29.2. /lib and /usr/lib             | 346 |
| 29.3. ldd                           | 346 |
| 29.4. ltrace                        | 347 |
| 29.5. dpkg -S and debsums           | 347 |
| 29.6. rpm -qf and rpm -V            | 348 |
| 29.7. tracing with strace           | 349 |
| VII. backup management              | 350 |
| 30. backup                          | 352 |
| 30.1. About tape devices            | 352 |
| 30.2. Compression                   | 353 |
| 30.3. tar                           | 353 |
| 30.4. Backup Types                  | 355 |
| 30.5. dump and restore              | 356 |
| 30.6. cpio                          | 356 |
| 30.7. dd                            | 357 |
| 30.8. split                         | 358 |
| 30.9. practice: backup              | 358 |
| VIII. Appendices                    |     |
| A. disk quotas                      | 362 |
| A.1. About Disk Quotas              |     |
| A.2. Practice Disk quotas           |     |
| B. introduction to vnc              |     |
| B.1. About VNC                      |     |
| B.2. VNC Server                     |     |
| B.3. VNC Client                     |     |
| B.4. Practice VNC                   |     |
| C. License                          |     |
| Index                               | 372 |

## **List of Tables**

| 4.1. ide device naming                        | 34 |
|---|----|
| 4.2. scsi device naming                       |    |
| 5.1. primary, extended and logical partitions |    |
| 5.2. Partition naming                         |    |
| 12.1. iSCSI Target and Initiator practice     |    |
| 12.2. iSCSI Target and Initiator practice     |    |
| 15.1. systemd power management                |    |



## **Table of Contents**

| 1. introduction to processes             | 3  |
|--|----|
| 1.1. terminology                         |    |
| 1.2. basic process management            | 5  |
| 1.3. signalling processes                |    |
| 1.4. practice: basic process management  |    |
| 1.5. solution : basic process management | 13 |
| 2. process priorities                    |    |
| 2.1. priority and nice values            |    |
| 2.2. practice : process priorities       | 19 |
| 2.3. solution : process priorities       |    |
| 3. background jobs                       | 22 |
| 3.1. background processes                |    |
| 3.2. practice: background processes      |    |
| 3.3. solution : background processes     |    |

| Chapter | 1. introdu | uction to | proce | sses |
|---------|------------|-----------|-------|------|
|         |            |           |       |      |
|         |            |           |       |      |
|         |            |           |       |      |
|         |            |           |       |      |
|         |            |           |       |      |
|         |            |           |       |      |
|         |            |           |       |      |
|         |            |           |       |      |
|         |            |           |       |      |
|         |            |           |       |      |
|         |            |           |       |      |

## 1.1. terminology

### **1.1.1. process**

A **process** is compiled source code that is currently running on the system.

#### 1.1.2. PID

All processes have a process id or PID.

#### 1.1.3. PPID

Every process has a parent process (with a **PPID**). The **child** process is often started by the **parent** process.

#### 1.1.4. init

The **init** process always has process ID 1. The **init** process is started by the **kernel** itself so technically it does not have a parent process. **init** serves as a **foster parent** for **orphaned** processes.

#### 1.1.5. kill

When a process stops running, the process dies, when you want a process to die, you kill it.

#### 1.1.6. daemon

Processes that start at system startup and keep running forever are called **daemon** processes or **daemons**. These **daemons** never die.

### 1.1.7. zombie

When a process is killed, but it still shows up on the system, then the process is referred to as **zombie**. You cannot kill zombies, because they are already dead.

## 1.2. basic process management

### 1.2.1. \$\$ and \$PPID

Some shell environment variables contain information about processes. The \$\$ variable will hold your current **process ID**, and **\$PPID** contains the **parent PID**. Actually \$\$ is a shell parameter and not a variable, you cannot assign a value to it.

Below we use **echo** to display the values of \$\$ and \$PPID.

```
[paul@RHEL4b ~]$ echo $$ $PPID 4224 4223
```

### 1.2.2. pidof

You can find all process id's by name using the **pidof** command.

```
root@rhel53 ~# pidof mingetty
2819 2798 2797 2796 2795 2794
```

### 1.2.3. parent and child

Processes have a parent-child relationship. Every process has a parent process.

When starting a new **bash** you can use **echo** to verify that the **pid** from before is the **ppid** of the new shell. The **child** process from above is now the **parent** process.

```
[paul@RHEL4b ~]$ bash
[paul@RHEL4b ~]$ echo $$ $PPID
4812 4224
```

Typing **exit** will end the current process and brings us back to our original values for **\$\$** and **\$PPID**.

```
[paul@RHEL4b ~]$ echo $$ $PPID 4812 4224 [paul@RHEL4b ~]$ exit exit [paul@RHEL4b ~]$ echo $$ $PPID 4224 4223 [paul@RHEL4b ~]$
```

#### 1.2.4. fork and exec

A process starts another process in two phases. First the process creates a **fork** of itself, an identical copy. Then the forked process executes an **exec** to replace the forked process with the target child process.

```
[paul@RHEL4b ~]$ echo $$
4224
[paul@RHEL4b ~]$ bash
[paul@RHEL4b ~]$ echo $$ $PPID
5310 4224
[paul@RHEL4b ~]$
```

#### 1.2.5. exec

With the **exec** command, you can execute a process without forking a new process. In the following screenshot a **Korn shell** (ksh) is started and is being replaced with a **bash shell** using the **exec** command. The **pid** of the **bash shell** is the same as the **pid** of the **Korn shell**. Exiting the child **bash shell** will get me back to the parent **bash**, not to the **Korn shell** (which does not exist anymore).

#### 1.2.6. ps

One of the most common tools on Linux to look at processes is **ps**. The following screenshot shows the parent child relationship between three bash processes.

```
[paul@RHEL4b ~]$ echo $$ $PPID
4224 4223
[paul@RHEL4b ~]$ bash
[paul@RHEL4b ~]$ echo $$ $PPID
4866 4224
[paul@RHEL4b ~]$ bash
[paul@RHEL4b ~]$ echo $$ $PPID
4884 4866
[paul@RHEL4b ~]$ ps fx
 PID TTY STAT TIME COMMAND
4223 ? S 0:01 sshd: paul@pts/0
4223 ?
4224 pts/0 Ss
                     0:00 \_ -bash
4866 pts/0 S 0:00
                            \_ bash
4884 pts/0 S 0:00
4902 pts/0 R+ 0:00
                                \_ bash
                                        \_ ps fx
[paul@RHEL4b ~]$ exit
[paul@RHEL4b ~]$ ps fx
PID TTY STAT TIME COMMAND
4223 ? S 0:01 sshd: paul@pts/0
4224 pts/0 Ss 0:00 \_ -bash
                    0:00 \_ bash
0:00 \_ ps fx
4866 pts/0 S
4903 pts/0 R+ 0:00
[paul@RHEL4b ~]$ exit
exit
[paul@RHEL4b ~]$ ps fx
 PID TTY STAT TIME COMMAND
4223 ?
             S 0:01 sshd: paul@pts/0
4224 pts/0 Ss 0:00
4904 pts/0 R+ 0:00
                      0:00 \_ -bash
                                \_ ps fx
[paul@RHEL4b ~]$
```

On Linux, **ps fax** is often used. On Solaris **ps -ef** (which also works on Linux) is common. Here is a partial output from **ps fax**.

### 1.2.7. pgrep

Similar to the **ps** -C, you can also use **pgrep** to search for a process by its command name.

You can also list the command name of the process with pgrep.

```
paul@laika:~$ pgrep -l sleep
9661 sleep
```

### 1.2.8. top

Another popular tool on Linux is **top**. The **top** tool can order processes according to **cpu usage** or other properties. You can also **kill** processes from within top. Press **h** inside **top** for help.

In case of trouble, top is often the first tool to fire up, since it also provides you memory and swap space information.

## 1.3. signalling processes

#### 1.3.1. kill

The **kill** command will kill (or stop) a process. The screenshot shows how to use a standard **kill** to stop the process with **pid** 1942.

```
paul@ubuntu910:~$ kill 1942
paul@ubuntu910:~$
```

By using the **kill** we are sending a **signal** to the process.

### 1.3.2. list signals

Running processes can receive signals from each other or from the users. You can have a list of signals by typing **kill -l**, that is a letter **l**, not the number 1.

```
[paul@RHEL4a ~]$ kill -1

1) SIGHUP 2) SIGINT 3) SIGQUIT 4) SIGILL

5) SIGTRAP 6) SIGABRT 7) SIGBUS 8) SIGFPE

9) SIGKILL 10) SIGUSR1 11) SIGSEGV 12) SIGUSR2

13) SIGPIPE 14) SIGALRM 15) SIGTERM 17) SIGCHLD

18) SIGCONT 19) SIGSTOP 20) SIGTSTP 21) SIGTTIN

22) SIGTTOU 23) SIGURG 24) SIGXCPU 25) SIGXFSZ

26) SIGVTALRM 27) SIGPROF 28) SIGWINCH 29) SIGIO

30) SIGPWR 31) SIGSYS 34) SIGRTMIN 35) SIGRTMIN+1

36) SIGRTMIN+2 37) SIGRTMIN+3 38) SIGRTMIN+4 39) SIGRTMIN+5

40) SIGRTMIN+6 41) SIGRTMIN+7 42) SIGRTMIN+8 43) SIGRTMIN+9

44) SIGRTMIN+10 45) SIGRTMIN+11 46) SIGRTMIN+12 47) SIGRTMIN+13

48) SIGRTMIN+14 49) SIGRTMIN+15 50) SIGRTMAX-14 51) SIGRTMAX-13

52) SIGRTMAX-12 53) SIGRTMAX-11 54) SIGRTMAX-10 55) SIGRTMAX-9

56) SIGRTMAX-8 57) SIGRTMAX-7 58) SIGRTMAX-6 59) SIGRTMAX-5

60) SIGRTMAX-4 61) SIGRTMAX-7 58) SIGRTMAX-2 63) SIGRTMAX-5

64) SIGRTMAX

[paul@RHEL4a ~]$
```

### 1.3.3. kill -1 (SIGHUP)

It is common on Linux to use the first signal **SIGHUP** (or HUP or 1) to tell a process that it should re-read its configuration file. Thus, the **kill -1 1** command forces the **init** process (**init** always runs with **pid 1**) to re-read its configuration file.

```
root@deb503:~# kill -1 1
root@deb503:~#
```

It is up to the developer of the process to decide whether the process can do this running, or whether it needs to stop and start. It is up to the user to read the documentation of the program.

### 1.3.4. kill -15 (SIGTERM)

The **SIGTERM** signal is also called a **standard kill**. Whenever **kill** is executed without specifying the signal, a **kill -15** is assumed.

Both commands in the screenshot below are identical.

```
paul@ubuntu910:~$ kill 1942
paul@ubuntu910:~$ kill -15 1942
```

### 1.3.5. kill -9 (SIGKILL)

The **SIGKILL** is different from most other signals in that it is not being sent to the process, but to the **Linux kernel**. A **kill -9** is also called a **sure kill**. The **kernel** will shoot down the process. As a developer you have no means to intercept a **kill -9** signal.

```
root@rhel53 ~# kill -9 3342
```

#### 1.3.6. SIGSTOP and SIGCONT

A running process can be **suspended** when it receives a **SIGSTOP** signal. This is the same as **kill -19** on Linux, but might have a different number in other Unix systems.

A **suspended** process does not use any **cpu cycles**, but it stays in memory and can be reanimated with a **SIGCONT** signal (**kill -18** on Linux).

Both signals will be used in the section about **background** processes.

#### 1.3.7. pkill

You can use the **pkill** command to kill a process by its command name.

#### 1.3.8. killall

The **killall** command will send a **signal 15** to all processes with a certain name.

```
paul@rhel65:~$ sleep 8472 &
[1] 18780
paul@rhel65:~$ sleep 1201 &
[2] 18781
paul@rhel65:~$ jobs
                             sleep 8472 &
[1]- Running
[2]+ Running
                            sleep 1201 &
paul@rhel65:~$ killall sleep
[1]- Terminated
                          sleep 8472
[2]+ Terminated
                             sleep 1201
paul@rhel65:~$ jobs
paul@rhel65:~$
```

#### 1.3.9. killall5

Its SysV counterpart **killall5** can by used when shutting down the system. This screenshot shows how Red Hat Enterprise Linux 5.3 uses **killall5** when halting the system.

```
root@rhel53 ~# grep killall /etc/init.d/halt action $"Sending all processes the TERM signal..." /sbin/killall5 -15 action $"Sending all processes the KILL signal..." /sbin/killall5 -9
```

### 1.3.10. top

Inside **top** the **k** key allows you to select a **signal** and **pid** to kill. Below is a partial screenshot of the line just below the summary in **top** after pressing **k**.

```
PID to kill: 1932

Kill PID 1932 with signal [15]: 9
```

## 1.4. practice : basic process management

- 1. Use **ps** to search for the **init** process by name.
- 2. What is the **process id** of the **init** process?
- 3. Use the **who am i** command to determine your terminal name.
- 4. Using your terminal name from above, use **ps** to find all processes associated with your terminal.
- 5. What is the **process id** of your shell?
- 6. What is the **parent process id** of your shell?
- 7. Start two instances of the **sleep 3342** in background.
- 8. Locate the **process id** of all **sleep** commands.
- 9. Display only those two **sleep** processes in **top**. Then quit top.
- 10. Use a **standard kill** to kill one of the **sleep** processes.
- 11. Use one command to kill all **sleep** processes.

## 1.5. solution: basic process management

1. Use **ps** to search for the **init** process by name.

```
root@rhel53 ~# ps -C init
PID TTY TIME CMD
1 ? 00:00:04 init
```

2. What is the **process id** of the **init** process ?

1

3. Use the **who am i** command to determine your terminal name.

```
root@rhel53 ~# who am i
paul pts/0 2010-04-12 17:44 (192.168.1.38)
```

4. Using your terminal name from above, use **ps** to find all processes associated with your terminal.

```
      oot@rhel53 ~# ps fax | grep pts/0

      2941 ?
      S 0:00 \_ sshd: paul@pts/0

      2942 pts/0 Ss 0:00 \_ -bash

      2972 pts/0 S 0:00 \_ su -

      2973 pts/0 S 0:00 \_ -bash

      3808 pts/0 R+ 0:00 \_ -ps fax

      3809 pts/0 R+ 0:00 \_ -grep pts/0
```

or also

```
root@rhel53 ~# ps -ef | grep pts/0
paul 2941 2939 0 17:44 ? 00:00:00 sshd: paul@pts/0
paul 2942 2941 0 17:44 pts/0 00:00:00 -bash
root 2972 2942 0 17:45 pts/0 00:00:00 -bash
root 2973 2972 0 17:45 pts/0 00:00:00 -bash
root 3816 2973 0 21:25 pts/0 00:00:00 ps -ef
root 3817 2973 0 21:25 pts/0 00:00:00 grep pts/0
```

5. What is the **process id** of your shell?

```
2973 in the screenshot above, probably different for you
```

echo \$\$ should display same number as the one you found

6. What is the **parent process id** of your shell?

```
2972 in the screenshot above, probably different for you
```

in this example the PPID is from the  $\mathbf{su}$  - command, but when inside gnome then for example gnome-terminal can be the parent process

7. Start two instances of the **sleep 3342** in background.

sleep 3342 & sleep 3342 &

8. Locate the **process id** of all **sleep** commands.

pidof sleep

9. Display only those two **sleep** processes in **top**. Then quit top.

top -p pidx,pidy (replace pidx pidy with the actual numbers)

10. Use a **standard kill** to kill one of the **sleep** processes.

kill pidx

11. Use one command to kill all **sleep** processes.

pkill sleep

| Chapter 2. process priorities |  |  |  |  |  |
|-------------------------------|--|--|--|--|--|
|                               |  |  |  |  |  |
|                               |  |  |  |  |  |
|                               |  |  |  |  |  |
|                               |  |  |  |  |  |
|                               |  |  |  |  |  |
|                               |  |  |  |  |  |
|                               |  |  |  |  |  |
|                               |  |  |  |  |  |
|                               |  |  |  |  |  |

## 2.1. priority and nice values

#### 2.1.1. introduction

All processes have a **priority** and a **nice** value. Higher priority processes will get more **cpu time** than lower priority processes. You can influence this with the **nice** and **renice** commands.

### 2.1.2. pipes (mkfifo)

Processes can communicate with each other via **pipes**. These **pipes** can be created with the **mkfifo** command.

The screenshots shows the creation of four distinct pipes (in a new directory).

```
paul@ubuntu910:~$ mkdir procs
paul@ubuntu910:~$ cd procs/
paul@ubuntu910:~/procs$ mkfifo pipe33a pipe33b pipe42a pipe42b
paul@ubuntu910:~/procs$ ls -1
total 0
prw-r--r-- 1 paul paul 0 2010-04-12 13:21 pipe33a
prw-r--r-- 1 paul paul 0 2010-04-12 13:21 pipe33b
prw-r--r-- 1 paul paul 0 2010-04-12 13:21 pipe42a
prw-r--r-- 1 paul paul 0 2010-04-12 13:21 pipe42b
paul@ubuntu910:~/procs$
```

#### 2.1.3. some fun with cat

To demonstrate the use of the **top** and **renice** commands we will make the **cat** command use the previously created **pipes** to generate a full load on the **cpu**.

The **cat** is copied with a distinct name to the current directory. (This enables us to easily recognize the processes within **top**. You could do the same exercise without copying the cat command, but using different users. Or you could just look at the **pid** of each process.)

```
paul@ubuntu910:~/procs$ cp /bin/cat proj33
paul@ubuntu910:~/procs$ cp /bin/cat proj42
paul@ubuntu910:~/procs$ echo -n x | ./proj33 - pipe33a > pipe33b &
[1] 1670
paul@ubuntu910:~/procs$ ./proj33 <pipe33b >pipe33a &
[2] 1671
paul@ubuntu910:~/procs$ echo -n z | ./proj42 - pipe42a > pipe42b &
[3] 1673
paul@ubuntu910:~/procs$ ./proj42 <pipe42b >pipe42a &
[4] 1674
```

The commands you see above will create two **proj33** processes that use **cat** to bounce the x character between **pipe33a** and **pipe33b**. And ditto for the z character and **proj42**.

#### 2.1.4. top

Just running **top** without options or arguments will display all processes and an overview of innformation. The top of the **top** screen might look something like this.

```
top - 13:59:29 up 48 min, 4 users, load average: 1.06, 0.25, 0.14

Tasks: 139 total, 3 running, 136 sleeping, 0 stopped, 0 zombie

Cpu(s): 0.3%us, 99.7%sy, 0.0%ni, 0.0%id, 0.0%wa, 0.0%hi, 0.0%si, 0.0%st

Mem: 509352k total, 460040k used, 49312k free, 66752k buffers

Swap: 746980k total, 0k used, 746980k free, 247324k cached
```

Notice the **cpu idle time (0.0%id)** is zero. This is because our **cat** processes are consuming the whole **cpu**. Results can vary on systems with four or more **cpu cores**.

#### 2.1.5. top -p

The **top -p 1670,1671,1673,1674** screenshot below shows four processes, all of then using approximately 25 percent of the **cpu**.

```
PID USER PR NI VIRT RES SHR S %CPU %MEM TIME+ COMMAND
1674 paul 20 0 2972 616 524 S 26.6 0.1 0:11.92 proj42
1670 paul 20 0 2972 616 524 R 25.0 0.1 0:23.16 proj33
1671 paul 20 0 2972 616 524 S 24.6 0.1 0:23.07 proj33
1673 paul 20 0 2972 620 524 R 23.0 0.1 0:11.48 proj42
```

All four processes have an equal **priority** (**PR**), and are battling for **cpu time**. On some systems the **Linux kernel** might attribute slightly varying **priority values**, but the result will still be four processes fighting for **cpu time**.

#### 2.1.6. renice

Since the processes are already running, we need to use the **renice** command to change their **nice value** (**NI**).

The screenshot shows how to use **renice** on both the **proj33** processes.

```
paul@ubuntu910:~$ renice +8 1670
1670: old priority 0, new priority 8
paul@ubuntu910:~$ renice +8 1671
1671: old priority 0, new priority 8
```

Normal users can attribute a **nice value** from zero to 20 to processes they own. Only the **root** user can use negative nice values. Be very careful with negative nice values, since they can make it impossible to use the keyboard or ssh to a system.

### 2.1.7. impact of nice values

The impact of a nice value on running processes can vary. The screenshot below shows the result of our **renice** +8 command. Look at the %CPU values.

```
PID USER PR NI VIRT RES SHR S %CPU %MEM TIME+ COMMAND 1674 paul 20 0 2972 616 524 S 46.6 0.1 0:22.37 proj42 1673 paul 20 0 2972 620 524 R 42.6 0.1 0:21.65 proj42 1671 paul 28 8 2972 616 524 S 5.7 0.1 0:29.65 proj33 1670 paul 28 8 2972 616 524 R 4.7 0.1 0:29.82 proj33
```

Important to remember is to always make less important processes nice to more important processes. Using **negative nice values** can have a severe impact on a system's usability.

#### 2.1.8. nice

The **nice** works identical to the **renice** but it is used when starting a command.

The screenshot shows how to start a script with a **nice** value of five.

```
paul@ubuntu910:~$ nice -5 ./backup.sh
```

## 2.2. practice: process priorities

- 1. Create a new directory and create six **pipes** in that directory.
- 2. Bounce a character between two **pipes**.
- 3. Use **top** and **ps** to display information (pid, ppid, priority, nice value, ...) about these two cat processes.
- 4. Bounce another character between two other pipes, but this time start the commands **nice**. Verify that all **cat** processes are battling for the cpu. (Feel free to fire up two more cats with the remaining pipes).
- 5. Use **ps** to verify that the two new **cat** processes have a **nice** value. Use the -o and -C options of **ps** for this.
- 6. Use **renice** te increase the nice value from 10 to 15. Notice the difference with the usual commands.

## 2.3. solution: process priorities

1. Create a new directory and create six **pipes** in that directory.

```
[paul@rhel53 ~]$ mkdir pipes ; cd pipes
[paul@rhel53 pipes]$ mkfifo p1 p2 p3 p4 p5 p6
[paul@rhel53 pipes]$ ls -1
total 0
prw-rw-r-- 1 paul paul 0 Apr 12 22:15 p1
prw-rw-r-- 1 paul paul 0 Apr 12 22:15 p2
prw-rw-r-- 1 paul paul 0 Apr 12 22:15 p3
prw-rw-r-- 1 paul paul 0 Apr 12 22:15 p4
prw-rw-r-- 1 paul paul 0 Apr 12 22:15 p5
prw-rw-r-- 1 paul paul 0 Apr 12 22:15 p6
```

2. Bounce a character between two **pipes**.

```
[paul@rhel53 pipes]$ echo -n x | cat - p1 > p2 &
[1] 4013
[paul@rhel53 pipes]$ cat <p2 >p1 &
[2] 4016
```

3. Use **top** and **ps** to display information (pid, ppid, priority, nice value, ...) about these two cat processes.

```
top (probably the top two lines)
[paul@rhel53 pipes]$ ps -C cat
 PID TTY TIME CMD
4013 pts/0 00:03:38 cat
4016 pts/0 00:01:07 cat
[paul@rhel53 pipes]$ ps fax | grep cat
           R
4013 pts/0
                    4:00
                                      \_ cat - p1
4016 pts/0
             S
                    1:13
                                      \setminus_ cat
4044 pts/0
           S+
                    0:00
                                      \_ grep cat
```

4. Bounce another character between two other pipes, but this time start the commands **nice**. Verify that all **cat** processes are battling for the cpu. (Feel free to fire up two more cats with the remaining pipes).

```
echo -n y | nice cat - p3 > p4 & nice cat <p4 >p3 &
```

5. Use **ps** to verify that the two new **cat** processes have a **nice** value. Use the -o and -C options of **ps** for this.

```
[paul@rhel53 pipes]$ ps -C cat -o pid,ppid,pri,ni,comm
PID PPID PRI NI COMMAND
4013 3947 14 0 cat
4016 3947 21 0 cat
4025 3947 13 10 cat
4026 3947 13 10 cat
```

6. Use **renice** to increase the nice value from 10 to 15. Notice the difference with the usual commands.

```
[paul@rhel53 pipes]$ renice +15 4025
4025: old priority 10, new priority 15
[paul@rhel53 pipes]$ renice +15 4026
```

```
4026: old priority 10, new priority 15

[paul@rhel53 pipes]$ ps -C cat -o pid,ppid,pri,ni,comm
PID PPID PRI NI COMMAND
4013 3947 14 0 cat
4016 3947 21 0 cat
4025 3947 9 15 cat
4026 3947 8 15 cat
```

| Chapter 3. background jobs |  |  |  |  |  |
|----------------------------|--|--|--|--|--|
|                            |  |  |  |  |  |
|                            |  |  |  |  |  |
|                            |  |  |  |  |  |
|                            |  |  |  |  |  |
|                            |  |  |  |  |  |
|                            |  |  |  |  |  |
|                            |  |  |  |  |  |
|                            |  |  |  |  |  |

## 3.1. background processes

### 3.1.1. jobs

Stuff that runs in background of your current shell can be displayed with the **jobs** command. By default you will not have any **jobs** running in background.

```
root@rhel53 ~# jobs
root@rhel53 ~#
```

This **jobs** command will be used several times in this section.

#### 3.1.2. control-Z

Some processes can be **suspended** with the **Ctrl-Z** key combination. This sends a **SIGSTOP** signal to the **Linux kernel**, effectively freezing the operation of the process.

When doing this in vi(m), then vi(m) goes to the background. The background vi(m) can be seen with the **jobs** command.

### **3.1.3. & ampersand**

Processes that are started in background using the & character at the end of the command line are also visible with the **jobs** command.

### 3.1.4. jobs -p

An interesting option is **jobs -p** to see the **process id** of background processes.

```
[paul@RHEL4b ~]$ sleep 500 &
[1] 4902
[paul@RHEL4b ~]$ sleep 400 &
[2] 4903
[paul@RHEL4b ~]$ jobs -p
4902
4903
[paul@RHEL4b ~]$ ps `jobs -p`
```

```
PID TTY STAT TIME COMMAND
4902 pts/0 S 0:00 sleep 500
4903 pts/0 S 0:00 sleep 400
[paul@RHEL4b ~]$
```

## 3.1.5. fg

Running the **fg** command will bring a background job to the foreground. The number of the background job to bring forward is the parameter of **fg**.

### 3.1.6. bg

Jobs that are **suspended** in background can be started in background with **bg**. The **bg** will send a **SIGCONT** signal.

Below an example of the sleep command (suspended with **Ctrl-Z**) being reactivated in background with **bg**.

```
[paul@RHEL5 ~]$ jobs
[paul@RHEL5 ~]$ sleep 5000 &
[1] 6702
[paul@RHEL5 ~]$ sleep 3000
[2]+ Stopped
                               sleep 3000
[paul@RHEL5 ~]$ jobs
[1]- Running
[2]+ Stopped
                              sleep 5000 &
                               sleep 3000
[paul@RHEL5 ~]$ bg 2
[2]+ sleep 3000 &
[paul@RHEL5 ~]$ jobs
[1]- Running
                              sleep 5000 &
[2]+ Running
                               sleep 3000 &
[paul@RHEL5 ~]$
```

## 3.2. practice: background processes

- 1. Use the **jobs** command to verify whether you have any processes running in background.
- 2. Use vi to create a little text file. Suspend vi in background.
- 3. Verify with **jobs** that **vi** is suspended in background.
- 4. Start **find** / > **allfiles.txt 2**>/**dev/null** in foreground. Suspend it in background before it finishes.
- 5. Start two long **sleep** processes in background.
- 6. Display all **jobs** in background.
- 7. Use the **kill** command to suspend the last **sleep** process.
- 8. Continue the **find** process in background (make sure it runs again).
- 9. Put one of the **sleep** commands back in foreground.
- 10. (if time permits, a general review question...) Explain in detail where the numbers come from in the next screenshot. When are the variables replaced by their value? By which shell?

```
[paul@RHEL4b ~]$ echo $$ $PPID 4224 4223 [paul@RHEL4b ~]$ bash -c "echo $$ $PPID" 4224 4223 [paul@RHEL4b ~]$ bash -c 'echo $$ $PPID' 5059 4224 [paul@RHEL4b ~]$ bash -c `echo $$ $PPID` 4223: 4224: command not found
```

## 3.3. solution: background processes

1. Use the **jobs** command to verify whether you have any processes running in background.

```
jobs (maybe the catfun is still running?)
```

2. Use vi to create a little text file. Suspend vi in background.

```
vi text.txt
(inside vi press ctrl-z)
```

3. Verify with **jobs** that **vi** is suspended in background.

```
[paul@rhe153 ~]$ jobs
[1]+ Stopped vim text.txt
```

4. Start **find** / > **allfiles.txt 2**>/**dev/null** in foreground. Suspend it in background before it finishes.

```
[paul@rhel53 ~]$ find / > allfiles.txt 2>/dev/null
   (press ctrl-z)
[2]+ Stopped find / > allfiles.txt 2> /dev/null
```

5. Start two long **sleep** processes in background.

```
sleep 4000 & ; sleep 5000 &
```

6. Display all **jobs** in background.

```
[paul@rhel53 ~]$ jobs
[1]- Stopped vim text.txt
[2]+ Stopped find / > allfiles.txt 2> /dev/null
[3] Running sleep 4000 &
[4] Running sleep 5000 &
```

7. Use the **kill** command to suspend the last **sleep** process.

```
[paul@rhel53 ~]$ kill -SIGSTOP 4519
[paul@rhel53 ~]$ jobs
[1] Stopped vim text.txt
[2]- Stopped find / > allfiles.txt 2> /dev/null
[3] Running sleep 4000 &
[4]+ Stopped sleep 5000
```

8. Continue the **find** process in background (make sure it runs again).

```
bg 2 (verify the job-id in your jobs list)
```

9. Put one of the **sleep** commands back in foreground.

```
fg 3 (again verify your job-id)
```

10. (if time permits, a general review question...) Explain in detail where the numbers come from in the next screenshot. When are the variables replaced by their value? By which shell?

```
[paul@RHEL4b ~]$ echo $$ $PPID
4224 4223
[paul@RHEL4b ~]$ bash -c "echo $$ $PPID"
```

```
4224 4223
[paul@RHEL4b ~]$ bash -c 'echo $$ $PPID'
5059 4224
[paul@RHEL4b ~]$ bash -c `echo $$ $PPID`
4223: 4224: command not found
```

The current bash shell will replace the \$\$ and \$PPID while scanning the line, and before executing the echo command.

```
[paul@RHEL4b ~]$ echo $$ $PPID
4224 4223
```

The variables are now double quoted, but the current bash shell will replace \$\$ and \$PPID while scanning the line, and before executing the bach -c command.

```
[paul@RHEL4b ~]$ bash -c "echo $$ $PPID"
4224 4223
```

The variables are now single quoted. The current bash shell will **not** replace the \$\$ and the \$PPID. The bash -c command will be executed before the variables replaced with their value. This latter bash is the one replacing the \$\$ and \$PPID with their value.

```
[paul@RHEL4b ~]$ bash -c 'echo $$ $PPID'
5059 4224
```

With backticks the shell will still replace both variable before the embedded echo is executed. The result of this echo is the two process id's. These are given as commands to bash -c. But two numbers are not commands!

```
[paul@RHEL4b ~]$ bash -c `echo $$ $PPID`
4223: 4224: command not found
```



## **Table of Contents**

| 4. disk devices                           |      |
|---|------|
| 4.1. terminology                          | . 32 |
| 4.2. device naming                        | . 34 |
| 4.3. discovering disk devices             | . 35 |
| 4.4. erasing a hard disk                  |      |
| 4.5. advanced hard disk settings          |      |
| 4.6. practice: hard disk devices          | 42   |
| 4.7. solution: hard disk devices          |      |
| 5. disk partitions                        |      |
| 5.1. about partitions                     |      |
| 5.2. discovering partitions               |      |
| 5.3. partitioning new disks               | . 49 |
| 5.4. about the partition table            | . 51 |
| 5.5. GUID partition table                 | . 52 |
| 5.6. labeling with parted                 | . 52 |
| 5.7. practice: partitions                 | . 54 |
| 5.8. solution: partitions                 | . 55 |
| 6. file systems                           | . 56 |
| 6.1. about file systems                   | . 57 |
| 6.2. common file systems                  | . 58 |
| 6.3. putting a file system on a partition | 61   |
| 6.4. tuning a file system                 | 62   |
| 6.5. checking a file system               | . 63 |
| 6.6. practice: file systems               | . 64 |
| 6.7. solution: file systems               | . 65 |
| 7. mounting                               |      |
| 7.1. mounting local file systems          | . 67 |
| 7.2. displaying mounted file systems      |      |
| 7.3. from start to finish                 | . 70 |
| 7.4. permanent mounts                     | . 71 |
| 7.5. securing mounts                      | . 72 |
| 7.6. mounting remote file systems         | . 73 |
| 7.7. practice: mounting file systems      | . 74 |
| 7.8. solution: mounting file systems      | . 75 |
| 8. troubleshooting tools                  | . 77 |
| 8.1. lsof                                 | . 78 |
| 8.2. fuser                                | . 79 |
| 8.3. chroot                               | . 80 |
| 8.4. iostat                               | . 81 |
| 8.5. iotop                                | . 82 |
| 8.6. vmstat                               | . 83 |
| 8.7. practice: troubleshooting tools      | . 84 |
| 8.8. solution: troubleshooting tools      | . 85 |
| 9. introduction to uuid's                 | . 86 |
| 9.1. about unique objects                 | . 87 |
| 9.2. tune2fs                              | . 87 |
| 9.3. uuid                                 | . 87 |
| 9.4. uuid in /etc/fstab                   |      |
| 9.5. uuid as a boot device                |      |
| 9.6. practice: uuid and filesystems       | 90   |
| 9.7. solution: uuid and filesystems       | . 91 |
| 10. introduction to raid                  |      |
| 10.1. hardware or software                | . 92 |
| 10.2. raid levels                         |      |
| 10.3. building a software raid5 array     | . 95 |

| 10.4. practice: raid                      | 98  |
|---|-----|
| 10.5. solution: raid                      |     |
| 11. logical volume management             | 100 |
| 11.1. introduction to lvm                 |     |
| 11.2. lvm terminology                     | 102 |
| 11.3. example: using lvm                  | 103 |
| 11.4. example: extend a logical volume    |     |
| 11.5. example: resize a physical Volume   | 107 |
| 11.6. example: mirror a logical volume    | 109 |
| 11.7. example: snapshot a logical volume  | 110 |
| 11.8. verifying existing physical volumes | 111 |
| 11.9. verifying existing volume groups    | 113 |
| 11.10. verifying existing logical volumes | 114 |
| 11.11. manage physical volumes            | 115 |
| 11.12. manage volume groups               | 117 |
| 11.13. manage logical volumes             | 119 |
| 11.14. practice : lvm                     | 121 |
| 11.15. solution : lvm                     | 122 |
| 12. iSCSI devices                         | 126 |
| 12.1. iSCSI terminology                   | 127 |
| 12.2. iSCSI Target in RHEL/CentOS         | 127 |
| 12.3. iSCSI Initiator in RHEL/CentOS      | 129 |
| 12.4. iSCSI target on Debian              | 131 |
| 12.5. iSCSI target setup with dd files    |     |
| 12.6. ISCSI initiator on ubuntu           |     |
| 12.7. using iSCSI devices                 | 136 |
| 12.8. iSCSI Target RHEL7/CentOS7          |     |
| 12.9. iSCSI Initiator RHEL7/CentOS7       |     |
| 12.10. practice: iSCSI devices            |     |
| 12.11. solution: iSCSI devices            |     |
| 13. introduction to multipathing          |     |
| 13.1. install multipath                   |     |
| 13.2. configure multipath                 |     |
| 13.3. network                             |     |
| 13.4. start multipathd and iscsi          |     |
| 13.5. multipath list                      |     |
| 13.6. using the device                    |     |
| 13.7. practice: multipathing              |     |
| 13.8. solution: multipathing              | 153 |

# Chapter 4. disk devices

This chapter teaches you how to locate and recognise **hard disk devices**. This prepares you for the next chapter, where we put **partitions** on these devices.

# 4.1. terminology

### 4.1.1. platter, head, track, cylinder, sector

Data is commonly stored on magnetic or optical **disk platters**. The platters are rotated (at high speeds). Data is read by **heads**, which are very close to the surface of the platter, without touching it! The heads are mounted on an arm (sometimes called a comb or a fork).

Data is written in concentric circles called **tracks**. Track zero is (usually) on the outside. The time it takes to position the head over a certain track is called the **seek time**. Often the platters are stacked on top of each other, hence the set of tracks accessible at a certain position of the comb forms a **cylinder**. Tracks are divided into 512 byte **sectors**, with more unused space (**gap**) between the sectors on the outside of the platter.

When you break down the advertised **access time** of a hard drive, you will notice that most of that time is taken by movement of the heads (about 65%) and **rotational latency** (about 30%).

#### 4.1.2. ide or scsi

Actually, the title should be **ata** or **scsi**, since ide is an ata compatible device. Most desktops use **ata devices**, most servers use **scsi**.

#### 4.1.3. ata

An **ata controller** allows two devices per bus, one **master** and one **slave**. Unless your controller and devices support **cable select**, you have to set this manually with jumpers.

With the introduction of **sata** (serial ata), the original ata was renamed to **parallel ata**. Optical drives often use **atapi**, which is an ATA interface using the SCSI communication protocol.

#### 4.1.4. scsi

A scsi controller allows more than two devices. When using SCSI (small computer system interface), each device gets a unique scsi id. The scsi controller also needs a scsi id, do not use this id for a scsi-attached device.

Older 8-bit SCSI is now called **narrow**, whereas 16-bit is **wide**. When the bus speeds was doubled to 10Mhz, this was known as **fast SCSI**. Doubling to 20Mhz made it **ultra SCSI**. Take a look at http://en.wikipedia.org/wiki/SCSI for more SCSI standards.

#### 4.1.5. block device

Random access hard disk devices have an abstraction layer called **block device** to enable formatting in fixed-size (usually 512 bytes) blocks. Blocks can be accessed independent of access to other blocks.

A block device has the letter b to denote the file type in the output of **ls -l**.

```
[root@centos65 ~]# ls -l /dev/sd*
brw-rw---. 1 root disk 8, 0 Apr 19 10:12 /dev/sda
brw-rw---. 1 root disk 8, 1 Apr 19 10:12 /dev/sda1
brw-rw---. 1 root disk 8, 2 Apr 19 10:12 /dev/sda2
brw-rw---. 1 root disk 8, 16 Apr 19 10:12 /dev/sdb
brw-rw---. 1 root disk 8, 32 Apr 19 10:12 /dev/sdc
```


Note that a **character device** is a constant stream of characters, being denoted by a c in **ls** - **l**. Note also that the **ISO 9660** standard for cdrom uses a **2048 byte** block size.

Old hard disks (and floppy disks) use **cylinder-head-sector** addressing to access a sector on the disk. Most current disks use **LBA** (**Logical Block Addressing**).

#### 4.1.6. solid state drive

A **solid state drive** or **ssd** is a block device without moving parts. It is comparable to **flash memory**. An **ssd** is more expensive than a hard disk, but it typically has a much faster access time.

In this book we will use the following pictograms for **spindle disks** (in brown) and **solid state disks** (in blue).



# 4.2. device naming

## 4.2.1. ata (ide) device naming

All **ata** drives on your system will start with **/dev/hd** followed by a unit letter. The master hdd on the first **ata controller** is /dev/hda, the slave is /dev/hdb. For the second controller, the names of the devices are /dev/hdc and /dev/hdd.

Table 4.1. ide device naming

| controller | connection | device name |
|------------|------------|-------------|
| ide0       | master     | /dev/hda    |
| ideo       | slave      | /dev/hdb    |
| ide1       | master     | /dev/hdc    |
|            | slave      | /dev/hdd    |

It is possible to have only /dev/hda and /dev/hdd. The first one is a single ata hard disk, the second one is the cdrom (by default configured as slave).

## 4.2.2. scsi device naming

**scsi** drives follow a similar scheme, but all start with /dev/sd. When you run out of letters (after/dev/sdz), you can continue with /dev/sdaa and /dev/sdab and so on. (We will see later on that **lvm** volumes are commonly seen as /dev/md0, /dev/md1 etc.)

Below a **sample** of how scsi devices on a Linux can be named. Adding a scsi disk or raid controller with a lower scsi address will change the naming scheme (shifting the higher scsi addresses one letter further in the alphabet).

Table 4.2. scsi device naming

| device            | scsi id | device name |
|-------------------|---------|-------------|
| disk 0            | 0       | /dev/sda    |
| disk 1            | 1       | /dev/sdb    |
| raid controller 0 | 5       | /dev/sdc    |
| raid controller 1 | 6       | /dev/sdd    |

A modern Linux system will use /dev/sd\* for scsi and sata devices, and also for sd-cards, usb-sticks, (legacy) ATA/IDE devices and solid state drives.

# 4.3. discovering disk devices

#### 4.3.1. fdisk

You can start by using /sbin/fdisk to find out what kind of disks are seen by the kernel. Below the result on old Debian desktop, with two ata-ide disks present.

```
root@barry:~# fdisk -l | grep Disk
Disk /dev/hda: 60.0 GB, 60022480896 bytes
Disk /dev/hdb: 81.9 GB, 81964302336 bytes
```

And here an example of **sata and scsi disks** on a server with CentOS. Remember that **sata** disks are also presented to you with the **scsi** /dev/sd\* notation.

```
[root@centos65 ~]# fdisk -1 | grep 'Disk /dev/sd'
Disk /dev/sda: 42.9 GB, 42949672960 bytes
Disk /dev/sdb: 77.3 GB, 77309411328 bytes
Disk /dev/sdc: 154.6 GB, 154618822656 bytes
Disk /dev/sdd: 154.6 GB, 154618822656 bytes
```

Here is an overview of disks on a RHEL4u3 server with two real 72GB **scsi disks**. This server is attached to a **NAS** with four **NAS disks** of half a terabyte. On the NAS disks, four LVM (/dev/mdx) software RAID devices are configured.

```
[root@tsvtl1 ~]# fdisk -l | grep Disk
Disk /dev/sda: 73.4 GB, 73407488000 bytes
Disk /dev/sdb: 73.4 GB, 73407488000 bytes
Disk /dev/sdc: 499.0 GB, 499036192768 bytes
Disk /dev/sdd: 499.0 GB, 499036192768 bytes
Disk /dev/sde: 499.0 GB, 499036192768 bytes
Disk /dev/sdf: 499.0 GB, 499036192768 bytes
Disk /dev/md0: 271 MB, 271319040 bytes
Disk /dev/md0: 21.4 GB, 21476081664 bytes
Disk /dev/md3: 21.4 GB, 21467889664 bytes
Disk /dev/md1: 21.4 GB, 21476081664 bytes
```

You can also use **fdisk** to obtain information about one specific hard disk device.

```
[root@centos65 ~]# fdisk -l /dev/sdc

Disk /dev/sdc: 154.6 GB, 154618822656 bytes
255 heads, 63 sectors/track, 18798 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk identifier: 0x00000000
```

Later we will use fdisk to do dangerous stuff like creating and deleting partitions.

#### 4.3.2. dmesg

Kernel boot messages can be seen after boot with **dmesg**. Since hard disk devices are detected by the kernel during boot, you can also use dmesg to find information about disk devices.

```
[root@centos65 ~]# dmesg | grep 'sd[a-z]' | head
sd 0:0:0:0: [sda] 83886080 512-byte logical blocks: (42.9 GB/40.0 GiB)
sd 0:0:0:0: [sda] Write Protect is off
sd 0:0:0:0: [sda] Mode Sense: 00 3a 00 00
sd 0:0:0:0: [sda] Write cache: enabled, read cache: enabled, doesn't support \
DPO or FUA
sda: sda1 sda2
sd 0:0:0:0: [sda] Attached SCSI disk
sd 3:0:0:0: [sdb] 150994944 512-byte logical blocks: (77.3 GB/72.0 GiB)
sd 3:0:0:0: [sdb] Write Protect is off
sd 3:0:0:0: [sdb] Mode Sense: 00 3a 00 00
sd 3:0:0:0: [sdb] Write cache: enabled, read cache: enabled, doesn't support \
DPO or FUA
```

Here is another example of **dmesg** on a computer with a 200GB at disk.

```
paul@barry:~$ dmesg | grep -i "ata disk"
[    2.624149] hda: ST360021A, ATA DISK drive
[    2.904150] hdb: Maxtor 6Y080L0, ATA DISK drive
[    3.472148] hdd: WDC WD2000BB-98DWA0, ATA DISK drive
```

Third and last example of **dmesg** running on RHEL5.3.

```
root@rhel53 ~# dmesg | grep -i "scsi disk"
sd 0:0:2:0: Attached scsi disk sda
sd 0:0:3:0: Attached scsi disk sdb
sd 0:0:6:0: Attached scsi disk sdc
```

#### 4.3.3. /sbin/lshw

The **lshw** tool will **list hardware**. With the right options **lshw** can show a lot of information about disks (and partitions).

Below a truncated screenshot on Debian 6:

```
root@debian6~# lshw -class volume | grep -A1 -B2 scsi
      description: Linux raid autodetect partition
      physical id: 1
      bus info: scsi@1:0.0.0,1
      logical name: /dev/sdb1
      description: Linux raid autodetect partition
      physical id: 1
      bus info: scsi@2:0.0.0,1
      logical name: /dev/sdc1
      description: Linux raid autodetect partition
      physical id: 1
      bus info: scsi@3:0.0.0,1
      logical name: /dev/sdd1
      description: Linux raid autodetect partition
      physical id: 1
      bus info: scsi@4:0.0.0,1
      logical name: /dev/sde1
      vendor: Linux
      physical id: 1
      bus info: scsi@0:0.0.0,1
      logical name: /dev/sda1
      vendor: Linux
      physical id: 2
      bus info: scsi@0:0.0.0,2
      logical name: /dev/sda2
      description: Extended partition
      physical id: 3
      bus info: scsi@0:0.0.0,3
      logical name: /dev/sda3
```

Redhat and CentOS do not have this tool (unless you add a repository).

## 4.3.4. /sbin/lsscsi

The **Isscsi** command provides a nice readable output of all scsi (and scsi emulated devices). This first screenshot shows **Isscsi** on a SPARC system.

```
root@shaka:~# lsscsi
[0:0:0:0] disk Adaptec RAID5 V1.0 /dev/sda
[1:0:0:0] disk SEAGATE ST336605FSUN36G 0438 /dev/sdb
root@shaka:~#
```

Below a screenshot of **Isscsi** on a QNAP NAS (which has four 750GB disks and boots from a usb stick).

```
lroot@debian6~# lsscsi
[0:0:0:0] disk SanDisk Cruzer Edge
                                      1.19 /dev/sda
[1:0:0:0]
          disk
                 ATA
                        ST3750330AS
                                      SD04 /dev/sdb
[2:0:0:0] disk
                 ATA
                        ST3750330AS
                                        SD04 /dev/sdc
[3:0:0:0] disk
                 ATA
                         ST3750330AS
                                        SD04 /dev/sdd
[4:0:0:0] disk
                 ATA
                     ST3750330AS
                                        SD04 /dev/sde
```

This screenshot shows the classic output of **lsscsi**.

```
root@debian6~# lsscsi -c
Attached devices:
Host: scsi0 Channel: 00 Target: 00 Lun: 00
 Vendor: SanDisk Model: Cruzer Edge
                                         Rev: 1.19
 Type: Direct-Access
                                         ANSI SCSI revision: 02
Host: scsil Channel: 00 Target: 00 Lun: 00
              Model: ST3750330AS
 Vendor: ATA
                                         Rev: SD04
 Type: Direct-Access
                                         ANSI SCSI revision: 05
Host: scsi2 Channel: 00 Target: 00 Lun: 00
 Vendor: ATA
                Model: ST3750330AS
                                         Rev: SD04
 Type:
         Direct-Access
                                         ANSI SCSI revision: 05
Host: scsi3 Channel: 00 Target: 00 Lun: 00
                                         Rev: SD04
 Vendor: ATA Model: ST3750330AS
 Type: Direct-Access
                                         ANSI SCSI revision: 05
Host: scsi4 Channel: 00 Target: 00 Lun: 00
                                         Rev: SD04
 Vendor: ATA Model: ST3750330AS
 Type: Direct-Access
                                         ANSI SCSI revision: 05
```

## 4.3.5. /proc/scsi/scsi

Another way to locate scsi (or sd) devices is via /proc/scsi/scsi.

This screenshot is from a **sparc** computer with adaptec RAID5.

Here we run **cat /proc/scsi/scsi** on the QNAP from above (with Debian Linux).

```
root@debian6~# cat /proc/scsi/scsi
Attached devices:
Host: scsi0 Channel: 00 Id: 00 Lun: 00
 Vendor: SanDisk Model: Cruzer Edge
                                         Rev: 1.19
                                        ANSI SCSI revision: 02
         Direct-Access
 Type:
Host: scsil Channel: 00 Id: 00 Lun: 00
 Vendor: ATA
                Model: ST3750330AS
                                        Rev: SD04
 Type: Direct-Access
                                        ANSI SCSI revision: 05
Host: scsi2 Channel: 00 Id: 00 Lun: 00
 Vendor: ATA Model: ST3750330AS
                                        Rev: SD04
                                        ANSI SCSI revision: 05
 Type: Direct-Access
Host: scsi3 Channel: 00 Id: 00 Lun: 00
                Model: ST3750330AS
                                        Rev: SD04
 Vendor: ATA
 Type: Direct-Access
                                        ANSI SCSI revision: 05
Host: scsi4 Channel: 00 Id: 00 Lun: 00
 Vendor: ATA Model: ST3750330AS
                                         Rev: SD04
 Type: Direct-Access
                                         ANSI SCSI revision: 05
```

Note that some recent versions of Debian have this disabled in the kernel. You can enable it (after a kernel compile) using this entry:

```
# CONFIG_SCSI_PROC_FS is not set
```

Redhat and CentOS have this by default (if there are scsi devices present).

```
[root@centos65 ~]# cat /proc/scsi/scsi
Attached devices:
Host: scsi0 Channel: 00 Id: 00 Lun: 00
 Vendor: ATA Model: VBOX HARDDISK
                                        Rev: 1.0
 Type: Direct-Access
                                        ANSI SCSI revision: 05
Host: scsi3 Channel: 00 Id: 00 Lun: 00
 Vendor: ATA
               Model: VBOX HARDDISK
                                        Rev: 1.0
 Type: Direct-Access
                                        ANSI SCSI revision: 05
Host: scsi4 Channel: 00 Id: 00 Lun: 00
             Model: VBOX HARDDISK
 Vendor: ATA
                                        Rev: 1.0
 Type: Direct-Access
                                        ANSI SCSI revision: 05
```

# 4.4. erasing a hard disk

Before selling your old hard disk on the internet, it may be a good idea to erase it. By simply repartitioning, or by using the Microsoft Windows format utility, or even after an **mkfs** command, some people will still be able to read most of the data on the disk.

```
root@debian6~# aptitude search foremost autopsy sleuthkit | tr -s ' '
p autopsy - graphical interface to SleuthKit
p foremost - Forensics application to recover data
p sleuthkit - collection of tools for forensics analysis
```

Although technically the /sbin/badblocks tool is meant to look for bad blocks, you can use it to completely erase all data from a disk. Since this is really writing to every sector of the disk, it can take a long time!

```
root@RHELv4u2:~# badblocks -ws /dev/sdb

Testing with pattern 0xaa: done

Reading and comparing: done

Testing with pattern 0x55: done

Reading and comparing: done

Testing with pattern 0xff: done

Reading and comparing: done

Testing with pattern 0x00: done

Reading and comparing: done

Reading and comparing: done
```

The previous screenshot overwrites every sector of the disk **four times**. Erasing **once** with a tool like **dd** is enough to destroy all data.

Warning, this screenshot shows how to permanently destroy all data on a block device.

```
[root@rhel65 ~]# dd if=/dev/zero of=/dev/sdb
```

# 4.5. advanced hard disk settings

Tweaking of hard disk settings (dma, gap, ...) are not covered in this course. Several tools exists, **hdparm** and **sdparm** are two of them.

**hdparm** can be used to display or set information and parameters about an ATA (or SATA) hard disk device. The -i and -I options will give you even more information about the physical properties of the device.

```
root@laika:~# hdparm /dev/sdb

/dev/sdb:
    IO_support = 0 (default 16-bit)
    readonly = 0 (off)
    readahead = 256 (on)
    geometry = 12161/255/63, sectors = 195371568, start = 0
```

Below **hdparm** info about a 200GB IDE disk.

Here a screenshot of **sdparm** on Ubuntu 10.10.

```
root@ubu1010:~# aptitude install sdparm
...
root@ubu1010:~# sdparm /dev/sda | head -1
    /dev/sda: ATA         FUJITSU MJA2160B 0081
root@ubu1010:~# man sdparm
```

Use **hdparm** and **sdparm** with care.

# 4.6. practice: hard disk devices

**About this lab:** To practice working with hard disks, you will need some hard disks. When there are no physical hard disk available, you can use virtual disks in **vmware** or **VirtualBox**. The teacher will help you in attaching a couple of ATA and/or SCSI disks to a virtual machine. The results of this lab can be used in the next three labs (partitions, file systems, mounting).

It is adviced to attach three 1GB disks and three 2GB disks to the virtual machine. This will allow for some freedom in the practices of this chapter as well as the next chapters (raid, lvm, iSCSI).

- 1. Use **dmesg** to make a list of hard disk devices detected at boot-up.
- 2. Use **fdisk** to find the total size of all hard disk devices on your system.
- 3. Stop a virtual machine, add three virtual 1 gigabyte **scsi** hard disk devices and one virtual 400 megabyte **ide** hard disk device. If possible, also add another virtual 400 megabyte **ide** disk.
- 4. Use **dmesg** to verify that all the new disks are properly detected at boot-up.
- 5. Verify that you can see the disk devices in /dev.
- 6. Use **fdisk** (with **grep** and **/dev/null**) to display the total size of the new disks.
- 7. Use **badblocks** to completely erase one of the smaller hard disks.
- 8. Look at /proc/scsi/scsi.
- 9. If possible, install **lsscsi**, **lshw** and use them to list the disks.

#### 4.7. solution: hard disk devices

1. Use **dmesg** to make a list of hard disk devices detected at boot-up.

```
Some possible answers...

dmesg | grep -i disk

Looking for ATA disks: dmesg | grep hd[abcd]

Looking for ATA disks: dmesg | grep -i "ata disk"

Looking for SCSI disks: dmesg | grep sd[a-f]

Looking for SCSI disks: dmesg | grep -i "scsi disk"
```

2. Use **fdisk** to find the total size of all hard disk devices on your system.

```
fdisk -l
```

3. Stop a virtual machine, add three virtual 1 gigabyte **scsi** hard disk devices and one virtual 400 megabyte **ide** hard disk device. If possible, also add another virtual 400 megabyte **ide** disk.

```
This exercise happens in the settings of vmware or VirtualBox.
```

4. Use **dmesg** to verify that all the new disks are properly detected at boot-up.

```
See 1.
```

5. Verify that you can see the disk devices in /dev.

```
SCSI+SATA: ls -l /dev/sd*

ATA: ls -l /dev/hd*
```

6. Use **fdisk** (with **grep** and **/dev/null**) to display the total size of the new disks.

```
root@rhel53 ~# fdisk -l 2>/dev/null | grep [MGT]B

Disk /dev/hda: 21.4 GB, 21474836480 bytes

Disk /dev/hdb: 1073 MB, 1073741824 bytes

Disk /dev/sda: 2147 MB, 2147483648 bytes

Disk /dev/sdb: 2147 MB, 2147483648 bytes

Disk /dev/sdc: 2147 MB, 2147483648 bytes
```

7. Use **badblocks** to completely erase one of the smaller hard disks.

```
#Verify the device (/dev/sdc??) you want to erase before typing this.
#
root@rhel53 ~# badblocks -ws /dev/sdc
Testing with pattern 0xaa: done
Reading and comparing: done
Testing with pattern 0x55: done
Reading and comparing: done
Testing with pattern 0xff: done
Reading and comparing: done
Testing with pattern 0x00: done
Reading and comparing: done
```

8. Look at /proc/scsi/scsi.

```
root@rhel53 ~# cat /proc/scsi/scsi
```

```
Attached devices:
Host: scsi0 Channel: 00 Id: 02 Lun: 00
 Vendor: VBOX Model: HARDDISK
                                        Rev: 1.0
 Type: Direct-Access
                                        ANSI SCSI revision: 05
Host: scsi0 Channel: 00 Id: 03 Lun: 00
 Vendor: VBOX Model: HARDDISK
                                        Rev: 1.0
                                        ANSI SCSI revision: 05
 Type: Direct-Access
Host: scsi0 Channel: 00 Id: 06 Lun: 00
 Vendor: VBOX Model: HARDDISK
                                        Rev: 1.0
 Type: Direct-Access
                                        ANSI SCSI revision: 05
```

#### 9. If possible, install **lsscsi**, **lshw** and use them to list the disks.

Debian, Ubuntu: aptitude install lsscsi lshw Fedora: yum install lsscsi lshw root@rhel53 ~# lsscsi [0:0:2:0] disk VBOX 1.0 /dev/sda HARDDISK disk VBOX [0:0:3:0] HARDDISK 1.0 /dev/sdb [0:0:6:0] disk VBOX HARDDISK 1.0 /dev/sdc

# Chapter 5. disk partitions

This chapter continues on the **hard disk devices** from the previous one. Here we will put **partitions** on those devices.

This chapter prepares you for the next chapter, where we put **file systems** on our partitions.

## 5.1. about partitions

#### 5.1.1. primary, extended and logical

Linux requires you to create one or more **partitions**. The next paragraphs will explain how to create and use partitions.

A partition's **geometry** and size is usually defined by a starting and ending cylinder (sometimes by sector). Partitions can be of type **primary** (maximum four), **extended** (maximum one) or **logical** (contained within the extended partition). Each partition has a **type field** that contains a code. This determines the computers operating system or the partitions file system.

Table 5.1. primary, extended and logical partitions

| Partition Type   | naming |
|------------------|--------|
| Primary (max 4)  | 1-4    |
| Extended (max 1) | 1-4    |
| Logical          | 5-     |


#### 5.1.2. partition naming

We saw before that hard disk devices are named /dev/hdx or /dev/sdx with x depending on the hardware configuration. Next is the partition number, starting the count at 1. Hence the four (possible) primary partitions are numbered 1 to 4. Logical partition counting always starts at 5. Thus /dev/hda2 is the second partition on the first ATA hard disk device, and / dev/hdb5 is the first logical partition on the second ATA hard disk device. Same for SCSI, / dev/sdb3 is the third partition on the second SCSI disk.

**Table 5.2. Partition naming** 

| partition | device   |
|-----------|--|
| /dev/hda1 | first primary partition on /dev/hda              |
| /dev/hda2 | second primary or extended partition on /dev/hda |
| /dev/sda5 | first logical drive on /dev/sda                  |
| /dev/sdb6 | second logical on /dev/sdb                       |

The picture below shows two (spindle) disks with partitions. Note that an extended partition is a container holding logical drives.



# 5.2. discovering partitions

#### 5.2.1. fdisk -l

In the **fdisk -1** example below you can see that two partitions exist on **/dev/sdb**. The first partition spans 31 cylinders and contains a Linux swap partition. The second partition is much bigger.

```
root@laika:~# fdisk -l /dev/sdb

Disk /dev/sdb: 100.0 GB, 100030242816 bytes

255 heads, 63 sectors/track, 12161 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes

Device Boot Start End Blocks Id System
/dev/sdb1 1 31 248976 82 Linux swap / Solaris
/dev/sdb2 32 12161 97434225 83 Linux
root@laika:~#
```

## 5.2.2. /proc/partitions

The /proc/partitions file contains a table with major and minor number of partitioned devices, their number of blocks and the device name in /dev. Verify with /proc/devices to link the major number to the proper device.

```
paul@RHELv4u4:~$ cat /proc/partitions
major minor #blocks name
       0
           524288 hda
           734003 hdb
  3
      64
      0 8388608 sda
      1
           104391 sda1
      2 8281507 sda2
  8
  8
     16 1048576 sdb
  8
     32 1048576 sdc
  8
     48 1048576 sdd
    0
1
253
           7176192 dm-0
           1048576 dm-1
```

The **major** number corresponds to the device type (or driver) and can be found in **/proc/devices**. In this case 3 corresponds to **ide** and 8 to **sd**. The **major** number determines the **device driver** to be used with this device.

The **minor** number is a unique identification of an instance of this device type. The **devices.txt** file in the kernel tree contains a full list of major and minor numbers.

#### 5.2.3. parted and others

You may be interested in alternatives to **fdisk** like **parted**, **cfdisk**, **sfdisk** and **gparted**. This course mainly uses **fdisk** to partition hard disks.

**parted** is recommended by some Linux distributions for handling storage with **gpt** instead of **mbr**.

Below a screenshot of **parted** on CentOS.

```
[root@centos65 ~]# rpm -q parted
parted-2.1-21.el6.x86_64
[root@centos65 ~]# parted /dev/sda
GNU Parted 2.1
Using /dev/sda
Welcome to GNU Parted! Type 'help' to view a list of commands.
(parted) print
Model: ATA VBOX HARDDISK (scsi)
Disk /dev/sda: 42.9GB
Sector size (logical/physical): 512B/512B
Partition Table: msdos
Number Start End Size
                             Type
                                     File system Flags
       1049kB 525MB 524MB primary ext4
1
                                                   boot
       525MB 42.9GB 42.4GB primary
                                                   lvm
(parted)
```

# 5.3. partitioning new disks

In the example below, we bought a new disk for our system. After the new hardware is properly attached, you can use **fdisk** and **parted** to create the necessary partition(s). This example uses **fdisk**, but there is nothing wrong with using **parted**.

#### 5.3.1. recognising the disk

First, we check with **fdisk** -**l** whether Linux can see the new disk. Yes it does, the new disk is seen as /dev/sdb, but it does not have any partitions yet.

```
root@RHELv4u2:~# fdisk -1
Disk /dev/sda: 12.8 GB, 12884901888 bytes
255 heads, 63 sectors/track, 1566 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
                                Blocks Id System
Device Boot
               Start
                         End
/dev/sda1 *
               1
                          13
                                 104391 83 Linux
                         1566
/dev/sda2
                  14
                                12474472+ 8e Linux LVM
Disk /dev/sdb: 1073 MB, 1073741824 bytes
255 heads, 63 sectors/track, 130 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
Disk /dev/sdb doesn't contain a valid partition table
```

## 5.3.2. opening the disk with fdisk

Then we create a partition with fdisk on /dev/sdb. First we start the fdisk tool with /dev/sdb as argument. Be very very careful not to partition the wrong disk!!

```
root@RHELv4u2:~# fdisk /dev/sdb
Device contains neither a valid DOS partition table, nor Sun, SGI...
Building a new DOS disklabel. Changes will remain in memory only,
until you decide to write them. After that, of course, the previous
content won't be recoverable.

Warning: invalid flag 0x0000 of partition table 4 will be corrected...
```

## 5.3.3. empty partition table

Inside the fdisk tool, we can issue the **p** command to see the current disks partition table.

```
Command (m for help): p

Disk /dev/sdb: 1073 MB, 1073741824 bytes

255 heads, 63 sectors/track, 130 cylinders

Units = cylinders of 16065 * 512 = 8225280 bytes

Device Boot Start End Blocks Id System
```

#### 5.3.4. create a new partition

No partitions exist yet, so we issue  $\mathbf{n}$  to create a new partition. We choose p for primary, 1 for the partition number, 1 for the start cylinder and 14 for the end cylinder.

```
Command (m for help): n

Command action

e extended

p primary partition (1-4)

p

Partition number (1-4): 1

First cylinder (1-130, default 1):

Using default value 1

Last cylinder or +size or +sizeM or +sizeK (1-130, default 130): 14
```

We can now issue p again to verify our changes, but they are not yet written to disk. This means we can still cancel this operation! But it looks good, so we use **w** to write the changes to disk, and then quit the fdisk tool.

```
Command (m for help): p

Disk /dev/sdb: 1073 MB, 1073741824 bytes

255 heads, 63 sectors/track, 130 cylinders

Units = cylinders of 16065 * 512 = 8225280 bytes

Device Boot Start End Blocks Id System
/dev/sdb1 1 14 112423+ 83 Linux

Command (m for help): w
The partition table has been altered!

Calling ioctl() to re-read partition table.

Syncing disks.
root@RHELv4u2:~#
```

## 5.3.5. display the new partition

Let's verify again with **fdisk -l** to make sure reality fits our dreams. Indeed, the screenshot below now shows a partition on /dev/sdb.

```
root@RHELv4u2:~# fdisk -1
Disk /dev/sda: 12.8 GB, 12884901888 bytes
255 heads, 63 sectors/track, 1566 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
                                  Blocks Id System
104391 83 Linux
              1
Device Boot
                          End
/dev/sda1 *
                           13
                         1566 12474472+ 8e Linux LVM
/dev/sda2
                 14
Disk /dev/sdb: 1073 MB, 1073741824 bytes
255 heads, 63 sectors/track, 130 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
                                     Blocks Id System
Device Boot
              Start
                           End
                           14
/dev/sdb1
                      1
                                     112423+ 83 Linux
root@RHELv4u2:~#
```

## 5.4. about the partition table

#### 5.4.1. master boot record

The **partition table** information (primary and extended partitions) is written in the **master boot record** or **mbr**. You can use **dd** to copy the mbr to a file.

This example copies the master boot record from the first SCSI hard disk.

```
dd if=/dev/sda of=/SCSIdisk.mbr bs=512 count=1
```

The same tool can also be used to wipe out all information about partitions on a disk. This example writes zeroes over the master boot record.

```
dd if=/dev/zero of=/dev/sda bs=512 count=1
```

Or to wipe out the whole partition or disk.

```
dd if=/dev/zero of=/dev/sda
```

#### 5.4.2. partprobe

Don't forget that after restoring a **master boot record** with **dd**, that you need to force the kernel to reread the partition table with **partprobe**. After running **partprobe**, the partitions can be used again.

```
[root@RHEL5 ~]# partprobe
[root@RHEL5 ~]#
```

#### 5.4.3. logical drives

The **partition table** does not contain information about **logical drives**. So the **dd** backup of the **mbr** only works for primary and extended partitions. To backup the partition table including the logical drives, you can use **sfdisk**.

This example shows how to backup all partition and logical drive information to a file.

```
sfdisk -d /dev/sda > parttable.sda.sfdisk
```

The following example copies the **mbr** and all **logical drive** info from /dev/sda to /dev/sdb.

```
sfdisk -d /dev/sda | sfdisk /dev/sdb
```

# 5.5. GUID partition table

**gpt** was developed because of the limitations of the 1980s **mbr** partitioning scheme (for example only four partitions can be defined, and they have a maximum size two terabytes).

Since 2010 **gpt** is a part of the **uefi** specification, but it is also used on **bios** systems.

Newer versions of **fdisk** work fine with **gpt**, but most production servers today (mid 2015) still have an older **fdisk**. You can use **parted** instead.

# 5.6. labeling with parted

**parted** is an interactive tool, just like **fdisk**. Type **help** in **parted** for a list of commands and options.

This screenshot shows how to start **parted** to manage partitions on /dev/sdb.

```
[root@rhel71 ~]# parted /dev/sdb
GNU Parted 3.1
Using /dev/sdb
Welcome to GNU Parted! Type 'help' to view a list of commands.
(parted)
```

Each command also has built-in help. For example **help mklabel** will list all supported labels. Note that we only discussed **mbr**(msdos) and **gpt** in this book.

We create an **mbr** label.

```
(parted) mklabel msdos>
Warning: The existing disk label on /dev/sdb will be destroyed and all data on
this disk will be lost. Do you want to continue?
Yes/No? yes
(parted) mklabel gpt
Warning: The existing disk label on /dev/sdb will be destroyed and all data on
this disk will be lost. Do you want to continue?
Yes/No? Y
(parted)
```

### 5.6.1. partitioning with parted

Once labeled it is easy to create partitions with **parted**. This screenshot starts with an unpartitioned (but **gpt** labeled) disk.

```
(parted) print
Model: ATA VBOX HARDDISK (scsi)
Disk /dev/sdb: 8590MB
Sector size (logical/physical): 512B/512B
Partition Table: gpt
Disk Flags:
Number Start End Size File system Name Flags
(parted)
```

This example shows how to create two primary partitions of equal size.

```
(parted) mkpart primary 0 50%
Warning: The resulting partition is not properly aligned for best performance.
Ignore/Cancel? I
(parted) mkpart primary 50% 100%
(parted)
```

Verify with **print** and exit with **quit**. Since **parted** works directly on the disk, there is no need to **w(rite)** like in **fdisk**.

```
(parted) print
Model: ATA VBOX HARDDISK (scsi)
Disk /dev/sdb: 8590MB
Sector size (logical/physical): 512B/512B
Partition Table: gpt
Disk Flags:
Number Start End
                      Size
                              File system Name
                                                   Flags
       17.4kB 4295MB 4295MB
1
                                          primary
       4295MB 8589MB 4294MB
                                          primary
(parted) quit
Information: You may need to update /etc/fstab.
[root@rhel71 ~]#
```

# 5.7. practice: partitions

- 1. Use **fdisk -l** to display existing partitions and sizes.
- 2. Use **df** -**h** to display existing partitions and sizes.
- 3. Compare the output of **fdisk** and **df**.
- 4. Create a 200MB primary partition on a small disk.
- 5. Create a 400MB primary partition and two 300MB logical drives on a big disk.
- 6. Use **df** -**h** and **fdisk** -**l** to verify your work.
- 7. Compare the output again of **fdisk** and **df**. Do both commands display the new partitions?
- 8. Create a backup with **dd** of the **mbr** that contains your 200MB primary partition.
- 9. Take a backup of the **partition table** containing your 400MB primary and 300MB logical drives. Make sure the logical drives are in the backup.
- 10. (optional) Remove all your partitions with fdisk. Then restore your backups.

# 5.8. solution: partitions

1. Use **fdisk** -l to display existing partitions and sizes.

```
as root: # fdisk -l
```

2. Use **df** -**h** to display existing partitions and sizes.

```
df -h
```

3. Compare the output of **fdisk** and **df**.

```
Some partitions will be listed in both outputs (maybe /dev/sda1 or /dev/hda1).
```

4. Create a 200MB primary partition on a small disk.

```
Choose one of the disks you added (this example uses /dev/sdc).

root@rhel53 ~# fdisk /dev/sdc
...

Command (m for help): n

Command action
    e extended
    p primary partition (1-4)

p

Partition number (1-4): 1

First cylinder (1-261, default 1): 1

Last cylinder or +size or +sizeM or +sizeK (1-261, default 261): +200m

Command (m for help): w

The partition table has been altered!

Calling ioctl() to re-read partition table.

Syncing disks.
```

5. Create a 400MB primary partition and two 300MB logical drives on a big disk.

```
Choose one of the disks you added (this example uses /dev/sdb)

fdisk /dev/sdb

inside fdisk : n p 1 +400m enter --- n e 2 enter enter --- n 1 +300m (twice)
```

6. Use **df** -**h** and **fdisk** -**l** to verify your work.

```
fdisk -l ; df -h
```

7. Compare the output again of **fdisk** and **df**. Do both commands display the new partitions?

```
The newly created partitions are visible with fdisk.

But they are not displayed by df.
```

8. Create a backup with **dd** of the **mbr** that contains your 200MB primary partition.

```
dd if=/dev/sdc of=bootsector.sdc.dd count=1 bs=512
```

9. Take a backup of the **partition table** containing your 400MB primary and 300MB logical drives. Make sure the logical drives are in the backup.

```
sfdisk -d /dev/sdb > parttable.sdb.sfdisk
```

# Chapter 6. file systems

When you are finished partitioning the hard disk, you can put a **file system** on each partition.

This chapter builds on the **partitions** from the previous chapter, and prepares you for the next one where we will **mount** the filesystems.

# 6.1. about file systems

A file system is a way of organizing files on your partition. Besides file-based storage, file systems usually include **directories** and **access control**, and contain meta information about files like access times, modification times and file ownership.

The properties (length, character set, ...) of filenames are determined by the file system you choose. Directories are usually implemented as files, you will have to learn how this is implemented! Access control in file systems is tracked by user ownership (and group owner-and membership) in combination with one or more access control lists.

#### 6.1.1. man fs

The manual page about filesystems is accessed by typing man fs.

```
[root@rhel65 ~]# man fs
```

## 6.1.2. /proc/filesystems

The Linux kernel will inform you about currently loaded file system drivers in /proc/filesystems.

```
root@rhel53 ~# cat /proc/filesystems | grep -v nodev
ext2
iso9660
ext3
```

## 6.1.3. /etc/filesystems

The /etc/filesystems file contains a list of autodetected filesystems (in case the mount command is used without the -t option.

Help for this file is provided by **man mount**.

```
[root@rhel65 ~]# man mount
```

# 6.2. common file systems

#### 6.2.1. ext2 and ext3

Once the most common Linux file systems is the **ext2** (the second extended) file system. A disadvantage is that file system checks on ext2 can take a long time.

**ext2** was being replaced by **ext3** on most Linux machines. They are essentially the same, except for the **journaling** which is only present in ext3.

Journaling means that changes are first written to a journal on the disk. The journal is flushed regularly, writing the changes in the file system. Journaling keeps the file system in a consistent state, so you don't need a file system check after an unclean shutdown or power failure.

## 6.2.2. creating ext2 and ext3

You can create these file systems with the /sbin/mkfs or /sbin/mke2fs commands. Use mke2fs -j to create an ext3 file system.

You can convert an ext2 to ext3 with **tune2fs -j**. You can mount an ext3 file system as ext2, but then you lose the journaling. Do not forget to run **mkinitrd** if you are booting from this device.

#### 6.2.3. ext4

The newest incarnation of the ext file system is named **ext4** and is available in the Linux kernel since 2008. **ext4** supports larger files (up to 16 terabyte) and larger file systems than **ext3** (and many more features).

Development started by making **ext3** fully capable for 64-bit. When it turned out the changes were significant, the developers decided to name it **ext4**.

#### 6.2.4. xfs

Redhat Enterprise Linux 7 will have **XFS** as the default file system. This is a highly scalable high-performance file system.

**xfs** was created for **Irix** and for a couple of years it was also used in **FreeBSD**. It is supported by the Linux kernel, but rarely used in dsitributions outside of the Redhat/CentOS realm.

#### 6.2.5. vfat

The **vfat** file system exists in a couple of forms: **fat12** for floppy disks, **fat16** on **ms-dos**, and **fat32** for larger disks. The Linux **vfat** implementation supports all of these, but vfat lacks a lot of features like security and links. **fat** disks can be read by every operating system, and are used a lot for digital cameras, **usb** sticks and to exchange data between different OS'ses on a home user's computer.

#### 6.2.6. iso 9660

**iso 9660** is the standard format for cdroms. Chances are you will encounter this file system also on your hard disk in the form of images of cdroms (often with the .iso extension). The **iso 9660** standard limits filenames to the 8.3 format. The Unix world didn't like this, and thus added the **rock ridge** extensions, which allows for filenames up to 255 characters and Unix-style file-modes, ownership and symbolic links. Another extensions to **iso 9660** is **joliet**, which adds 64 unicode characters to the filename. The **el torito** standard extends **iso 9660** to be able to boot from CD-ROM's.

#### 6.2.7. udf

Most optical media today (including cd's and dvd's) use **udf**, the Universal Disk Format.

#### 6.2.8. swap

All things considered, swap is not a file system. But to use a partition as a **swap partition** it must be formatted and mounted as swap space.

## 6.2.9. gfs

Linux clusters often use a dedicated cluster filesystem like GFS, GFS2, ClusterFS, ...

### 6.2.10. and more...

You may encounter **reiserfs** on older Linux systems. Maybe you will see Sun's **zfs** or the open source **btrfs**. This last one requires a chapter on itself.

## 6.2.11. /proc/filesystems

The /proc/filesystems file displays a list of supported file systems. When you mount a file system without explicitly defining one, then mount will first try to probe /etc/filesystems and then probe /proc/filesystems for all the filesystems without the nodev label. If /etc/filesystems ends with a line containing only an asterisk (\*) then both files are probed.

```
paul@RHELv4u4:~$ cat /proc/filesystems
nodev sysfs
nodev rootfs
nodev bdev
nodev proc
nodev sockfs
nodev binfmt_misc
nodev
       usbfs
nodev usbdevfs
nodev futexfs
nodev tmpfs
nodev pipefs
nodev eventpollfs
nodev devpts
       ext2
nodev ramfs
nodev hugetlbfs
       iso9660
nodev
       relayfs
nodev
       mqueue
nodev
       selinuxfs
       ext3
nodev rpc_pipefs
nodev vmware-hgfs
nodev autofs
paul@RHELv4u4:~$
```

# 6.3. putting a file system on a partition

We now have a fresh partition. The system binaries to make file systems can be found with ls.

It is time for you to read the manual pages of **mkfs** and **mke2fs**. In the example below, you see the creation of an **ext2 file system** on /dev/sdb1. In real life, you might want to use options like -m0 and -j.

```
root@RHELv4u2:~# mke2fs /dev/sdb1
mke2fs 1.35 (28-Feb-2004)
Filesystem label=
OS type: Linux
Block size=1024 (log=0)
Fragment size=1024 (log=0)
28112 inodes, 112420 blocks
5621 blocks (5.00%) reserved for the super user
First data block=1
Maximum filesystem blocks=67371008
14 block groups
8192 blocks per group, 8192 fragments per group
2008 inodes per group
Superblock backups stored on blocks:
8193, 24577, 40961, 57345, 73729
Writing inode tables: done
Writing superblocks and filesystem accounting information: done
This filesystem will be automatically checked every 37 mounts or
180 days, whichever comes first. Use tune2fs -c or -i to override.
```

# 6.4. tuning a file system

You can use **tune2fs** to list and set file system settings. The first screenshot lists the reserved space for root (which is set at five percent).

This example changes this value to ten percent. You can use tune2fs while the file system is active, even if it is the root file system (as in this example).

# 6.5. checking a file system

The **fsck** command is a front end tool used to check a file system for errors.

```
[root@RHEL4b ~]# ls /sbin/*fsck*
/sbin/dosfsck /sbin/fsck /sbin/fsck.ext2 /sbin/fsck.msdos
/sbin/e2fsck /sbin/fsck.cramfs /sbin/fsck.ext3 /sbin/fsck.vfat
[root@RHEL4b ~]#
```

The last column in /etc/fstab is used to determine whether a file system should be checked at boot-up.

```
[paul@RHEL4b ~]$ grep ext /etc/fstab
/dev/VolGroup00/LogVol00 / ext3 defaults 1 1
LABEL=/boot /boot ext3 defaults 1 2
[paul@RHEL4b ~]$
```

Manually checking a mounted file system results in a warning from fsck.

```
[root@RHEL4b ~]# fsck /boot
fsck 1.35 (28-Feb-2004)
e2fsck 1.35 (28-Feb-2004)
/dev/sda1 is mounted.

WARNING!!! Running e2fsck on a mounted filesystem may cause
SEVERE filesystem damage.

Do you really want to continue (y/n)? no
check aborted.
```

But after unmounting fsck and **e2fsck** can be used to check an ext2 file system.

```
[root@RHEL4b ~]# fsck /boot
fsck 1.35 (28-Feb-2004)
e2fsck 1.35 (28-Feb-2004)
/boot: clean, 44/26104 files, 17598/104388 blocks
[root@RHEL4b ~]# fsck -p /boot
fsck 1.35 (28-Feb-2004)
/boot: clean, 44/26104 files, 17598/104388 blocks
[root@RHEL4b ~]# e2fsck -p /dev/sda1
/boot: clean, 44/26104 files, 17598/104388 blocks
```

# 6.6. practice: file systems

- 1. List the filesystems that are known by your system.
- 2. Create an ext2 filesystem on the 200MB partition.
- 3. Create an **ext3** filesystem on one of the 300MB logical drives.
- 4. Create an **ext4** on the 400MB partition.
- 5. Set the reserved space for root on the ext3 filesystem to 0 percent.
- 6. Verify your work with **fdisk** and **df**.
- 7. Perform a file system check on all the new file systems.

# 6.7. solution: file systems

1. List the filesystems that are known by your system.

man fs
cat /proc/filesystems
cat /etc/filesystems (not on all Linux distributions)

2. Create an **ext2** filesystem on the 200MB partition.

mke2fs /dev/sdc1 (replace sdc1 with the correct partition)

3. Create an **ext3** filesystem on one of the 300MB logical drives.

mke2fs -j /dev/sdb5 (replace sdb5 with the correct partition)

4. Create an **ext4** on the 400MB partition.

mkfs.ext4 /dev/sdb1 (replace sdb1 with the correct partition)

5. Set the reserved space for root on the ext3 filesystem to 0 percent.

tune2fs -m 0 /dev/sdb5

6. Verify your work with **fdisk** and **df**.

mkfs (mke2fs) makes no difference in the output of these commands

The big change is in the next topic: mounting

7. Perform a file system check on all the new file systems.

fsck /dev/sdb1
fsck /dev/sdc1
fsck /dev/sdb5

# Chapter 7. mounting

Once you've put a file system on a partition, you can **mount** it. Mounting a file system makes it available for use, usually as a directory. We say **mounting a file system** instead of mounting a partition because we will see later that we can also mount file systems that do not exists on partitions.

On all **Unix** systems, every file and every directory is part of one big file tree. To access a file, you need to know the full path starting from the root directory. When adding a **file system** to your computer, you need to make it available somewhere in the file tree. The directory where you make a file system available is called a **mount point**.

# 7.1. mounting local file systems

### 7.1.1. mkdir

This example shows how to create a new **mount point** with **mkdir**.

```
root@RHELv4u2:~# mkdir /home/project42
```

### 7.1.2. mount

When the **mount point** is created, and a **file system** is present on the partition, then **mount** can **mount** the **file system** on the **mount point directory**.

```
root@RHELv4u2:~# mount -t ext2 /dev/sdb1 /home/project42/
```

Once mounted, the new file system is accessible to users.

### 7.1.3. /etc/filesystems

Actually the explicit **-t ext2** option to set the file system is not always necessary. The **mount** command is able to automatically detect a lot of file systems.

When mounting a file system without specifying explicitly the file system, then **mount** will first probe /etc/filesystems. Mount will skip lines with the **nodev** directive.

```
paul@RHELv4u4:~$ cat /etc/filesystems
ext3
ext2
nodev proc
nodev devpts
iso9660
vfat
hfs
```

### 7.1.4. /proc/filesystems

When /etc/filesystems does not exist, or ends with a single \* on the last line, then mount will read /proc/filesystems.

```
[root@RHEL52 ~]# cat /proc/filesystems | grep -v ^nodev
ext2
iso9660
ext3
```

### 7.1.5. umount

You can **unmount** a mounted file system using the **umount** command.

```
root@pasha:~# umount /home/reet
```

# 7.2. displaying mounted file systems

To display all mounted file systems, issue the **mount** command. Or look at the files **/proc/mounts** and **/etc/mtab**.

### 7.2.1. mount

The simplest and most common way to view all mounts is by issuing the **mount** command without any arguments.

```
root@RHELv4u2:~# mount | grep /dev/sdb
/dev/sdb1 on /home/project42 type ext2 (rw)
```

### 7.2.2. /proc/mounts

The kernel provides the info in /proc/mounts in file form, but /proc/mounts does not exist as a file on any hard disk. Looking at /proc/mounts is looking at information that comes directly from the kernel.

```
root@RHELv4u2:~# cat /proc/mounts | grep /dev/sdb
/dev/sdb1 /home/project42 ext2 rw 0 0
```

### 7.2.3. /etc/mtab

The /etc/mtab file is not updated by the kernel, but is maintained by the mount command. Do not edit /etc/mtab manually.

```
root@RHELv4u2:~# cat /etc/mtab | grep /dev/sdb
/dev/sdb1 /home/project42 ext2 rw 0 0
```

### 7.2.4. df

A more user friendly way to look at mounted file systems is **df**. The **df** (**diskfree**) command has the added benefit of showing you the free space on each mounted disk. Like a lot of Linux commands, **df** supports the **-h** switch to make the output more **human readable**.

```
root@RHELv4u2:~# df
                               Used Available Use% Mounted on
Filesystem
                  1K-blocks
/dev/mapper/VolGroup00-LogVol00
11707972 6366996 4746240 58% /
                  101086 9300 86567 10% /boot
/dev/sda1
                  127988 0 127988 0% /dev/shm
/dev/sdb1
                   108865 1550 101694 2% /home/project42
root@RHELv4u2:~# df -h
Filesystem
                  Size Used Avail Use% Mounted on
/dev/mapper/VolGroup00-LogVol00
12G 6.1G 4.6G 58% /
/dev/sda1
                    99M 9.1M 85M 10% /boot
                        0 125M
none
                   125M
                                   0% /dev/shm
                   107M 1.6M 100M 2% /home/project42
/dev/sdb1
```

### 7.2.5. df -h

In the **df** -h example below you can see the size, free space, used gigabytes and percentage and mount point of a partition.

```
root@laika:~# df -h | egrep -e "(sdb2|File)"

Filesystem Size Used Avail Use% Mounted on /dev/sdb2 92G 83G 8.6G 91% /media/sdb2
```

### 7.2.6. du

The **du** command can summarize **disk usage** for files and directories. By using **du** on a mount point you effectively get the disk space used on a file system.

While **du** can go display each subdirectory recursively, the **-s** option will give you a total summary for the parent directory. This option is often used together with **-h**. This means **du -sh** on a mount point gives the total amount used by the file system in that partition.

```
root@debian6~# du -sh /boot /srv/wolf
6.2M /boot
1.1T /srv/wolf
```

### 7.3. from start to finish

Below is a screenshot that show a summary roadmap starting with detection of the hardware (/dev/sdb) up until mounting on /mnt.

```
[root@centos65 ~]# dmesg | grep '\[sdb\]'
sd 3:0:0:0: [sdb] 150994944 512-byte logical blocks: (77.3 GB/72.0 GiB)
sd 3:0:0:0: [sdb] Write Protect is off
sd 3:0:0:0: [sdb] Mode Sense: 00 3a 00 00
sd 3:0:0:0: [sdb] Write cache: enabled, read cache: enabled, doesn't support \
DPO or FUA
sd 3:0:0:0: [sdb] Attached SCSI disk
[root@centos65 ~]# parted /dev/sdb
(parted) mklabel msdos
(parted) mkpart primary ext4 1 77000
(parted) print
Model: ATA VBOX HARDDISK (scsi)
Disk /dev/sdb: 77.3GB
Sector size (logical/physical): 512B/512B
Partition Table: msdos
Number Start End
                       Size
                                         File system Flags
                                Type
       1049kB 77.0GB 77.0GB primary
(parted) quit
[root@centos65 ~]# mkfs.ext4 /dev/sdb1
mke2fs 1.41.12 (17-May-2010)
Filesystem label=
OS type: Linux
Block size=4096 (log=2)
Fragment size=4096 (log=2)
Stride=0 blocks, Stripe width=0 blocks
4702208 inodes, 18798592 blocks
939929 blocks (5.00%) reserved for the super user
First data block=0
Maximum filesystem blocks=4294967296
574 block groups
32768 blocks per group, 32768 fragments per group
8192 inodes per group
( output truncated )
[root@centos65 ~]# mount /dev/sdb1 /mnt
[root@centos65 ~]# mount | grep mnt
/dev/sdb1 on /mnt type ext4 (rw)
[root@centos65 ~]# df -h | grep mnt
/dev/sdb1
                       71G 180M 67G 1% /mnt
[root@centos65 \sim]# du -sh /mnt
       /mnt
[root@centos65 ~]# umount /mnt
```

# 7.4. permanent mounts

Until now, we performed all mounts manually. This works nice, until the next reboot. Luckily there is a way to tell your computer to automatically mount certain file systems during boot.

### 7.4.1. /etc/fstab

The file system table located in /etc/fstab contains a list of file systems, with an option to automtically mount each of them at boot time.

Below is a sample /etc/fstab file.

| root@RHELv4u2:~# cat /etc/fstab |          |          |                |     |  |  |  |  |  |  |
|---------------------------------|----------|----------|----------------|-----|--|--|--|--|--|--|
| /dev/VolGroup00/LogVol0         | ext3     | defaults | 1 1            |     |  |  |  |  |  |  |
| LABEL=/boot                     | /boot    | ext3     | defaults       | 1 2 |  |  |  |  |  |  |
| none                            | /dev/pts | devpts   | gid=5,mode=620 | 0 0 |  |  |  |  |  |  |
| none                            | /dev/shm | tmpfs    | defaults       | 0 0 |  |  |  |  |  |  |
| none                            | /proc    | proc     | defaults       | 0 0 |  |  |  |  |  |  |
| none                            | /sys     | sysfs    | defaults       | 0 0 |  |  |  |  |  |  |
| /dev/VolGroup00/LogVol0         | 1 swap   | swap     | defaults       | 0 0 |  |  |  |  |  |  |

By adding the following line, we can automate the mounting of a file system.

/dev/sdb1 /home/project42 ext2 defaults 0 0

### 7.4.2. mount /mountpoint

Adding an entry to /etc/fstab has the added advantage that you can simplify the mount command. The command in the screenshot below forces mount to look for the partition info in /etc/fstab.

root@rhel65:~# mount /home/project42

# 7.5. securing mounts

File systems can be secured with several **mount options**. Here are some examples.

### 7.5.1. ro

The **ro** option will mount a file system as read only, preventing anyone from writing.

```
root@rhel53 ~# mount -t ext2 -o ro /dev/hdb1 /home/project42
root@rhel53 ~# touch /home/project42/testwrite
touch: cannot touch `/home/project42/testwrite': Read-only file system
```

### 7.5.2. noexec

The **noexec** option will prevent the execution of binaries and scripts on the mounted file system.

```
root@rhel53 ~# mount -t ext2 -o noexec /dev/hdb1 /home/project42
root@rhel53 ~# cp /bin/cat /home/project42
root@rhel53 ~# /home/project42/cat /etc/hosts
-bash: /home/project42/cat: Permission denied
root@rhel53 ~# echo echo hello > /home/project42/helloscript
root@rhel53 ~# chmod +x /home/project42/helloscript
root@rhel53 ~# /home/project42/helloscript
-bash: /home/project42/helloscript: Permission denied
```

### 7.5.3. nosuid

The **nosuid** option will ignore **setuid** bit set binaries on the mounted file system.

Note that you can still set the **setuid** bit on files.

```
root@rhel53 ~# mount -o nosuid /dev/hdb1 /home/project42
root@rhel53 ~# cp /bin/sleep /home/project42/
root@rhel53 ~# chmod 4555 /home/project42/sleep
root@rhel53 ~# ls -l /home/project42/sleep
-r-sr-xr-x 1 root root 19564 Jun 24 17:57 /home/project42/sleep
```

But users cannot exploit the **setuid** feature.

```
root@rhel53 ~# su - paul
[paul@rhel53 ~]$ /home/project42/sleep 500 &
[1] 2876
[paul@rhel53 ~]$ ps -f 2876
UID PID PPID C STIME TTY STAT TIME CMD
paul 2876 2853 0 17:58 pts/0 S 0:00 /home/project42/sleep 500
[paul@rhel53 ~]$
```

### 7.5.4. noacl

To prevent cluttering permissions with acl's, use the **noacl** option.

```
root@rhel53 ~# mount -o noacl /dev/hdb1 /home/project42
```

More **mount options** can be found in the manual page of **mount**.

# 7.6. mounting remote file systems

### 7.6.1. smb/cifs

The Samba team (samba.org) has a Unix/Linux service that is compatible with the SMB/CIFS protocol. This protocol is mainly used by networked Microsoft Windows computers.

Connecting to a Samba server (or to a Microsoft computer) is also done with the mount command.

This example shows how to connect to the **10.0.0.42** server, to a share named **data2**.

```
[root@centos65 ~]# mount -t cifs -o user=paul //10.0.0.42/data2 /home/data2
Password:
[root@centos65 ~]# mount | grep cifs
//10.0.0.42/data2 on /home/data2 type cifs (rw)
```

The above requires **yum install cifs-client**.

### 7.6.2. nfs

Unix servers often use **nfs** (aka the network file system) to share directories over the network. Setting up an nfs server is discussed later. Connecting as a client to an nfs server is done with **mount**, and is very similar to connecting to local storage.

This command shows how to connect to the nfs server named **server42**, which is sharing the directory /**srv/data**. The **mount point** at the end of the command (/**home/data**) must already exist.

```
[root@centos65 ~]# mount -t nfs server42:/srv/data /home/data
[root@centos65 ~]#
```

If this server42 has ip-address 10.0.0.42 then you can also write:

```
[root@centos65 ~]# mount -t nfs 10.0.0.42:/srv/data /home/data
[root@centos65 ~]# mount | grep data
10.0.0.42:/srv/data on /home/data type nfs (rw,vers=4,addr=10.0.0.42,clienta\ddr=10.0.0.33)
```

### 7.6.3. nfs specific mount options

```
bg If mount fails, retry in background.
fg (default)If mount fails, retry in foreground.
soft Stop trying to mount after X attempts.
hard (default)Continue trying to mount.
```

The **soft+bg** options combined guarantee the fastest client boot if there are NFS problems.

```
retrans=X Try X times to connect (over udp).
tcp Force tcp (default and supported)
udp Force udp (unsupported)
```

# 7.7. practice: mounting file systems

- 1. Mount the small 200MB partition on /home/project22.
- 2. Mount the big 400MB primary partition on /mnt, the copy some files to it (everything in / etc). Then umount, and mount the file system as read only on /srv/nfs/salesnumbers. Where are the files you copied ?
- 3. Verify your work with **fdisk**, **df** and **mount**. Also look in /etc/mtab and /proc/mounts.
- 4. Make both mounts permanent, test that it works.
- 5. What happens when you mount a file system on a directory that contains some files?
- 6. What happens when you mount two file systems on the same mount point?
- 7. (optional) Describe the difference between these commands: find, locate, updatedb, makewhatis, whereis, apropos, which and type.
- 8. (optional) Perform a file system check on the partition mounted at /srv/nfs/salesnumbers.

# 7.8. solution: mounting file systems

1. Mount the small 200MB partition on /home/project22.

```
mkdir /home/project22
mount /dev/sdc1 /home/project22
```

2. Mount the big 400MB primary partition on /mnt, the copy some files to it (everything in / etc). Then umount, and mount the file system as read only on /srv/nfs/salesnumbers. Where are the files you copied ?

```
mount /dev/sdb1 /mnt
cp -r /etc /mnt
ls -l /mnt

umount /mnt
ls -l /mnt

mkdir -p /srv/nfs/salesnumbers
mount /dev/sdb1 /srv/nfs/salesnumbers

You see the files in /srv/nfs/salenumbers now...

But physically they are on ext3 on partition /dev/sdb1
```

3. Verify your work with **fdisk**, **df** and **mount**. Also look in /etc/mtab and /proc/mounts.

```
fdisk -1
df -h
mount

All three the above commands should show your mounted partitions.

grep project22 /etc/mtab
grep project22 /proc/mounts
```

4. Make both mounts permanent, test that it works.

```
add the following lines to /etc/fstab

/dev/sdc1 /home/project22 auto defaults 0 0

/dev/sdb1 /srv/nfs/salesnumbers auto defaults 0 0
```

5. What happens when you mount a file system on a directory that contains some files?

```
The files are hidden until umount.
```

6. What happens when you mount two file systems on the same mount point?

```
Only the last mounted fs is visible.
```

7. (optional) Describe the difference between these commands: find, locate, updatedb, makewhatis, whereis, apropos, which and type.

```
man find
man locate
...
```

8. (optional) Perform a file system check on the partition mounted at /srv/nfs/salesnumbers.

```
# umount /srv/nfs/salesnumbers (optional but recommended)
# fsck /dev/sdb1
```

# **Chapter 8. troubleshooting tools**

This chapter introduces some tools that go beyond **df -h** and **du -sh**. Tools that will enable you to troubleshoot a variety of issues with **file systems** and storage.

### 8.1. Isof

List open files with **lsof**.

When invoked without options, **lsof** will list all open files. You can see the command (init in this case), its PID (1) and the user (root) has openend the root directory and **/sbin/init**. The FD (file descriptor) columns shows that / is both the root directory (rtd) and current working directory (cwd) for the /sbin/init command. The FD column displays **rtd** for root directory, **cwd** for current directory and **txt** for text (both including data and code).

```
root@debian7:~# lsof | head -4
COMMAND PID TID USER FD
                                  DEVICE SIZE/OFF
                                                     NODE NAME
                           TYPE
init 1
                          DIR
                                 254,0 4096
                                                      2 /
               root cwd
                                                       2 /
               root rtd
                            DIR
                                   254,0
                                            4096
init
        1
                                   254,0
                                           36992
               root txt
                            REG
                                                   130856 /sbin/init
```

Other options in the FD column besides w for writing, are r for reading and u for both reading and writing. You can look at open files for a process id by typing **lsof -p PID**. For **init** this would look like this:

```
lsof -p 1
```

The screenshot below shows basic use of **lsof** to prove that **vi** keeps a **.swp** file open (even when stopped in background) on our freshly mounted file system.

Here we see that **rsyslog** has a couple of log files open for writing (the FD column).

```
root@debian7:~# lsof /var/log/*

COMMAND PID USER FD TYPE DEVICE SIZE/OFF NODE NAME

rsyslogd 2013 root 1w REG 254,0 454297 1308187 /var/log/syslog

rsyslogd 2013 root 2w REG 254,0 419328 1308189 /var/log/kern.log

rsyslogd 2013 root 5w REG 254,0 116725 1308200 /var/log/debug

rsyslogd 2013 root 6w REG 254,0 309847 1308201 /var/log/messages

rsyslogd 2013 root 7w REG 254,0 17591 1308188 /var/log/daemon.log

rsyslogd 2013 root 8w REG 254,0 101768 1308186 /var/log/auth.log
```

You can specify a specific user with **lsof -u**. This example shows the current working directory for a couple of command line programs.

```
[paul@RHEL65 ~]$ lsof -u paul | grep home
bash 3302 paul cwd DIR 253,0 4096 788024 /home/paul
lsof 3329 paul cwd DIR 253,0 4096 788024 /home/paul
grep 3330 paul cwd DIR 253,0 4096 788024 /home/paul
lsof 3331 paul cwd DIR 253,0 4096 788024 /home/paul
```

The -u switch of **lsof** also supports the ^ character meaning 'not'. To see all open files, but not those open by root:

```
lsof -u^root
```

### **8.2.** fuser

The **fuser** command will display the 'user' of a file system.

In this example we still have a vi process in background and we use **fuser** to find the process id of the process using this file system.

```
[root@RHEL65 ~]# jobs
[1]+ Stopped vi /srv/project33/busyfile.txt
[root@RHEL65 ~]# fuser -m /srv/project33/
/srv/project33/: 3243
```

Adding the **-u** switch will also display the user name.

```
[root@RHEL65 ~]# fuser -m -u /srv/project33/
/srv/project33/: 3243(root)
```

You can quickly kill all processes that are using a specific file (or directory) with the -k switch.

```
[root@RHEL65 ~]# fuser -m -k -u /srv/project33/
/srv/project33/: 3243(root)
[1]+ Killed vi /srv/project33/busyfile.txt
[root@RHEL65 ~]# fuser -m -u /srv/project33/
[root@RHEL65 ~]#
```

This example shows all processes that are using the current directory (bash and vi in this case).

This example shows that the vi command actually accesses /usr/bin/vim.basic as an executable file.

```
root@debian7:~/test42# fuser -v $(which vi)

USER PID ACCESS COMMAND
/usr/bin/vim.basic: root 3113 ...e. vi
```

The last example shows how to find the process that is accessing a specific file.

### 8.3. chroot

The **chroot** command creates a shell with an alternate root directory. It effectively hides anything outside of this directory.

In the example below we assume that our system refuses to start (maybe because there is a problem with /etc/fstab or the mounting of the root file system).

We start a live system (booted from cd/dvd/usb) to troubleshoot our server. The live system will not use our main hard disk as root device

We create some test file on the current rootfs.

First we mount the root file system from the disk (which is on **lvm** so we use **/dev/mapper** instead of **/dev/sda5**).

```
root@livecd:~# mount /dev/mapper/packer--debian--7-root /mnt
```

We are now ready to **chroot** into the rootfs on disk.

```
root@livecd:~# cd /mnt
root@livecd:/mnt# chroot /mnt
root@livecd:/# ls /
bin dev initrd.img lost+found opt run srv usr vmlinuz
boot etc lib media proc sbin sys vagrant
data home lib64 mnt root selinux tmp var
```

Our test files (file42 and dir42) are not visible because they are out of the **chrooted** environment.

Note that the **hostname** of the chrooted environment is identical to the existing hostname.

To exit the **chrooted** file system:

```
root@livecd:/# exit
exit
root@livecd:~# ls /
bin dir42 home    lib64 opt run    srv usr
boot etc    initrd.img media proc sbin    sys var
dev file42 lib    mnt    root selinux tmp vmlinuz
```

# 8.4. iostat

**iostat** reports IO statitics every given period of time. It also includes a small cpu usage summary. This example shows **iostat** running every ten seconds with /dev/sdc and /dev/sdc showing a lot of write activity.

| [root@RHE<br>Linux 2.6 |         |        | 10 3<br>6_64 (RHEL65) | 06/16/2014 | _x86_64_ | (1 CPU)  |  |
|------------------------|---------|--------|-----------------------|------------|----------|----------|--|
|                        |         |        |                       |            |          |          |  |
| avg-cpu:               | %user   | %nice  | %system %iowa         | ait %steal | %idle    |          |  |
|                        | 5.81    | 0.00   | 3.15 0.               | .18 0.00   | 90.85    |          |  |
| Device:                |         | tps    | Blk_read/s            | Blk_wrtn/s | Blk_read | Blk_wrtn |  |
| sda                    |         | 42.08  | 1204.10               | 1634.88    | 1743708  | 2367530  |  |
| sdb                    |         | 1.20   | 7.69                  | 45.78      | 11134    | 66292    |  |
| sdc                    |         | 0.92   | 5.30                  | 45.82      | 7672     | 66348    |  |
| sdd                    |         | 0.91   | 5.29                  | 45.78      | 7656     | 66292    |  |
| sde                    |         | 1.04   | 6.28                  | 91.49      | 9100     | 132496   |  |
| sdf                    |         | 0.70   | 3.40                  | 91.46      | 4918     | 132440   |  |
| sdg                    |         | 0.69   | 3.40                  | 91.46      | 4918     | 132440   |  |
| dm-0                   |         | 191.68 | 1045.78               | 1362.30    | 1514434  | 1972808  |  |
| dm-1                   |         | 49.26  | 150.54                | 243.55     | 218000   | 352696   |  |
| avg-cpu:               | %user   | %nice  | %system %iowa         | ait %steal | %idle    |          |  |
|                        | 56.11   | 0.00   | 16.83 0               | .10 0.00   | 26.95    |          |  |
| Device:                |         | tps    | Blk_read/s            | Blk_wrtn/s | Blk_read | Blk_wrtn |  |
| sda                    |         | 257.01 | 10185.97              | 76.95      | 101656   | 768      |  |
| sdb                    |         | 0.00   | 0.00                  | 0.00       | 0        | 0        |  |
| sdc                    |         | 3.81   | 1.60                  | 2953.11    | 16       | 29472    |  |
| sdd                    |         | 0.00   | 0.00                  | 0.00       | 0        | 0        |  |
| sde                    |         | 4.91   | 1.60                  | 4813.63    | 16       | 48040    |  |
| sdf                    |         | 0.00   | 0.00                  | 0.00       | 0        | 0        |  |
| sdg                    |         | 0.00   | 0.00                  | 0.00       | 0        | 0        |  |
| dm-0                   |         | 283.77 | 10185.97              | 76.95      | 101656   | 768      |  |
| dm-1                   |         | 0.00   | 0.00                  | 0.00       | 0        | 0        |  |
| avg-cpu:               | %user   | %nice  | %system %iowa         | ait %steal | %idle    |          |  |
|                        | 67.65   | 0.00   | 31.11 0               | .11 0.00   | 1.13     |          |  |
| Device:                |         | tps    | Blk_read/s            | Blk_wrtn/s | Blk_read | Blk_wrtn |  |
| sda                    |         | 466.86 | 26961.09              | 178.28     | 238336   | 1576     |  |
| sdb                    |         | 0.00   | 0.00                  | 0.00       | 0        | 0        |  |
| sdc                    |         | 31.45  | 0.90                  | 24997.29   | 8        | 220976   |  |
| sdd                    |         | 0.00   | 0.00                  | 0.00       | 0        | 0        |  |
| sde                    |         | 0.34   | 0.00                  | 5.43       | 0        | 48       |  |
| sdf                    |         | 0.00   | 0.00                  | 0.00       | 0        | 0        |  |
| sdg                    |         | 0.00   | 0.00                  | 0.00       | 0        | 0        |  |
| dm-0                   |         | 503.62 | 26938.46              | 178.28     | 238136   | 1576     |  |
| dm-1                   |         | 2.83   | 22.62                 | 0.00       | 200      | 0        |  |
| [root@RHE              | L65 ~]: | #      |                       |            |          |          |  |
|                        |         |        |                       |            |          |          |  |

Other options are to specify the disks you want to monitor (every 5 seconds here):

iostat sdd sde sdf 5

Or to show statistics per partition:

iostat -p sde -p sdf 5

# **8.5.** iotop

iotop works like the top command but orders processes by input/output instead of by CPU.

By default **iotop** will show all processes. This example uses **iotop -o** to only display processes with actual I/O.

```
[root@RHEL65 ~]# iotop -o

Total DISK READ: 8.63 M/s | Total DISK WRITE: 0.00 B/s

TID PRIO USER DISK READ DISK WRITE SWAPIN IO> COMMAND

15000 be/4 root 2.43 M/s 0.00 B/s 0.00 % 14.60 % tar cjf /srv/di...

25000 be/4 root 6.20 M/s 0.00 B/s 0.00 % 6.15 % tar czf /srv/di...

24988 be/4 root 0.00 B/s 7.21 M/s 0.00 % 0.00 % gzip

25003 be/4 root 0.00 B/s 1591.19 K/s 0.00 % 0.00 % gzip

25004 be/4 root 0.00 B/s 193.51 K/s 0.00 % 0.00 % bzip2
```

Use the **-b** switch to create a log of **iotop** output (instead of the default interactive view).

```
[root@RHEL65 ~]# iotop -bod 10

Total DISK READ: 12.82 M/s | Total DISK WRITE: 5.69 M/s

TID PRIO USER DISK READ DISK WRITE SWAPIN IO COMMAND

25153 be/4 root 2.05 M/s 0.00 B/s 0.00 % 7.81 % tar cjf /srv/di...

25152 be/4 root 10.77 M/s 0.00 B/s 0.00 % 2.94 % tar czf /srv/di...

25144 be/4 root 408.54 B/s 0.00 B/s 0.00 % 0.05 % python /usr/sbi...

12516 be/3 root 0.00 B/s 1491.33 K/s 0.00 % 0.04 % [jbd2/sdc1-8]

12522 be/3 root 0.00 B/s 45.48 K/s 0.00 % 0.01 % [jbd2/sde1-8]

25158 be/4 root 0.00 B/s 0.00 B/s 0.00 % 0.00 % [flush-8:64]

25155 be/4 root 0.00 B/s 493.12 K/s 0.00 % 0.00 % gzip

25156 be/4 root 0.00 B/s 528.63 K/s 0.00 % 0.00 % [flush-8:32]
```

This is an example of **iotop** to track disk I/O every ten seconds for one user named **vagrant** (and only one process of this user, but this can be omitted). The **-a** switch accumulates I/O over time.

```
[root@RHEL65 ~]# iotop -q -a -u vagrant -b -p 5216 -d 10 -n 10
Total DISK READ: 0.00 B/s | Total DISK WRITE: 0.00 B/s
 TID PRIO USER DISK READ DISK WRITE SWAPIN
                                                         COMMAND
5216 be/4 vagrant
                    0.00 B
                              0.00 B 0.00 % 0.00 % gzip
Total DISK READ: 818.22 B/s | Total DISK WRITE: 20.78 M/s
 5216 be/4 vagrant 0.00 B 213.89 M 0.00 % 0.00 % gzip
Total DISK READ: 2045.95 B/s | Total DISK WRITE: 23.16 M/s
5216 be/4 vagrant 0.00 B 430.70 M 0.00 % 0.00 % gzip
Total DISK READ: 1227.50 B/s | Total DISK WRITE: 22.37 M/s
5216 be/4 vagrant 0.00 B 642.02 M 0.00 % 0.00 % gzip
Total DISK READ: 818.35 B/s | Total DISK WRITE: 16.44 M/s
5216 be/4 vagrant 0.00 B 834.09 M 0.00 % 0.00 % gzip
Total DISK READ: 6.95 M/s | Total DISK WRITE: 8.74 M/s
5216 be/4 vagrant 0.00 B 920.69 M 0.00 % 0.00 % gzip
Total DISK READ: 21.71 M/s | Total DISK WRITE: 11.99 M/s
```

### 8.6. vmstat

While **vmstat** is mainly a memory monitoring tool, it is worth mentioning here for its reporting on summary I/O data for block devices and swap space.

This example shows some disk activity (underneath the ----io---- column), without swapping.

You can benefit from **vmstat**'s ability to display memory in kilobytes, megabytes or even kibibytes and mebibytes using -S (followed by k K m or M).

| [root@RHEL65 ~]# vmstat -SM 5 10 |     |     |        |      |        |       |    |           |       |      |      |      |    |    |     |      |    |
|----------------------------------|-----|-----|--------|------|--------|-------|----|-----------|-------|------|------|------|----|----|-----|------|----|
| procsmemory                      |     |     |        |      | swapio |       |    | systemcpu |       |      |      |      |    |    |     |      |    |
|                                  | r   | b   | swpd   | free | buff   | cache | si | so        | bi    | bo   | in   | CS   | us | sy | id  | wa s | зt |
|                                  | 0   | 0   | 5      | 14   | 11     | 334   | 0  | 0         | 259   | 255  | 79   | 107  | 2  | 1  | 97  | 0    | 0  |
|                                  | 0   | 0   | 5      | 14   | 11     | 334   | 0  | 0         | 0     | 2    | 21   | 18   | 0  | 0  | 100 | 0    | 0  |
|                                  | 0   | 0   | 5      | 15   | 11     | 334   | 0  | 0         | 6     | 0    | 35   | 31   | 0  | 0  | 100 | 0    | 0  |
|                                  | 2   | 0   | 5      | 6    | 11     | 336   | 0  | 0         | 17100 | 7814 | 1378 | 2945 | 48 | 21 | 31  | 0    | 0  |
|                                  | 2   | 0   | 5      | 6    | 11     | 336   | 0  | 0         | 13193 | 14   | 1662 | 3343 | 78 | 22 | 0   | 0    | 0  |
|                                  | 2   | 0   | 5      | 13   | 11     | 330   | 0  | 0         | 11656 | 9781 | 1419 | 2642 | 82 | 18 | 0   | 0    | 0  |
|                                  | 2   | 0   | 5      | 9    | 11     | 334   | 0  | 0         | 10705 | 2716 | 1504 | 2657 | 81 | 19 | 0   | 0    | 0  |
|                                  | 1   | 0   | 5      | 14   | 11     | 336   | 0  | 0         | 6467  | 3788 | 765  | 1384 | 43 | 9  | 48  | 0    | 0  |
|                                  | 0   | 0   | 5      | 14   | 11     | 336   | 0  | 0         | 0     | 13   | 28   | 24   | 0  | 0  | 100 | 0    | 0  |
|                                  | 0   | 0   | 5      | 14   | 11     | 336   | 0  | 0         | 0     | 0    | 20   | 15   | 0  | 0  | 100 | 0    | 0  |
|                                  | [ro | ot@ | RHEL65 | ~]#  |        |       |    |           |       |      |      |      |    |    |     |      |    |

vmstat is also discussed in other chapters.

# 8.7. practice: troubleshooting tools

- 0. It is imperative that you practice these tools **before** trouble arises. It will help you get familiar with the tools and allow you to create a base line of normal behaviour for your systems.
- 1. Read the theory on **fuser** and explore its man page. Use this command to find files that you open yourself.
- 2. Read the theory on **lsof** and explore its man page. Use this command to find files that you open yourself.
- 3. Boot a live image on an existing computer (virtual or real) and **chroot** into to it.
- 4. Start one or more disk intensive jobs and monitor them with **iostat** and **iotop** (compare to **vmstat**).

# 8.8. solution: troubleshooting tools

- 0. It is imperative that you practice these tools **before** trouble arises. It will help you get familiar with the tools and allow you to create a base line of normal behaviour for your systems.
- 1. Read the theory on **fuser** and explore its man page. Use this command to find files that you open yourself.
- 2. Read the theory on **lsof** and explore its man page. Use this command to find files that you open yourself.
- 3. Boot a live image on an existing computer (virtual or real) and **chroot** into to it.
- 4. Start one or more disk intensive jobs and monitor them with **iostat** and **iotop** (compare to **vmstat**).

# Chapter 9. introduction to uuid's

A **uuid** or **universally unique identifier** is used to uniquely identify objects. This 128bit standard allows anyone to create a unique **uuid**.

This chapter takes a brief look at **uuid's**.

# 9.1. about unique objects

Older versions of Linux have a **vol\_id** utility to display the **uuid** of a file system.

```
root@debian5:~# vol_id --uuid /dev/sda1
193c3c9b-2c40-9290-8b71-4264ee4d4c82
```

Red Hat Enterprise Linux 5 puts **vol\_id** in **/lib/udev/vol\_id**, which is not in the \$PATH. The syntax is also a bit different from Debian/Ubuntu/Mint.

```
root@rhel53 ~# /lib/udev/vol_id -u /dev/hda1
48a6a316-9ca9-4214-b5c6-e7b33a77e860
```

This utility is not available in standard installations of RHEL6 or Debian6.

### 9.2. tune2fs

Use **tune2fs** to find the **uuid** of a file system.

### 9.3. uuid

There is more information in the manual of **uuid**, a tool that can generate uuid's.

```
[root@rhel65 ~]# yum install uuid
(output truncated)
[root@rhel65 ~]# man uuid
```

### 9.4. uuid in /etc/fstab

You can use the **uuid** to make sure that a volume is universally uniquely identified in /etc/fstab. The device name can change depending on the disk devices that are present at boot time, but a **uuid** never changes.

First we use **tune2fs** to find the **uuid**.

```
[root@RHEL5 ~]# tune2fs -l /dev/sdc1 | grep UUID
Filesystem UUID: 7626d73a-2bb6-4937-90ca-e451025d64e8
```

Then we check that it is properly added to /etc/fstab, the uuid replaces the variable devicename /dev/sdc1.

```
[root@RHEL5 ~]# grep UUID /etc/fstab
UUID=7626d73a-2bb6-4937-90ca-e451025d64e8 /home/pro42 ext3 defaults 0 0
```

Now we can mount the volume using the mount point defined in /etc/fstab.

The real test now, is to remove /dev/sdb from the system, reboot the machine and see what happens. After the reboot, the disk previously known as /dev/sdc is now /dev/sdb.

```
[root@RHEL5 ~]# tune2fs -l /dev/sdb1 | grep UUID
Filesystem UUID: 7626d73a-2bb6-4937-90ca-e451025d64e8
```

And thanks to the **uuid** in **/etc/fstab**, the mountpoint is mounted on the same disk as before.

## 9.5. uuid as a boot device

Recent Linux distributions (Debian, Ubuntu, ...) use **grub** with a **uuid** to identify the root file system.

This example shows how a **root=/dev/sda1** is replaced with a **uuid**.

```
title Ubuntu 9.10, kernel 2.6.31-19-generic
uuid f001ba5d-9077-422a-9634-8d23d57e782a
kernel /boot/vmlinuz-2.6.31-19-generic \
root=UUID=f001ba5d-9077-422a-9634-8d23d57e782a ro quiet splash
initrd /boot/initrd.img-2.6.31-19-generic
```

The screenshot above contains only four lines. The line starting with **root**= is the continuation of the **kernel** line.

RHEL and CentOS boot from LVM after a default install.

# 9.6. practice: uuid and filesystems

- 1. Find the **uuid** of one of your **ext3** partitions with **tune2fs** ( and **vol\_id** if you are on RHEL5).
- 2. Use this **uuid** in /etc/fstab and test that it works with a simple mount.
- 3. (optional) Test it also by removing a disk (so the device name is changed). You can edit settings in vmware/Virtualbox to remove a hard disk.
- 4. Display the **root**= directive in **/boot/grub/menu.lst**. (We see later in the course how to maintain this file.)
- 5. (optional on ubuntu) Replace the /dev/xxx in /boot/grub/menu.lst with a uuid (use an extra stanza for this). Test that it works.

# 9.7. solution: uuid and filesystems

1. Find the **uuid** of one of your **ext3** partitions with **tune2fs** ( and **vol\_id** if you are on RHEL5).

2. Use this **uuid** in /**etc/fstab** and test that it works with a simple **mount**.

```
tail -1 /etc/fstab
UUID=60926898-2c78-49b4-a71d-c1d6310c87cc /home/pro42 ext3 defaults 0 0
```

- 3. (optional) Test it also by removing a disk (so the device name is changed). You can edit settings in vmware/Virtualbox to remove a hard disk.
- 4. Display the **root**= directive in **/boot/grub/menu.lst**. (We see later in the course how to maintain this file.)

```
paul@deb503:~$ grep ^[^#] /boot/grub/menu.lst | grep root=
kernel /boot/vmlinuz-2.6.26-2-686 root=/dev/hda1 ro selinux=1 quiet
kernel /boot/vmlinuz-2.6.26-2-686 root=/dev/hda1 ro selinux=1 single
```

5. (optional on ubuntu) Replace the /dev/xxx in /boot/grub/menu.lst with a uuid (use an extra stanza for this). Test that it works.

# Chapter 10. introduction to raid

### 10.1. hardware or software

Redundant Array of Independent (originally Inexpensive) Disks or **RAID** can be set up using hardware or software. Hardware RAID is more expensive, but offers better performance. Software RAID is cheaper and easier to manage, but it uses your CPU and your memory.

Where ten years ago nobody was arguing about the best choice being hardware RAID, this has changed since technologies like mdadm, lvm and even zfs focus more on managability. The workload on the cpu for software RAID used to be high, but cpu's have gotten a lot faster.

### 10.2. raid levels

### 10.2.1. raid 0

raid 0 uses two or more disks, and is often called **striping** (or stripe set, or striped volume). Data is divided in **chunks**, those chunks are evenly spread across every disk in the array. The main advantage of **raid** 0 is that you can create **larger drives**. **raid** 0 is the only **raid** without redundancy.

### 10.2.2. jbod

**jbod** uses two or more disks, and is often called **concatenating** (spanning, spanned set, or spanned volume). Data is written to the first disk, until it is full. Then data is written to the second disk... The main advantage of **jbod** (Just a Bunch of Disks) is that you can create **larger drives**. JBOD offers no redundancy.

### 10.2.3. raid 1

**raid 1** uses exactly two disks, and is often called **mirroring** (or mirror set, or mirrored volume). All data written to the array is written on each disk. The main advantage of raid 1 is **redundancy**. The main disadvantage is that you lose at least half of your available disk space (in other words, you at least double the cost).

### 10.2.4. raid 2, 3 and 4?

raid 2 uses bit level striping, raid 3 byte level, and raid 4 is the same as raid 5, but with a dedicated parity disk. This is actually slower than raid 5, because every write would have to write parity to this one (bottleneck) disk. It is unlikely that you will ever see these raid levels in production.

### 10.2.5. raid 5

**raid 5** uses **three** or more disks, each divided into chunks. Every time chunks are written to the array, one of the disks will receive a **parity** chunk. Unlike **raid 4**, the parity chunk will alternate between all disks. The main advantage of this is that **raid 5** will allow for full data recovery in case of **one** hard disk failure.

### 10.2.6. raid 6

raid 6 is very similar to raid 5, but uses two parity chunks. raid 6 protects against two hard disk failures. Oracle Solaris zfs calls this raidz2 (and also had raidz3 with triple parity).

### 10.2.7. raid 0+1

raid 0+1 is a mirror(1) of stripes(0). This means you first create two raid 0 stripe sets, and then you set them up as a mirror set. For example, when you have six 100GB disks, then the stripe sets are each 300GB. Combined in a mirror, this makes 300GB total. raid 0+1 will survive one disk failure. It will only survive the second disk failure if this disk is in the same stripe set as the previous failed disk.

### 10.2.8. raid 1+0

raid 1+0 is a stripe(0) of mirrors(1). For example, when you have six 100GB disks, then you first create three mirrors of 100GB each. You then stripe them together into a 300GB drive. In this example, as long as not all disks in the same mirror fail, it can survive up to three hard disk failures.

### 10.2.9. raid 50

raid 5+0 is a stripe(0) of raid 5 arrays. Suppose you have nine disks of 100GB, then you can create three raid 5 arrays of 200GB each. You can then combine them into one large stripe set.

### 10.2.10. many others

There are many other nested **raid** combinations, like **raid** 30, 51, 60, 100, 150, ...

# 10.3. building a software raid5 array

### 10.3.1. do we have three disks?

First, you have to attach some disks to your computer. In this scenario, three brand new disks of eight gigabyte each are added. Check with **fdisk -1** that they are connected.

```
[root@rhel6c ~]# fdisk -1 2> /dev/null | grep MB
Disk /dev/sdb: 8589 MB, 8589934592 bytes
Disk /dev/sdc: 8589 MB, 8589934592 bytes
Disk /dev/sdd: 8589 MB, 8589934592 bytes
```

### 10.3.2. fd partition type

The next step is to create a partition of type **fd** on every disk. The **fd** type is to set the partition as **Linux RAID autodetect**. See this (truncated) screenshot:

```
[root@rhel6c ~]# fdisk /dev/sdd
Command (m for help): n
Command action
  e extended
  p primary partition (1-4)
g
Partition number (1-4): 1
First cylinder (1-1044, default 1):
Using default value 1
Last cylinder, +cylinders or +size\{K,M,G\} (1-1044, default 1044):
Using default value 1044
Command (m for help): t
Selected partition 1
Hex code (type L to list codes): fd
Changed system type of partition 1 to fd (Linux raid autodetect)
Command (m for help): w
The partition table has been altered!
Calling ioctl() to re-read partition table.
Syncing disks.
```

### 10.3.3. verify all three partitions

Now all three disks are ready for **raid 5**, so we have to tell the system what to do with these disks.

### 10.3.4. create the raid5

The next step used to be *create the raid table in /etc/raidtab*. Nowadays, you can just issue the command **mdadm** with the correct parameters.

The command below is split on two lines to fit this print, but you should type it on one line, without the backslash (\).

```
[root@rhel6c ~]# mdadm --create /dev/md0 --chunk=64 --level=5 --raid-\
devices=3 /dev/sdb1 /dev/sdc1 /dev/sdd1
mdadm: Defaulting to version 1.2 metadata
mdadm: array /dev/md0 started.
```

Below a partial screenshot how fdisk -l sees the **raid 5**.

```
[root@rhel6c ~]# fdisk -l /dev/md0

Disk /dev/md0: 17.2 GB, 17172135936 bytes
2 heads, 4 sectors/track, 4192416 cylinders
Units = cylinders of 8 * 512 = 4096 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 65536 bytes / 131072 bytes
Disk identifier: 0x00000000
Disk /dev/md0 doesn't contain a valid partition table
```

We could use this software **raid 5** array in the next topic: **lvm**.

### 10.3.5. /proc/mdstat

The status of the raid devices can be seen in /proc/mdstat. This example shows a raid 5 in the process of rebuilding.

This example shows an active software **raid 5**.

```
[root@rhel6c ~]# cat /proc/mdstat
Personalities : [raid6] [raid5] [raid4]
md0 : active raid5 sdd1[3] sdc1[1] sdb1[0]
    16769664 blocks super 1.2 level 5, 64k chunk, algorithm 2 [3/3] [UUU]
```

### 10.3.6. mdadm --detail

Use **mdadm** --detail to get information on a raid device.

```
[root@rhel6c ~]# mdadm --detail /dev/md0
/dev/md0:
       Version: 1.2
 Creation Time : Sun Jul 17 13:48:41 2011
    Raid Level : raid5
    Array Size : 16769664 (15.99 GiB 17.17 GB)
 Used Dev Size : 8384832 (8.00 GiB 8.59 GB)
  Raid Devices : 3
 Total Devices : 3
   Persistence : Superblock is persistent
   Update Time : Sun Jul 17 13:49:43 2011
         State : clean
Active Devices : 3
Working Devices : 3
Failed Devices : 0
 Spare Devices : 0
        Layout : left-symmetric
    Chunk Size : 64K
          Name : rhel6c:0 (local to host rhel6c)
          UUID : c10fd9c3:08f9a25f:be913027:999c8e1f
        Events: 18
   Number
            Major
                    Minor RaidDevice State
                                                    /dev/sdb1
              8
                    17
                           0 active sync
      Ω
              8
                      33
                                                    /dev/sdc1
      1
                               1
                                      active sync
                                  active sync
                                                    /dev/sdd1
```

### 10.3.7. removing a software raid

The software raid is visible in /proc/mdstat when active. To remove the raid completely so you can use the disks for other purposes, you stop (de-activate) it with mdadm.

```
[root@rhel6c ~]# mdadm --stop /dev/md0
mdadm: stopped /dev/md0
```

The disks can now be repartitioned.

### 10.3.8. further reading

Take a look at the man page of **mdadm** for more information. Below an example command to add a new partition while removing a faulty one.

```
mdadm /dev/md0 --add /dev/sdd1 --fail /dev/sdb1 --remove /dev/sdb1
```

# 10.4. practice: raid

- 1. Add three virtual disks of 1GB each to a virtual machine.
- 2. Create a software **raid 5** on the three disks. (It is not necessary to put a filesystem on it)
- 3. Verify with **fdisk** and in /**proc** that the **raid 5** exists.
- 4. Stop and remove the **raid 5**.
- 5. Create a **raid 1** to mirror two disks.

## 10.5. solution: raid

- 1. Add three virtual disks of 1GB each to a virtual machine.
- 2. Create a software **raid 5** on the three disks. (It is not necessary to put a filesystem on it)
- 3. Verify with **fdisk** and in **/proc** that the **raid 5** exists.
- 4. Stop and remove the **raid 5**.
- 5. Create a **raid 1** to mirror two disks.

# Chapter 11. logical volume management

Most **lvm** implementations support **physical storage grouping**, **logical volume resizing** and **data migration**.

Physical storage grouping is a fancy name for grouping multiple block devices (hard disks, but also iSCSI etc) into a logical mass storage device. To enlarge this physical group, block devices (including partitions) can be added at a later time.


The size of **lvm volumes** on this **physical group** is independent of the individual size of the components. The total size of the group is the limit.

One of the nice features of **lvm** is the logical volume resizing. You can increase the size of an **lvm volume**, sometimes even without any downtime. Additionally, you can migrate data away from a failing hard disk device, create mirrors and create snapshots.

## 11.1. introduction to lvm

### 11.1.1. problems with standard partitions


There are some problems when working with hard disks and standard partitions. Consider a system with a small and a large hard disk device, partitioned like this. The first disk (/dev/sda) is partitioned in two, the second disk (/dev/sdb) has two partitions and some empty space.



In the example above, consider the options when you want to enlarge the space available for /srv/project42. What can you do? The solution will always force you to unmount the file system, take a backup of the data, remove and recreate partitions, and then restore the data and remount the file system.

#### 11.1.2. solution with lym

Using **lvm** will create a virtual layer between the mounted file systems and the hardware devices. This virtual layer will allow for an administrator to enlarge a mounted file system in use. When **lvm** is properly used, then there is no need to unmount the file system to enlarge it.



## 11.2. lvm terminology

### 11.2.1. physical volume (pv)

A **physical volume** is any block device (a disk, a partition, a RAID device or even an iSCSI device). All these devices can become a member of a **volume group**.

The commands used to manage a **physical volume** start with pv.

```
[root@centos65 ~]# pv
pvchange pvck pvcreate pvdisplay pvmove pvremove
pvresize pvs pvscan
```

### 11.2.2. volume group (vg)

A volume group is an abstraction layer between block devices and logical volumes.

The commands used to manage a **volume group** start with vg.

```
[root@centos65 ~]# vg
vgcfgbackup
            vgconvert
                            vgextend
                                           vgmknodes
                                                          vgs
vgcfgrestore
              vgcreate
                            vgimport
                                           vgreduce
                                                          vgscan
vgchange
              vgdisplay
                            vgimportclone vgremove
                                                          vgsplit
              vgexport
                            vgmerge
                                           vgrename
```

## 11.2.3. logical volume (lv)

A **logical volume** is created in a **volume group**. Logical volumes that contain a file system can be mounted. The use of **logical volumes** is similar to the use of **partitions** and is accomplished with the same standard commands (mkfs, mount, fsck, df, ...).

The commands used to manage a **logical volume** start with lv.

```
[root@centos65 ~]# lv
lvchange
          lvextend
                        lvmdiskscan lvmsar
                                                  lvresize
lvconvert
           lvm
                        lvmdump
                                     lvreduce
                                                  lvs
lvcreate
           lvmchange
                        lvmetad
                                     lvremove
                                                  lvscan
lvdisplay lvmconf
                         lvmsadc
                                     lvrename
```

## 11.3. example: using lvm

This example shows how you can use a device (in this case /dev/sdc, but it could have been / dev/sdb or any other disk or partition) with lvm, how to create a volume group (vg) and how to create and use a logical volume (vg/lvol0).

First thing to do, is create physical volumes that can join the volume group with **pvcreate**. This command makes a disk or partition available for use in Volume Groups. The screenshot shows how to present the SCSI Disk device to LVM.

```
root@RHEL4:~# pvcreate /dev/sdc
Physical volume "/dev/sdc" successfully created
```

Note: lvm will work fine when using the complete device, but another operating system on the same computer (or on the same SAN) will not recognize lvm and will mark the block device as being empty! You can avoid this by creating a partition that spans the whole device, then run pvcreate on the partition instead of the disk.

Then **vgcreate** creates a volume group using one device. Note that more devices could be added to the volume group.

```
root@RHEL4:~# vgcreate vg /dev/sdc
Volume group "vg" successfully created
```

The last step **lvcreate** creates a logical volume.

```
root@RHEL4:~# lvcreate --size 500m vg
Logical volume "lvol0" created
```

The logical volume /dev/vg/lvol0 can now be formatted with ext3, and mounted for normal use.

```
root@RHELv4u2:~# mke2fs -m0 -j /dev/vg/lvol0
mke2fs 1.35 (28-Feb-2004)
Filesystem label=
OS type: Linux
Block size=1024 (log=0)
Fragment size=1024 (log=0)
128016 inodes, 512000 blocks
0 blocks (0.00%) reserved for the super user
First data block=1
Maximum filesystem blocks=67633152
63 block groups
8192 blocks per group, 8192 fragments per group
2032 inodes per group
Superblock backups stored on blocks:
8193, 24577, 40961, 57345, 73729, 204801, 221185, 401409
Writing inode tables: done
Creating journal (8192 blocks): done
Writing superblocks and filesystem accounting information: done
This filesystem will be automatically checked every 37 mounts or
180 days, whichever comes first. Use tune2fs -c or -i to override.
root@RHELv4u2:~# mkdir /home/project10
root@RHELv4u2:~# mount /dev/vg/lvol0 /home/project10/
root@RHELv4u2:~# df -h | grep proj
/dev/mapper/vg-lvol0 485M 11M 474M 3% /home/project10
```

A logical volume is very similar to a partition, it can be formatted with a file system, and can be mounted so users can access it.

## 11.4. example: extend a logical volume

A logical volume can be extended without unmounting the file system. Whether or not a volume can be extended depends on the file system it uses. Volumes that are mounted as vfat or ext2 cannot be extended, so in the example here we use the ext3 file system.

The fdisk command shows us newly added scsi-disks that will serve our lvm volume. This volume will then be extended. First, take a look at these disks.

```
[root@RHEL5 ~]# fdisk -l | grep sd[bc]
Disk /dev/sdb doesn't contain a valid partition table
Disk /dev/sdc doesn't contain a valid partition table
Disk /dev/sdb: 1181 MB, 1181115904 bytes
Disk /dev/sdc: 429 MB, 429496320 bytes
```

You already know how to partition a disk, below the first disk is partitioned (in one big primary partition), the second disk is left untouched.

You also know how to prepare disks for lym with **pycreate**, and how to create a volume group with **vgcreate**. This example adds both the partitioned disk and the untouched disk to the volume group named **vg2**.

```
[root@RHEL5 ~]# pvcreate /dev/sdb1
Physical volume "/dev/sdb1" successfully created
[root@RHEL5 ~]# pvcreate /dev/sdc
Physical volume "/dev/sdc" successfully created
[root@RHEL5 ~]# vgcreate vg2 /dev/sdb1 /dev/sdc
Volume group "vg2" successfully created
```

You can use **pvdisplay** to verify that both the disk and the partition belong to the volume group.

And you are familiar both with the **lvcreate** command to create a small logical volume and the **mke2fs** command to put ext3 on it.

```
[root@RHEL5 ~]# lvcreate --size 200m vg2
Logical volume "lvol0" created
[root@RHEL5 ~]# mke2fs -m20 -j /dev/vg2/lvol0
...
```

As you see, we end up with a mounted logical volume that according to **df** is almost 200 megabyte in size.

Extending the volume is easy with **lvextend**.

```
[root@RHEL5 ~]# lvextend -L +100 /dev/vg2/lvol0
Extending logical volume lvol0 to 300.00 MB
Logical volume lvol0 successfully resized
```

But as you can see, there is a small problem: it appears that df is not able to display the extended volume in its full size. This is because the filesystem is only set for the size of the volume before the extension was added.

```
[root@RHEL5 ~]# df -h | grep resizetest
194M 5.6M 149M 4% /home/resizetest
```

With **lvdisplay** however we can see that the volume is indeed extended.

```
[root@RHEL5 ~]# lvdisplay /dev/vg2/lvol0 | grep Size
LV Size 300.00 MB
```

To finish the extension, you need **resize2fs** to span the filesystem over the full size of the logical volume.

```
[root@RHEL5 ~]# resize2fs /dev/vg2/lvol0 resize2fs 1.39 (29-May-2006) Filesystem at /dev/vg2/lvol0 is mounted on /home/resizetest; on-line re\sizing required Performing an on-line resize of /dev/vg2/lvol0 to 307200 (1k) blocks. The filesystem on /dev/vg2/lvol0 is now 307200 blocks long.
```

Congratulations, you just successfully expanded a logical volume.

## 11.5. example: resize a physical Volume

This is a humble demonstration of how to resize a physical Volume with lvm (after you resize it with fdisk). The demonstration starts with a 100MB partition named /dev/sde1. We used fdisk to create it, and to verify the size.

Now we can use pvcreate to create the Physical Volume, followed by pvs to verify the creation.

The next step is to use fdisk to enlarge the partition (actually deleting it and then recreating / dev/sde1 with more cylinders).

```
[root@RHEL5 ~]# fdisk /dev/sde
Command (m for help): p
Disk /dev/sde: 858 MB, 858993152 bytes
64 heads, 32 sectors/track, 819 cylinders
Units = cylinders of 2048 * 512 = 1048576 bytes
  Device Boot
                  Start
                                 End
                                          Blocks
                                                   Id System
/dev/sde1
                                 100
                                           102384
                                                   83 Linux
Command (m for help): d
Selected partition 1
Command (m for help): n
Command action
  e extended
  p primary partition (1-4)
p
Partition number (1-4):
Value out of range.
Partition number (1-4): 1
First cylinder (1-819, default 1):
Using default value 1
Last cylinder or +size or +sizeM or +sizeK (1-819, default 819): 200
Command (m for help): w
The partition table has been altered!
Calling ioctl() to re-read partition table.
Syncing disks.
[root@RHEL5 ~]#
```

When we now use fdisk and pvs to verify the size of the partition and the Physical Volume, then there is a size difference. LVM is still using the old size.

Executing pyresize on the Physical Volume will make lym aware of the size change of the partition. The correct size can be displayed with pys.

## 11.6. example: mirror a logical volume

We start by creating three physical volumes for lvm. Then we verify the creation and the size with pvs. Three physical disks because lvm uses two disks for the mirror and a third disk for the mirror log!

Then we create the Volume Group and verify again with pvs. Notice how the three physical volumes now belong to vg33, and how the size is rounded down (in steps of the extent size, here 4MB).

The last step is to create the Logical Volume with **lvcreate**. Notice the **-m 1** switch to create one mirror. Notice also the change in free space in all three Physical Volumes!

You can see the copy status of the mirror with lvs. It currently shows a 100 percent copy.

## 11.7. example: snapshot a logical volume

A snapshot is a virtual copy of all the data at a point in time on a volume. A snapshot Logical Volume will retain a copy of all changed files of the snapshotted Logical Volume.

The example below creates a snapshot of the bigLV Logical Volume.

```
[root@RHEL5 ~]# lvcreate -L100M -s -n snapLV vg42/bigLV
Logical volume "snapLV" created
[root@RHEL5 ~]#
```

You can see with lvs that the snapshot snapLV is indeed a snapshot of bigLV. Moments after taking the snapshot, there are few changes to bigLV (0.02 percent).

But after using bigLV for a while, more changes are done. This means the snapshot volume has to keep more original data (10.22 percent).

You can now use regular backup tools (dump, tar, cpio, ...) to take a backup of the snapshot Logical Volume. This backup will contain all data as it existed on bigLV at the time the snapshot was taken. When the backup is done, you can remove the snapshot.

```
[root@RHEL5 ~]# lvremove vg42/snapLV
Do you really want to remove active logical volume "snapLV"? [y/n]: y
  Logical volume "snapLV" successfully removed
[root@RHEL5 ~]#
```

## 11.8. verifying existing physical volumes

#### 11.8.1. lymdiskscan

To get a list of block devices that can be used with LVM, use **lvmdiskscan**. The example below uses grep to limit the result to SCSI devices.

```
[root@RHEL5 ~]# lvmdiskscan | grep sd
 /dev/sda1
                                101.94 MB]
 /dev/sda2
                                 15.90 GB] LVM physical volume
 /dev/sdb
                                409.60 MB]
                          [
 /dev/sdc
                                 409.60 MB]
                         [
 /dev/sdd
                                 409.60 MB] LVM physical volume
                         [
 /dev/sde1
                          [
                                 95.98 MB]
 /dev/sde5
                          [
                                 191.98 MB]
 /dev/sdf
                          [
                                 819.20 MB] LVM physical volume
                         [
 /dev/sdg1
                                818.98 MB]
[root@RHEL5 ~]#
```

### 11.8.2. pvs

The easiest way to verify whether devices are known to lvm is with the **pvs** command. The screenshot below shows that only /dev/sda2 is currently known for use with LVM. It shows that /dev/sda2 is part of Volgroup00 and is almost 16GB in size. It also shows /dev/sdc and / dev/sdd as part of vg33. The device /dev/sdb is knwon to lvm, but not linked to any Volume Group.

```
[root@RHEL5 ~]# pvs

PV VG Fmt Attr PSize PFree

/dev/sda2 VolGroup00 lvm2 a- 15.88G 0

/dev/sdb lvm2 -- 409.60M 409.60M

/dev/sdc vg33 lvm2 a- 408.00M 408.00M

/dev/sdd vg33 lvm2 a- 408.00M 408.00M

[root@RHEL5 ~]#
```

### 11.8.3. pvscan

The **pvscan** command will scan all disks for existing Physical Volumes. The information is similar to pvs, plus you get a line with total sizes.

### 11.8.4. pvdisplay

Use **pvdisplay** to get more information about physical volumes. You can also use **pvdisplay** without an argument to display information about all physical (lvm) volumes.

```
[root@RHEL5 ~]# pvdisplay /dev/sda2
 --- Physical volume ---
 PV Name
                       /dev/sda2
 VG Name
                       VolGroup00
 PV Size
Allocatable
                      15.90 GB / not usable 20.79 MB
                       yes (but full)
                      32768
 PE Size (KByte)
 Total PE
                      508
 Free PE
 Allocated PE
 PV UUID
                       TobYfp-Ggg0-Rf8r-xtLd-5XgN-RSPc-8vkTHD
[root@RHEL5 ~]#
```

## 11.9. verifying existing volume groups

### 11.9.1. vgs

Similar to **pvs** is the use of **vgs** to display a quick overview of all volume groups. There is only one volume group in the screenshot below, it is named VolGroup00 and is almost 16GB in size.

### 11.9.2. vgscan

The **vgscan** command will scan all disks for existing Volume Groups. It will also update the **/etc/lvm/.cache** file. This file contains a list of all current lvm devices.

```
[root@RHEL5 ~]# vgscan
  Reading all physical volumes. This may take a while...
  Found volume group "VolGroup00" using metadata type lvm2
[root@RHEL5 ~]#
```

LVM will run the vgscan automatically at boot-up, so if you add hot swap devices, then you will need to run vgscan to update /etc/lvm/.cache with the new devices.

### 11.9.3. vgdisplay

The **vgdisplay** command will give you more detailed information about a volume group (or about all volume groups if you omit the argument).

```
[root@RHEL5 ~]# vgdisplay VolGroup00
 --- Volume group ---
 VG Name
                       VolGroup00
 System ID
 Format
                       lvm2
 Metadata Areas
 Metadata Sequence No 3
 VG Access
                      read/write
 VG Status
                      resizable
 WY XYM
                      Ω
                      2
 Cur LV
 Open LV
                      2
 Max PV
 Cur PV
                      1
 Act PV
                      1
                     15.88 GB
 VG Size
                      32.00 MB
 PE Size
 Total PE
                      508
 Alloc PE / Size 508 / 15.88 GB Free PE / Size 0 / 0
 VG UUID
                       qsXvJb-71qV-917U-ishX-FobM-qptE-VXmKIg
[root@RHEL5 ~]#
```

## 11.10. verifying existing logical volumes

#### 11.10.1. lvs

Use **lvs** for a quick look at all existing logical volumes. Below you can see two logical volumes named LogVol00 and LogVol01.

```
[root@RHEL5 ~]# lvs
LV    VG     Attr    LSize Origin Snap% Move Log Copy%
LogVol00 VolGroup00 -wi-ao 14.88G
LogVol01 VolGroup00 -wi-ao 1.00G
[root@RHEL5 ~]#
```

#### 11.10.2. lyscan

The **lvscan** command will scan all disks for existing Logical Volumes.

### 11.10.3. Ivdisplay

More detailed information about logical volumes is available through the **lvdisplay(1)** command.

```
[root@RHEL5 ~]# lvdisplay VolGroup00/LogVol01
 --- Logical volume ---
 LV Name
                        /dev/VolGroup00/LogVol01
 VG Name
                       VolGroup00
 LV UUID
                       RnTGK6-xWsi-t530-ksJx-7cax-co5c-A1KlDp
 LV Write Access
                       read/write
                       available
 LV Status
 # open
                       1
                       1.00 GB
 LV Size
 Current LE
                       32
 Segments
                       1
 Allocation
                       inherit
 Read ahead sectors
 Block device
                        253:1
[root@RHEL5 ~]#
```

## 11.11. manage physical volumes

### 11.11.1. pvcreate

Use the **pvcreate** command to add devices to lvm. This example shows how to add a disk (or hardware RAID device) to lvm.

```
[root@RHEL5 ~]# pvcreate /dev/sdb
Physical volume "/dev/sdb" successfully created
[root@RHEL5 ~]#
```

This example shows how to add a partition to lvm.

```
[root@RHEL5 ~]# pvcreate /dev/sdc1
Physical volume "/dev/sdc1" successfully created
[root@RHEL5 ~]#
```

You can also add multiple disks or partitions as target to pvcreate. This example adds three disks to lvm.

```
[root@RHEL5 ~]# pvcreate /dev/sde /dev/sdf /dev/sdg
Physical volume "/dev/sde" successfully created
Physical volume "/dev/sdf" successfully created
Physical volume "/dev/sdg" successfully created
[root@RHEL5 ~]#
```

#### 11.11.2. pvremove

Use the **pvremove** command to remove physical volumes from lvm. The devices may not be in use.

```
[root@RHEL5 ~]# pvremove /dev/sde /dev/sdf /dev/sdg
Labels on physical volume "/dev/sde" successfully wiped
Labels on physical volume "/dev/sdf" successfully wiped
Labels on physical volume "/dev/sdg" successfully wiped
[root@RHEL5 ~]#
```

### 11.11.3. pvresize

When you used fdisk to resize a partition on a disk, then you must use **pvresize** to make lvm recognize the new size of the physical volume that represents this partition.

```
[root@RHEL5 ~]# pvresize /dev/sde1
Physical volume "/dev/sde1" changed
1 physical volume(s) resized / 0 physical volume(s) not resized
```

### 11.11.4. pvchange

With **pvchange** you can prevent the allocation of a Physical Volume in a new Volume Group or Logical Volume. This can be useful if you plan to remove a Physical Volume.

```
[root@RHEL5 ~]# pvchange -xn /dev/sdd
Physical volume "/dev/sdd" changed
1 physical volume changed / 0 physical volumes not changed
[root@RHEL5 ~]#
```

To revert your previous decision, this example shows you how te re-enable the Physical Volume to allow allocation.

```
[root@RHEL5 ~]# pvchange -xy /dev/sdd
Physical volume "/dev/sdd" changed
1 physical volume changed / 0 physical volumes not changed
[root@RHEL5 ~]#
```

### 11.11.5. pvmove

With **pvmove** you can move Logical Volumes from within a Volume Group to another Physical Volume. This must be done before removing a Physical Volume.

## 11.12. manage volume groups

### 11.12.1. vgcreate

Use the **vgcreate** command to create a volume group. You can immediately name all the physical volumes that span the volume group.

```
[root@RHEL5 ~]# vgcreate vg42 /dev/sde /dev/sdf
Volume group "vg42" successfully created
[root@RHEL5 ~]#
```

### 11.12.2. vgextend

Use the **vgextend** command to extend an existing volume group with a physical volume.

```
[root@RHEL5 ~]# vgextend vg42 /dev/sdg
  Volume group "vg42" successfully extended
[root@RHEL5 ~]#
```

### 11.12.3. vgremove

Use the **vgremove** command to remove volume groups from lvm. The volume groups may not be in use.

```
[root@RHEL5 ~]# vgremove vg42
  Volume group "vg42" successfully removed
[root@RHEL5 ~]#
```

### 11.12.4. vgreduce

Use the **vgreduce** command to remove a Physical Volume from the Volume Group.

The following example adds Physical Volume /dev/sdg to the vg1 Volume Group using vgextend. And then removes it again using vgreduce.

### 11.12.5. vgchange

Use the **vgchange** command to change parameters of a Volume Group.

This example shows how to prevent Physical Volumes from being added or removed to the Volume Group vg1.

```
[root@RHEL5 ~]# vgchange -xn vg1
Volume group "vg1" successfully changed
[root@RHEL5 ~]# vgextend vg1 /dev/sdg
Volume group vg1 is not resizable.
```

You can also use vgchange to change most other properties of a Volume Group. This example changes the maximum number of Logical Volumes and maximum number of Physical Volumes that vg1 can serve.

### 11.12.6. vgmerge

Merging two Volume Groups into one is done with **vgmerge**. The following example merges vg2 into vg1, keeping all the properties of vg1.

```
[root@RHEL5 ~]# vgmerge vg1 vg2
Volume group "vg2" successfully merged into "vg1"
[root@RHEL5 ~]#
```

### 11.13. manage logical volumes

#### 11.13.1. lvcreate

Use the **lvcreate** command to create Logical Volumes in a Volume Group. This example creates an 8GB Logical Volume in Volume Group vg42.

```
[root@RHEL5 ~]# lvcreate -L5G vg42
  Logical volume "lvol0" created
[root@RHEL5 ~]#
```

As you can see, lvm automatically names the Logical Volume **lvol0**. The next example creates a 200MB Logical Volume named MyLV in Volume Group vg42.

```
[root@RHEL5 ~]# lvcreate -L200M -nMyLV vg42
  Logical volume "MyLV" created
[root@RHEL5 ~]#
```

The next example does the same thing, but with different syntax.

```
[root@RHEL5 ~]# lvcreate --size 200M -n MyLV vg42
Logical volume "MyLV" created
[root@RHEL5 ~]#
```

This example creates a Logical Volume that occupies 10 percent of the Volume Group.

```
[root@RHEL5 ~]# lvcreate -l 10%VG -n MyLV2 vg42
  Logical volume "MyLV2" created
[root@RHEL5 ~]#
```

This example creates a Logical Volume that occupies 30 percent of the remaining free space in the Volume Group.

```
[root@RHEL5 ~]# lvcreate -1 30%FREE -n MyLV3 vg42
  Logical volume "MyLV3" created
[root@RHEL5 ~]#
```

#### 11.13.2. Ivremove

Use the **lvremove** command to remove Logical Volumes from a Volume Group. Removing a Logical Volume requires the name of the Volume Group.

```
[root@RHEL5 ~]# lvremove vg42/MyLV
Do you really want to remove active logical volume "MyLV"? [y/n]: y
  Logical volume "MyLV" successfully removed
[root@RHEL5 ~]#
```

Removing multiple Logical Volumes will request confirmation for each individual volume.

```
[root@RHEL5 ~]# lvremove vg42/MyLV vg42/MyLV2 vg42/MyLV3
Do you really want to remove active logical volume "MyLV"? [y/n]: y
  Logical volume "MyLV" successfully removed
Do you really want to remove active logical volume "MyLV2"? [y/n]: y
  Logical volume "MyLV2" successfully removed
Do you really want to remove active logical volume "MyLV3"? [y/n]: y
  Logical volume "MyLV3" successfully removed
[root@RHEL5 ~]#
```

#### 11.13.3. Ivextend

Extending the volume is easy with **lvextend**. This example extends a 200MB Logical Volume with 100 MB.

The next example creates a 100MB Logical Volume, and then extends it to 500MB.

```
[root@RHEL5 ~]# lvcreate --size 100M -n extLV vg42
Logical volume "extLV" created
[root@RHEL5 ~]# lvextend -L 500M vg42/extLV
Extending logical volume extLV to 500.00 MB
Logical volume extLV successfully resized
[root@RHEL5 ~]#
```

This example doubles the size of a Logical Volume.

```
[root@RHEL5 ~]# lvextend -l+100%LV vg42/extLV
Extending logical volume extLV to 1000.00 MB
Logical volume extLV successfully resized
[root@RHEL5 ~]#
```

#### 11.13.4. lyrename

Renaming a Logical Volume is done with **lvrename**. This example renames extLV to bigLV in the vg42 Volume Group.

```
[root@RHEL5 ~]# lvrename vg42/extLV vg42/bigLV
Renamed "extLV" to "bigLV" in volume group "vg42"
[root@RHEL5 ~]#
```

## 11.14. practice: Ivm

- 1. Create a volume group that contains a complete disk and a partition on another disk.
- 2. Create two logical volumes (a small one and a bigger one) in this volumegroup. Format them wih ext3, mount them and copy some files to them.
- 3. Verify usage with fdisk, mount, pvs, vgs, lvs, pvdisplay, vgdisplay, lvdisplay and df. Does fdisk give you any information about lvm?
- 4. Enlarge the small logical volume by 50 percent, and verify your work!
- 5. Take a look at other commands that start with vg\*, pv\* or lv\*.
- 6. Create a mirror and a striped Logical Volume.
- 7. Convert a linear logical volume to a mirror.
- 8. Convert a mirror logical volume to a linear.
- 9. Create a snapshot of a Logical Volume, take a backup of the snapshot. Then delete some files on the Logical Volume, then restore your backup.
- 10. Move your volume group to another disk (keep the Logical Volumes mounted).
- 11. If time permits, split a Volume Group with vgsplit, then merge it again with vgmerge.

#### 11.15. solution : lvm

1. Create a volume group that contains a complete disk and a partition on another disk.

#### step 1: select disks:

```
root@rhe165:~# fdisk -1 | grep Disk

Disk /dev/sda: 8589 MB, 8589934592 bytes

Disk identifier: 0x00055ca0

Disk /dev/sdb: 1073 MB, 1073741824 bytes

Disk identifier: 0x00000000

Disk /dev/sdc: 1073 MB, 1073741824 bytes

Disk identifier: 0x000000000

...
```

I choose /dev/sdb and /dev/sdc for now.

#### step 2: partition /dev/sdc

```
root@rhel65:~# fdisk /dev/sdc
Device contains neither a valid DOS partition table, nor Sun, SGI or OSF disk
Building a new DOS disklabel with disk identifier 0x94c0e5d5.
Changes will remain in memory only, until you decide to write them.
After that, of course, the previous content won't be recoverable.
Warning: invalid flag 0x0000 of partition table 4 will be corrected by w(rite)
WARNING: DOS-compatible mode is deprecated. It's strongly recommended to
         switch off the mode (command 'c') and change display units to
         sectors (command 'u').
Command (m for help): n
Command action
  e extended
  p primary partition (1-4)
Partition number (1-4): 1
First cylinder (1-130, default 1):
Using default value 1
Last cylinder, +cylinders or +size{K,M,G} (1-130, default 130):
Using default value 130
Command (m for help): w
The partition table has been altered!
Calling ioctl() to re-read partition table.
Syncing disks.
```

#### step 3: pvcreate and vgcreate

```
root@rhel65:~# pvcreate /dev/sdb /dev/sdc1
Physical volume "/dev/sdb" successfully created
Physical volume "/dev/sdc1" successfully created
root@rhel65:~# vgcreate VG42 /dev/sdb /dev/sdc1
Volume group "VG42" successfully created
```

2. Create two logical volumes (a small one and a bigger one) in this volumegroup. Format them wih ext3, mount them and copy some files to them.

```
root@rhel65:~# lvcreate --size 200m --name LVsmall VG42
  Logical volume "LVsmall" created
root@rhel65:~# lvcreate --size 600m --name LVbig VG42
 Logical volume "LVbig" created
root@rhel65:~# ls -1 /dev/mapper/VG42-LVsmall
lrwxrwxrwx. 1 root root 7 Apr 20 20:41 /dev/mapper/VG42-LVsmall -> ../dm-2
root@rhel65:~# ls -l /dev/VG42/LVsmall
lrwxrwxrwx. 1 root root 7 Apr 20 20:41 /dev/VG42/LVsmall -> ../dm-2
root@rhel65:~# ls -1 /dev/dm-2
brw-rw---. 1 root disk 253, 2 Apr 20 20:41 /dev/dm-2
root@rhel65:~# mkfs.ext3 /dev/mapper/VG42-LVsmall
mke2fs 1.41.12 (17-May-2010)
Filesystem label=
OS type: Linux
Block size=1024 (log=0)
Fragment size=1024 (log=0)
Stride=0 blocks, Stripe width=0 blocks
51200 inodes, 204800 blocks
10240 blocks (5.00%) reserved for the super user
First data block=1
Maximum filesystem blocks=67371008
25 block groups
8192 blocks per group, 8192 fragments per group
2048 inodes per group
Superblock backups stored on blocks:
 8193, 24577, 40961, 57345, 73729
Writing inode tables: done
Creating journal (4096 blocks): done
Writing superblocks and filesystem accounting information: done
This filesystem will be automatically checked every 39 mounts or
180 days, whichever comes first. Use tune2fs -c or -i to override.
root@rhel65:~# mkfs.ext3 /dev/VG42/LVbig
mke2fs 1.41.12 (17-May-2010)
Filesystem label=
OS type: Linux
Block size=4096 (log=2)
Fragment size=4096 (log=2)
Stride=0 blocks, Stripe width=0 blocks
38400 inodes, 153600 blocks
7680 blocks (5.00%) reserved for the super user
First data block=0
Maximum filesystem blocks=159383552
5 block groups
32768 blocks per group, 32768 fragments per group
7680 inodes per group
Superblock backups stored on blocks:
 32768, 98304
Writing inode tables: done
Creating journal (4096 blocks): done
Writing superblocks and filesystem accounting information: done
This filesystem will be automatically checked every 25 mounts or
180 days, whichever comes first. Use tune2fs -c or -i to override.
```

The mounting and copying of files.

```
root@rhel65:~# mkdir /srv/LVsmall
root@rhel65:~# mkdir /srv/LVbig
root@rhel65:~# mount /dev/mapper/VG42-LVsmall /srv/LVsmall
root@rhel65:~# mount /dev/VG42/LVbig /srv/LVbig
root@rhel65:~# cp -r /etc /srv/LVsmall/
root@rhel65:~# cp -r /var/log /srv/LVbig/
```

3. Verify usage with fdisk, mount, pvs, vgs, lvs, pvdisplay, vgdisplay, lvdisplay and df. Does fdisk give you any information about lvm?

Run all those commands (only two are shown below), then answer 'no'.

```
root@rhel65:~# df -h
Filesystem
                     Size Used Avail Use% Mounted on
/dev/mapper/VolGroup-lv_root
                     6.7G 1.4G 5.0G 21% /
                     246M
                           0 246M 0% /dev/shm
/dev/sda1
                    485M
                           77M 383M 17% /boot
/dev/mapper/VG42-LVsmall
                     194M
                           30M 154M 17% /srv/LVsmall
/dev/mapper/VG42-LVbig
                     591M
                           20M 541M
                                      4% /srv/LVbig
root@rhel65:~# mount | grep VG42
/dev/mapper/VG42-LVsmall on /srv/LVsmall type ext3 (rw)
/dev/mapper/VG42-LVbig on /srv/LVbig type ext3 (rw)
```

4. Enlarge the small logical volume by 50 percent, and verify your work!

- 5. Take a look at other commands that start with vg\*, pv\* or lv\*.
- 6. Create a mirror and a striped Logical Volume.
- 7. Convert a linear logical volume to a mirror.
- 8. Convert a mirror logical volume to a linear.
- 9. Create a snapshot of a Logical Volume, take a backup of the snapshot. Then delete some files on the Logical Volume, then restore your backup.
- 10. Move your volume group to another disk (keep the Logical Volumes mounted).
- 11. If time permits, split a Volume Group with vgsplit, then merge it again with vgmerge.

# Chapter 12. iSCSI devices

| This chapter teaches you how to setup an iSCSI target server and an iSCSI initiator client |
|--|
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |
|  |

## 12.1. iSCSI terminology

**iSCSI** is a protocol that enables SCSI over IP. This means that you can have local SCSI devices (like /dev/sdb) without having the storage hardware in the local computer.

The computer holding the physical storage hardware is called the **iSCSI Target**. Each individual addressable iSCSI device on the target server will get a **LUN number**.

The iSCSI client computer that is connecting to the Target server is called an **Initiator**. An initiator will send SCSI commands over IP instead of directly to the hardware. The Initiator will connect to the Target.

## 12.2. iSCSI Target in RHEL/CentOS

This section will describe iSCSI Target setup on RHEL6, RHEL7 and CentOS.

Start with installing the **iSCSI Target** package.

```
yum install scsi-target-utils
```

We configure three local disks in /etc/tgt/targets.conf to become three LUN's.

```
<target iqn.2008-09.com.example:server.target2>
    direct-store /dev/sdb
    direct-store /dev/sdc
    direct-store /dev/sdd
    incominguser paul hunter2
</target>
```

Restart the service.

```
[root@centos65 ~]# service tgtd start
Starting SCSI target daemon: [ OK ]
```

The standard local port for iSCSI Target is 3260, in case of doubt you can verify this with **netstat**.

The **tgt-admin -s** command should now give you a nice overview of the three LUN's (and also LUN 0 for the controller).

```
[root@server1 tgt]# tgt-admin -s
Target 1: iqn.2014-04.be.linux-training:server1.target1
   System information:
       Driver: iscsi
       State: ready
    I_T nexus information:
   LUN information:
        LUN: 0
            Type: controller
            SCSI ID: IET
                             00010000
            SCSI SN: beaf10
            Size: 0 MB, Block size: 1
            Online: Yes
            Removable media: No
            Prevent removal: No
            Readonly: No
            Backing store type: null
            Backing store path: None
            Backing store flags:
        LUN: 1
            Type: disk
            SCSI ID: IET
                             00010001
            SCSI SN: VB9f23197b-af6cfb60
            Size: 1074 MB, Block size: 512
            Online: Yes
            Removable media: No
            Prevent removal: No
            Readonly: No
            Backing store type: rdwr
            Backing store path: /dev/sdb
            Backing store flags:
        LUN: 2
            Type: disk
            SCSI ID: IET
                             00010002
            SCSI SN: VB8f554351-a1410828
            Size: 1074 MB, Block size: 512
            Online: Yes
            Removable media: No
            Prevent removal: No
            Readonly: No
            Backing store type: rdwr
            Backing store path: /dev/sdc
            Backing store flags:
        LUN: 3
            Type: disk
            SCSI ID: IET
                             00010003
            SCSI SN: VB1035d2f0-7ae90b49
            Size: 1074 MB, Block size: 512
            Online: Yes
            Removable media: No
            Prevent removal: No
            Readonly: No
            Backing store type: rdwr
            Backing store path: /dev/sdd
            Backing store flags:
   Account information:
   ACL information:
        ALL
```

### 12.3. iSCSI Initiator in RHEL/CentOS

This section will describe iSCSI Initiator setup on RHEL6, RHEL7 and CentOS.

Start with installing the **iSCSI Initiator** package.

```
[root@server2 ~]# yum install iscsi-initiator-utils
```

Then ask the **iSCSI target server** to send you the target names.

We received iqn.2014-04.be.linux-training:centos65.target1.

We use this iqn to configure the username and the password (paul and hunter2) that we set on the target server.

```
[root@server2 iscsi]# iscsiadm -m node --targetname iqn.2014-04.be.linux-tra\ ining:centos65.target1 --portal "192.168.1.95:3260" --op=update --name node.\ session.auth.username --value=paul [root@server2 iscsi]# iscsiadm -m node --targetname iqn.2014-04.be.linux-tra\ ining:centos65.target1 --portal "192.168.1.95:3260" --op=update --name node.\ session.auth.password --value=hunter2 [root@server2 iscsi]# iscsiadm -m node --targetname iqn.2014-04.be.linux-tra\ ining:centos65.target1 --portal "192.168.1.95:3260" --op=update --name node.\ session.auth.authmethod --value=CHAP
```

RHEL and CentOS will store these in /var/lib/iscsi/nodes/.

```
[root@server2 iscsi]# grep auth /var/lib/iscsi/nodes/iqn.2014-04.be.linux-tr\
aining\:centos65.target1/192.168.1.95\,3260\,1/default
node.session.auth.authmethod = CHAP
node.session.auth.username = paul
node.session.auth.password = hunter2
node.conn[0].timeo.auth_timeout = 45
[root@server2 iscsi]#
```

A restart of the **iscsi** service will add three new devices to our system.

```
[root@server2 iscsi]# fdisk -l | grep Disk
Disk /dev/sda: 42.9 GB, 42949672960 bytes
Disk identifier: 0x0004f229
Disk /dev/sdb: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdc: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdd: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sde: 2147 MB, 2147483648 bytes
Disk identifier: 0x00000000
Disk /dev/sdf: 2147 MB, 2147483648 bytes
Disk identifier: 0x00000000
Disk /dev/sdg: 2147 MB, 2147483648 bytes
Disk identifier: 0x00000000
Disk /dev/mapper/VolGroup-lv_root: 41.4 GB, 41448112128 bytes
Disk identifier: 0x00000000
Disk /dev/mapper/VolGroup-lv_swap: 973 MB, 973078528 bytes
Disk identifier: 0x00000000
[root@server2 iscsi]# service iscsi restart
Stopping iscsi:
                                                            [ OK ]
Starting iscsi:
                                                            [ OK ]
[root@server2 iscsi]# fdisk -l | grep Disk
Disk /dev/sda: 42.9 GB, 42949672960 bytes
Disk identifier: 0x0004f229
Disk /dev/sdb: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdc: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdd: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sde: 2147 MB, 2147483648 bytes
Disk identifier: 0x00000000
Disk /dev/sdf: 2147 MB, 2147483648 bytes
Disk identifier: 0x00000000
Disk /dev/sdg: 2147 MB, 2147483648 bytes
Disk identifier: 0x00000000
Disk /dev/mapper/VolGroup-lv_root: 41.4 GB, 41448112128 bytes
Disk identifier: 0x00000000
Disk /dev/mapper/VolGroup-lv_swap: 973 MB, 973078528 bytes
Disk identifier: 0x00000000
Disk /dev/sdh: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdi: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdj: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
```

#### You can verify iscsi status with:

```
service iscsi status
```

## 12.4. iSCSI target on Debian

Installing the software for the target server requires **iscsitarget** on Ubuntu and Debian, and an extra **iscsitarget-dkms** for the kernel modules only on Debian.

```
root@debby6:~# aptitude install iscsitarget
The following NEW packages will be installed:
    iscsitarget
0 packages upgraded, 1 newly installed, 0 to remove and 0 not upgraded.
Need to get 69.4 kB of archives. After unpacking 262 kB will be used.
Get:1 http://ftp.belnet.be/debian/ squeeze/main iscsitarget i386 1.4.20.2-1\
[69.4 kB]
Fetched 69.4 kB in 0s (415 kB/s)
Selecting previously deselected package iscsitarget.
(Reading database ... 36441 files and directories currently installed.)
Unpacking iscsitarget (from .../iscsitarget_1.4.20.2-1_i386.deb) ...
Processing triggers for man-db ...
Setting up iscsitarget (1.4.20.2-1) ...
iscsitarget not enabled in "/etc/default/iscsitarget", not starting...(warning).
```

On Debian 6 you will also need **aptitude install iscsitarget-dkms** for the kernel modules, on Debian 5 this is **aptitude install iscsitarget-modules-`uname -a`**. Ubuntu includes the kernel modules in the main package.

The iSCSI target server is disabled by default, so we enable it.

```
root@debby6:~# cat /etc/default/iscsitarget
ISCSITARGET_ENABLE=false
root@debby6:~# vi /etc/default/iscsitarget
root@debby6:~# cat /etc/default/iscsitarget
ISCSITARGET_ENABLE=true
```

## 12.5. iSCSI target setup with dd files

You can use LVM volumes (/dev/md0/lvol0), physical partitions (/dev/sda) ,raid devices (/dev/md0) or just plain files for storage. In this demo, we use files created with **dd**.

This screenshot shows how to create three small files (100MB, 200MB and 300MB).

```
root@debby6:~# mkdir /iscsi
root@debby6:~# dd if=/dev/zero of=/iscsi/lun1.img bs=1M count=100
100+0 records in
100+0 records out
104857600 bytes (105 MB) copied, 0.315825 s, 332 MB/s
root@debby6:~# dd if=/dev/zero of=/iscsi/lun2.img bs=1M count=200
200+0 records in
200+0 records out
209715200 bytes (210 MB) copied, 1.08342 s, 194 MB/s
root@debby6:~# dd if=/dev/zero of=/iscsi/lun3.img bs=1M count=300
300+0 records in
300+0 records out
314572800 bytes (315 MB) copied, 1.36209 s, 231 MB/s
```

We need to declare these three files as iSCSI targets in /etc/iet/ietd.conf (used to be /etc/ietd.conf).

```
root@debby6:/etc/iet# cp ietd.conf ietd.conf.original
root@debby6:/etc/iet# > ietd.conf
root@debby6:/etc/iet# vi ietd.conf
root@debby6:/etc/iet# cat ietd.conf
Target iqn.2010-02.be.linux-training:storage.lun1
 IncomingUser isuser hunter2
 OutgoingUser
 Lun 0 Path=/iscsi/lun1.img, Type=fileio
Target iqn.2010-02.be.linux-training:storage.lun2
 IncomingUser isuser hunter2
 OutgoingUser
Lun 0 Path=/iscsi/lun2.img, Type=fileio
 Alias LUN2
Target iqn.2010-02.be.linux-training:storage.lun3
 IncomingUser isuser hunter2
 OutgoingUser
 Lun 0 Path=/iscsi/lun3.img, Type=fileio
```

We also need to add our devices to the /etc/initiators.allow file.

```
root@debby6:/etc/iet# cp initiators.allow initiators.allow.original
root@debby6:/etc/iet# >initiators.allow
root@debby6:/etc/iet# vi initiators.allow
root@debby6:/etc/iet# cat initiators.allow
iqn.2010-02.be.linux-training:storage.lun1
iqn.2010-02.be.linux-training:storage.lun2
iqn.2010-02.be.linux-training:storage.lun3
```

#### Time to start the server now:

```
root@debby6:/etc/iet# /etc/init.d/iscsitarget start
Starting iSCSI enterprise target service:.
.
root@debby6:/etc/iet#
```

#### Verify activation of the storage devices in /proc/net/iet:

```
root@debby6:/etc/iet# cat /proc/net/iet/volume
tid:3 name:iqn.2010-02.be.linux-training:storage.lun3
lun:0 state:0 iotype:fileio iomode:wt blocks:614400 blocksize:\
512 path:/iscsi/lun3.img
tid:2 name:iqn.2010-02.be.linux-training:storage.lun2
lun:0 state:0 iotype:fileio iomode:wt blocks:409600 blocksize:\
512 path:/iscsi/lun2.img
tid:1 name:iqn.2010-02.be.linux-training:storage.lun1
lun:0 state:0 iotype:fileio iomode:wt blocks:204800 blocksize:\
512 path:/iscsi/lun1.img
root@debby6:/etc/iet# cat /proc/net/iet/session
tid:3 name:iqn.2010-02.be.linux-training:storage.lun3
tid:2 name:iqn.2010-02.be.linux-training:storage.lun2
tid:1 name:iqn.2010-02.be.linux-training:storage.lun1
```

### 12.6. ISCSI initiator on ubuntu

First we install the iSCSi client software (on another computer than the target).

```
root@ubu1104:~# aptitude install open-iscsi
Reading package lists... Done
Building dependency tree
Reading state information... Done
Reading extended state information
Initializing package states... Done
The following NEW packages will be installed:
   open-iscsi open-iscsi-utils{a}
```

Then we set the iSCSI client to start automatically.

```
root@ubul104:/etc/iscsi# cp iscsid.conf iscsid.conf.original
root@ubul104:/etc/iscsi# vi iscsid.conf
root@ubul104:/etc/iscsi# grep ^node.startup iscsid.conf
node.startup = automatic
```

Or you could start it manually.

```
root@ubu1104:/etc/iscsi/nodes# /etc/init.d/open-iscsi start
  * Starting iSCSI initiator service iscsid [ OK ]
  * Setting up iSCSI targets [ OK ]
root@ubu1104:/etc/iscsi/nodes#
```

Now we can connect to the Target server and use **iscsiadm** to discover the devices it offers:

```
root@ubul104:/etc/iscsi# iscsiadm -m discovery -t st -p 192.168.1.31
192.168.1.31:3260,1 iqn.2010-02.be.linux-training:storage.lun2
192.168.1.31:3260,1 iqn.2010-02.be.linux-training:storage.lun1
192.168.1.31:3260,1 iqn.2010-02.be.linux-training:storage.lun3
```

We can use the same **iscsiadm** to edit the files in /etc/iscsi/nodes/.

```
root@ubu1104:/etc/iscsi# iscsiadm -m node --targetname "iqn.2010-02.be.linu\x-training:storage.lun1" --portal "192.168.1.31:3260" --op=update --name no\de.session.auth.authmethod --value=CHAP
root@ubu1104:/etc/iscsi# iscsiadm -m node --targetname "iqn.2010-02.be.linu\x-training:storage.lun1" --portal "192.168.1.31:3260" --op=update --name no\de.session.auth.username --value=isuser
root@ubu1104:/etc/iscsi# iscsiadm -m node --targetname "iqn.2010-02.be.linu\x-training:storage.lun1" --portal "192.168.1.31:3260" --op=update --name no\de.session.auth.password --value=hunter2
```

Repeat the above for the other two devices.

#### Restart the initiator service to log in to the target.

#### Use **fdisk** -l to enjoy three new iSCSI devices.

```
root@ubu1104:/etc/iscsi/nodes# fdisk -1 2> /dev/null | grep Disk
Disk /dev/sda: 17.2 GB, 17179869184 bytes
Disk identifier: 0x0001983f
Disk /dev/sdb: 209 MB, 209715200 bytes
Disk identifier: 0x00000000
Disk /dev/sdd: 314 MB, 314572800 bytes
Disk identifier: 0x00000000
Disk /dev/sdc: 104 MB, 104857600 bytes
Disk identifier: 0x00000000
```

#### The Target (the server) now shows active sessions.

```
root@debby6:/etc/iet# cat /proc/net/iet/session
tid:3 name:iqn.2010-02.be.linux-training:storage.lun3
sid:5348024611832320 initiator:iqn.1993-08.org.debian:01:8983ed2d770
cid:0 ip:192.168.1.35 state:active hd:none dd:none
tid:2 name:iqn.2010-02.be.linux-training:storage.lun2
sid:4785074624856576 initiator:iqn.1993-08.org.debian:01:8983ed2d770
cid:0 ip:192.168.1.35 state:active hd:none dd:none
tid:1 name:iqn.2010-02.be.linux-training:storage.lun1
sid:5066549618344448 initiator:iqn.1993-08.org.debian:01:8983ed2d770
cid:0 ip:192.168.1.35 state:active hd:none dd:none
root@debby6:/etc/iet#
```

## 12.7. using iSCSI devices

There is no difference between using SCSI or iSCSI devices once they are connected: partition, make filesystem, mount.

```
root@ubu1104:/etc/iscsi/nodes# history | tail -13
   94 fdisk /dev/sdc
   95 fdisk /dev/sdd
   96 fdisk /dev/sdb
  97 mke2fs /dev/sdb1
  98 mke2fs -j /dev/sdc1
  99 mkfs.ext4 /dev/sdd1
 100 mkdir /mnt/is1
 101 mkdir /mnt/is2
 102 mkdir /mnt/is3
 103 mount /dev/sdb1 /mnt/is1
 104 mount /dev/sdc1 /mnt/is2
      mount /dev/sdd1 /mnt/is3
 106 history | tail -13
root@ubu1104:/etc/iscsi/nodes# mount | grep is
/dev/sdb1 on /mnt/is1 type ext2 (rw)
/dev/sdc1 on /mnt/is2 type ext3 (rw)
/dev/sdd1 on /mnt/is3 type ext4 (rw)
```

# 12.8. iSCSI Target RHEL7/CentOS7

The prefered tool to setup an iSCSI Target on RHEL is targetcli.

```
[root@centos7 ~]# yum install targetcli
Loaded plugins: fastestmirror
...
...
Installed:
  targetcli.noarch 0:2.1.fb37-3.el7

Complete!
[root@centos7 ~]#
```

The **targetcli** tool is interactive and represents the configuration fo the **target** in a structure that resembles a directory tree with several files. Although this is explorable inside **targetcli** with **ls**, **cd** and **pwd**, this are not files on the file system.

This tool also has tab-completion, which is very handy for the **iqn** names.

```
[root@centos7 ~]# targetcli
targetcli shell version 2.1.fb37
Copyright 2011-2013 by Datera, Inc and others.
For help on commands, type 'help'.
/> cd backstores/
/backstores> ls
o- backstores ......[...]
 o- block ...... [Storage Objects: 0]
 o- fileio ...... [Storage Objects: 0]
 o- pscsi ...... [Storage Objects: 0]
 o- ramdisk ...... [Storage Objects: 0]
/backstores> cd block
/backstores/block> ls
o- block ...... [Storage Objects: 0]
/backstores/block> create server1.disk1 /dev/sdb
Created block storage object server1.disk1 using /dev/sdb.
/backstores/block> ls
o- block ...... [Storage Objects: 1]
 o- server1.disk1 ...... [/dev/sdb (2.0GiB) write-thru deactivated]
/backstores/block> cd /iscsi
/iscsi> create iqn.2015-04.be.linux:iscsi1
Created target ign.2015-04.be.linux:iscsi1.
Created TPG 1.
Global pref auto_add_default_portal=true
Created default portal listening on all IPs (0.0.0.0), port 3260.
/iscsi> cd /iscsi/iqn.2015-04.be.linux:iscsi1/tpg1/acls
/iscsi/iqn.20...sil/tpg1/acls> create iqn.2015-04.be.linux:server2
Created Node ACL for iqn.2015-04.be.linux:server2
/iscsi/iqn.20...si1/tpg1/acls> cd iqn.2015-04.be.linux:server2
/iscsi/iqn.20...linux:server2> set auth userid=paul
Parameter userid is now 'paul'.
/iscsi/iqn.20...linux:server2> set auth password=hunter2
Parameter password is now 'hunter2'.
/iscsi/iqn.20...linux:server2> cd /iscsi/iqn.2015-04.be.linux:iscsi1/tpg1/luns
/iscsi/iqn.20...si1/tpg1/luns> create /backstores/block/server1.disk1
Created LUN 0->0 mapping in node ACL iqn.2015-04.be.linux:server2
s/scsi/iqn.20...si1/tpg1/luns> cd /iscsi/iqn.2015-04.be.linux:iscsi1/tpg1/portals
/iscsi/iqn.20.../tpg1/portals> create 192.168.1.128
Using default IP port 3260
Could not create NetworkPortal in configFS.
```

```
/iscsi/iqn.20.../tpg1/portals> cd /
/> ls
0- / ...... [...]
 o- block ...... [Storage Objects: 1]
  o- serverl.disk1 ...... [/dev/sdb (2.0GiB) write-thru activated]
  o- fileio ...... [Storage Objects: 0]
  o- pscsi ...... [Storage Objects: 0]
 o- ramdisk ...... [Storage Objects: 0]
 o- iscsi ...... [Targets: 1]
  o- iqn.2015-04.be.linux:iscsi1 ..... [TPGs: 1]
   o- tpg1 ..... [no-gen-acls, no-auth]
    o- acls ...... [ACLs: 1]
     o- iqn.2015-04.be.linux:server2 ..... [Mapped LUNs: 1]
      o- mapped_lun0 ...... [lun0 block/server1.disk1 (rw)]
    o- luns ...... [LUNs: 1]
    o-lun0 ...... [block/server1.disk1 (/dev/sdb)]
    o- portals ..... [Portals: 1]
     o- 0.0.0:3260 .....[OK]
 o- loopback ...... [Targets: 0]
/> saveconfig
Last 10 configs saved in /etc/target/backup.
Configuration saved to /etc/target/saveconfig.json
Global pref auto_save_on_exit=true
Last 10 configs saved in /etc/target/backup.
Configuration saved to /etc/target/saveconfig.json
[root@centos7 ~]#
```

Use the **systemd** tools to manage the service:

```
[root@centos7 ~]# systemctl enable target
ln -s '/usr/lib/systemd/system/target.service' '/etc/systemd/system/multi-user.target.wants/ta
[root@centos7 ~]# systemctl start target
[root@centos7 ~]#
```

Depending on your organisations policy, you may need to configure firewall and SELinux. The screenshot belows adds a firewall rule to allow all traffic over port 3260, and disables SELinux.

```
[root@centos7 ~]# firewall-cmd --permanent --add-port=3260/tcp
[root@centos7 ~]# firewall-cmd --reload
[root@centos7 ~]# setenforce 0
```

The total configuration is visible using **ls** from the root.

The iSCSI Target is now ready.

## 12.9. iSCSI Initiator RHEL7/CentOS7

This is identical to the RHEL6/CentOS6 procedure:

```
[root@centos7 ~]# yum install iscsi-initiator-utils
Loaded plugins: fastestmirror
...
...
Installed:
   iscsi-initiator-utils.x86_64 0:6.2.0.873-29.el7

Dependency Installed:
   iscsi-initiator-utils-iscsiuio.x86_64 0:6.2.0.873-29.el7
Complete!
```

Map your initiator name to the **targetcli** acl.

```
[root@centos7 ~]# cat /etc/iscsi/initiatorname.iscsi
InitiatorName=iqn.2015-04.be.linux:server2
[root@centos7 ~]#
```

Enter the CHAP authentication in /etc/iscsi/iscsid.conf.

```
[root@centos7 ~]# vi /etc/iscsi/iscsid.conf
...
[root@centos7 ~]# grep ^node.session.auth /etc/iscsi/iscsid.conf
node.session.auth.authmethod = CHAP
node.session.auth.username = paul
node.session.auth.password = hunter2
[root@centos7 ~]#
```

There are no extra devices yet...

```
[root@centos7 ~]# fdisk -1 | grep sd
Disk /dev/sda: 22.0 GB, 22038806528 bytes, 43044544 sectors
/dev/sda1 * 2048 1026047 512000 83 Linux
/dev/sda2 1026048 43042815 21008384 8e Linux LVM
Disk /dev/sdb: 2147 MB, 2147483648 bytes, 4194304 sectors
```

Enable the service and discover the target.

```
[root@centos7 ~]# systemctl enable iscsid
ln -s '/usr/lib/systemd/system/iscsid.service' '/etc/systemd/system/multi-user.target.wants/is
[root@centos7 ~]# iscsiadm -m discovery -t st -p 192.168.1.128
192.168.1.128:3260,1 iqn.2015-04.be.linux:iscsil
```

Log into the target and see /dev/sdc appear.

```
[root@centos7 ~]# iscsiadm -m node -T iqn.2015-04.be.linux:iscsi1 -p 192.168.1.128 -1
Logging in to [iface: default, target: iqn.2015-04.be.linux:iscsil, portal: 192.168.1.128,3260
Login to [iface: default, target: iqn.2015-04.be.linux:iscsi1, portal: 192.168.1.128,3260] suc
[root@centos7 ~]#
[root@centos7 ~]# fdisk -l | grep sd
Disk /dev/sda: 22.0 GB, 22038806528 bytes, 43044544 sectors
/dev/sda1 *
                    2048
                             1026047
                                          512000 83 Linux
/dev/sda2
                 1026048
                            43042815
                                        21008384
                                                   8e Linux LVM
Disk /dev/sdb: 2147 MB, 2147483648 bytes, 4194304 sectors
Disk /dev/sdc: 2147 MB, 2147483648 bytes, 4194304 sectors
[root@centos7 ~]#
```

# 12.10. practice: iSCSI devices

- 1. Set up a target (using an LVM and a SCSI device) and an initiator that connects to both.
- 2. Set up an iSCSI Target and Initiator on two CentOS7/RHEL7 computers with the following information:

Table 12.1. iSCSI Target and Initiator practice

| variable                 | value                   |
|--------------------------|-------------------------|
| Target Server IP         |                         |
| shared devices on target | /dev/sd /dev/sd /dev/sd |
| shared device name sd    |                         |
| shared device name sd    |                         |
| shared device name sd    |                         |
| target iqn               |                         |
| initiator iqn            |                         |
| username                 |                         |
| password                 |                         |

# 12.11. solution: iSCSI devices

1. Set up a target (using an LVM and a SCSI device) and an initiator that connects to both.

This solution was done on **Debian/ubuntu/Mint**. For RHEL/CentOS check the theory.

Decide (with a partner) on a computer to be the Target and another computer to be the Initiator.

#### On the Target computer:

First install iscsitarget using the standard tools for installing software in your distribution. Then use your knowledge from the previous chapter to setup a logical volume (/dev/vg/lvol0) and use the RAID chapter to setup /dev/md0. Then perform the following step:

```
vi /etc/default/iscsitarget (set enable to true)
```

Add your devices to /etc/iet/ietf.conf

```
root@debby6:/etc/iet# cat ietd.conf
Target iqn.2010-02.be.linux-training:storage.lun1
IncomingUser isuser hunter2
OutgoingUser
Lun 0 Path=/dev/vg/lvol0,Type=fileio
Alias LUN1
Target iqn.2010-02.be.linux-training:storage.lun2
IncomingUser isuser hunter2
OutgoingUser
Lun 0 Path=/dev/md0,Type=fileio
Alias LUN2
```

Add both devices to /etc/iet/initiators.allow

```
root@debby6:/etc/iet# cat initiators.allow
iqn.2010-02.be.linux-training:storage.lun1
iqn.2010-02.be.linux-training:storage.lun2
```

Now start the isositarget daemon and move over to the Initiator.

#### On the Initiator computer:

Install open-iscsi and start the daemon.

Then use **iscsiadm -m discovery -t st -p 'target-ip'** to see the iscsi devices on the Target.

Edit the files /etc/iscsi/nodes/ as shown in the book. Then restart the iSCSI daemon and rund fdisk -l to see the iSCSI devices.

2. Set up an iSCSI Target and Initiator on two CentOS7/RHEL7 computers with the following information:

Table 12.2. iSCSI Target and Initiator practice

| variable                 | value                                   |
|--------------------------|---|
| Target Server IP         | 192.168.1.143 (Adjust for your subnet!) |
| shared devices on target | /dev/sdb /dev/sdc /dev/sdd              |
| shared device name sdb   | target.disk1                            |
| shared device name sdc   | target.disk2                            |
| shared device name sdd   | target.disk3                            |
| target iqn               | iqn.2015-04.be.linux:target             |
| initiator iqn            | iqn.2015-04.be.linux:initiator          |
| username                 | paul                                    |
| password                 | hunter2                                 |

#### On the iSCSI Target server:

```
[root@centos7 ~]# targetcli
targetcli shell version 2.1.fb37
Copyright 2011-2013 by Datera, Inc and others.
For help on commands, type 'help'.
/> cd /backstores/block
/backstores/block> ls
o- block ...... [Storage Objects: 0]
/backstores/block> create target.disk1 /dev/sdb
Created block storage object target.disk1 using /dev/sdb.
/backstores/block> create target.disk2 /dev/sdc
Created block storage object target.disk2 using /dev/sdc.
/backstores/block> create target.disk3 /dev/sdd
Created block storage object target.disk3 using /dev/sdd.
/backstores/block> ls
o- block ...... [Storage Objects: 3]
 o- target.disk1 ...... [/dev/sdb (8.0GiB) write-thru deactivated]
 o- target.disk2 ..... [/dev/sdc (8.0GiB) write-thru deactivated]
 o- target.disk3 ...... [/dev/sdd (8.0GiB) write-thru deactivated]
/backstores/block> cd /iscsi
/iscsi> create iqn.2015-04.be.linux:target
Created target iqn.2015-04.be.linux:target.
Created TPG 1.
Global pref auto_add_default_portal=true
Created default portal listening on all IPs (0.0.0.0), port 3260.
/iscsi> cd /iscsi/iqn.2015-04.be.linux:target/tpg1/acls
/iscsi/iqn.20...get/tpg1/acls> create iqn.2015-04.be.linux:initiator
Created Node ACL for iqn.2015-04.be.linux:initiator
/iscsi/iqn.20...get/tpg1/acls> cd iqn.2015-04.be.linux:initiator
/iscsi/iqn.20...nux:initiator> pwd
/iscsi/iqn.2015-04.be.linux:target/tpg1/acls/iqn.2015-04.be.linux:initiator
/iscsi/iqn.20...nux:initiator> set auth userid=paul
Parameter userid is now 'paul'.
/iscsi/iqn.20...nux:initiator> set auth password=hunter2
Parameter password is now 'hunter2'.
/iscsi/iqn.20...nux:initiator> cd /iscsi/iqn.2015-04.be.linux:target/tpg1/
/iscsi/iqn.20...x:target/tpg1> ls
o- tpg1 ..... [no-gen-acls, no-auth]
 o- acls ...... [ACLs: 1]
| o- iqn.2015-04.be.linux:initiator ..... [Mapped LUNs: 0]
```

```
o- luns ..... [LUNs: 0]
 o- portals ...... [Portals: 1]
  /iscsi/iqn.20...x:target/tpg1> cd luns
/iscsi/iqn.20...get/tpg1/luns> create /backstores/block/target.disk1
Created LUN 0.
Created LUN 0->0 mapping in node ACL iqn.2015-04.be.linux:initiator
/iscsi/iqn.20...get/tpg1/luns> create /backstores/block/target.disk2
Created LUN 1.
Created LUN 1->1 mapping in node ACL iqn.2015-04.be.linux:initiator
/iscsi/iqn.20...get/tpg1/luns> create /backstores/block/target.disk3
Created LUN 2->2 mapping in node ACL iqn.2015-04.be.linux:initiator
s/scsi/iqn.20...get/tpg1/luns> cd /iscsi/iqn.2015-04.be.linux:target/tpg1/portals
/iscsi/iqn.20.../tpg1/portals> create 192.168.1.143
Using default IP port 3260
Could not create NetworkPortal in configFS.
/iscsi/iqn.20.../tpg1/portals> cd /
/> ls
o- / ...... [...]
 o- block ...... [Storage Objects: 3]
  o-target.disk1 ...... [/dev/sdb (8.0GiB) write-thru activated]
   o- target.disk2 ..... [/dev/sdc (8.0GiB) write-thru activated]
  o- fileio ...... [Storage Objects: 0]
  o- pscsi ...... [Storage Objects: 0]
 o- ramdisk ...... [Storage Objects: 0]
 o- iscsi ...... [Targets: 1]
  o- iqn.2015-04.be.linux:target ..... [TPGs: 1]
    o- tpg1 ..... [no-gen-acls, no-auth]
     o- acls ...... [ACLs: 1]
     o-iqn.2015-04.be.linux:initiator ............................ [Mapped LUNs: 3]
       o- mapped_lun0 ...... [lun0 block/target.disk1 (rw)]
       o- mapped_lun1 ..... [lun1 block/target.disk2 (rw)]
       o- mapped_lun2 ..... [lun2 block/target.disk3 (rw)]
     o- luns ...... [LUNs: 3]
     o-lun0 ...... [block/target.disk1 (/dev/sdb)]
      o- lun1 ...... [block/target.disk2 (/dev/sdc)]
     | o- lun2 ..... [block/target.disk3 (/dev/sdd)]
     o- portals ...... [Portals: 1]
      o- 0.0.0.0:3260 ......[OK]
 o- loopback ...... [Targets: 0]
/> exit
Global pref auto_save_on_exit=true
Last 10 configs saved in /etc/target/backup.
Configuration saved to /etc/target/saveconfig.json
[root@centos7 ~]# systemctl enable target
ln -s '/usr/lib/systemd/system/target.service' '/etc/systemd/system/multi-user.target.wants/ta
[root@centos7 ~]# systemctl start target
[root@centos7 ~]# setenforce 0
```

#### On the Initiator:

```
[root@centos7 ~]# cat /etc/iscsi/initiatorname.iscsi
InitiatorName=iqn.2015-04.be.linux:initiator
[root@centos7 ~]# vi /etc/iscsi/iscsid.conf
[root@centos7 ~]# grep ^node.session.au /etc/iscsi/iscsid.conf
node.session.auth.authmethod = CHAP
node.session.auth.username = paul
node.session.auth.password = hunter2
[root@centos7 ~]# fdisk -1 2>/dev/null | grep sd
Disk /dev/sda: 22.0 GB, 22038806528 bytes, 43044544 sectors
/dev/sda1 * 2048 1026047 512000 83 Linux
```

```
1026048 43042815 21008384 8e Linux LVM
/dev/sda2
Disk /dev/sdb: 8589 MB, 8589934592 bytes, 16777216 sectors
                  2048
                            821247 409600 83 Linux
                                       409600 83 Linux
                 821248
                            1640447
/dev/sdb3
                 1640448
                            2459647
                                        409600 83 Linux
Disk /dev/sdc: 8589 MB, 8589934592 bytes, 16777216 sectors
Disk /dev/sdd: 8589 MB, 8589934592 bytes, 16777216 sectors
Disk /dev/sde: 2147 MB, 2147483648 bytes, 4194304 sectors
Disk /dev/sdf: 2147 MB, 2147483648 bytes, 4194304 sectors
[root@centos7 ~]# systemctl enable iscsid
ln -s '/usr/lib/systemd/system/iscsid.service' '/etc/systemd/system/multi-user.target.wants/is
[root@centos7 ~]# iscsiadm -m node -T iqn.2015-04.be.linux:target -p 192.168.1.143 -1
Logging in to [iface: default, target: iqn.2015-04.be.linux:target, portal: 192.168.1.143,3260
Login to [iface: default, target: iqn.2015-04.be.linux:target, portal: 192.168.1.143,3260] suc
[root@centos7 ~]# fdisk -l 2>/dev/null | grep sd
Disk /dev/sda: 22.0 GB, 22038806528 bytes, 43044544 sectors
/dev/sda1 *
                  2048
                           1026047 512000 83 Linux
                1026048
/dev/sda2
                           43042815
                                      21008384
                                                8e Linux LVM
Disk /dev/sdb: 8589 MB, 8589934592 bytes, 16777216 sectors
/dev/sdb1
                  2048 821247 409600 83 Linux
                                                83 Linux
/dev/sdb2
                 821248
                            1640447
                                        409600
/dev/sdb3
                 1640448
                            2459647
                                        409600
                                                 83 Linux
Disk /dev/sdc: 8589 MB, 8589934592 bytes, 16777216 sectors
Disk /dev/sdd: 8589 MB, 8589934592 bytes, 16777216 sectors
Disk /dev/sde: 2147 MB, 2147483648 bytes, 4194304 sectors
Disk /dev/sdf: 2147 MB, 2147483648 bytes, 4194304 sectors
Disk /dev/sdg: 8589 MB, 8589934592 bytes, 16777216 sectors
Disk /dev/sdh: 8589 MB, 8589934592 bytes, 16777216 sectors
Disk /dev/sdi: 8589 MB, 8589934592 bytes, 16777216 sectors
[root@centos7 ~]#
```

# Chapter 13. introduction to multipathing

# 13.1. install multipath

RHEL and CentOS need the device-mapper-multipath package.

```
yum install device-mapper-multipath
```

This will create a sample multipath.conf in /usr/share/doc/device-mapper-multipath-0.4.9/multipath.conf.

There is no /etc/multipath.conf until you initialize it with mpathconf.

# 13.2. configure multipath

You can now choose to either edit /etc/multipath.conf or use mpathconf to change this file for you.

```
[root@server2 ~]# grep user_friendly_names /etc/multipath.conf
user_friendly_names yes
# user_friendly_names yes
[root@server2 ~]# mpathconf --enable --user_friendly_names n
[root@server2 ~]# grep user_friendly_names /etc/multipath.conf
user_friendly_names no
# user_friendly_names yes
[root@server2 ~]# mpathconf --enable --user_friendly_names y
[root@server2 ~]# grep user_friendly_names /etc/multipath.conf
user_friendly_names yes
# user_friendly_names yes
```

### 13.3. network

This example uses three networks, make sure the iSCSI Target is connected to all three networks.

The same must be true for the multipath Initiator:

Test the triple discovery in three networks (screenshot newer than above).

```
[root@centos7 ~]# iscsiadm -m discovery -t st -p 192.168.1.150
192.168.1.150:3260,1 iqn.2015-04.be.linux:target1
[root@centos7 ~]# iscsiadm -m discovery -t st -p 192.168.2.150
192.168.2.150:3260,1 iqn.2015-04.be.linux:target1
[root@centos7 ~]# iscsiadm -m discovery -t st -p 192.168.3.150
192.168.3.150:3260,1 iqn.2015-04.be.linux:target1
```

# 13.4. start multipathd and iscsi

Time to start (or restart) both the multipathd and iscsi services:

```
[root@server2 ~]# service multipathd restart
Stopping multipathd daemon: [ OK ]
Starting multipathd daemon: [ OK ]
[root@server2 ~]# service iscsi restart
Stopping iscsi: [ OK ]
Starting iscsi: [ OK ]
```

This shows **fdisk** output when leaving the default friendly\_names option to yes. The bottom three are the multipath devices to use.

```
[root@server2 ~]# fdisk -l | grep Disk
Disk /dev/sda: 42.9 GB, 42949672960 bytes
Disk identifier: 0x0004f229
Disk /dev/sdb: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdc: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdd: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sde: 2147 MB, 2147483648 bytes
Disk identifier: 0x00000000
Disk /dev/sdf: 2147 MB, 2147483648 bytes
Disk identifier: 0x00000000
Disk /dev/sdg: 2147 MB, 2147483648 bytes
Disk identifier: 0x00000000
Disk /dev/mapper/VolGroup-lv_root: 41.4 GB, 41448112128 bytes
Disk identifier: 0x00000000
Disk /dev/mapper/VolGroup-lv_swap: 973 MB, 973078528 bytes
Disk identifier: 0x00000000
Disk /dev/sdh: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdi: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdj: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdl: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdn: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdk: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdm: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdp: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/sdo: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/mapper/mpathh: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/mapper/mpathi: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
Disk /dev/mapper/mpathj: 1073 MB, 1073741824 bytes
Disk identifier: 0x00000000
[root@server2 ~]#
```

# 13.5. multipath list

You can list the multipath connections and devices with **multipath -ll**.

```
[root@server2 ~]# multipath -11
mpathj (1IET
                00010001) dm-4 Reddy, VBOX HARDDISK
size=1.0G features='0' hwhandler='0' wp=rw
|-+- policy='round-robin 0' prio=1 status=active
   - 13:0:0:1 sdh 8:112 active ready running
|-+- policy='round-robin 0' prio=1 status=enabled
| `- 12:0:0:1 sdi 8:128 active ready running
 -+- policy='round-robin 0' prio=1 status=enabled
  `- 14:0:0:1 sdm 8:192 active ready running
mpathi (1IET 00010003) dm-3 Reddy, VBOX HARDDISK
size=1.0G features='0' hwhandler='0' wp=rw
|-+- policy='round-robin 0' prio=1 status=active
 `- 13:0:0:3 sdk 8:160 active ready running
|-+- policy='round-robin 0' prio=1 status=enabled
 `- 12:0:0:3 sdn 8:208 active ready running
 -+- policy='round-robin 0' prio=1 status=enabled
 `- 14:0:0:3 sdp 8:240 active ready running
mpathh (1IET 00010002) dm-2 Reddy, VBOX HARDDISK
size=1.0G features='0' hwhandler='0' wp=rw
|-+- policy='round-robin 0' prio=1 status=active
 `- 12:0:0:2 sdl 8:176 active ready running
|-+- policy='round-robin 0' prio=1 status=enabled
`- 13:0:0:2 sdj 8:144 active ready running
 -+- policy='round-robin 0' prio=1 status=enabled
 `- 14:0:0:2 sdo 8:224 active ready running
[root@server2 ~]#
```

The IET (iSCSI Enterprise Target) ID should match the ones you see on the Target server.

```
[root@server1 ~]# tgt-admin -s | grep -e LUN -e IET -e dev
   LUN information:
       LUN: 0
           SCSI ID: IET
                            00010000
       LUN: 1
           SCSI ID: IET
                            00010001
           Backing store path: /dev/sdb
       TJIN: 2
           SCSI ID: IET
                            00010002
           Backing store path: /dev/sdc
       LUN: 3
           SCSI ID: IET
                            00010003
           Backing store path: /dev/sdd
```

# 13.6. using the device

The rest is standard mkfs, mkdir, mount:

```
[root@server2 ~]# mkfs.ext4 /dev/mapper/mpathi
mke2fs 1.41.12 (17-May-2010)
Filesystem label=
OS type: Linux
Block size=4096 (log=2)
Fragment size=4096 (log=2)
Stride=0 blocks, Stripe width=0 blocks
65536 inodes, 262144 blocks
13107 blocks (5.00%) reserved for the super user
First data block=0
Maximum filesystem blocks=268435456
8 block groups
32768 blocks per group, 32768 fragments per group
8192 inodes per group
Superblock backups stored on blocks:
32768, 98304, 163840, 229376
Writing inode tables: done
Creating journal (8192 blocks): done
Writing superblocks and filesystem accounting information: done
This filesystem will be automatically checked every 38 mounts or
180 days, whichever comes first. Use tune2fs -c or -i to override.
[root@server2 ~]# mkdir /srv/multipath
[root@server2 ~]# mount /dev/mapper/mpathi /srv/multipath/
[root@server2 ~]# df -h /srv/multipath/
                    Size Used Avail Use% Mounted on
/dev/mapper/mpathi 1008M 34M 924M 4% /srv/multipath
```

# 13.7. practice: multipathing

- 1. Find a partner and decide who will be iSCSI Target and who will be iSCSI Initiator and Multipather. Set up Multipath as we did in the theory.
- 2. Uncomment the big 'defaults' section in /etc/multipath.conf and disable friendly names. Verify that multipath can work. You may need to check the manual for /lib/dev/scsi\_id and for multipath.conf.

# 13.8. solution: multipathing

1. Find a partner and decide who will be iSCSI Target and who will be iSCSI Initiator and Multipather. Set up Multipath as we did in the theory.

```
Look in the theory...
```

2. Uncomment the big 'defaults' section in /etc/multipath.conf and disable friendly names. Verify that multipath can work. You may need to check the manual for /lib/dev/scsi\_id and for multipath.conf.

```
vi multipath.conf
remove # for the big defaults section
add # for the very small one with friendly_names active
add the --replace-whitespace option to scsi_id.
defaults {
       udev_dir
                                /dev
       polling_interval
path_selector
                               10
                               "round-robin 0"
       path_grouping_policy multibus
       getuid_callout
                                "/lib/udev/scsi_id --whitelisted --replace\
-whitespace --device=/dev/%n"
       prio
                                const
       path_checker
                                readsector0
       rr_min_io
                                100
       \max_{fds}
                               8192
       rr_weight
                               priorities
       failback
                               immediate
       no_path_retry
                               fail
       user_friendly_names
                                no
```

The names now (after service restart) look like:

```
root@server2 etc]# multipath -ll
1IET_00010001 dm-8 Reddy, VBOX HARDDISK
size=1.0G features='0' hwhandler='0' wp=rw
`-+- policy='round-robin 0' prio=1 status=active
 |- 17:0:0:1 sdh 8:112 active ready running
  |- 16:0:0:1 sdi 8:128 active ready running
   - 15:0:0:1 sdn 8:208 active ready running
1IET_00010003 dm-10 Reddy, VBOX HARDDISK
size=1.0G features='0' hwhandler='0' wp=rw
 -+- policy='round-robin 0' prio=1 status=active
  |- 17:0:0:3 sdl 8:176 active ready running
  |- 16:0:0:3 sdm 8:192 active ready running
  `- 15:0:0:3 sdp 8:240 active ready running
1IET_00010002 dm-9 Reddy, VBOX HARDDISK
size=1.0G features='0' hwhandler='0' wp=rw
 -+- policy='round-robin 0' prio=1 status=active
 |- 17:0:0:2 sdj 8:144 active ready running
  |- 16:0:0:2 sdk 8:160 active ready running
  `- 15:0:0:2 sdo 8:224 active ready running
```

### Did you blacklist your own devices ?



# **Table of Contents**

| 14. bootloader                      | 157 |
|-------------------------------------|-----|
| 14.1. boot terminology              | 158 |
| 14.2. grub                          | 161 |
| 14.3. grub2                         | 166 |
| 14.4. lilo                          | 167 |
| 14.5. practice: bootloader          | 168 |
| 14.6. solution: bootloader          |     |
| 15. init and runlevels              |     |
| 15.1. system init(ialization)       | 171 |
| 15.2. daemon or demon?              | 176 |
| 15.3. starting and stopping daemons |     |
| 15.4. chkconfig                     | 177 |
| 15.5. update-rc.d                   | 179 |
| 15.6. bum                           | 180 |
| 15.7. runlevels                     |     |
| 15.8. systemd                       | 183 |
| 15.9. practice: init                |     |
| 15.10. solution: init               | 190 |

# Chapter 14. bootloader

This chapter briefly discusses the boot sequence of an (Intel 32-bit or 64-bit) Linux computer.

Systems booting with **lilo** are rare nowadays, so this section is brief.

The most common bootloader on Linux systems today is **grub**, yet this is not a Linux project. Distributions like **FreeBSD** and **Solaris** also use **grub**.

Likewise, grub is not limited to Intel architecture. It can also load kernels on PowerPC.

Note that **grub**, while still the default in Debian, is slowly being replaced in most distributions with **grub2**.

# 14.1. boot terminology

The exact order of things that happen when starting a computer system, depends on the hardware architecture (**Intel x86** is different from **Sun Sparc** etc), on the boot loader (**grub** is different from **lilo**) and on the operating system (**Linux**, **Solaris**, **BSD** etc). Most of this chapter is focused on booting **Linux** on **Intel x86** with **grub**.


### 14.1.1. post

A computer starts booting the moment you turn on the power (no kidding). This first process is called **post** or **power on self test**. If all goes well then this leads to the **bios**. If all goes not so well, then you might hear nothing, or hear beeping, or see an error message on the screen, or maybe see smoke coming out of the computer (burning hardware smells bad!).

#### 14.1.2. bios

All **Intel x86** computers will have a **basic input/output system** or **bios** to detect, identify and initialize hardware. The **bios** then goes looking for a **boot device**. This can be a floppy, hard disk, cdrom, network card or usb drive.

During the **bios** you can see a message on the screen telling you which key (often **Del** or **F2**) to press to enter the **bios** setup.



### 14.1.3. openboot


Sun **sparc** systems start with **openboot** to test the hardware and to boot the operating system. **Bill Callkins** explains **openboot** in his Solaris System Administration books. The details of **openboot** are not the focus of this course.

### 14.1.4. boot password

The **bios** allows you to set a password. Do not forget this password, or you will have to open up the hardware to reset it. You can sometimes set a password to boot the system, and another password to protect the **bios** from being modified.

#### 14.1.5. boot device

The **bios** will look for a **boot device** in the order configured in the bios setup. Usually an operating system on a production server boots of a hard disk.



#### 14.1.6. master boot record

The **master boot record** or **mbr** is the first sector of a hard disk. The partitioning of a disk in **primary** partitions, and the active partition are defined in the **mbr**.

The **mbr** is 512 bytes long and can be copied with **dd**.

```
dd if=/dev/sda of=bootsect.mbr count=1 bs=512
```

#### 14.1.7. bootloader

The **mbr** is executed by the **bios** and contains either (a small) **bootloader** or code to load a **bootloader**.

Looking at the **mbr** with **od** can reveal information about the **bootloader**.

```
paul@laika:~$ sudo dd if=/dev/sda count=1 bs=16 skip=24 2>/dev/null|od -c 0000000 376 G R U B \0 G e o m \0 H a r d 0000020
```

There are a variety of bootloaders available, most common on **Intel** architecture is **grub**, which is replacing **lilo** in many places. When installing **Linux** on **sparc** architecture, you can choose **silo**, **Itanium** systems can use **elilo**, **IBM S/390** and **zSeries** use **z/IPL**, **Alpha** uses **milo** and **PowerPC** architectures use **yaboot** (yet another boot loader).

Bootable cd's and dvd's often use **syslinux**.

### 14.1.8. kernel

The goal of all this is to load an operating system, or rather the **kernel** of an operating system. A typical bootloader like **grub** will copy a kernel from hard disk to memory, and will then hand control of the computer to the kernel (execute the kernel).

Once the Linux kernel is loaded, the bootloader turns control over to it. From that moment on, the kernel is in control of the system. After discussing bootloaders, we continue with the **init system** that starts all the daemons.

# 14.2. grub

### 14.2.1. /boot/grub/grub.cfg

Debian switched to **grub2**, which will be discussed in the next section. The main boot menu configuration file for **grub2** is **grub.cfg**.

```
root@debian7:~# ls -l /boot/grub/grub.cfg
-r--r-- 1 root root 2453 May 13 17:22 /boot/grub/grub.cfg
root@debian7:~#
```

### 14.2.2. /boot/grub/grub.conf

Distributions like Red Hat Enterprise Linux 6 use **grub.conf** and provide a symbolic link from **/boot/grub/menu.lst** and from **/etc/grub.conf** to this file.

```
[root@centos65 ~]# ls -l /boot/grub/menu.lst
lrwxrwxrwx. 1 root root 11 Mar 7 11:53 /boot/grub/menu.lst -> ./grub.conf
[root@centos65 ~]# ls -l /boot/grub/grub.conf
-rw-----. 1 root root 1189 May 5 11:47 /boot/grub/grub.conf
[root@centos65 ~]#
```

The file currently (RHEL 6.5) looks like this:

```
[root@centos65 ~]# more /boot/grub/grub.conf
# grub.conf generated by anaconda
# Note that you do not have to rerun grub after making changes to this file
# NOTICE: You have a /boot partition. This means that
          all kernel and initrd paths are relative to /boot/, eg.
#
          root (hd0,0)
#
          kernel /vmlinuz-version ro root=/dev/mapper/VolGroup-lv_root
           initrd /initrd-[generic-]version.img
#boot=/dev/sda
default=0
timeout=5
splashimage=(hd0,0)/grub/splash.xpm.gz
hiddenmenu
title CentOS (2.6.32-431.11.2.el6.x86_64)
       root (hd0,0)
        kernel /vmlinuz-2.6.32-431.11.2.el6.x86_64 ro root=/dev/mapper/VolGr\
oup-lv_root rd_NO_LUKS LANG=en_US.UTF-8 rd_NO_MD rd_LVM_LV=VolGroup/lv_swap \
SYSFONT=latarcyrheb-sun16 crashkernel=auto rd_LVM_LV=VolGroup/lv_root KEYBO\
ARDTYPE=pc KEYTABLE=us rd_NO_DM rhgb quiet
        initrd /initramfs-2.6.32-431.11.2.el6.x86_64.img
title CentOS (2.6.32-431.el6.x86_64)
        root (hd0,0)
        kernel /vmlinuz-2.6.32-431.el6.x86_64 ro root=/dev/mapper/VolGroup-l\
v_root rd_NO_LUKS LANG=en_US.UTF-8 rd_NO_MD rd_LVM_LV=VolGroup/lv_swap SYSFO\
NT=latarcyrheb-sun16 crashkernel=auto rd_LVM_LV=VolGroup/lv_root KEYBOARDTY\
PE=pc KEYTABLE=us rd_NO_DM rhqb quiet
        initrd /initramfs-2.6.32-431.el6.x86_64.img
[root@centos65 ~]#
```

### 14.2.3. menu commands

The **menu commands** must be at the top of **grub**'s configuration file.

#### default

The **default** command sets a default **entry** to start. The first **entry** has number 0.

default=0

Each entry or **stanza** starts with a **title** directive.

#### fallback

In case the **default** does not boot, use the **fallback** entry instead.

fallback=1

#### timeout

The **timeout** will wait a number of seconds before booting the **default** entry.

timeout=5

#### hiddenmenu

The **hiddenmenu** will hide the **grub** menu unless the user presses **Esc** before the **timeout** expires.

hiddenmenu

#### title

With **title** we can start a new **entry** or **stanza**.

```
title CentOS (2.6.32-431.11.2.el6.x86_64)
```

### password

You can add a **password** to prevent interactive selection of a boot environment while **grub** is running.

```
password --md5 $1$Ec.id/$T2C2ahI/EG3WRRsmmu/HN/
```

Use the **grub** interactive shell to create the password hash.

```
grub> md5crypt

Password: *******
Encrypted: $1$Ec.id/$T2C2ahI/EG3WRRsmmu/HN/
```

#### 14.2.4. stanza commands

Every **operating system** or **kernel** that you want to boot with **grub** will have a **stanza** aka an **entry** of a couple of lines. Listed here are some of the common **stanza** commands.

#### boot

Technically the **boot** command is only mandatory when running the **grub command line**. This command does not have any parameters and can only be set as the last command of a stanza.

boot.

#### kernel

The **kernel** command points to the location of the kernel. To boot Linux this means booting a **gzip** compressed **zImage** or **bzip2** compressed **bzImage**.

This screenshot shows a kernel command used to load a Debian kernel.

```
kernel /boot/vmlinuz-2.6.17-2-686 root=/dev/hda1 ro
```

And this is how RHEL 5 uses the **kernel** command.

```
kernel /vmlinuz-2.6.18-128.el5 ro root=/dev/VolGroup00/LogVol00 rhgb quiet
```

All parameters in the kernel line can be read by the kernel itself or by any other program (which are started later) by reading /proc/cmdline

#### initrd

Many **Linux** installations will need an **initial ramdisk** at boot time. This can be set in **grub** with the **initrd** command.

Here a screenshot of Debian 4.0

```
initrd /boot/initrd.img-2.6.17-2-686
```

And the same for Red Hat Enterprise Linux 5

```
initrd /initrd-2.6.18-128.el5.img
```

#### root

The **root** command accepts the root device as a parameter.

The **root** command will point to the hard disk and partition to use, with **hd0** as the first hard disk device and **hd1** as the second hard disk device. The same numbering is used for partitions, so **hd0,0** is the first partition on the first disk and **hd0,1** is the second partition on that disk.

```
root (hd0,0)
```

#### savedefault

The **savedefault** command can be used together with **default saved** as a menu command. This combination will set the currently booted stanza as the next default stanza to boot.

```
default saved
timeout 10

title Linux
root (hd0,0)
kernel /boot/vmlinuz
savedefault

title DOS
root (hd0,1)
makeactive
chainloader +1
savedefault
```

## 14.2.5. chainloading

With **grub** booting, there are two choices: loading an operating system or **chainloading** another bootloader. The **chainloading** feature of grub loads the bootsector of a partition (that contains an operating system).

Some older operating systems require a **primary partition** that is set as **active**. Only one partition can be set **active** so **grub** can do this on the fly just before **chainloading**.

This screenshot shows how to set the first primary partition active with grub.

```
root (hd0,0)
makeactive
```

Chainloading refers to grub loading another operating system's bootloader. The **chainloader** switch receives one option: the number of sectors to read and boot. For **DOS** and **OS/2** one sector is enough. Note that **DOS** requires the boot/root partition to be active!

Here is a complete example to **chainload** an old operating system.

```
title MS-DOS 6.22
root (hd0,1)
makeactive
chainloader +1
```

### 14.2.6. simple stanza examples

This is a screenshot of a **Debian 4** stanza.

```
title Debian GNU/Linux, kernel 2.6.17-2-686
root (hd0,0)
kernel /boot/vmlinuz-2.6.17-2-686 root=/dev/hda1 ro
initrd /boot/initrd.img-2.6.17-2-686
```

Here a screenshot of a **Red Hat Enterprise Linux 5** stanza.

```
title Red Hat Enterprise Linux Server (2.6.18-128.el5)
root (hd0,0)
kernel /vmlinuz-2.6.18-98.el5 ro root=/dev/VolGroup00/LogVol00 rhgb quiet
initrd /initrd-2.6.18-98.el5.img
```

# 14.2.7. editing grub at boot time

At boot time, when the **grub** menu is displayed, you can type **e** to edit the current stanza. This enables you to add parameters to the kernel.

One such parameter, useful when you lost the root password, is **single**. This will boot the kernel in single user mode (although some distributions will still require you to type the root password.

```
kernel /boot/vmlinuz-2.6.17-2-686 root=/dev/hda1 ro single
```

Another option to reset a root password is to use an **init=/bin/bash** parameter.

```
kernel /boot/vmlinuz-2.6.17-2-686 root=/dev/hda1 ro init=/bin/bash
```

Note that some distributions will disable this option at kernel compile time.

# 14.2.8. installing grub

Run the **grub-install** command to install **grub**. The command requires a destination for overwriting the **boot sector** or **mbr**.

```
# grub-install /dev/hda
```

You will rarely have to do this manually, since grub is installed when installing the operating system and does not need any re-install when changing configuration (as is the case for **lilo**).

# 14.3. grub2

### 14.3.1. grub 2.0?

The main configuration file is now /boot/grub/grub.cfg. And while this file may look familiar, one should never edit this file directly (because it is generated!).

```
root@debian7:~# ls -l /boot/grub/grub.cfg
-r--r-- 1 root root 2453 May 13 17:22 /boot/grub/grub.cfg
root@debian7:~# head -3 /boot/grub/grub.cfg
#
# DO NOT EDIT THIS FILE
#
```

### 14.3.2. /etc/grub.d/40\_custom

The /etc/grub.d/40\_custom file can be changed to include custom entries. These entries are automatically added to grub.

```
root@debian7:~# ls -l /etc/grub.d/40_custom
-rwxr-xr-x l root root 214 Jul 3 2013 /etc/grub.d/40_custom
root@debian7:~# cat /etc/grub.d/40_custom
#!/bin/sh
exec tail -n +3 $0
# This file provides an easy way to add custom menu entries. Simply type the
# menu entries you want to add after this comment. Be careful not to change
# the 'exec tail' line above.
```

# 14.3.3. /etc/default/grub

The new configuration file for changing grub is now /etc/default/grub.

```
root@debian7:~# head /etc/default/grub
# If you change this file, run 'update-grub' afterwards to update
# /boot/grub/grub.cfg.
# For full documentation of the options in this file, see:
# info -f grub -n 'Simple configuration'

GRUB_DEFAULT=0
GRUB_TIMEOUT=5
GRUB_DISTRIBUTOR=`lsb_release -i -s 2> /dev/null || echo Debian`
GRUB_CMDLINE_LINUX_DEFAULT="quiet"
GRUB_CMDLINE_LINUX="debian-installer=en_US"
```

# 14.3.4. update-grub

Whenever the /etc/default/grub file is changed, you will need to run update-grub to apply the changes.

```
root@debian7:~# vi /etc/default/grub
root@debian7:~# update-grub
Generating grub.cfg ...
Found linux image: /boot/vmlinuz-3.2.0-4-amd64
Found initrd image: /boot/initrd.img-3.2.0-4-amd64
done
```

# 14.4. lilo

### 14.4.1. Linux loader

**lilo** used to be the most used Linux bootloader, but is steadily being replaced with **grub** and recently **grub2**.

### 14.4.2. lilo.conf

Here is an example of a **lilo.conf** file. The **delay** switch receives a number in tenths of a second. So the delay below is three seconds, not thirty!

```
boot = /dev/hda
delay = 30

image = /boot/vmlinuz
  root = /dev/hda1
  label = Red Hat 5.2

image = /boot/vmlinuz
  root = /dev/hda2
  label = S.U.S.E. 8.0

other = /dev/hda4
  table = /dev/hda
  label = MS-DOS 6.22
```

The configration file shows three example stanzas. The first one boots Red Hat from the first partition on the first disk (hda1). The second stanza boots Suse 8.0 from the next partition. The last one loads MS-DOS.

# 14.5. practice: bootloader

- 0. Find out whether your system is using lilo, grub or grub2. Only do the practices that are appropriate for your system.
- 1. Make a copy of the kernel, initrd and System.map files in /boot. Put the copies also in / boot but replace 2.x or 3.x with 4.0 (just imagine that Linux 4.0 is out.).
- 2. Add a stanza in grub for the 4.0 files. Make sure the title is different.
- 3. Set the boot menu timeout to 30 seconds.
- 4. Reboot and test the new stanza.

# 14.6. solution: bootloader

- 0. Find out whether your system is using lilo, grub or grub2. Only do the practices that are appropriate for your system.
- 1. Make a copy of the kernel, initrd and System.map files in /boot. Put the copies also in / boot but replace 2.x or 3.x with 4.0 (just imagine that Linux 4.0 is out.).

```
[root@centos65 boot]# uname -r
2.6.32-431.11.2.el6.x86_64
[root@centos65 boot]# cp System.map-2.6.32-431.11.2.el6.x86_64 System.map-4.0
[root@centos65 boot]# cp vmlinuz-2.6.32-431.11.2.el6.x86_64 vmlinuz-4.0
[root@centos65 boot]# cp initramfs-2.6.32-431.11.2.el6.x86_64.img initramfs-4.0\
.img
```

Do not forget that the initrd (or initramfs) file ends in .img.

2. Add a stanza in grub for the 4.0 files. Make sure the title is different.

3. Set the boot menu timeout to 30 seconds.

```
[root@centos65 grub]# vi menu.lst
[root@centos65 grub]# grep timeout /boot/grub/grub.conf
timeout=30
```

4. Reboot and test the new stanza.

[root@centos65 grub]# reboot

```
GNU GRUB version 0.97 (639K lower / 490432K upper memory)

CentOS (4.0)
CentOS (2.6.32-431.11.2.el6.x86_64)
CentOS (2.6.32-431.el6.x86_64)
```

Select your stanza and if it boots then you did it correct.

# Chapter 15. init and runlevels

Many Unix and Linux distributions use **init** scripts to start daemons in the same way that **Unix System V** did. This chapter will explain in detail how that works.

Init starts daemons by using scripts, where each script starts one daemon, and where each script waits for the previous script to finish. This serial process of starting daemons is slow, and although slow booting is not a problem on servers where uptime is measured in years, the recent uptake of Linux on the desktop results in user complaints.

To improve Linux startup speed, **Canonical** has developed **upstart**, which was first used in Ubuntu. Solaris also used **init** up to Solaris 9, for Solaris 10 **Sun** developed **Service Management Facility**. Both systems start daemons in parallel and can replace the SysV init scripts. There is also an ongoing effort to create **initng** (init next generation).

In 2014 the **systemd** initiative has taken a lead when after Fedora, RHEL7 and CentOS7 also Debian has chosen this to be the prefered replacement for init. The end of this module contains an introduction to **systemd**.

# 15.1. system init(ialization)

### 15.1.1. process id 1

The kernel receives system control from the bootloader. After a while the kernel starts the **init daemon**. The **init** daemon (/**sbin/init**) is the first daemon that is started and receives **process id 1** (PID 1). **Init** never dies.

### 15.1.2. configuration in /etc/inittab

When /sbin/init is started, it will first read its configuration file /etc/inittab. In that file, it will look for the value of initdefault (3 in the screenshot below).

```
[paul@rhel4 ~]$ grep ^id /etc/inittab
id:3:initdefault:
```

#### 15.1.3. initdefault

The value found in **initdefault** indicates the default **runlevel**. Some Linux distributions have a brief description of runlevels in /etc/inittab, like here on Red Hat Enterprise Linux 4.

```
# Default runlevel. The runlevels used by RHS are:
# 0 - halt (Do NOT set initdefault to this)
# 1 - Single user mode
# 2 - Multiuser, without NFS (The same as 3, if you don't have network)
# 3 - Full multiuser mode
# 4 - unused
# 5 - X11
# 6 - reboot (Do NOT set initdefault to this)
```

**Runlevel 0** means the system is shutting down. **Runlevel 1** is used for troubleshooting, only the root user can log on, and only at the console. **Runlevel 3** is typical for servers, whereas **runlevel 5** is typical for desktops (graphical logon). Besides runlevels 0, 1 and 6, the use may vary depending on the distribution. Debian and derived Linux systems have full network and GUI logon on runlevels 2 to 5. So always verify the proper meaning of runlevels on your system.

### 15.1.4. sysinit script

### /etc/rc.d/rc.sysinit

The next line in /etc/inittab in Red Hat and derivatives is the following.

```
si::sysinit:/etc/rc.d/rc.sysinit
```

This means that independent of the selected runlevel, **init** will run the /etc/rc.d/rc.sysinit script. This script initializes hardware, sets some basic environment, populates /etc/mtab while mounting file systems, starts swap and more.

```
[paul@rhel ~]$ egrep -e"^# Ini" -e"^# Sta" -e"^# Che" /etc/rc.d/rc.sysinit
# Check SELinux status
# Initialize hardware
# Start the graphical boot, if necessary; /usr may not be mounted yet...
# Initialiaze ACPI bits
# Check filesystems
# Start the graphical boot, if necessary and not done yet.
# Check to see if SELinux requires a relabel
# Initialize pseudo-random number generator
# Start up swapping.
# Initialize the serial ports.
```

That egrep command could also have been written with grep like this:

```
grep "^# \(Ini\|Sta\|Che\)".
```

#### /etc/init.d/rcS

Debian has the following line after **initdefault**.

```
si::sysinit:/etc/init.d/rcS
```

The /etc/init.d/rcS script will always run on Debian (independent of the selected runlevel). The script is actually running all scripts in the /etc/rcS.d/ directory in alphabetical order.

```
root@barry:~# cat /etc/init.d/rcS
#! /bin/sh
#
# rcS
#
# Call all S??* scripts in /etc/rcS.d/ in numerical/alphabetical order
#
exec /etc/init.d/rc S
```

### 15.1.5. rc scripts

Init will continue to read /etc/inittab and meets this section on Debian Linux.

```
10:0:wait:/etc/init.d/rc 0
11:1:wait:/etc/init.d/rc 1
12:2:wait:/etc/init.d/rc 2
13:3:wait:/etc/init.d/rc 3
14:4:wait:/etc/init.d/rc 4
15:5:wait:/etc/init.d/rc 5
16:6:wait:/etc/init.d/rc 6
```

On Red Hat Enterprise Linux it is identical except **init.d** is **rc.d**.

```
10:0:wait:/etc/rc.d/rc 0
11:1:wait:/etc/rc.d/rc 1
12:2:wait:/etc/rc.d/rc 2
13:3:wait:/etc/rc.d/rc 3
14:4:wait:/etc/rc.d/rc 4
15:5:wait:/etc/rc.d/rc 5
16:6:wait:/etc/rc.d/rc 6
```

In both cases, this means that **init** will start the rc script with the runlevel as the only parameter. Actually /etc/inittab has fields separated by colons. The second field determines the runlevel in which this line should be executed. So in both cases, only one line of the seven will be executed, depending on the runlevel set by **initdefault**.

### 15.1.6. rc directories

When you take a look any of the /etc/rcX.d/ directories, then you will see a lot of (links to) scripts who's name start with either uppercase K or uppercase S.

```
[root@RHEL52 rc3.d]# ls -l | tail -4
lrwxrwxrwx 1 root root 19 Oct 11 2008 S98haldaemon -> ../init.d/haldaemon
lrwxrwxrwx 1 root root 19 Oct 11 2008 S99firstboot -> ../init.d/firstboot
lrwxrwxrwx 1 root root 11 Jan 21 04:16 S99local -> ../rc.local
lrwxrwxrwx 1 root root 16 Jan 21 04:17 S99smartd -> ../init.d/smartd
```

The /etc/rcX.d/ directories only contain links to scripts in /etc/init.d/. Links allow for the script to have a different name. When entering a runlevel, all scripts that start with uppercase K or uppercase S will be started in alphabetical order. Those that start with K will be started first, with stop as the only parameter. The remaining scripts with S will be started with start as the only parameter.

All this is done by the /etc/rc.d/rc script on Red Hat and by the /etc/init.d/rc script on Debian.

## 15.1.7. mingetty

### mingetty in /etc/inittab

Almost at the end of /etc/inittab there is a section to start and respawn several mingetty daemons.

```
[root@RHEL4b ~]# grep getty /etc/inittab
# Run gettys in standard runlevels
1:2345:respawn:/sbin/mingetty tty1
2:2345:respawn:/sbin/mingetty tty2
3:2345:respawn:/sbin/mingetty tty3
4:2345:respawn:/sbin/mingetty tty4
5:2345:respawn:/sbin/mingetty tty5
6:2345:respawn:/sbin/mingetty tty6
```

### mingetty and /bin/login

This /sbin/mingetty will display a message on a virtual console and allow you to type a userid. Then it executes the /bin/login command with that userid. The /bin/login program will verify whether that user exists in /etc/passwd and prompt for (and verify) a password. If the password is correct, /bin/login passes control to the shell listed in /etc/passwd.

### respawning mingetty

The mingetty daemons are started by **init** and watched until they die (user exits the shell and is logged out). When this happens, the **init** daemon will **respawn** a new mingetty. So even if you **kill** a mingetty daemon, it will be restarted automatically.

This example shows that init respawns mingetty daemons. Look at the PID's of the last two mingetty processes.

```
[root@RHEL52 ~]# ps -C mingetty
PID TTY TIME CMD

2407 ttyl 00:00:00 mingetty
2408 tty2 00:00:00 mingetty
2409 tty3 00:00:00 mingetty
2410 tty4 00:00:00 mingetty
2411 tty5 00:00:00 mingetty
2412 tty6 00:00:00 mingetty
```

When we **kill** the last two mingettys, then **init** will notice this and start them again (with a different PID).

### disabling a mingetty

You can disable a mingetty for a certain tty by removing the runlevel from the second field in its line in /etc/inittab. Don't forget to tell init about the change of its configuration file with **kill -1 1**.

The example below shows how to disable mingetty on tty3 to tty6 in runlevels 4 and 5.

```
[root@RHEL52 ~]# grep getty /etc/inittab
# Run gettys in standard runlevels
1:2345:respawn:/sbin/mingetty tty1
2:2345:respawn:/sbin/mingetty tty2
3:23:respawn:/sbin/mingetty tty3
4:23:respawn:/sbin/mingetty tty4
5:23:respawn:/sbin/mingetty tty5
6:23:respawn:/sbin/mingetty tty6
```

### 15.2. daemon or demon?

A **daemon** is a process that runs in background, without a link to a GUI or terminal. Daemons are usually started at system boot, and stay alive until the system shuts down. In more recent technical writings, daemons are often refered to as **services**.

Unix **daemons** are not to be confused with demons. **Evi Nemeth**, co-author of the UNIX System Administration Handbook has the following to say about daemons:

Many people equate the word "daemon" with the word "demon", implying some kind of satanic connection between UNIX and the underworld. This is an egregious misunderstanding. "Daemon" is actually a much older form of "demon"; daemons have no particular bias towards good or evil, but rather serve to help define a person's character or personality. The ancient Greeks' concept of a "personal daemon" was similar to the modern concept of a "guardian angel" ....

# 15.3. starting and stopping daemons

The K and S scripts are links to the real scripts in /etc/init.d/. These can also be used when the system is running to start and stop daemons (or services). Most of them accept the following parameters: start, stop, restart, status.

For example in this screenshot we restart the samba daemon.

```
root@laika:~# /etc/init.d/samba restart

* Stopping Samba daemons... [ OK ]

* Starting Samba daemons... [ OK ]
```

You can achieve the same result on RHEL/Fedora with the service command.

```
[root@RHEL4b ~]# service smb restart
Shutting down SMB services: [ OK ]
Shutting down NMB services: [ OK ]
Starting SMB services: [ OK ]
Starting NMB services: [ OK ]
```

You might also want to take a look at **chkconfig**, **update-rc.d**.

# 15.4. chkconfig

The purpose of **chkconfig** is to relieve system administrators of manually managing all the links and scripts in **/etc/init.d** and **/etc/rcX.d**/.

# 15.4.1. chkconfig --list

Here we use **chkconfig** to list the status of a service in the different runlevels. You can see that the **crond** daemon (or service) is only activated in runlevels 2 to 5.

When you compare the screenshot above with the one below, you can see that **off** equals to a K link to the script, whereas **on** equals to an S link.

```
[root@RHEL52 etc]# find ./rc?.d/ -name \*crond -exec ls -l {} \; | cut -b40-
./rc0.d/K60crond -> ../init.d/crond
./rc1.d/K60crond -> ../init.d/crond
./rc2.d/S90crond -> ../init.d/crond
./rc3.d/S90crond -> ../init.d/crond
./rc4.d/S90crond -> ../init.d/crond
./rc5.d/S90crond -> ../init.d/crond
./rc6.d/K60crond -> ../init.d/crond
```

## 15.4.2. runlevel configuration

Here you see how to use chkconfig to disable (or enable) a service in a certain runlevel.

This screenshot shows how to disable **crond** in runleyel 3.

This screenshot shows how to enable **crond** in runlevels 3 and 4.

### 15.4.3. chkconfig configuration

Every script in **/etc/init.d/** can have (comment) lines to tell chkconfig what to do with the service. The line with **# chkconfig:** contains the runlevels in which the service should be started (2345), followed by the priority for start (90) and stop (60).

```
[root@RHEL52 ~]# head -9 /etc/init.d/crond | tail -5
# chkconfig: 2345 90 60
# description: cron is a standard UNIX program that runs user-specified
# programs at periodic scheduled times. vixie cron adds a
# number of features to the basic UNIX cron, including better
# security and more powerful configuration options.
```

### 15.4.4. enable and disable services

Services can be enabled or disabled in all runlevels with one command. Runlevels 0, 1 and 6 are always stopping services (or calling the scripts with **stop**) even when their name starts with uppercase S.

# 15.5. update-rc.d

### 15.5.1. about update-rc.d

The Debian equivalent of **chkconfig** is called **update-rc.d**. This tool is designed for use in scripts, if you prefer a graphical tool then look at **bum**.

When there are existing links in /etc/rcX.d/ then update-rc.d does not do anything. This is to avoid that post installation scripts using update-rc.d are overwriting changes made by a system administrator.

```
root@barry:~# update-rc.d cron remove update-rc.d: /etc/init.d/cron exists during rc.d purge (use -f to force)
```

As you can see in the next screenshot, nothing changed for the cron daemon.

```
root@barry:~# find /etc/rc?.d/ -name '*cron' -exec ls -l {} \;|cut -b44-
/etc/rc0.d/K1lcron -> ../init.d/cron
/etc/rc1.d/K1lcron -> ../init.d/cron
/etc/rc2.d/S89cron -> ../init.d/cron
/etc/rc3.d/S89cron -> ../init.d/cron
/etc/rc4.d/S89cron -> ../init.d/cron
/etc/rc5.d/S89cron -> ../init.d/cron
/etc/rc6.d/K1lcron -> ../init.d/cron
```

## 15.5.2. removing a service

Here we remove **cron** from all runlevels. Remember that the proper way to disable a service is to put K scripts oin all runlevels!

```
root@barry:~# update-rc.d -f cron remove
Removing any system startup links for /etc/init.d/cron ...
  /etc/rc0.d/K1lcron
  /etc/rc1.d/K1lcron
  /etc/rc2.d/S89cron
  /etc/rc3.d/S89cron
  /etc/rc4.d/S89cron
  /etc/rc5.d/S89cron
  root@barry:~# find /etc/rc?.d/ -name '*cron' -exec ls -l {} \;|cut -b44-root@barry:~#
```

### 15.5.3. enable a service

This screenshot shows how to use **update-rc.d** to enable a service in runlevels 2, 3, 4 and 5 and disable the service in runlevels 0, 1 and 6.

```
root@barry:~# update-rc.d cron defaults
Adding system startup for /etc/init.d/cron ...
  /etc/rc0.d/K20cron -> ../init.d/cron
  /etc/rc1.d/K20cron -> ../init.d/cron
  /etc/rc6.d/K20cron -> ../init.d/cron
  /etc/rc2.d/S20cron -> ../init.d/cron
  /etc/rc3.d/S20cron -> ../init.d/cron
  /etc/rc4.d/S20cron -> ../init.d/cron
  /etc/rc5.d/S20cron -> ../init.d/cron
```


### 15.5.4. customize a service

And here is an example on how to set your custom configuration for the cron daemon.

```
root@barry:~# update-rc.d -n cron start 11 2 3 4 5 . stop 89 0 1 6 .
Adding system startup for /etc/init.d/cron ...
  /etc/rc0.d/K89cron -> ../init.d/cron
  /etc/rc1.d/K89cron -> ../init.d/cron
  /etc/rc6.d/K89cron -> ../init.d/cron
  /etc/rc2.d/S11cron -> ../init.d/cron
  /etc/rc3.d/S11cron -> ../init.d/cron
  /etc/rc4.d/S11cron -> ../init.d/cron
  /etc/rc5.d/S11cron -> ../init.d/cron
```

# 15.6. bum

This screenshot shows **bum** in advanced mode.



### 15.7. runlevels

### 15.7.1. display the runlevel

You can see your current runlevel with the **runlevel** or **who -r** commands.

The runlevel command is typical Linux and will output the previous and the current runlevel. If there was no previous runlevel, then it will mark it with the letter N.

```
[root@RHEL4b ~]# runlevel
N 3
```

The history of **who -r** dates back to Seventies Unix, it still works on Linux.

```
[root@RHEL4b ~]# who -r
run-level 3 Jul 28 09:15 last=S
```

## 15.7.2. changing the runlevel

You can switch to another runlevel with the **telinit** command. On Linux /**sbin/telinit** is usually a (hard) link to /**sbin/init**.

This screenshot shows how to switch from runlevel 2 to runlevel 3 without reboot.

```
root@barry:~# runlevel
N 2
root@barry:~# init 3
root@barry:~# runlevel
2 3
```

### 15.7.3. /sbin/shutdown

The **shutdown** command is used to properly shut down a system.

Common switches used with **shutdown** are **-a**, **-t**, **-h** and **-r**.

The -a switch forces /sbin/shutdown to use /etc/shutdown.allow. The -t switch is used to define the number of seconds between the sending of the **TERM** signal and the **KILL** signal. The -h switch halts the system instead of changing to runlevel 1. The -r switch tells /sbin/shutdown to reboot after shutting down.

This screenshot shows how to use **shutdown** with five seconds between TERM and KILL signals.

```
root@barry:~# shutdown -t5 -h now
```

The **now** is the time argument. This can be  $+\mathbf{m}$  for the number of minutes to wait before shutting down (with **now** as an alias for  $+\mathbf{0}$ . The command will also accept hh:mm instead of  $+\mathbf{m}$ .

# 15.7.4. halt, reboot and poweroff

The binary /sbin/reboot is the same as /sbin/halt and /sbin/poweroff. Depending on the name we use to call the command, it can behave differently.

When in runlevel 0 or 6 halt, reboot and poweroff will tell the kernel to halt, reboot or poweroff the system.

When not in runlevel 0 or 6, typing **reboot** as root actually calls the **shutdown** command with the **-r** switch and typing **poweroff** will switch off the power when halting the system.

## 15.7.5. /var/log/wtmp

halt, reboot and poweroff all write to /var/log/wtmp. To look at /var/log/wtmp, we need to use th last.

### 15.7.6. Ctrl-Alt-Del

When **rc** is finished starting all those scripts, **init** will continue to read /etc/inittab. The next line is about what to do when the user hits **Ctrl-Alt-Delete** on the keyboard.

Here is what Debian 4.0 does.

```
root@barry:~# grep -i ctrl /etc/inittab
# What to do when CTRL-ALT-DEL is pressed.
ca:12345:ctrlaltdel:/sbin/shutdown -tl -a -r now
```

Which is very similar to the default Red Hat Enterprise Linux 5.2 action.

```
[root@RHEL52 ~]# grep -i ctrl /etc/inittab
# Trap CTRL-ALT-DELETE
ca::ctrlaltdel:/sbin/shutdown -t3 -r now
```

One noticable difference is that Debian forces shutdown to use /etc/shutdown.allow, where Red Hat allows everyone to invoke shutdown pressing Ctrl-Alt-Delete.

### 15.7.7. UPS and loss of power

```
[root@RHEL52 ~]# grep ^p /etc/inittab
pf::powerfail:/sbin/shutdown -f -h +2 "Power Failure; System Shutting Down"
pr:12345:powerokwait:/sbin/shutdown -c "Power Restored; Shutdown Cancelled"
```

It will read commands on what to execute in case of **powerfailure**, **powerok** and **Ctrl-Alt-Delete**. The init process never stops keeping an eye on power failures and that triple key combo.

```
root@barry:~# grep ^p /etc/inittab
pf::powerwait:/etc/init.d/powerfail start
pn::powerfailnow:/etc/init.d/powerfail now
po::powerokwait:/etc/init.d/powerfail stop
```

# 15.8. systemd

It is likely that **systemd** will replace all the standard init/runlevel/rc functionality. Both Red Hat and Debian have decided in 2014 that **systemd** will be replacing **init** in future releases (RHEL7/CentOS7 and Debian 8).

The screenshot below shows **systemd** running as **pid 1** on RHEL7.

```
[root@rhel7 ~]# ps fax | grep systemd | cut -c1-76
   1 ? Ss 0:01 /usr/lib/systemd/systemd --switched-root --system
                Ss
  505 ?
                        0:00 /usr/lib/systemd/systemd-journald
                Ss 0:00 /usr/lib/systemd/systemd-journal
Ss 0:00 /usr/lib/systemd/systemd-udevd
Ss 0:00 /usr/lib/systemd/systemd-loginal
  545 ?
  670 ?
                Ss
                        0:00 /usr/lib/systemd/systemd-logind
                Ssl
S+
 677 ?
                        0:00 /bin/dbus-daemon --system --address=systemd: --no
2662 pts/1 S+
                                        \_ grep --color=auto systemd
                        0:00
[root@rhel7 ~]#
```

Debian 8 (not yet released in September 2014) uses parts of **systemd**, but still has **init** as **pid 1**.

### 15.8.1. systemd targets

The first command to learn is **systemctl list-units --type=target** (or the shorter version **systemctl -t target**). It will show you the different targets on the system.

```
UNIT LOAD ACTIVE SUB DESCRIPTION basic.target loaded active active
[root@rhel7 ~]# systemctl list-units --type=target
                      loaded active active Basic System
cryptsetup.target loaded active active Encrypted Volumes
getty.target loaded active active Login Prompts graphical.target loaded active active Graphical Interface
local-fs-pre.target loaded active active Local File Systems (Pre)
local-fs.target loaded active active Local File Systems
multi-user.target loaded active active Multi-User System
network.target loaded active active Network
nfs.target loaded active active Network File System Server paths.target loaded active active Paths
remote-fs.target loaded active active Remote File Systems
slices.target loaded active active Slices sockets.target loaded active active Sockets
swap.target loaded active active Swap
sysinit.target loaded active active System Initialization
timers.target loaded active active Timers
LOAD = Reflects whether the unit definition was properly loaded.
ACTIVE = The high-level unit activation state, i.e. generalization of SUB.
SUB = The low-level unit activation state, values depend on unit type.
16 loaded units listed. Pass --all to see loaded but inactive units, too.
To show all installed unit files use 'systemctl list-unit-files'.
[root@rhel7 ~]#
```

Targets are the replacement of runlevels and define specific points to reach when booting the system. For example the **graphical.target** is reached when you get a graphical interface, and the **nfs.target** requires a running nfs server.

To switch to a target (for example **multi-user.target**), we now use **systemctl isolate** (instead of the equivalent **init 3** to change the runlevel).

```
[root@rhe17 ~]# ps fax | wc -l
169
[root@rhe17 ~]# systemctl isolate multi-user.target
[root@rhe17 ~]# ps fax | wc -l
129
[root@rhe17 ~]#
```

To change the default target, we again use this **systemctl** command (instead of editing the /etc/inittab file).

```
[root@rhe17 ~]# systemctl enable multi-user.target --force
rm '/etc/systemd/system/default.target'
ln -s '/usr/lib/systemd/system/multi-user.target' '/etc/systemd/system/default\
.target'
[root@rhe17 ~]#
```

This command removed the file /etc/systemd/system/default.target and replaced it with a symbolic link to the multi-user-.target target.

### 15.8.2. systemd dependencies

Dependencies are no longer defined by alfabetical order of running scripts, but by configuration in /etc/systemd/system/. For example here are the required services for the multi-user.target on Red Hat Enterprise 7.

```
[root@rhel7 ~]# ls /etc/systemd/system/multi-user.target.wants/
abrt-ccpp.service hypervkvpd.service postfix.service
abrtd.service hypervvssd.service remote-fs.target
abrt-oops.service irqbalance.service rhsmcertd.service
abrt-vmcore.service ksm.service rngd.service
abrt-xorg.service ksmtuned.service rpcbind.service
atd.service libstoragemgmt.service rsyslog.service
auditd.service libvirtd.service smartd.service
avahi-daemon.service mdmonitor.service sshd.service
chronyd.service ModemManager.service tuned.service
crond.service nfs.target vmtoolsd.service
[root@rhel7 ~]#
```

#### Debian8 is not fully migrated yet.

```
root@debian8:~# ls /etc/systemd/system/multi-user.target.wants/
anacron.service binfmt-support.service pppd-dns.service ssh.service
atd.service fancontrol.service remote-fs.target
avahi-daemon.service lm-sensors.service rsyslog.service
```

Typical **rc scripts** are replaced with services. Issue the **systemctl list-units -t service --all** (or **systemctl -at service**) to get a list of all services on your system.

```
[root@rhel7 ~]# systemctl -at service | head -5 | column -t | cut -c1-78

UNIT LOAD ACTIVE SUB DESCRIPTION

abrt-ccpp.service loaded active exited Install ABRT coredump

abrt-oops.service loaded active running ABRT kernel log

abrt-vmcore.service loaded inactive dead Harvest vmcores for

abrt-xorg.service loaded active running ABRT Xorg log

[root@rhel7 ~]#
```

And here an example on how to see the status of the **sshd** service.

### 15.8.3. systemd services

The **chkconfig** and **service** commands are considered 'legacy'. They are replaced with **systemctl**.

This screenshot shows the new way to start and stop a service.

```
[root@rhel7 ~]# systemctl start crond.service
[root@rhel7 ~]# systemctl show crond.service | grep State
LoadState=loaded
ActiveState=active
SubState=running
UnitFileState=enabled
[root@rhel7 ~]# systemctl stop crond.service
[root@rhel7 ~]# systemctl show crond.service | grep State
LoadState=loaded
ActiveState=inactive
SubState=dead
UnitFileState=enabled
[root@rhel7 ~]#
```

And here is the new way to stop and disable a service.

```
[root@rhel7 ~]# systemctl stop crond.service
[root@rhel7 ~]# systemctl disable crond.service
rm '/etc/systemd/system/multi-user.target.wants/crond.service'
[root@rhel7 ~]# systemctl show crond.service | grep State
LoadState=loaded
ActiveState=inactive
SubState=dead
UnitFileState=disabled
[root@rhel7 ~]#
```

This screenshot shows how to enable and start the service again.

```
[root@rhel7 ~]# systemctl enable crond.service
ln -s '/usr/lib/systemd/system/crond.service' '/etc/systemd/system/multi-user.\
target.wants/crond.service'
[root@rhel7 ~]# systemctl start crond.service
[root@rhel7 ~]# systemctl show crond.service | grep State
LoadState=loaded
ActiveState=active
SubState=running
UnitFileState=enabled
[root@rhel7 ~]#
```

### 15.8.4. systemd signalling

You can also use **systemd** to **kill** problematic services.

```
[root@rhel7 ~]# systemctl show crond.service | grep State
LoadState=loaded
ActiveState=active
SubState=running
UnitFileState=enabled
[root@rhel7 ~]# systemctl kill -s SIGKILL crond.service
[root@rhel7 ~]# systemctl show crond.service | grep State
LoadState=loaded
ActiveState=failed
SubState=failed
UnitFileState=enabled
[root@rhel7 ~]#
```

### 15.8.5. systemd shutdown

The **poweroff**, **halt** and **reboot** commands are considered legacy now and are handeld by **systemctl**. The table below shows the legacy commands on the left and their new **systemd** equivalent on the right.

Table 15.1. systemd power management

| legacy command | systemd command     |
|----------------|---------------------|
| poweroff       | systemctl poweroff  |
| reboot         | systemctl reboot    |
| halt           | systemctl halt      |
| pm-suspend     | systemctl suspend   |
| pm-hibernate   | systemctl hibernate |

### 15.8.6. remote systemd

The **systemctl** utility has a buil-in remote control providing there is an **ssh daemon** running on the remote system.

This screenshot shows how to use **systemctl** to verify a service on an other RHEL server.

```
[root@rhel7 ~]# systemctl -H root@192.168.1.65 status sshd
root@192.168.1.65's password:
sshd.service - OpenSSH server daemon
   Loaded: loaded (/usr/lib/systemd/system/sshd.service; enabled)
   Active: active (running) since Thu 2014-09-11 13:04:10 CEST; 16min ago
   Process: 1328 ExecStartPre=/usr/sbin/sshd-keygen (code=exited, status=0/SUCCE\
SS)
Main PID: 1363 (sshd)
   CGroup: /system.slice/sshd.service
[root@rhel7 ~]#
```

## 15.8.7. there is more systemd

There are other tools...

```
systemd-analyze
                                systemd-loginctl
systemd-ask-password
                                systemd-machine-id-setup
systemd-cat
                                systemd-notify
systemd-cgls
                               systemd-nspawn
systemd-cgtop
                               systemd-run
systemd-coredumpctl
                               systemd-stdio-bridge
systemd-delta
                                systemd-sysv-convert
systemd-detect-virt
                                systemd-tmpfiles
systemd-inhibit
                                systemd-tty-ask-password-agent
```

For example **systemd-analyze blame** will give you an overview of the time it took for each service to boot.

# 15.9. practice: init

- 1. Change /etc/inittab so that only two mingetty's are respawned. Kill the other mingetty's and verify that they don't come back.
- 2. Use the Red Hat Enterprise Linux virtual machine. Go to runlevel 5, display the current and previous runlevel, then go back to runlevel 3.
- 3. Is the sysinit script on your computers setting or changing the PATH environment variable ?
- 4. List all init.d scripts that are started in runlevel 2.
- 5. Write a script that acts like a daemon script in /etc/init.d/. It should have a case statement to act on start/stop/restart and status. Test the script!
- 6. Use **chkconfig** to setup your script to start in runlevels 3,4 and 5, and to stop in any other runlevel.

## 15.10. solution: init

1. Change /etc/inittab so that only two mingetty's are respawned. Kill the other mingetty's and verify that they don't come back.

Killing the mingetty's will result in init respawning them. You can edit /etc/inittab so it looks like the screenshot below. Don't forget to also run kill -1 1.

```
[root@RHEL5 ~]# grep tty /etc/inittab
# Run gettys in standard runlevels
1:2345:respawn:/sbin/mingetty tty1
2:2345:respawn:/sbin/mingetty tty2
3:2:respawn:/sbin/mingetty tty3
4:2:respawn:/sbin/mingetty tty4
5:2:respawn:/sbin/mingetty tty5
6:2:respawn:/sbin/mingetty tty6
[root@RHEL5 ~]#
```

2. Use the Red Hat Enterprise Linux virtual machine. Go to runlevel 5, display the current and previous runlevel, then go back to runlevel 3.

```
init 5 (watch the console for the change taking place)
runlevel
init 3 (again you can follow this on the console)
```

3. Is the sysinit script on your computers setting or changing the PATH environment variable ?

On Red Hat, grep for PATH in /etc/rc.sysinit, on Debian/Ubuntu check /etc/rc.local and / etc/ini.t/rc.local. The answer is probably no, but on RHEL5 the rc.sysinit script does set the HOSTNAME variable.

```
[root@RHEL5 etc]# grep HOSTNAME rc.sysinit
```

4. List all init.d scripts that are started in runlevel 2.

```
root@RHEL5 ~# chkconfig --list | grep '2:on'
```

5. Write a script that acts like a daemon script in /etc/init.d/. It should have a case statement to act on start/stop/restart and status. Test the script!

The script could look something like this.

```
#!/bin/bash
#
# chkconfig: 345 99 01
# description: pold demo script
#
# /etc/init.d/pold
```

```
#
case "$1" in
 start)
    echo -n "Starting pold..."
    sleep 1;
    touch /var/lock/subsys/pold
    echo "done."
    echo pold started >> /var/log/messages
 stop)
    echo -n "Stopping pold..."
    sleep 1;
    rm -rf /var/lock/subsys/pold
    echo "done."
    echo pold stopped >> /var/log/messages
    echo "Usage: /etc/init.d/pold {start|stop}"
    exit 1
esac
exit 0
```

The **touch /var/lock/subsys/pold** is mandatory and must be the same filename as the script name, if you want the stop sequence (the K01pold link) to be run.

6. Use **chkconfig** to setup your script to start in runlevels 3,4 and 5, and to stop in any other runlevel.

```
chkconfig --add pold
```

The command above will only work when the # **chkconfig:** and # **description:** lines in the pold script are there.



# **Table of Contents**

| 16. scheduling                                    | 194 |
|---|-----|
| 16.1. one time jobs with at                       | 195 |
| 16.2. cron  | 197 |
| 16.3. practice: scheduling                        |     |
| 16.4. solution: scheduling                        |     |
| 17. logging                                       |     |
| 17.1. login logging                               |     |
| 17.2. syslogd                                     |     |
| 17.3. logger                                      |     |
| 17.4. watching logs                               |     |
| 17.5. rotating logs                               |     |
| 17.5. Totaling logs                               |     |
| 17.0. practice : logging                          |     |
|   |     |
| 18. memory management                             |     |
| 18.1. displaying memory and cache                 |     |
| 18.2. managing swap space                         |     |
| 18.3. monitoring memory with vmstat               |     |
| 18.4. practice: memory                            |     |
| 18.5. solution: memory                            |     |
| 19. resource monitoring                           |     |
| 19.1. four basic resources                        |     |
| 19.2. top   |     |
| 19.3. free  |     |
| 19.4. watch                                       | 222 |
| 19.5. vmstat                                      | 222 |
| 19.6. iostat                                      | 223 |
| 19.7. mpstat                                      | 224 |
| 19.8. sadc and sar                                |     |
| 19.9. ntop  |     |
| 19.10. iftop                                      |     |
| 19.11. iptraf                                     |     |
| 19.12. nmon                                       |     |
| 19.13. http                                       |     |
| 20. package management                            |     |
| 20.1. package terminology                         |     |
| 20.2. deb package management                      |     |
| 20.3. apt-get                                     |     |
| 20.4. aptitude                                    | 235 |
| 1   |     |
| 20.5. apt   |     |
| 20.6. rpm   |     |
| 20.7. yum   |     |
| 20.8. alien                                       |     |
| 20.9. downloading software outside the repository |     |
| 20.10. compiling software                         |     |
| 20.11. practice: package management               |     |
| 20.12. solution: package management               | 249 |

# Chapter 16. scheduling

Linux administrators use the **at** to schedule one time jobs. Recurring jobs are better scheduled with **cron**. The next two sections will discuss both tools.

# 16.1. one time jobs with at

### 16.1.1. at

Simple scheduling can be done with the **at** command. This screenshot shows the scheduling of the date command at 22:01 and the sleep command at 22:03.

*In real life you will hopefully be scheduling more useful commands* ;-)

### 16.1.2. atq

It is easy to check when jobs are scheduled with the **atq** or **at -l** commands.

The at command understands English words like tomorrow and teatime to schedule commands the next day and at four in the afternoon.

```
root@laika:~# at 10:05 tomorrow

at> sleep 100

at> <EOT>
job 5 at Thu Aug 2 10:05:00 2007

root@laika:~# at teatime tomorrow

at> tea

at> <EOT>
job 6 at Thu Aug 2 16:00:00 2007

root@laika:~# atq

6     Thu Aug 2 16:00:00 2007 a root

5     Thu Aug 2 10:05:00 2007 a root

root@laika:~#
```

### 16.1.3. atrm

Jobs in the at queue can be removed with **atrm**.

# 16.1.4. at.allow and at.deny

You can also use the /etc/at.allow and /etc/at.deny files to manage who can schedule jobs with at.

The /etc/at.allow file can contain a list of users that are allowed to schedule at jobs. When /etc/at.allow does not exist, then everyone can use at unless their username is listed in / etc/at.deny.

If none of these files exist, then everyone can use at.

### 16.2. cron

### 16.2.1. crontab file

The **crontab(1)** command can be used to maintain the **crontab(5)** file. Each user can have their own crontab file to schedule jobs at a specific time. This time can be specified with five fields in this order: minute, hour, day of the month, month and day of the week. If a field contains an asterisk (\*), then this means all values of that field.

The following example means: run script42 eight minutes after two, every day of the month, every month and every day of the week.

```
8 14 * * * script42
```

Run script8472 every month on the first of the month at 25 past midnight.

```
25 0 1 * * script8472
```

Run this script33 every two minutes on Sunday (both 0 and 7 refer to Sunday).

```
*/2 * * * 0
```

Instead of these five fields, you can also type one of these: @reboot, @yearly or @annually, @monthly, @weekly, @daily or @midnight, and @hourly.

### 16.2.2. crontab command

Users should not edit the crontab file directly, instead they should type **crontab -e** which will use the editor defined in the EDITOR or VISUAL environment variable. Users can display their cron table with **crontab -l**.

### 16.2.3. cron.allow and cron.deny

The **cron daemon crond** is reading the cron tables, taking into account the **/etc/cron.allow** and **/etc/cron.deny** files.

These files work in the same way as **at.allow** and **at.deny**. When the **cron.allow** file exists, then your username has to be in it, otherwise you cannot use **cron**. When the **cron.allow** file does not exists, then your username cannot be in the **cron.deny** file if you want to use **cron**.

### 16.2.4. /etc/crontab

The /etc/crontab file contains entries for when to run hourly/daily/weekly/monthly tasks. It will look similar to this output.

```
SHELL=/bin/sh
PATH=/usr/local/sbin:/usr/local/bin:/sbin:/usr/sbin:/usr/bin

20 3 * * * root run-parts --report /etc/cron.daily
40 3 * * 7 root run-parts --report /etc/cron.weekly
55 3 1 * * root run-parts --report /etc/cron.monthly
```

### 16.2.5. /etc/cron.\*

The directories shown in the next screenshot contain the tasks that are run at the times scheduled in /etc/crontab. The /etc/cron.d directory is for special cases, to schedule jobs that require finer control than hourly/daily/weekly/monthly.

```
paul@laika:~$ ls -ld /etc/cron.*
drwxr-xr-x 2 root root 4096 2008-04-11 09:14 /etc/cron.d
drwxr-xr-x 2 root root 4096 2008-04-19 15:04 /etc/cron.daily
drwxr-xr-x 2 root root 4096 2008-04-11 09:14 /etc/cron.hourly
drwxr-xr-x 2 root root 4096 2008-04-11 09:14 /etc/cron.monthly
drwxr-xr-x 2 root root 4096 2008-04-11 09:14 /etc/cron.weekly
```

### 16.2.6. /etc/cron.\*

Note that Red Hat uses **anacron** to schedule daily, weekly and monthly cron jobs.

```
root@rhel65:/etc# cat anacrontab
# /etc/anacrontab: configuration file for anacron
# See anacron(8) and anacrontab(5) for details.
SHELL=/bin/sh
PATH=/sbin:/bin:/usr/sbin:/usr/bin
MAILTO=root
# the maximal random delay added to the base delay of the jobs
RANDOM_DELAY=45
# the jobs will be started during the following hours only
START_HOURS_RANGE=3-22
#period in days delay in minutes job-identifier command
        5 cron.daily nice run-parts /etc/cron.daily
25 cron.weekly nice run-parts /etc/cron.weekly
1
        25
               cron.weekly
                                        nice run-parts /etc/cron.weekly
@monthly 45 cron.monthly
                                      nice run-parts /etc/cron.monthly
root@rhel65:/etc#
```

# 16.3. practice: scheduling

- 1. Schedule two jobs with at, display the at queue and remove a job.
- 2. As normal user, use **crontab -e** to schedule a script to run every four minutes.
- 3. As root, display the **crontab** file of your normal user.
- 4. As the normal user again, remove your **crontab** file.
- 5. Take a look at the **cron** files and directories in /etc and understand them. What is the **run-parts** command doing?

# 16.4. solution: scheduling

1. Schedule two jobs with at, display the at queue and remove a job.

```
root@rhel55 ~# at 9pm today
at> echo go to bed >> /root/todo.txt
at> <EOT>
job 1 at 2010-11-14 21:00
root@rhel55 ~# at 17h31 today
at> echo go to lunch >> /root/todo.txt
at> <EOT>
job 2 at 2010-11-14 17:31
root@rhel55 ~# atq
2 2010-11-14 17:31 a root
1 2010-11-14 21:00 a root
root@rhel55 ~# atrm 1
root@rhel55 ~# atq
2 2010-11-14 17:31 a root
root@rhel55 ~# date
Sun Nov 14 17:31:01 CET 2010
root@rhel55 ~# cat /root/todo.txt
go to lunch
```

2. As normal user, use **crontab -e** to schedule a script to run every four minutes.

```
paul@rhel55 ~$ crontab -e
no crontab for paul - using an empty one
crontab: installing new crontab
```

3. As root, display the **crontab** file of your normal user.

```
root@rhel55 ~# crontab -l -u paul
*/4 * * * echo `date` >> /home/paul/crontest.txt
```

4. As the normal user again, remove your **crontab** file.

```
paul@rhel55 ~$ crontab -r
paul@rhel55 ~$ crontab -l
no crontab for paul
```

5. Take a look at the **cron** files and directories in /etc and understand them. What is the **run-parts** command doing?

```
run-parts runs a script in a directory
```

# **Chapter 17. logging**

This chapter has three distinct subjects.

First we look at login logging; how can we find out who is logging in to the system, when and from where. And who is not logging in, who fails at **su** or **ssh**.

Second we discuss how to configure the syslog daemon, and how to test it with logger.

The last part is mostly about **rotating logs** and mentions the **tail -f** and **watch** commands for **watching logs**.

# 17.1. login logging

To keep track of who is logging into the system, Linux can maintain the /var/log/wtmp, /var/log/btmp, /var/run/utmp and /var/log/lastlog files.

## 17.1.1. /var/run/utmp (who)

Use the **who** command to see the /var/run/utmp file. This command is showing you all the **currently** logged in users. Notice that the utmp file is in /var/run and not in /var/log.

```
[root@rhel4 ~]# who
paul pts/1 Feb 14 18:21 (192.168.1.45)
sandra pts/2 Feb 14 18:11 (192.168.1.42)
inge pts/3 Feb 14 12:01 (192.168.1.33)
els pts/4 Feb 14 14:33 (192.168.1.19)
```

## 17.1.2. /var/log/wtmp (last)

The /var/log/wtmp file is updated by the **login program**. Use **last** to see the /var/run/wtmp file.

```
[root@rhel4a ~]# last | head
       pts/1 192.168.1.45
                                       Wed Feb 14 18:39 still logged in
reboot system boot 2.6.9-42.0.8.ELs Wed Feb 14 18:21
                                                                   (01:15)
nicolas pts/5 pc-dss.telematic Wed Feb 14 12:32 - 13:06 (00:33)
stefaan pts/3
                    pc-sde.telematic Wed Feb 14 12:28 - 12:40 (00:12)
nicolas pts/3 pc-nae.telematic Wed Feb 14 11:36 - 12:21 (00:45) nicolas pts/3 pc-nae.telematic Wed Feb 14 11:34 - 11:36 (00:01)
                    pc-dss.telematic Wed Feb 14 10:03 - 12:31 (02:28)
dirk pts/5
                    pc-nae.telematic Wed Feb 14 09:45 - 11:34
nicolas pts/3
                                                                   (01:48)
dimitri pts/5 stefaan pts/4
                                       Wed Feb 14 07:57 - 08:38
                     rhel4
                                                                   (00:40)
                     pc-sde.telematic Wed Feb 14 07:16 - down
                                                                   (05:50)
[root@rhel4a ~]#
```

The last command can also be used to get a list of last reboots.

```
[paul@rekkie ~]$ last reboot
reboot system boot 2.6.16-rekkie Mon Jul 30 05:13 (370+08:42)
wtmp begins Tue May 30 23:11:45 2006
[paul@rekkie ~]
```

## 17.1.3. /var/log/lastlog (lastlog)

Use **lastlog** to see the /var/log/lastlog file.

```
[root@rhel4a ~]# lastlog | tail
tim pts/5 10.170.1.122 Tue Feb 13 09:36:54 +0100 2007
               pts/6 rhel4
                                     Tue Feb 13 10:06:56 +0100 2007
rm
henk
                                       **Never logged in**
stefaan
              pts/3 pc-sde.telematic Wed Feb 14 12:28:38 +0100 2007
               pts/5 pc-dss.telematic Wed Feb 14 10:03:11 +0100 2007
dirk
                                       **Never logged in**
arsene
nicolas
              pts/5 pc-dss.telematic Wed Feb 14 12:32:18 +0100 2007
              pts/5 rhel4 Wed Feb 14 07:57:19 +0100 2007 pts/7 rhel4 Tue Feb 13 10:35:40 +0100 2007
dimitri
bashuserrm
                pts/5 rhel4
kornuserrm
                                       Tue Feb 13 10:06:17 +0100 2007
[root@rhel4a ~]#
```

## 17.1.4. /var/log/btmp (lastb)

There is also the **lastb** command to display the **/var/log/btmp** file. This file is updated by the login program when entering the wrong password, so it contains failed login attempts. Many computers will not have this file, resulting in no logging of failed login attempts.

```
[root@RHEL4b ~]# lastb
lastb: /var/log/btmp: No such file or directory
Perhaps this file was removed by the operator to prevent logging lastb\
info.
[root@RHEL4b ~]#
```

The reason given for this is that users sometimes type their password by mistake instead of their login, so this world readable file poses a security risk. You can enable bad login logging by simply creating the file. Doing a chmod o-r /var/log/btmp improves security.

```
[root@RHEL4b ~]# touch /var/log/btmp
[root@RHEL4b ~]# 11 /var/log/btmp
-rw-r--r- 1 root root 0 Jul 30 06:12 /var/log/btmp
[root@RHEL4b ~]# chmod o-r /var/log/btmp
[root@RHEL4b ~]# lastb

btmp begins Mon Jul 30 06:12:19 2007
[root@RHEL4b ~]#
```

Failed logins via ssh, rlogin or su are not registered in /var/log/btmp. Failed logins via tty are.

### 17.1.5. su and ssh logins

Depending on the distribution, you may also have the /var/log/secure file being filled with messages from the auth and/or authpriv syslog facilities. This log will include su and/or ssh failed login attempts. Some distributions put this in /var/log/auth.log, verify the syslog configuration.

```
[root@RHEL4b ~]# cat /var/log/secure
Jul 30 07:09:03 sshd[4387]: Accepted publickey for paul from ::ffff:19\
2.168.1.52 port 33188 ssh2
Jul 30 05:09:03 sshd[4388]: Accepted publickey for paul from ::ffff:19\
2.168.1.52 port 33188 ssh2
Jul 30 07:22:27 sshd[4655]: Failed password for Hermione from ::fffff:1\
92.168.1.52 port 38752 ssh2
Jul 30 05:22:27 sshd[4656]: Failed password for Hermione from ::ffff:1\
92.168.1.52 port 38752 ssh2
Jul 30 07:22:30 sshd[4655]: Failed password for Hermione from ::fffff:1\
92.168.1.52 port 38752 ssh2
Jul 30 05:22:30 sshd[4656]: Failed password for Hermione from ::ffff:1\
92.168.1.52 port 38752 ssh2
Jul 30 07:22:33 sshd[4655]: Failed password for Hermione from ::ffff:1\
92.168.1.52 port 38752 ssh2
Jul 30 05:22:33 sshd[4656]: Failed password for Hermione from ::ffff:1\
92.168.1.52 port 38752 ssh2
Jul 30 08:27:33 sshd[5018]: Invalid user roberto from ::ffff:192.168.1\
.52
Jul 30 06:27:33 sshd[5019]: input_userauth_request: invalid user rober\
Jul 30 06:27:33 sshd[5019]: Failed none for invalid user roberto from \
::ffff:192.168.1.52 port 41064 ssh2
Jul 30 06:27:33 sshd[5019]: Failed publickey for invalid user roberto \
from ::ffff:192.168.1.52 port 41064 ssh2
Jul 30 08:27:36 sshd[5018]: Failed password for invalid user roberto f\
rom ::ffff:192.168.1.52 port 41064 ssh2
Jul 30 06:27:36 sshd[5019]: Failed password for invalid user roberto f\
rom ::ffff:192.168.1.52 port 41064 ssh2
[root@RHEL4b ~]#
```

You can enable this yourself, with a custom log file by adding the following line tot syslog.conf.

```
auth.*,authpriv.* /var/log/customsec.log
```

# 17.2. syslogd

### 17.2.1. about syslog

The standard method of logging on Linux was through the **syslogd** daemon. Syslog was developed by **Eric Allman** for sendmail, but quickly became a standard among many Unix applications and was much later written as rfc 3164. The syslog daemon can receive messages on udp **port 514** from many applications (and appliances), and can append to log files, print, display messages on terminals and forward logs to other syslogd daemons on other machines. The syslogd daemon is configured in **/etc/syslog.conf**.

## 17.2.2. about rsyslog

The new method is called **reliable and extended syslogd** and uses the **rsyslogd** daemon and the /**etc/rsyslogd.conf** configuration file. The syntax is backwards compatible.

Each line in the configuration file uses a **facility** to determine where the message is coming from. It also contains a **priority** for the severity of the message, and an **action** to decide on what to do with the message.

### 17.2.3. modules

The new **rsyslog** has many more features that can be expanded by using modules. Modules allow for example exporting of syslog logging to a database.

Se the manuals for more information (when you are done with this chapter).

root@rhel65:/etc# man rsyslog.conf root@rhel65:/etc# man rsyslogd root@rhel65:/etc#

### 17.2.4. facilities

The **man rsyslog.conf** command will explain the different default facilities for certain daemons, such as mail, lpr, news and kern(el) messages. The local0 to local7 facility can be used for appliances (or any networked device that supports syslog). Here is a list of all facilities for rsyslog.conf version 1.3. The security keyword is deprecated.

```
auth (security)
authpriv
cron
daemon
ftp
kern
lpr mail
mark (internal use only)
news
syslog
user
uucp
local0-7
```

## 17.2.5. priorities

The worst severity a message can have is **emerg** followed by **alert** and **crit**. Lowest priority should go to **info** and **debug** messages. Specifying a severity will also log all messages with a higher severity. You can prefix the severity with = to obtain only messages that match that severity. You can also specify **.none** to prevent a specific action from any message from a certain facility.

Here is a list of all priorities, in ascending order. The keywords warn, error and panic are deprecated.

```
debug
info
notice
warning (warn)
err (error)
crit
alert
emerg (panic)
```

### 17.2.6. actions

The default action is to send a message to the username listed as action. When the action is prefixed with a / then rsyslog will send the message to the file (which can be a regular file, but also a printer or terminal). The @ sign prefix will send the message on to another syslog server. Here is a list of all possible actions.

```
root,user1 list of users, separated by comma's

* message to all logged on users

/ file (can be a printer, a console, a tty, ...)

-/ file, but don't sync after every write

| named pipe

@ other syslog hostname
```

In addition, you can prefix actions with a - to omit syncing the file after every logging.

## 17.2.7. configuration

Below a sample configuration of custom local4 messages in /etc/rsyslog.conf.

### 17.2.8. restarting rsyslogd

Don't forget to restart the server after changing its configuration.

```
root@rhel65:/etc# service rsyslog restart

Shutting down system logger: [ OK ]

Starting system logger: [ OK ]

root@rhel65:/etc#
```

# **17.3.** logger

The logger command can be used to generate syslog test messages. You can aslo use it in scripts. An example of testing syslogd with the **logger** tool.

```
[root@rhel4a ~]# logger -p local4.debug "l4 debug"
[root@rhel4a ~]# logger -p local4.crit "l4 crit"
[root@rhel4a ~]# logger -p local4.emerg "l4 emerg"
[root@rhel4a ~]#
```

The results of the tests with logger.

```
[root@rhel4a ~]# cat /var/log/critandabove
Feb 14 19:55:19 rhel4a paul: 14 crit
Feb 14 19:55:28 rhel4a paul: 14 emerg
[root@rhel4a ~]# cat /var/log/onlycrit
Feb 14 19:55:19 rhel4a paul: 14 crit
[root@rhel4a ~]# cat /var/log/alllocal4
Feb 14 19:55:11 rhel4a paul: 14 debug
Feb 14 19:55:19 rhel4a paul: 14 crit
Feb 14 19:55:28 rhel4a paul: 14 emerg
[root@rhel4a ~]#
```

# 17.4. watching logs

You might want to use the **tail -f** command to look at the last lines of a log file. The **-f** option will dynamically display lines that are appended to the log.

```
paul@ubu1010:~$ tail -f /var/log/udev
SEQNUM=1741
SOUND_INITIALIZED=1
ID_VENDOR_FROM_DATABASE=nVidia Corporation
ID_MODEL_FROM_DATABASE=MCP79 High Definition Audio
ID_BUS=pci
ID_VENDOR_ID=0x10de
ID_MODEL_ID=0x0ac0
ID_PATH=pci-0000:00:08.0
SOUND_FORM_FACTOR=internal
```

You can automatically repeat commands by preceding them with the **watch** command. When executing the following:

```
[root@rhel6 ~]# watch who
```

Something similar to this, repeating the output of the **who** command every two seconds, will appear on the screen.

```
Every 2.0s: who Sun Jul 17 15:31:03 2011

root ttyl 2011-07-17 13:28
paul pts/0 2011-07-17 13:31 (192.168.1.30)
paul pts/1 2011-07-17 15:19 (192.168.1.30)
```

### 17.5. rotating logs

A lot of log files are always growing in size. To keep this within bounds, you may want to use **logrotate** to rotate, compress, remove and mail log files. More info on the logrotate command in **/etc/logrotate.conf**. Individual configurations can be found in the **/etc/logrotate.d/** directory.

Below a screenshot of the default Red Hat logrotate.conf file.

```
root@rhel65:/etc# cat logrotate.conf
# see "man logrotate" for details
# rotate log files weekly
weekly
# keep 4 weeks worth of backlogs
rotate 4
# create new (empty) log files after rotating old ones
# use date as a suffix of the rotated file
dateext
# uncomment this if you want your log files compressed
#compress
# RPM packages drop log rotation information into this directory
include /etc/logrotate.d
# no packages own wtmp and btmp -- we'll rotate them here
/var/log/wtmp {
   monthly
    create 0664 root utmp
        minsize 1M
    rotate 1
/var/log/btmp {
   missingok
   monthly
   create 0600 root utmp
   rotate 1
}
# system-specific logs may be also be configured here.
root@rhel65:/etc#
```

### 17.6. practice: logging

- 1. Display the /var/run/utmp file with the proper command (not with cat or vi).
- 2. Display the /var/log/wtmp file.
- 3. Use the lastlog and lastb commands, understand the difference.
- 4. Examine syslog to find the location of the log file containing ssh failed logins.
- 5. Configure syslog to put local4.error and above messages in /var/log/l4e.log and local4.info only .info in /var/log/l4i.log. Test that it works with the logger tool!
- 6. Configure /var/log/Mysu.log, all the su to root messages should go in that log. Test that it works!
- 7. Send the local5 messages to the syslog server of your neighbour. Test that it works.
- 8. Write a script that executes logger to local4 every 15 seconds (different message). Use tail -f and watch on your local4 log files.

### 17.7. solution: logging

1. Display the /var/run/utmp file.

who

2. Display the /var/log/wtmp file.

last

3. Use the lastlog and lastb commands, understand the difference.

```
lastlog: when users last logged on
lastb: failed (bad) login attempts
```

4. Examine syslog to find the location of the log file containing ssh failed logins.

Answer depends on whether you machine uses **syslog** or **rsyslog** (newer).

```
[root@rhel53 ~]# grep authpriv /etc/syslog.conf
authpriv.* /var/log/secure

[root@rhel71 ~]# grep ^authpriv /etc/rsyslog.conf
authpriv.* /var/log/secure

paul@debian8:~$ grep ^auth /etc/rsyslog.conf
auth,authpriv.* /var/log/auth.log
```

5. Configure syslog to put local4.error and above messages in /var/log/l4e.log and local4.info only .info in /var/log/l4i.log. Test that it works with the logger tool!

#### With **syslog:**

```
echo local4.error /var/log/14e.log >> /etc/syslog.conf
echo local4.=info /var/log/14i.log >> /etc/syslog.conf
service syslog restart
```

#### With **rsyslog:**

```
echo local4.error /var/log/l4e.log >> /etc/rsyslog.conf
echo local4.=info /var/log/l4i.log >> /etc/rsyslog.conf
service rsyslog restart
```

#### On both:

```
logger -p local4.error "14 error test"
logger -p local4.alert "14 alert test"
logger -p local4.info "14 info test"
cat /var/log/l4e.log
cat /var/log/l4i.log
```

6. Configure /var/log/Mysu.log, all the su to root messages should go in that log. Test that it works!

```
echo authpriv.* /var/log/Mysu.log >> /etc/syslog.conf
```

This will log more than just the **su** usage.

7. Send the local5 messages to the syslog server of your neighbour. Test that it works.

On RHEL5, edit /etc/sysconfig/syslog to enable remote listening on the server.

On RHEL7, uncomment these two lines in /etc/rsyslog.conf to enable 'UDP syslog reception'.

```
# Provides UDP syslog reception
$ModLoad imudp
$UDPServerRun 514
```

On Debian/Ubuntu edit /etc/default/syslog or /etc/default/rsyslog.

```
on the client: logger -p local5.info "test local5 to neighbour"
```

8. Write a script that executes logger to local4 every 15 seconds (different message). Use tail -f and watch on your local4 log files.

```
root@rhel53 scripts# cat logloop
#!/bin/bash

for i in `seq 1 10`
do
logger -p local4.info "local4.info test number $i"
sleep 15
done

root@rhel53 scripts# chmod +x logloop
root@rhel53 scripts# ./logloop &
[1] 8264
root@rhel53 scripts# tail -f /var/log/local4.all.log
Mar 28 13:13:36 rhel53 root: local4.info test number 1
Mar 28 13:13:51 rhel53 root: local4.info test number 2
...
```

# Chapter 18. memory management

This chapter will tell you how to manage RAM memory and cache.

We start with some simple tools to display information about memory: **free -om**, **top** and **cat/proc/meminfo**.

We continue with managing swap space, using terms like **swapping**, **paging** and **virtual memory**.

The last part is about using **vmstat** to monitor swap usage.

### 18.1. displaying memory and cache

### 18.1.1. /proc/meminfo

Displaying /proc/meminfo will tell you a lot about the memory on your Linux computer.

The first line contains the total amount of physical RAM, the second line is the unused RAM. **Buffers** is RAM used for buffering files, **cached** is the amount of RAM used as cache and **SwapCached** is the amount of swap used as cache. The file gives us much more information outside of the scope of this course.

#### 18.1.2. free

The **free** tool can display the information provided by /**proc/meminfo** in a more readable format. The example below displays brief memory information in megabytes.

```
paul@ubu1010:~$ free -om
                 used
                                                    buffers
          total
                                 free
                                          shared
                                                                cached
Mem:
           3740
                      3519
                                  221
                                               0
                                                         42
                                                                  1994
Swap:
           6234
                        82
                                 6152
```

#### 18.1.3. top

The **top** tool is often used to look at processes consuming most of the cpu, but it also displays memory information on line four and five (which can be toggled by pressing **m**).

Below a screenshot of top on the same ubu1010 from above.

```
top - 10:44:34 up 16 days, 9:56, 6 users, load average: 0.13, 0.09, 0.12
Tasks: 166 total, 1 running, 165 sleeping, 0 stopped, 0 zombie
Cpu(s): 5.1%us, 4.6%sy, 0.6%ni, 88.7%id, 0.8%wa, 0.0%hi, 0.3%si, 0.0%st
Mem: 3830176k total, 3613720k used, 216456k free, 45452k buffers
Swap: 6384636k total, 84988k used, 6299648k free, 2050948k cached
```

### 18.2. managing swap space

### 18.2.1. about swap space

When the operating system needs more memory than physically present in RAM, it can use **swap space**. Swap space is located on slower but cheaper memory. Notice that, although hard disks are commonly used for swap space, their access times are one hundred thousand times slower.

The swap space can be a file, a partition, or a combination of files and partitions. You can see the swap space with the **free** command, or with **cat /proc/swaps**.

```
paul@ubu1010:~$ free -o | grep -v Mem
                                                    buffers
          total
                      used
                                 free
                                          shared
                                                                cached
        6384636
                     84988
                              6299648
Swap:
paul@ubu1010:~$ cat /proc/swaps
Filename
                       Type
                                       Size
                                                Used
                                                       Priority
                       partition
                                       6384636 84988 -1
```

The amount of swap space that you need depends heavily on the services that the computer provides.

### 18.2.2. creating a swap partition

You can activate or deactivate swap space with the **swapon** and **swapoff** commands. New swap space can be created with the **mkswap** command. The screenshot below shows the creation and activation of a swap partition.

Now you can see that /proc/swaps displays all swap spaces separately, whereas the free - om command only makes a human readable summary.

```
root@RHELv4u4:~# cat /proc/swaps
                                                         Priority
Filename
                               Type
                                          Size
                                                  Used
/dev/mapper/VolGroup00-LogVol01
                               partition
                                          1048568 0
                                                         -1
                                          524120 0
                                                         - 2
/dev/hda1
                               partition
root@RHELv4u4:~# free -om
                               shared buffers
        total used
                         free
                                                 cached
Mem:
         249
                  245
                         4
                                   0
                                            125
                                                      54
                         1535
Swap:
      1535
```

### 18.2.3. creating a swap file

Here is one more example showing you how to create a **swap file**. On Solaris you can use **mkfile** instead of **dd**.

```
root@RHELv4u4:~# dd if=/dev/zero of=/smallswapfile bs=1024 count=4096
4096+0 records in
4096+0 records out
root@RHELv4u4:~# mkswap /smallswapfile
Setting up swapspace version 1, size = 4190 kB
root@RHELv4u4:~# swapon /smallswapfile
root@RHELv4u4:~# cat /proc/swaps
                                              Size
                                                      Used
                                                             Priority
Filename
                                  Type
/dev/mapper/VolGroup00-LogVol01
                                  partition
                                              1048568 0
                                                             -1
                                  partition
/dev/hda1
                                              524120 0
                                                              -2
/smallswapfile
                                  file
                                              4088
                                                              -3
```

### 18.2.4. swap space in /etc/fstab

If you like these swaps to be permanent, then don't forget to add them to /etc/fstab. The lines in /etc/fstab will be similar to the following.

```
/dev/hdal swap swap defaults 0 0 /smallswapfile swap swap defaults 0 0
```

## 18.3. monitoring memory with vmstat

You can find information about swap usage using vmstat.

Below a simple **vmstat** displaying information in megabytes.

```
paul@ubu1010:~$ vmstat -S m

procs -----memory------ ---swap-- ----io---- -system- ----cpu---

r b swpd free buff cache si so bi bo in cs us sy id wa

0 0 87 225 46 2097 0 0 2 5 14 8 6 5 89 1
```

Below a sample **vmstat** when (in another terminal) root launches a **find** /. It generates a lot of disk i/o (bi and bo are disk blocks in and out). There is no need for swapping here.

Below a sample **vmstat** when executing (on RHEL6) a simple memory leaking program. Now you see a lot of memory being swapped (si is 'swapped in').

```
[paul@rhel6c ~]$ vmstat 2 100

procs ------memory------ ---swap-- ---io--- --system-- ----cpu----
r b swpd free buff cache si so bi bo in cs us sy id wa st
0 3 245208 5280 232 1916 261 0 0 42 27 21 0 1 98 1 0
0 2 263372 4800 72 908 143840 128 0 1138 462 191 2 10 0 88 0
1 3 350672 4792 56 992 169280 256 0 1092 360 142 1 13 0 86 0
1 4 449584 4788 56 1024 95880 64 0 606 471 191 2 13 0 85 0
0 4 471968 4828 56 1140 44832 80 0 390 235 90 2 12 0 87 0
3 5 505960 4764 56 1136 68008 16 0 538 286 109 1 12 0 87 0
```

The code below was used to simulate a memory leak (and force swapping). This code was found on wikipedia without author.

```
paul@mac:~$ cat memleak.c
#include <stdlib.h>

int main(void)
{
    while (malloc(50));
    return 0;
}
```

## 18.4. practice: memory

- 1. Use **dmesg** to find the total amount of memory in your computer.
- 2. Use **free** to display memory usage in kilobytes (then in megabytes).
- 3. On a virtual machine, create a swap partition (you might need an extra virtual disk for this).
- 4. Add a 20 megabyte swap file to the system.
- 5. Put all swap spaces in /etc/fstab and activate them. Test with a reboot that they are mounted.
- 6. Use **free** to verify usage of current swap.
- 7. (optional) Display the usage of swap with **vmstat** and **free -s** during a memory leak.

### 18.5. solution: memory

1. Use **dmesg** to find the total amount of memory in your computer.

```
dmesg | grep Memory
```

2. Use **free** to display memory usage in kilobytes (then in megabytes).

```
free ; free -m
```

3. On a virtual machine, create a swap partition (you might need an extra virtual disk for this).

```
mkswap /dev/sdd1 ; swapon /dev/sdd1
```

4. Add a 20 megabyte swap file to the system.

```
dd if=/dev/zero of=/swapfile20mb bs=1024 count=20000
mkswap /swapfile20mb
swapon /swapfile20mb
```

5. Put all swap spaces in /etc/fstab and activate them. Test with a reboot that they are mounted.

```
root@computer# tail -2 /etc/fstab
/dev/sdd1 swap swap defaults 0 0
/swapfile20mb swap swap defaults 0 0
```

6. Use **free** to verify usage of current swap.

```
free -om
```

7. (optional) Display the usage of swap with **vmstat** and **free -s** during a memory leak.

# Chapter 19. resource monitoring

Monitoring is the process of obtaining information about the utilization of memory, cpu, bandwidth and storage. You should start monitoring your system as soon as possible, to be able to create a **baseline**. Make sure that you get to know your system! This baseline is important because it allows you to see a steady or sudden growth in **resource utilization** and likewise steady (or sudden) decline in **resource availability**. It will allow you to plan for scaling up or scaling out.

Let us look at some tools that go beyond **ps fax**, **df -h**, **free -om** and **du -sh**.

#### 19.1. four basic resources

The four basic resources to monitor are:

- cpu
- · network
- · ram memory
- storage

### 19.2. top

To start monitoring, you can use **top**. This tool will monitor ram memory, cpu and swap. Top will automatically refresh. Inside **top** you can use many commands, like **k** to kill processes, or **t** and **m** to toggle displaying task and memory information, or the number **1** to have one line per cpu, or one summary line for all cpu's.

```
top - 12:23:16 up 2 days, 4:01, 2 users, load average: 0.00, 0.00, 0.00
Tasks: 61 total, 1 running, 60 sleeping, 0 stopped, 0 zombie
Cpu(s): 0.3% us, 0.5% sy, 0.0% ni, 98.9% id, 0.2% wa, 0.0% hi, 0.0% si
Mem:
                                   255972k total, 240952k used, 15020k free,
                                                                                                                                                                                                                                                                                                    59024k buffers
 Swap: 524280k total,
                                                                                                                                              144k used,
                                                                                                                                                                                                                  524136k free,
                                                                                                                                                                                                                                                                                                    112356k cached
PID USER PR NI VIRT RES SHR S &CPU & PREPARATION TO THE PROPERTY OF THE PROPER
                                                                                                                                                                                                                                                               TIME+ COMMAND
                                                    16 0 2816 560 480 S 0.0 0.2 0:00.91 init

34 19 0 0 0 S 0.0 0.0 0:00.01 ksoftirqd/0

5 -10 0 0 0 S 0.0 0.0 0:00.57 events/0

5 -10 0 0 0 S 0.0 0.0 0:00.00 khelper

15 -10 0 0 0 S 0.0 0.0 0:00.00 kacpid

5 -10 0 0 0 S 0.0 0.0 0:00.08 kblockd/0

15 0 0 0 S 0.0 0.0 0:02.86 pdflush
    4 root
    5 root
 16 root
 26 root
```

You can customize top to display the columns of your choice, or to display only the processes that you find interesting.

```
[paul@RHELv4u3 ~]$ top p 3456 p 8732 p 9654
```

### 19.3. free

The **free** command is common on Linux to monitor free memory. You can use free to display information every x seconds, but the output is not ideal.

| [paul@RHE             | Lv4u3 gen]: | \$ free -om | -s 10  |         |        |     |  |  |
|-----------------------|-------------|-------------|--------|---------|--------|-----|--|--|
| total                 | used        | free        | shared | buffers | cached |     |  |  |
| Mem:                  | 249         | 222         | 27     | 0       | 50     | 109 |  |  |
| Swap:                 | 511         | 0           | 511    |         |        |     |  |  |
|                       |             |             |        |         |        |     |  |  |
| total                 | used        | free        | shared | buffers | cached |     |  |  |
| Mem:                  | 249         | 222         | 27     | 0       | 50     | 109 |  |  |
| Swap:                 | 511         | 0           | 511    |         |        |     |  |  |
|                       |             |             |        |         |        |     |  |  |
| [paul@RHELv4u3 gen]\$ |             |             |        |         |        |     |  |  |

#### 19.4. watch

It might be more interesting to combine free with the **watch** program. This program can run commands with a delay, and can highlight changes (with the -d switch).

```
[paul@RHELv4u3 ~]$ watch -d -n 3 free -om
Every 3.0s: free -om
                                          Sat Jan 27 12:13:03 2007
          used
                   free
total
                           shared
                                    buffers
                                              cached
Mem:
          249
                    230
                           19
                                               56
                                                             109
Swap:
```

#### 19.5. vmstat

To monitor CPU, disk and memory statistics in one line there is **vmstat**. The screenshot below shows vmstat running every two seconds 100 times (or until the Ctrl-C). Below the r, you see the number of processes waiting for the CPU, sleeping processes go below b. Swap usage (swpd) stayed constant at 144 kilobytes, free memory dropped from 16.7MB to 12.9MB. See man vmstat for the rest.

```
[paul@RHELv4u3 ~]$ vmstat 2 100
procs -----memory----- --swap-- ---io--- --system-- ---cpu----
r b swpd free
                   buff cache si so bi bo
                                                   in cs us sy id wa
                                             4

    144
    16708
    58212
    111612
    0
    0
    3
    4
    75

    144
    16708
    58212
    111612
    0
    0
    0
    0
    976

    144
    16708
    58212
    111612
    0
    0
    0
    0
    958

                                                          62 0 1 99
0
  0
                                                          22
                                                              0
                                                                 0 100 0
                                                         14 0 1 99 0
0
  0
      144 16528 58212 111612 0 0 0 18 1432
                                                        7417 1 32 66
1
  0
     144 16468 58212 111612 0 0 0
1
  Ω
                                              0 2910 20048 4 95 1
     144 16408 58212 111612 0 0 0 0 3210 19509 4 97
1
  0
1
     144 15568 58816 111612 0 0 300 1632 2423 10189 2 62 0 36
     144 13648 60324 111612 0 0 754 0 1910 2843 1 27 0 72
0
 0
     144 12928 60948 111612 0 0 312 418 1346 1258 0 14 57 29
0 0
     144 12928 60948 111612 0 0 0 0 977 19 0 0 100 0
      144 12988 60948 111612 0 0 0 977
                                                        15 0 0 100 0
0 0
      144 12988 60948 111612 0 0 0 0 978 18 0 0 100 0
[paul@RHELv4u3 ~]$
```

### 19.6. iostat

The **iostat** tool can display disk and cpu statistics. The -d switch below makes iostat only display disk information (500 times every two seconds). The first block displays statistics since the last reboot.

| [paul@RHELv4                             | u3 ~]\$ io | ostat -d 2 500 | )          |          |          |
|--|------------|----------------|------------|----------|----------|
| Linux 2.6.9-34.EL (RHELv4u3.localdomain) |            |                | 01/27/2007 |          |          |
|  |            |                |            |          |          |
| Device:                                  | tps        | Blk_read/s     | Blk_wrtn/s | Blk_read | Blk_wrtn |
| hdc                                      | 0.00       | 0.01           | 0.00       | 1080     | 0        |
| sda                                      | 0.52       | 5.07           | 7.78       | 941798   | 1445148  |
| sda1                                     | 0.00       | 0.01           | 0.00       | 968      | 4        |
| sda2                                     | 1.13       | 5.06           | 7.78       | 939862   | 1445144  |
| dm-0                                     | 1.13       | 5.05           | 7.77       | 939034   | 1444856  |
| dm-1                                     | 0.00       | 0.00           | 0.00       | 360      | 288      |
|  |            |                |            |          |          |
| Device:                                  | tps        | Blk_read/s     | Blk_wrtn/s | Blk_read | Blk_wrtn |
| hdc                                      | 0.00       | 0.00           | 0.00       | 0        | 0        |
| sda                                      | 0.00       | 0.00           | 0.00       | 0        | 0        |
| sda1                                     | 0.00       | 0.00           | 0.00       | 0        | 0        |
| sda2                                     | 0.00       | 0.00           | 0.00       | 0        | 0        |
| dm-0                                     | 0.00       | 0.00           | 0.00       | 0        | 0        |
| dm-1                                     | 0.00       | 0.00           | 0.00       | 0        | 0        |
|  |            |                |            |          |          |
| [paul@RHELv4                             | u3 ~]\$    |                |            |          |          |
| =  |            |                |            |          |          |

You can have more statistics using **iostat -d -x**, or display only cpu statistics with **iostat -c**.

```
[paul@RHELv4u3 ~]$ iostat -c 5 500
Linux 2.6.9-34.EL (RHELv4u3.localdomain)
                                         01/27/2007
avg-cpu: %user %nice %sys %iowait
                                   %idle
0.31 0.02 0.52 0.23
avg-cpu: %user %nice %sys %iowait
                                   %idle
     0.00 52.16 47.23
0.62
avg-cpu: %user %nice %sys %iowait
                                   %idle
2.92 0.00 36.95 60.13
avg-cpu: %user %nice %sys %iowait
                                   %idle
0.63 0.00 36.63 62.32
avg-cpu: %user %nice %sys %iowait
                                   %idle
0.00 0.00 0.20 0.20 99.59
[paul@RHELv4u3 ~]$
```

### 19.7. mpstat

On multi-processor machines, mpstat can display statistics for all, or for a selected cpu.

```
paul@laika:~$ mpstat -P ALL
Linux 2.6.20-3-generic (laika)
                               02/09/2007
CPU %user %nice %sys %iowait
                                 %irq %soft %steal
                                                        %idle
                                                               intr/s
all 1.77 0.03
0 1.73 0.02
1 1.81 0.03
                 1.37 1.03
                                      0.39
                                               0.00
                                 0.02
                                                        95.40
                                                              1304.91
                  1.47
                          1.93
                                 0.04
                                         0.77
                                                 0.00
                                                        94.04 1304.91
                                         0.00
                  1.27
                          0.13
                                 0.00
                                                 0.00
                                                        96.76
                                                                  0.00
paul@laika:~$
```

### 19.8. sadc and sar

The **sadc** tool writes system utilization data to /var/log/sa/sa??, where ?? is replaced with the current day of the month. By default, cron runs the **sal** script every 10 minutes, the sal script runs sadc for one second. Just before midnight every day, cron runs the **sa2** script, which in turn invokes **sar**. The sar tool will read the daily data generated by sadc and put it in /var/log/sa/sar??. These **sar reports** contain a lot of statistics.

You can also use sar to display a portion of the statistics that were gathered. Like this example for cpu statistics.

| [paul@RHELv4u3 s<br>Linux 2.6.9-34.1 |       |       | domain) | 01/25   | 7/2007  |       |
|--------------------------------------|-------|-------|---------|---------|---------|-------|
|                                      |       |       |         |         |         |       |
| 12:00:01 AM                          | CPU   | %user | %nice   | %system | %iowait | %idle |
| 12:10:01 AM                          | all   | 0.48  | 0.01    | 0.60    | 0.04    | 98.87 |
| 12:20:01 AM                          | all   | 0.49  | 0.01    | 0.60    | 0.06    | 98.84 |
| 12:30:01 AM                          | all   | 0.49  | 0.01    | 0.64    | 0.25    | 98.62 |
| 12:40:02 AM                          | all   | 0.44  | 0.01    | 0.62    | 0.07    | 98.86 |
| 12:50:01 AM                          | all   | 0.42  | 0.01    | 0.60    | 0.10    | 98.87 |
| 01:00:01 AM                          | all   | 0.47  | 0.01    | 0.65    | 0.08    | 98.80 |
| 01:10:01 AM                          | all   | 0.45  | 0.01    | 0.68    | 0.08    | 98.78 |
| [paul@RHELv4u3 s                     | sa]\$ |       |         |         |         |       |

There are other useful sar options, like **sar -I PROC** to display interrupt activity per interrupt and per CPU, or **sar -r** for memory related statistics. Check the manual page of sar for more.

### 19.9. ntop

The **ntop** tool is not present in default Red Hat installs. Once run, it will generate a very extensive analysis of network traffic in html on http://localhost:3000.

### 19.10. iftop

The **iftop** tool will display bandwidth by socket statistics for a specific network device. Not available on default Red Hat servers.

```
1.91Mb
             3.81Mb
                            5.72Mb
                                          7.63Mb 9.54Mb
                                                 4.94Kb 6.65Kb 69.9Kb
laika.local
                  => barry
                                                                766Kb
                                                 7.41Kb 16.4Kb
                  <=
                                                   0b 1.58Kb 14.4Kb
laika.local
                  => ik-in-f19.google.com
                                                    0b
                                                         292b
                                                                41.0Kb
laika.local
                  => ik-in-f99.google.com
                                                    0b
                                                           83b
                                                                4.01Kb
                                                    0b
                                                           83b
                                                                39.8Kb
laika.local
                  => ug-in-f189.google.com
                                                    0b
                                                           42b
                                                                  664b
                  <=
                                                    0b
                                                           42b
                                                                  406b
laika.local
                  => 10.0.0.138
                                                                  149b
                                                    0b
                                                            0b
                                                    0b
                                                            0b
                                                                  256b
                  <=
laika.local
                  => 224.0.0.251
                                                    0b
                                                            0b
                                                                   86b
                                                                   0b
laika.local
                  => ik-in-f83.google.com
                                                    0b
                                                            0b
                                                                   39b
                                                    0b
                                                            0b
                                                                   21b
```

## 19.11. iptraf

Use **iptraf** for a colourful display of ip traffic over the network cards.

```
[root@centos65 ~]# iptraf
[root@centos65 ~]# iptraf -i eth0
```

#### 19.12. nmon

Another popular and all round tool is **nmon**.

### 19.13. htop

You can use **htop** instead of top.

```
Tasks: 83, 167 thr; 1 running
                                                                          Load average: 0.66 0.34 0.26
                                                                          Uptime: 05:13:03
                                      2270M
24732
543M
                                                                                          2:11.71 /usr/lib/virtualbox/Vir
0:00.54 htop
0:35.59 xfce4-terminal
                                                                                  5.4
0.0
                           20
20
20
20
20
20
20
20
20
20
20
                                                 2496
19156
26485 root
                                    Θ
                                                             1444
 3375 paul
                                                            12140
26495
19427
                                    0
                                                                                           0:00.08 xfce4-screenshooter
0:15.51 /usr/lib/virtualbox/Vi
0:11.68 /usr/lib/virtualbox/Vi
                                        379M
                                                 13684
                                                           10676
                                                                                  0.2
                                      2270M
                                                             388M
                                    Θ
                                                                                  0.5
19264
                                       1005M
                                                 41668
                                                           30172
                                                                                           3:46.55 /usr/lib/virtualbox/vir
1:00.14 /usr/lib/virtualbox/Vir
0:12.83 /usr/lib/virtualbox/VB
0:10.92 /usr/lib/virtualbox/Vir
 2714 root
                                    Θ
                                                 26704
                                                           13984
                                                                          0.0
 19448
                                       2270M
                                                                          0.0
         paul
19279 paul
                                                 12128
                                                                          0.0
                                                                                  0.1
                                                             7624
19462 paul
                                       2270M
                                                                          0.0
                                                  423N
                                                                                           0:01.69 xfdesktop --display :0.
0:06.19 /usr/lib/virtualbox/VBo
 3044 paul
                                        591M 30132
                                                                                  0.4
                                                           12860
                                                                          0.0
19274 paul
                            20
                                         103M
                                                  6048
                                                             3820
                                                                          0.0
                                                                                  0.1
                                                 12128
                                         636M
                                                             7624
                                                                                           0:05.49
                                                                                                         /usr/lib/virtualbox/VE
 3401 paul
                                                             1208
                           20
20
20
20
20
                                       <del>30</del>356
                                                  6328
                                                                          0.0
                                                                                  0.1
                                                                                           0:13.10 tmux
                                                                                          0:13.10 tmux

0:05.62 xfwm4 --display :0.0 --

0:03.55 /usr/lib/virtualbox/Vir

0:00.67 x-session-manager

0:02.75 /usr/lib/virtualbox/Vir
                                                 12924
                                                             9728
                                                                          0.0
                                                                                  0.2
 3038 paul
                                    0
19426 paul
                                    Θ
                                       2270M
                                                  423M
                                                             388M
                                                                          0.0
3027 paul
19276 paul
                                                           5812
30172
                                                  8592
                                    Θ
                                                                          0.0
                                    Θ
                                       1005M 41668
                                                                          0.0
                                                                                           0:03.68 xfce4-panel --display
```

# Chapter 20. package management

Most Linux distributions have a **package management** system with online **repositories** containing thousands of packages. This makes it very easy to install and remove applications, operating system components, documentation and much more.

We first discuss the Debian package format .deb and its tools dpkg, apt-get and aptitude. This should be similar on Debian, Ubuntu, Mint and all derived distributions.

Then we look at the Red Hat package format **.rpm** and its tools **rpm** and **yum**. This should be similar on Red Hat, Fedora, CentOS and all derived distributions.

### 20.1. package terminology

### 20.1.1. repository

A lot of software and documentation for your Linux distribution is available as **packages** in one or more centrally distributed **repositories**. These **packages** in such a **repository** are tested and very easy to install (or remove) with a graphical or command line installer.

#### 20.1.2. .deb packages

Debian, Ubuntu, Mint and all derivatives from Debian and Ubuntu use .deb packages. To manage software on these systems, you can use aptitude or apt-get, both these tools are a front end for dpkg.

### 20.1.3. .rpm packages

Red Hat, Fedora, CentOS, OpenSUSE, Mandriva, Red Flag and others use .rpm packages. The tools to manage software packages on these systems are yum and rpm.

### 20.1.4. dependency

Some packages need other packages to function. Tools like **apt-get**, **aptitude** and **yum** will install all **dependencies** you need. When using **dpkg** or **rpm**, or when building from **source**, you will need to install dependencies yourself.

### 20.1.5. open source


These repositories contain a lot of independent **open source software**. Often the source code is customized to integrate better with your distribution. Most distributions also offer this modified source code as a **package** in one or more **source repositories**.

You are free to go to the project website itself (samba.org, apache.org, github.com, ...) an download the **vanilla** (= without the custom distribution changes) source code.

### 20.1.6. GUI software management

End users have several graphical applications available via the desktop (look for 'add/remove software' or something similar).

Below a screenshot of Ubuntu Software Center running on Ubuntu 12.04. Graphical tools are not discussed in this book.



### 20.2. deb package management

#### 20.2.1. about deb

Most people use **aptitude** or **apt-get** to manage their Debian/Ubuntu family of Linux distributions. Both are a front end for **dpkg** and are themselves a back end for **synaptic** and other graphical tools.

### 20.2.2. dpkg -l

The low level tool to work with **.deb** packages is **dpkg**. Here you see how to obtain a list of all installed packages on a Debian server.

```
root@debian6:~# dpkg -l | wc -l
265
```

Compare this to the same list on a Ubuntu Desktop computer.

```
root@ubu1204~# dpkg -1 | wc -1
2527
```

### 20.2.3. dpkg -I \$package

Here is an example on how to get information on an individual package. The ii at the beginning means the package is installed.

```
root@debian6:~# dpkg -l rsync | tail -1 | tr -s ' '
ii rsync 3.0.7-2 fast remote file copy program (like rcp)
```

### 20.2.4. dpkg -S

You can find the package that installed a certain file on your computer with **dpkg -S**. This example shows how to find the package for three files on a typical Debian server.

```
root@debian6:~# dpkg -S /usr/share/doc/tmux/ /etc/ssh/ssh_config /sbin/ifconfig
tmux: /usr/share/doc/tmux/
openssh-client: /etc/ssh/ssh_config
net-tools: /sbin/ifconfig
```

#### 20.2.5. dpkg -L

You can also get a list of all files that are installed by a certain program. Below is the list for the **tmux** package.

```
root@debian6:~# dpkg -L tmux
/.
/etc
/etc/init.d
/etc/init.d/tmux-cleanup
/usr
/usr/share
/usr/share/lintian
/usr/share/lintian/overrides
/usr/share/lintian/overrides/tmux
/usr/share/doc
```

```
/usr/share/doc/tmux
/usr/share/doc/tmux/TODO.gz
/usr/share/doc/tmux/FAQ.qz
/usr/share/doc/tmux/changelog.Debian.gz
/usr/share/doc/tmux/NEWS.Debian.gz
/usr/share/doc/tmux/changelog.gz
/usr/share/doc/tmux/copyright
/usr/share/doc/tmux/examples
/usr/share/doc/tmux/examples/tmux.vim.gz
/usr/share/doc/tmux/examples/h-boetes.conf
/usr/share/doc/tmux/examples/n-marriott.conf
/usr/share/doc/tmux/examples/screen-keys.conf
/usr/share/doc/tmux/examples/t-williams.conf
/usr/share/doc/tmux/examples/vim-keys.conf
/usr/share/doc/tmux/NOTES
/usr/share/man
/usr/share/man/man1
/usr/share/man/man1/tmux.1.gz
/usr/bin
/usr/bin/tmux
```

#### 20.2.6. dpkg

You could use **dpkg -i** to install a package and **dpkg -r** to remove a package, but you'd have to manually keep track of dependencies. Using **apt-get** or **aptitude** is much easier.

### 20.3. apt-get

**Debian** has been using **apt-get** to manage packages since 1998. Today Debian and many Debian-based distributions still actively support **apt-get**, though some experts claim **aptitude** is better at handling dependencies than **apt-get**.

Both commands use the same configuration files and can be used alternately; whenever you see **apt-get** in documentation, feel free to type **aptitude**.

We will start with **apt-get** and discuss **aptitude** in the next section.

### 20.3.1. apt-get update

When typing **apt-get update** you are downloading the names, versions and short description of all packages available on all configured repositories for your system.

In the example below you can see some repositories at the url **be.archive.ubuntu.com** because this computer was installed in Belgium. This url can be different for you.

```
root@ubul204~# apt-get update

Ign http://be.archive.ubuntu.com precise InRelease

Ign http://extras.ubuntu.com precise InRelease

Ign http://security.ubuntu.com precise-security InRelease

Ign http://archive.canonical.com precise InRelease

Ign http://be.archive.ubuntu.com precise-updates InRelease

...

Hit http://be.archive.ubuntu.com precise-backports/main Translation-en

Hit http://be.archive.ubuntu.com precise-backports/multiverse Translation-en

Hit http://be.archive.ubuntu.com precise-backports/restricted Translation-en

Hit http://be.archive.ubuntu.com precise-backports/universe Translation-en

Fetched 13.7 MB in 8s (1682 kB/s)

Reading package lists... Done

root@mac~#
```

Run apt-get update every time before performing other package operations.

#### 20.3.2. apt-get upgrade

One of the nicest features of **apt-get** is that it allows for a secure update of **all software** currently installed on your computer with just **one** command.

```
root@debian6:~# apt-get upgrade
Reading package lists... Done
Building dependency tree
Reading state information... Done
0 upgraded, 0 newly installed, 0 to remove and 0 not upgraded.
root@debian6:~#
```

The above screenshot shows that all software is updated to the latest version available for my distribution.

### 20.3.3. apt-get clean

**apt-get** keeps a copy of downloaded packages in /var/cache/apt/archives, as can be seen in this screenshot.

```
root@ubu1204~# ls /var/cache/apt/archives/ | head accountsservice_0.6.15-2ubuntu9.4_i386.deb apport_2.0.1-0ubuntu14_all.deb apport_gtk_2.0.1-0ubuntu14_all.deb apt_0.8.16~exp12ubuntu10.3_i386.deb apt_transport_https_0.8.16~exp12ubuntu10.3_i386.deb apt_utils_0.8.16~exp12ubuntu10.3_i386.deb bind9-host_1%3a9.8.1.dfsg.P1-4ubuntu0.4_i386.deb chromium-browser_20.0.1132.47~r144678-0ubuntu0.12.04.1_i386.deb chromium-browser-l10n_20.0.1132.47~r144678-0ubuntu0.12.04.1_all.deb chromium-codecs-ffmpeg_20.0.1132.47~r144678-0ubuntu0.12.04.1_i386.deb
```

Running **apt-get clean** removes all .deb files from that directory.

```
root@ubu1204~# apt-get clean
root@ubu1204~# ls /var/cache/apt/archives/*.deb
ls: cannot access /var/cache/apt/archives/*.deb: No such file or directory
```

### 20.3.4. apt-cache search

Use **apt-cache search** to search for availability of a package. Here we look for **rsync**.

```
root@ubu1204~# apt-cache search rsync | grep ^rsync
rsync - fast, versatile, remote (and local) file-copying tool
rsyncrypto - rsync friendly encryption
```

### 20.3.5. apt-get install

You can install one or more applications by appending their name behind **apt-get install**. The screenshot shows how to install the **rsync** package.

```
root@ubu1204~# apt-get install rsync
Reading package lists... Done
Building dependency tree
Reading state information... Done
The following NEW packages will be installed:
0 upgraded, 1 newly installed, 0 to remove and 8 not upgraded.
Need to get 299 kB of archives.
After this operation, 634 kB of additional disk space will be used.
Get:1 http://be.archive.ubuntu.com/ubuntu/ precise/main rsync i386 3.0.9-lubuntu1 [299 kB]
Fetched 299 kB in 0s (740 kB/s)
Selecting previously unselected package rsync.
(Reading database ... 323649 files and directories currently installed.)
Unpacking rsync (from .../rsync_3.0.9-lubuntu1_i386.deb) ...
Processing triggers for man-db ...
Processing triggers for ureadahead ...
Setting up rsync (3.0.9-lubuntul) ...
Removing any system startup links for /etc/init.d/rsync ...
root@ubu1204~#
```

#### 20.3.6. apt-get remove

You can remove one or more applications by appending their name behind **apt-get remove**. The screenshot shows how to remove the **rsync** package.

```
root@ubu1204~# apt-get remove rsync
Reading package lists... Done
Building dependency tree
Reading state information... Done
```

```
The following packages will be REMOVED:
    rsync ubuntu-standard

0 upgraded, 0 newly installed, 2 to remove and 8 not upgraded.

After this operation, 692 kB disk space will be freed.

Do you want to continue [Y/n]?

(Reading database ... 323681 files and directories currently installed.)

Removing ubuntu-standard ...

Removing rsync ...

* Stopping rsync daemon rsync

Processing triggers for ureadahead ...

Processing triggers for man-db ...

root@ubu1204~#
```

Note however that some configuration information is not removed.

```
root@ubu1204~# dpkg -l rsync | tail -l | tr -s ' '
rc rsync 3.0.9-lubuntul fast, versatile, remote (and local) file-copying tool
```

#### 20.3.7. apt-get purge

You can purge one or more applications by appending their name behind **apt-get purge**. Purging will also remove all existing configuration files related to that application. The screenshot shows how to purge the **rsync** package.

```
root@ubu1204~# apt-get purge rsync
Reading package lists... Done
Building dependency tree
Reading state information... Done
The following packages will be REMOVED:
    rsync*
0 upgraded, 0 newly installed, 1 to remove and 8 not upgraded.
After this operation, 0 B of additional disk space will be used.
Do you want to continue [Y/n]?
(Reading database ... 323651 files and directories currently installed.)
Removing rsync ...
Purging configuration files for rsync ...
Processing triggers for ureadahead ...
root@ubu1204~#
```

Note that **dpkg** has no information about a purged package, except that it is uninstalled and no configuration is left on the system.

```
root@ubu1204~# dpkg -l rsync | tail -1 | tr -s ' '
un rsync <none> (no description available)
```

### 20.4. aptitude

Most people use aptitude for package management on Debian, Mint and Ubuntu systems.

To synchronize with the repositories.

aptitude update

To patch and upgrade all software to the latest version on Debian.

aptitude upgrade

To patch and upgrade all software to the latest version on Ubuntu and Mint.

aptitude safe-upgrade

To install an application with all dependencies.

aptitude install \$package

To search the repositories for applications that contain a certain string in their name or description.

aptitude search \$string

To remove an application.

aptitude remove \$package

To remove an application and all configuration files.

aptitude purge \$package

### 20.5. apt

Both **apt-get** and **aptitude** use the same configuration information in **/etc/apt/**. Thus adding a repository for one of them, will automatically add it for both.

### 20.5.1. /etc/apt/sources.list

The resource list used by **apt-get** and **aptitude** is located in /etc/apt/sources.list. This file contains a list of http or ftp sources where packages for the distribution can be downloaded.

This is what that list looks like on my Debian server.

```
root@debian6:~# cat /etc/apt/sources.list
deb http://ftp.be.debian.org/debian/ squeeze main
deb-src http://ftp.be.debian.org/debian/ squeeze main

deb http://security.debian.org/ squeeze/updates main
deb-src http://security.debian.org/ squeeze/updates main

# squeeze-updates, previously known as 'volatile'
deb http://ftp.be.debian.org/debian/ squeeze-updates main
deb-src http://ftp.be.debian.org/debian/ squeeze-updates main
```

On my Ubuntu there are four times as many online repositories in use.

```
root@ubu1204~# wc -l /etc/apt/sources.list
63 /etc/apt/sources.list
```

There is much more to learn about apt, explore commands like add-apt-repository, aptkey and apropos apt.

### 20.6. rpm

#### 20.6.1. about rpm

The **Red Hat package manager** can be used on the command line with **rpm** or in a graphical way going to Applications--System Settings--Add/Remove Applications. Type **rpm --help** to see some of the options.

Software distributed in the **rpm** format will be named **foo-version.platform.rpm**.

#### 20.6.2. rpm -qa

To obtain a list of all installed software, use the **rpm** -qa command.

```
[root@RHEL52 ~]# rpm -qa | grep samba

system-config-samba-1.2.39-1.el5

samba-3.0.28-1.el5_2.1

samba-client-3.0.28-1.el5_2.1

samba-common-3.0.28-1.el5_2.1
```

#### 20.6.3. rpm -q

To verify whether one package is installed, use **rpm** -q.

```
root@RHELv4u4:~# rpm -q gcc
gcc-3.4.6-3
root@RHELv4u4:~# rpm -q laika
package laika is not installed
```

#### 20.6.4. rpm -Uvh

To install or upgrade a package, use the -Uvh switches. The -U switch is the same as -i for install, except that older versions of the software are removed. The -vh switches are for nicer output.

```
root@RHELv4u4:~# rpm -Uvh gcc-3.4.6-3
```

#### 20.6.5. rpm -e

To remove a package, use the -e switch.

```
root@RHELv4u4:~# rpm -e gcc-3.4.6-3
```

**rpm** -e verifies dependencies, and thus will prevent you from accidentailly erasing packages that are needed by other packages.

```
[root@RHEL52 ~]# rpm -e gcc-4.1.2-42.el5
error: Failed dependencies:
gcc = 4.1.2-42.el5 is needed by (installed) gcc-c++-4.1.2-42.el5.i386
gcc = 4.1.2-42.el5 is needed by (installed) gcc-gfortran-4.1.2-42.el5.i386
gcc is needed by (installed) systemtap-0.6.2-1.el5_2.2.i386
```

### 20.6.6. /var/lib/rpm

The **rpm** database is located at **/var/lib/rpm**. This database contains all meta information about packages that are installed (via rpm). It keeps track of all files, which enables complete removes of software.

### 20.6.7. rpm2cpio

We can use **rpm2cpio** to convert an **rpm** to a **cpio** archive.

```
[root@RHEL53 ~]# file kernel.src.rpm
kernel.src.rpm: RPM v3 src PowerPC kernel-2.6.18-92.1.13.el5
[root@RHEL53 ~]# rpm2cpio kernel.src.rpm > kernel.cpio
[root@RHEL53 ~]# file kernel.cpio
kernel.cpio: ASCII cpio archive (SVR4 with no CRC)
```

But why would you want to do this?

Perhaps just to see of list of files in the **rpm** file.

```
[root@RHEL53 ~]# rpm2cpio kernel.src.rpm | cpio -t | head -5
COPYING.modules
Config.mk
Module.kabi_i686
Module.kabi_i686PAE
Module.kabi_i686xen
```

Or to extract one file from an **rpm** package.

```
[root@RHEL53 ~]# rpm2cpio kernel.src.rpm | cpio -iv Config.mk
Config.mk
246098 blocks
```

### 20.7. yum

### 20.7.1. about yum

The Yellowdog Updater, Modified (yum) is an easier command to work with rpm packages. It is installed by default on Fedora and Red Hat Enterprise Linux since version 5.2.

#### 20.7.2. yum list

Issue **yum list available** to see a list of available packages. The **available** parameter is optional.

```
root@rhel65:/etc# yum list | wc -l
This system is receiving updates from Red Hat Subscription Management.
3935
root@rhel65:/etc#
```

Issue yum list \$package to get all versions (in different repositories) of one package.

### 20.7.3. yum search

To search for a package containing a certain string in the description or name use **yum search \$string**.

### 20.7.4. yum provides

To search for a package containing a certain file (you might need for compiling things) use **yum provides \$filename**.

```
root@rhel65:/etc# yum provides /usr/share/man/man5/passwd.5.gz
Loaded plugins: product-id, subscription-manager
This system is receiving updates from Red Hat Subscription Management.
rhel-6-server-cf-tools-1-rpms
                                                             | 2.8 kB
rhel-6-server-rpms
                                                             3.7 kB
                                                                         00:00
man-pages-3.22-12.el6.noarch : Man (manual) pages from the Linux Documenta...
       : rhel-6-server-rpms
Matched from:
Filename
          : /usr/share/man/man5/passwd.5.gz
man-pages-3.22-20.el6.noarch : Man (manual) pages from the Linux Documenta...
      : rhel-6-server-rpms
Matched from:
Filename : /usr/share/man/man5/passwd.5.gz
man-pages-3.22-17.el6.noarch : Man (manual) pages from the Linux Documenta...
Repo : rhel-6-server-rpms
Matched from:
Filename : /usr/share/man/man5/passwd.5.gz
man-pages-3.22-20.el6.noarch : Man (manual) pages from the Linux Documenta...
      : installed
Matched from:
           : Provides-match: /usr/share/man/man5/passwd.5.gz
root@rhel65:/etc#
```

### 20.7.5. yum install

To install an application, use **yum install \$package**. Naturally **yum** will install all the necessary dependencies.

```
[root@rhel55 ~]# yum install sudo
Loaded plugins: rhnplugin, security
Setting up Install Process
Resolving Dependencies
--> Running transaction check
---> Package sudo.i386 0:1.7.2p1-7.el5_5 set to be updated
--> Finished Dependency Resolution
Dependencies Resolved
______
Package Arch Version
                                Repository
______
Installing:
sudo
         i386 1.7.2p1-7.el5_5 rhel-i386-server-5
                                                    230 k
Transaction Summary
______
Install 1 Package(s)
Upgrade 0 Package(s)
          0 Package(s)
Total download size: 230 k
Is this ok [y/N]: y
Downloading Packages:
sudo-1.7.2p1-7.el5_5.i386.rpm
                                         | 230 kB 00:00
Running rpm_check_debug
Running Transaction Test
Finished Transaction Test
Transaction Test Succeeded
Running Transaction
 Installing
                                                  1/1
Installed:
 sudo.i386 0:1.7.2p1-7.el5_5
Complete!
```

You can add more than one parameter here.

```
yum install $package1 $package2 $package3
```

#### **20.7.6.** yum update

To bring all applications up to date, by downloading and installing them, issue **yum update**. All software that was installed via **yum** will be updated to the latest version that is available in the repository.

yum update

If you only want to update one package, use yum update \$package.

```
[root@rhel55 ~]# yum update sudo
Loaded plugins: rhnplugin, security
Skipping security plugin, no data
Setting up Update Process
Resolving Dependencies
Skipping security plugin, no data
--> Running transaction check
---> Package sudo.i386 0:1.7.2p1-7.el5_5 set to be updated
--> Finished Dependency Resolution
Dependencies Resolved
______
Package Arch Version Repository Size
______
Updating:
         i386
              1.7.2p1-7.el5_5 rhel-i386-server-5
sudo
                                                230 k
Transaction Summary
______
Upgrade 1 Package(s)
Total download size: 230 k
Is this ok [y/N]: y
Downloading Packages:
                                       | 230 kB 00:00
sudo-1.7.2p1-7.el5_5.i386.rpm
Running rpm_check_debug
Running Transaction Test
Finished Transaction Test
Transaction Test Succeeded
Running Transaction
 Updating : sudo
                                                  1/2
 Cleanup
            : sudo
                                                  2/2
Updated:
 sudo.i386 0:1.7.2p1-7.el5_5
Complete!
```

### 20.7.7. yum software groups

Issue **yum grouplist** to see a list of all available software groups.

```
[root@rhel55 ~]# yum grouplist
Loaded plugins: rhnplugin, security
Setting up Group Process
Installed Groups:
  Administration Tools
  Authoring and Publishing
  DNS Name Server
  Development Libraries
  Development Tools
  Editors
  GNOME Desktop Environment
  GNOME Software Development
  Graphical Internet
  Graphics
  Legacy Network Server
  Legacy Software Development
  Legacy Software Support
  Mail Server
  Network Servers
  Office/Productivity
  Printing Support
  Server Configuration Tools
  System Tools
  Text-based Internet
  Web Server
  Windows File Server
  X Software Development
  X Window System
Available Groups:
  Engineering and Scientific
  FTP Server
  Games and Entertainment
  Java Development
  KDE (K Desktop Environment)
  KDE Software Development
  MySQL Database
  News Server
  OpenFabrics Enterprise Distribution
  PostgreSQL Database
  Sound and Video
Done
```

To install a set of applications, brought together via a group, use **yum groupinstall \$groupname**.

```
[root@rhel55 ~]# yum groupinstall 'Sound and video'
Loaded plugins: rhnplugin, security
Setting up Group Process
Package alsa-utils-1.0.17-1.el5.i386 already installed and latest version
Package sox-12.18.1-1.i386 already installed and latest version
Package 9:mkisofs-2.01-10.7.el5.i386 already installed and latest version
Package 9:cdrecord-2.01-10.7.el5.i386 already installed and latest version
Package cdrdao-1.2.1-2.i386 already installed and latest version
Resolving Dependencies
--> Running transaction check
---> Package cdda2wav.i386 9:2.01-10.7.el5 set to be updated
---> Package cdparanoia.i386 0:alpha9.8-27.2 set to be updated
---> Package sound-juicer.i386 0:2.16.0-3.el5 set to be updated
--> Processing Dependency: libmusicbrainz >= 2.1.0 for package: sound-juicer
--> Processing Dependency: libmusicbrainz.so.4 for package: sound-juicer
---> Package vorbis-tools.i386 1:1.1.1-3.el5 set to be updated
--> Processing Dependency: libao >= 0.8.4 for package: vorbis-tools
--> Processing Dependency: libao.so.2 for package: vorbis-tools
--> Running transaction check
---> Package libao.i386 0:0.8.6-7 set to be updated
---> Package libmusicbrainz.i386 0:2.1.1-4.1 set to be updated
--> Finished Dependency Resolution
```

Read the manual page of **yum** for more information about managing groups in **yum**.

### 20.7.8. /etc/yum.conf and repositories

The configuration of **yum** repositories is done in /etc/yum/yum.conf and /etc/yum/repos.d/

Configurating **yum** itself is done in **/etc/yum.conf**. This file will contain the location of a log file and a cache directory for **yum** and can also contain a list of repositories.

Recently **yum** started accepting several **repo** files with each file containing a list of **repositories**. These **repo** files are located in the /etc/yum.repos.d/ directory.

One important flag for yum is **enablerepo**. Use this command if you want to use a repository that is not enabled by default.

```
yum $command $foo --enablerepo=$repo
```

An example of the contents of the repo file: MyRepo.repo

```
[$repo]
name=My Repository
baseurl=http://path/to/MyRepo
gpgcheck=1
gpgkey=file:///etc/pki/rpm-gpg/RPM-GPG-KEY-MyRep
```

### 20.8. alien

**alien** is experimental software that converts between **rpm** and **deb** package formats (and others).

Below an example of how to use **alien** to convert an **rpm** package to a **deb** package.

```
paul@barry:~$ ls -l netcat*
  -rw-r--r-- 1 paul paul 123912 2009-06-04 14:58 netcat-0.7.1-1.i386.rpm
paul@barry:~$ alien --to-deb netcat-0.7.1-1.i386.rpm
netcat_0.7.1-2_i386.deb generated
paul@barry:~$ ls -l netcat*
  -rw-r--r-- 1 paul paul 123912 2009-06-04 14:58 netcat-0.7.1-1.i386.rpm
  -rw-r--r-- 1 root root 125236 2009-06-04 14:59 netcat_0.7.1-2_i386.deb
```

In real life, use the **netcat** tool provided by your distribution, or use the .deb file from their website.

# 20.9. downloading software outside the repository

First and most important, whenever you download software, start by reading the README file!

Normally the readme will explain what to do after download. You will probably receive a .tar.gz or a .tgz file. Read the documentation, then put the compressed file in a directory. You can use the following to find out where the package wants to install.

```
tar tvzpf $downloadedFile.tgz
```

You unpack them like with tar xzf, it will create a directory called applicationName-1.2.3

```
tar xzf $applicationName.tgz
```

Replace the z with a j when the file ends in .tar.bz2. The **tar**, **gzip** and **bzip2** commands are explained in detail in the Linux Fundamentals course.

If you download a .deb file, then you'll have to use dpkg to install it, .rpm's can be installed with the rpm command.

### 20.10. compiling software

First and most important, whenever you download source code for installation, start by reading the README file!

Usually the steps are always the same three: running ./configure followed by make (which is the actual compiling) and then by make install to copy the files to their proper location.

./configure make make install

### 20.11. practice: package management

- 1. Verify whether gcc, sudo and we noth are installed.
- 2. Use yum or aptitude to search for and install the scp, tmux, and man-pages packages. Did you find them all ?
- 3. Search the internet for 'webmin' and figure out how to install it.
- 4. If time permits, search for and install samba including the samba docs pdf files (thousands of pages in two pdf's).

### 20.12. solution: package management

1. Verify whether gcc, sudo and we noth are installed.

```
On Red Hat/CentOS:

rpm -qa | grep gcc

rpm -qa | grep sudo

rpm -qa | grep wesnoth

On Debian/Ubuntu:

dpkg -l | grep gcc

dpkg -l | grep sudo

dpkg -l | grep sudo
```

2. Use yum or aptitude to search for and install the scp, tmux, and man-pages packages. Did you find them all ?

```
On Red Hat/CentOS:
yum search scp
yum search tmux
yum search man-pages

On Debian/Ubuntu:
aptitude search scp
aptitude search tmux
aptitude search man-pages
```

3. Search the internet for 'webmin' and figure out how to install it.

```
Google should point you to webmin.com.

There are several formats available there choose .rpm, .deb or .tgz .
```

4. If time permits, search for and install samba including the samba docs pdf files (thousands of pages in two pdf's).



### **Table of Contents**

| 21. general networking                       | 253 |
|--|-----|
| 21.1. network layers                         | 254 |
| 21.2. unicast, multicast, broadcast, anycast | 257 |
| 21.3. lan-wan-man                            | 259 |
| 21.4. internet - intranet - extranet         | 261 |
| 21.5. tcp/ip                                 | 262 |
| 22. interface configuration                  | 263 |
| 22.1. to gui or not to gui                   |     |
| 22.2. Debian nic configuration               |     |
| 22.3. RHEL nic configuration                 |     |
| 22.4. ifconfig                               |     |
| 22.5. ip                                     |     |
| 22.6. dhclient                               |     |
| 22.7. hostname                               |     |
| 22.8. arp                                    |     |
| 22.9. route                                  |     |
| 22.10. ping                                  |     |
| 22.11. optional: ethtool                     |     |
| 22.12. practice: interface configuration     |     |
| 22.13. solution: interface configuration     |     |
| 23. network sniffing                         |     |
| 23.1. wireshark                              |     |
| 23.2. tcpdump                                |     |
| 23.3. practice: network sniffing             |     |
| 23.4. solution: network sniffing             |     |
| 24. binding and bonding                      |     |
| 24.1. binding on Redhat/Fedora               |     |
| 24.1. binding on Redna/Pedora                |     |
| 24.3. bonding on Redhat/Fedora               |     |
| 24.4. bonding on Debian/Ubuntu               |     |
| 24.5. practice: binding and bonding          |     |
| 24.6. solution: binding and bonding          |     |
| 24.6. Solution: officing and bonding         |     |
|  |     |
| 25.1. about ssh                              |     |
| 25.2. log on to a remote server              |     |
| 25.3. executing a command in remote          |     |
| 25.4. scp                                    |     |
| 25.5. setting up passwordless ssh            |     |
| 25.6. X forwarding via ssh                   |     |
| 25.7. troubleshooting ssh                    |     |
| 25.8. sshd                                   |     |
| 25.9. sshd keys                              |     |
| 25.10. ssh-agent                             |     |
| 25.11. practice: ssh                         |     |
| 25.12. solution: ssh                         |     |
| 26. introduction to nfs                      |     |
| 26.1. nfs protocol versions                  |     |
| 26.2. rpcinfo                                |     |
| 26.3. server configuration                   |     |
| 26.4. /etc/exports                           |     |
| 26.5. exportfs                               |     |
| 26.6. client configuration                   |     |
| 26.7. practice: introduction to nfs          |     |
| 27. introduction to networking               |     |
| 27.1. introduction to iptables               | 314 |

#### network management

| 27.2. practice: iptables            | . 315 |
|-------------------------------------|-------|
| 27.3. solution: iptables            |       |
| 27.4. xinetd and inetd              |       |
| 27.5. practice: inetd and xinetd    | . 319 |
| 27.6. network file system           |       |
| 27.7 practice : network file system |       |

# Chapter 21. general networking

While this chapter is not directly about  $\mathbf{Linux}$ , it does contain general networking concepts that will help you in troubleshooting networks on  $\mathbf{Linux}$ .

### 21.1. network layers

### 21.1.1. seven OSI layers

When talking about protocol layers, people usually mention the seven layers of the **osi** protocol (Application, Presentation, Session, Transport, Network, Data Link and Physical). We will discuss layers 2 and 3 in depth, and focus less on the other layers. The reason is that these layers are important for understanding networks. You will hear administrators use words like "this is a layer 2 device" or "this is a layer 3 broadcast", and you should be able to understand what they are talking about.

### 21.1.2. four DoD layers

The **DoD** (or tcp/ip) model has only four layers, roughly mapping its **network access layer** to OSI layers 1 and 2 (Physical and Datalink), its **internet** (IP) layer to the OSI **network layer**, its **host-to-host** (tcp, udp) layer to OSI layer 4 (transport) and its **application layer** to OSI layers 5, 6 and 7.

Below an attempt to put OSI and DoD layers next to some protocols and devices.

| OSI Model     | DoD Model         | protocols   |                      | devices/apps   |
|---------------|-------------------|---|----------------------|--|
| layer 5, 6, 7 | application       | dns, dhcp, ntp,<br>snmp, https, ftp,<br>ssh, telnet, http,<br>pop3 others |                      | web server,<br>mail server,<br>browser,<br>mail client |
| layer 4       | host-to-host      | tcp   | udp                  | gateway  |
| layer 3       | internet          | ip, icmp, igmp  |                      | router, firewall<br>layer 3 switch                     |
| layer 2       | network           | arp (mac), rarp   |                      | bridge<br>layer 2 switch                               |
| layer 1       | access<br>layer 1 |   | ethernet, token ring |  |

### 21.1.3. short introduction to the physical layer

The physical layer, or **layer 1**, is all about voltage, electrical signals and mechanical connections. Some networks might still use **coax** cables, but most will have migrated to **utp** (cat 5 or better) with **rj45** connectors.

Devices like **repeaters** and **hubs** are part of this layer. You cannot use software to 'see' a **repeater** or **hub** on the network. The only thing these devices are doing is amplifying electrical signals on cables. **Passive hubs** are multiport amplifiers that amplify an incoming electrical signal on all other connections. **Active hubs** do this by reading and retransmitting bits, without interpreting any meaning in those bits.

Network technologies like **csma/cd** and **token ring** are defined on this layer.

This is all we have to say about **layer 1** in this book.

### 21.1.4. short introduction to the data link layer

The data link layer, or **layer 2** is about frames. A frame has a **crc** (cyclic redundancy check). In the case of ethernet (802.3), each network card is identifiable by a unique 48-bit **mac** address (media access control address).

On this layer we find devices like bridges and switches. A bridge is more intelligent than a hub because a **bridge** can make decisions based on the mac address of computers. A **switch** also understands mac addresses.

In this book we will discuss commands like **arp** and **ifconfig** to explore this layer.

### 21.1.5. short introduction to the network layer

**Layer 3** is about ip packets. This layer gives every host a unique 32-bit ip address. But **ip** is not the only protocol on this layer, there is also icmp, igmp, ipv6 and more. A complete list can be found in the **/etc/protocols** file.

On this layer we find devices like **routers** and layer 3 switches, devices that know (and have) an ip address.

In tcp/ip this layer is commonly referred to as the **internet layer**.

#### 21.1.6. short introduction to the transport layer

We will discuss the **tcp** and **udp** protocols in the context of layer 4. The DoD model calls this the host-to-host layer.

### 21.1.7. layers 5, 6 and 7

The tcp/ip application layer includes layers 5, 6 and 7. Details on the difference between these layers are out of scope of this course.

### 21.1.8. network layers in this book

Stacking of layers in this book is based on the **Protocols in Frame** explanation in the **wireshark** sniffer. When sniffing a dhcp packet, we notice the following in the sniffer.

```
[Protocols in Frame: eth:ip:udp:bootp]
```


Sniffing for ntp (Network Time Protocol) packets gives us this line, which makes us conclude to put **ntp** next to **bootp** in the protocol chart below.

```
[Protocols in Frame: eth:ip:udp:ntp]
```

Sniffing an **arp** broadcast makes us put arp next to **ip**. All these protocols are explained later in this chapter.

```
[Protocols in Frame: eth:arp]
```


Below is a protocol chart based on wireshark's knowledge. It contains some very common protocols that are discussed in this book. The chart does not contain all protocols.



## 21.2. unicast, multicast, broadcast, anycast


#### 21.2.1. unicast

A **unicast** communication originates from one computer and is destined for exactly one other computer (or host). It is common for computers to have many **unicast** communications.



#### 21.2.2. multicast


A multicast is destined for a group (of computers).



Some examples of **multicast** are Realplayer (.sdp files) and **ripv2** (a routing protocol).

#### 21.2.3. broadcast

A **broadcast** is meant for everyone.




Typical example here is the BBC (British Broadcasting Corporation) broadcasting to everyone. In datacommunications a broadcast is most common confined to the **lan**.

Careful, a **layer 2 broadcast** is very different from a **layer 3 broadcast**. A layer two broadcast is received by all network cards on the same segment (it does not pass any router), whereas a layer 3 broadcast is received by all hosts in the same ip subnet.

### 21.2.4. anycast

The **root name servers** of the internet use **anycast**. An **anycast** signal goes the the (geographically) nearest of a well defined group.



With thanks to the nice anonymous wikipedia contributor to put these pictures in the public domain.


### 21.3. lan-wan-man

The term **lan** is used for local area networks, as opposed to a **wan** for wide area networks. The difference between the two is determined by the **distance** between the computers, and not by the number of computers in a network. Some protocols like **atm** are designed for use in a **wan**, others like **ethernet** are designed for use in a **lan**.

#### 21.3.1. lan

A **lan** (Local Area Network) is a local network. This can be one room, or one floor, or even one big building. We say **lan** as long as computers are **close** to each other. You can also define a **lan** when all computers are **ethernet** connected.

A lan can contain multiple smaller lan's. The picture below shows three lan's that together make up one lan.




#### 21.3.2. man

A man (Metropolitan Area Network) is something inbetween a lan and a wan, often comprising several buildings on the same campus or in the same city. A man can use fddi or ethernet or other protocols for connectivity.

#### 21.3.3. wan

A wan (Wide Area Network) is a network with a lot of distance between the computers (or hosts). These hosts are often connected by leased lines. A wan does not use ethernet, but protocols like fddi, frame relay, ATM or X.25 to connect computers (and networks).

The picture below shows a branch office that is connected through **Frame Relay** with headquarters.



The acronym wan is also used for large surface area networks like the internet.

**Cisco** is known for their **wan** technology. They make **routers** that connect many **lan** networks using **wan** protocols.

### 21.3.4. pan-wpan

Your home network is called a pan (Personal Area Network). A wireless pan is a wpan.

### 21.4. internet - intranet - extranet

The **internet** is a global network. It connects many networks using the **tcp/ip** protocol stack.

The origin of the **internet** is the **arpanet**. The **arpanet** was created in 1969, that year only four computers were connected in the network. In 1971 the first **e-mail** was sent over the **arpanet**. **E-mail** took 75 percent of all **arpanet** traffic in 1973. 1973 was also the year **ftp** was introduced, and saw the connection of the first European countries (Norway and UK). In 2009 the internet was available to 25 percent of the world population. In 2011 it is estimated that only a quarter of internet webpages are in English.

An **intranet** is a private **tcp/ip** network. An **intranet** uses the same protocols as the **internet**, but is only accessible to people from within one organization.

An **extranet** is similar to an **intranet**, but some trusted organizations (partners/clients/suppliers/...) also get access.

### 21.5. tcp/ip

### 21.5.1. history of tcp/ip

In the Sixties development of the **tcp/ip** protocol stack was started by the US Department of Defense. In the Eighties a lot of commercial enterprises developed their own protocol stack: IBM created **sna**, Novell had **ipx/spx**, Microsoft completed **netbeui** and Apple worked with **appletalk**. All the efforts from the Eighties failed to survive the Nineties. By the end of the Nineties, almost all computers in the world were able to speak tcp/ip.

In my humble opinion, the main reason for the survival of **tcp/ip** over all the other protocols is its openness. Everyone is free to develop and use the tcp/ip protocol suite.

### 21.5.2. rfc (request for comment)

The protocols that are used on the internet are defined in **rfc's**. An rfc or **request for comment** describes the inner working of all internet protocols. The **IETF** (Internet Engineering Task Force) is the sole publisher of these protocols since 1986.

The official website for the rfc's is **http://www.rfc-editor.org**. This website contains all rfc's in plain text, for example rfc2132 (which defines dhcp and bootp) is accessible at http://www.rfc-editor.org/rfc/rfc2132.txt.

### 21.5.3. many protocols

For reliable connections, you use **tcp**, whereas **udp** is connectionless but faster. The **icmp** error messages are used by **ping**, multicast groups are managed by **igmp**.

These protocols are visible in the protocol field of the ip header, and are listed in the /etc/ protocols file.

#### 21.5.4. many services

Network cards are uniquely identified by their **mac address**, hosts by their **ip address** and applications by their **port number**.

Common application level protocols like smtp, http, ssh, telnet and ftp have fixed **port numbers**. There is a list of **port numbers** in /etc/services.

```
paul@ubu1010:~$ grep ssh /etc/services
ssh 22/tcp # SSH Remote Login Protocol
ssh 22/udp
```

# Chapter 22. interface configuration

This chapter explains how to configure **network interface cards** to work with **tcp/ip**.

### 22.1. to gui or not to gui

Recent Linux distributions often include a graphical application to configure the network. Some people complain that these applications mess networking configurations up when used simultaneously with command line configurations. Notably **Network Manager** (often replaced by **wicd**) and **yast** are known to not care about configuration changes via the command line.

Since the goal of this course is **server** administration, we will assume our Linux servers are always administered through the command line.

This chapter only focuses on using the command line for network interface configuration!

Unfortunately there is no single combination of Linux commands and /etc files that works on all Linux distributions. We discuss networking on two (large but distinct) Linux distribution families.

We start with **Debian** (this should also work on Ubuntu and Mint), then continue with **RHEL** (which is identical to CentOS and Fedora).

### 22.2. Debian nic configuration

#### 22.2.1. /etc/network/interfaces

The /etc/network/interfaces file is a core network interface card configuration file on debian.

#### dhcp client

The screenshot below shows that our computer is configured for **dhcp** on **eth0** (the first network interface card or nic).

```
paul@debian8:~$ cat /etc/network/interfaces
# This file describes the network interfaces available on your system
# and how to activate them. For more information, see interfaces(5).
# The loopback network interface
auto lo
iface lo inet loopback
auto eth0
iface eth0 inet dhcp
```

Configuring network cards for **dhcp** is good practice for clients, but servers usually require a **fixed ip address**.

#### fixed ip

The screenshot below shows /etc/network/interfaces configured with a fixed ip address.

```
root@debian7~# cat /etc/network/interfaces
auto lo
iface lo inet loopback

auto eth0
iface eth0 inet static
address 10.42.189.198
broadcast 10.42.189.207
netmask 255.255.255.240
gateway 10.42.189.193
```

The screenshot above also shows that you can provide more configuration than just the ip address. See **interfaces(5)** for help on setting a **gateway**, **netmask** or any of the other options.

#### 22.2.2. /sbin/ifdown

It is adviced (but not mandatory) to down an interface before changing its configuration. This can be done with the **ifdown** command.

The command will not give any output when downing an interface with a fixed ip address. However **ifconfig** will no longer show the interface.

```
root@ubul104srv:~# ifdown eth0
root@ubul104srv:~# ifconfig
lo Link encap:Local Loopback
   inet addr:127.0.0.1 Mask:255.0.0.0
   inet6 addr: ::1/128 Scope:Host
   UP LOOPBACK RUNNING MTU:16436 Metric:1
   RX packets:106 errors:0 dropped:0 overruns:0 frame:0
   TX packets:106 errors:0 dropped:0 overruns:0 carrier:0
   collisions:0 txqueuelen:0
   RX bytes:11162 (11.1 KB) TX bytes:11162 (11.1 KB)
```

An interface that is down cannot be used to connect to the network.

### 22.2.3. /sbin/ifup

Below a screenshot of **ifup** bringing the **eth0** ethernet interface up using dhcp. (Note that this is a Ubuntu 10.10 screenshot, Ubuntu 11.04 omits **ifup** output by default.)

```
root@ubu1010srv:/etc/network# ifup eth0
Internet Systems Consortium DHCP Client V3.1.3
Copyright 2004-2009 Internet Systems Consortium.
All rights reserved.
For info, please visit https://www.isc.org/software/dhcp/
Listening on LPF/eth0/08:00:27:cd:7f:fc
Sending on LPF/eth0/08:00:27:cd:7f:fc
Sending on Socket/fallback
DHCPREQUEST of 192.168.1.34 on eth0 to 255.255.255.255 port 67
DHCPNAK from 192.168.33.100
DHCPDISCOVER on eth0 to 255.255.255.255 port 67 interval 3
DHCPOFFER of 192.168.33.77 from 192.168.33.100
DHCPREQUEST of 192.168.33.77 on eth0 to 255.255.255.255 port 67
DHCPACK of 192.168.33.77 from 192.168.33.100
bound to 192.168.33.77 -- renewal in 95 seconds.
ssh stop/waiting
ssh start/running, process 1301
root@ubu1010srv:/etc/network#
```

The details of **dhcp** are covered in a separate chapter in the **Linux Servers** course.

### 22.3. RHEL nic configuration

### 22.3.1. /etc/sysconfig/network

The /etc/sysconfig/network file is a global (across all network cards) configuration file. It allows us to define whether we want networking (NETWORKING=yes|no), what the hostname should be (HOSTNAME=) and which gateway to use (GATEWAY=).

```
[root@rhel6 ~]# cat /etc/sysconfig/network
NETWORKING=yes
HOSTNAME=rhel6
GATEWAY=192.168.1.1
```

There are a dozen more options settable in this file, details can be found in /usr/share/doc/initscripts-\*/sysconfig.txt.

Note that this file contains no settings at all in a default RHEL7 install (with networking enabled).

```
[root@rhel71 ~]# cat /etc/sysconfig/network
# Created by anaconda
```

### 22.3.2. /etc/sysconfig/network-scripts/ifcfg-

Each network card can be configured individually using the /etc/sysconfig/network-scripts/ ifcfg-\* files. When you have only one network card, then this will probably be /etc/sysconfig/network-scripts/ifcfg-eth0.

#### dhcp client

Below a screenshot of /etc/sysconfig/network-scripts/ifcfg-eth0 configured for dhcp (BOOTPROTO="dhcp"). Note also the NM\_CONTROLLED paramater to disable control of this nic by Network Manager. This parameter is not explained (not even mentioned) in /usr/share/doc/initscripts-\*/sysconfig.txt, but many others are.

```
[root@rhel6 ~]# cat /etc/sysconfig/network-scripts/ifcfg-eth0
DEVICE="eth0"
HWADDR="08:00:27:DD:0D:5C"
NM_CONTROLLED="no"
BOOTPROTO="dhcp"
ONBOOT="yes"
```

The BOOTPROTO variable can be set to either **dhcp** or **bootp**, anything else will be considered **static** meaning there should be no protocol used at boot time to set the interface values.

RHEL7 adds **ipv6** variables to this file.

```
[root@rhel71 network-scripts]# cat ifcfg-enp0s3

TYPE="Ethernet"
BOOTPROTO="dhcp"
DEFROUTE="yes"
PEERDNS="yes"
PEERROUTES="yes"
IPV4_FAILURE_FATAL="no"
```

```
IPV6INIT="yes"
IPV6_AUTOCONF="yes"
IPV6_DEFROUTE="yes"
IPV6_PEERDNS="yes"
IPV6_PEERROUTES="yes"
IPV6_FAILURE_FATAL="no"
NAME="enp0s3"
UUID="9fa6a83a-2f8e-4ecc-962c-5f614605f4ee"
DEVICE="enp0s3"
ONBOOT="yes"
[root@rhe171 network-scripts]#
```

#### fixed ip

Below a screenshot of a **fixed ip** configuration in /etc/sysconfig/network-scripts/ifcfg-eth0.

```
[root@rhel6 ~]# cat /etc/sysconfig/network-scripts/ifcfg-eth0
DEVICE="eth0"
HWADDR="08:00:27:DD:0D:5C"
NM_CONTROLLED="no"
BOOTPROTO="none"
IPADDR="192.168.1.99"
NETMASK="255.255.255.0"
GATEWAY="192.168.1.1"
ONBOOT="yes"
```

The HWADDR can be used to make sure that each network card gets the correct name when multiple network cards are present in the computer. It can not be used to assign a **mac address** to a network card. For this, you need to specify the MACADDR variable. Do not use HWADDR and MACADDR in the same **ifcfg-ethx** file.

The BROADCAST= and NETWORK= parameters from previous RHEL/Fedora versions are obsoleted.

### 22.3.3. nmcli

On RHEL7 you should run **nmcli connection reload** if you changed configuration files in **/etc/sysconfig/** to enable your changes.

The **nmcli** tool has many options to configure networking on the command line in RHEL7/CentOS7

man nmcli

#### 22.3.4. nmtui

Another recommendation for RHEL7/CentOS7 is to use **nmtui**. This tool will use a 'windowed' interface in command line to manage network interfaces.

nmtui

### 22.3.5. /sbin/ifup and /sbin/ifdown

The **ifup** and **ifdown** commands will set an interface up or down, using the configuration discussed above. This is identical to their behaviour in Debian and Ubuntu.

```
[root@rhel6 ~]# ifdown eth0 && ifup eth0
[root@rhel6 ~]# ifconfig eth0
eth0 Link encap:Ethernet HWaddr 08:00:27:DD:0D:5C
   inet addr:192.168.1.99 Bcast:192.168.1.255 Mask:255.255.255.0
   inet6 addr: fe80::a00:27ff:fedd:d5c/64 Scope:Link
   UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
   RX packets:2452 errors:0 dropped:0 overruns:0 frame:0
   TX packets:1881 errors:0 dropped:0 overruns:0 carrier:0
   collisions:0 txqueuelen:1000
   RX bytes:257036 (251.0 KiB) TX bytes:184767 (180.4 KiB)
```

### 22.4. ifconfig

The use of /sbin/ifconfig without any arguments will present you with a list of all active network interface cards, including wireless and the loopback interface. In the screenshot below eth0 has no ip address.

```
root@ubu1010:~# ifconfig
eth0 Link encap:Ethernet
                         HWaddr 00:26:bb:5d:2e:52
    UP BROADCAST MULTICAST MTU:1500 Metric:1
    RX packets:0 errors:0 dropped:0 overruns:0 frame:0
    TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
    collisions:0 txqueuelen:1000
    RX bytes:0 (0.0 B) TX bytes:0 (0.0 B)
    Interrupt:43 Base address:0xe000
eth1 Link encap:Ethernet HWaddr 00:26:bb:12:7a:5e
    inet addr:192.168.1.30 Bcast:192.168.1.255 Mask:255.255.255.0
    inet6 addr: fe80::226:bbff:fe12:7a5e/64 Scope:Link
    UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
    RX packets:11141791 errors:202 dropped:0 overruns:0 frame:11580126
    TX packets:6473056 errors:3860 dropped:0 overruns:0 carrier:0
    collisions:0 txqueuelen:1000
    RX bytes:3476531617 (3.4 GB) TX bytes:2114919475 (2.1 GB)
    Interrupt:23
lo Link encap:Local Loopback
    inet addr:127.0.0.1 Mask:255.0.0.0
    inet6 addr: ::1/128 Scope:Host
    UP LOOPBACK RUNNING MTU:16436 Metric:1
    RX packets:2879 errors:0 dropped:0 overruns:0 frame:0
    TX packets:2879 errors:0 dropped:0 overruns:0 carrier:0
    collisions:0 txqueuelen:0
    RX bytes:486510 (486.5 KB) TX bytes:486510 (486.5 KB)
```

You can also use **ifconfig** to obtain information about just one network card.

```
[root@rhel6 ~]# ifconfig eth0
eth0 Link encap:Ethernet    HWaddr 08:00:27:DD:0D:5C
    inet addr:192.168.1.99    Bcast:192.168.1.255    Mask:255.255.255.0
    inet6 addr: fe80::a00:27ff:fedd:d5c/64    Scope:Link
    UP BROADCAST RUNNING MULTICAST    MTU:1500    Metric:1
    RX packets:2969 errors:0 dropped:0 overruns:0 frame:0
    TX packets:1918 errors:0 dropped:0 overruns:0 carrier:0
    collisions:0 txqueuelen:1000
```

```
RX bytes:335942 (328.0 KiB) TX bytes:190157 (185.7 KiB)
```

When /sbin is not in the \$PATH of a normal user you will have to type the full path, as seen here on Debian.

```
paul@debian5:~$ /sbin/ifconfig eth3
eth3 Link encap:Ethernet    HWaddr 08:00:27:ab:67:30
    inet addr:192.168.1.29    Bcast:192.168.1.255    Mask:255.255.255.0
    inet6 addr: fe80::a00:27ff:feab:6730/64    Scope:Link
    UP BROADCAST RUNNING MULTICAST    MTU:1500    Metric:1
    RX packets:27155 errors:0 dropped:0 overruns:0 frame:0
    TX packets:30527 errors:0 dropped:0 overruns:0 carrier:0
    collisions:0 txqueuelen:1000
    RX bytes:13095386 (12.4 MiB)    TX bytes:25767221 (24.5 MiB)
```

### 22.4.1. up and down

You can also use **ifconfig** to bring an interface up or down. The difference with **ifup** is that **ifconfig eth0 up** will re-activate the nic keeping its existing (current) configuration, whereas **ifup** will read the correct file that contains a (possibly new) configuration and use this config file to bring the interface up.

```
[root@rhel6 ~]# ifconfig eth0 down
[root@rhel6 ~]# ifconfig eth0 up
[root@rhel6 ~]# ifconfig eth0
eth0 Link encap:Ethernet HWaddr 08:00:27:DD:0D:5C
    inet addr:192.168.1.99 Bcast:192.168.1.255 Mask:255.255.255.0
    inet6 addr: fe80::a00:27ff:fedd:d5c/64 Scope:Link
    UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
    RX packets:2995 errors:0 dropped:0 overruns:0 frame:0
    TX packets:1927 errors:0 dropped:0 overruns:0 carrier:0
    collisions:0 txqueuelen:1000
    RX bytes:339030 (331.0 KiB) TX bytes:191583 (187.0 KiB)
```

### 22.4.2. setting ip address

You can **temporary** set an ip address with **ifconfig**. This ip address is only valid until the next **ifup/ifdown** cycle or until the next **reboot**.

```
[root@rhel6 ~]# ifconfig eth0 | grep 192
    inet addr:192.168.1.99    Bcast:192.168.1.255    Mask:255.255.255.0
[root@rhel6 ~]# ifconfig eth0 192.168.33.42 netmask 255.255.0.0
[root@rhel6 ~]# ifconfig eth0 | grep 192
    inet addr:192.168.33.42    Bcast:192.168.255.255    Mask:255.255.0.0
[root@rhel6 ~]# ifdown eth0 && ifup eth0
[root@rhel6 ~]# ifconfig eth0 | grep 192
    inet addr:192.168.1.99    Bcast:192.168.1.255    Mask:255.255.255.0
```

### 22.4.3. setting mac address

You can also use **ifconfig** to set another **mac address** than the one hard coded in the network card. This screenshot shows you how.

```
[root@rhel6 ~]# ifconfig eth0 | grep HWaddr
eth0 Link encap:Ethernet HWaddr 08:00:27:DD:0D:5C
[root@rhel6 ~]# ifconfig eth0 hw ether 00:42:42:42:42:42
[root@rhel6 ~]# ifconfig eth0 | grep HWaddr
eth0 Link encap:Ethernet HWaddr 00:42:42:42:42
```

### 22.5. ip

The **ifconfig** tool is deprecated on some systems. Use the **ip** tool instead.

To see ip addresses on RHEL7 for example, use this command:

```
[root@rhel71 ~]# ip a
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN
    link/loopback 00:00:00:00:00 brd 00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
        valid_lft forever preferred_lft forever
    inet6 ::1/128 scope host
        valid_lft forever preferred_lft forever
2: enp0s3: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state UP qlen 1000
    link/ether 08:00:27:89:22:33 brd ff:ff:ff:ff:ff
    inet 192.168.1.135/24 brd 192.168.1.255 scope global dynamic enp0s3
        valid_lft 6173sec preferred_lft 6173sec
    inet6 fe80::a00:27ff:fe89:2233/64 scope link
        valid_lft forever preferred_lft forever
[root@rhel71 ~]#
```

#### 22.6. dhclient

Home and client Linux desktops often have /sbin/dhclient running. This is a daemon that enables a network interface to lease an ip configuration from a dhcp server. When your adapter is configured for dhcp or bootp, then /sbin/ifup will start the dhclient daemon.

When a lease is renewed, **dhclient** will override your **ifconfig** set ip address!

#### 22.7. hostname

Every host receives a **hostname**, often placed in a **DNS name space** forming the **fqdn** or Fully Qualified Domain Name.

This screenshot shows the **hostname** command and the configuration of the hostname on Red Hat/Fedora.

```
[root@rhel6 ~]# grep HOSTNAME /etc/sysconfig/network
HOSTNAME=rhel6
[root@rhel6 ~]# hostname
rhel6
```

Starting with RHEL7/CentOS7 this file is empty. The hostname is configured in the standard /etc/hostname file.

```
[root@rhel71 ~]# cat /etc/hostname
rhel71.linux-training.be
[root@rhel71 ~]#
```

Ubuntu/Debian uses the /etc/hostname file to configure the hostname.

```
paul@debian8:~$ cat /etc/hostname
server42
paul@debian8:~$ hostname
server42
```

On all Linux distributions you can change the **hostname** using the **hostname** \$newname command. This is not a permanent change.

```
[root@rhel6 ~]# hostname server42
[root@rhel6 ~]# hostname
server42
```

On any Linux you can use **sysctl** to display and set the hostname.

```
[root@rhel6 ~]# sysctl kernel.hostname
kernel.hostname = server42
[root@rhel6 ~]# sysctl kernel.hostname=rhel6
kernel.hostname = rhel6
[root@rhel6 ~]# sysctl kernel.hostname
kernel.hostname = rhel6
[root@rhel6 ~]# hostname
rhel6
```

### 22.8. arp

The **ip to mac** resolution is handled by the **layer two broadcast** protocol **arp**. The **arp table** can be displayed with the **arp tool**. The screenshot below shows the list of computers that this computer recently communicated with.

```
root@barry:~# arp -a
? (192.168.1.191) at 00:0C:29:3B:15:80 [ether] on eth1
agapi (192.168.1.73) at 00:03:BA:09:7F:D2 [ether] on eth1
anya (192.168.1.1) at 00:12:01:E2:87:FB [ether] on eth1
faith (192.168.1.41) at 00:0E:7F:41:0D:EB [ether] on eth1
kiss (192.168.1.49) at 00:D0:E0:91:79:95 [ether] on eth1
laika (192.168.1.40) at 00:90:F5:4E:AE:17 [ether] on eth1
pasha (192.168.1.71) at 00:03:BA:02:C3:82 [ether] on eth1
shaka (192.168.1.72) at 00:03:BA:09:7C:F9 [ether] on eth1
root@barry:~#
```

Anya is a Cisco Firewall, faith is a laser printer, kiss is a Kiss DP600, laika is a laptop and Agapi, Shaka and Pasha are SPARC servers. The question mark is a Red Hat Enterprise Linux server running on a virtual machine.

You can use **arp -d** to remove an entry from the **arp table**.

```
[root@rhel6 ~]# arp
Address
                   HWtype HWaddress
                                               Flags Mask
                                                               Iface
                   ether 00:26:bb:12:7a:5e
ubu1010
                                               C
                                                               et.h0
                   ether
                           00:02:cf:aa:68:f0
                                               C
                                                                eth0
anya
[root@rhel6 ~]# arp -d anya
[root@rhel6 ~]# arp
Address
                 HWtype HWaddress
                                               Flags Mask
                                                               Iface
ubu1010
                   ether 00:26:bb:12:7a:5e
                                                                eth0
anya
                           (incomplete)
                                                                eth0
[root@rhel6 ~]# ping anya
PING anya (192.168.1.1) 56(84) bytes of data.
64 bytes from anya (192.168.1.1): icmp_seq=1 ttl=254 time=10.2 ms
[root@rhel6 ~]# arp
Address
                   HWtype HWaddress
                                               Flags Mask
                                                               Iface
                           00:26:bb:12:7a:5e
ubu1010
                   ether
                                               C
                                                                eth0
                   ether
                           00:02:cf:aa:68:f0
                                               C
                                                                eth0
anya
```

### 22.9. route

You can see the computer's local routing table with the /sbin/route command (and also with netstat -r ).

```
root@RHEL4b ~]# netstat -r
Kernel IP routing table
                           Flags
                                       MSS Window irtt Iface
Destination Gateway
                    Genmask
                    255.255.255.0 U 0 0
192.168.1.0
                                                    0 eth0
[root@RHEL4b ~]# route
Kernel IP routing table
Destination Gateway Genmask
                                Flags Metric Ref Use Iface
192.168.1.0
                    255.255.255.0 U 0
                                           0 0 eth0
[root@RHEL4b ~]#
```

It appears this computer does not have a **gateway** configured, so we use **route add default gw** to add a **default gateway** on the fly.

Unless you configure the gateway in one of the /etc/ file from the start of this chapter, your computer will forget this gateway after a reboot.

### 22.10. ping

If you can **ping** to another host, then **tcp/ip** is configured.

```
[root@RHEL4b ~]# ping 192.168.1.5
PING 192.168.1.5 (192.168.1.5) 56(84) bytes of data.
64 bytes from 192.168.1.5: icmp_seq=0 ttl=64 time=1004 ms
64 bytes from 192.168.1.5: icmp_seq=1 ttl=64 time=1.19 ms
64 bytes from 192.168.1.5: icmp_seq=2 ttl=64 time=0.494 ms
64 bytes from 192.168.1.5: icmp_seq=2 ttl=64 time=0.494 ms
64 bytes from 192.168.1.5: icmp_seq=3 ttl=64 time=0.419 ms
--- 192.168.1.5 ping statistics ---
4 packets transmitted, 4 received, 0% packet loss, time 3009ms
rtt min/avg/max/mdev = 0.419/251.574/1004.186/434.520 ms, pipe 2
[root@RHEL4b ~]#
```

### 22.11. optional: ethtool

To display or change network card settings, use **ethtool**. The results depend on the capabilities of your network card. The example shows a network that auto-negotiates it's bandwidth.

```
root@laika:~# ethtool eth0
Settings for eth0:
Supported ports: [ TP ]
Supported link modes:
                         10baseT/Half 10baseT/Full
                         100baseT/Half 100baseT/Full
                         1000baseT/Full
Supports auto-negotiation: Yes
Advertised link modes: 10baseT/Half 10baseT/Full
                         100baseT/Half 100baseT/Full
                         1000baseT/Full
Advertised auto-negotiation: Yes
Speed: 1000Mb/s
Duplex: Full
Port: Twisted Pair
PHYAD: 0
Transceiver: internal
Auto-negotiation: on
Supports Wake-on: pumbg
Wake-on: g
Current message level: 0x00000033 (51)
Link detected: yes
```

This example shows how to use ethtool to switch the bandwidth from 1000Mbit to 100Mbit and back. Note that some time passes before the nic is back to 1000Mbit.

```
root@laika:~# ethtool eth0 | grep Speed

Speed: 1000Mb/s

root@laika:~# ethtool -s eth0 speed 100

root@laika:~# ethtool eth0 | grep Speed

Speed: 100Mb/s

root@laika:~# ethtool -s eth0 speed 1000

root@laika:~# ethtool eth0 | grep Speed

Speed: 1000Mb/s
```

### 22.12. practice: interface configuration

- 1. Verify whether **dhclient** is running.
- 2. Display your current ip address(es).
- 3. Display the configuration file where this **ip address** is defined.
- 4. Follow the **nic configuration** in the book to change your ip address from **dhcp client** to **fixed**. Keep the same **ip address** to avoid conflicts!
- 5. Did you also configure the correct **gateway** in the previous question? If not, then do this now.
- 6. Verify that you have a gateway.
- 7. Verify that you can connect to the gateway, that it is alive.
- 8. Change the last two digits of your **mac address**.
- 9. Which ports are used by http, pop3, ssh, telnet, nntp and ftp?
- 10. Explain why e-mail and websites are sent over **tcp** and not **udp**.
- 11. Display the **hostname** of your computer.
- 12. Which ip-addresses did your computer recently have contact with?

### 22.13. solution: interface configuration

1. Verify whether **dhclient** is running.

```
paul@debian5:~$ ps fax | grep dhclient
```

2. Display your current ip address(es).

```
paul@debian5:~$ /sbin/ifconfig | grep 'inet '
   inet addr:192.168.1.31 Bcast:192.168.1.255 Mask:255.255.255.0
   inet addr:127.0.0.1 Mask:255.0.0.0
```

3. Display the configuration file where this **ip address** is defined.

```
Ubuntu/Debian: cat /etc/network/interfaces
Redhat/Fedora: cat /etc/sysconfig/network-scripts/ifcfg-eth*
```

4. Follow the **nic configuration** in the book to change your ip address from **dhcp client** to **fixed**. Keep the same **ip address** to avoid conflicts!

```
Ubuntu/Debian:
ifdown eth0
vi /etc/network/interfaces
ifup eth0

Redhat/Fedora:
ifdown eth0
vi /etc/sysconfig/network-scripts/ifcfg-eth0
ifup eth0
```

- 5. Did you also configure the correct **gateway** in the previous question? If not, then do this now.
- 6. Verify that you have a gateway.

```
paul@debian5:~$ /sbin/route
Kernel IP routing table
Destination Gateway Genmask Flags Metric Ref Use Iface
192.168.1.0 * 255.255.255.0 U 0 0 0 eth0
default 192.168.1.1 0.0.0.0 UG 0 0 0 eth0
```

7. Verify that you can connect to the gateway, that it is alive.

```
paul@debian5:~$ ping -c3 192.168.1.1
PING 192.168.1.1 (192.168.1.1) 56(84) bytes of data.
64 bytes from 192.168.1.1: icmp_seq=1 ttl=254 time=2.28 ms
64 bytes from 192.168.1.1: icmp_seq=2 ttl=254 time=2.94 ms
64 bytes from 192.168.1.1: icmp_seq=3 ttl=254 time=2.34 ms
--- 192.168.1.1 ping statistics ---
3 packets transmitted, 3 received, 0% packet loss, time 2008ms
rtt min/avg/max/mdev = 2.283/2.524/2.941/0.296 ms
```

8. Change the last two digits of your **mac address**.

```
[root@rhel6 ~]# ifconfig eth0 hw ether 08:00:27:ab:67:XX
```

9. Which ports are used by http, pop3, ssh, telnet, nntp and ftp?

```
root@rhel6 ~# grep ^'http ' /etc/services
```

```
http 80/tcp www www-http # WorldWideWeb HTTP http 80/udp www www-http # HyperText Transfer
                                           # HyperText Transfer Protocol
root@rhel6 ~# grep ^'smtp ' /etc/services
smtp 25/tcp mail smtp 25/udp mail
root@rhel6 ~# grep ^'ssh ' /etc/services
                     # The Secure Shell (SSH) Protocol
ssh 22/tcp
          22/udp
                                      # The Secure Shell (SSH) Protocol
ssh
root@rhel6 ~# grep ^'telnet ' /etc/services
telnet 23/tcp
telnet 23/udp
root@rhel6 ~# grep ^'nntp ' /etc/services
nntp 119/tcp
                   readnews untp
readnews untp
                                          # USENET News Transfer Protocol
nntp
         119/udp
                                           # USENET News Transfer Protocol
root@rhel6 ~# grep ^'ftp ' /etc/services
          21/tcp
         21/udp
                     fsp fspd
ftp
```

10. Explain why e-mail and websites are sent over **tcp** and not **udp**.

Because tcp is reliable and udp is not.

11. Display the **hostname** of your computer.

```
paul@debian5:~$ hostname debian5
```

12. Which ip-addresses did your computer recently have contact with?

```
root@rhel6 ~# arp -a
? (192.168.1.1) at 00:02:cf:aa:68:f0 [ether] on eth2
? (192.168.1.30) at 00:26:bb:12:7a:5e [ether] on eth2
? (192.168.1.31) at 08:00:27:8e:8a:a8 [ether] on eth2
```

# Chapter 23. network sniffing

A network administrator should be able to use a sniffer like **wireshark** or **tcpdump** to troubleshoot network problems.

A student should often use a sniffer to learn about networking. This chapter introduces you to **network sniffing**.

### 23.1. wireshark

### 23.1.1. installing wireshark

This example shows how to install **wireshark** on **.deb** based distributions (including Debian, Mint, Xubuntu, and others).

```
root@debian8:~# apt-get install wireshark
Reading package lists... Done
Building dependency tree
Reading state information... Done
... (output truncated)
```

On .rpm based distributions like CentOS, RHEL and Fedora you can use yum to install wireshark.

```
[root@centos7 ~]# yum install wireshark
Loaded plugins: fastestmirror
Loading mirror speeds from cached hostfile
... (output truncated)
```

### 23.1.2. selecting interface

When you start **wireshark** for the first time, you will need to select an interface. You will see a dialog box that looks similar to this one.



It is possible that there are no interfaces available because some distributions only allow root to sniff the network. You may need to use **sudo wireshark**.

Or you can follow the general advice to sniff using **tcpdump** or any other tool, and save the capture to a file. Any saved capture can be analyzed using **wireshark** at a later time.

#### 23.1.3. minimize traffic

Sniffing a network can generate many thousands of packets in a very short time. This can be overwhelming. Try to mitigate by isolating your sniffer on the network. Preferably sniff an isolated virtual network interface over which you control all traffic.

If you are at home to learn sniffing, then it could help to close all network programs on your computer, and disconnect other computers and devices like smartphones and tablets to minimize the traffic.


Even more important than this is the use of **filters** which will be discussed in this chapter.

#### 23.1.4. sniffing ping

I started the sniffer and captured all packets while doing these three **ping** commands (there is no need for root to do this):

```
root@debian7:~# ping -c2 ns1.paul.local
PING nsl.paul.local (10.104.33.30) 56(84) bytes of data.
64 bytes from 10.104.33.30: icmp_req=1 ttl=64 time=0.010 ms
64 bytes from 10.104.33.30: icmp_req=2 ttl=64 time=0.023 ms
--- nsl.paul.local ping statistics ---
2 packets transmitted, 2 received, 0% packet loss, time 1001ms
rtt min/avg/max/mdev = 0.010/0.016/0.023/0.007 ms
root@debian7:~# ping -c3 linux-training.be
PING linux-training.be (188.93.155.87) 56(84) bytes of data.
64 bytes from antares.ginsys.net (188.93.155.87): icmp_req=1 ttl=56 time=15.6 ms
64 bytes from antares.ginsys.net (188.93.155.87): icmp_req=2 ttl=56 time=17.8 ms
64 bytes from antares.ginsys.net (188.93.155.87): icmp_req=3 ttl=56 time=14.7 ms
--- linux-training.be ping statistics ---
3 packets transmitted, 3 received, 0% packet loss, time 2003ms
rtt min/avg/max/mdev = 14.756/16.110/17.881/1.309 ms
root@debian7:~# ping -c1 centos7.paul.local
PING centos7.paul.local (10.104.33.31) 56(84) bytes of data.
64 bytes from 10.104.33.31: icmp_req=1 ttl=64 time=0.590 ms
--- centos7.paul.local ping statistics ---
1 packets transmitted, 1 received, 0% packet loss, time 0ms
rtt min/avg/max/mdev = 0.590/0.590/0.590/0.000 ms
```


In total more than 200 packets were sniffed from the network. Things become clearer when you enter **icmp** in the filter field and press the **apply** button.



#### 23.1.5. sniffing ping and dns

Using the same capture as before, but now with a different **filter**. We want to see both **dns** and **icmp** traffic, so we enter both in the filter field.

We put **dns or icmp** in the filter to achieve this. Putting **dns and icmp** would render nothing because there is no packet that matches both protocols.




In the screenshot above you can see that packets 25 and 26 both have 10.104.33.30 as **source** and **destination** ip address. That is because the dns client is the same computer as the dns server.

The same is true for packets 31 and 32, since the machine is actually pinging itself.

#### 23.1.6. specific ip address


This is a screenshot that filters for **dns** packets that contain a certain **ip address**. The filter in use is **ip.addr==10.104.33.30** and **dns**. The **and** directive forces each displayed packet to match both conditions.



Packet 93 is the **dns query** for the A record of linux-training.be. Packet 98 is the response from the **dns server**. What do you think happened in the packets between 93 and 98? Try to answer this before reading on (it always helps to try to predict what you will see, and then checking your prediction).

#### 23.1.7. filtering by frame

The correct technical term for a **packet** as sniffed is a **frame** (because we sniff on layer two). So to display packets with certain numbers, we use **frame.number** in the filter.



#### 23.1.8. looking inside packets

The middle pane can be expanded. When selecting a line in this pane, you can see the corresponding bytes in the frame in the bottom panel.


This screenshot shows the middle pane with the source address of my laptop selected.

```
▶|Frame 1: 77 bytes on wire (616 bits), 77 bytes captured (616 bits) on interface 0
Ethernet II, Src: Apple_36:24:28 (b8:e8:56:36:24:28), Dst: IcpElect_c9:07:10 (00:08:9b:c9:07:10)
  ▶ Destination: IcpElect_c9:07:10 (00:08:9b:c9:07:10)
     Type: IP (0x0800)
▶ Internet Protocol Version 4, Src: 192.168.1.35 (192.168.1.35), Dst: 192.168.1.42 (192.168.1.42)
User Datagram Protocol, Src Port: 57676 (57676), Dst Port: 53 (53)
▶ Domain Name System (query)
      00 08 9b c9 07 10 b8 e8
                                    36 24 28 08 00 45 00
                                                                       V6$(..E.
                                                             .?os@.@. G....#..
.*.L.5.+ .D.....
                                 47 9d c0 a8 01 23 c0 a8
      00 3f 6f 73 40 00 40 11
                                                             .*.L.5.+ .D.....
      01 2a e1 4c 00 35 00 2b
00 00 00 00 00 00 0e 6c
                                be 44 af c5 01 00 00 01
69 6e 75 78 2d 74 72 61
      69 6e 69 6e 67 02 62 65 00 00 01 00 01
```


Note that the above works fine when sniffing one interface. When sniffing with for example **tcpdump -i any** you will end up with **Linux cooked** at this level.

#### 23.1.9. other filter examples

You can combine two protocols with a logical **or** between them. The example below shows how to filter only **arp** and **bootp** (or **dhcp**) packets.



This example shows how to filter for **dns** traffic containing a certain **ip address**.



# 23.2. tcpdump

Sniffing on the command line can be done with **tcpdump**. Here are some examples.

Using the **tcpdump host \$ip** command displays all traffic with one host (192.168.1.38 in this example).

```
root@ubuntu910:~# tcpdump host 192.168.1.38
tcpdump: verbose output suppressed, use -v or -vv for full protocol decode
listening on eth0, link-type EN10MB (Ethernet), capture size 96 bytes
```

Capturing only ssh (tcp port 22) traffic can be done with **tcpdump tcp port \$port**. This screenshot is cropped to 76 characters for readability in the pdf.

```
root@deb503:~# tcpdump tcp port 22
tcpdump: verbose output suppressed, use -v or -vv for full protocol decode
listening on eth1, link-type EN10MB (Ethernet), capture size 96 bytes
14:22:20.716313 IP deb503.local.37973 > rhel53.local.ssh: P 666050963:66605
14:22:20.719936 IP rhel53.local.ssh > deb503.local.37973: P 1:49(48) ack 48
14:22:20.720922 IP rhel53.local.ssh > deb503.local.37973: P 49:113(64) ack
14:22:20.721321 IP rhel53.local.ssh > deb503.local.37973: P 113:161(48) ack
14:22:20.721820 IP deb503.local.37973 > rhel53.local.ssh: . ack 161 win 200
14:22:20.722492 IP rhel53.local.ssh > deb503.local.37973: P 161:225(64) ack
14:22:20.760602 IP deb503.local.37973 > rhel53.local.ssh: . ack 225 win 200
14:22:23.108106 IP deb503.local.54424 > ubuntu910.local.ssh: P 467252637:46
14:22:23.116804 IP ubuntu910.local.ssh > deb503.local.54424: P 1:81(80) ack
14:22:23.116844 IP deb503.local.54424 > ubuntu910.local.ssh: . ack 81 win 2
10 packets captured
10 packets received by filter
0 packets dropped by kernel
```

Same as above, but write the output to a file with the **tcpdump -w \$filename** command.

```
root@ubuntu910:~# tcpdump -w sshdump.tcpdump tcp port 22
tcpdump: listening on eth0, link-type EN10MB (Ethernet), capture size 96 bytes
^C
17 packets captured
17 packets received by filter
0 packets dropped by kernel
```

With **tcpdump -r \$filename** the file created above can be displayed.

```
root@ubuntu910:~# tcpdump -r sshdump.tcpdump
```

Many more examples can be found in the manual page of **tcpdump**.

# 23.3. practice: network sniffing

- 1. Install wireshark on your computer (not inside a virtual machine).
- 2. Start a ping between your computer and another computer.
- 3. Start sniffing the network.
- 4. Display only the ping echo's in the top pane using a filter.
- 5. Now ping to a name (like www.linux-training.be) and try to sniff the DNS query and response. Which DNS server was used? Was it a tcp or udp query and response?
- 6. Find an amateur/hobby/club website that features a login prompt. Attempt to login with user 'paul' and password 'hunter2' while your sniffer is running. Now find this information in the sniffer.

# 23.4. solution: network sniffing

1. Install wireshark on your computer (not inside a virtual machine).

```
Debian/Ubuntu: aptitude install wireshark

Red Hat/Mandriva/Fedora: yum install wireshark
```

2. Start a ping between your computer and another computer.

```
ping $ip_address
```

3. Start sniffing the network.

```
(sudo) wireshark
select an interface (probably eth0)
```

4. Display only the ping echo's in the top pane using a filter.

```
type 'icmp' (without quotes) in the filter box, and then click 'apply'
```

5. Now ping to a name (like www.linux-training.be) and try to sniff the DNS query and response. Which DNS server was used? Was it a tcp or udp query and response?

```
First start the sniffer.

Enter 'dns' in the filter box and click apply.

root@ubuntu910:~# ping www.linux-training.be

PING www.linux-training.be (88.151.243.8) 56(84) bytes of data.

64 bytes from fosfor.openminds.be (88.151.243.8): icmp_seq=1 ttl=58 time=14.9 ms

64 bytes from fosfor.openminds.be (88.151.243.8): icmp_seq=2 ttl=58 time=16.0 ms


^C

--- www.linux-training.be ping statistics ---

2 packets transmitted, 2 received, 0% packet loss, time 1002ms

rtt min/avg/max/mdev = 14.984/15.539/16.095/0.569 ms
```

The wireshark screen should look something like this.



The details in wireshark will say the DNS query was inside a udp packet.

6. Find an amateur/hobby/club website that features a login prompt. Attempt to login with user 'paul' and password 'hunter2' while your sniffer is running. Now find this information in the sniffer.

# Chapter 24. binding and bonding

Sometimes a server needs more than one **ip address** on the same network card, we call this **binding** ip addresses.

Linux can also activate multiple network cards behind the same **ip address**, this is called **bonding**.

This chapter will teach you how to configure **binding** and **bonding** on the most common Linux distributions.

# 24.1. binding on Redhat/Fedora

#### 24.1.1. binding extra ip addresses

To bind more than one **ip address** to the same interface, use **ifcfg-eth0:0**, where the last zero can be anything else. Only two directives are required in the files.

```
[root@rhel6 ~]# cat /etc/sysconfig/network-scripts/ifcfg-eth0:0
DEVICE="eth0:0"
IPADDR="192.168.1.133"
[root@rhel6 ~]# cat /etc/sysconfig/network-scripts/ifcfg-eth0:1
DEVICE="eth0:0"
IPADDR="192.168.1.142"
```

#### 24.1.2. enabling extra ip-addresses

To activate a virtual network interface, use **ifup**, to deactivate it, use **ifdown**.

#### 24.1.3. verifying extra ip-addresses

Use **ping** from another computer to check the activation, or use **ifconfig** like in this screenshot.

## 24.2. binding on Debian/Ubuntu

#### 24.2.1. binding extra ip addresses

The configuration of multiple ip addresses on the same network card is done in /etc/network/ interfaces by adding eth0:x devices. Adding the netmask is mandatory.

```
debian5:~# cat /etc/network/interfaces
# This file describes the network interfaces available on your system
# and how to activate them. For more information, see interfaces(5).
# The loopback network interface
auto lo
iface lo inet loopback
# The primary network interface
iface eth0 inet static
address 192.168.1.34
network 192.168.1.0
netmask 255.255.255.0
gateway 192.168.1.1
auto eth0
auto eth0:0
iface eth0:0 inet static
address 192.168.1.233
netmask 255.255.255.0
auto eth0:1
iface eth0:1 inet static
address 192.168.1.242
netmask 255.255.255.0
```

#### 24.2.2. enabling extra ip-addresses

Use **ifup** to enable the extra addresses.

```
debian5:~# ifup eth0:0
debian5:~# ifup eth0:1
```

#### 24.2.3. verifying extra ip-addresses

Use **ping** from another computer to check the activation, or use **ifconfig** like in this screenshot.

```
debian5:~# ifconfig | grep 'inet '
   inet addr:192.168.1.34   Bcast:192.168.1.255   Mask:255.255.255.0
   inet addr:192.168.1.233   Bcast:192.168.1.255   Mask:255.255.255.0
   inet addr:192.168.1.242   Bcast:192.168.1.255   Mask:255.255.255.0
   inet addr:127.0.0.1   Mask:255.0.0.0
```

# 24.3. bonding on Redhat/Fedora

We start with **ifconfig -a** to get a list of all the network cards on our system.

```
[root@rhel6 network-scripts]# ifconfig -a | grep Ethernet
eth0    Link encap:Ethernet   HWaddr 08:00:27:DD:0D:5C
eth1    Link encap:Ethernet   HWaddr 08:00:27:DA:C1:49
eth2    Link encap:Ethernet   HWaddr 08:00:27:40:03:3B
```

In this demo we decide to bond **eth1** and **eth2**.

We will name our bond **bond0** and add this entry to **modprobe** so the kernel can load the **bonding module** when we bring the interface up.

```
[root@rhel6 network-scripts]# cat /etc/modprobe.d/bonding.conf
alias bond0 bonding
```

Then we create /etc/sysconfig/network-scripts/ifcfg-bond0 to configure our bond0 interface.

```
[root@rhel6 network-scripts]# pwd
/etc/sysconfig/network-scripts
[root@rhel6 network-scripts]# cat ifcfg-bond0
DEVICE=bond0
IPADDR=192.168.1.199
NETMASK=255.255.255.0
ONBOOT=yes
BOOTPROTO=none
USERCTL=no
```

Next we create two files, one for each network card that we will use as slave in **bond0**.

```
[root@rhel6 network-scripts]# cat ifcfg-eth1
DEVICE=eth1
BOOTPROTO=none
ONBOOT=yes
MASTER=bond0
SLAVE=yes
USERCTL=no
[root@rhel6 network-scripts]# cat ifcfg-eth2
DEVICE=eth2
BOOTPROTO=none
ONBOOT=yes
MASTER=bond0
SLAVE=yes
USERCTL=no
```

Finally we bring the interface up with **ifup bond0**.

The **bond** should also be visible in **/proc/net/bonding**.

```
[root@rhel6 network-scripts]# cat /proc/net/bonding/bond0
Ethernet Channel Bonding Driver: v3.5.0 (November 4, 2008)

Bonding Mode: load balancing (round-robin)
MII Status: up
MII Polling Interval (ms): 0
Up Delay (ms): 0
Down Delay (ms): 0

Slave Interface: eth1
MII Status: up
Link Failure Count: 0
Permanent HW addr: 08:00:27:da:c1:49

Slave Interface: eth2
MII Status: up
Link Failure Count: 0
Permanent HW addr: 08:00:27:40:03:3b
```

# 24.4. bonding on Debian/Ubuntu

We start with **ifconfig -a** to get a list of all the network cards on our system.

```
debian5:~# ifconfig -a | grep Ethernet
eth0    Link encap:Ethernet    HWaddr 08:00:27:bb:18:a4
eth1    Link encap:Ethernet    HWaddr 08:00:27:63:9a:95
eth2    Link encap:Ethernet    HWaddr 08:00:27:27:a4:92
```

In this demo we decide to bond **eth1** and **eth2**.

We also need to install the **ifenslave** package.

```
debian5:~# aptitude search ifenslave
p ifenslave - Attach and detach slave interfaces to a bonding device
p ifenslave-2.6 - Attach and detach slave interfaces to a bonding device
debian5:~# aptitude install ifenslave
Reading package lists... Done
...
```

Next we update the /etc/network/interfaces file with information about the bond0 interface.

```
debian5:~# tail -7 /etc/network/interfaces
iface bond0 inet static
address 192.168.1.42
netmask 255.255.255.0
gateway 192.168.1.1
slaves eth1 eth2
bond-mode active-backup
bond_primary eth1
```

On older version of Debian/Ubuntu you needed to **modprobe bonding**, but this is no longer required. Use **ifup** to bring the interface up, then test that it works.

The **bond** should also be visible in **/proc/net/bonding**.

```
debian5:~# cat /proc/net/bonding/bond0
Ethernet Channel Bonding Driver: v3.2.5 (March 21, 2008)

Bonding Mode: fault-tolerance (active-backup)
Primary Slave: eth1
Currently Active Slave: eth1
MII Status: up
MII Polling Interval (ms): 0
Up Delay (ms): 0
Down Delay (ms): 0

Slave Interface: eth1
MII Status: up
Link Failure Count: 0
```

Permanent HW addr: 08:00:27:63:9a:95

Slave Interface: eth2

MII Status: up

Link Failure Count: 0

Permanent HW addr: 08:00:27:27:a4:92

# 24.5. practice: binding and bonding

- 1. Add an extra **ip address** to one of your network cards. Test that it works (have your neighbour ssh to it)!
- 2. Use **ifdown** to disable this extra **ip address**.
- 3. Make sure your neighbour also succeeded in **binding** an extra ip address before you continue.
- 4. Add an extra network card (or two) to your virtual machine and use the theory to **bond** two network cards.

# 24.6. solution: binding and bonding

1. Add an extra **ip address** to one of your network cards. Test that it works (have your neighbour ssh to it)!

```
Redhat/Fedora:
add an /etc/sysconfig/network-scripts/ifcfg-ethX:X file
as shown in the theory

Debian/Ubuntu:
expand the /etc/network/interfaces file
as shown in the theory
```

2. Use **ifdown** to disable this extra **ip address**.

```
ifdown eth0:0
```

3. Make sure your neighbour also succeeded in **binding** an extra ip address before you continue.

```
ping $extra_ip_neighbour
or
ssh $extra_ip_neighbour
```

4. Add an extra network card (or two) to your virtual machine and use the theory to **bond** two network cards.

```
Redhat/Fedora:
add ifcfg-ethX and ifcfg-bondX files in /etc/sysconfig/network-scripts
as shown in the theory
and don't forget the modprobe.conf

Debian/Ubuntu:
expand the /etc/network/interfaces file
as shown in the theory
and don't forget to install the ifenslave package
```

# Chapter 25. ssh client and server

The **secure shell** or **ssh** is a collection of tools using a secure protocol for communications with remote Linux computers.

This chapter gives an overview of the most common commands related to the use of the **sshd** server and the **ssh** client.

#### 25.1. about ssh

#### 25.1.1. secure shell

Avoid using **telnet**, **rlogin** and **rsh** to remotely connect to your servers. These older protocols do not encrypt the login session, which means your user id and password can be sniffed by tools like **wireshark** or **tcpdump**. To securely connect to your servers, use **ssh**.

The **ssh protocol** is secure in two ways. Firstly the connection is **encrypted** and secondly the connection is **authenticated** both ways.

An ssh connection always starts with a cryptographic handshake, followed by **encryption** of the transport layer using a symmetric cypher. In other words, the tunnel is encrypted before you start typing anything.

Then **authentication** takes place (using user id/password or public/private keys) and communication can begin over the encrypted connection.

The **ssh protocol** will remember the servers it connected to (and warn you in case something suspicious happened).

The **openssh** package is maintained by the **OpenBSD** people and is distributed with a lot of operating systems (it may even be the most popular package in the world).

#### 25.1.2. /etc/ssh/

Configuration of **ssh** client and server is done in the /**etc/ssh** directory. In the next sections we will discuss most of the files found in /**etc/ssh**/.

#### 25.1.3. ssh protocol versions

The **ssh** protocol has two versions (1 and 2). Avoid using version 1 anywhere, since it contains some known vulnerabilities. You can control the protocol version via **/etc/ssh/ssh\_config** for the client side and **/etc/ssh/sshd\_config** for the openssh-server daemon.

```
paul@ubu1204:/etc/ssh$ grep Protocol ssh_config
# Protocol 2,1
paul@ubu1204:/etc/ssh$ grep Protocol sshd_config
Protocol 2
```

#### 25.1.4. public and private keys

The **ssh** protocol uses the well known system of **public and private keys**. The below explanation is succinct, more information can be found on wikipedia.

```
http://en.wikipedia.org/wiki/Public-key_cryptography
```

Imagine Alice and Bob, two people that like to communicate with each other. Using **public** and **private keys** they can communicate with **encryption** and with **authentication**.

When Alice wants to send an encrypted message to Bob, she uses the **public key** of Bob. Bob shares his **public key** with Alice, but keeps his **private key** private! Since Bob is the only one to have Bob's **private key**, Alice is sure that Bob is the only one that can read the encrypted message.

When Bob wants to verify that the message came from Alice, Bob uses the **public key** of Alice to verify that Alice signed the message with her **private key**. Since Alice is the only one to have Alice's **private key**, Bob is sure the message came from Alice.

#### 25.1.5. rsa and dsa algorithms

This chapter does not explain the technical implementation of cryptographic algorithms, it only explains how to use the ssh tools with **rsa** and **dsa**. More information about these algorithms can be found here:

```
http://en.wikipedia.org/wiki/RSA_(algorithm)
http://en.wikipedia.org/wiki/Digital_Signature_Algorithm
```

# 25.2. log on to a remote server

The following screenshot shows how to use **ssh** to log on to a remote computer running Linux. The local user is named **paul** and he is logging on as user **admin42** on the remote system.

```
paul@ubu1204:~$ ssh admin42@192.168.1.30

The authenticity of host '192.168.1.30 (192.168.1.30)' can't be established.

RSA key fingerprint is b5:fb:3c:53:50:b4:ab:81:f3:cd:2e:bb:ba:44:d3:75.

Are you sure you want to continue connecting (yes/no)?
```

As you can see, the user **paul** is presented with an **rsa** authentication fingerprint from the remote system. The user can accepts this bu typing **yes**. We will see later that an entry will be added to the **~/.ssh/known\_hosts** file.

```
paul@ubu1204:~$ ssh admin42@192.168.1.30
The authenticity of host '192.168.1.30 (192.168.1.30)' can't be established.
RSA key fingerprint is b5:fb:3c:53:50:b4:ab:81:f3:cd:2e:bb:ba:44:d3:75.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added '192.168.1.30' (RSA) to the list of known hosts.
admin42@192.168.1.30's password:
Welcome to Ubuntu 12.04 LTS (GNU/Linux 3.2.0-26-generic-pae i686)

* Documentation: https://help.ubuntu.com/

1 package can be updated.
0 updates are security updates.

Last login: Wed Jun 6 19:25:57 2012 from 172.28.0.131
admin42@ubuserver:~$
```

The user can get log out of the remote server by typing **exit** or by using **Ctrl-d**.

```
admin42@ubuserver:~$ exit
logout
Connection to 192.168.1.30 closed.
paul@ubu1204:~$
```

# 25.3. executing a command in remote

This screenshot shows how to execute the **pwd** command on the remote server. There is no need to **exit** the server manually.

```
paul@ubu1204:~$ ssh admin42@192.168.1.30 pwd
admin42@192.168.1.30's password:
/home/admin42
paul@ubu1204:~$
```

# 25.4. scp

The **scp** command works just like **cp**, but allows the source and destination of the copy to be behind **ssh**. Here is an example where we copy the **/etc/hosts** file from the remote server to the home directory of user paul.

Here is an example of the reverse, copying a local file to a remote server.

# 25.5. setting up passwordless ssh

To set up passwordless ssh authentication through public/private keys, use **ssh-keygen** to generate a key pair without a passphrase, and then copy your public key to the destination server. Let's do this step by step.

In the example that follows, we will set up ssh without password between Alice and Bob. Alice has an account on a Red Hat Enterprise Linux server, Bob is using Ubuntu on his laptop. Bob wants to give Alice access using ssh and the public and private key system. This means that even if Bob changes his password on his laptop, Alice will still have access.

#### 25.5.1. ssh-keygen

The example below shows how Alice uses **ssh-keygen** to generate a key pair. Alice does not enter a passphrase.

```
[alice@RHEL5 ~]$ ssh-keygen -t rsa
Generating public/private rsa key pair.
Enter file in which to save the key (/home/alice/.ssh/id_rsa):
Created directory '/home/alice/.ssh'.
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in /home/alice/.ssh/id_rsa.
Your public key has been saved in /home/alice/.ssh/id_rsa.pub.
The key fingerprint is:
9b:ac:ac:56:c2:98:e5:d9:18:c4:2a:51:72:bb:45:eb alice@RHEL5
[alice@RHEL5 ~]$
```

You can use **ssh-keygen -t dsa** in the same way.

#### 25.5.2. ~/.ssh

While **ssh-keygen** generates a public and a private key, it will also create a hidden **.ssh** directory with proper permissions. If you create the **.ssh** directory manually, then you need to chmod 700 it! Otherwise ssh will refuse to use the keys (world readable private keys are not secure!).

As you can see, the **.ssh** directory is secure in Alice's home directory.

```
[alice@RHEL5 ~]$ ls -ld .ssh
drwx----- 2 alice alice 4096 May 1 07:38 .ssh
[alice@RHEL5 ~]$
```

Bob is using Ubuntu at home. He decides to manually create the **.ssh** directory, so he needs to manually secure it.

```
bob@laika:~$ mkdir .ssh
bob@laika:~$ ls -ld .ssh
drwxr-xr-x 2 bob bob 4096 2008-05-14 16:53 .ssh
bob@laika:~$ chmod 700 .ssh/
bob@laika:~$
```

#### 25.5.3. id\_rsa and id\_rsa.pub

The **ssh-keygen** command generate two keys in .ssh. The public key is named **~/.ssh/id\_rsa.pub**. The private key is named **~/.ssh/id\_rsa**.

```
[alice@RHEL5 ~]$ ls -l .ssh/
total 16
-rw----- 1 alice alice 1671 May 1 07:38 id_rsa
-rw-r--r- 1 alice alice 393 May 1 07:38 id_rsa.pub
```

The files will be named **id\_dsa** and **id\_dsa.pub** when using **dsa** instead of **rsa**.

### 25.5.4. copy the public key to the other computer

To copy the public key from Alice's server tot Bob's laptop, Alice decides to use scp.

Be careful when copying a second key! Do not overwrite the first key, instead append the key to the same ~/.ssh/authorized\_keys file!

```
cat id_rsa.pub >> ~/.ssh/authorized_keys
```

Alice could also have used **ssh-copy-id** like in this example.

```
ssh-copy-id -i .ssh/id_rsa.pub bob@192.168.48.92
```

#### 25.5.5. authorized\_keys

In your ~/.ssh directory, you can create a file called **authorized\_keys**. This file can contain one or more public keys from people you trust. Those trusted people can use their private keys to prove their identity and gain access to your account via ssh (without password). The example shows Bob's authorized\_keys file containing the public key of Alice.

```
bob@laika:~$ cat .ssh/authorized_keys
ssh-rsa AAAAB3NzaClyc2EAAAABIwAAAQEApCQ9xzyLzJes1sR+hPyqW2vyzt1D4zTLqk\
MDWBR4mMFuUZD/O583I3Lg/Q+JIq0RSksNzaL/BNLDou1jMpBe2Dmf/u22u4KmqlJBfDhe\
yTmGSBzeNYCYRSMq78CT919a+y6x/shucwhaILsy8A2XfJ9VCggkVtu7XlWFDL2cum08/0\
mRFwVrfc/uPsAn5XkkTsc14g21mQbnp9wJC40pGSJXXMuF0k8MgCb5ieSnpKFniAKM+tEo\
/vjDGSi3F/bxu691jscrU0VUdIoOSo98HUfEf7jKBRikxGAC7I4HLa+/zX73OIvRFAb2hv\
tUhn6RHrBtUJUjbSGiYeFTLDfcTQ== alice@RHEL5
```

#### 25.5.6. passwordless ssh

Alice can now use ssh to connect passwordless to Bob's laptop. In combination with **ssh**'s capability to execute commands on the remote host, this can be useful in pipes across different machines.

```
[alice@RHEL5 ~]$ ssh bob@192.168.48.92 "ls -l .ssh"
total 4
-rw-r--r- 1 bob bob 393 2008-05-14 17:03 authorized_keys
[alice@RHEL5 ~]$
```

# 25.6. X forwarding via ssh

Another popular feature of ssh is called X11 forwarding and is implemented with ssh -X.

Below an example of X forwarding: user paul logs in as user greet on her computer to start the graphical application mozilla-thunderbird. Although the application will run on the remote computer from greet, it will be displayed on the screen attached locally to paul's computer.

```
paul@debian5:~/PDF$ ssh -X greet@greet.dyndns.org -p 55555
Warning: Permanently added the RSA host key for IP address \
'81.240.174.161' to the list of known hosts.
Password:
Linux raika 2.6.8-2-686 #1 Tue Aug 16 13:22:48 UTC 2005 i686 GNU/Linux

Last login: Thu Jan 18 12:35:56 2007
greet@raika:~$ ps fax | grep thun
greet@raika:~$ mozilla-thunderbird &
[1] 30336
```

# 25.7. troubleshooting ssh

Use **ssh** -**v** to get debug information about the ssh connection attempt.

```
paul@debian5:~$ ssh -v bert@192.168.1.192
OpenSSH_4.3p2 Debian-8ubuntu1, OpenSSL 0.9.8c 05 Sep 2006
debug1: Reading configuration data /home/paul/.ssh/config
debug1: Reading configuration data /etc/ssh/ssh_config
debug1: Applying options for *
debug1: Connecting to 192.168.1.192 [192.168.1.192] port 22.
debug1: Connection established.
debug1: identity file /home/paul/.ssh/identity type -1
debug1: identity file /home/paul/.ssh/id_rsa type 1
debug1: identity file /home/paul/.ssh/id_dsa type -1
debug1: Remote protocol version 1.99, remote software version OpenSSH_3
debug1: match: OpenSSH_3.9p1 pat OpenSSH_3.*
debug1: Enabling compatibility mode for protocol 2.0
...
```

#### 25.8. sshd

The ssh server is called **sshd** and is provided by the **openssh-server** package.

```
root@ubu1204~# dpkg -l openssh-server | tail -l
ii openssh-server 1:5.9p1-5ubuntul secure shell (SSH) server,...
```

# 25.9. sshd keys

The public keys used by the sshd server are located in /etc/ssh and are world readable. The private keys are only readable by root.

```
root@ubu1204~# ls -l /etc/ssh/ssh_host_*
-rw----- l root root 668 Jun 7 2011 /etc/ssh/ssh_host_dsa_key
-rw-r--r- l root root 598 Jun 7 2011 /etc/ssh/ssh_host_dsa_key.pub
-rw----- l root root 1679 Jun 7 2011 /etc/ssh/ssh_host_rsa_key
-rw-r--r- l root root 390 Jun 7 2011 /etc/ssh/ssh_host_rsa_key.pub
```

# 25.10. ssh-agent

When generating keys with **ssh-keygen**, you have the option to enter a passphrase to protect access to the keys. To avoid having to type this passphrase every time, you can add the key to **ssh-agent** using **ssh-add**.

Most Linux distributions will start the **ssh-agent** automatically when you log on.

```
root@ubu1204~# ps -ef | grep ssh-agent
paul 2405 2365 0 08:13 ? 00:00:00 /usr/bin/ssh-agent...
```

This clipped screenshot shows how to use **ssh-add** to list the keys that are currently added to the **ssh-agent** 

```
paul@debian5:~$ ssh-add -L
ssh-rsa AAAAB3NzaClyc2EAAAABIwAAAQEAvgI+Vx5UrIsusZPl8da8URHGsxG7yivv3/\
...
wMGqa48Kelwom8TGb4Sgcwpp/V0/ldA5m+BGCw== paul@deb503
```

## 25.11. practice: ssh

- 0. Make sure that you have access to **two Linux computers**, or work together with a partner for this exercise. For this practice, we will name one of the machines the server.
- 1. Install **sshd** on the server
- 2. Verify in the ssh configuration files that only protocol version 2 is allowed.
- 3. Use **ssh** to log on to the server, show your current directory and then exit the server.
- 4. Use **scp** to copy a file from your computer to the server.
- 5. Use **scp** to copy a file from the server to your computer.
- 6. (optional, only works when you have a graphical install of Linux) Install the xeyes package on the server and use ssh to run xeyes on the server, but display it on your client.
- 7. (optional, same as previous) Create a bookmark in firefox, then quit firefox on client and server. Use **ssh** -**X** to run firefox on your display, but on your neighbour's computer. Do you see your neighbour's bookmark?
- 8. Use **ssh-keygen** to create a key pair without passphrase. Setup passwordless ssh between you and your neighbour. (or between your client and your server)
- 9. Verify that the permissions on the server key files are correct; world readable for the public keys and only root access for the private keys.
- 10. Verify that the **ssh-agent** is running.
- 11. (optional) Protect your keypair with a **passphrase**, then add this key to the **ssh-agent** and test your passwordless ssh to the server.

#### 25.12. solution: ssh

- 0. Make sure that you have access to **two Linux computers**, or work together with a partner for this exercise. For this practice, we will name one of the machines the server.
- 1. Install **sshd** on the server

```
apt-get install openssh-server (on Ubuntu/Debian)
yum -y install openssh-server (on Centos/Fedora/Red Hat)
```

2. Verify in the ssh configuration files that only protocol version 2 is allowed.

```
grep Protocol /etc/ssh/ssh*_config
```

3. Use **ssh** to log on to the server, show your current directory and then exit the server.

```
user@client$ ssh user@server-ip-address
user@server$ pwd
/home/user
user@server$ exit
```

4. Use **scp** to copy a file from your computer to the server.

```
scp localfile user@server:~
```

5. Use **scp** to copy a file from the server to your computer.

```
scp user@server:~/serverfile .
```

6. (optional, only works when you have a graphical install of Linux) Install the xeyes package on the server and use ssh to run xeyes on the server, but display it on your client.

```
on the server:
apt-get install xeyes
on the client:
ssh -X user@server-ip
xeyes
```

- 7. (optional, same as previous) Create a bookmark in firefox, then quit firefox on client and server. Use **ssh** -**X** to run firefox on your display, but on your neighbour's computer. Do you see your neighbour's bookmark?
- 8. Use **ssh-keygen** to create a key pair without passphrase. Setup passwordless ssh between you and your neighbour. (or between your client and your server)

```
See solution in book "setting up passwordless ssh"
```

9. Verify that the permissions on the server key files are correct; world readable for the public keys and only root access for the private keys.

```
ls -l /etc/ssh/ssh_host_*
```

10. Verify that the **ssh-agent** is running.

```
ps fax | grep ssh-agent
```

11. (optional) Protect your keypair with a **passphrase**, then add this key to the **ssh-agent** and test your passwordless ssh to the server.

man ssh-keygen man ssh-agent man ssh-add

# Chapter 26. introduction to nfs

The **network file system** (or simply **nfs**) enables us since the Eighties to share a directory with other computers on the network.

In this chapter we see how to setup an **nfs** server and an **nfs** client computer.

# 26.1. nfs protocol versions

The older **nfs** versions 2 and 3 are stateless (**udp**) by default (but they can use **tcp**). The more recent **nfs** version 4 brings a stateful protocol with better performance and stronger security.

NFS version 4 was defined in **rfc 3010** in 2000 and **rfc 3530** in 2003 and requires tcp (port 2049). It also supports **Kerberos** user authentication as an option when mounting a share. NFS versions 2 and 3 authenticate only the host.

# 26.2. rpcinfo

Clients connect to the server using **rpc** (on Linux this can be managed by the **portmap** daemon). Look at **rpcinfo** to verify that **nfs** and its related services are running.

```
root@RHELv4u2:~# /etc/init.d/portmap status
portmap (pid 1920) is running...
root@RHELv4u2:~# rpcinfo -p
program vers proto port
100000 2 tcp 111 portmapper
100000 2 udp 111 portmapper
100024 1 udp 32768 status
100024 1 tcp 32769 status
root@RHELv4u2:~# service nfs start
Starting NFS services: [ OK ]
Starting NFS quotas: [ OK ]
Starting NFS daemon: [ OK ]
Starting NFS mountd: [ OK ]
```

The same **rpcinfo** command when **nfs** is started.

```
root@RHELv4u2:~# rpcinfo -p
program vers proto port
100000 2 tcp 111 portmap
100000 2 udp 111 portmap
100024 1 udp 32768 status
100024 1 tcp 32769 status
                    111 portmapper
                    111 portmapper
100011 1 udp
                  985 rquotad
100011 2 udp
                  985 rquotad
100011 1 tcp 988 rquotad
100011 2 tcp
                  988 rquotad
100003 2 udp 2049 nfs
100003 3 udp 2049 nfs
100003 4 udp 2049 nfs
100003 2 tcp 2049 nfs
        3 tcp 2049 nfs
4 tcp 2049 nfs
1 udp 32770 nlockmgr
3 udp 32770 nlockmgr
100003
100003
100021
100021
        4 udp 32770 nlockmgr
100021
        1 tcp 32789 nlockmgr
100021
100021 3 tcp 32789 nlockmgr
100021 4 tcp 32789 nlockmgr
100005 1 udp 1004 mountd
100005 1 tcp 1007 mountd
100005 2 udp 1004 mountd
100005 2 tcp 1007 mountd
100005 3 udp 1004 mountd
100005 3 tcp 1007 mountd
```

# 26.3. server configuration

**nfs** is configured in /**etc/exports**. You might want some way (**ldap**?) to synchronize userid's across computers when using **nfs** a lot.

The **rootsquash** option will change UID 0 to the UID of a **nobody** (or similar) user account. The **sync** option will write writes to disk before completing the client request.

# 26.4. /etc/exports

Here is a sample /etc/exports to explain the syntax:

```
paul@laika:~$ cat /etc/exports
# Everyone can read this share
/mnt/data/iso *(ro)

# Only the computers named pasha and barry can readwrite this one
/var/www pasha(rw) barry(rw)

# same, but without root squashing for barry
/var/ftp pasha(rw) barry(rw,no_root_squash)

# everyone from the netsec.local domain gets access
/var/backup *.netsec.local(rw)

# ro for one network, rw for the other
/var/upload 192.168.1.0/24(ro) 192.168.5.0/24(rw)
```

More recent incarnations of **nfs** require the **subtree\_check** option to be explicitly set (or unset with **no\_subtree\_check**). The **/etc/exports** file then looks like this:

```
root@debian6 ~# cat /etc/exports
# Everyone can read this share
/srv/iso *(ro,no_subtree_check)

# Only the computers named pasha and barry can readwrite this one
/var/www pasha(rw,no_subtree_check) barry(rw,no_subtree_check)

# same, but without root squashing for barry
/var/ftp pasha(rw,no_subtree_check) barry(rw,no_root_squash,no_subtree_check)
```

## 26.5. exportfs

You don't need to restart the nfs server to start exporting your newly created exports. You can use the **exportfs -va** command to do this. It will write the exported directories to /var/lib/nfs/etab, where they are immediately applied.

```
root@debian6 ~# exportfs -va
exporting pasha:/var/ftp
exporting barry:/var/ftp
exporting pasha:/var/www
exporting barry:/var/www
exporting *:/srv/iso
```

# 26.6. client configuration

We have seen the **mount** command and the /etc/fstab file before.

```
root@RHELv4u2:~# mount -t nfs barry:/mnt/data/iso /home/project55/
root@RHELv4u2:~# cat /etc/fstab | grep nfs
barry:/mnt/data/iso /home/iso nfs defaults 0 0
root@RHELv4u2:~#
```

Here is another simple example. Suppose the project55 people tell you they only need a couple of CD-ROM images, and you already have them available on an **nfs** server. You could issue the following command to mount this storage on their **/home/project55** mount point.

```
root@RHELv4u2:~# mount -t nfs 192.168.1.40:/mnt/data/iso /home/project55/
root@RHELv4u2:~# ls -lh /home/project55/
total 3.6G
drwxr-xr-x 2 1000 1000 4.0K Jan 16 17:55 RHELv4u1
drwxr-xr-x 2 1000 1000 4.0K Jan 16 14:14 RHELv4u2
drwxr-xr-x 2 1000 1000 4.0K Jan 16 14:54 RHELv4u3
drwxr-xr-x 2 1000 1000 4.0K Jan 16 11:09 RHELv4u4
-rw-r--r-- 1 root root 1.6G Oct 13 15:22 sled10-vmwarews5-vm.zip
root@RHELv4u2:~#
```

# 26.7. practice: introduction to nfs

- 1. Create two directories with some files. Use **nfs** to share one of them as read only, the other must be writable. Have your neighbour connect to them to test.
- 2. Investigate the user owner of the files created by your neighbour.
- 3. Protect a share by ip-address or hostname, so only your neighbour can connect.

# Chapter 27. introduction to networking

# 27.1. introduction to iptables

#### 27.1.1. iptables firewall

The Linux kernel has a built-in stateful firewall named **iptables**. To stop the **iptables** firewall on Red Hat, use the service command.

```
root@RHELv4u4:~# service iptables stop

Flushing firewall rules: [ OK ]

Setting chains to policy ACCEPT: filter [ OK ]

Unloading iptables modules: [ OK ]

root@RHELv4u4:~#
```

The easy way to configure iptables, is to use a graphical tool like KDE's **kmyfirewall** or **Security Level Configuration Tool**. You can find the latter in the graphical menu, somewhere in System Tools - Security, or you can start it by typing **system-config-securitylevel** in bash. These tools allow for some basic firewall configuration. You can decide whether to enable or disable the firewall, and what typical standard ports are allowed when the firewall is active. You can even add some custom ports. When you are done, the configuration is written to **/etc/sysconfig/iptables** on Red Hat.

```
root@RHELv4u4:~# cat /etc/sysconfig/iptables
# Firewall configuration written by system-config-securitylevel
# Manual customization of this file is not recommended.
*filter
:INPUT ACCEPT [0:0]
:FORWARD ACCEPT [0:0]
:OUTPUT ACCEPT [0:0]
:RH-Firewall-1-INPUT - [0:0]
-A INPUT -j RH-Firewall-1-INPUT
-A FORWARD -j RH-Firewall-1-INPUT
-A RH-Firewall-1-INPUT -i lo -j ACCEPT
-A RH-Firewall-1-INPUT -p icmp --icmp-type any -j ACCEPT
-A RH-Firewall-1-INPUT -p 50 -j ACCEPT
-A RH-Firewall-1-INPUT -p 51 -j ACCEPT
-A RH-Firewall-1-INPUT -p udp --dport 5353 -d 224.0.0.251 -j ACCEPT
-A RH-Firewall-1-INPUT -p udp -m udp --dport 631 -j ACCEPT
-A RH-Firewall-1-INPUT -m state --state ESTABLISHED, RELATED -j ACCEPT
-A RH-F...NPUT -m state --state NEW -m tcp -p tcp --dport 22 -j ACCEPT
-A RH-F...NPUT -m state --state NEW -m tcp -p tcp --dport 80 -j ACCEPT
-A RH-F...NPUT -m state --state NEW -m tcp -p tcp --dport 21 -j ACCEPT
-A RH-F...NPUT -m state --state NEW -m tcp -p tcp --dport 25 -j ACCEPT
-A RH-Firewall-1-INPUT -j REJECT --reject-with icmp-host-prohibited
COMMIT
root@RHELv4u4:~#
```

To start the service, issue the **service iptables start** command. You can configure iptables to start at boot time with chkconfig.

```
root@RHELv4u4:~# service iptables start
Applying iptables firewall rules: [ OK ]
root@RHELv4u4:~# chkconfig iptables on
root@RHELv4u4:~#
```

One of the nice features of iptables is that it displays extensive **status** information when queried with the **service iptables status** command.

```
root@RHELv4u4:~# service iptables status
Table: filter
Chain INPUT (policy ACCEPT)
target prot opt source
                                       destination
RH-Firewall-1-INPUT all -- 0.0.0.0/0
                                                0.0.0.0/0
Chain FORWARD (policy ACCEPT)
target prot opt source
                                       destination
RH-Firewall-1-INPUT all -- 0.0.0.0/0
                                                0.0.0.0/0
Chain OUTPUT (policy ACCEPT)
         prot opt source
                                       destination
Chain RH-Firewall-1-INPUT (2 references)
target prot opt source destination
ACCEPT all -- 0.0.0.0/0 0.0.0.0/0
ACCEPT icmp -- 0.0.0.0/0 0.0.0.0/0
                                      icmp type 255
ACCEPT esp -- 0.0.0.0/0
ACCEPT ah -- 0.0.0.0/0
                           0.0.0.0/0
                           0.0.0.0/0
       udp -- 0.0.0.0/0
ACCEPT
                           224.0.0.251 udp dpt:5353
ACCEPT udp -- 0.0.0.0/0
                          0.0.0.0/0 udp dpt:631
ACCEPT all -- 0.0.0.0/0 0.0.0/0 state RELATED, ESTABLISHED
ACCEPT tcp -- 0.0.0.0/0 0.0.0.0/0 state NEW tcp dpt:22
ACCEPT tcp -- 0.0.0.0/0 0.0.0.0/0 state NEW tcp dpt:80
ACCEPT tcp -- 0.0.0.0/0 0.0.0.0/0 state NEW tcp dpt:21
ACCEPT tcp -- 0.0.0.0/0
                          0.0.0.0/0 state NEW tcp dpt:25
REJECT all -- 0.0.0.0/0
                          0.0.0.0/0 reject-with icmp-host-prohibited
root@RHELv4u4:~#
```

Mastering firewall configuration requires a decent knowledge of tcp/ip. Good iptables tutorials can be found online here http://iptables-tutorial.frozentux.net/iptables-tutorial.html and here http://tldp.org/HOWTO/IP-Masquerade-HOWTO/.

# 27.2. practice: iptables

- 1. Verify whether the firewall is running.
- 2. Stop the running firewall.

# 27.3. solution: iptables

#### 1. Verify whether the firewall is running.

```
root@rhel55 ~# service iptables status | head
Table: filter
Chain INPUT (policy ACCEPT)
num target prot opt source destination
1 RH-Firewall-1-INPUT all -- 0.0.0.0/0
Chain FORWARD (policy ACCEPT)
num target prot opt source destination
1 RH-Firewall-1-INPUT all -- 0.0.0.0/0
Chain OUTPUT (policy ACCEPT)
```

#### 2. Stop the running firewall.

```
root@rhel55 ~# service iptables stop

Flushing firewall rules: [ OK ]

Setting chains to policy ACCEPT: filter [ OK ]

Unloading iptables modules: [ OK ]

root@rhel55 ~# service iptables status

Firewall is stopped.
```

### 27.4. xinetd and inetd

## 27.4.1. the superdaemon

Back when resources like RAM memory were limited, a super-server was devised to listen to all sockets and start the appropriate daemon only when needed. Services like **swat**, **telnet** and **ftp** are typically served by such a super-server. The **xinetd** superdaemon is more recent than **inetd**. We will discuss the configuration both daemons.

Recent Linux distributions like RHEL5 and Ubuntu10.04 do not activate **inetd** or **xinetd** by default, unless an application requires it.

### 27.4.2. inetd or xinetd

First verify whether your computer is running **inetd** or **xinetd**. This Debian 4.0 Etch is running **inetd**.

```
root@barry:~# ps fax | grep inet
3870 ? Ss 0:00 /usr/sbin/inetd
```

This Red Hat Enterprise Linux 4 update 4 is running **xinetd**.

Both daemons have the same functionality (listening to many ports, starting other daemons when they are needed), but they have different configuration files.

## 27.4.3. xinetd superdaemon

The **xinetd** daemon is often called a superdaemon because it listens to a lot of incoming connections, and starts other daemons when they are needed. When a connection request is received, **xinetd** will first check TCP wrappers (/etc/hosts.allow and /etc/hosts.deny) and then give control of the connection to the other daemon. This superdaemon is configured through /etc/xinetd.conf and the files in the directory /etc/xinetd.d. Let's first take a look at /etc/xinetd.conf.

```
}
includedir /etc/xinetd.d
paul@RHELv4u2:~$
```

According to the settings in this file, xinetd can handle 60 client requests at once. It uses the **authpriv** facility to log the host ip-address and pid of successful daemon spawns. When a service (aka protocol linked to daemon) gets more than 25 cps (connections per second), it holds subsequent requests for 30 seconds.

The directory /etc/xinetd.d contains more specific configuration files. Let's also take a look at one of them.

```
paul@RHELv4u2:~$ ls /etc/xinetd.d
                            klogin rexec talk
amanda chargen-udp echo
amandaidx cups-lpd echo-udp krb5-telnet rlogin telnet
amidxtape daytime
                     eklogin kshell rsh tftp
auth daytime-udp finger ktalk chargen dbskkd-cdb gssftp ntalk
                                          rsync time
                                          swat time-udp
paul@RHELv4u2:~$ cat /etc/xinetd.d/swat
# default: off
# description: SWAT is the Samba Web Admin Tool. Use swat \
        to configure your Samba server. To use SWAT, \setminus
            connect to port 901 with your favorite web browser.
service swat
{
port = 901
socket_type = stream
user
              = root
             = /usr/sbin/swat
log_on_failure += USERID
disable
              = yes
}
paul@RHELv4u2:~$
```

The services should be listed in the /etc/services file. Port determines the service port, and must be the same as the port specified in /etc/services. The socket\_type should be set to stream for tcp services (and to dgram for udp). The log\_on\_failure += concats the userid to the log message formatted in /etc/xinetd.conf. The last setting disable can be set to yes or no. Setting this to no means the service is enabled!

Check the xinetd and xinetd.conf manual pages for many more configuration options.

## 27.4.4. inetd superdaemon

This superdaemon has only one configuration file /etc/inetd.conf. Every protocol or daemon that it is listening for, gets one line in this file.

```
root@barry:~# grep ftp /etc/inetd.conf
tftp dgram udp wait nobody /usr/sbin/tcpd /usr/sbin/in.tftpd /boot/tftp
root@barry:~#
```

You can disable a service in inetd.conf above by putting a # at the start of that line. Here an example of the disabled vmware web interface (listening on tcp port 902).

```
paul@laika:~$ grep vmware /etc/inetd.conf
#902 stream tcp nowait root /usr/sbin/vmware-authd vmware-authd
```

# 27.5. practice: inetd and xinetd

- 1. Verify on all systems whether they are using xinetd or inetd.
- 2. Look at the configuration files.
- 3. (If telnet is installable, then replace swat in these questions with telnet) Is swat installed? If not, then install swat and look at the changes in the (x)inetd configuration. Is swat enabled or disabled?
- 4. Disable swat, test it. Enable swat, test it.

## 27.6. network file system

## 27.6.1. protocol versions

The older **nfs** versions 2 and 3 are stateless (udp) by default, but they can use tcp. Clients connect to the server using **rpc** (on Linux this is controlled by the **portmap** daemon. Look at **rpcinfo** to verify that **nfs** and its related services are running.

```
root@RHELv4u2:~# /etc/init.d/portmap status
portmap (pid 1920) is running...
root@RHELv4u2:~# rpcinfo -p
program vers proto port
100000 2 tcp 111 portmapper
100000 2 udp 111 portmapper
100024 1 udp 32768 status
100024 1 tcp 32769 status
root@RHELv4u2:~# service nfs start
Starting NFS services: [ OK ]
Starting NFS quotas: [ OK ]
Starting NFS daemon: [ OK ]
Starting NFS mountd: [ OK ]
```

The same **rpcinfo** command when **nfs** is started.

```
root@RHELv4u2:~# rpcinfo -p
program vers proto port
100000 2 tcp 111 portmapper
100000 2 udp 111 portmapper
100024 1 udp 32768 status
100024 1 tcp 32769 status
100024 1 tcp 32769 status

100011 1 udp 985 rquotad

100011 2 udp 985 rquotad

100011 1 tcp 988 rquotad

100011 2 tcp 988 rquotad

100003 2 udp 2049 nfs

100003 3 udp 2049 nfs

100003 4 udp 2049 nfs

100003 2 tcp 2049 nfs

100003 3 tcp 2049 nfs
100003 4 tcp 2049 nfs
100021 1 udp 32770 nlockmgr
100021 3 udp 32770 nlockmgr
100021 4 udp 32770 nlockmgr
100021 1 tcp 32789 nlockmgr
100021 3 tcp 32789 nlockmgr
100021 4 tcp 32789 nlockmgr
100005 1 udp 1004 mountd
100005 1 tcp 1007 mountd
100005 2 udp 1004 mountd
100005 2 tcp 1007 mountd
100005
              3
                            1004 mountd
100005
                    udp
100005 3 tcp
                            1007 mountd
root@RHELv4u2:~#
```

**nfs version 4** requires tcp (port 2049) and supports **Kerberos** user authentication as an option. **nfs** authentication only takes place when mounting the share. **nfs** versions 2 and 3 authenticate only the host.

## 27.6.2. server configuration

**nfs** is configured in /etc/exports. Here is a sample /etc/exports to explain the syntax. You need some way (NIS domain or LDAP) to synchronize userid's across computers when using **nfs** a lot. The **rootsquash** option will change UID 0 to the UID of the nfsnobody user account. The **sync** option will write writes to disk before completing the client request.

```
paul@laika:~$ cat /etc/exports
# Everyone can read this share
/mnt/data/iso *(ro)

# Only the computers barry and pasha can readwrite this one
/var/www pasha(rw) barry(rw)

# same, but without root squashing for barry
/var/ftp pasha(rw) barry(rw,no_root_squash)

# everyone from the netsec.lan domain gets access
/var/backup *.netsec.lan(rw)

# ro for one network, rw for the other
/var/upload 192.168.1.0/24(ro) 192.168.5.0/24(rw)
```

You don't need to restart the nfs server to start exporting your newly created exports. You can use the **exportfs -va** command to do this. It will write the exported directories to /var/lib/nfs/etab, where they are immediately applied.

## 27.6.3. client configuration

We have seen the **mount** command and the /etc/fstab file before.


```
root@RHELv4u2:~# mount -t nfs barry:/mnt/data/iso /home/project55/
root@RHELv4u2:~# cat /etc/fstab | grep nfs
barry:/mnt/data/iso /home/iso nfs defaults 0 0
root@RHELv4u2:~#
```

Here is another simple example. Suppose the project55 people tell you they only need a couple of CD-ROM images, and you already have them available on an **nfs** server. You could issue the following command to mount this storage on their /home/project55 mount point.

```
root@RHELv4u2:~# mount -t nfs 192.168.1.40:/mnt/data/iso /home/project55/
root@RHELv4u2:~# ls -lh /home/project55/
total 3.6G
drwxr-xr-x 2 1000 1000 4.0K Jan 16 17:55 RHELv4u1
drwxr-xr-x 2 1000 1000 4.0K Jan 16 14:14 RHELv4u2
drwxr-xr-x 2 1000 1000 4.0K Jan 16 14:54 RHELv4u3
drwxr-xr-x 2 1000 1000 4.0K Jan 16 11:09 RHELv4u4
-rw-r--r- 1 root root 1.6G Oct 13 15:22 sled10-vmwarews5-vm.zip
root@RHELv4u2:~#
```

# 27.7. practice : network file system

- 1. Create two directories with some files. Use **nfs** to share one of them as read only, the other must be writable. Have your neighbour connect to them to test.
- 2. Investigate the user owner of the files created by your neighbour.
- 3. Protect a share by ip-address or hostname, so only your neighbour can connect.



## **Table of Contents**

| 28. the Linux kernel         | 325 |
|------------------------------|-----|
| 28.1. about the Linux kernel |     |
| 28.2. Linux kernel source    | 329 |
| 28.3. kernel boot files      |     |
| 28.4. Linux kernel modules   |     |
| 28.5. compiling a kernel     | 340 |
| 28.6. compiling one module   | 343 |
| 29. library management       | 345 |
|                              |     |
| 29.2. /lib and /usr/lib      | 346 |
| 29.3. ldd                    |     |
| 29.4. ltrace                 | 347 |
| 29.5. dpkg -S and debsums    | 347 |
| 29.6. rpm -qf and rpm -V     | 348 |
| 29.7. tracing with strace    | 349 |



## 28.1. about the Linux kernel

### 28.1.1. kernel versions

In 1991 Linux Torvalds wrote (the first version of) the Linux kernel. He put it online, and other people started contributing code. Over 4000 individuals contributed source code to the latest kernel release (version 2.6.27 in November 2008).

Major Linux kernel versions used to come in even and odd numbers. Versions **2.0**, **2.2**, **2.4** and **2.6** are considered stable kernel versions. Whereas **2.1**, **2.3** and **2.5** were unstable (read development) versions. Since the release of 2.6.0 in January 2004, all development has been done in the 2.6 tree. There is currently no v2.7.x and according to Linus the even/stable vs odd/development scheme is abandoned forever.

#### 28.1.2. uname -r

To see your current Linux kernel version, issue the **uname -r** command as shown below.

This first example shows Linux major version **2.6** and minor version **24**. The rest **-22-generic** is specific to the distribution (Ubuntu in this case).

```
paul@laika:~$ uname -r
2.6.24-22-generic
```

The same command on Red Hat Enterprise Linux shows an older kernel (2.6.18) with **-92.1.17.el5** being specific to the distribution.

```
[paul@RHEL52 ~]$ uname -r
2.6.18-92.1.17.el5
```

## 28.1.3. /proc/cmdline

The parameters that were passed to the kernel at boot time are in /proc/cmdline.

```
paul@RHELv4u4:~$ cat /proc/cmdline
ro root=/dev/VolGroup00/LogVol00 rhgb quiet
```

## 28.1.4. single user mode

When booting the kernel with the **single** parameter, it starts in **single user mode**. Linux can start in a bash shell with the **root** user logged on (without password).

Some distributions prevent the use of this feature (at kernel compile time).

### 28.1.5. init=/bin/bash

Normally the kernel invokes **init** as the first daemon process. Adding **init=/bin/bash** to the kernel parameters will instead invoke bash (again with root logged on without providing a password).

## 28.1.6. /var/log/messages

The kernel reports during boot to **syslog** which writes a lot of kernel actions in /**var/log/messages**. Looking at this file reveals when the kernel was started, including all the devices that were detected at boot time.

```
[root@RHEL53 ~]# grep -A16 "syslogd 1.4.1:" /var/log/messages|cut -b24-
syslogd 1.4.1: restart.
kernel: klogd 1.4.1, log source = /proc/kmsg started.
kernel: Linux version 2.6.18-128.el5 (mockbuild@hs20-bc1-5.build.red...
kernel: BIOS-provided physical RAM map:
kernel: BIOS-e820: 000000000000000 - 00000000009f800 (usable)
kernel: BIOS-e820: 000000000009f800 - 00000000000a0000 (reserved)
kernel: BIOS-e820: 000000001fef0000 - 000000001feff000 (ACPI data)
kernel: BIOS-e820: 000000001feff000 - 000000001ff00000 (ACPI NVS)
kernel: BIOS-e820: 000000001ff00000 - 0000000020000000 (usable)
kernel: BIOS-e820: 00000000fec000000 - 00000000fec10000 (reserved)
kernel: BIOS-e820: 00000000fee00000 - 00000000fee01000 (reserved)
kernel: BIOS-e820: 00000000fffe0000 - 0000000100000000 (reserved)
kernel: OMB HIGHMEM available.
kernel: 512MB LOWMEM available.
```

This example shows how to use /var/log/messages to see kernel information about /dev/sda.

```
[root@RHEL53 ~]# grep sda /var/log/messages | cut -b24-
kernel: SCSI device sda: 41943040 512-byte hdwr sectors (21475 MB)
kernel: sda: Write Protect is off
kernel: sda: cache data unavailable
kernel: sda: assuming drive cache: write through
kernel: SCSI device sda: 41943040 512-byte hdwr sectors (21475 MB)
kernel: sda: Write Protect is off
kernel: sda: cache data unavailable
kernel: sda: assuming drive cache: write through
kernel: sda: sdal sda2
kernel: sd 0:0:0:0: Attached scsi disk sda
kernel: EXT3 FS on sdal, internal journal
```

## 28.1.7. dmesg

The **dmesg** command prints out all the kernel bootup messages (from the last boot).

Thus to find information about /dev/sda, using **dmesg** will yield only kernel messages from the last boot.

```
[root@RHEL53 ~]# dmesg | grep sda

SCSI device sda: 41943040 512-byte hdwr sectors (21475 MB)

sda: Write Protect is off

sda: Mode Sense: 5d 00 00 00

sda: cache data unavailable

sda: assuming drive cache: write through

SCSI device sda: 41943040 512-byte hdwr sectors (21475 MB)

sda: Write Protect is off

sda: Mode Sense: 5d 00 00 00

sda: cache data unavailable

sda: assuming drive cache: write through

sda: sdal sda2

sd 0:0:0:0: Attached scsi disk sda

EXT3 FS on sdal, internal journal
```

## 28.2. Linux kernel source

## 28.2.1. ftp.kernel.org

The home of the Linux kernel source is **ftp.kernel.org**. It contains all official releases of the Linux kernel source code from 1991. It provides free downloads over http, ftp and rsync of all these releases, as well as changelogs and patches. More information can be otained on the website **www.kernel.org**.

Anyone can anonymously use an ftp client to access ftp.kernel.org

```
paul@laika:~$ ftp ftp.kernel.org
Connected to pub3.kernel.org.

220 Welcome to ftp.kernel.org.

Name (ftp.kernel.org:paul): anonymous

331 Please specify the password.

Password:

230- Welcome to the

230-

230- LINUX KERNEL ARCHIVES

230- ftp.kernel.org
```

All the Linux kernel versions are located in the pub/linux/kernel/directory.

```
ftp> ls pub/linux/kernel/v*
200 PORT command successful. Consider using PASV.
150 Here comes the directory listing.
drwxrwsr-x 2 536 536 4096 Mar 20 2003 v1.0
drwxrwsr-x 2 536 536 20480 Mar 20 2003 v1.1
drwxrwsr-x 2 536 536 8192 Mar 20 2003 v1.2
drwxrwsr-x 2 536 536 40960 Mar 20 2003 v1.3
drwxrwsr-x 3 536 536 16384 Feb 08 2004 v2.0
drwxrwsr-x 2 536 536 536 53248 Mar 20 2003 v2.1
drwxrwsr-x 3 536 536 536 12288 Mar 24 2004 v2.2
drwxrwsr-x 3 536 536 24576 Mar 20 2003 v2.3
drwxrwsr-x 5 536 536 28672 Dec 02 08:14 v2.4
drwxrwsr-x 4 536 536 32768 Jul 14 2003 v2.5
drwxrwsr-x 7 536 536 110592 Dec 05 22:36 v2.6
226 Directory send OK.
ftp>
```

### 28.2.2. /usr/src

On your local computer, the kernel source is located in /usr/src. Note though that the structure inside /usr/src might be different depending on the distribution that you are using.

First let's take a look at /usr/src on Debian. There appear to be two versions of the complete Linux source code there. Looking for a specific file (e1000\_main.c) with find reveals it's exact location.

```
paul@barry:~$ ls -l /usr/src/
drwxr-xr-x 20 root root 4096 2006-04-04 22:12 linux-source-2.6.15
drwxr-xr-x 19 root root 4096 2006-07-15 17:32 linux-source-2.6.16
paul@barry:~$ find /usr/src -name e1000_main.c
/usr/src/linux-source-2.6.15/drivers/net/e1000/e1000_main.c
/usr/src/linux-source-2.6.16/drivers/net/e1000/e1000_main.c
```

This is very similar to /usr/src on Ubuntu, except there is only one kernel here (and it is newer).

```
paul@laika:~$ ls -l /usr/src/
drwxr-xr-x 23 root root 4096 2008-11-24 23:28 linux-source-2.6.24
paul@laika:~$ find /usr/src -name "e1000_main.c"
/usr/src/linux-source-2.6.24/drivers/net/e1000/e1000_main.c
```

Now take a look at /usr/src on Red Hat Enterprise Linux.

```
[paul@RHEL52 ~]$ ls -l /usr/src/
drwxr-xr-x 5 root root 4096 Dec 5 19:23 kernels
drwxr-xr-x 7 root root 4096 Oct 11 13:22 redhat
```

We will have to dig a little deeper to find the kernel source on Red Hat!

```
[paul@RHEL52 ~]$ cd /usr/src/redhat/BUILD/
[paul@RHEL52 BUILD]$ find . -name "e1000_main.c"
./kernel-2.6.18/linux-2.6.18.i686/drivers/net/e1000/e1000_main.c
```

## 28.2.3. downloading the kernel source

#### Debian

Installing the kernel source on Debian is really simple with **aptitude install linux-source**. You can do a search for all linux-source packages first, like in this screenshot.

```
root@barry:~# aptitude search linux-source
v linux-source -
v linux-source-2.6 -
id linux-source-2.6.15 - Linux kernel source for version 2.6.15
i linux-source-2.6.16 - Linux kernel source for version 2.6.16
p linux-source-2.6.18 - Linux kernel source for version 2.6.18
p linux-source-2.6.24 - Linux kernel source for version 2.6.24
```

And then use aptitude install to download and install the Debian Linux kernel source code.

```
root@barry:~# aptitude install linux-source-2.6.24
```

When the aptitude is finished, you will see a new file named /usr/src/linux-source-<version>.tar.bz2

```
root@barry:/usr/src# ls -lh
drwxr-xr-x 20 root root 4.0K 2006-04-04 22:12 linux-source-2.6.15
drwxr-xr-x 19 root root 4.0K 2006-07-15 17:32 linux-source-2.6.16
-rw-r--r- 1 root root 45M 2008-12-02 10:56 linux-source-2.6.24.tar.bz2
```

#### Ubuntu

Ubuntu is based on Debian and also uses **aptitude**, so the task is very similar.

```
root@laika:~# aptitude search linux-source
i linux-source - Linux kernel source with Ubuntu patches
v linux-source-2.6 -
i A linux-source-2.6.24 - Linux kernel source for version 2.6.24
root@laika:~# aptitude install linux-source
```

And when aptitude finishes, we end up with a /usr/src/linux-source-<version>.tar.bz file.

```
oot@laika:~# ll /usr/src
total 45M
-rw-r--r-- 1 root root 45M 2008-11-24 23:30 linux-source-2.6.24.tar.bz2
```

### **Red Hat Enterprise Linux**

The Red Hat kernel source is located on the fourth source cdrom. The file is called **kernel-2.6.9-42.EL.src.rpm** (example for RHELv4u4). It is also available online at ftp://ftp.redhat.com/pub/redhat/linux/enterprise/5Server/en/os/SRPMS/ (example for RHEL5).

To download the kernel source on RHEL, use this long wget command (on one line, without the trailing \).

```
wget ftp://ftp.redhat.com/pub/redhat/linux/enterprise/5Server/en/os/\
SRPMS/kernel-`uname -r`.src.rpm
```

When the wget download is finished, you end up with a 60M .rpm file.

```
[root@RHEL52 src]# 11
total 60M
-rw-r--r- 1 root root 60M Dec 5 20:54 kernel-2.6.18-92.1.17.el5.src.rpm
drwxr-xr-x 5 root root 4.0K Dec 5 19:23 kernels
drwxr-xr-x 7 root root 4.0K Oct 11 13:22 redhat
```

We will need to perform some more steps before this can be used as kernel source code.

First, we issue the **rpm -i kernel-2.6.9-42.EL.src.rpm** command to install this Red Hat package.

```
[root@RHEL52 src]# 11
total 60M
-rw-r--r- 1 root root 60M Dec 5 20:54 kernel-2.6.18-92.1.17.el5.src.rpm
drwxr-xr-x 5 root root 4.0K Dec 5 19:23 kernels
drwxr-xr-x 7 root root 4.0K Oct 11 13:22 redhat
[root@RHEL52 src]# rpm -i kernel-2.6.18-92.1.17.el5.src.rpm
```

Then we move to the SPECS directory and perform an **rpmbuild**.

```
[root@RHEL52 ~]# cd /usr/src/redhat/SPECS
[root@RHEL52 SPECS]# rpmbuild -bp -vv --target=i686 kernel-2.6.spec
```

The rpmbuild command put the RHEL Linux kernel source code in /usr/src/redhat/BUILD/kernel-<version>/.

```
[root@RHEL52 kernel-2.6.18]# pwd
/usr/src/redhat/BUILD/kernel-2.6.18
[root@RHEL52 kernel-2.6.18]# 11
total 20K
drwxr-xr-x 2 root root 4.0K Dec 6 2007 config
-rw-r--r- 1 root root 3.1K Dec 5 20:58 Config.mk
drwxr-xr-x 20 root root 4.0K Dec 5 20:58 linux-2.6.18.i686
drwxr-xr-x 19 root root 4.0K Sep 20 2006 vanilla
drwxr-xr-x 8 root root 4.0K Dec 6 2007 xen
```

## 28.3. kernel boot files

### 28.3.1. vmlinuz

The **vmlinuz** file in /boot is the compressed kernel.

```
paul@barry:~$ ls -lh /boot | grep vmlinuz

-rw-r--r- 1 root root 1.2M 2006-03-06 16:22 vmlinuz-2.6.15-1-486

-rw-r--r- 1 root root 1.1M 2006-03-06 16:30 vmlinuz-2.6.15-1-686

-rw-r--r- 1 root root 1.3M 2008-02-11 00:00 vmlinuz-2.6.18-6-686

paul@barry:~$
```

### 28.3.2. initrd

The kernel uses **initrd** (an initial RAM disk) at boot time. The initrd is mounted before the kernel loads, and can contain additional drivers and modules. It is a **compressed cpio archive**, so you can look at the contents in this way.

```
root@RHELv4u4:/boot# mkdir /mnt/initrd
root@RHELv4u4:/boot# cp initrd-2.6.9-42.0.3.EL.img TMPinitrd.gz
root@RHELv4u4:/boot# gunzip TMPinitrd.gz
root@RHELv4u4:/boot# file TMPinitrd
TMPinitrd: ASCII cpio archive (SVR4 with no CRC)
root@RHELv4u4:/boot# cd /mnt/initrd/
root@RHELv4u4:/mnt/initrd# cpio -i | /boot/TMPinitrd
4985 blocks
root@RHELv4u4:/mnt/initrd# ls -1
total 76
drwxr-xr-x 2 root root 4096 Feb 5 08:36 bin
drwxr-xr-x 2 root root 4096 Feb 5 08:36 dev
drwxr-xr-x 4 root root 4096 Feb 5 08:36 etc
-rwxr-xr-x 1 root root 1607 Feb 5 08:36 init
drwxr-xr-x 2 root root 4096 Feb 5 08:36 lib
drwxr-xr-x 2 root root 4096 Feb 5 08:36 loopfs
drwxr-xr-x 2 root root 4096 Feb 5 08:36 proc
lrwxrwxrwx 1 root root 3 Feb 5 08:36 sbin -> bin
drwxr-xr-x 2 root root 4096 Feb 5 08:36 sys
drwxr-xr-x 2 root root 4096 Feb 5 08:36 sysroot
root@RHELv4u4:/mnt/initrd#
```

## **28.3.3. System.map**

The **System.map** contains the symbol table and changes with every kernel compile. The symbol table is also present in **/proc/kallsyms** (pre 2.6 kernels name this file /proc/ksyms).

```
root@RHELv4u4:/boot# head System.map-`uname -r`
00000400 A __kernel_vsyscall
0000041a A SYSENTER_RETURN_OFFSET
00000420 A __kernel_sigreturn
00000440 A
           __kernel_rt_sigreturn
c0100000 A _text
c0100000 T startup_32
c01000c6 t checkCPUtype
c0100147 t is486
c010014e t is386
c010019f t L6
root@RHELv4u4:/boot# head /proc/kallsyms
c0100228 t _stext
c0100228 t calibrate_delay_direct
c0100228 t stext
c0100337 t calibrate_delay
c01004db t rest_init
c0100580 t do_pre_smp_initcalls
c0100585 t run_init_process
c01005ac t init
c0100789 t early_param_test
c01007ad t early_setup_test
root@RHELv4u4:/boot#
```

## 28.3.4. .config

The last file copied to the /boot directory is the kernel configuration used for compilation. This file is not necessary in the /boot directory, but it is common practice to put a copy there. It allows you to recompile a kernel, starting from the same configuration as an existing working one.

## 28.4. Linux kernel modules

### 28.4.1. about kernel modules

The Linux kernel is a monolithic kernel with loadable modules. These modules contain parts of the kernel used typically for device drivers, file systems and network protocols. Most of the time the necessary kernel modules are loaded automatically and dynamically without administrator interaction.

### 28.4.2. /lib/modules

The modules are stored in the /lib/modules/<kernel-version> directory. There is a separate directory for each kernel that was compiled for your system.

```
paul@laika:~$ 11 /lib/modules/
total 12K
drwxr-xr-x 7 root root 4.0K 2008-11-10 14:32 2.6.24-16-generic
drwxr-xr-x 8 root root 4.0K 2008-12-06 15:39 2.6.24-21-generic
drwxr-xr-x 8 root root 4.0K 2008-12-05 12:58 2.6.24-22-generic
```

#### 28.4.3. <module>.ko

The file containing the modules usually ends in **.ko**. This screenshot shows the location of the isdn module files.

```
paul@laika:~$ find /lib/modules -name isdn.ko
/lib/modules/2.6.24-21-generic/kernel/drivers/isdn/i41/isdn.ko
/lib/modules/2.6.24-22-generic/kernel/drivers/isdn/i41/isdn.ko
/lib/modules/2.6.24-16-generic/kernel/drivers/isdn/i41/isdn.ko
```

### 28.4.4. Ismod

To see a list of currently loaded modules, use **lsmod**. You see the name of each loaded module, the size, the use count, and the names of other modules using this one.

## 28.4.5. /proc/modules

/proc/modules lists all modules loaded by the kernel. The output would be too long to display here, so lets grep for the vm module.

We see that vmmon and vmnet are both loaded. You can display the same information with **lsmod**. Actually **lsmod** only reads and reformats the output of **/proc/modules**.

## 28.4.6. module dependencies

Some modules depend on others. In the following example, you can see that the nfsd module is used by exportfs, lockd and sunrpc.

```
paul@laika:~$ cat /proc/modules | grep nfsd
nfsd 267432 17 - Live 0xffffffff88a40000
exportfs 7808 1 nfsd, Live 0xffffffff88a3d000
lockd 73520 3 nfs,nfsd, Live 0xffffffff88a2a000
sunrpc 185032 12 nfs,nfsd,lockd, Live 0xffffffff889fb000
paul@laika:~$ lsmod | grep nfsd
nfsd 267432 17
exportfs 7808 1 nfsd
lockd 73520 3 nfs,nfsd
sunrpc 185032 12 nfs,nfsd,lockd
paul@laika:~$
```

### 28.4.7. insmod

Kernel modules can be manually loaded with the **insmod** command. This is a very simple (and obsolete) way of loading modules. The screenshot shows **insmod** loading the fat module (for fat file system support).

```
root@barry:/lib/modules/2.6.17-2-686# lsmod | grep fat
root@barry:/lib/modules/2.6.17-2-686# insmod kernel/fs/fat/fat.ko
root@barry:/lib/modules/2.6.17-2-686# lsmod | grep fat
fat 46588 0
```

**insmod** is not detecting dependencies, so it fails to load the isdn module (because the isdn module depends on the slhc module).

```
[root@RHEL52 drivers]# pwd
/lib/modules/2.6.18-92.1.18.el5/kernel/drivers
[root@RHEL52 kernel]# insmod isdn/i4l/isdn.ko
insmod: error inserting 'isdn/i4l/isdn.ko': -1 Unknown symbol in module
```

#### 28.4.8. modinfo

As you can see in the screenshot of **modinfo** below, the isdn module depends in the slhc module.

## 28.4.9. modprobe

The big advantage of **modprobe** over **insmod** is that modprobe will load all necessary modules, whereas insmod requires manual loading of dependencies. Another advantage is that you don't need to point to the filename with full path.

This screenshot shows how modprobe loads the isdn module, automatically loading slhc in background.

## 28.4.10. /lib/modules/<kernel>/modules.dep

Module dependencies are stored in modules.dep.

```
[root@RHEL52 2.6.18-92.1.18.el5]# pwd
/lib/modules/2.6.18-92.1.18.el5
[root@RHEL52 2.6.18-92.1.18.el5]# head -3 modules.dep
/lib/modules/2.6.18-92.1.18.el5/kernel/drivers/net/tokenring/3c359.ko:
/lib/modules/2.6.18-92.1.18.el5/kernel/drivers/net/pcmcia/3c574_cs.ko:
/lib/modules/2.6.18-92.1.18.el5/kernel/drivers/net/pcmcia/3c589_cs.ko:
```

## 28.4.11. depmod

The **modules.dep** file can be updated (recreated) with the **depmod** command. In this screenshot no modules were added, so **depmod** generates the same file.

```
root@barry:/lib/modules/2.6.17-2-686# ls -1 modules.dep
-rw-r--r- 1 root root 310676 2008-03-01 16:32 modules.dep
root@barry:/lib/modules/2.6.17-2-686# depmod
root@barry:/lib/modules/2.6.17-2-686# ls -1 modules.dep
-rw-r--r- 1 root root 310676 2008-12-07 13:54 modules.dep
```

### 28.4.12. rmmod

Similar to insmod, the **rmmod** command is rarely used anymore.

```
[root@RHELv4u3 ~]# modprobe isdn
[root@RHELv4u3 ~]# rmmod slhc
ERROR: Module slhc is in use by isdn
[root@RHELv4u3 ~]# rmmod isdn
[root@RHELv4u3 ~]# rmmod slhc
[root@RHELv4u3 ~]# lsmod | grep isdn
[root@RHELv4u3 ~]#
```

## 28.4.13. modprobe -r

Contrary to rmmod, **modprobe** will automatically remove unneeded modules.

## 28.4.14. /etc/modprobe.conf

The /etc/modprobe.conf file and the /etc/modprobe.d directory can contain aliases (used by humans) and options (for dependent modules) for modprobe.

```
[root@RHEL52 ~]# cat /etc/modprobe.conf
alias scsi_hostadapter mptbase
alias scsi_hostadapter1 mptspi
alias scsi_hostadapter2 ata_piix
alias eth0 pcnet32
alias eth2 pcnet32
```

alias eth1 pcnet32

## 28.5. compiling a kernel

### 28.5.1. extraversion

Enter into /usr/src/redhat/BUILD/kernel-2.6.9/linux-2.6.9/ and change the extraversion in the Makefile.

```
[root@RHEL52 linux-2.6.18.i686]# pwd
/usr/src/redhat/BUILD/kernel-2.6.18/linux-2.6.18.i686
[root@RHEL52 linux-2.6.18.i686]# vi Makefile
[root@RHEL52 linux-2.6.18.i686]# head -4 Makefile
VERSION = 2
PATCHLEVEL = 6
SUBLEVEL = 18
EXTRAVERSION = -paul2008
```

## 28.5.2. make mrproper

Now clean up the source from any previous installs with **make mrproper**. If this is your first after downloading the source code, then this is not needed.

```
[root@RHEL52 linux-2.6.18.i686]# make mrproper
CLEAN scripts/basic
CLEAN scripts/kconfig
CLEAN include/config
CLEAN .config .config.old
```

## 28.5.3. .config

Now copy a working **.config** from /boot to our kernel directory. This file contains the configuration that was used for your current working kernel. It determines whether modules are included in compilation or not.

```
[root@RHEL52 linux-2.6.18.i686]# cp /boot/config-2.6.18-92.1.18.el5 .config
```

## 28.5.4. make menuconfig

Now run **make menuconfig** (or the graphical **make xconfig**). This tool allows you to select whether to compile stuff as a module (m), as part of the kernel (\*), or not at all (smaller kernel size). If you remove too much, your kernel will not work. The configuration will be stored in the hidden **.config** file.

```
[root@RHEL52 linux-2.6.18.i686]# make menuconfig
```

### 28.5.5. make clean

Issue a **make clean** to prepare the kernel for compile. **make clean** will remove most generated files, but keeps your kernel configuration. Running a **make mrproper** at this point would destroy the .config file that you built with **make menuconfig**.

```
[root@RHEL52 linux-2.6.18.i686]# make clean
```

### 28.5.6. make bzlmage

And then run **make bzImage**, sit back and relax while the kernel compiles. You can use **time make bzImage** to know how long it takes to compile, so next time you can go for a short walk.

```
[root@RHEL52 linux-2.6.18.i686]# time make bzImage
HOSTCC scripts/basic/fixdep
HOSTCC scripts/basic/docproc
HOSTCC scripts/kconfig/conf.o
HOSTCC scripts/kconfig/kxgettext.o
...
```

This command will end with telling you the location of the **bzImage** file (and with time info if you also specified the time command.

```
Kernel: arch/i386/boot/bzImage is ready (#1)

real 13m59.573s
user 1m22.631s
sys 11m51.034s
[root@RHEL52 linux-2.6.18.i686]#
```

You can already copy this image to /boot with **cp arch/i386/boot/bzImage /boot/vmlinuz-**<kernel-version>.

#### 28.5.7. make modules

Now run **make modules**. It can take 20 to 50 minutes to compile all the modules.

```
[root@RHEL52 linux-2.6.18.i686]# time make modules
  CHK    include/linux/version.h
  CHK    include/linux/utsrelease.h
  CC [M]    arch/i386/kernel/msr.o
  CC [M]    arch/i386/kernel/cpuid.o
  CC [M]    arch/i386/kernel/microcode.o
```

### 28.5.8. make modules\_install

To copy all the compiled modules to /lib/modules just run make modules\_install (takes about 20 seconds). Here's a screenshot from before the command.

```
[root@RHEL52 linux-2.6.18.i686]# ls -l /lib/modules/
total 20
drwxr-xr-x 6 root root 4096 Oct 15 13:09 2.6.18-92.1.13.el5
drwxr-xr-x 6 root root 4096 Nov 11 08:51 2.6.18-92.1.17.el5
drwxr-xr-x 6 root root 4096 Dec 6 07:11 2.6.18-92.1.18.el5
[root@RHEL52 linux-2.6.18.i686]# make modules_install
```

And here is the same directory after. Notice that **make modules\_install** created a new directory for the new kernel.

```
[root@RHEL52 linux-2.6.18.i686]# ls -l /lib/modules/
total 24
drwxr-xr-x 6 root root 4096 Oct 15 13:09 2.6.18-92.1.13.el5
drwxr-xr-x 6 root root 4096 Nov 11 08:51 2.6.18-92.1.17.el5
drwxr-xr-x 6 root root 4096 Dec 6 07:11 2.6.18-92.1.18.el5
drwxr-xr-x 3 root root 4096 Dec 6 08:50 2.6.18-paul2008
```

### 28.5.9. /boot

We still need to copy the kernel, the System.map and our configuration file to /boot. Strictly speaking the .config file is not obligatory, but it might help you in future compilations of the kernel.

```
[root@RHEL52 ]# pwd
/usr/src/redhat/BUILD/kernel-2.6.18/linux-2.6.18.i686
[root@RHEL52 ]# cp System.map /boot/System.map-2.6.18-paul2008
[root@RHEL52 ]# cp .config /boot/config-2.6.18-paul2008
[root@RHEL52 ]# cp arch/i386/boot/bzImage /boot/vmlinuz-2.6.18-paul2008
```

#### 28.5.10. mkinitrd

The kernel often uses an initrd file at bootup. We can use **mkinitrd** to generate this file. Make sure you use the correct kernel name!

```
[root@RHEL52 ]# pwd
/usr/src/redhat/BUILD/kernel-2.6.18/linux-2.6.18.i686
[root@RHEL52 ]# mkinitrd /boot/initrd-2.6.18-paul2008 2.6.18-paul2008
```

### 28.5.11. bootloader

Compilation is now finished, don't forget to create an additional stanza in grub or lilo.

## 28.6. compiling one module

### 28.6.1. hello.c

A little C program that will be our module.

```
[root@rhel4a kernel_module]# cat hello.c
#include <linux/module.h>
#include <section>
int init_module(void)
{
   printk(KERN_INFO "Start Hello World...\n");
   return 0;
}

void cleanup_module(void)
{
   printk(KERN_INFO "End Hello World...\n");
}
```

#### 28.6.2. Makefile

The make file for this module.

```
[root@rhel4a kernel_module]# cat Makefile
obj-m += hello.o
all:
make -C /lib/modules/$(shell uname -r)/build M=$(PWD) modules
clean:
make -C /lib/modules/$(shell uname -r)/build M=$(PWD) clean
```

These are the only two files needed.

```
[root@rhel4a kernel_module]# 11
total 16
-rw-rw-r-- 1 paul paul 250 Feb 15 19:14 hello.c
-rw-rw-r-- 1 paul paul 153 Feb 15 19:15 Makefile
```

### 28.6.3. make

The running of the **make** command.

```
[root@rhel4a kernel_module]# make
make -C /lib/modules/2.6.9-paul-2/build M=~/kernel_module modules
make[1]: Entering dir... `/usr/src/redhat/BUILD/kernel-2.6.9/linux-2.6.9'
CC [M] /home/paul/kernel_module/hello.o
Building modules, stage 2.
MODPOST
CC /home/paul/kernel_module/hello.mod.o
LD [M] /home/paul/kernel_module/hello.ko
make[1]: Leaving dir... `/usr/src/redhat/BUILD/kernel-2.6.9/linux-2.6.9'
[root@rhel4a kernel_module]#
```

Now we have more files.

### 28.6.4. hello.ko

Use **modinfo** to verify that it is really a module.

```
[root@rhel4a kernel_module]# modinfo hello.ko
filename: hello.ko
vermagic: 2.6.9-paul-2 SMP 686 REGPARM 4KSTACKS gcc-3.4
depends:
[root@rhel4a kernel_module]#
```

Good, so now we can load our hello module.

Finally /var/log/messages has a little surprise.

```
[root@rhel4a kernel_module]# tail -2 /var/log/messages
Feb 15 19:16:07 rhel4a kernel: Start Hello World...
Feb 15 19:16:35 rhel4a kernel: End Hello World...
[root@rhel4a kernel_module]#
```

| Chapter 29. library management |  |  |  |  |  |
|--------------------------------|--|--|--|--|--|
|                                |  |  |  |  |  |
|                                |  |  |  |  |  |
|                                |  |  |  |  |  |
|                                |  |  |  |  |  |
|                                |  |  |  |  |  |
|                                |  |  |  |  |  |
|                                |  |  |  |  |  |
|                                |  |  |  |  |  |

## 29.1. introduction

With **libraries** we are talking about dynamically linked libraries (aka shared objects). These are binaries that contain functions and are not started themselves as programs, but are called by other binaries.

Several programs can use the same library. The name of the library file usually starts with **lib**, followed by the actual name of the library, then the chracters **.so** and finally a version number.

## 29.2. /lib and /usr/lib

When you look at the /lib or the /usr/lib directory, you will see a lot of symbolic links. Most libraries have a detailed version number in their name, but receive a symbolic link from a filename which only contains the major version number.

```
root@rhel53 ~# ls -l /lib/libext*
lrwxrwxrwx 1 root root    16 Feb 18 16:36 /lib/libext2fs.so.2 -> libext2fs.so.2.4
-rwxr-xr-x 1 root root 113K Jun 30    2009 /lib/libext2fs.so.2.4
```

### 29.3. Idd

Many programs have dependencies on the installation of certain libraries. You can display these dependencies with **ldd**.

This example shows the dependencies of the **su** command.

```
paul@RHEL5 ~$ ldd /bin/su
  linux-gate.so.1 => (0x003f7000)
  libpam.so.0 => /lib/libpam.so.0 (0x00d5c000)
  libpam_misc.so.0 => /lib/libpam_misc.so.0 (0x0073c000)
  libcrypt.so.1 => /lib/libcrypt.so.1 (0x00aa4000)
  libdl.so.2 => /lib/libdl.so.2 (0x00800000)
  libc.so.6 => /lib/libc.so.6 (0x00ec1000)
  libaudit.so.0 => /lib/libaudit.so.0 (0x0049f000)
  /lib/ld-linux.so.2 (0x4769c000)
```

## 29.4. Itrace

The **ltrace** program allows to see all the calls made to library functions by a program. The example below uses the -c option to get only a summary count (there can be many calls), and the -l option to only show calls in one library file. All this to see what calls are made when executing **su - serena** as root.

```
root@deb503:~# ltrace -c -l /lib/libpam.so.0 su - serena
serena@deb503:~$ exit
        seconds usecs/call calls
% time
_____ _____
70.31 0.014117 14117
12.36 0.002482 2482
                               1 pam_start
                             1 pam_open_session
                   2482
 5.17 0.001039
                    1039
                               1 pam_acct_mgmt
 4.36 0.000876
                     876
                               1 pam_end
 3.36 0.000675
3.22 0.000646
                     675
                               1 pam_close_session
                    646
                               1 pam_authenticate
 0.48 0.000096
                     48
                               2 pam_set_item
                      54
 0.27 0.000054
                               1 pam_setcred
                      50
 0.25 0.000050
0.22 0.000044
                               1 pam_getenvlist
                      44
                                1 pam_get_item
100.00 0.020079
```

## 29.5. dpkg -S and debsums

Find out on Debian/Ubuntu to which package a library belongs.

```
paul@deb503:/lib$ dpkg -S libext2fs.so.2.4
e2fslibs: /lib/libext2fs.so.2.4
```

You can then verify the integrity of all files in this package using **debsums**.

Should a library be broken, then reinstall it with aptitude reinstall \$package.

```
root@deb503:~# aptitude reinstall e2fslibs
Reading package lists... Done
Building dependency tree
Reading state information... Done
Reading extended state information
Initializing package states... Done
Reading task descriptions... Done
The following packages will be REINSTALLED:
    e2fslibs
...
```

# 29.6. rpm -qf and rpm -V

Find out on Red Hat/Fedora to which package a library belongs.

```
paul@RHEL5 ~$ rpm -qf /lib/libext2fs.so.2.4
e2fsprogs-libs-1.39-8.el5
```

You can then use **rpm** -V to verify all files in this package. In the example below the output shows that the Size and the Time stamp of the file have changed since installation.

```
root@rhel53 ~# rpm -V e2fsprogs-libs
prelink: /lib/libext2fs.so.2.4: prelinked file size differs
S.?....T /lib/libext2fs.so.2.4
```

You can then use **yum reinstall \$package** to overwrite the existing library with an original version.

```
root@rhel53 lib# yum reinstall e2fsprogs-libs
Loaded plugins: rhnplugin, security
Setting up Reinstall Process
Resolving Dependencies
--> Running transaction check
---> Package e2fsprogs-libs.i386 0:1.39-23.el5 set to be erased
---> Package e2fsprogs-libs.i386 0:1.39-23.el5 set to be updated
---> Finished Dependency Resolution
...
```

The package verification now reports no problems with the library.

```
root@rhel53 lib# rpm -V e2fsprogs-libs
root@rhel53 lib#
```

## 29.7. tracing with strace

More detailed tracing of all function calls can be done with **strace**. We start by creating a read only file.

```
root@deb503:~# echo hello > 42.txt

root@deb503:~# chmod 400 42.txt

root@deb503:~# ls -1 42.txt

-r----- 1 root root 6 2011-09-26 12:03 42.txt
```

We open the file with **vi**, but include the **strace** command with an output file for the trace before **vi**. This will create a file with all the function calls done by **vi**.

```
root@deb503:~# strace -o strace.txt vi 42.txt
```

The file is read only, but we still change the contents, and use the :w! directive to write to this file. Then we close vi and take a look at the trace log.

```
root@deb503:~# grep chmod strace.txt
chmod("42.txt", 0100600) = -1 ENOENT (No such file or directory)
chmod("42.txt", 0100400) = 0
root@deb503:~# ls -1 42.txt
-r------ 1 root root 12 2011-09-26 12:04 42.txt
```

Notice that **vi** changed the permissions on the file twice. The trace log is too long to show a complete screenshot in this book.

```
root@deb503:~# wc -l strace.txt
941 strace.txt
```



## **Table of Contents**

| 30. backup               |  |
|--------------------------|--|
| 30.1. About tape devices |  |
| 30.2. Compression        |  |
| 30.3. tar                |  |
| 30.4. Backup Types       |  |
| 30.5. dump and restore   |  |
| 30.6. cpio               |  |
| 30.7. dd                 |  |
| 30.8. split              |  |
| 30.9. practice: backup   |  |

# Chapter 30. backup

## 30.1. About tape devices

Don't forget that the name of a device strictly speaking has no meaning since the kernel will use the major and minor number to find the hardware! See the man page of **mknod** and the devices.txt file in the Linux kernel source for more info.

## **30.1.1. SCSI tapes**

On the official Linux device list (http://www.lanana.org/docs/device-list/) we find the names for SCSI tapes (major 9 char). SCSI tape devices are located underneath /dev/st and are numbered starting with 0 for the first tape device.

```
/dev/st0 First tape device
/dev/st1 Second tape device
/dev/st2 Third tape device
```

To prevent **automatic rewinding of tapes**, prefix them with the letter n.

```
/dev/nst0 First no rewind tape device
/dev/nst1 Second no rewind tape device
/dev/nst2 Third no rewind tape device
```

By default, SCSI tapes on Linux will use the highest hardware compression that is supported by the tape device. To lower the compression level, append one of the letters l (low), m (medium) or a (auto) to the tape name.

```
/dev/st0l First low compression tape device
/dev/st0m First medium compression tape device
/dev/nst2m Third no rewind medium compression tape device
```

### 30.1.2. IDE tapes

On the official Linux device list (http://www.lanana.org/docs/device-list/) we find the names for IDE tapes (major 37 char). IDE tape devices are located underneath /dev/ht and are numbered starting with 0 for the first tape device. No rewind and compression is similar to SCSI tapes.

```
/dev/ht0 First IDE tape device
/dev/nht0 Second no rewind IDE tape device
/dev/ht0m First medium compression IDE tape device
```

### 30.1.3. mt

To manage your tapes, use **mt** (Magnetic Tape). Some examples.

To receive information about the status of the tape.

```
mt -f /dev/st0 status

To rewind a tape...

mt -f /dev/st0 rewind

To rewind and single tage...
```

To rewind and eject a tape...

```
mt -f /dev/st0 eject
```

To erase a tape...

```
mt -f /dev/st0 erase
```

# 30.2. Compression

It can be beneficial to compress files before backup. The two most popular tools for compression of regular files on Linux are **gzip/gunzip** and **bzip2/bunzip2**. Below you can see gzip in action, notice that it adds the .gz extension to the file.

```
paul@RHELv4u4:~/test$ ls -l allfiles.tx*
-rw-rw-r-- 1 paul paul 8813553 Feb 27 05:38 allfiles.txt
paul@RHELv4u4:~/test$ gzip allfiles.txt
paul@RHELv4u4:~/test$ ls -l allfiles.tx*
-rw-rw-r-- 1 paul paul 931863 Feb 27 05:38 allfiles.txt.gz
paul@RHELv4u4:~/test$ gunzip allfiles.txt.gz
paul@RHELv4u4:~/test$ ls -l allfiles.txt*
-rw-rw-r-- 1 paul paul 8813553 Feb 27 05:38 allfiles.txt
paul@RHELv4u4:~/test$
```

In general, gzip is much faster than bzip2, but the latter one compresses a lot better. Let us compare the two.

```
paul@RHELv4u4:~/test$ cp allfiles.txt bllfiles.txt
paul@RHELv4u4:~/test$ time gzip allfiles.txt
       0m0.050s
real
      0m0.041s
user
       0m0.009s
paul@RHELv4u4:~/test$ time bzip2 bllfiles.txt
       0m5.968s
real
       0m5.794s
user
       0m0.076s
paul@RHELv4u4:~/test$ ls -l ?llfiles.tx*
-rw-rw-r-- 1 paul paul 931863 Feb 27 05:38 allfiles.txt.gz
-rw-rw-r-- 1 paul paul 708871 May 12 10:52 bllfiles.txt.bz2
paul@RHELv4u4:~/test$
```

# 30.3. tar

The **tar** utility gets its name from **Tape ARchive**. This tool will receive and send files to a destination (typically a tape or a regular file). The c option is used to create a tar archive

(or tarfile), the f option to name/create the **tarfile**. The example below takes a backup of / etc into the file /backup/etc.tar .

Compression can be achieved without pipes since tar uses the z flag to compress with gzip, and the j flag to compress with bzip2.

```
root@RHELv4u4:~# tar czf /backup/etc.tar.gz /etc
root@RHELv4u4:~# tar cjf /backup/etc.tar.bz2 /etc
root@RHELv4u4:~# ls -l /backup/etc.ta*
-rw-r--r- 1 root root 47800320 May 12 11:47 /backup/etc.tar
-rw-r--r- 1 root root 6077340 May 12 11:48 /backup/etc.tar.bz2
-rw-r--r- 1 root root 8496607 May 12 11:47 /backup/etc.tar.gz
root@RHELv4u4:~#
```

The t option is used to **list the contents of a tar file**. Verbose mode is enabled with v (also useful when you want to see the files being archived during archiving).

To **list a specific file in a tar archive**, use the t option, added with the filename (without leading /).

```
root@RHELv4u4:~# tar tvf /backup/etc.tar etc/resolv.conf
-rw-r--r- root/root 77 2007-05-12 08:31:32 etc/resolv.conf
root@RHELv4u4:~#
```

Use the x flag to **restore a tar archive**, or a single file from the archive. Remember that by default tar will restore the file in the current directory.

```
root@RHELv4u4:~# tar xvf /backup/etc.tar etc/resolv.conf
etc/resolv.conf
root@RHELv4u4:~# ls -l /etc/resolv.conf
-rw-r--r- 2 root root 40 May 12 12:05 /etc/resolv.conf
root@RHELv4u4:~# ls -l etc/resolv.conf
-rw-r--r- 1 root root 77 May 12 08:31 etc/resolv.conf
root@RHELv4u4:~#
```

You can **preserve file permissions** with the p flag. And you can exclude directories or file with **--exclude**.

```
root ~# tar cpzf /backup/etc_with_perms.tgz /etc
```

```
root ~# tar cpzf /backup/etc_no_sysconf.tgz /etc --exclude /etc/sysconfig
root ~# ls -l /backup/etc_*
-rw-r--r-- 1 root root 8434293 May 12 12:48 /backup/etc_no_sysconf.tgz
-rw-r--r-- 1 root root 8496591 May 12 12:48 /backup/etc_with_perms.tgz
root ~#
```

You can also create a text file with names of files and directories to archive, and then supply this file to tar with the -T flag.

```
root@RHELv4u4:~# find /etc -name *.conf > files_to_archive.txt
root@RHELv4u4:~# find /home -name *.pdf >> files_to_archive.txt
root@RHELv4u4:~# tar cpzf /backup/backup.tgz -T files_to_archive.txt
```

The tar utility can receive filenames from the find command, with the help of xargs.

```
find /etc -type f -name "*.conf" | xargs tar czf /backup/confs.tar.gz
```

You can also use tar to copy a directory, this is more efficient than using cp -r.

```
(cd /etc; tar -cf - . ) | (cd /backup/copy_of_etc/; tar -xpf - )
```

Another example of tar, this copies a directory securely over the network.

```
(cd /etc;tar -cf - .) | (ssh user@srv 'cd /backup/cp_of_etc/; tar -xf - ')
```

tar can be used together with gzip and copy a file to a remote server through ssh

```
cat backup.tar | gzip | ssh bashuser@192.168.1.105 "cat - > backup.tgz"
```

Compress the tar backup when it is on the network, but leave it uncompressed at the destination.

```
cat backup.tar | gzip | ssh user@192.168.1.105 "gunzip|cat - > backup.tar"
```

Same as the previous, but let ssh handle the compression

```
cat backup.tar | ssh -C bashuser@192.168.1.105 "cat - > backup.tar"
```

# 30.4. Backup Types

Linux uses **multilevel incremental** backups using distinct levels. A full backup is a backup at level 0. A higher level x backup will include all changes since the last level x-1 backup.

Suppose you take a full backup on Monday (level 0) and a level 1 backup on Tuesday, then the Tuesday backup will contain all changes since Monday. Taking a level 2 on Wednesday

will contain all changes since Tuesday (the last level 2-1). A level 3 backup on Thursday will contain all changes since Wednesday (the last level 3-1). Another level 3 on Friday will also contain all changes since Wednesday. A level 2 backup on Saturday would take all changes since the last level 1 from Tuesday.

# 30.5. dump and restore

While **dump** is similar to tar, it is also very different because it looks at the file system. Where tar receives a lists of files to backup, dump will find files to backup by itself by examining ext2. Files found by dump will be copied to a tape or regular file. In case the target is not big enough to hold the dump (end-of-media), it is broken into multiple volumes.

Restoring files that were backed up with dump is done with the **restore** command. In the example below we take a full level 0 backup of two partitions to a SCSI tape. The no rewind is mandatory to put the volumes behind each other on the tape.

```
dump 0f /dev/nst0 /boot
dump 0f /dev/nst0 /
```

Listing files in a dump archive is done with **dump -t**, and you can compare files with **dump -C**.

You can omit files from a dump by changing the dump attribute with the **chattr** command. The d attribute on ext will tell dump to skip the file, even during a full backup. In the following example, /etc/hosts is excluded from dump archives.

```
chattr +d /etc/hosts
```

To restore the complete file system with **restore**, use the -r option. This can be useful to change the size or block size of a file system. You should have a clean file system mounted and cd'd into it. Like this example shows.

```
mke2fs /dev/hda3
mount /dev/hda3 /mnt/data
cd /mnt/data
restore rf /dev/nst0
```

To extract only one file or directory from a dump, use the -x option.

```
restore -xf /dev/st0 /etc
```

# 30.6. cpio

Different from tar and dump is **cpio** (Copy Input and Output). It can be used to receive filenames, but copies the actual files. This makes it an easy companion with find! Some examples below.

find sends filenames to cpio, which puts the files in an archive.

```
find /etc -depth -print | cpio -oaV -O archive.cpio
```

The same, but compressed with gzip

```
find /etc -depth -print | cpio -oaV | gzip -c > archive.cpio.gz
```

Now pipe it through ssh (backup files to a compressed file on another machine)

```
find /etc -depth -print|cpio -oaV|gzip -c|ssh server "cat - > etc.cpio.gz"
```

find sends filenames to cpio | cpio sends files to ssh | ssh sends files to cpio 'cpio extracts files'

```
find /etc -depth -print | cpio -oaV | ssh user@host 'cpio -imVd'
```

the same but reversed: copy a dir from the remote host to the local machine

```
ssh user@host "find path -depth -print | cpio -oaV" | cpio -imVd
```

## 30.7. dd

#### 30.7.1. About dd

Some people use **dd** to create backups. This can be very powerful, but dd backups can only be restored to very similar partitions or devices. There are however a lot of useful things possible with dd. Some examples.

## 30.7.2. Create a CDROM image

The easiest way to create a **.ISO file** from any CD. The if switch means Input File, of is the Output File. Any good tool can burn a copy of the CD with this .ISO file.

```
dd if=/dev/cdrom of=/path/to/cdrom.ISO
```

## 30.7.3. Create a floppy image

A little outdated maybe, but just in case: make an image file from a 1.44MB floppy. Blocksize is defined by bs, and count contains the number of blocks to copy.

```
dd if=/dev/floppy of=/path/to/floppy.img bs=1024 count=1440
```

## 30.7.4. Copy the master boot record

Use dd to copy the **MBR** (Master Boot Record) of hard disk /dev/hda to a file.

```
dd if=/dev/hda of=/MBR.img bs=512 count=1
```

## 30.7.5. Copy files

This example shows how dd can copy files. Copy the file summer.txt to copy\_of\_summer.txt.

```
dd if=~/summer.txt of=~/copy_of_summer.txt
```

## 30.7.6. Image disks or partitions

And who needs ghost when dd can create a (compressed) image of a partition.

```
dd if=/dev/hdb2 of=/image_of_hdb2.IMG
dd if=/dev/hdb2 | gzip > /image_of_hdb2.IMG.gz
```

## 30.7.7. Create files of a certain size

dd can be used to create a file of any size. The first example creates a one MEBIbyte file, the second a one MEGAbyte file.

```
dd if=/dev/zero of=file1MB count=1024 bs=1024
dd if=/dev/zero of=file1MB count=1000 bs=1024
```

## 30.7.8. CDROM server example

And there are of course endless combinations with ssh and bzip2. This example puts a bzip2 backup of a cdrom on a remote server.

```
dd if=/dev/cdrom |bzip2|ssh user@host "cat - > /backups/cd/cdrom.iso.bz2"
```

# 30.8. split

The **split** command is useful to split files into smaller files. This can be useful to fit the file onto multiple instances of a medium too small to contain the complete file. In the example below, a file of size 5000 bytes is split into three smaller files, with maximum 2000 bytes each.

```
paul@laika:~/test$ ls -1
total 8
-rw-r--r-- 1 paul paul 5000 2007-09-09 20:46 bigfile1
paul@laika:~/test$ split -b 2000 bigfile1 splitfile.
paul@laika:~/test$ ls -1
total 20
-rw-r--r-- 1 paul paul 5000 2007-09-09 20:46 bigfile1
-rw-r--r-- 1 paul paul 2000 2007-09-09 20:47 splitfile.aa
-rw-r--r-- 1 paul paul 2000 2007-09-09 20:47 splitfile.ab
-rw-r--r-- 1 paul paul 1000 2007-09-09 20:47 splitfile.ac
```

## 30.9. practice: backup

- !! Careful with tar options and the position of the backup file, mistakes can destroy your system!!
- 1. Create a directory (or partition if you like) for backups. Link (or mount) it under /mnt/backup.

- 2a. Use tar to backup /etc in /mnt/backup/etc\_date.tgz, the backup must be gzipped. (Replace date with the current date)
- 2b. Use tar to backup /bin to /mnt/backup/bin\_date.tar.bz2, the backup must be bzip2'd.
- 2c. Choose a file in /etc and /bin and verify with tar that the file is indeed backed up.
- 2d. Extract those two files to your home directory.
- 3a. Create a backup directory for your neighbour, make it accessible under /mnt/neighbourName
- 3b. Combine ssh and tar to put a backup of your /boot on your neighbours computer in / mnt/YourName
- 4a. Combine find and cpio to create a cpio archive of /etc.
- 4b. Choose a file in /etc and restore it from the cpio archive into your home directory.
- 5. Use dd and ssh to put a backup of the master boot record on your neighbours computer.
- 6. (On the real computer) Create and mount an ISO image of the ubuntu cdrom.
- 7. Combine dd and gzip to create a 'ghost' image of one of your partitions on another partition.
- 8. Use dd to create a five megabyte file in ~/testsplit and name it biggest. Then split this file in smaller two megabyte parts.

```
mkdir testsplit

dd if=/dev/zero of=~/testsplit/biggest count=5000 bs=1024

split -b 2000000 biggest parts
```

# Part VIII. Appendices

# **Table of Contents**

| A. disk quotas            | 362 |
|---------------------------|-----|
| A.1. About Disk Quotas    | 362 |
| A.2. Practice Disk quotas |     |
| B. introduction to vnc    |     |
| B.1. About VNC            |     |
| B.2. VNC Server           | 363 |
| B.3. VNC Client           |     |
| B.4. Practice VNC         |     |
| C. License                |     |

# Appendix A. disk quotas

## A.1. About Disk Quotas

To limit the disk space used by user, you can set up **disk quotas**. This requires adding **usrquota** and/or **grpquota** to one or more of the file systems in /etc/fstab.

```
root@RHELv4u4:~# cat /etc/fstab | grep usrquota
/dev/VolGroup00/LogVol02 /home ext3 usrquota,grpquota 0 0
```

Next you need to remount the file system.

```
root@RHELv4u4:~# mount -o remount /home
```

The next step is to build the **quota.user** and/or **quota.group** files. These files (called the **quota files**) contain the table of the disk usage on that file system. Use the **quotacheck** command to accomplish this.

```
root@RHELv4u4:~# quotacheck -cug /home
root@RHELv4u4:~# quotacheck -avug
```

The -c is for create, u for user quota, g for group, a for checking all quota enabled file systems in /etc/fstab and v for verbose information. The next step is to edit individual user quotas with edquota or set a general quota on the file system with edquota -t. The tool will enable you to put hard (this is the real limit) and soft (allows a grace period) limits on blocks and inodes. The quota command will verify that quota for a user is set. You can have a nice overview with repquota.

The final step (before your users start complaining about lack of disk space) is to enable quotas with **quotaon(1)**.

```
root@RHELv4u4:~# quotaon -vaug
```

Issue the **quotaoff** command to stop all complaints.

```
root@RHELv4u4:~# quotaoff -vaug
```

# A.2. Practice Disk quotas

- 1. Implement disk quotas on one of your new partitions. Limit one of your users to 10 megabyte.
- 2. Test that they work by copying many files to the quota'd partition.

# Appendix B. introduction to vnc

## **B.1. About VNC**

VNC can be configured in gnome or KDE using the **Remote Desktop Preferences**. **VNC** can be used to run your desktop on another computer, and you can also use it to see and take over the Desktop of another user. The last part can be useful for help desks to show users how to do things. VNC has the added advantage of being operating system independent, a lot of products (realvnc, tightvnc, xvnc, ...) use the same protocol on Solaris, Linux, BSD and more.

## **B.2. VNC Server**

Starting the vnc server for the first time.

```
[root@RHELv4u3 conf]# rpm -qa | grep -i vnc
vnc-server-4.0-8.1
vnc-4.0-8.1
[root@RHELv4u3 conf]# vncserver :2

You will require a password to access your desktops.

Password:
Verify:
xauth: creating new authority file /root/.Xauthority

New 'RHELv4u3.localdomain:2 (root)' desktop is RHELv4u3.localdomain:2

Creating default startup script /root/.vnc/xstartup
Starting applications specified in /root/.vnc/xstartup
Log file is /root/.vnc/RHELv4u3.localdomain:2.log

[root@RHELv4u3 conf]#
```

## **B.3. VNC Client**

You can now use the **vncviewer** from another machine to connect to your vnc server. It will default to a very simple graphical interface...

```
paul@laika:~$ vncviewer 192.168.1.49:2

VNC viewer version 3.3.7 - built Nov 20 2006 13:05:04

Copyright (C) 2002-2003 RealVNC Ltd.

Copyright (C) 1994-2000 AT&T Laboratories Cambridge.

See http://www.realvnc.com for information on VNC.

VNC server supports protocol version 3.8 (viewer 3.3)

Password:

VNC authentication succeeded

Desktop name "RHELv4u3.localdomain:2 (root)"

Connected to VNC server, using protocol version 3.3

...
```

If you don't like the simple twm window manager, you can comment out the last two lines of **~/.vnc/xstartup** and add a **gnome-session &** line to have vnc default to gnome instead.

```
[root@RHELv4u3 ~]# cat .vnc/xstartup
#!/bin/sh

# Uncomment the following two lines for normal desktop:
# unset SESSION_MANAGER
# exec /etc/X11/xinit/xinitrc

[ -x /etc/vnc/xstartup ] && exec /etc/vnc/xstartup
[ -r $HOME/.Xresources ] && xrdb $HOME/.Xresources
xsetroot -solid grey
vncconfig -iconic &
# xterm -geometry 80x24+10+10 -ls -title "$VNCDESKTOP Desktop" &
# twm &
gnome-session &
[root@RHELv4u3 ~]#
```

Don't forget to restart your vnc server after changing this file.

```
[root@RHELv4u3 ~]# vncserver -kill :2
Killing Xvnc process ID 5785
[root@RHELv4u3 ~]# vncserver :2
New 'RHELv4u3.localdomain:2 (root)' desktop is RHELv4u3.localdomain:2
Starting applications specified in /root/.vnc/xstartup
Log file is /root/.vnc/RHELv4u3.localdomain:2.log
```

## **B.4. Practice VNC**

1. Use VNC to connect from one machine to another.

# Appendix C. License

GNU Free Documentation License

Version 1.3, 3 November 2008

Copyright © 2000, 2001, 2002, 2007, 2008 Free Software Foundation, Inc.

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

#### 0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

#### 1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles

are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

The "publisher" means any person or entity that distributes copies of the Document to the public.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

#### 2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either

commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

#### 3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

#### 4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

\* A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.

- \* B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- \* C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
  - \* D. Preserve all the copyright notices of the Document.
- \* E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- \* F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- \* G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
  - \* H. Include an unaltered copy of this License.
- \* I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- \* J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- \* K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- \* L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- $\ ^{*}$  M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- \* N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
  - \* O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of,

you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

#### 5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

#### 6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

#### 7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

#### 8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

#### 9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, or distribute it is void, and will automatically terminate your rights under this License.

However, if you cease all violation of this License, then your license from a particular copyright holder is reinstated (a) provisionally, unless and until the copyright holder explicitly and finally terminates your license, and (b) permanently, if the copyright holder fails to notify you of the violation by some reasonable means prior to 60 days after the cessation.

Moreover, your license from a particular copyright holder is reinstated permanently if the copyright holder notifies you of the violation by some reasonable means, this is the first time you have received notice of violation of this License (for any work) from that copyright holder, and you cure the violation prior to 30 days after your receipt of the notice.

Termination of your rights under this section does not terminate the licenses of parties who have received copies or rights from you under this License. If your rights have been terminated and not permanently reinstated, receipt of a copy of some or all of the same material does not give you any rights to use it.

#### 10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See http://www.gnu.org/copyleft/.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation. If the Document specifies

that a proxy can decide which future versions of this License can be used, that proxy's public statement of acceptance of a version permanently authorizes you to choose that version for the Document.

#### 11. RELICENSING

"Massive Multiauthor Collaboration Site" (or "MMC Site") means any World Wide Web server that publishes copyrightable works and also provides prominent facilities for anybody to edit those works. A public wiki that anybody can edit is an example of such a server. A "Massive Multiauthor Collaboration" (or "MMC") contained in the site means any set of copyrightable works thus published on the MMC site.

"CC-BY-SA" means the Creative Commons Attribution-Share Alike 3.0 license published by Creative Commons Corporation, a not-for-profit corporation with a principal place of business in San Francisco, California, as well as future copyleft versions of that license published by that same organization.

"Incorporate" means to publish or republish a Document, in whole or in part, as part of another Document.

An MMC is "eligible for relicensing" if it is licensed under this License, and if all works that were first published under this License somewhere other than this MMC, and subsequently incorporated in whole or in part into the MMC, (1) had no cover texts or invariant sections, and (2) were thus incorporated prior to November 1, 2008.

The operator of an MMC Site may republish an MMC contained in the site under CC-BY-SA on the same site at any time before August 1, 2009, provided the MMC is eligible for relicensing.

# Index

## **Symbols**

/bin/dmesg, 36 /bin/login, 174

/boot/grub/grub.conf, 161

/boot/grub/menu.lst, 161

/dev, 47

/dev/hdX, 34

/dev/ht, 352

/dev/nst, 352

/dev/sdb, 88

/dev/sdX, 34

/dev/st, 352

/etc/apt/sources.list, 236

/etc/at.allow, 196

/etc/at.denv. 196

/etc/cron.allow, 197

/etc/cron.d, 198

/etc/cron.deny, 197

/etc/crontab, 198

/etc/default/grub, 166

/etc/exports, 310, 321

/etc/filesystems, 60, 67

/etc/fstab, 63, 71, 88, 216, 311, 321, 362

/etc/grub.conf, 161

/etc/grub.d/40\_custom, 166

/etc/hostname, 272

/etc/inetd.conf, 318

/etc/init.d/, 176, 178

/etc/init.d/rc, 173

/etc/init.d/rcS, 172

/etc/inittab, 171, 173, 174

/etc/lvm/.cache, 113

/etc/modprobe.conf, 338

/etc/modprobe.d/, 338

/etc/mtab, 68, 172

/etc/network/interfaces, 265, 289, 292

/etc/passwd, 174

/etc/protocols, 262

/etc/raidtab, 96

/etc/rc.d/rc, 173

/etc/rc.d/rc.sysinit, 172

/etc/rcS.d/, 172

/etc/rcX.d/, 173

/etc/rsyslog.conf, 207

/etc/services, 262, 318

/etc/shutdown.allow, 182

/etc/ssh, 297

/etc/ssh/ssh\_config, 297

/etc/ssh/sshd\_config, 297

/etc/sysconfig/iptables, 314

/etc/sysconfig/network, 267

/etc/sysconfig/network-scripts/, 267

/etc/sysconfig/network-scripts/ifcfg-bond0, 290

/etc/syslog.conf, 205

/etc/xinetd.conf, 317

/etc/xinetd.d, 317

/etc/yum.conf, 245

/etc/yum.repos.d/, 245

/lib, 346

/lib/modules, 335, 341

/lib/modules/<kernel-version>/modules.dep, 338

/proc/cmdline, 163, 326

/proc/devices, 47, 47

/proc/filesystems, 60, 67

/proc/kallsyms, 334

/proc/mdstat, 96

/proc/meminfo, 213, 214

/proc/modules, 336

/proc/mounts, 68

/proc/net/bonding, 290, 292

/proc/partitions, 47

/proc/scsi/scsi, 39

/proc/swaps, 215

/sbin, 270

/sbin/init, 171

/sbin/mingetty, 174

/sbin/telinit, 181

/usr/lib, 346

/usr/share/doc, 267

/usr/src, 330

/var/lib/nfs/etab, 310, 321

/var/lib/rpm, 238

/var/log/auth.log, 204

/var/log/btmp, 202, 203

/var/log/lastlog, 202

/var/log/messages, 327, 344

/var/log/sa, 224

/var/log/secure, 204

/var/log/wtmp, 182, 202

/var/run/utmp, 202

./configure, 247

.deb, 227

.rpm, 227

.ssh, 301

~/.ssh/authorized\_keys, 302

\$\$, 5

\$PPID, 5

#### Α

access time, 32

active partition, 164

Alica and Bob, 298

anycast, 258

apt-get(8), 228, 232

aptitude, 347

aptitude(1), 331

aptitude(8), 228, 235

arp(1), 273

arp table, 273

at(1), 194, 195

ata, 32

atapi, 32

atm, 260 dhcp, 267, 283 atq(1), 195dhcp client, 265, 272 atrm(1), 196 directory, 57 disk platters, 32 dmesg(1), 36 В dmesg(8), 328 badblocks(8), 40 dns, 283 bg(1), 24DOS, 164 Bill Callkins, 159 dpkg(8), 228, 230 binding, 288 dpkg -S, 347 binding(ip), 287 dsa, 298 **BIOS**, 158 du, 220 block device, 33 du(1), 69bonding(ip), 287 dump(1), 356 boot(grub), 163 bootloader, 160 Ε bootp, 267, 283 broadcast, 258 e2fsck(1), 63 BSD, 158 echo(1), 5btrfs, 59 edquota(1), 362 bum(8), 180 egrep, 172 bzImage, 163 elilo, 160 bzip2, 163 el torito, 59 bzip2(1), 353 Eric Allman, 205 eth0, 265 C ethtool(1), 275Evi Nemeth, 176 cable select, 32 exec, 6 Canonical, 170 exportfs(1), 310, 321 chainloader, 164 ext2, 58, 61 chainloading, 164 ext3, 58 character device, 33 extended partition, 46 chattr(1), 356 chkconfig, 176 F chkconfig(8), 177 chroot, 80 fallback(grub), 162 CHS, 33 fat16, 59 Cisco, 260 fat32, 59 cpio(1), 238, 356 fd (partition type), 95 cron(8), 194 fddi, 260 crontab(1), 197 fdisk, 135 crontab(5), 197 fdisk(1), 47, 49, 50, 95 Ctrl-Alt-Delete, 182, 182 fdisk(8), 35 Ctrl-Z, 23 fdisk limitations, 52 cylinder, 32 fg(1), 24file system, 56

#### D

daemon, 4, 176 dd(1), 51, 160, 216, 357 deb(5), 228 debsums, 347 default(grub), 162, 164 default gateway, 274 depmod(1), 338 device driver, 47 devices.txt, 47 df, 220 df(1), 69, 69 dhclient(1), 272 fatiback(grub), 102
fat16, 59
fat32, 59
fd (partition type), 95
fddi, 260
fdisk, 135
fdisk(1), 47, 49, 50, 95
fdisk(8), 35
fdisk limitations, 52
fg(1), 24
file system, 56
fixed ip, 268
fixed ip address, 265
fork, 6
FQDN, 272
frame relay, 260
free, 220, 221
free(1), 213, 214
fsck(1), 63
ftp, 317
ftp://ftp.kernel.org, 329
fuser, 79, 79

| G   | K  |
|---|--|
| gateway, 274                              | Kerberos, 309, 320                               |
| gnome-session, 363                        | kernel(grub), 163                                |
| gpt, 52                                   | kill(1), 4, 9, 9, 174, 175                       |
| grep, 172, 336                            | killall(1), 11                                   |
| grpquota, 362                             | kmyfirewall, 314                                 |
| grub, 157, 160, 164                       |  |
| grub2, 161                                | L  |
| grub-install, 165                         | LAN, 259   |
| gzip(1), 163, 353                         | last(1), 182, 202                                |
| 11  | lastb(1), 203                                    |
| Н   | lastlog(1), 203                                  |
| halt(8), 182                              | LBA, 33  |
| hdparm(8), 41                             | ldap, 310  |
| head (hard disk device), 32               | ldd, 346   |
| hiddenmenu(grub), 162                     | libraries, 346                                   |
| hostname, 272                             | lilo, 160, 167                                   |
| hostname(1), 272                          | lilo.conf, 167                                   |
| http://www.kernel.org, 329                | logger(1), 208                                   |
| I   | logical drive, 46                                |
|   | logical drives, 51                               |
| icmp, 262                                 | login, 202                                       |
| id_dsa, 302                               | logrotate(1), 209<br>lsmod, 336                  |
| id_dsa.pub, 302                           | lsmod(1), 335                                    |
| id_rsa, 301                               | lsof, 78   |
| id_rsa.pub, 301 ide, 47                   | lsscsi(1), 38                                    |
| ifcfg(1), 288                             | ltrace, 347                                      |
| ifcfg-eth0, 268                           | lvcreate(1), 103, 105, 119                       |
| ifconfig(1), 269, 270, 288, 289, 290, 292 | lvdisplay(1), 106, 114                           |
| ifdown(1), 266, 269, 270, 288             | lvextend(1), 106, 120                            |
| ifenslave, 292                            | lvm, 80  |
| iftop(1), 225                             | LVM, 100   |
| ifup(1), 266, 269, 270, 288, 289, 290     | lvmdiskscan(1), 111                              |
| igmp, 262                                 | lvol0, 119                                       |
| inetd, 317                                | lvremove(1), 119                                 |
| init, 4, 171, 182                         | lvrename(1), 120                                 |
| init=/bin/bash, 327                       | lvs(1), 114                                      |
| initiator(iSCSI), 127                     | lvscan(1), 114                                   |
| initng, 170                               |  |
| initrd, 333                               | M  |
| initrd(grub), 163                         | mac address, 270                                 |
| insmod(1), 337, 337                       | major number, 47                                 |
| Intel, 158                                | make, 344  |
| iostat, 81                                | make(1), 247                                     |
| iostat(1), 223                            | make bzImage, 341                                |
| iotop, 82                                 | make clean, 340                                  |
| iptables, 314<br>iSCSI, 127               | make menuconfig, 340                             |
| iscsiadm, 134                             | make modules, 341                                |
| iso9660, 59, 357                          | make mrproper, 340                               |
| 100000, 50, 551                           | make xconfig, 340                                |
| J   | MAN, 259   |
|   | master (hard disk device), 32                    |
| jbod, 93<br>jobs, 23                      | master boot record, 51, 160 mbr, 51, 51, 52, 160 |
| joliet, 59                                | MBR, 357   |
| journaling, 58                            | mdadm(1), 96                                     |
| J   |  |

| mingetty, 174              | pgrep(1), 8                               |
|----------------------------|---|
| minor number, 47           | PID, 4                                    |
| mirror, 93                 | pidof(1), 5                               |
|                            | ± ' '                                     |
| mkdir, 67                  | ping, 262, 274                            |
| mke2fs(1), 58, 61, 105     | pipes, 16                                 |
| mkfifo, 16                 | pkill(1), 11                              |
| mkfile(1), 216             | portmap, 309, 320                         |
| mkfs(1), 58, 61            | POST, 158                                 |
| mkinitrd(1), 58, 342       | poweroff(8), 182                          |
| mknod(1), 352              | Power On Self Test, 158                   |
| mkswap(1), 215             | PPID, 4                                   |
| ± 1 1                      |   |
| modinfo, 344               | primary partition, 46, 160, 164           |
| modinfo(1), 337            | private key, 298                          |
| modprobe(1), 337, 338      | process, 4                                |
| mount, 67                  | process id, 4                             |
| mount(1), 66, 68, 311, 321 | ps, 7, 220                                |
| mounting, 66               | ps -ef, 7                                 |
| <u> </u>                   |   |
| mount point, 66            | ps fax, 7                                 |
| mpstat(1), 224             | public key, 298                           |
| mt(1), 352                 | pvchange(1), 116                          |
| multicast, 257             | pvcreate(1), 103, 105, 115                |
| multipath, 147             | pvdisplay(1), 105, 112                    |
|                            | pvmove(1), 116                            |
| A1                         | •   |
| N                          | pvremove(1), 115                          |
| netstat(1), 274            | pvresize(1), 115                          |
| network file system, 308   | pvs(1), 111                               |
| nfs, 308, 309              | pvscan(1), 111                            |
|                            |   |
| NFS, 320                   | Q   |
| nice, 18                   | Q   |
| nice(1), 16                | quota.group, 362                          |
| no_subtree_check(nfs), 310 | quota.user, 362                           |
| noacl(mount), 72           | quota's, 362                              |
| nodev, 60, 67              | quota(1), 362                             |
| noexec(mount), 72          | · ·                                       |
|                            | quotacheck(1), 362                        |
| nosuid(mount), 72          | quotaoff(1), 362                          |
| ntop(1), 225               | quotaon(1), 362                           |
|                            |   |
| 0                          | R   |
| 1/4) 4.50                  |   |
| od(1), 160                 | RAID, 92                                  |
| OpenBoot(Sun), 159         | raid 1, 93                                |
| OpenBSD, 297               | reboot(8), 182                            |
| openssh, 297               | reiserfs, 59                              |
| openssh-server, 304        | Remote Desktop, 363                       |
| OS/2, 164                  | <u> -</u>                                 |
| 05/2, 104                  | renice, 17                                |
|                            | renice(1), 16                             |
| P                          | repository, 227, 228                      |
| package management, 227    | repquota(1), 362                          |
|                            | resize2fs(1), 106                         |
| paging, 213                | respawn(init), 174, 174                   |
| PAN, 260                   | restore(1), 356                           |
| Parallel ATA, 32           | * **                                      |
| parity(raid), 93           | rfc 3010, 309                             |
| parted, 52, 53             | rfc 3530, 309                             |
| parted(1), 49              | rlogin, 297                               |
| partition, 46              | rmmod(1), 338                             |
| •                          | rock ridge, 59                            |
| partition table, 51, 51    | _   |
| partprobe(1), 51           |   |
| password(grub), 162        | root(grub), 163<br>root servers(DNS), 258 |

| rootsquash 210 221           | on 246                                |
|------------------------------|---------------------------------------|
| rootsquash, 310, 321         | su, 346                               |
| rotational latency, 32       | subtree_check(nfs), 310               |
| route(1), 274, 274           | Sun, 158, 170                         |
| router, 260                  | swapoff(1), 215                       |
| rpc, 309                     | swapon(1), 215                        |
| RPC, 320                     | swap partition, 59                    |
| rpcinfo(1), 309, 320         | swap partition(s), 217                |
| rpm, 237                     | swapping, 213                         |
| rpm(8), 228                  | swap space, 215                       |
| rpm2cpio(8), 238             | swat, 317                             |
| rpm -qf, 348                 |                                       |
|                              | sysctl(1), 272                        |
| rpm -V, 348                  | syslog, 327                           |
| rsa, 298                     | syslogd, 205, 205                     |
| rsh, 297                     | System.map, 334                       |
| rsyslog, 78                  | system-config-securitylevel, 314      |
| runlevel, 171                | System V, 170                         |
| runlevel(1), 181             |                                       |
|                              | Т                                     |
| S                            | tail(1), 208                          |
| sa2(1), 224                  | tar(1), 247, 353, 354                 |
| sadc(1), 224                 | tcp, 262, 309                         |
| sal, 224                     | tcpdump, 279, 284, 284                |
| sar(1), 224, 224             |                                       |
| sata, 32                     | telinit(8), 181                       |
| savedefault(grub), 164       | telnet, 297, 317                      |
| _                            | time(1), 341                          |
| scp(1), 302                  | timeout(grub), 162                    |
| scsi, 32                     | title(grub), 162                      |
| scsi id, 32                  | top, 11                               |
| sector, 32                   | top(1), 8, 213, 214, 221              |
| seek time, 32                | track, 32                             |
| service(1), 176, 314         | tune2fs(1), 58, 62, 87                |
| setuid, 72                   | · · · · · · · · · · · · · · · · · · · |
| sfdisk(1), 51                | U                                     |
| shutdown(8), 181             | _                                     |
| SIGHUP, 9                    | udf, 59                               |
| SIGKILL, 181                 | udp, 262, 309                         |
| SIGTERM, 11, 181             | uefi, 52                              |
| silo, 160                    | uname(1), 326                         |
| single user mode, 327        | universally unique identifier, 86     |
| slave (hard disk device), 32 | update-grub, 166                      |
|                              | update-rc.d, 176                      |
| SMF, 170                     | update-rc.d(8), 179                   |
| Solaris, 158                 | upstart, 170                          |
| solid state drive, 33        | usrquota, 362                         |
| SPARC, 159                   | uuid, 86                              |
| split(1), 358                | uulu, oo                              |
| ssd, 33                      | V                                     |
| ssh, 297                     | <u>-</u>                              |
| ssh_host_dsa_key, 304        | vanilla, 228                          |
| ssh_host_dsa_key.pub, 304    | vfat, 59                              |
| ssh_host_rsa_key, 304        | vgchange(1), 118                      |
| ssh_host_rsa_key.pub, 304    | vgcreate(1), 103, 105, 117            |
| sshd, 304                    | vgdisplay(1), 113                     |
| ssh-keygen, 301              | vgextend(1), 117                      |
| ssh-keygen(1), 301           | vgmerge(1), 118                       |
| ssh -X, 302                  | vgreduce(1), 117                      |
| stanza(grub), 163            | vgremove(1), 117                      |
| strace, 349                  | vgs(1), 113                           |
| striped disk, 93             | vgs(1), 113<br>vgscan(1), 113         |
| SUIDCU UISK. 7J              | v 2 5 C 4 H ( 1 J , 1 J , .)          |

vi, 349 virtual memory, 213 vmlinuz, 333 vmstat, 83, 217 vmstat(1), 222 vnc, 363 vncviewer(1), 363 vol\_id(1), 87

## W

WAN, 260 watch(1), 208, 222 who(1), 181, 202 wireshark, 279, 297 WPAN, 260

## X

X.25, 260 x86, 158 xinetd, 317, 317 xstartup(vnc), 363

#### Y

yaboot, 160 yum, 348 yum(8), 239

#### Ζ

z/IPL, 160 zfs, 59 zImage, 163 zombie, 4