Arnold 5 Porting Guide

Last updated: 13-Mar-17, 12:06

Types

Some types have disappeared:

```
AtUInt32 -> uint32_t
AtUInt64 ->
AtByte -> uint8_t
```

Metadata

Replace metadata store argument with node entry in **AiMetaDataSetX()**:

```
AiMetaDataSetBool(mds, "input", "always_linear", true) // arnold 4
AiMetaDataSetBool(nentry, "input", "always_linear", true) // arnold 5
```

AtParamValue

AtParamValue is no longer a union but a class, the members become accessors:

```
sg->out.RGB -> sg->out.RGB()
```

Note: Do not replace in the Python code, where members are accessed as if they were still a union.

Parameters

When declaring parameters, the deprecated **AiParameterXXX()** forms have been removed, replace with **AiParameterXxx()**. Also, the **PNT** and **PNT2** forms have to be replaced with **Vec** and **Vec2**:

```
AiParameterBYTE(n,c)
                       -> AiParameterByte(n,c)
AiParameterINT(n,c)
                       -> AiParameterInt(n,c)
AiParameterUINT(n,c)
                       -> AiParameterUInt(n,c)
AiParameterBOOL(n,c)
                       -> AiParameterBool(n,c)
                        -> AiParameterFlt(n,c)
AiParameterFLT(n,c)
AiParameterVEC(n,x,y,z) -> AiParameterVec(n,x,y,z)
AiParameterPNT(n,x,y,z) -> AiParameterVec(n,x,y,z)
AiParameterPNT2(n,x,y) -> AiParameterVec2(n,x,y)
AiParameterSTR(n,c)
                       -> AiParameterStr(n,c)
AiParameterPTR(n,c)
                       -> AiParameterPtr(n,c)
AiParameterNODE(n,c)
                       -> AiParameterNode(n,c)
AiParameterARRAY(n,c)
                       -> AiParameterArray(n,c)
AiParameterMTX(n,c)
                        -> AiParameterMtx(n,c)
AiParameterENUM(n,c,e) -> AiParameterEnum(n,c,e)
```

AtColor

The redundant **AtColor** type has been replaced with **AtRGB**:

```
AtColor -> AtRGB
```

Replace AiColor() with AtRGB constructor:

```
AiColor(r, g, b) -> AtRGB(r, g, b)
```

Replace **AtColorCreate()** with simple **AtRGB** member assignments:

```
AtColorCreate(rgb, r, g, b) -> rgb.r = r; rgb.g = g; rgb.b = b;
```

Alternatively, assign the an **AtRGB** allocated on the stack:

```
AtColorCreate(rgb, r, g, b) -> rgb = AtRGB(r, g, b)
```

Similarly with AiRGBACreate(), with AtRGBA member assignments:

```
AiRGBACreate(rgba, r, g, b, a) -> rgba.r = r; rgba.g = g; rgba.b = b; rgba.a = a;
```

Or with the AtRGBA constructor:

```
AiRGBACreate(rgba, r, g, b, a) -> rgba = AtRGBA(r, g, b, a)
```

Replace AiColorLerp() and AiRGBALerp() with the templated LERP():

```
AiColorLerp(t, rgb1, rgb2) -> L(t, rgb1, rgb2)
AiRGBALerp(t, rgba1, rgba2) -> L(t, rgba1, rgba2)
```

Replace AiColorClamp() with the templated AiRGBClamp():

```
out = AiColorClamp(rgb, min, max) -> out = AiRGBClamp(rgb, min, max)
```

The obsolete define AiColorIsZero() must be replaced with AiColorIsSmall():

```
AiColorIsZero(rgb) -> AiColorIsSmall(rgb)
```

Unless what you really want to test is if the color is pure black:

```
AiColorIsZero(rgb) -> (rgb == AI_RGB_BLACK)
```

Replace **AiColorEqual()** with a simple comparison:

```
AiColorEqual(rgb1, rgb2) -> (rgb1 == rgb2)
```

AI_RGBA_BLACK

To alleviate ambiguity, **AI_RGBA_BLACK** (0, 0, 0, 0) is now **AI_RGBA_ZERO**. Note that **AI_RGBA_BLACK** might come back as (0, 0, 0, 1) in subsequent versions of Arnold:

```
AI_RGBA_BLACK -> AI_RGBA_ZERO
```

Macros and utility functions

The MIN(), MIN3(), MIN4(), and corresponding MAX functions have all been renamed to AiMin() and AiMax(), which are overloaded and support 2, 3, or 4 arguments:

```
MAX(a, b) -> AiMax(a, b)
MIN(a, b) -> AiMin(a, b)
MIN3(a, b, c) -> AiMin(a, b, c)
MIN4(a, b, c, d) -> AiMin(a, b, c, d)
```

Replace **ABS()** with **std::abs()** note that ai_math.h includes appropriate headers for both the floating point and integer versions of abs:

```
ABS(a) -> std::abs(a)
```

SGN() has disappeared:

```
SGN(a) -> (a < 0 ? -1 : 1)
```

AtVector

Replace **AiVector**() with **AtVector** constructor:

```
AiVector(x, y, z) -> AtVector(x, y, z)
```

The obsolete define **AiV3IsZero()** must be replaced with **AiV3IsSmall()**:

```
AiV3IsZero(vec) -> AiV3IsSmall(vec)
```

unless you really wanted to test if the vector was zero:

```
AiV3IsZero(vec) -> (vec == AI_V3_ZERO)
```

Replace **AiV3Create()** with **AtVector** assignment:

```
AiV3Create(vec, x, y, z) -> vec = AtVector(x, y, z);
```

AtPoint2

The AtPoint2 type has been renamed AtVector2:

```
AtPoint2 -> AtVector2
```

The corresponding type ID is now AI_TYPE_VECTOR2:

```
AI_TYPE_POINT2 -> AI_TYPE_VECTOR2
```

All API functions containing **Pnt2** must be renamed with **Vec2** instead:

```
AiNodeSetPnt2() -> AiNodeSetVec2()
AiArraySetPnt2() -> AiArraySetVec2()
AiUDataGetPnt2() -> AiUDataGetVec2()
AiParameterPnt2() -> AiParameterVec2()
[...]
```

The AtParamValue accessor PNT2() is renamed VEC2():

```
sg->out.PNT2() -> sg->out.VEC2()
```

AtPoint

The **AtPoint** type is phased out and simply replaced with **AtVector**:

```
AtPoint -> AtVector
```

Thus AI_TYPE_POINT should be replaced with AI_TYPE_VECTOR. Often times, entire branches in switch() or if() branches will disappear in the AI_TYPE_POINT case. Watch out for AI_TYPE_POINTER occurrences in search & replace operations:

```
AI_TYPE_POINT -> AI_TYPE_VECTOR
```

Replace AtParamValue's PNT() accessors with VEC():

```
sg->out.PNT() -> sg->out.VEC()
```

Replace **Pnt** suffix with **Vec** in all functions with type variants:

```
AiNodeGetPnt() -> AiNodeGetVec()
AiArraySetPnt() -> AiArraySetVec()
AiParameterPnt() -> AiParameterVec()
[...]
```

AtMatrix

AiM4Identity() no longer takes an argument but returns an **AtMatrix**:

```
AiM4Identity(mtx) -> mtx = AiM4Identity()
```

AiM4Transpose(), AiM4Invert(), AiM4Mult() lose the output argument and return an

AtMatrix:

```
AiM4Transpose(mtx, mout) -> mout = AiM4Transpose(mtx)
AiM4Invert(mtx, mout) -> mout = AiM4Invert(mtx)
```

AiM4Frame(), AiM4Translation(), AiM4Scaling(), AiM4Lerp(), AiM4RotationX(), AiM4RotationY(), AiM4RotationZ() pointer arguments become references and they return an AtMatrix:

```
AiM4Frame(mout, &o, &u, &v, &w) -> mout = AiM4Frame(o, u, v, w)

AiM4Translation(mout, &t) -> mout = AiM4Translation(t)

AiM4Scaling(mout, &s) -> mout = AiM4Scaling(s)

AiM4RotationX(mout, rx) -> mout = AiM4Rotation(rx)
```

AiM4VectorByMatrixMult(), AiM4PointByMatrixMult(), AiM4HPointByMatrixMult() and AiM4VectorByMatrixTMult() pointer arguments become references and they return an AtVector:

```
AiM4VectorByMatrixMult(&mout, mtx, &vec) -> mout = AiM4VectorByMatrixMult(mtx, vec)
AiM4PointByMatrixMult(&mout, mtx, &vec) -> mout = AiM4PointByMatrixMult(mtx, vec)
AiM4HPointByMatrixMult(&mout, mtx, &vec) -> mout = AiM4HPointByMatrixMult(mtx, vec)
AiM4VectorByMatrixTMult(&mout, mtx, &vec) -> mout = AiM4VectorByMatrixTMult(mtx, vec)
```

AiM4Berp() has disappeared.

AtArray

Members are no longer accessible directly.

```
arr->nelements -> AiArrayGetNumElements(arr)
arr->nkeys -> AiArrayGetNumKeys(arr)
arr->type -> AiArrayGetType(arr)
```

Note: Verify Python API, these functions are not exposed.

User Data

AiUserGetX() functions take a reference instead of a pointer to the destination variable:

```
AiUDataGetVec2(uvname, &uv) -> AiUDataGetVec2(uvname, uv)
```

AiSampler

AiSampler() now takes a seed argument to avoid correlation artifacts when several samplers are present in the scene graph. In shaders, it is reasonable to use the node name hash as the seed:

```
static const uint32_t seed =
    static_cast<uint32_t>(AiNodeEntryGetNameAtString(AiNodeGetNodeEntry(node)).hash());
AtSampler* sampler = AiSampler(seed, nsamples, ndim);
```

AiBuildLocalFrameShirley

AiBuildLocalFrameShirley() has been replaced by AiV3BuildLocalFrame():

AiBuildLocalFrameShirley(&u, &v, &N) -> AiV3BuildLocalFrame(u, v, N)

AiMakeRay

AiMakeRay() returns an **AtRay** and takes reference arguments, except optional **dir**, thus:

```
AtRay ray;
AiMakeRay(&ray, AI_RAY_REFLECTED, &sg->P, &dir, AI_BIG, sg); // arnold 4
```

becomes:

AtRay ray = AiMakeRay(AI_RAY_REFLECTED, sg->P, &dir, AI_BIG, sg); // arnold 5

AI_PROCEDURAL_NODE_EXPORT_METHODS(MyProceduralMtd);procedural_cleanup();//cleanupprocedural_get_node{} // GetNode(i) = MyProceduralMtd; node->output_type = AI_TYPE_NONE; node->name = "my_procedural"; AI_NODE_SHAPE_PROCEDURAL; strcpy(node->version, AI_VERSION); return true;



AiDriverInitialize() no longer has a data parameter, use AiNodeSetLocalData() instead:

```
AiDriverInitialize(node, supports_multiple_outputs, data); // arnold 4
```

becomes:

```
AiDriverInitialize(node, supports_multiple_outputs); // arnold 5
AiNodeSetLocalData(data);
```

AiDriverGetLocalData() is removed, use AiNodeGetLocalData() instead.

```
AiDriverGetLocalData() -> AiNodeGetLocalData()
```

There's no need to call **AiDriverDestroy()** anymore.

AtString

A lot of functions now require **AtString** arguments instead of **const char***.

AiState(Get|Set)MsgX(), **AiAOVSetX()** now take an **AtString** argument. For example:

```
AiStateSetMsgFlt("mylabel", f); // arnold 4
AiStateGetMsgFlt("mylabel", &f);
```

becomes:

```
static const AtString mylabel("mylabel"); // arnold 5
AiStateSetMsgFlt(mylabel, f);
AiStateGetMsgFlt(mylabel, &f);
```

Reciprocally however, functions expecting a **const char*** can be passed an **AtString** transparently except with variadic arguments. In this case, you need to explicitly call the **AtString::c_str()** method:

```
AtString mystring("toto");
AiMsgWarning("my string: %s", mystring.c_str());
```

Light Sampling

AiLightsGetSample() returns the sample in an **AtLightSample** instead of storing it in the shader globals:

All light sample related shader globals are now mebers of **AtLightSample**. Note that **sg->we** has disappeared, replace it with **1/ls.pdf**:

```
sg->Lp -> ls.Lp
sg->Ldist -> ls.Ldist
sg->Ld -> ls.Ld
sg->Li -> ls.Li
sg->Liu -> ls.Liu
sg->Lo -> ls.Lo
sg->we -> 1.0f / ls.pdf
```

The functions AiLightGetAffect{Diffuse|Specular}() were removed, use directly AiLightGet{Diffuse|Specular}() instead:

```
if (AiLightGetAffectDiffuse(sg->Lp)) {...} -> if (AiLightGetDiffuse(ls.Lp) > 0.0f) {...}
```

Lighting functions

AiIndirectDiffuse() takes references instead of pointers and adds an **AtRGB** weight argument:

```
AiIndirectDiffuse(&sg->Nf, sg) -> AiIndirectDiffuse(sg->Nf, sg, AI_RGB_WHITE)
```

AiCookTorranceIntegrate() was been phased out, use **AiMicrofacetBSDF()** and **AiBSDFIntegrate()** instead. For example, this code:

becomes:

Shader utils

AiReflect() return an **AtVector**, takes reference arguments:

```
AiReflect(&n, &i, &r) -> r = AiReflect(n, i)
```

AtShaderGlobals

Light sampling related shader globals have been removed: Li, Liu, Lo, Ldist, Ld, Lp, i, n, we. These are available as members of an AtLightSample, see Light Sampling section.

The **sx** and **sy** globals have been replaced with subpixel camera sample coordinates **px** and **py**. If **sx** and **sy** are needed they can be computed using the following code:

```
sx = -1 + (sg->x + sg->px) * (2.0f / AiNodeGetInt(AiUniverseGetOptions(), "xres"));
sy = 1 - (sg->y + sg->py) * (2.0f / AiNodeGetInt(AiUniverseGetOptions(), "yres"));
```

The area global was also removed, use AiShaderGlobalsArea() instead:

```
sg->area -> AiShaderGlobalArea(sg)
```

AtBBox

The AtBBox related functions are now class member functions:

```
AiBBoxInit(bbox, f) -> bbox.init(f)
AiBBoxIsEmpty(bbox) -> bbox.isEmpty()
```

AiBBoxUnion() and AiBBoxIntersection() now return the result AtBBox:

```
AiBBoxUnion(bbu, bb1, bb2) -> bbu = AiBBoxUnion(bb1, bb2)
AiBBoxIntersection(bbi, bb1, bb2) -> bbi = AiBBoxIntersection(bb1, bb2)
```

Tickets

These are the tickets related to porting to Arnold 5:

- #5556: **AtParamValue** broken in Python bindings
- #5573: Restore AiRGBGamma() and AiRGBAGamma()

Opacity must now be premultiplied into the weight of BSDFs, BSSRDFs and other closures. For surface closures, the general rule is that the sum of all closure weights should not exceed 1 for the shader to be energy conserving.
closures.add(AiOrenNayarBSDF(sg, Kd, sg->Nf));