

Lab4报告

内存管理程序的核心思路:

首先明确使用的数据结构,通常来说应该用双向链表来保存空闲内存,但由于我们的实验规模小,没有对性能的要求,我们简单地用两个数组分别保存空闲内存表和已分配内存表。下面的表格是一个例子

空闲内存表

index	初始地址	大小
0	0x00	300B
1	0x900	124B

已分配内存

进程名	初始地址	大小
P0	0x300	600B

查找可用块, 分割, 分配

当一个进程申请若干内存,我们需要首先在内存表查找到一块合适的内存块,将其分割出适合的大小分配给进程,并将剩余内存加入空闲内存表。但如果第一次查找没有找到合适的内存块,还不代表系统中剩余内存不足,可能是碎片太多,应当进行一次紧缩后再次试图分配,这次分配失败了,才认为分配失败。

```
1 int allocateByCommand(string processName, int needSize, char waytofit, bool tryagain)
 2
        //usr waytofit to choose a function to get a block
 3
        //W:worst fit, B:best fit, F:firstfit
 4
 5
        if(fail)
 6
            if(tryagain)
 8
 9
10
                Compress();
                 allocateByCommand(processName, needSize,waytofit, false);
11
12
            else
13
14
                cout<<"allocate fail"<<endl;</pre>
15
16
            }
17
        }
18 }
```

紧缩

因我们的程序并不需要真的分配内存给进程运行,也不需要处理进程的重定位问题,我们可以简单的遍历已分配内存表,修改其初始地址,使其成为一片从0开始的连续内存区域,并把空闲内存表中清空,置入一个新的,始地址为最后一个进程末尾地址,大小为(全部内存-进程占用内存量)的大内存块。

回收

我们已经讨论了分配,紧缩的情况,现在该讨论回收问题。

假如现在进程P某声明工作结束,可以立刻释放内存,这时我们要到表中查找到它应插入的位置。这一点只需要通过比较初始地址项就可以找到。但之后我们要考虑三种情况。

- 1. 恰在这块内存前的一个块是空闲的(prev.start + prev.length == this.start),那么只需修改前一个空闲块的大小 (prev.length += this.length),将这个块归并到前一块即可。
- 2. 恰在这块内存前的一个块不是空闲的(prev.start + prev.length != this.start),但恰在这个内存块后的块是空闲的 (this.start + this.length != next.start),那么就可以直接修改下一个块的始地址和大小 (next.start=this.start;next.size+=this.size)。
- 3. 这个空闲内存前后两个块都不是恰好和要回收块相邻的,那么就得插入一个新项。此举主要的坏处是带来内存碎片。

注意这个做法有个简单的缺陷,如果两个空闲块中间有一个碎片被回收了,那么这个碎片只回收到前面的块上,而不能把三个块合并,但假如要考虑这样的情况,就不得不再考虑一层层向上递归回收的问题,不如当内存不足的时候直接进行紧缩。

此外,要注意用户输入可能有误,要求回收一个不存在的进程,这点需要做特殊处理,否则可能出现越界错误。

测试:

我们需要构建一个足够复杂的测试例,能充足说明各分配算法工作正确,回收算法,紧缩算法正确,在遇到内存不足时,可以正确紧缩,尝试重新分配。

```
1 ./allocator 5000
2 allocator>RQ PO 100 W
3 allocator>RQ P1 2000 W
   allocator>RQ P2 400 W
   allocator>RQ P3 600 W
 6
   allocator>STAT
   #由于开始时只有一个内存块,无论要求使用何种算法分配, PO-3都会被分配连续的0-3100这段内存
7
8 #预计输出:
9
   #0-100 P0
10 #100-2100 P1
11 #2100-2500 P2
12 #2500-3100 P3
13 #3100-5000 P4
```

Linux 控制台窗口 ▼ ♀ ×

Init:5000B

allocator>RQ P0 100 W

allocate success

allocator>RQ P1 2000 W

allocate success

allocator>RQ P2 400 Wallocate success

allocator>RQ P3 600 Wallocate success

allocator>STAT

Addresses[0:100] Process P0

Addresses[100:2100] Process P1

Addresses[2100:2500] Process P2

Addresses[2500:3100] Process P3

Addresses[3100:5000] Unused

allocator>

```
1 allocator>RL P0
2 allocator>RL P2
3 allocator>STAT
4 #预计输出:
5 #0-100 U
6 #100-2100 P1
7 #2100-2500 U
8 #2500-3100 P3
9 #3100-5000 U
```

allocator>RL P0

allocator>RL P2

allocator>STAT

Addresses[0:100] Unused

Addresses[100:2100] Process P1

Addresses[2100:2500] Unused

Addresses[2500:3100] Process P3

Addresses[3100:5000] Unused

allocator>

```
1 #worst fit
2 allocator>RQ P4 100 W
3 allocator>STAT
4 #预计输出:
5 #0-100 U
6 #100-2100 P1
7 #2100-2500 U
8 #2500-3100 P3
9 #3100-3200 P4
10 #3200-5000 U
```

```
allocator>RQ P4 100 W
allocate success
allocator>STAT
Addresses[0:100] Unused
Addresses[100:2100] Process P1
Addresses[2100:2500] Unused
Addresses[2500:3100] Process P3
Addresses[3100:3200] Process P4
Addresses[3200:5000] Unused
```

```
1  #best fit
2  allocator>RQ P5 300 B
3  allocator>STAT
4  #预计输出:
5  #0-100 U
6  #100-2100 P1
7  #2100-2400 P5
8  #2400-2500 U
9  #2500-3100 P3
10  #3100-3200 P4
11  #3200-5000 U
```

```
allocator>RQ P5 300 B
allocate success
allocator>STAT
Addresses[0:100] Unused
Addresses[100:2100] Process P1
Addresses[2100:2400] Process P5
Addresses[2400:2500] Unused
Addresses[2500:3100] Process P3
Addresses[3100:3200] Process P4
Addresses[3200:5000] Unused
```

```
1 #first fit
2 allocator>RQ P6 50 F
3 allocator>STAT
4 #预计输出:
5 #0-50 P6
6 #50-100 U
7 #100-2100 P1
8 #2100-2400 P5
9 #2400-2500 U
10 #2500-3100 P3
11 #3100-3200 P4
12 #3200-5000 U
```

```
allocator>RQ P6 50 F
allocate success
allocator>STAT
Addresses[0:50] Process P6
Addresses[50:100] Unused
Addresses[100:2100] Process P1
Addresses[2100:2400] Process P5
Addresses[2400:2500] Unused
Addresses[2500:3100] Process P3
Addresses[3100:3200] Process P4
Addresses[3200:5000] Unused
```

```
1 #申请一个大于最大碎片,但小于剩余总内存的块(最大块1800,总剩余1950)
2 allocator>RQ P7 1850 B
3 #预计进行紧缩后分配成功
4 #预计输出:
5 #0-100 P4
6 #100-2100 P1
7 #2100-2400 P5
8 #2400-3000 P3
9 #3000-3050 P6
10 #3050-4950 P7
11 #4950-5000 U
```

```
allocator>RQ P7 1850 B
no enough memory, we'll try compress first
allocate success
allocator>STAT
Addresses[0:50] Process P6
Addresses[50:2050] Process P1
Addresses[2050:2350] Process P5
Addresses[2350:2950] Process P3
Addresses[2950:3050] Process P4
Addresses[3050:4900] Process P7
Addresses[4900:5000] Unused
```

```
1#申请一个不可能分配出的内存2allocator>RQ P8 200 B3#预计输出失败信息
```

allocator>RQ P8 200 B no enough memory, we'll try compress first not enough memory, failed

实验输出与预测结果一致,说明实验代码工作正确。