

Docker Installation

This guide will cover how to install and setup docker on Ubuntu 24.04 LTS such that it can interact with a NVIDIA GPU and run multiple containers simultaneously.

Prerequisites / Assumptions

This guide assumes that you are using [Linux Ubuntu 24.04 LTS](#) and don't have a previous docker installation on your system.

Setting up Docker

Docker is a complex piece of virtualization software. It runs every piece of software in a separate container, each defined by an image. That said, I'm not aware how one can integrate the NVIDIA Container Toolkit with the Docker Desktop version, which is why we will stick to the CLI version.

1. Installing Docker

1. Clean machine | Uninstall all conflicting packages

```
for pkg in docker.io docker-doc docker-compose docker-  
compose-v2 podman-docker containerd runc; do sudo apt-get  
remove $pkg; done
```

2. Setup Docker's repository

```
# Add Docker's official GPG key:  
sudo apt-get update  
sudo apt-get install ca-certificates curl  
sudo install -m 0755 -d /etc/apt/keyrings  
sudo curl -fsSL https://download.docker.com/linux/ubuntu/gpg  
-o /etc/apt/keyrings/docker.asc  
sudo chmod a+r /etc/apt/keyrings/docker.asc  
  
# Add the repository to Apt sources:
```

```
echo \  
"deb [arch=$(dpkg --print-architecture) signed-  
by=/etc/apt/keyrings/docker.asc]  
https://download.docker.com/linux/ubuntu \  
$(. /etc/os-release && echo  
"${UBUNTU_CODENAME:-$VERSION_CODENAME}") stable" | \  
sudo tee /etc/apt/sources.list.d/docker.list > /dev/null  
sudo apt-get update
```

3. Install docker packages

```
sudo apt-get install docker-ce docker-ce-cli containerd.io  
docker-buildx-plugin docker-compose-plugin
```

2. Verfying installation

```
# For the free world  
sudo docker run hello-world  
  
# For mainland china  
  
sudo docker run docker.1ms.run/hello-world
```

3. *Optional set docker as start up service*

As of now docker is dorment requires manual restarting each time the terminal is closed using:

```
sudo systemctl start docker
```

If you want to have docker automatically available from the moment of boot up run:

```
sudo systemctl enable docker.service  
sudo systemctl enable containerd.service
```

To stop this behaviour, use disable:

```
sudo systemctl disable docker.service  
sudo systemctl disable containerd.service
```

Note docker requires you to run it as a root-user. While it is possible to run it as a non-root-user, we will not cover

| that.

4. Setting up Nvidia

Follow the nvidia setup guide, defined in setup_nvidia_gpu.pdf. It is recommended to complete this guide in a seperate terminal.

5. Finalising Installation

The following step is only necessary for chinese users to by pass the restrictions imposed by the great firewall of china.

To by pass the great firewall of china legally, one has to use mirrors. I recommend docker.1ms.run but I'm sure that there are plenty of other options.

1. Open the dockerd configuration file

```
sudo nano /etc/docker/daemon.json
```

2. Overwrite the files content

```
sudo systemctl restart docker
```

Sources

- [Installing Docker](#)
- [Configuring Docker after installation](#)