U.N.A.M. - C.F.R.T.

Forense

Alumno: Luis Fernando Resendiz Cruz

Creacion de la particion 1 Linux.

```
Iresendiz@luis-resendiz:~$ sudo fdisk /dev/sdb
Welcome to fdisk (util-linux 2.31.1).
Changes will remain in memory only, until you decide to write them.
Be careful before using the write command.

Device does not contain a recognized partition table.
Created a new DOS disklabel with disk identifier 0x5aafea79.

Command (m for help): n
Partition type
    p    primary (0 primary, 0 extended, 4 free)
    e     e    extended (container for logical partitions)
Select (default p): p
Partition number (1-4, default 1): 1
First sector (2048-2097151, default 2048):
Last sector, +sectors or +size{K,M,G,T,P} (2048-2097151, default 2097151): +50M
Created a new partition 1 of type 'Linux' and of size 50 MiB.
```

Creación de la partición 2 SWAP.

```
Command (m for help): n
Partition type
   p primary (1 primary, 0 extended, 3 free)
   e extended (container for logical partitions)
Select (default p): p
Partition number (2-4, default 2):
First sector (104448-2097151, default 104448):
Last sector, +sectors or +size{K,M,G,T,P} (104448-2097151, default 2097151): +50M

Created a new partition 2 of type 'Linux' and of size 50 MiB.

Command (m for help): t
Partition number (1,2, default 2): 2
Hex code (type L to list all codes): 82

Changed type of partition 'Linux' to 'Linux swap / Solaris'.
```

Creacion de la partición 3 Windows.

```
Command (m for help): n
Partition type
   p primary (2 primary, 0 extended, 2 free)
   e extended (container for logical partitions)
Select (default p): p
Partition number (3,4, default 3): 3
First sector (206848-2097151, default 206848):
Last sector, +sectors or +size{K,M,G,T,P} (206848-2097151, default 2097151): +50M

Created a new partition 3 of type 'Linux' and of size 50 MiB.

Command (m for help): t
Partition number (1-3, default 3):
Hex code (type L to list all codes): 7

Changed type of partition 'Linux' to 'HPFS/NTFS/exFAT'.
```

Creación de la partición 4 Datos (Extended)

```
Command (m for help): n
Partition type
   p primary (3 primary, 0 extended, 1 free)
   e extended (container for logical partitions)
Select (default e): e

Selected partition 4
First sector (309248-2097151, default 309248):
Last sector, +sectors or +size{K,M,G,T,P} (309248-2097151, default 2097151): +50M

Created a new partition 4 of type 'Extended' and of size 50 MiB.
```

Verificación de las particiones que contiene el volumen de almacenamiento.

```
Command (m for help): p
Disk /dev/sdb: 1 GiB, 1073741824 bytes, 2097152 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disklabel type: dos
Disk identifier: 0x5aafea79
Device
           Boot Start
                         End Sectors Size Id Type
/dev/sdb1
                  2048 104447 102400 50M 83 Linux
/dev/sdb2
                104448 206847 102400 50M 82 Linux swap / Solaris
/dev/sdb3
                206848 309247 102400 50M 7 HPFS/NTFS/exFAT
/dev/sdb4
                              102400 50M 5 Extended
                309248 411647
```

Vizualisacion de el MBR.

```
lresendiz@luis-resendiz:~$ sudo dd if=/dev/sdb count=1 | hd
000001b0
       00 00 00 00 00 00 00
                              4a 7f fb 86 00 00 00 20
000001c0
        21 00 83 7f 39 06 00 08
                              00 00 00 90 01 00 00 7f
000001d0
        3a 06 82 df 13 0c 00 98
                              01 00 00 90 01 00 00 df
        14 0c 07 3f 2c 13 00 28
000001e0
                              03 00 00 90 01 00 00 3f
        2d 13 05 9f 06 19 00 b8
000001f0
                              04 00 00 90 01 00 55 aa
1+0 records in
1+0 records out
512 bytes copied, 0.019558 s, 26.2 kB/s
00000200
```

Para un análisis mas sencillo se decidió mover la salida a un archivo y limpiar lo que no se necesita en estos momentos. Se aislaron los 64 bytes que preceden al identificador del MBR, cada 16 bytes representan una partición.

```
00 20 21 00 83 7f 39 06 00 08 00 00 00 90 01 00 00 7f 3a 06 82 df 13 0c 00 98 01 00 00 90 01 00 00 df 14 0c 07 3f 2c 13 00 28 03 00 00 90 01 00 00 3f 2d 13 05 9f 06 19 00 b8 04 00 00 90 01 00 55 aa
```

Partición de arranque: Ninguno debido a que todos están en 0.

```
00 20 21 00 83 7f 39 06 00 08 00 00 00 90 01 00 00 7f 3a 06 82 df 13 0c 00 98 01 00 00 90 01 00 00 df 14 0c 07 3f 2c 13 00 28 03 00 00 90 01 00 2d 13 05 9f 06 19 00 b8 04 00 00 90 01 00 55 aa
```

Cabezal donde inicia la partición:

Partición 1: 20 Partición 2: 7f Partición 3: df Partición 4: 3f

```
00 20 21 00 83 7f 39 06 00 08 00 00 00 90 01 00 00 7f 3a 06 82 df 13 0c 00 98 01 00 00 90 01 00 00 df 14 0c 07 3f 2c 13 00 28 03 00 00 90 01 00 00 3f 2d 13 05 9f 06 19 00 b8 04 00 00 90 01 00 55 aa
```

Sector y cilindró donde inicia la partición:

Partición 1: 21 00 Partición 2: 3a 06 Partición 3: 14 0c Partición 4: 2d 13

```
00 20 21 00 83 7f 39 06 00 08 00 00 00 90 01 00 00 7f 3a 06 82 df 13 0c 00 98 01 00 00 90 01 00 00 df 14 0c 07 3f 2c 13 00 28 03 00 00 90 01 00 00 3f 2d 13 05 9f 06 19 00 b8 04 00 00 90 01 00 55 aa
```

Tipo de partición:

Partición 1: 83 (Linux)

Partición 2: 82 (Linux SWAP / Solaris)

Partición 3: 07 (HPFS / NTFS)
Partición 4: 05 (Extended - Datos)

```
00 20 21 00 83 7f 39 06 00 08 00 00 00 90 01 00 00 7f 3a 06 82 df 13 0c 00 98 01 00 00 90 01 00 00 df 14 0c 07 3f 2c 13 00 28 03 00 00 90 01 00 00 3f 2d 13 05 9f 06 19 00 b8 04 00 00 90 01 00 55 aa
```

Cabezal donde finaliza la partición:

Partición 1: 7f

Partición 2: df

Partición 3: 3f

Partición 4: 9f

```
00 20 21 00 83 7f 39 06 00 08 00 00 00 90 01 00 00 7f 3a 06 82 df 13 0c 00 98 01 00 00 90 01 00 00 df 14 0c 07 3f 2c 13 00 28 03 00 00 90 01 00 00 3f 2d 13 05 9f 06 19 00 b8 04 00 00 90 01 00 55 aa
```

Sector y cilindró donde inicia la partición:

Partición 1: 39 06 Partición 2: 13 0c Partición 3: 2c 13 Partición 4: 06 19

```
00 20 21 00 83 7f 39 06 00 08 00 00 00 90 01 00 00 7f 3a 06 82 df 13 0c 00 98 01 00 00 90 01 00 00 df 14 0c 07 3f 2c 13 00 28 03 00 00 90 01 00 00 3f 2d 13 05 9f 06 19 00 b8 04 00 00 90 01 00 55 aa
```

Distancia en sectores, desde la tabla de particiones al sector de la partición:

Partición 1: 06 00 08 00 Partición 2: 0c 00 98 01 Partición 3: 13 00 28 03 Partición 4: 19 00 b8 04

```
00 20 21 00 83 7f 39 06 00 08 00 00 00 90 01 00 00 7f 3a 06 82 df 13 0c 00 98 01 00 00 90 01 00 00 df 14 0c 07 3f 2c 13 00 28 03 00 00 90 01 00 00 3f 2d 13 05 9f 06 19 00 b8 04 00 00 90 01 00 55 aa
```

Tamaño de partición:

```
Numero en hexadecimal → Numero de sectores → Tamaño en Bytes → Tamaño en Megas Partición 1: 00 01 90 00 → 102,400 \rightarrow 52,428,800 \rightarrow 52.4288 MB Partición 2: 00 01 90 00 \rightarrow 102,400 \rightarrow 52,428,800 \rightarrow 52.4288 MB Partición 3: 00 01 90 00 \rightarrow 102,400 \rightarrow 52,428,800 \rightarrow 52.4288 MB Partición 4: 00 01 90 00 \rightarrow 102,400 \rightarrow 52,428,800 \rightarrow 52.4288 MB
```