

Operating Systems

Virtual Memory

Virtual Memory

- Background
- Demand Paging
- Copy-on-Write
- Page Replacement
- Allocation of Frames
- Thrashing
- Memory-Mapped Files
- Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Objectives

- To describe the benefits of a virtual memory system
- To explain the concepts of demand paging, page-replacement algorithms, and allocation of page frames
- To discuss the principle of the working-set model


Background

- Code needs to be in memory to execute, but entire program rarely used
 - Error code, unusual routines, large data structures
- Entire program code not needed at same time
- Consider ability to execute partially-loaded program
 - Program no longer constrained by limits of physical memory
 - Program and programs could be larger than physical memory


Background

- Virtual memory separation of user logical memory from physical memory
 - Only part of the program needs to be in memory for execution
 - Logical address space can therefore be much larger than physical address space
 - Allows address spaces to be shared by several processes
 - Allows for more efficient process creation
 - More programs running concurrently
 - Less I/O needed to load or swap processes
- Virtual memory can be implemented via:
 - Demand paging
 - Demand segmentation

Virtual Memory That is Larger Than Physical Memory




Virtual-address Space



Virtual Address Space

- Enables <u>sparse</u> address spaces with holes left for growth, dynamically linked libraries, etc
- System libraries shared via mapping into virtual address space
- Shared memory by mapping pages read-write into virtual address space
- Pages can be shared during fork(), speeding process creation

Shared Library Using Virtual Memory



Demand Paging


Could bring entire process into memory at load time
Or bring a page into memory only when it is needed
Less I/O needed, no unnecessary I/O
Less memory needed
Faster response
More users

Page is needed ⇒ reference to it invalid reference ⇒ abort not-in-memory ⇒ bring to memory

Lazy swapper – never swaps a page into memory unless page will be needed

Swapper that deals with pages is a pager

Transfer of a Paged Memory to Contiguous Disk Space



Valid-Invalid Bit

With each page table entry a valid-invalid bit is associated (**v** ⇒ in-memory – **memory resident**, **i** ⇒ not-in-memory)

Initially valid—invalid bit is set to i on all entries


Example of a page table snapshot:



page table

During address translation, if valid-invalid bit in page table entry is $I \Rightarrow$ page fault

Page Table When Some Pages Are Not in Main Memory



Page Fault

If there is a reference to a page, first reference to that page will trap to operating system:

page fault

Operating system looks at another table to decide:

Invalid reference ⇒ abort

Just not in memory

Get empty frame

Swap page into frame via scheduled disk operation

Reset tables to indicate page now in memory


Set validation bit = v

Restart the instruction that caused the page fault

Aspects of Demand Paging

- Extreme case start process with no pages in memory
 - OS sets instruction pointer to first instruction of process, nonmemory-resident -> page fault
 - And for every other process pages on first access
 - Pure demand paging
- Actually, a given instruction could access multiple pages -> multiple page faults
 - Pain decreased because of locality of reference
- Hardware support needed for demand paging
 - Page table with valid / invalid bit
 - Secondary memory (swap device with swap space)
 - Instruction restart

Steps in Handling a Page Fault



Performance of Demand Paging

Stages in Demand Paging

- 1. Trap to the operating system
- 2. Save the user registers and process state
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal and determine the location of the page on the disk
- 5. Issue a read from the disk to a free frame:
 - 1. Wait in a queue for this device until the read request is serviced
 - 2. Wait for the device seek and/or latency time
 - 3. Begin the transfer of the page to a free frame
- 6. While waiting, allocate the CPU to some other user
- 7. Receive an interrupt from the disk I/O subsystem (I/O completed)
- 8. Save the registers and process state for the other user
- 9. Determine that the interrupt was from the disk
- 10. Correct the page table and other tables to show page is now in memory
- 11. Wait for the CPU to be allocated to this process again
- 12. Restore the user registers, process state, and new page table, and then resume the interrupted instruction

Performance of Demand Paging (Cont.)

```
Page Fault Rate 0 \le p \le 1
    if p = 0 no page faults
    if p = 1, every reference is a fault
Effective Access Time (EAT)
                    EAT = (1 - p) \times memory access
                          + p (page fault overhead
                                 + swap page out
                                 + swap page in
                                 + restart overhead
```

Demand Paging Example

Memory access time = 200 nanoseconds Average page-fault service time = 8 milliseconds

EAT =
$$(1 - p) \times 200 + p$$
 (8 milliseconds)
= $(1 - p \times 200 + p \times 8,000,000$
= $200 + p \times 7,999,800$
If one access out of 1,000 causes a page fault, then
EAT = 8.2 microseconds.
This is a slowdown by a factor of 40!!
If want performance degradation < 10 percent
 $220 > 200 + 7,999,800 \times p$
 $20 > 7,999,800 \times p$
p < .0000025
< one page fault in every 400,000 memory accesses

Demand Paging Optimizations

Copy entire process image to swap space at process load time

Then page in and out of swap space

Used in older BSD Unix


Demand page in from program binary on disk, but discard rather than paging out when freeing frame

Used in Solaris and current BSD


Copy-on-Write

- Copy-on-Write (COW) allows both parent and child processes to initially share the same pages in memory
 - If either process modifies a shared page, only then is the page copied
- COW allows more efficient process creation as only modified pages are copied
- In general, free pages are allocated from a pool of zero-fill-ondemand pages
 - Why zero-out a page before allocating it?
- vfork() variation on fork() system call has parent suspend and child using copy-on-write address space of parent
 - Designed to have child call exec()
 - Very efficient

Before Process 1 Modifies Page C



After Process 1 Modifies Page C



What Happens if There is no Free Frame?

Used up by process pages
Also in demand from the kernel, I/O buffers, etc
How much to allocate to each?

Page replacement – find some page in memory, but not really in use, page it out

Algorithm – terminate? swap out? replace the page?

Performance – want an algorithm which will result in minimum number of page faults

Same page may be brought into memory several times


Page Replacement

Prevent over-allocation of memory by modifying page-fault service routine to include page replacement

Use **modify (dirty) bit** to reduce overhead of page transfers – only modified pages are written to disk

Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory


Need For Page Replacement



Basic Page Replacement

- 1. Find the location of the desired page on disk
- 2. Find a free frame:
 - If there is a free frame, use it
 - If there is no free frame, use a page replacement algorithm to select a victim frame
 - Write victim frame to disk if dirty
- 3. Bring the desired page into the (newly) free frame; update the page and frame tables
- 4. Continue the process by restarting the instruction that caused the trap

Page Replacement



Page and Frame Replacement Algorithms

Frame-allocation algorithm determines

How many frames to give each process

Which frames to replace

Page-replacement algorithm

Want lowest page-fault rate on both first access and re-access

Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string


String is just page numbers, not full addresses

Repeated access to the same page does not cause a page fault

In all our examples, the reference string is

7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1

Graph of Page Faults Versus The Number of Frames



First-In-First-Out (FIFO) Algorithm

Reference string: **7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1**3 frames (3 pages can be in memory at a time per process)

```
      1
      7
      2
      4
      0
      7

      2
      0
      3
      2
      1
      0
      15 page faults

      3
      1
      0
      3
      2
      1
```


Can vary by reference string: consider 1,2,3,4,1,2,5,1,2,3,4,5
Adding more frames can cause more page faults!

Belady's Anomaly


How to track ages of pages?

Just use a FIFO queue

FIFO Page Replacement



FIFO Illustrating Belady's Anomaly



Optimal Algorithm


Replace page that will not be used for longest period of time 9 is optimal for the example on the next slide

How do you know this?

Can't read the future

Used for measuring how well your algorithm performs

Optimal Page Replacement




Least Recently Used (LRU) Algorithm

Use past knowledge rather than future

Replace page that has not been used in the most amount of time

Associate time of last use with each page



12 faults – better than FIFO but worse than OPT Generally good algorithm and frequently used But how to implement?

LRU Algorithm (Cont.)

Counter implementation

Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter

When a page needs to be changed, look at the counters to find smallest value

Search through table needed

Stack implementation

Keep a stack of page numbers in a double link form:

Page referenced:

move it to the top


requires 6 pointers to be changed

But each update more expensive

No search for replacement

LRU and OPT are cases of **stack algorithms** that don't have Belady's Anomaly

Use Of A Stack to Record The Most Recent Page References



LRU Approximation Algorithms

```
LRU needs special hardware and still slow

Reference bit

With each page associate a bit, initially = 0

When page is referenced bit set to 1
```

Replace any with reference bit = 0 (if one exists)

We do not know the order, however

Second-chance algorithm

Generally FIFO, plus hardware-provided reference bit

Clock replacement


If page to be replaced has

Reference bit = 0 -> replace it

reference bit = 1 then:

set reference bit 0, leave page in memory replace next page, subject to same rules

Second-Chance (clock) Page-Replacement Algorithm



Counting Algorithms

Keep a counter of the number of references that have been made to each page

Not common

LFU Algorithm: replaces page with smallest count

MFU Algorithm: based on the argument that the page with the smallest count was probably just brought in and has yet to be used

Page-Buffering Algorithms

- Keep a pool of free frames, always
 - Then frame available when needed, not found at fault time
 - Read page into free frame and select victim to evict and add to free pool
 - When convenient, evict victim
- Possibly, keep list of modified pages
 - When backing store otherwise idle, write pages there and set to non-dirty
- Possibly, keep free frame contents intact and note what is in them
 - If referenced again before reused, no need to load contents again from disk
 - Generally useful to reduce penalty if wrong victim frame selected

Applications and Page Replacement

- All of these algorithms have OS guessing about future page access
- Some applications have better knowledge i.e. databases
- Memory intensive applications can cause double buffering
 - OS keeps copy of page in memory as I/O buffer
 - Application keeps page in memory for its own work
- Operating system can given direct access to the disk, getting out of the way of the applications
 - Raw disk mode
- Bypasses buffering, locking, etc.

Allocation of Frames

- Each process needs minimum number of frames
- Example: IBM 370 6 pages to handle SS MOVE instruction:
 - instruction is 6 bytes, might span 2 pages
 - 2 pages to handle from
 - 2 pages to handle to
- Maximum of course is total frames in the system.
- Two major allocation schemes
 - fixed allocation
 - priority allocation
- Many variations

Fixed Allocation

- Equal allocation For example, if there are 100 frames (after allocating frames for the OS) and 5 processes, give each process 20 frames
 - Keep some as free frame buffer pool
- Proportional allocation Allocate according to the size of process
 - Dynamic as degree of multiprogramming, process sizes change

$$s_i = \text{size of process } p_i$$

 $S = \sum s_i$

m = total number of frames

$$a_i =$$
allocation for $p_i = \frac{s_i}{S} \times m$

$$m = 64$$

$$s_1 = 10$$

$$s_2 = 127$$

$$a_1 = \frac{10}{137} \times 64 \approx 5$$

$$a_2 = \frac{127}{137} \times 64 \approx 59$$

Priority Allocation

- Use a proportional allocation scheme using priorities rather than size
- If process P_i generates a page fault,
 - select for replacement one of its frames
 - select for replacement a frame from a process with lower priority number

Global vs. Local Allocation

Global replacement – process selects a replacement frame from the set of all frames; one process can take a frame from another

But then process execution time can vary greatly

But greater throughput so more common

Local replacement – each process selects from only its own set of allocated frames

More consistent per-process performance

But possibly underutilized memory


Non-Uniform Memory Access

- So far all memory accessed equally
- Many systems are NUMA speed of access to memory varies
 - Consider system boards containing CPUs and memory, interconnected over a system bus
- Optimal performance comes from allocating memory "close to" the CPU on which the thread is scheduled
 - And modifying the scheduler to schedule the thread on the same system board when possible
 - Solved by Solaris by creating Igroups
 - Structure to track CPU / Memory low latency groups
 - Used my schedule and pager
 - When possible schedule all threads of a process and allocate all memory for that process within the Igroup

Thrashing

- If a process does not have "enough" pages, the page-fault rate is very high
 - Page fault to get page
 - Replace existing frame
 - But quickly need replaced frame back
 - This leads to:
 - Low CPU utilization
 - Operating system thinking that it needs to increase the degree of multiprogramming
 - Another process added to the system
- Thrashing = a process is busy swapping pages in and out

Thrashing (Cont.)



Demand Paging and Thrashing

Why does demand paging work?

Locality model

Process migrates from one locality to another


Localities may overlap

Why does thrashing occur?

 Σ size of locality > total memory size

Limit effects by using local or priority page replacement

Locality In A Memory-Reference Pattern



Working-Set Model

```
\Delta = working-set window = a fixed number of page references Example: 10,000 instructions
```

```
WSS<sub>i</sub> (working set of Process P_i) = total number of pages referenced in the most recent \Delta (varies in time)
```

if Δ too small will not encompass entire locality

if Δ too large will encompass several localities

if $\Delta = \infty \Rightarrow$ will encompass entire program

 $D = \Sigma WSS_i \equiv \text{total demand frames}$ Approximation of locality

if $D > m \Rightarrow$ Thrashing

Policy if D > m, then suspend or swap out one of the processes

Working-set model

 $WS(t_1) = \{1,2,5,6,7\}$

page reference table ... 2 6 1 5 7 7 7 7 5 1 6 2 3 4 1 2 3 4 4 4 3 4 3 4 4 4 1 3 2 3 4 4 4 3 4 4 4 . . .

 $WS(t_2) = \{3,4\}$

Keeping Track of the Working Set

Approximate with interval timer + a reference bit

Example: $\Delta = 10,000$

Timer interrupts after every 5000 time units

Keep in memory 2 bits for each page

Whenever a timer interrupts copy and sets the values of all reference bits to 0

If one of the bits in memory = $1 \Rightarrow$ page in working set

Why is this not completely accurate?

Improvement = 10 bits and interrupt every 1000 time units


Page-Fault Frequency

More direct approach than WSS


Establish "acceptable" page-fault frequency rate and use local replacement policy

If actual rate too low, process loses frame

If actual rate too high, process gains frame



Working Sets and Page Fault Rates




Memory-Mapped Files

- Memory-mapped file I/O allows file I/O to be treated as routine memory access by mapping a disk block to a page in memory
- A file is initially read using demand paging
 - A page-sized portion of the file is read from the file system into a physical page
 - Subsequent reads/writes to/from the file are treated as ordinary memory accesses
- Simplifies and speeds file access by driving file I/O through memory rather than read() and write() system calls
- Also allows several processes to map the same file allowing the pages in memory to be shared
- But when does written data make it to disk?
 - Periodically and / or at file close() time
 - For example, when the pager scans for dirty pages

Memory-Mapped File Technique for all I/O


- Some OSes uses memory mapped files for standard I/O
- Process can explicitly request memory mapping a file via mmap ()
 system call
 - Now file mapped into process address space
- For standard I/O (open(), read(), write(), close()), mmap anyway
 - But map file into kernel address space
 - Process still does read() and write()
 - Copies data to and from kernel space and user space
 - Uses efficient memory management subsystem
 - Avoids needing separate subsystem
- COW can be used for read/write non-shared pages
- Memory mapped files can be used for shared memory (although again via separate system calls)

Memory Mapped Files



Memory-Mapped Shared Memory

in Windows




Allocating Kernel Memory

- Treated differently from user memory
- Often allocated from a free-memory pool
 - Kernel requests memory for structures of varying sizes
 - Some kernel memory needs to be contiguous
 - I.e. for device I/O

Buddy System

- Allocates memory from fixed-size segment consisting of physically-contiguous pages
- Memory allocated using power-of-2 allocator
 - Satisfies requests in units sized as power of 2
 - Request rounded up to next highest power of 2
 - When smaller allocation needed than is available, current chunk split into two buddies of next-lower power of 2
 - Continue until appropriate sized chunk available
- For example, assume 256KB chunk available, kernel requests 21KB
 - Split into A_{L and} A_r of 128KB each
 - One further divided into B_L and B_R of 64KB
 - One further into C_L and C_R of 32KB each one used to satisfy request
- Advantage quickly coalesce unused chunks into larger chunk
- Disadvantage fragmentation

Buddy System Allocator



Slab Allocator

Alternate strategy

Slab is one or more physically contiguous pages

Cache consists of one or more slabs

Single cache for each unique kernel data structure

Each cache filled with **objects** – instantiations of the data structure

When cache created, filled with objects marked as free


When structures stored, objects marked as used

If slab is full of used objects, next object allocated from empty slab

If no empty slabs, new slab allocated

Benefits include no fragmentation, fast memory request satisfaction

Slab Allocation



Other Considerations -- Prepaging

Prepaging

To reduce the large number of page faults that occurs at process startup

Prepage all or some of the pages a process will need, before they are referenced

But if prepaged pages are unused, I/O and memory was wasted

Assume s pages are prepaged and α of the pages is used Is cost of s * α save pages faults > or < than the cost of prepaging s * (1- α) unnecessary pages?

α near zero ⇒ prepaging loses

Other Issues – Page Size

- Sometimes OS designers have a choice
 - Especially if running on custom-built CPU
- Page size selection must take into consideration:
 - Fragmentation
 - Page table size
 - Resolution
 - I/O overhead
 - Number of page faults
 - Locality
 - TLB size and effectiveness
- Always power of 2, usually in the range 2¹² (4,096 bytes) to 2²² (4,194,304 bytes)
- On average, growing over time

Other Issues - TLB Reach

TLB Reach - The amount of memory accessible from the TLB

TLB Reach = (TLB Size) X (Page Size)

Ideally, the working set of each process is stored in the TLB Otherwise there is a high degree of page faults

Increase the Page Size

This may lead to an increase in fragmentation as not all applications require a large page size

Provide Multiple Page Sizes

This allows applications that require larger page sizes the opportunity to use them without an increase in fragmentation

Other Issues – Program Structure

```
Program structure
   Int[128,128] data;
   Each row is stored in one page
   Program 1
                  for (j = 0; j < 128; j++)
                       for (i = 0; i < 128; i++)
                              data[i,j] = 0;
      128 \times 128 = 16,384 page faults
   Program 2
                  for (i = 0; i < 128; i++)
                       for (j = 0; j < 128; j++)
                              data[i,j] = 0;
```


128 page faults

Other Issues – I/O interlock

I/O Interlock – Pages must sometimes be locked into memory

Consider I/O - Pages that are used for copying a file from a device must be locked from being selected for eviction by a page replacement algorithm

Reason Why Frames Used For I/O Must Be In Memory



Reference Book

"Operating System Concepts" by Silberchartz, Galvin, Gagne, Wiley India Publications.

