

Operating Systems

Mass-Storage Systems

Overview

- Overview of Mass Storage Structure
- Disk Structure
- Disk Attachment
- Disk Scheduling
- Disk Management
- Swap-Space Management
- Disk Attachment
- Stable-Storage Implementation
- Tertiary Storage Devices
- Operating System Support
- Performance Issues

Objectives


 Describe the physical structure of secondary and tertiary storage devices and the resulting effects on the uses of the devices

 Explain the performance characteristics of massstorage devices

Overview of Mass Storage Structure

- Magnetic disks provide bulk of secondary storage of modern computers
 - Drives rotate at 60 to 200 times per second
 - Transfer rate is rate at which data flow between drive and computer
 - Positioning time (random-access time) is time to move disk arm to desired cylinder (seek time) and time for desired sector to rotate under the disk head (rotational latency)
 - Head crash results from disk head making contact with the disk surface
 - That's bad
- Disks can be removable
- Drive attached to computer via I/O bus
 - Busses vary, including EIDE, ATA, SATA, USB, Fibre Channel, SCSI
 - Host controller in computer uses bus to talk to disk controller built into drive or storage array

Moving-head Disk Mechanism



Overview of Mass Storage Structure (Cont.)

Magnetic tape

- Was early secondary-storage medium
- Relatively permanent and holds large quantities of data
- Access time slow
- Random access ~1000 times slower than disk
- Mainly used for backup, storage of infrequently-used data, transfer medium between systems
- Kept in spool and wound or rewound past read-write head
- Once data under head, transfer rates comparable to disk
- 20-200GB typical storage
- Common technologies are 4mm, 8mm, 19mm, LTO-2 and SDLT

Disk Structure


- Disk drives are addressed as large 1-dimensional arrays of logical blocks, where the logical block is the smallest unit of transfer.
- The 1-dimensional array of logical blocks is mapped into the sectors of the disk sequentially.
 - Sector 0 is the first sector of the first track on the outermost cylinder.
 - Mapping proceeds in order through that track, then the rest of the tracks in that cylinder, and then through the rest of the cylinders from outermost to innermost.

Disk Attachment

- Host-attached storage accessed through I/O ports talking to I/O busses
- SCSI itself is a bus, up to 16 devices on one cable, SCSI initiator requests operation and SCSI targets perform tasks
 - Each target can have up to 8 logical units (disks attached to device controller
- FC is high-speed serial architecture
 - Can be switched fabric with 24-bit address space the basis of storage area networks (SANs) in which many hosts attach to many storage units
 - Can be arbitrated loop (FC-AL) of 126 devices


Network-Attached Storage

- Network-attached storage (NAS) is storage made available over a network rather than over a local connection (such as a bus)
- NFS and CIFS are common protocols
- Implemented via remote procedure calls (RPCs) between host and storage
- New iSCSI protocol uses IP network to carry the SCSI protocol



Storage Area Network

- Common in large storage environments (and becoming more common)
- Multiple hosts attached to multiple storage arrays flexible



Disk Scheduling

- The operating system is responsible for using hardware efficiently — for the disk drives, this means having a fast access time and disk bandwidth
- Access time has two major components
 - Seek time is the time for the disk are to move the heads to the cylinder containing the desired sector
 - Rotational latency is the additional time waiting for the disk to rotate the desired sector to the disk head
- Minimize seek time
- Seek time ≈ seek distance
- Disk **bandwidth** is the total number of bytes transferred, divided by the total time between the first request for service and the completion of the last transfer

Disk Scheduling (Cont.)


- Several algorithms exist to schedule the servicing of disk I/O requests
- We illustrate them with a request queue (0-199)

98, 183, 37, 122, 14, 124, 65, 67

Head pointer 53

FCFS


Illustration shows total head movement of 640 cylinders



SSTF

- Selects the request with the minimum seek time from the current head position
- SSTF scheduling is a form of SJF scheduling; may cause starvation of some requests
- Illustration shows total head movement of 236 cylinders


SSTF (Cont.)



SCAN

- The disk arm starts at one end of the disk, and moves toward the other end, servicing requests until it gets to the other end of the disk, where the head movement is reversed and servicing continues.
- SCAN algorithm sometimes called the elevator algorithm
- Illustration shows total head movement of 208 cylinders


SCAN (Cont.)



C-SCAN

- Provides a more uniform wait time than SCAN
- The head moves from one end of the disk to the other, servicing requests as it goes
 - When it reaches the other end, however, it immediately returns to the beginning of the disk, without servicing any requests on the return trip
- Treats the cylinders as a circular list that wraps around from the last cylinder to the first one


C-SCAN (Cont.)



C-LOOK

- Version of C-SCAN
- Arm only goes as far as the last request in each direction, then reverses direction immediately, without first going all the way to the end of the disk

C-LOOK (Cont.)




Selecting a Disk-Scheduling Algorithm

- SSTF is common and has a natural appeal.
- SCAN and C-SCAN perform better for systems that place a heavy load on the disk.
- Performance depends on the number and types of requests.
- Requests for disk service can be influenced by the file-allocation method.
- The disk-scheduling algorithm should be written as a separate module of the operating system, allowing it to be replaced with a different algorithm if necessary.
- Either SSTF or LOOK is a reasonable choice for the default algorithm.

Disk Management

- Low-level formatting, or physical formatting Dividing a disk into sectors that the disk controller can read and write
- To use a disk to hold files, the operating system still needs to record its own data structures on the disk
 - Partition the disk into one or more groups of cylinders
 - Logical formatting or "making a file system"
 - To increase efficiency most file systems group blocks into clusters
 - Disk I/O done in blocks
 - File I/O done in clusters
- Boot block initializes system
 - The bootstrap is stored in ROM
 - Bootstrap loader program
- Methods such as sector sparing used to handle bad blocks


Booting from a Disk in Windows 2000



Swap-Space Management

- Swap-space Virtual memory uses disk space as an extension of main memory
- Swap-space can be carved out of the normal file system, or, more commonly, it can be in a separate disk partition
- Swap-space management
 - 4.3BSD allocates swap space when process starts; holds text segment (the program) and data segment
 - Kernel uses swap maps to track swap-space use
 - Solaris 2 allocates swap space only when a page is forced out of physical memory, not when the virtual memory page is first created

Data Structures for Swapping on Linux Systems



Tertiary Storage Devices

- Low cost is the defining characteristic of tertiary storage
- Generally, tertiary storage is built using removable media
- Common examples of removable media are floppy disks and CD-ROMs; other types are available

Removable Disks

- Floppy disk thin flexible disk coated with magnetic material, enclosed in a protective plastic case
 - Most floppies hold about 1 MB; similar technology is used for removable disks that hold more than 1 GB
 - Removable magnetic disks can be nearly as fast as hard disks, but they are at a greater risk of damage from exposure

Removable Disks (Cont.)

- A magneto-optic disk records data on a rigid platter coated with magnetic material.
 - Laser heat is used to amplify a large, weak magnetic field to record a bit.
 - Laser light is also used to read data (Kerr effect).
 - The magneto-optic head flies much farther from the disk surface than a magnetic disk head, and the magnetic material is covered with a protective layer of plastic or glass; resistant to head crashes.
- Optical disks do not use magnetism; they employ special materials that are altered by laser light.

WORM Disks

- The data on read-write disks can be modified over and over.
- WORM ("Write Once, Read Many Times") disks can be written only once.
- Thin aluminum film sandwiched between two glass or plastic platters.
- To write a bit, the drive uses a laser light to burn a small hole through the aluminum; information can be destroyed by not altered.
- Very durable and reliable
- Read-only disks, such ad CD-ROM and DVD, com from the factory with the data pre-recorded.

Tapes

Compared to a disk, a tape is less expensive and holds more data, but random access is much slower.

Tape is an economical medium for purposes that do not require fast random access, e.g., backup copies of disk data, holding huge volumes of data.

Large tape installations typically use robotic tape changers that move tapes between tape drives and storage slots in a tape library stacker – library that holds a few tapes silo – library that holds thousands of tapes

A disk-resident file can be **archived** to tape for low cost storage; the computer can **stage** it back into disk storage for active use.

Operating System Support

- Major OS jobs are to manage physical devices and to present a virtual machine abstraction to applications.
- For hard disks, the OS provides two abstraction:
 - Raw device an array of data blocks
 - File system the OS queues and schedules the interleaved requests from several applications

Application Interface

- Most OSs handle removable disks almost exactly like fixed disks a new cartridge is formatted and an empty file system is generated on the disk.
- Tapes are presented as a raw storage medium, i.e., and application does not not open a file on the tape, it opens the whole tape drive as a raw device.
- Usually the tape drive is reserved for the exclusive use of that application.
- Since the OS does not provide file system services, the application must decide how to use the array of blocks.
- Since every application makes up its own rules for how to organize a tape, a tape full of data can generally only be used by the program that created it.

Tape Drives

The basic operations for a tape drive differ from those of a disk drive.

locate () positions the tape to a specific logical block, not an entire track (corresponds to seek()).

The read position() operation returns the logical block number where the tape head is.

The space () operation enables relative motion.

Tape drives are "append-only" devices; updating a block in the middle of the tape also effectively erases everything beyond that block.

An EOT mark is placed after a block that is written.

File Naming

The issue of naming files on removable media is especially difficult when we want to write data on a removable cartridge on one computer, and then use the cartridge in another computer.

Contemporary OSs generally leave the name space problem unsolved for removable media, and depend on applications and users to figure out how to access and interpret the data.

Some kinds of removable media (e.g., CDs) are so well standardized that all computers use them the same way.

Speed

- Two aspects of speed in tertiary storage are bandwidth and latency.
- Bandwidth is measured in bytes per second.
 - Sustained bandwidth average data rate during a large transfer;
 # of bytes/transfer time
 Data rate when the data stream is actually flowing
 - Effective bandwidth average over the entire I/O time, including seek() or locate(), and cartridge switching
 Drive's overall data rate

Speed (Cont.)

- Access latency amount of time needed to locate data
 - Access time for a disk move the arm to the selected cylinder and wait for the rotational latency; < 35 milliseconds.
 - Access on tape requires winding the tape reels until the selected block reaches the tape head; tens or hundreds of seconds.
 - Generally say that random access within a tape cartridge is about a thousand times slower than random access on disk.
- The low cost of tertiary storage is a result of having many cheap cartridges share a few expensive drives.
- A removable library is best devoted to the storage of infrequently used data, because the library can only satisfy a relatively small number of I/O requests per hour.

Reliability

- A fixed disk drive is likely to be more reliable than a removable disk or tape drive.
- An optical cartridge is likely to be more reliable than a magnetic disk or tape.
- A head crash in a fixed hard disk generally destroys the data, whereas the failure of a tape drive or optical disk drive often leaves the data cartridge unharmed.

Cost


Main memory is much more expensive than disk storage.

The cost per megabyte of hard disk storage is competitive with magnetic tape if only one tape is used per drive.


The cheapest tape drives and the cheapest disk drives have had about the same storage capacity over the years.

Tertiary storage gives a cost savings only when the number of cartridges is considerably larger than the number of drives.

Price per Megabyte of DRAM From 1981 to 2004




Price per Megabyte of Magnetic Hard Disk From 1981 to 2004



Price per Megabyte of a Tape Drive

From 1984-2000



Reference Book

"Operating System Concepts" by Silberchartz, Galvin, Gagne, Wiley India Publications.

