low level

registers

Contents

1	Preamble	1
2	T _E X primitives	1
3	$arepsilon$ -T $_{ m E}$ X primitives	4
4	LuaT _E X primitives	4
5	LuaMetaT _E X primitives	5
6	Units	6

1 Preamble

Registers are sets of variables that are accessed by index and a such resemble registers in a processing unit. You can store a quantity in a register, retrieve it, and also manipulate it.

There is hardly any need to use them in ConTFXt so we keep it simple.

2 T_FX primitives

There are several categories:

- Integers (int): in order to be portable (at the time it surfaced) there are only integers and no floats. The only place where TEX uses floats internally is when glue gets effective which happens in the backend.
- Dimensions (dimen): internally these are just integers but when they are entered they are sliced into two parts so that we have a fractional part. The internal representation is called a scaled point.
- Glue (skip): these are dimensions with a few additional properties: stretch and shrink. Being a compound entity they are stored differently and thereby a bit less efficient than numbers and dimensions.
- Math glue (muskip): this is the same as glue but with a unit that adapts to the current math style properties. It's best to think about them as being relative measures.
- Token lists (toks): these contain a list of tokens coming from the input or coming from a place where they already have been converted.

The original T_{EX} engine had 256 entries per set. The first ten of each set are normally reserved for scratch purposes: the even ones for local use, and the odd ones for global

usage. On top of that macro packages can reserve some for its own use. It was quite easy to reach the maximum but there were tricks around that. This limitation is no longer present in the variants in use today.

Let's set a few dimension registers:

```
\dimen 0 = 10 pt
\dimen2=10pt
\dimen4 10pt
\scratchdimen 10pt
```

We can serialize them with:

```
\the \dimen0
\number \dimen2
\meaning\dimen4
\meaning\scratchdimen
```

The results of these operations are:

```
10.0pt
655360
\dimen4
constant dimension 10.0pt
```

The last two is not really useful but it is what you see when tracing options are set. Here \scratchdimen is a shortcut for a register. This is *not* a macro but a defined register. The low level \dimendef is used for this but in a macro package you should not use that one but the higher level \newdimen macro that uses it.

```
\newdimen\MyDimenA
\def \MyDimenB{\dimen999}
\dimendef\MyDimenC998
\meaning\MyDimenA
\meaning\MyDimenB
\meaning\MyDimenC

Watch the difference:
\dimen267
```

macro:\dimen 999 \dimen998 The first definition uses a yet free register so you won't get a clash. The second one is just a shortcut using a macro and the third one too but again direct shortcut. Try to imagine how the second line gets interpreted:

```
\MyDimenA10pt \MyDimenA10.5pt
\MyDimenB10pt \MyDimenB10.5pt
\MyDimenC10pt \MyDimenC10.5pt
```

Also try to imagine what messing around with \MyDimenC will do when we also have defined a few hundred extra dimensions with \newdimen.

In the case of dimensions the \number primitive will make the register serialize as scaled points without unit sp.

Next we see some of the other registers being assigned:

```
\count 0 = 100
\skip 0 = 10pt plus 3pt minus 2pt
\skip 0 = 10pt plus 1fill
\muskip 0 = 10mu plus 3mu minus 2mu
\muskip 0 = 10mu minus 1 fil
\toks 0 = {hundred}
```

When a number is expected, you can use for instance this:

```
\scratchcounter\scratchcounterone
```

Here we use a few predefined scratch registers. You can also do this:

\scratchcounter\numexpr\scratchcounterone+\scratchcountertwo\relax

There are some quantities that also qualify as number:

```
\chardef\MyChar=123 % refers to character 123 (if present)
\scratchcounter\MyChar
```

In the past using \c was a way to get around the limited number of registers, but it still had (in traditional T_EX) a limitation: you could not go beyond 255. The $\mbox{mathchardef}$ could fo higher as it also encodes a family number and class. This limitation has been lifted in Lua T_EX .

A character itself can also be interpreted as number, in which case it has to be prefixed with a reverse quote: `, so:

\scratchcounter\numexpr`0+5\relax \char\scratchcounter

produces "5" because the `0 expands into the (ascii and utf8) slot 48 which represents the character zero. In this case the next makes more sense:

\char\numexpr\0+5\relax

If you want to know more about all these quantities, "TEX By Topic" provides a good summary of what TEX has to offer, and there is no need to repeat it here.

3 ε -T_EX primitives

Apart from the ability to use expressions, the contribution to registers that ε -T_EX brought was that suddenly we could use upto 65K of them, which is more than enough. The extra registers were not as efficient as the first 256 because they were stored in the hash table, but that was not really a problem. In Omega and later LuaT_EX regular arrays were used, at the cost of more memory which in the meantime has become cheap. As ConT_EXt moved to ε -T_EX rather early its users never had to worry about it.

4 LuaT_EX primitives

The Lua T_EX engine introduced attributes. These are numeric properties that are bound to the nodes that are the result of typesetting operations. They are basically like integer registers but when set their values get bound and when unset they are kind of invisible.

• Attribute (attribute): a numeric property that when set becomes part of the current attribute list that gets assigned to nodes.

Attributes can be used to communicate properties to Lua callbacks. There are several functions available for setting them and querying them.

\arrowvert attribute999 = 123

Using attributes this way is dangerous (of course I can only speak for ConT_EXt) because an attribute value might trigger some action in a callback that gives unwanted side effects. For convenience ConT_EXt provides:

\newattribute\MyAttribute

Which currently defines \MyAttribute as constant integer 1025 and is meant to be used as:1

```
\attribute\MyAttribute = 123
```

Just be aware that defining attributes can have an impact on performance. As you cannot access them at the T_EX end you seldom need them. If you do you can better use the proper more high level definers (not discussed here).

5 LuaMetaT_FX primitives

The fact that scanning stops at a non-number or \relax can be sort of unpredictable which is why in LuaMetaT_FX we also support the following variant:

```
\scratchdimen\dimexpr 10pt + 3pt \relax
\scratchdimen\dimexpr {10pt + 3pt}
```

At the cost of one more token braces can be used as boundaries instead of the single \relax boundary.

An important property of registers is that they can be accessed by a number. This has big consequences for the implementation: they are part of the big memory store and consume dedicated ranges. If we had only named access T_EX 's memory layout could be a bit leaner. In principle we could make the number of registers smaller because any limit on the amount at some point can be an obstacle. It is for that reason that we also have name-only variants:

```
\dimensiondef \MyDimenA 12pt
\integerdef \MyIntegerA 12
\gluespecdef \MyGlueA 12pt + 3pt minus 4pt
\mugluespecdef\MyMuA 12mu + 3mu minus 4mu
```

These are as efficient but not accessible by number but they behave like registers which means that you (can) use \the, \advance, \multiply and \divide with them.² In case you wonder why there is no alternative for \toksdef, there actually are multiple: they are called macros.

todo: expressions

¹ The low level \attributedef command is rather useless in the perspective of ConT_EXt.

² There are also the slightly more efficient \advanceby, \multiplyby and \divideby that don't check for the by keyword.

6 Units

The LuaMeta T_EX engine supports the following units. The first batch is constant with hard coded fine tuned values. The second set is related to the current font. The last group is kind of special, the es is a replacement for the in and has a little sister in ts. The dk is dedicated to the master and makes a nice offset for so called T_EX pages that we use for demos.

```
1.0
pt
              point
bp
     1.00374
              big point (aka postscript point)
    72.26999
in
               inch
    28.45274
               centimeter
cm
     2.84526
              milimeter
mm
dd
        1.07
               didot
     12.8401
              cicero
СС
        12.0
рс
               pica
     0.00002
               scaled points
sp
     0.00002
               pixel
рх
     5.70947
               ex height
ex
               em width
em
        11.0
          1.0
               math unit
mu
     7.11317
ts
               tove
    71.13177
es
               edith
    71.13177
               european unit
eu
dk
     6.43985
               knuth
```

The fi[lll] unit is not really a unit but a multiplier for infinite stretch and shrink; original T_{EX} doesn't have the simple fi.

In addition to these we can have many more. In principle a user can define additional ones but there's always a danger of clashing. For users we reserve the units starting with an u. Here is how you define your own, we show three variants:

```
\newdimension \FooA \FooA 1.23pt
\newdimen \FooB \FooB 12.3pt
\protected\def\FooC {\the\dimexpr\FooA +\FooB\relax}

\pushoverloadmode % just in case
   \newuserunit\FooA ua
   \newuserunit\FooB ub
   \newuserunit\FooC uc
```

\popoverloadmode

```
And this is how they show up:
```

```
2.45999pt 24.6pt 27.06pt
```

with

```
\the\dimexpr 2 ua \relax\quad
\the\dimexpr 2 ub \relax\quad
\the\dimexpr 2 uc \relax
```

The following additional units are predefined (reserved). The values are in points and some depend on the current layout and document font.

```
3.14159 \pi for Mikael
рi
   867.23999 foot for Alan
ft
fs
         11.0 (global body) font size
tw 483.69687 (layout) text width
th 645.88272 (layout) text height
hs
   483.69687 (current) hsize
   645.88272 (current) vsize
٧S
          0.0 (when set) column distance
cd
   483.69687 (when set) column width
CW
    236.34843 combination cell width
     28.45274 user unit (MetaFun)
uu
```

Here is an example of usage:

one	two	three	four
1	2	3	4

The uu can be set by users using the \uunit dimension variable. The default valu sis 1cm. Its current value is also known at the MetaPost end, as demonstrated in figure 1.

```
\startcombination[nx=2,ny=1]
```


```
\startcontent
        \uunit=1cm
        \framed[offset=luu]
            \bgroup
                \startMPcode
                    fill fullcircle scaled 3uu withcolor "red"
                    fill fullcircle scaled 2cm withcolor "green";
                \stopMPcode
            \egroup
    \stopcontent
    \startcaption
        \type {\uunit = 1cm}
    \stopcaption
    \startcontent
        \uunit=1cx
        \framed[offset=.1uu]
            \bgroup
                \startMPcode
                    fill fullcircle scaled .5uu withcolor "red"
                    fill fullcircle scaled 2cm withcolor "green" ;
                \stopMPcode
            \egroup
    \stopcontent
    \startcaption
        \type {\uunit = 1cx}
    \stopcaption
\stopcombination
```

There is one catch here. If you use your own uu as numeric, you might need this:

```
save uu ; numeric uu ; uu := 1cm ;
```

That is: make sure the meaning is restored afterwards and explicitly declare the variable. But this is good practice anyway when you generate multiple graphics using the same MetaPost instance.

9



 $\textbf{Figure 1} \quad \text{Shared user units in $T_E\!X$ and MetaFun.}$

6 Colofon

Author Hans Hagen ConT_EXt 2023.08.15 15:41

LuaMetaT_EX 211.0

Support www.pragma-ade.com

contextgarden.net