

Getting Started Guide

Configure Ping Access Management (PingAM) / ForgeRock Access Management
with LexisNexis IDVerse Nodes

Version 1.0.0
September 2026

Table of Contents

SCOPE	3
Document Organization.....	3
LEXISNEXIS IDVERSE NODES	4
Nodes Compatibility	4
LexisNexis IDVerse Initiate.....	4
Input	5
Configuration Parameters	5
Outputs.....	6
Callbacks	6
Outcomes	6
LexisNexis IDVerse Check.....	7
Input	7
Configuration Parameters	7
Callbacks	8
Outcomes	8
LexisNexis IDVerse Response.....	8
Input	9
Configuration Parameters	9
Outputs.....	9
Callbacks	9
Outcomes	10
NODES INSTALLATION.....	11
DYNAMIC DECISION PLATFORM PORTAL CONFIGURATION	12
Retrieve OrgID and API Key.....	12
Dynamic Decision Platform Portal Policy	13
Enterprise Connector Configuration	13
Policy: IDVerse Transaction Initiate.....	13
Policy: IDVerse Get Results	17
Policy: IDVerse Cancel Transaction	18
AUTHENTICATION TREE CONFIGURATION	21
Authentication Tree: Registration IDVerse	21

SCOPE

LexisNexis IDVerse® is a cutting-edge document authentication and biometric verification solution that will help you confidently approve trusted transactions while detecting deepfakes and forged documents. Powered by state-of-the-art, proprietary AI models and a deep neural network, the IDVerse® solution delivers fully automated authentication of ID documents and verification of ID holders' identities within seconds.

The LexisNexis IDVerse nodes provide the capability for administrators to integrate identity proofing through document verification within Ping Access Management (PingAM), formerly ForgeRock Access Management (AM). This document contains the detailed steps and supporting information required to install and configure an authentication tree using the LexisNexis IDVerse nodes. This guide is intended to install a simple configuration to support testing.

The following are architecture assumptions and limitations:

- PingAM / ForgeRock Access Management server has been previously installed
- PingAM / ForgeRock Access Management server has an Identity Store configured

Document Organization

This document is divided into four sections as follows:

- **Scope.** Defines the purpose of this document.
- **LexisNexis IDVerse Nodes.** Provides an overview of the nodes available for authentication tree integration.
- **LexisNexis Nodes Installation.** Provides information to install the LexisNexis IDVerse nodes upon an on-premise PingAM server.
- **LexisNexis Dynamic Decision Platform Portal.** Provides detailed information regarding the configuration of LexisNexis Dynamic Decision Platform (DDP) to include configuration of a simple policy and how to access configuration parameters required for the authentication tree.
- **Authentication Tree Configuration.** Provides detailed steps to configure an authentication tree with LexisNexis IDVerse Nodes as part of account creation.

LEXISNEXIS IDVERSE NODES

LexisNexis IDVerse® is a cutting-edge document authentication and biometric verification solution that will help you confidently approve trusted transactions while detecting deepfakes and forged documents. Powered by state-of-the-art, proprietary AI models and a deep neural network, the IDVerse® solution delivers fully automated authentication of ID documents and verification of ID holders' identities within seconds.

LexisNexis IDVerse is primarily integrated into the following orchestration journeys:

- New Account Origination to prevent synthetic accounts, as well as validating the account is linked to a physical person with high fidelity.
- Account Management to know who you are doing business with at every step of the journey while maintaining AML/KYC regulations
- Password Reset to validate identity prior to allowing a change.
- Login Multi-Factor Authentication (MFA) for high-risk transactions

To include a LexisNexis IDVerse node in an authentication tree, enter LexisNexis into the Filter nodes to get a listing of available capabilities. For IDVerse, the following nodes are available:

- LexisNexis IDVerse Initiate - This node starts an IDVerse transaction
- LexisNexis IDVerse Check - This node checks the status of a transaction and performs polling until the transaction completes
- LexisNexis IDVerse Response - This node processes the final result of an IDVerse transaction

Nodes Compatibility

Product	Compatible?
Ping Advanced Identity Cloud (PingAIC)	Yes
Ping Access Management (PingAM) (self-managed)	Yes

LexisNexis IDVerse Initiate

The LexisNexis IDVerse Initiate node calls the LexisNexis Dynamic Decision Platform (DDP) Authentication Hub to initiate an IDVerse transaction. The configuration of the nodes work with the configuration of DDP Policy to invoke the IDVerse product. LexisNexis Professional Services (PS) team will configure DDP for IDVerse and assist with the development of the policy. The policy name in DDP will be configured in the node. The node parameter for Delivery Method should match how the DDP Policy is configured, mainly initiating a QR Code, Email, or SMS delivery method to the user. There is no user interface implemented by this node.

Input

The LexisNexis IDVerse Initiate Node retrieves the following from journey shared state based upon the configuration of the Attribute Source parameter.

- **AM Username (username)** - Required in shared state, or `objectAttributes`, to resolve the desired AM identity when the Attribute Source is configured for User Directory.
 - If Delivery Method is `Email`, then the node will fetch the configured the user's email address based on the attribute name configured for email from the AM Identity of the corresponding username.
 - If Delivery Method is `SMS`, then the node will fetch the configured the user's mobile phone number based on the attribute name configured for mobile phone number from the AM Identity of the corresponding username.
- **objectAttributes** - Required when the Attribute Source is configured for Shared State.
 - Must at least include the following user attribute keys:
 - `mail` if using the Email delivery method. The attribute key is a configuration parameter, and the value `mail` is the default.
 - `mobile` if using the SMS delivery method.

Configuration Parameters

The LexisNexis IDVerse Initiate Node has the following configuration parameters:

- **Org ID** - Org ID is the unique id associated with your organization on Dynamic Decision Platform (DDP).
- **API Key** - Defines the unique security API key associated with the Org ID.
- **Base URL** - Defines the domain URL for the DDP region where API Requests are to be sent. The default value is the global region. The URL is relative and should end with "/" character.
- **Policy** - The DDP Portal policy to be used to integrate with IDVerse. The Policy and Delivery Method together should be configured to initiate IDVerse for a specific delivery to the end-user.
- **Service Type** - Defines the API Response output fields returned from the API Request. The default configuration is Authentication Hub, which returns the IDVerse information along with core DDP output API Attributes.
- **Delivery Method** - Defines how the user will receive the initiation of an IDVerse transaction, mainly QR Code, `Email` or `SMS`. The Policy and Delivery Method together should be configured to initiate IDVerse for a specific delivery to the end-user.
- **Attribute Source** - This determines where the LexisNexis IDVerse Initiate node will inspect and gather user parameters to be mapped into the attributes of the IDVerse API Request. This can be configured for User Directory or for Shared State. The attribute source Shared State is typically configured in an orchestration where IDVerse is used for identity proofing for use cases such as new account origination since the user account does not exist. The attribute source User Directory is typically configured in a orchestration where IDVerse is used for identity proofing an individual as part of a login or password reset for second factor of high assurance identity.

- **User Attributes** - Attributes used to fulfill API Request to IDVerse. This includes biometric matching attributes to compare with the data extracted from the user's government identity document if **Validate Biometric Data** configuration is selected. The user attributes must contain email address if Delivery Method is Email, or must contain mobile phone if Delivery Method is SMS.
- **Validate Biometric Data** - If selected, the User Attributes configuration for biometric matching attributes will be compared with the data extracted from the user's government identity document. Valid user attributes include `account_first_name`, `account_last_name` and `account_date_of_birth`. For more information on list of valid biometric matching attributes, refer to the DDP Knowledge Base.
- **Store Initiate API Response** - If selected, the API Response from the IDVerse Initiate API to DDP will be written into shared state. This allows for subsequent nodes in the authentication tree/journey to process the information. For example, a node may read the information to write the data into an offline analysis system.

Outputs

The LexisNexis IDVerse Initiate Node has the following outputs placed into shared state:

- **Delivery Method** - The configured delivery method will be contained in the state variable named `idverse.delivery_method`. This state variable is further used by the LexisNexis IDVerse Check Node to display a user interface while the transaction is in progress.
- **IDVerse Transaction ID** - Upon success of the LexisNexis IDVerse Initiate Node, the IDVerse Transaction ID will be contained in the state variable named `idverse.transaction_id`. This state variable is further used by the LexisNexis IDVerse Check Node and LexisNexis IDVerse Response Node to query for updated IDVerse status.
- **IDVerse QR Code URL** - Upon success of the LexisNexis IDVerse Initiate Node and if the **Delivery Method** is configured as QR Code, then the IDVerse QR Code URL will be contained in the state variable named `idverse.short_url`. This state variable is further used by the LexisNexis IDVerse Check Node to display the QR Code on the user interface.
- **DDP API Response** - Upon success of the LexisNexis IDVerse Initiate Node, and if the **Store Initiate API Response** configuration parameter is selected, then the DDP API Response JSON will be contained in the state variable named `idverse.ddp_api_response`.

Callbacks

The LexisNexis IDVerse Initiate Node does not have any callbacks as there is no user interface displayed.

Outcomes

The LexisNexis IDVerse Initiate Node has the following outcomes:

- **Next** - This outcome is triggered when the API Request returns with success to indicate the IDVerse transaction has been started. The Delivery Method and IDVerse Transaction ID are placed into Shared State, along with optionally including the API Response. The LexisNexis IDVerse Check Node uses the delivery method and transaction ID to check status and generate user interface.

- **Error** - This outcome is triggered when there is a fundamental integration error, or a new bug is discovered. First attempt to fix the integration error by looking at debug log files for the node to determine if the integration error is due to configuration. If the configuration looks accurate, then open a support case with LexisNexis Risk Solutions.

LexisNexis IDVerse Check

This node will query the status of an IDVerse Transaction based on the **Delivery Method** and **IDVerse Transaction ID** stored as state variables in shared state. This node first calls the DDP API for the status of the IDVerse transaction based on the policy defined in DDP to retrieve status. LexisNexis Professional Services (PS) team will configure DDP for IDVerse and assist with the development of the query status policy. The policy name in DDP will be configured in the node. If the check for status policy returns transaction complete, the Next outcome is triggered. Otherwise, user interface processing is invoked that checks for failure conditions (e.g. timeout or cancelled transaction) and builds the user interface if the transaction is in progress.

Input

The LexisNexis IDVerse Check Node retrieves the following from the journey shared state that is used for processing:

- **Delivery Method** - Required in shared state. When the delivery method is QR Code and the user has not started the IDVerse Document Verification process, then the QR code URL contained in the input variable **IDVerse QR Code URL** will be used to build the user interface. Otherwise this state variable has no effect upon the LexisNexis IDVerse Check Node.
- **IDVerse Transaction ID** - Required in shared state. This state variable is used for the DDP API Request for the specific IDVerse Transaction to query for status.
- **IDVerse Short URL** - Required in shared state if the **Delivery Method** is configured for QR Code. This value is used to display the QR Code to the user.

Configuration Parameters

The LexisNexis IDVerse Check Node has the following configuration parameters:

- **Org ID** - Org ID is the unique id associated with your organization on Dynamic Decision Platform (DDP).
- **API Key** - Defines the unique security API key associated with the Org ID.
- **Base URL** - Defines the domain URL for the DDP region where API Requests are to be sent. The default value is the global region. The URL is relative and should end with “/” character.
- **Policy** - The DDP Portal policy to be used to integrate with IDVerse to retrieve status.
- **QR Code Message** - When the delivery method is QR Code, this configuration parameter defines the message that will be displayed with instructions to scan the QR code to begin the identity verification process. When entering the configuration, the key is the locale for the associated value text to display.
- **Polling Message** - This message is displayed while the IDVerse transaction is in progress. When entering the configuration, the key is the locale for the associated value text to display.

- **Polling Timeout (Seconds)** - The period of time (in seconds) to wait for a response to the IDVerse transaction. If no response is received during this time, the node times out and the verification process fails. The node will send a cancel transaction API Request as part of the timeout processing.
- **Polling Wait Time (Seconds)** - The period of time (in seconds) to wait between IDVerse status checks.
- **Cancel Policy** - The DDP Portal policy to be used to send a cancel transaction to IDVerse.

Callbacks

The LexisNexis IDVerse Check Node has the following callbacks:

- When using the QR Code delivery method, the node sends the following callbacks:
 - **TextTextOutputCallback** - Contains the QR Code message.
 - **ScriptTextOutputCallback** - Contains JavaScript script to run to display the QR code.
 - **PollingWaitCallback** - Waits for the user to complete the verification and contains the Waiting message.
- When using the Email or SMS delivery method, the node sends the following callbacks:
 - **PollingWaitCallback** - Waits for the user to complete the verification and contains the Waiting message.

Outcomes

The LexisNexis IDVerse Check Node has the following outcomes:

- **Next** - This outcome is triggered when a completed IDVerse transaction is processed and the user successfully completed the IDVerse evaluation.
- **Failure** - This outcome is triggered when an IDVerse transaction is cancelled or fails.
- **Timeout** - This outcome is triggered when the configured timeout is exceeded and the node did not receive a response indicating the user completed the verification.
- **Error** - This outcome is triggered when there is a fundamental integration error, or a new bug is discovered. First attempt to fix the integration error by looking at debug log files for the node to determine if the integration error is due to configuration. If the configuration looks accurate, then open a support case with LexisNexis Risk Solutions.

LexisNexis IDVerse Response

This node is to be invoked when the LexisNexis IDVerse Check Node completes. The main purpose of this node is to get the final status of the IDVerse user evaluation once the LexisNexis IDVerse Check Node indicates success of a transaction. There is no user interface.

Input

The LexisNexis IDVerse Response Node retrieves the following from the journey shared state that is used for processing:

- **IDVerse Transaction ID** - Required in shared state. This state variable is used for the DDP API Request for the specific IDVerse Transaction to query for the final response.

Configuration Parameters

The LexisNexis IDVerse Response Node has the following configuration parameters:

- **Org ID** - Org ID is the unique id associated with your organization on the Dynamic Decision Platform (DDP)
- **API Key** - Defines the unique security API key associated with the Org ID.
- **Base URL** - Defines the domain URL for the DDP region where API Requests are to be sent. The default value is the global region. The URL is relative and should end with “/” character.
- **Policy** - The DDP Portal policy to be used to integrate with IDVerse to get results for the completion of the transaction.
- **Service Type** - Defines the API Response output fields returned from the API Request. The default configuration is Authentication Hub, which returns the IDVerse information along with core DDP output API Attributes.
- **Store IDVerse Final Response** - If selected, the API Response from the IDVerse Get Results API to DDP will be written into shared state. This allows for subsequent nodes in the authentication tree/journey to process the information. For example, a node may read the information to write the data into an offline analysis system.

Outputs

The LexisNexis IDVerse Response Node has the following outputs placed into shared state:

- **IDVerse API Response** - Upon success of the LexisNexis IDVerse Initiate Node, and if the **Store IDVerse Final Response** configuration parameter is selected, then the IDVerse API Response JSON will be contained in the state variable named `idverse.api_response`.
- **IDVerse Failure Reason** - If the outcome **Failure** is returned by the node, then this output state variable named `idverse.failure_reason` will contain the reason for the failure.

Note: This node clears shared state for the following variables used for a typical journey as these values are not required to be maintained for processing.

- IDVerse Transaction ID contained in state variable `idverse.transaction_id`
- IDVerse Delivery Method contained in state variable `idverse.delivery_method`
- IDVerse QR Code URL contained in state variable `idverse.short_url`

Callbacks

The LexisNexis IDVerse Response Node does not have any callbacks.

Outcomes

The LexisNexis IDVerse Response Node has the following outcomes:

- **Success** - This outcome is triggered when the API Request results in a biometric match and the IDVerse evaluation is passing for Document Check, Document Integrity, Document Image Composition, Document Image Quality, Face Check, and Liveness.
- **Failure** - This outcome is triggered when an IDVerse transaction is cancelled or fails. The output state variable **IDVerse Failure Reason** will contain the reason for the failure.
- **Error** - This outcome is triggered when there is a fundamental integration error, or a new bug is discovered. First attempt to fix the integration error by looking at debug log files for the node to determine if the integration error is due to configuration. If the configuration looks accurate, then open a support case with LexisNexis Risk Solutions.

NODES INSTALLATION

This section describes how to deploy the LexisNexis IDVerse Nodes to PingAM / ForgeRock Access Management hosted on Apache Tomcat. The server will need to be stopped and restarted for the nodes to be properly deployed. This instruction assumes a Apache Tomcat application web server

1. Stop the Tomcat server
2. Remove any previously installed versions of LexisNexis IDVerse Nodes from the server:
Directory: `<install>/tomcat/webapps/openam/WEB-INF/lib`
3. Copy the LexisNexis IDVerse Nodes media as follows:
Filename: `lexisnexis-idverse-1.0.0.jar`
Directory: `<install>/tomcat/webapps/openam/WEB-INF/lib`
4. Restart Tomcat server from command line

If there is an existing authentication tree, be sure to update configuration and validate the workflows.

NOTE: For other web servers, please utilize Ping identity documentation for deployment processes.

DYNAMIC DECISION PLATFORM PORTAL CONFIGURATION


This section defines the high-level LexisNexis Dynamic Decision Platform (DDP) Portal configuration items that will be needed for the overall configuration. There are two main categories of configuration, mainly,

- Organization ID and API Key for the REST API interfaces. This information is needed by the LexisNexis IDVerse Nodes and will be entered as part of configuration.
- LexisNexis DDP Portal Policies. The configured policies within DDP provide the configuration for the Authentication Hub to access IDVerse services. For IDVerse, there are typically three policies needed:
 - IDVerse Initiate
 - IDVerse Get Results
 - IDVerse Cancel


Retrieve OrgID and API Key

To retrieve the DDP Portal values for Organization ID and API Key, perform the following steps.

1. Access **DDP Portal** over the internet by logging into your administrative account with credentials provided by LexisNexis Risk Solutions.
2. From the **DDP Portal** home page, select the user information dropdown that will display username, OrgName and OrgID. This will be the OrgID to enter for the configuration of the LexisNexis IDVerse Nodes.



3. Within the **DDP Portal** home page, select **Admin** followed by selecting the **API Keys** tile. Retrieve the value for API Key. In the event no API Key is listed, select the **Create New API Key** button to generate a new key. This will be the API Key to enter into the configuration of the LexisNexis IIDQA Nodes. The API Key is to be protected. Do not email or keep this value in cleartext on any computer system.



Dynamic Decision Platform Portal Policy

For the purposes of the getting started guide and to have a simple test configuration for different outcomes, the DDP IDVerse policies will be configured to directly integrate without any further policy rules. For IDVerse, there are typically three different policies that should be configured for DDP, mainly:

- IDVerse Transaction Initiate
- IDVerse Get Results from Transaction
- IDVerse Cancel Transaction

The example for the remainder of this quick start guide assumes QR Code as the Delivery Method. The DDP Enterprise Connector Configuration will be established for QR Code (e.g. also known as IDVerse store transaction).

Enterprise Connector Configuration

In order for IDVerse policies to be configured, there are core DDP Enterprise configuration settings that are required to be performed by LexisNexis Risk Solutions professional services, which includes the following **Connector Configurations**:

- **LexisNexis-Connectors Add IDVerse** – This is a first class connector that links to the IDVerse hosted instance. The configuration defines the IDVerse Channel to be used along with flow type and whether or not biometric attributes for matching are to be provided. The purpose of this enterprise configuration is to link DDP to IDVerse for initiating transactions. In the following example, the connector is configured for QP Code delivery method.
- **LexisNexis Connectors IDVerse Response** – This is a first class connector that links to the IDVerse hosted instance to fetch the results from a transaction. The purpose of this configuration is to check status and get final transaction status.
- **LexisNexis Connectors Cancel IDVerse** – This is an external API connector that links to the IDVerse hosted instance to cancel a transaction. This is used for timeout conditions to automatically cancel a transaction.

Policy: IDVerse Transaction Initiate

To initiate a transaction via DDP to IDVerse, there are two policies required, mainly an Authentication Selection policy, and a Standard Policy that starts the transaction. To setup the policies for IDVerse Initiate, perform the following steps.

1. Access **DDP Portal** over the internet by logging into your administrative account with credentials provided by LexisNexis.
2. From the **DDP Portal** home page, select **Policies** from the menu bar. This will provide a listing of available policies. The first step is to select the **Create** dropdown menu followed by **New Policy (Auth Selection)**.

- On the Policy Summary, the **Properties** interface tab will be displayed. Enter the following:

Policy Name IDVerse-QR-Auth-Selection
 Active button Selected
 Auto Initiate Authentication Selected

The screenshot shows the 'Properties' tab of the 'IDVerse-QR-Auth-Selection v2228340' policy. The interface includes a top navigation bar with 'Policies' selected. Below the header, there are tabs for 'Properties', 'Rules', and 'Versions'. The 'Properties' tab is active, showing fields for 'Policy Name' (IDVerse-QR-Auth-Selection), 'Summary' (Enter Summary...), and 'Date Modified' (25 Jul, 2026, 02:26 PM). The 'Workflow Status' is 'Live Saved' and 'Active' is checked. The 'Auto Initiate Authentication' checkbox is also checked, with a note: 'When enabled, authentication will automatically start for the first Auth Selection rule that has all required attributes'. The 'Default Termination' section shows a 'Review' dropdown menu.

- To create the policy rules, select the **Rules** interface tab. The IDVerse-QR-Auth-Selection policy will be a single rule to integrate the IDVerse. From the palette of rule types, drag and drop the **Add IDVerse** rule displayed under Authentication Hub in the rules for the policy.

The screenshot shows the 'Rules' tab of the 'IDVerse-QR-Auth-Selection v2228340' policy. The interface includes a top navigation bar with 'Policies' selected. Below the header, there are tabs for 'Properties', 'Rules', and 'Versions'. The 'Rules' tab is active, showing a table with one rule: 'Add IDVerse' (Rule Type: Add IDVerse, Description: Authentication Hub IDVerse, Risk Weight: 0, Review: Yes). On the right side, there is a palette of rule types categorized under 'Flow Control', 'Additional LexisNexis® Products', 'Integration Hub', and 'Authentication Hub'. The 'Authentication Hub' category is expanded, showing 'Add IDVerse' as one of the available rules.

- Double-click the rule to display the **Authentication Rule Editor**. Within this interface, the **Product Configuration** is the Authentication Hub IDVerse Enterprise Connector Configuration that is established via LexisNexis Risk Solutions Professional Services. The product configuration is for IDVerse to send QR Code as the delivery method.

Add IDVerse Rule Editor

Name *

Add IDVerse

Summary

☒ Generate Reason

☐ Generate Summary Reason

Product Configuration

IDVerse Send QR Code

Credential Attributes:

Credentials Used for authentication

Authentication Credentials

Account Email

Cancel

OK

- Save the Authentication Selection policy.
- From the **Policies** page, select the **Create** dropdown menu followed by **New Policy (Standard)**.
- On the Policy Summary, the **Properties** interface tab will be displayed. Enter the following:

Policy Name IDVerse-QR-Initiate
Active button Selected

LexisNexis®
RISK SOLUTIONS

Dynamic Decision Platform™
Powered by ThreatMetrix®

Forensics LexID Digital Workspace® Reporting **Policies** Cases Lists Jobs Admin ? ?

Policy Summary IDVerse-QR-Initiate v2228343 Policy Templates

Properties Rules Versions

Save

Save as Template

Approval Workflow

Manual Event

Export

Import

Reset

Policy Name

IDVerse-QR-Initiate

Summary

Enter Summary...

Date Modified: 25 Jul, 2026, 02:28 PM

Modified By: ericuythoven@lexisnexisrisk.com

Number of Rules: 1

Workflow Status: **Live Saved**

☒ Active

THRESHOLDS

☐ Cap Overall Score at the Last Rule **New**

Risk Thresholds

High

-100

0

100

-30

Medium

-100

0

100

-20

Low

-100

0

100

-1

Neutral

-100

0

100

0

Status Thresholds

Reject

-100

0

100

-30

Review

-100

0

100

-20

 LexisNexis®
RISK SOLUTIONS

15

- To create the policy rules, select the **Rules** interface tab. The IDVerse-QR-Initiate policy will be a single rule to integrate the IDVerse. From the palette of rule types, drag and drop the **If Then** rule type displayed under Flow Control in the rules for the policy.

The screenshot shows the LexisNexis Dynamic Decision Platform interface. The top navigation bar includes 'Forensics', 'LexID Digital', 'Workspace', 'Reporting', 'Policies', 'Cases', 'Lists', 'Jobs', and 'Admin'. The 'Policies' tab is active, showing a list of policies. The 'IDVerse-QR-Initiate v2228343' policy is selected, and the 'Rules' tab is active. The 'Rules' tab displays a table with columns: NAME (REASON CODE), RULE TYPE, DESCRIPTION, RISK WE..., and RE... The table contains one rule: 'Call IDVerse AS Policy' with rule type 'IF Then' and description 'Conditional statement for flow control'. The logic type is 'OR', and the policy is present. The risk weight is 0, and the review status is 'challenge'. The 'Auth Selection Policy' is 'IDVerse-QR-Auth-Selection'. The sidebar on the right shows a 'Flow Control' palette with options: A-B Testing, Alert, Call Policy, Condition, Date Time Check, Expression Condition, and IF.

- Double-click the rule to display the **Authentication Rule Editor**. Within this interface, the **Authentication Selection** policy is linked to initiate a QR Code IDVerse transaction.

The 'IF Then Rule Editor' dialog box is shown. It has a blue header with the title 'IF Then Rule Editor' and a close button. The form contains the following fields and options:

- Name***: Call IDVerse AS Policy
- Risk Weight**: 0
- Summary**:
 - ☐ Invert
 - ☒ Generate Reason
 - ☐ Generate Summary Reason

Please choose dependent rules by specifying them in the Dependency drop down and/or specify one or more attribute conditions. Multiple conditions can be added by clicking Add Attribute. Dependency refers to any rule located in the policy above this rule which must have triggered.
- Logic Type***: OR
- Dependencies**: (empty dropdown)
- Attribute**: Policy
- Operator**: is present
- Value**: (empty text field)
- Add Attribute**: (button)
- Then**:
 - ☐ Then
 - ☒ Terminate
- Policy Score**: (empty text field)
- Risk Rating**: use calculated
- Review Status**: challenge
- Auth Selection Policy**: IDVerse-QR-Auth-Selection

At the bottom of the dialog are 'Cancel' and 'OK' buttons.

- Consult with LexisNexis professional services for a more comprehensive policy configuration.

Policy: IDVerse Get Results

Once an IDVerse transaction has been initiated, the transaction will continue until one of the following status conditions occurs:

- Timeout
- Cancellation
- Completion

The policy IDVerse Get Results is to inspect the current state of the transaction to determine if a transaction is still in progress or has met a termination status. To setup the IDVerse Get Results policy, perform the following steps.

1. Access **DDP Portal** over the internet by logging into your administrative account with credentials provided by LexisNexis.
2. From the **DDP Portal** home page, select **Policies** from the menu bar. This will provide a listing of available policies. The first step is to select the **Create** dropdown menu followed by **New Policy (Standard)**.
3. On the Policy Summary, the **Properties** interface tab will be displayed. Enter the following:

Policy Name IDVerse-QR-GetResults
Active button Selected

The screenshot shows the LexisNexis Dynamic Decision Platform (DDP) interface. The top navigation bar includes 'Forensics', 'LexID Digital', 'Workspace', 'Reporting', 'Policies', 'Cases', 'Lists', 'Jobs', and 'Admin'. The 'Policies' tab is selected. Below the navigation bar, the 'Policy Summary' tab is active, showing the policy name 'IDVerse-QR-GetResults v2228358' and a 'Policy Templates' link. The 'Properties' tab is selected, displaying the policy details. The 'Policy Name' field contains 'IDVerse-QR-GetResults'. The 'Summary' field contains 'Enter Summary...'. The 'Date Modified' is '25 Jul, 2026, 03:13 PM'. The 'Modified By' is 'eric.uythoven@lexisnexisrisk.com'. The 'Number of Rules' is '1'. The 'Workflow Status' is 'Live Saved'. The 'Active' checkbox is checked. Below the 'Properties' tab, the 'THRESHOLDS' section is visible. It includes a checkbox for 'Cap Overall Score at the Last Rule' (checked) and a '+ New' button. The 'Risk Thresholds' section shows four sliders: 'High' (range -100 to 100, value -30), 'Medium' (range -100 to 100, value -20), 'Low' (range -100 to 100, value -1), and 'Neutral' (range -100 to 100, value 0). The 'Status Thresholds' section shows two sliders: 'Reject' (range -100 to 100, value -30) and 'Review' (range -100 to 100, value -20).

- To create the policy rules, select the **Rules** interface tab. The IDVerse-QR-GetResults policy will be a single rule to integrate the IDVerse. From the palette of rule types, drag and drop the **IDVerse Response** rule displayed under Authentication Hub in the rules for the policy.

- Double-click the rule to display the **Authentication Rule Editor**. Within this interface, the **Product Configuration** is the Authentication Hub IDVerse Enterprise Connector Configuration that is established via LexisNexis Risk Solutions Professional Services. The product configuration is to query IDVerse for the current response and status. This rule will be used in the LexisNexis IDVerse nodes for both polling for status, as well as returning the final response.

Policy: IDVerse Cancel Transaction

The LexisNexis IDVerse nodes have been design with a controllable timeout that can be tuned to meet security policies and requirements for how long a user transaction is allowed. When the timeout occurs, this policy is invoked to cancel the transaction within the DDP IDVerse service. To setup the IDVerse Cancel Transaction policy, perform the following steps.

- Access **DDP Portal** over the internet by logging into your administrative account with credentials provided by LexisNexis.
- From the **DDP Portal** home page, select **Policies** from the menu bar. This will provide a listing of available policies. The first step is to select the **Create** dropdown menu followed by **New Policy (Standard)**.

3. On the Policy Summary, the **Properties** interface tab will be displayed. Enter the following:

Policy Name IDVerse-QR-Cancel
Active button Selected

LexisNexis® RISK SOLUTIONS Dynamic Decision Platform® Powered by ThreatMetrix®

Forensics LexID Digital Workspace Reporting **Policies** Cases Lists Jobs Admin ? ?

Policy Summary IDVerse-Cancel v2228344 Policy Templates

Properties Rules Versions Save Save as Template Approval Workflow Manual Event Export Import Reset

Policy Name
IDVerse-Cancel

Summary
Enter Summary...

Date Modified: 25 Jul, 2026, 02:40 PM
Modified By: eric.uythoven@lexisnexisrisk.com
Number of Rules: 1
Workflow Status: **Live Saved**
☒ Active

THRESHOLDS

☐ Cap Overall Score at the Last Rule **NEW**

Risk Thresholds

High -100 0 100 -30

Medium -100 0 100 -20

Low -100 0 100 -1

Neutral -100 0 100 0

Status Thresholds

Reject -100 0 100 -30

Review -100 0 100 -20

4. To create the policy rules, select the **Rules** interface tab. The IDVerse-QR-Cancel policy will be a single rule to integrate the IDVerse. From the palette of rule types, drag and drop the **External API Call** rule displayed in the rules for the policy.

LexisNexis® RISK SOLUTIONS Dynamic Decision Platform® Powered by ThreatMetrix®

Forensics LexID Digital Workspace Reporting **Policies** Cases Lists Jobs Admin ? ?

Policy Summary IDVerse-Cancel v2228344 Policy Templates

Properties Rules Versions Save Save as Template Approval Workflow Manual Event Export Import Reset

Copy Selected Paste Delete ☐ Show Details

Enter search text... Enter search text...

NAME (REASON CODE)	RULE TYPE	DESCRIPTION	RISK WE...	RE...
External API Call	External API Call	Calls a configured external 3rd party service. Provider: LexisNexis - Connectors; API: IDVerse_Cancel; Timeout: 2000; Invert: No	0	Yes

Flow Control

- A-B Testing
- Alert
- Call Policy
- Condition

5. Double-click the rule to display the **Authentication Rule Editor**. Within this interface, the **Product Configuration** is the Authentication Hub IDVerse Enterprise Connector Configuration that is established via LexisNexis Risk Solutions Professional Services. The product configuration is to query IDVerse for the current response and status. This rule will be used in the LexisNexis IDVerse nodes for both polling for status, as well as returning the final response.

External API Call Rule Editor

Name*

External API Call

Risk Weight

0

Summary

☐ Invert

☒ Generate Reason

☐ Generate Summary Reason

Provider

LexisNexis - Connectors

API

IDVerse_Cancel

Timeout

2000

Product Configuration

IDVerse Cancel

Inputs

transaction tokens

A

IDVerse.Transaction ID

tps_customer_timeout

T

2000

Results

Count of cancelled transactions

Authentication.Custom Output 1

esbx_clone_transaction_id

Authentication.Custom Output 2

status

Authentication.Custom Output 3


Cancel

OK

AUTHENTICATION TREE CONFIGURATION

Authentication Tree: Registration IDVerse

This section provides the steps to configure a PingAM / ForgeRock Authentication Tree with LexisNexis IDVerse nodes from the marketplace. LexisNexis IDVerse Nodes are used for Identity proofing as well as a multi-factor authentication (MFA) of a user. This example depicts a simple orchestration for Account Registration where Identity Verification is performed via the LexisNexis Risk Solutions IDVerse product and node integration. The workflow starts with gathering information from the user to create an account, where information is gathered via the attribute collector node and placed into shared memory. The attributes collected would be driven by customer designed user interface requirements, as well as requirements for the delivery method configured for IDVerse. LexisNexis Risk Solution recommends QR Code for delivery method. LexisNexis IDVerse nodes also provide the Biometric Matching feature which means that attributes such as user's first/last name and date of birth can be compared to the document verified in the IDVerse transaction, which is also considered a best practice. LexisNexis Risk Solutions Professional Services (PS) can advise on the best configuration settings and assist with defining the configuration for the nodes. Once the information for account registration is gathered, then the orchestration of nodes starts with LexisNexis IDVerse Initiate to start the transaction, followed by LexisNexis IDVerse Check to poll and check for completion, followed by LexisNexis IDVerse Response when the status indicates complete.



The flow is as follows:

- Page Node. Gathers information from the user for the purpose of showing how registration identity proofing will operate with LexisNexis IDVerse. Note that this flow is a happy path data flow to get starting using the nodes. More complex use cases involve data mapping and data flow mapping along with IDVerse policy configuration.
- LexisNexis IDVerse Initiate node. The configuration determines whether to pull user parameters from: (i) a user credential store, or (ii) from shared state in the journey/tree. The node then uses the information to generate an API Request and start the IDVerse transaction based on the Delivery Method configured.
- LexisNexis IDVerse Check node. This node will query IDVerse for the current status of the transaction. If the transaction is in progress, the user interface will be generated and displayed to the user, which includes the QR Code if the user has not started the mobile phone portion of the user workflow. Once a transaction has completed, timed out, or been cancelled, the node will return the appropriate outcome.
- LexisNexis IDVerse Response node to get the final transaction response status. The outcome will be returned that represents the status. If the outcome is failure, then the shared variable IDVerse Failure Reason will contain the failure reason.


To configure the Authentication Tree, perform the following to configure the server:

1. From a workstation, launch a browser and enter the following URL:


Example: `https://sso.threatmetrix.com:8443/openam`

NOTE: In this example, communications proceed over the HTTPS protocol to a FQDN (`sso.threatmetrix.com`), over a standard Java web container port number (8443), to a specific deployment URI (`/openam`).


2. Login as Administrator, for example `amadmin` and credentials
3. Upon login, select the **Realms** dropdown menu and click **Top Level Realm**.



4. On the **Realm Overview** display, click the **Authentication Trees** tile.



5. On the **Authentication Trees** display, click the **Create Tree** tile.



6. On the **New Tree** display, enter “Registration-IDVerse” followed by the **Create** button.

7. The result is the **Authentication Trees > Registration-IDVerse** display. This is the interface to build up the authentication policy as a tree depiction showing the nodes in the policy. At this point, the tree will be built by drag-n-drop of Components on the left side of the screen. Each node in the policy will then be configured.
8. Build the Account Creation screen, do the following:
 - On the **Components Filter** on the left side of the interface, enter **page**. When the **Page Node** is displayed as a component, drag and drop it into the authentication tree.
 - When the **Page Node** properties are displayed on the right side of the interface, enter **Account Creation** as the **Node Name**. Optionally the **Header** can be configured with a value such as **Account Registration** and an optional **Description** to describe what the user is required to perform.
 - On the **Components Filter** on the left side of the interface, enter **username**. When the **Username Collector** is displayed as a component, drag and drop the **Username Collector** into the authentication tree into the **Account Creation** page node.
 - On the **Components Filter** on the left side of the interface, enter **attribute**. When the **Attribute Collector** is displayed as a component, drag and drop it into the authentication tree into the **Account Creation** page node.
 - Select the **Attribute Collector** Node component to display the configuration properties on the right side of the interface. All attribute values must be present and viewable in the identity schema for the identity object. Thus, ensure that the user directory is mapped properly for PingIDM. Enter the following property values.

Attributes to Collect	Defines the user parameter mapping from the Attribute Source to IIDQA attributes. For example, givenName, sn birthdate
All Attributes Required	Enabled – This ensures all attributes are collected
Validate Input	Enabled – This validates collected attributes against the validation policies for the specified property
Identity Attribute	username – This ties the information to the username to create if the IDVerse transaction is successful

9. Build the LexisNexis IDVerse Initiate, do the following:

- On the **Components Filter** on the left side of the interface, enter **lexisnexis**. When the **LexisNexis IDVerse Initiate** is displayed as a component, drag and drop it into the authentication tree.
- Select the **LexisNexis IDVerse Initiate** node component to display the configuration properties on the right side of the interface. Enter the following property values.

Org ID	<ENTER ORG ID FROM DDP PORTAL>
API Key	<ENTER API KEY FROM DDP PORTAL>
Policy	<ENTER THE POLICY NAME AS CONFIGURED IN DDP PORTAL> For example: IDVerse-QR-Initiate
Base URL	https://h-api.online-metrix.net/
Service Type	Authentication Hub
Delivery Method	QR Code
Attribute Source	Shared State
User Attributes	Defines the user parameter mapping from the Attribute Source to IDVerse API Request attributes. For example, Key =account_first_name, Value =givenName, Key =account_last_name, Value =sn Key =account_date_of_birth, Value =birthdate
Validate Biometric Data	Enabled
Store API Response	Not Enabled

Note: The example journey here assumes QR Code for the IDVerse delivery method. The Enterprise Connector Configuration and associated Policy configuration in this document also assumes QR Code delivery method will be configured. When the configuration Validate Biometric Data is enabled, the Enterprise Connector Configuration to IDVerse will also be enabled to pass the data for validation.

Note: The toggle for Attribute Source allows flexibility in the journey/tree. This determines where the IDVerse Initiate node will inspect and gather user parameters to be mapped into the attributes of the DDP API Request to start an IDVerse transaction. This can be configured for User Directory or from Shared State. User Directory is typically configured in an orchestration where IDVerse is used for Multi-Factor Authentication (MFA) since the information for the user should be in the directory. The Shared State specification is typically configured in an orchestration where IDVerse is used for identity proofing for use cases such as new account origination since the user account does not exist.

Note: The Attribute List defines a mapping of user parameters to IDVerse attributes used for Biometric validation. The values should match the types of government documents anticipated as part of the document verification and identity proofing. For example first name, last name and date of birth.

The user parameters will be fetched based on the Attribute Source.

Note: If the **Store Initiate API Response** configuration parameter is selected, then the DDP API Response JSON will be contained in the state variable named `idverse.ddp_api_response`.

10. Build the LexisNexis IDVerse Check, do the following:

- The LexisNexis IDVerse Check node may optionally be placed into a Page Node container for additional heading and messaging, or as a standalone node. This decision is up to the administrator.
- On the **Components Filter** on the left side of the interface, enter **lexisnexis**. When the **LexisNexis IDVerse Check** is displayed as a component, drag and drop it into the authentication tree.
- Select the **LexisNexis IDVerse Check** Node component to display the configuration properties on the right side of the interface. Enter the following property values.

Org ID	<ENTER ORG ID FROM DDP PORTAL>
API Key	<ENTER API KEY FROM DDP PORTAL>
Policy	<ENTER THE POLICY NAME AS CONFIGURED IN DDP PORTAL> For example: IDVerse-QR-GetResponse
Base URL	https://h-api.online-metrix.net/
QR Code Message	Leave Blank
Polling Message	QR Code
Polling Timeout (Seconds)	600
Polling Wait Time (Seconds)	8
Cancel Policy	<ENTER THE POLICY NAME AS CONFIGURED IN DDP PORTAL> For example: IDVerse-Cancel

Note: When left blank, the configuration parameter QR Code Message by default uses English to display the message “Scan the QR code to initiate the identity verification process.”

To define a specific message, add the text per locale for internationalization. This only displays when the QR Code delivery method is selected, as well as only displays until the user activates the IDVerse process on their mobile phone. Enter the key value as the locale, and enter the value for the text to display to the user.

Note: The polling message is displayed while the IDVerse transaction is in progress. When left blank, the configuration parameter QR Code Message by default uses English to display the message “Waiting for identity verification completion.”

To define a specific message, add the text per locale for internationalization. Enter the key value as the locale, and enter the value for the text to display to the user.

Note: The polling time out is the maximum time allowed for the user to complete the IDVerse transaction. By default, the configuration is set to 600 seconds (10 minutes). The polling wait time is set to 8 seconds which is the time elapsed between status checks where a DDP API Request is sent to determine the current status of an IDVerse transaction.

When the elapsed time exceeds the polling timeout, the Cancel Policy is invoked to cancel the transaction within the IDVerse service.

11. Build the LexisNexis IDVerse Response, do the following:

- On the **Components Filter** on the left side of the interface, enter **lexisnexis**. When the **LexisNexis IDVerse Response** is displayed as a component, drag and drop it into the authentication tree.
- Select the **LexisNexis IDVerse Response** node component to display the configuration properties on the right side of the interface. Enter the following property values.

Org ID	<ENTER ORG ID FROM DDP PORTAL>
API Key	<ENTER API KEY FROM DDP PORTAL>
Policy	<ENTER THE POLICY NAME AS CONFIGURED IN DDP PORTAL> For example: IDVerse-QR-GetResponse
Base URL	https://h-api.online-metrix.net/
Service Type	Authentication Hub
Store API Response	Not Enabled

Note: If the **Store API Response** configuration parameter is selected, then the IDVerse API Response JSON will be contained in the state variable named `idverse.api_response`.

12. Link together the nodes of the authentication tree

Note: This example authentication tree is meant to provide a starting point for integration. The orchestration here collects attributes, initiates the IDVerse transaction while passing those attributes to the LexisNexis Risk Solutions IDVerse product. The final get response node will return the final status of the IDVerse transaction to include whether or not the provided biometric attributes match the users document presented for identity verification.