| Module 4: MySQL Manage Table | | | | |
|---|--|--|--|--|
| Alter command: | | | | |
| 1) to add column to table: | | | | |
| ☐ To add column: | | | | |
| → □ ALTER | | | | |
| □ ADD | | | | |
| ☐ To add multiple columns: | | | | |
| ☐ ALTER TABLE table_name | | | | |
| ☐ ADD [COLUMN] column_name1 data_type, | | | | |
| □ ADD [COLUMN] column_name2 data_type; | | | | |
| ☐ To add column to first position: | | | | |
| ☐ ALTER TABLE table_name | | | | |
| □ ADD [COLUMN] column_name data_type FIRST; | | | | |
| ☐ To add column after particular column: | | | | |
| ☐ ALTER TABLE table_name | | | | |
| ADD [COLUMN] column_name data_type AFTER exisiting_column_name; | | | | |
| 2) to change datatype: To change a columns datatype: ALTER TABLE table_name MODIFY To change multiple columns datatype: ALTER TABLE table_name MODIFY existing_col_name_1 new_datatype, MODIFY existing_col_name_2 new_datatype; Note: MySQL wont allow us to change a column's datatype if that change would cause the data to be lost. | | | | |
| 3) to change column attributes: | | | | |
| ☐ To change column attributes: | | | | |
| ☐ ALTER TABLE table_name | | | | |
| ☐ MODIFY existing_col_name datatype column_attributes; | | | | |
| ☐ To change multiple column attributes: | | | | |
| ☐ ALTER TABLE table_name | | | | |
| MODIFY existing_col_name_1 datatype column_attributes;MODIFY existing_col_name_2 datatype column_attributes; | | | | |
| ■ Note: MySQL wont allow us to change a column if that change would cause the data | | | | |
| to be lost. | | | | |
| | | | | |
| Module 4 – MySQL Manage Table MySQL Notes prepared by Kamal Sir M4-1 | | | | |

| 4) to renome a column. | | | |
|--|--|------|--|
| 4) to rename a column: | | | |
| ☐ ALTER TABLE table_n | ame | | |
| → □ CHANGE | ane | | |
| ☐ To rename multiple columns: | | | |
| ☐ ALTER TABLE table_n | | | |
| | ne_1 new_col_name_1 datatype, | | |
| | ne_2 new_col_name_2 datatype; | | |
| 5) to drop a column: | | . \$ | |
| ☐ To drop a column: | (| | |
| ☐ ALTER TABLE table_n | ame | 11. | |
| ☐ DROP existing_col_na | | | |
| ☐ To drop multiple columns: | | | |
| ☐ ALTER TABLE table_n | ame | | |
| DROP existing_col_na | ame_1, | | |
| DROP existing_col_na | ame_2; | | |
| ☐ Note: a column cannot be dr | opped if it's the only column in the table. | | |
| | | | |
| ALTER – MCQs | | | |
| Q1) consider a table tab1 with one | column a. | | |
| Which of the following command w Options: | vill add a column b to the above table. | | |
| A. alter tab1 add column | b varchar(10); | | |
| B. alter table tab1 add co | olumn b varchar(10); | | |
| C. alter table tab1 add b | column varchar(10); | | |
| D. alter tab1 add b varch | 20 A CONTRACTOR OF THE CONTRAC | | |
| Solution: | (10)) | | |
| JOHN LOW THE PROPERTY OF THE P | | | |
| Q2) consider a table tab1 with two | | | |
| What will the result of following co | mmand? | | |
| alter table tab1 add c int first, | | | |
| add d char(10) first, | | | |
| add e tinyint(2) after a; | | | |
| Options: | | | |
| A. table will have 5 colur | | | |
| B. table will have 4 colun | nns: d , a, e and b | | |
| C. table will have 5 colun | nns: d, c, a, e and b | | |
| D. error. | | | |
| Solution: | | | |
| | | | |
| Module 4 – MySQL Manage Table | MySQL Notes prepared by Kamal Sir | M4-2 | |

Q3) consider a table tab2 with one column a - int.

Which of the following command can change the datatype of column a to varchar(10).

Options:

- A. modify table tab2 modify a varchar(10);
- B. alter table tab2 modify a varchar(10);
- C. change table tab2 modify a varchar(10);
- D. alter table tab2 modify a int a varchar(10);

Solution:

Q4) consider a table tab2 with one column a - varchar(10);

Which of the following command can change the datatype of column a to int

Options:

- A. alter table tab2 change a varchar(10) a int;
- B. alter table tab2 modify a a int;
- C. change table tab2 alter a a int;
- D. alter table tab2 change a a int;

Solution:

Q5) consider a table with two columns a - int and b - int.

Which of the following command can be used to drop column a from the table?

Options:

- A. modify table tab2 drop a;
- B. alter table tab2 delete a;
- C. alter table tab2 drop a;
- D. alter tab2 drop a;

Solution:

Q6) consider a table with one column b - int.

Which of the following command can be used to drop column a from the table? Options:

- A. it cannot be dropped.
- B. alter table tab2 drop a;
- C. alter table tab2 delete a;
- D. alter tab2 drop a;

Solution:

| Truncate, Rena | ame and Drop Command: | |
|--|---|---------------|
| Truncate a Table: ☐ TRUNCATE TABLE statement can deleting the column definitions ☐ TRUNCATE TABLE cannot be use ☐ The syntax is: ☐ TRUNCATE | | able without |
| reset the sequence. | CATE statement is optional. TO_INCREMENT column, then TRUNCATI int in another table refers to this table th | |
| | sed for renaming an existing table. se the name of a table without modifying tored in the table. | its column |
| definition of the table, includin table. | to delete all the data from the table along the constraints, triggers, views and inconstraints to this table then the | lexes for the |
| Module 4 – MySQL Manage Table | MySQL Notes prepared by Kamal Sir | M4-4 |

T,R and D- MCQs

Q1) consider a table tab2 with one column b - int.

Which of the following command can be used to rename the table to tab3.

Options:

- A. it cannot be renamed.
- B. rename table tab2 to tab3;
- C. rename table tab2 to table tab3;
- D. change table tab2 to tab3;

Solution:

Q2) consider a database cric_db with two tables.

Which of the following command can be used to rename the database to cricket_info.

Options:

- A. it cannot be renamed.
- B. rename database cric_db to cricket_info;
- C. rename cric_db to cricket_info;
- D. change database cric_db to cricket_info;

Solution:

Q3) consider a table tab4 with one column b - int.

Which of the following command can be used to truncate the table.

Options:

- A. it cannot be truncated.
- B. truncate table tab4;
- C. drop table tab4;
- D. truncate tab4 table;

Solution:

Q4) consider a table tab4 with one column b - int.

Which of the following command can be used to drop the table.

Options:

- A. drop table tab4;
- B. drop tab4;
- C. table cannot be dropped as it has only one column.
- D. delete table tab4;

Solution: