



cFS Basecamp Hello World Coding Lessons



Version 1.10
December 2023



Introduction



- These slides provide guidance for doing the Hello World coding tutorial exercises
- The "Hello App Designs" section in Basecamp's *Application Developer's Guide* provides design information for all of Hello App coding tutorials
 - Having all of the design information in one place makes the developer's guide flow better
 - It should be used in conjunction with this guide
- The Hello World app template creates a minimal cFS application
 - The application design follows the Basecamp app design conventions as described in the developer's guide
 - The coding exercises introduce developer's to the different app components

Prerequisites

- Working knowledge of the C programming language
- Familiarity with Basecamp's GUI operations covered by the built-in introduction tutorial
- Basic understanding of flight software context, the cFS architecture, and the cFS Application Developer's Guide and Basecamp's Application Developer's Guide



Hello World Operations (1 of 3)



- Start the cFS target using the cFS <Start> button
 - Scroll up in the cFS Target Process Window and you should see the following two event messages that indicate the Hello World app successfully started

```
CFS Target Process Window Telecommand: 127.0.0.1:1234 Telemetry: Local Time: 1001055

EVS PORT 66/1/PL_SIM 100: PL_SIM App Initialized. Version 1.0.0

EVS Port1 66/1/PL_MGR 4: JSON initialization file successfully processed with 11 parameters EVS Port1 66/1/PL_MGR 100: PL_MGR App Initialized. Version 1.0.0

EVS Port1 66/1/HELLO 4: JSON initialization file successfully processed with 7 parameters EVS Port1 66/1/HELLO 100: HELLO App Initialized. Version 1.0.0

EVS Port1 66/1/KIT_SCH 300: Message Table load updated 23 entries
```

- Use the File Browser to download hello_ini.json and open it in the text editor
 - Note the TOPICID values are populated when "make topicids" is executed

```
"title": "Hello initialization file",
  "description": ["Define runtime configurations"],
  "config": {

    "APP_CFE_NAME": "HELLO",
    "APP_PERF_ID": 127,

    "APP_CMD_PIPE_DEPTH": 5,
    "APP_CMD_PIPE_NAME": "HELLO_CMD",

    "HELLO_CMD_TOPICID": 6247,
    "BC_SCH_4_SEC_TOPICID": 6228,
    "HELLO_HK_TLM_TOPICID": 2163
}
}
```




Hello World Operations (2 of 3)



Open the Hello World status telemetry message

It only contains the valid and invalid command counters



Status telemetry is sent every 4 seconds

- The app subscribes to receive the Scheduler App's 4 sec message BC SCH 4 SEC TOPICID
- BC_SCH_4_SEC_TOPICID is a parameter in the JSON init file so it can be referenced by the app



Hello World Operations (3 of 3)



Issue multiple Hello World Noop commands

Note the Quick Cmd menu includes a "Noop/Reset App" entry that may be more convenient than Send Cmd



- Issue a Hello World Reset App command to clear the command counters
 - Note Basecamp's convention is to have the reset command clear the command counters and then the counter increments to 1 because the reset command was successful






Lesson 1 – Add a Command (1 of 3)



Objectives

- Learn how to define commands using Electronic Data Sheets
- Learn how to use APP_C_FW's Command Manager utility for registering and dispatching commands



Typically new commands would not be added to the main app file because in Basecamp's object-based design strategy new commands would be part of an object owned by the main app. It is being done here to tech the objectives while keeping the app structure simple.



Lesson 1 – Add a Command (2 of 3)



hello.xml

- The new command is defined in two parts
- The SetParam_CmdPayload defines the command parameter
 - The Developer's Guide explains the naming convention
 - BASETYPES is an EDS package defined in the cFE EDS specs
- APP_C_FW/APP_BASE_CC is the starting Command Code for apps
 - The Noop and Reset commands are in every app so the framework defines their command codes

hello_app.h

- The new command requires a new event message identifier and by convention the macros names end in _EID
- XXX_SetParamCmd() definition must follow the APP_C_FW Command Manager requirements

hello_app.c

- The const *CmdPayload definition in XXX*CmdPayload() is a coding idiom that makes accessing command parameters easy and consistent
- CMDMGR_RegisterFunc() registers the command processing function which is invoked because of the call to CMDMGR_DispatchFunc() in ProcessCommands()




Lesson 1 – Add a Command (3 of 3)



Verification

- 1. Use the main screen's cFS Build button to build the target (only existing files changed)
- 2. Since the EDS was modified, the GUI, must be restarted to use the new command
- 3. Verify the new code by sending the new command, observing the event message and valid command counter

Telecommand






Lesson 2 – Add Telemetry Data Point (1 of 3)



Objectives

- Learn how to define telemetry messages using Electronic Data Sheets
- Introduce how telemetry messages are managed in a Basecamp app

The following files are modified in this lesson





Lesson 2 – Add Telemetry Data Point (2 of 3)



hello.xml

Since the StatusTIm_Payload container type already exists, this change only requires a new entry

hello_app.h

- A new variable needs to be added to save the command parameter so it can be sent in telemetry
- This variable is added to the hello world app's object data
- As mentioned in lesson one, this new command would typically be part of an object owned by the main app and it is being done here to keep the exercise simple

hello_app.c

- The XXX_SetParamCmd() function needs to be modified to save the parameter value
- The SendStatusTlm() needs to be modified to copy the command parameter into the telemetry packet




Lesson 2 – Add Telemetry Data Point (3 of 3)



Verification

- 1. Use the main screen's cFS Build button to build the target (only existing files changed)
- 2. Since the EDS was modified, the GUI ,must be restarted to use the new telemetry
- Verify the new code by sending the set parameter command and observing the telemetry is updated with the commanded value






Lesson 3 – Rename JSON Init Parameter (1 of 3)



Objectives

- Introduce Basecamp's app parameter initialization JSON files
- Learn how init parameters are defined and accessed

The following files are modified in this lesson





Lesson 3 – Rename JSON Init Parameter (2 of 3)



cpu1_hello_wrld.ini

- Changing the APP_CMD_PIPE_DEPTH parameter name does not effect the how the parameter is used
- The value of 7 is chosen because it is not used by any other apps and will be used as part of the verification
- During the target build process this file is copied from basecamp_defs to the build/exe/cpu1/cf and the 'cpu1_' prefix is removed from the filename

app_cfg.h

- This JSON initialization file parameter names are defined in this file, block comment has detailed instructions
- Initialization parameters can either by of type string or integer

hello_app.c

- The initialization parameters values are retrieved using either the INITBL_GetIntConfig() or INITBL_GetStrConfig() functions
- APP_CMD_PIPE_MAX is used in the CFE_SB_CreatePipe() call and defines the maximum number of packets that
 can be on the pipe




Lesson 3 – Rename JSON Init Parameter (3 of 3)



Verification

- 1. The Software Bus Stats telemetry message will be used to indirectly verify the initialization parameter
- 2. Open SB's STATS TLM using the "View Tlm" drop down menu
- 3. Issue a SendSbStatsCmd which causes SB to send one STATS_TLM message. Scroll down until you find an app with a MaxQueueDepth of 7 which implies this is the Hello World app. You can change the parameter value again and follow these steps to verify you find an app with the expected value.





Telemetry

```
View TIm: -- Telemetry Topic --

-- Telemetry Topic --

CFE_ES/Application/HK_TLM

CFE_ES/Application/APP_TLM

CFE_ES/Application/MEMSTATS_TLM

CFE_EVS/Application/HK_TLM

CFE_EVS/Application/SHORT_EVENT_MSG

CFE_EVS/Application/LONG_EVENT_MSG

CFE_SB/Application/HK_TLM

CFE_SB/Application/STATS_TLM

CFE_SB/Application/STATS_TLM

CFE_SB/Application/STATS_TLM

CFE_SB/Application/ALLSUBS_TLM
```

StatsTlm.Payload.PipeDepthStats[6].PipeId.BaseType : 34996231
StatsTlm.Payload.PipeDepthStats[6].MaxQueueDepth : 7
StatsTlm.Payload.PipeDepthStats[6].CurrentQueueDepth : 0
StatsTlm.Payload.PipeDepthStats[6].PeakQueueDepth : 1