Advanced Operating Systems
MS degree in Computer Engineering
University of Rome Tor Vergata
Lecturer: Francesco Quaglia

Linux modules

- 1. Support system calls and services
- 2. Programming facilities
- 3. Kernel probing

Modules basics


- A LINUX module is a software component which can be added as part of the kernel (hence being included into the kernel memory image) when the latter is already running
- One advantage of using modules is that the kernel does not need to be recompiled in order to add the corresponding software facility
- Modules are also used as a base technology for developing new parts of the kernel that are then integrated (once stable) in the original compiled image
- They are also used to tailor the start-up of a kernel configuration, depending on specific needs

Steps for module insertion

- We need memory for loading in RAM both code blocks and data structures included in the module
- We need to know where the corresponding logical buffer is located in order to resolve internal references by the module (to either data or code)
- We need to know where in logical memory are located the kernel facilities the module relies on
- While loading the module, actual manipulation for symbols resolution (to addresses) needs to be carried out

A scheme

Kernel image



Who does the job??

- It depends on the kernel release
- Up to kernel 2.4 most of the job (but not all) is done at application level
 - ✓ A module is a **.o** ELF
 - ✓ Shell commands are used to reserve memory, <u>resolve</u> the symbols' addresses and load the module in RAM
- From kernel 2.6 most of the job is kernel-internal
 - ✓ A module is a .ko ELF
 - ✓ Shell commands are used to trigger the kernel actions for memory allocation, <u>address resolving</u> and module loading

System call suite up to kernel 2.4

create module

- ✓ reserves the logical kernel buffer
- ✓ associates a name to the buffer

init module

- ✓ loads the finalized module image into the kernel buffer
- ✓ calls the module setup function

delete module

- ✓ calls the module shutdown function
- ✓ releases the logical memory buffer

System call suite from kernel 2.6

create module

✓ no more supported

init_module

- ✓ reserves the logical kernel buffer
- ✓ associates a name to the buffer
- ✓ loads the non-finalized module image into the kernel buffer
- ✓ calls the module setup function

delete module

- ✓ calls the module shutdown function
- ✓ releases the logical memory buffer

Common parts (i)

- A module is featured by two main functions which indicate the actions to be executed upon <u>loading</u> or <u>unloading</u> the module
- These two functions have the following prototypes

Common parts (ii)

- Within the metadata that are used to handle a module we have a so called <u>usage-count</u> (or reference-count)
- If the usage-count is not set to zero, then the module is so called "locked"
- This means that we can expect that some thread will eventually need to used the module stuff (either in process context or in interrupt context), e.g. for task finalization purposes
- Unload in this case fails, except if explicitly forced
- If the usage-count is set to zero, the module is unlocked, and can be unloaded with no particular care (or force command)

Common parts (iii)

- We can pass parameters two modules in both technologies
- These are not passed as actual function parameters
- Rather, they are passed as initial values of global variables appearing in the module source code
- These variables, after being declared, need to be marked as "module parameters" explicitly

Declaration of module parameters

- For any parameter to be provided in input we need to rely on the below macros defined in include/linux/module.h or include/linux/moduleparm.h
 - ✓ MODULE_PARM(variable, type)(old style)
 - ✓ module param(variable, type, perm)
- These macros specify the name of the global variable to be treated as input parameter and the corresponding data type ("i" int "l" long "s" string "b" byte etc.)
- The three-parameter version is used in order to expose the variable value as a pseudo-file content (hence we need to specify permissions)

Module parameters dynamic audit

- It can be done via the /sys pseudo-file system
- It is an aside one with respect to /proc
- In /sys for each module we find pseudo-files for inspecting the state of the module
- These include files for all the module parameters that are declared as accessible (on the basis of the permission mask) in the pseudo file system
- We can even modify the parameters at run-time, if permissions allow it

A variant for array arguments

- module_param_array() can be used to declare the presence of parameters that are array of values
- this macro takes in input 4 parameters
 - ✓ The array-variable name
 - ✓ The base type of an array element
 - ✓ The address of a variable that will specify the array size
 - ✓ The permission for the access to the module parameter on the pseudo file system

An example

```
module_param_array(myintarray,int,&size,0)
```

Loading/unloading a module

- A module can be loaded by the administrator via the shell command insmod
- You an use this also for passing parameters (in the for variable=value)
- This command takes the name of the object file generated by compiling the module source code as the parameter
- The unloading of a module can be executed via the shell command rmmod
- We can also use modprobe, which by default looks for the actual module in the directory /lib/modules/'uname -r'

Actual execution path of insmod

Up to kernel 2.4

insmod /

create_module

init_module

Relocate module (exploiting symtab, e.g. exposed via /proc/ksyms)

since kernel 2.6

insmod

init_module

Module suited system calls – up to 2.4

```
#include <linux/module.h>
caddr_t create_module(const char *name,
size_t size);
```

DESCRIPTION

create_module attempts to create a loadable module entry and reserve the kernel memory that will be needed to hold the module. This system call is only open to the superuser.

RETURN VALUE

On success, returns the kernel address at which the module will reside. On error -1 is returned and errno is set appropriately.

```
#include <linux/module.h>
int init_module(const char *name, struct module
*image);
```

DESCRIPTION

init_module **loads the relocated module** image into kernel space and runs the module's init function. The module image begins with a module structure and is followed by code and data as appropri ate. The module structure is defined as follows:

```
struct module {
    unsigned long size_of_struct;
    struct module *next; const char *name;
    unsigned long size; long usecount;
    unsigned long flags; unsigned int nsyms;
    unsigned int ndeps; struct module_symbol *syms;
    struct module_ref *deps; struct module_ref *refs;
    int (*init) (void); void (*cleanup) (void);
    const struct exception_table_entry *ex_table_start;
    const struct exception_table_entry *ex_table_end;
    #ifdef __alpha__
        unsigned long gp;
    #endif
};
```

In the 2.4 tool chain parameters are setup by the insmod user program

In fact their existence is not reflected into any module-suited system call signature

They cannot be changed at run-time from external module stuff (except if we hack their memory locations)

```
#include <linux/module.h>
int delete_module(const char *name);
```

DESCRIPTION

delete_module attempts to remove an unused loadable module entry. If name is NULL, all unused modules marked auto-clean will be removed. This system call is only open to the superuser.

RETURN VALUE

On success, zero is returned. On error, -1 is returned and errno is set appropriately.

Module suited system calls – since 2.6

SYNOPSIS

Note: glibc provides no header file declaration of init_module() and no wrapper function for finit_module(); see NOTES.

DESCRIPTION

init_module() loads an ELF image into kernel space, performs any necessary symbol relocations, initializes module parameters to values provided by the caller, and then runs the module's init function. This system call requires privilege.

The module_image argument points to a buffer containing the binary image to be loaded; len specifies the size of that buffer. The module image should be a valid ELF image, built for the running kernel.

What about the missing address resolution job by insmod in the 2.6 tool-chain?

- To make a .ko file, we start with a regular .o file.
- The **modpost** program creates (from the .o file) a C source file that describes the additional sections that are required for the .ko file
- The C file is called .mod file
- The .mod file is compiled and linked with the original .o file to make a .ko file

Module headings

```
For inclusion of header files with pre-processor
                           directive ifdef
                                         KERNEL
                               For inclusion of header files with
   #define
                KERNEL
                               Pre-processor directive ifdef MODULE
   #define MOD
  #include <linux/module.h>
   #include <linux/kernel.h>
#define SMP /* if compiled for SMP
```

Module in-use indications (classical style)

- The LINUX kernel associated with any loaded module a counter
- Typically, this counter is used to indicate how many processes/threads/top-bottom-halves still need to rely on the module software for finalizing some job
- In case the counter is currently greater than zero, the unload of the module will fail
- There are macros defined in include/linux/module.h, which are suited for accessing/manipulating the counter
 - >MOD INC USE COUNT
 - >MOD DEC USE COUNT
 - >MOD_IN_USE

• NOTE:

➤ While debugging the module it would be convenient to redefine the macros MOD_INC_USE_COUNT and MOD_DEC_USE_COUNT as no-ops, so to avoid blocking scenarios when attempting to unload the module

• NOTE:

➤ the proc file system exposes a proper file /proc/modules which provides information on any loaded module, including the usage counter and the amount of memory reserved for the module

Reference counter interface in 2.6

We have the following functions:

- ✓ <u>try_module_get(struct module *module)</u>
 for incrementing the reference counter
- ✓ module_put(struct module *module) for decrementing the reference counter
- ✓ CONFIG_MODULE_UNLOAD can be used to check unloadability

Finding a module to lock/unlock

struct module *find_module(const char *name)

This provides us with capabilities of targeting an "external" module

The macro THIS_MODULE passed in input can be used to identify the module that is calling the API, it clearly works also with try_module_lock/module_put

Kernel exported symbols

- Either the LINUX kernel or its modules can export symbols
- An exported symbol (e.g., the name of a variable or the name of a function) is made available and can be referenced by any module to be loaded
- If a module references a symbol which is not exported, then the loading of the module will fail
- The Kernel (including the modules) can export symbols by relying on the macro EXPORT_SYMBOL (symbol) which is defined in include/linux/module.h
- **NOTE** (for old style management)
 - ➤ If a module exports symbols it must rely on the pre-processor directive specified by the macro EXPORT_SYMTAB, to be inserted right before including include/linux/module.h
 - ➤ In case no symbol is exported by the module, then it is common practice to indicate this to the pre-processor by exploiting the macro EXPORT NO SYMBOLS

Exported symbols table

- There exist a table including all the symbols that are exported by the compiled kernel
- Further, each module is associated with a per module table of exported symbols (if any)
- All the symbols that are currently exported by the kernel (and by its modules) are accessible via the **proc file system** through the file /proc/ksyms
- This file keeps a line for each exported symbol, which has the following format
 - Kernel-memory-address symbol-name
- More recently the /proc/kallsyms file has been used, also exposing the symbol type

A note on exporting symbols

• kernel can be parameterized (compiled) to export differentiated types of symbols via standard facilities (e.g. /proc/kallsyms)

A few examples

```
CONFIG_KALLSYMS = y
CONFIG_KALLSYMS_ALL = y symbol table includes all the variables (including EXPORT_SYMBOL derived variables)
```

All the previous are required for exporting variables (not located in the stack)

Dynamic symbols querying and kernel patching

```
int __kprobes register_kprobe(struct kprobe *p)
static int __kprobes __unregister_kprobe_top(struct kprobe *p)
int __kprobes register_kretprobe(struct kprobe *p)

To enable kprobes: CONFIG_KPROBES=y and
CONFIG_KALLSYMS=y or CONFIG_KALLSYMS_ALL=y
```

Example usage

```
// Get a kernel probe to access flush_tlb_all
    memset(&kp, 0, sizeof(kp));
    kp.symbol_name = "flush_tlb_all";
    if (!register_kprobe(&kp)) {
        flush_tlb_all_lookup = (void *) kp.addr;
        unregister_kprobe(&kp);
    }
```


struct kprobe

```
<linux/kprobes.h>
struct kprobe {
      struct hlist node hlist; /* Internal */
      kprobe opcode t addr; /* Address of probe */
      kprobe pre handler t pre handler;
                        /* Address of pre-handler */
      kprobe post handler t post handler;
                        /* Address of post-handler */
      kprobe fault handler t fault handler;
                        /* Address of fault handler */
      kprobe break handler t break handler;
                        /* Internal */
      kprobe opcode t opcode; /* Internal */
      kprobe opcode t insn[MAX INSN SIZE]; /* Internal */
```


struct kprobe (kernel 3 or 4)

```
struct kprobe {
      struct hlist node hlist;
      /* list of kprobes for multi-handler support */
      struct list head list;
      /*count the number of times this probe
        was temporarily disarmed */
      unsigned long nmissed;
```

Kprobe mechanism



Trap to a debugger module that in the end manages kprobes



Kprobe handlers

```
typedef int (*kprobe pre handler t)
                  (struct kprobe*, struct pt regs*);
typedef void (*kprobe post handler t)
      (struct kprobe*, struct pt regs*,
                        unsigned long flags);
typedef int (*kprobe fault handler t)
            (struct kprobe*, struct pt regs*, int trapnr);
```

Modifiable registers status

kretprobe

```
Same interface as other
                                  probe handlers
struct kretprobe {
     struct kprobe_kp;___
   kretprobe handler t handler;
     kretprobe handler t entry handler;
     int maxactive;
     int nmissed;
     size t data size;
     struct hlist head free instances;
     raw spinlock t lock;
};
```

Probing deny

- Not all kernel functions can be probed
- A few of them are blacklisted (depending on compilation choices)
- Those that are blacklisted can be fount in the pseudofile

/sys/kernel/debug/kprobes/blacklist

Motivations can be compiler optimizations
 (such as in-lining) or the fact that these
 functions can be triggered by probe executions

Symbol versioning

- If the kernel is compiled with the macro <code>CONFIG_MODVERSIONS</code> activated (as usually happens), then each symbol is associated with a specific code representing the symbol version
- The code is computed by an algorithm relying on the Cyclic Redundancy Code (CRC) applied to the symbol prototype
- In such a case the /proc/ksyms file will contain symbol names expressed as

symbol-namel_Rversion

• NOTE:

- ➤ If CONFIG_MODVERSIONS is active a check on the symbols used within the module is performed in order to verify their version compliance with the ones exported by the kernel (except for cases where the -f option is passed to insmod)
- ➤ Hence we can recognize whether a module is adequate for loading onto a specific kernel version

Still on versioning

- the macro expanding the symbol name into one having the versioning suffix is defined within the file include/linux/modversions.h
- EXPORT SYMBOL () will rely onto the above macro
- For enabling versioning within a module we need CONFIG_MODVERSIONS==1, MODVERSIONS needs to be defined and include/linux/modversions.h must be included

• NOTE:

- >Symbols can anyhow be exported without versioning
- This can be done via the macro

 EXPORT_SYMBOL_NOVERS (symbol) which is defined in /include/linux/module.h

LINUX kernel versioning

- The include/linux/version.h file is automatically included via the inclusion of include/linux/module.h (except for cases where the __NO_VERSION__ macro is used)
- The include/linux/version.h file entails macros that can be used for catching information related to the actual kernel version such as:
 - ➤ UTS_RELEASE, which is expanded as a string defining the version of the kernel which is the target for the compilation of the module (e.g. "2.3.48")
 - > LINUX_VERSION_CODE which is expanded to the binary representation of the kernel version (with one byte for each number specifying the version)
 - ➤ KERNEL_VERSION (major, minor, release) which is expanded to the binary value representing the version number as defined via major, minor and release

Renaming of module startup/shutdown functions

- Starting from version 2.3.13 we have facilities for renaming the startup and shutdown functions of a module
- These are defined in the file include/linux/init.h as:
 - > module_init (my_init) which generates a startup routine associated with the symbol my init
 - > module_exit (my_exit) which generates a shutdown routine
 associated with the symbol my exit
- These should be used at the bottom of the main source file for the module
- They can help on the side of debugging since we can avoid using functions with the same name for the modules
- Further, we can develop code that can natively be integrated within the initial kernel image or can still represent some module for specific compilation targets