Wavefront OBJ

Reference

Menu:

File • Import/Export • Wavefront (.obj)

OBJ format is a popular plain text format, however, it has only basic geometry and material support.

Note

There is no support for armatures, lights, cameras, empty objects, parenting, or transformations. See Compatibility for more information.

Importing

Import geometry and curves to the OBJ format.

If there is a matching $\ . \ \mathtt{MTL}$ for the OBJ then its materials will be imported too.

General

Scale

Value by which to scale the imported objects in relation to the world's origin.

Clamp Bounding Box

OBJ-files often vary greatly in scale, this setting clamps the imported file to a fixed size.

Forward Axis, Up Axis

Since many applications use a different axis for 'Up', these are axis conversion for these settings, Forward and Up axes – By mapping these to different axes you can convert rotations between applications default up and forward axes.

Blender uses Y Forward, Z Up (since the front view looks along the +Y direction). For example, it's common for applications to use Y as the up axis, in that case -Z Forward, Y Up is needed.

Options

Split By Object

Import each OBJ "object name" group (o) as a separate object.

Split By Group

Import each OBJ "object name" group (g) as a separate object.

Vertex Groups

Import OBJ groups as vertex groups.

Validate Meshes

Check the imported mesh for corrupt data and fix it if necessary. When disabled, erroneous data may cause crashes displaying or editing the meshes. This option will make the importing slower but is recommended, as data errors are not always obvious.

Detect Cyclic Curves

Joins curve endpoints if overlapping control points are detected (if disabled, no curves will be cyclic).

Path Separator

Character used to separate an object's name into a hierarchical structure using Collections.

Exporting

Export geometry and curves to the OBJ format.

General

Include: Selected Only

Only export the selected objects. Otherwise export all objects in the scene.

Scale

Global scale to use on export.

Forward Axis, Up Axis

Since many applications use a different axis for 'Up', there are axis conversion settings, Forward and Up axis – By mapping these to different axis you can convert rotations between applications default up and forward axis.

Blender uses Y Forward, Z Up (since the front view looks along the +Y direction). For example, its common for applications to use Y as the up axis, in that case -Z Forward, Y Up is needed.

Geometry Properties

UV Coordinates

Write out the active UV layers coordinates from Blender.

Normals

Write out Blender's face and vertex normals (depending on the faces smooth setting).

Mostly this isn't needed since most applications will calculate their own normals but to match Blender's normal map textures you will need to write these too.

Colors

Write out the active vertex colors attribute layer, if present. Colors are exported in "xyzrgb" OBJ extension format.

Curves as NURBS

Write out NURBS curves as OBJ NURBS rather than converting to geometry.

Triangulated Mesh

Write out quads as two triangles. Some programs only have very basic OBJ support and only support triangles.

Apply Modifiers

Export objects using the evaluated mesh, meaning the resulting mesh after all Modifiers have been calculated.

Properties

For properties that have different settings for the viewport/final render pick which is used for output. One example where this is important is the Subdivision Surface Modifier.

Viewport:

Use viewport properties.

Render:

Use final render properties.

Grouping

Object Groups

Write out each Blender object as an OBJ object.

Note

Note that as far as Blender is concerned there is no difference between OBJ Groups and Objects, this option is only included for applications that treat them differently.

Material Groups

Generate an OBJ group for each part of a geometry using a different material.

Vertex Groups

Export the name of the vertex group of a face. It is approximated by choosing the vertex group with the most members among the vertices of a fac

Smooth Groups

Write Blender's sharp edges as smooth groups.

Smooth Group Bitflags

Generate Bitflags for smooth Groups.

Materials

Write out the MTL-file along with the OBJ. Most importers that support OBJ will also read the MTL-file.

PBR Extensions

Export MTL library using PBR extensions (roughness, metallic, sheen, clearcoat, anisotropy, transmission).

Path Mode

When referencing paths in exported files you may want some control as to the method used since absolute paths may only be correct on your owr system. Relative paths, on the other hand, are more portable but mean that you have to keep your files grouped when moving about on your local file system. In some cases, the path doesn't matter since the target application will search a set of predefined paths anyway so you have the option to strip the path too.

Auto:

Uses relative paths for files which are in a subdirectory of the exported location, absolute for any directories outside that.

Absolute:

Uses full paths.

Relative:

Uses relative paths in every case (except when on a different drive on Windows).

Match:

Uses relative / absolute paths based on the paths used in Blender.

Strip Path:

Only write the filename and omit the path component.

Copy:

Copy the file on exporting and reference it with a relative path.

Animation

Exports a numbered OBJ for each frame from the start to the end frame. Please be aware that this can take quite a long time.

Frame Start, End

The first and last frame to export, used to determine the range of exported frames.

Compatibility

NURBS surfaces, text3D and metaballs are converted to meshes at export time.

Previous Universal Scene Description Copyright ©: This page is licensed under a CC-BY-SA 4.0 Int. License Made with Furo

Last updated on 2025-05-10

View Source View Translation Report issue on this page

Stanford PI