Skip to content

Cryptomatte Node (Legacy)

The Cryptomatte node uses the Cryptomatte standard to efficiently create mattes for compositing. Cycles and EEVEE output the required render passes, which can then be used in the Compositor or another compositor with Cryptomatte support to create masks for specified objects.

Unlike the Material and Object Index passes, the objects to isolate are selected in compositing, and mattes will be anti-aliased and take into account effects like motion blur and transparency.

Important

The Cryptomatte Legacy node is deprecated and replaced by Cryptomatte Node. The legacy node will be removed in a future Blender release.

Inputs

Image

Standard color input.

Crypto Passes

Each crypto layer will be given its own render pass; each of these render passes must be connected to one of these crypto layer inputs. By default there are only four layers, see Adding/Removing Layers to add more.

Properties

Add/Remove

Adds/Removes an object or material from matte, by picking a color from the Pick output.

Matte ID

List of object and material crypto IDs to include in matte. This can be used for example to quickly clear all mattes by deleting the text or used to copy-and-paste crypto IDs from other software.

Outputs

Image

A colored output of the input image with the matte applied to only include selected layers.

Matte

A black-and-white alpha mask of the all the selected crypto layers.

Pick

A colored representation of the Cryptomatte pass which can be used with a Viewer node to select which crypto passes are used to create the ma image.

Usage

- 1. Enable Cryptomatte Object render pass in the Passes panel, and render.
- 2. In the compositing nodes, create a Cryptomatte node and link the Render Layer matching Image and Cryptomatte passes to it.
- 3. Attach a Viewer node to the Pick output of the Cryptomatte node.
- 4. Use the Cryptomatte Add/Remove button to sample objects in the Pick Viewer node.
- 5. Use the Matte output of the Cryptomatte node to get the alpha mask.

Adding/Removing Layers

By default there are only four crypto layers available as inputs to the Cryptomatte node. You can add or remove layer inputs through Sidebar * Item* Properties * Add/Remove Crypto Layer. These operators will add/remove layers from the bottom of the pass inputs.

No Box Mask No

Previous Cryptomatte Node Copyright ©: This page is licensed under a CC-BY-SA 4.0 Int. License

Made with Furo

Last updated on 2025-05-10

View Source View Translation Report issue on this page