

The Curve to Mesh node converts all splines of a curve to a mesh. Optionally, a profile curve can be provided to give the curve a custom shape. This profile curve is scaled by the radius at each control point; see the Set Curve Radius Node.

The node transfers attributes to the result. Attributes that are built-in on meshes but not curves, like sharp_face, will be transferred to the correct domain as well.

Tip

The output mesh has sharp edges set from the profile curve tagged automatically. If any splines in the profile curve are Bézier splines and any of the control points use Free or Vector handles, the corresponding edges will be shaded sharp.

Inputs

Curve

Standard geometry input. All non-curve components are ignored.

Note

If no radius attribute exists on the curve, the profile will not be scaled. This is inconsistent with elsewhere in Blender where the default radius of 0.01m is used when the attribute does not exist.

Profile Curve

If a profile curve is provided, it will be extruded along all splines. Otherwise the generated mesh will just be a chain of edges.

Fill Caps

If the profile spline is cyclic, fill the ends of the generated mesh with n-gons. The resulting mesh is Manifold, the two new faces for each spline are simply connected to existing edges.

Properties

This node has no properties.

Outputs

Mesh

Standard geometry output.

Previous Curve Operation Nodes Copyright ©: This page is licensed under a CC-BY-SA 4.0 Int. License Made with Furo

Last updated on 2025-05-10

Curve to Points No

View Source View Translation Report issue on this page