Skip to content **Markers**

Markers are used to denote frames with key points or significant events within an animation. E.g. it could be that a character's animation starts, the camera changes position, or a door opens. Markers can be given names to make them more meaningful at a quick glance. They are available in many of Blender's editors.

Note

Unlike keyframes, markers are always placed at a whole frame number, you cannot set a marker at frame 2.5.

Markers can be created and edited in the following editors:

- Graph Editor
- Dope Sheet
- NLA Editor
- Video Sequence Editor
- Timeline

Note

A marker created in one of these editors will also appear in all others that support them.

Types

Besides standard markers, *pose markers* are another type of markers, which are specific to armatures and shape keys. They are used to denote poses i the Action Editor mode and Shape Keys Editor of Dope Sheet.

Visualization

In the supported editors, if at least one is created, markers are visualized in a separate row at their bottom. This area can be disabled per editor via the View > Show Markers menu option.

Note

While the markers area is disabled, markers operators are not available in that editor, and in the header the Marker menu is hidden.

Standard

Regular markers are shown as small white triangles, empty if unselected or filled if selected, and with a dashed line that covers the editor height at the corresponding frame. If they have a name, this is shown to their right in white.

3D Viewport

The 3D Viewport does not allow you to create, edit or remove markers, but it shows their name in the Object Info in to upper left corner, when on their frame.

Pose Markers

Pose markers show a diamond-shaped icon in the Dope Sheet. In the NLA editor pose markers are shown as a red dashed line inside the relative action strip.



v 🔳 Object Mode ∨

(15) Collection | Cube < Mark1>

User Perspective



Add Marker

Reference

Mode:
All modes

Menu:
Marker • Add Marker

Shortcut:

M

The simplest way to add a marker is to move to the frame where you would like it to appear, and press $\,^{\,\mathrm{M}}$.

Hint

Markers can also be added during playback.

Pose Markers

If Show Pose Markers is checked, a pose marker and a new pose in the Old Pose Library are added.

Selecting

Reference

Mode:
All modes
Shortcut:

Click $^{\mathrm{LMB}}$ on the marker's triangle to select it. Use $^{\mathrm{Shift}}$ - $^{\mathrm{LMB}}$ to select multiple markers.

In the Graph Editor, Dope Sheet, NLA Editor, Timeline, and Video Sequence Editor, you can also select all markers with A while hovering the mouse over the marker row, and apply selection tools on them like Box Select, etc. (as usual, LMB to select, RMB to deselect). The corresponding options are found in the Select menu of these editors.

Editing

Duplicate Marker

Reference

Mode:

All modes

Menu:

Marker • Duplicate Marker

Shortcut:

Shift _ D

You can duplicate the selected markers by pressing Shift - D. Once duplicated, the new ones are automatically placed in select mode, so you can move them to the desired location.

Note

Note that unlike most other duplications in Blender, the names of the duplicated markers are not altered at all (no .001 numeric counter append).

Duplicate Marker to Scene

Refe	rence			
Mode:				
A	ll modes			
Menu:				
M	arker • Duplicate Marker to Scene			

Duplicates the selected markers into another scene.

Delete Marker

Reference

Mode:
All modes

Menu:
Marker > Delete Marker

Shortcut:
X

To delete the selected markers simply press $\ ^{X}$, and confirm the pop-up message with $\ ^{LMB}$.

Rename Marker

Reference

Mode:
All modes

Menu:
Marker • Rename Marker

Shortcut:
F2

Having dozens of markers scattered throughout your scene's time will not help you much unless you know what they stand for. You can name a marker l selecting it, pressing l , typing the name, and press l Return

Move Marker

Reference

Mode:
All modes

Menu:
Marker * Move Marker

Shortcut:
G

Once you have one or more markers selected, press G , while hovering with the mouse over the marker bar, to move them, and confirm the move with LMB or Return (as usual, cancel the move with RMB , or Esc). Or drag them with the LMB .

By default, you move the markers in one-frame steps, but if you hold Ctrl, the markers will move in steps corresponding to 1 second (according to 1 scene's FPS).

Select

Reference		
Mode		

All modes

Menu:

Marker - Select

Convenient operators for selecting Marks; see Selecting for more information on selecting Markers.

All A

Selects all Markers.

None Ctrl - A

Deselects any already selected Markers.

Invert Ctrl - I

Select all unselected Markers and deselects all selected Markers.

Before Current Frame

Selects all Markers to the left of the current frame and the Marker on the current frame if it exists.

After Current Frame

Selects all Markers to the Right of the current frame and the Marker on the current frame if it exists.

Show Pose Markers

Reference

Editor:

Dope Sheet

Mode:

Action Editor or Shape Keys Editor mode

Menu:

Marker - Show Pose Markers

Shows markers belonging to the active action instead of scene markers.

Make Markers Local

Reference

Mode:

All modes

Menu:

Marker - Make Markers Local

It is possible to convert standard markers into pose markers with Marker • Make Markers Local. Note that the original marker will be gone. If you wan to keep it, make a duplicate before you convert.

Jump to Next/Previous Marker

Reference

Mode:

All modes

Menu:

Marker • Jump to Next/Previous Marker

Moves the Playhead to the next/previous marker relative to the current frame.

Bind Camera to Markers

Reference

Editor:

Timeline

Menu:

Marker • Bind Camera to Markers

Shortcut:

Ctrl - B

Bind Camera to Markers is a special operator only available in the *Timeline*. The operator allows markers to be used to set the active object as the active camera.

To use this operator, select the object to become the active camera and select a marker to bind the active camera to. If no marker is selected when the operator is applied, a marker will be added. When an object is bound to a marker, the marker will be renamed to the name of the active object. These markers also have a camera icon next to the left of the name to easily distinguish them from other informative markers.

These markers can be moved to change the frame at which the active camera is changed to the object the marker is bound to.

Previous Troubleshooting Copyright ©: This page is licensed under a CC-BY-SA 4.0 Int. License

Made with Furo

Last updated on 2025-05-10

 $\begin{array}{c} N_{\ell} \\ \text{Shape } K_{\ell} \end{array}$

View Source View Translation Report issue on this page