Numeric Input

Using the mouse for transformations is convenient, but if you require more precise control, you can also enter numeric values. After pressing the shortcut type a number to indicate the magnitude of the transformation. Then confirm or cancel. E.g. pressing S 2, Return will double the scale of an object.

Move G

By default and with no other key presses, the translation will occur along the X axis.

Rotation R

The rotation is in clockwise direction for positive values.

Scale S

Scaling works in almost identical fashion to translation. The primary difference is that by default, scaling applies equally to all three axes.

You can see the numbers you enter in the 3D Viewport footer.

```
Dx: [pi * 2|] = 6m 28cm Dy: NONE Dz: NONE (6.283m)

User Perspective
(1) Collection | Cube
```

Numeric input displayed in the footer.

Tip

Numeric input can also be inputted in the Properties region.

Simple Mode

Blender has two "modes" a simple and an advanced one. Simple mode only accepts simple numbers. You can use basic text editing except selection.

Decimals Period

Decimals can be entered by pressing Period.

Negate Minus

Negate the whole value by pressing Minus.

Inverse Slash

Hitting Slash during number entry switches the number being entered to its reciprocal, e.g. 2 / results in 0.5 (1/2); 20 / results in 0.05 (1/20).

Reset Backspace

Hitting Backspace after having deleted all leading chars will first reset the edited value to initial state, and on second press, the whole number editing will be canceled, going back to usual transform with mouse.

Next/Previous Component Tab, Ctrl - Tab

To enter numeric values for multiple axes, use \mbox{Tab} or $\mbox{Ctrl} - \mbox{Tab}$. E.g. To move an object, one unit on all three axes press: \mbox{G} 1 and \mbox{Tab} 1 and \mbox{Tab} 1.

Non-number Inputs

You can also combine numeric input with Axis Locking to limit movement to a particular axis or tool specific shortcuts.

Advanced Mode

In advanced mode you can additionally enter expressions and units.

 $U_{Se} = or NumpadAsterisk$ to enable advanced mode, and Ctrl - = or Ctrl - NumpadAsterisk to switch back to simple mode. It features:

- Units (cm, ", deg, etc.). See unit system.
- Basic operations from Python (+, *, /, **, etc.).
- Math constants and functions (pi, sin, sqrt, etc.). See Python's math module.

You can still use the negate and inverse shortcuts (Minus, Slash), as well as non-number inputs, but you have to hold Ctrl to activate them

Previous Transform Control Copyright © : This page is licensed under a CC-BY-SA 4.0 Int. License

Made with Furo

Last updated on 2025-05-10

No Axis Lock

View Source View Translation Report issue on this page