Chapter 12: Mass-Storage Systems

Chapter 12: Mass-Storage Systems

- Overview of Mass Storage Structure
- Disk Structure
- Disk Attachment
- Disk Scheduling
- Disk Management
- Swap-Space Management
- RAID Structure
- Disk Attachment
- Stable-Storage Implementation


Objectives

- Describe the physical structure of secondary and tertiary storage devices and the resulting effects on the uses of the devices
- Explain the performance characteristics of mass-storage devices
- Discuss operating-system services provided for mass storage, including RAID and HSM

Overview of Mass Storage Structure

- Magnetic disks provide bulk of secondary storage of modern computers
 - Drives rotate at 60 to 200 times per second
 - **Transfer rate** is rate at which data flow between drive and computer
 - Positioning time (random-access time) is time to move disk arm to desired cylinder (seek time) and time for desired sector to rotate under the disk head (rotational latency)
 - Head crash results from disk head making contact with the disk surface
 - That's bad
- Disks can be removable
- Drive attached to computer via I/O bus
 - Buses vary, including EIDE, ATA, SATA, USB, Fiber Channel, SCSI
 - Host controller in computer uses bus to talk to disk controller built into drive or storage array

Moving-head Disk Machanism



Disk Sector

Disk structures:


A.Track (磁道)

B.Geometrical sector

C.Track sector (扇区)

D.Cluster (簇)

Each sector stores a fixed amount of user-accessible data, traditionally 512 bytes for hard disk drives (HDDs) and 2048 bytes for CD-ROMs and DVD-ROMs. Newer HDDs use 4096-byte (4 KiB) sectors, which are known as the Advanced Format (AF).



Nonvolatile Memory Devices

- SSD uses NVM devices
- Data cannot be overwritten— rather, the NAND cells have to be erased first. An
 erasure is much slower than a read (the fastest operation) or a write (slower than
 read)
- Maximum ~100,000 program-erase cycles



Overview of Mass Storage Structure (Cont.)

- Magnetic tape
 - Was early secondary-storage medium
 - Relatively permanent and holds large quantities of data
 - Access time slow
 - Random access ~1000 times slower than disk
 - Mainly used for backup, storage of infrequently-used data, transfer medium between systems
 - Kept in spool and wound or rewound past read-write head
 - Once data under head, transfer rates comparable to disk
 - 20-200GB typical storage
 - Common technologies are 4mm, 8mm, 19mm, LTO-2 and SDLT

Disk Structure

- Disk drives are addressed as large 1-dimensional arrays of logical blocks, where the logical block is the smallest unit of transfer.
- The 1-dimensional array of logical blocks is mapped into the sectors of the disk sequentially.
 - Sector 0 is the first sector of the first track on the *outermost* cylinder.
 - Mapping proceeds in order through that track, then the rest of the tracks in that cylinder, and then through the rest of the cylinders from *outermost* to innermost.

Disk Attachment



Fibre Channel



SCSI



ATA(IDE)




Serial ATA

Disk Attachment

- Host-attached storage accessed through I/O ports talking to I/O buses
- SCSI itself is a bus, up to 16 devices on one cable, SCSI initiator requests operation and SCSI targets perform tasks
 - Each target can have up to 8 **logical units** (disks attached to device controller
- Fibre Channel (FC) is high-speed serial architecture
 - Can be switched fabric with 24-bit address space the basis of storage area networks (SANs) in which many hosts attach to many storage units
 - Can be arbitrated loop (FC-AL) of 126 devices


Network-Attached Storage

- Network-attached storage (NAS) is storage made available over a network rather than over a local connection (such as a bus)
- NFS and CIFS are common protocols
- Implemented via remote procedure calls (RPCs) between host and storage
- New iSCSI protocol uses IP network to carry the SCSI protocol



Storage Area Network

- Common in large storage environments (and becoming more common)
- Multiple hosts attached to multiple storage arrays flexible




Accessing a Disk Page

- Time to access (read/write) a disk block:
 - seek time (moving arms to position disk head on track)
 - rotational delay (waiting for block to rotate under head)
 - transfer time (actually moving data to/from disk surface)
- Seek time and rotational delay dominate.
 - Seek time varies from about 1 to 20msec
 - Rotational delay varies from 0 to 10msec
 - Transfer rate is about 1msec per 4KB page
- Key to lower I/O cost: reduce seek/rotation delays! Hardware vs. software solutions?

Multi Actuator Technology: A New Performance Breakthrough

 An actuator is the component that moves a hard drive's heads over the media surface, to read and write data. Each recording head sits at the end of a moving actuator arm. Hard drives today are equipped with a single actuator, which moves all the read-write heads together in synchronous motion.



Disk Scheduling

- The operating system is responsible for using hardware efficiently for the disk drives, this means having a fast access time and disk bandwidth.
- Access time has two major components
 - Seek time is the time for the disk are to move the heads to the cylinder containing the desired sector.
 - Rotational latency is the additional time waiting for the disk to rotate the desired sector to the disk head.
- Minimize seek time
- Metric: Seek time ≈ seek distance
- Disk bandwidth is the total number of bytes transferred, divided by the total time between the first request for service and the completion of the last transfer.

Disk Scheduling (Cont.)


- Several algorithms exist to schedule the servicing of disk I/O requests.
- We illustrate them with a request queue (0-199).

98, 183, 37, 122, 14, 124, 65, 67

Current head pointer 53

FCFS


Illustration shows total head movement of 640 cylinders.



Shortest-seek-time-first (SSTF)

- Selects the request with the minimum seek time from the current head position.
- SSTF scheduling is a form of SJF scheduling; may cause starvation of some requests.
- Illustration shows total head movement of 236 cylinders.


SSTF (Cont.)



SCAN

- The disk arm starts at one end of the disk, and moves toward the other end, servicing requests until it gets to the other end of the disk, where the head movement is reversed and servicing continues.
- Sometimes called the elevator algorithm.

SCAN (Cont.)




■LOOK needs total head movement of 208 cylinders.

C-SCAN

- Provides a more uniform wait time than SCAN.
- The head moves from one end of the disk to the other. servicing requests as it goes. When it reaches the other end, however, it immediately returns to the beginning of the disk, without servicing any requests on the return trip.
- Treats the cylinders as a circular list that wraps around from the last cylinder to the first one.


C-SCAN (Cont.)



C-LOOK

- Version of C-SCAN
- Arm only goes as far as the last request in each direction, then reverses direction immediately, without first going all the way to the end of the disk.

C-LOOK (Cont.)




Selecting a Disk-Scheduling Algorithm

- SSTF is common and has a natural appeal
- SCAN and C-SCAN perform better for systems that place a heavy load on the disk.
- Performance depends on the number and types of requests.
- Requests for disk service can be influenced by the file-allocation method.
- The disk-scheduling algorithm should be written as a separate module of the operating system, allowing it to be replaced with a different algorithm if necessary.
- Either SSTF or LOOK is a reasonable choice for the default algorithm.
- Question: What scheduling algorithm is good for SSD?

Swapping re-examined:

Why Swap-out to Contiguous Disk Blocks?


Remember that we swap out process memory pages onto hard disk while swap in those demanded by paging.



Disk Management

- Low-level formatting, or physical formatting Dividing a disk into sectors that the disk controller can read and write.
- To use a disk to hold files, the operating system still needs to record its own data structures on the disk.
 - Partition the disk into one or more groups of cylinders.
 - Logical formatting or "making a file system".
- Boot block initializes system.
 - The bootstrap is stored in ROM.
 - Bootstrap loader program.
- Methods such as sector sparing used to handle bad blocks.


Booting from a Disk in Windows



Swap-Space Management

- Swap-space Virtual memory uses disk space as an extension of main memory.
- Swap-space can be carved out of the normal file system, or, more commonly, it can be in a separate disk partition.
- Swap-space management
 - 4.3BSD allocates swap space when process starts; holds text segment (the program) and data segment.
 - Kernel uses swap maps to track swap-space use.
 - Solaris 2 allocates swap space only when a page is forced out of physical memory, not when the virtual memory page is first created.

Data Structures for Swapping on Linux Systems



processes


RAID Structure


- Redundant Arrays of Independent Disks
- RAID multiple disk drives provides reliability via redundancy.
- RAID is arranged into six different levels.

RAID (cont)

- Several improvements in disk-use techniques involve the use of multiple disks working cooperatively.
- Disk striping (条带化) uses a group of disks as one storage unit.
 - Bit-level Striping
 - Block-level Striping different blocks of a file are striped
- RAID schemes improve performance and improve the reliability of the storage system by storing redundant data.
 - Mirroring or shadowing keeps duplicate of each disk.
 - Block interleaved parity uses much less redundancy.


RAID Levels





- RAID 1: Provides fault tolerance from disk errors and failure of all but one of the drives. Increased read performance occurs when using a multi-threaded operating system that supports split seeks, very small performance reduction when writing. Array continues to operate so long as at least one drive is functioning.
- RAID 2: memory-style Hamming code parity. Not really practical.
- RAID 3: The single parity disk is a bottleneck for writing since every write requires updating the parity data.
- RAID 4: Identical with RAID 3 except using block level parity. The parity disk can become a bottleneck. Large (parallel) reads and writes are good. Small write causes 4 page accesses. (read data/parity and write them back.)
- RAID 5: Distributed parity requires all drives but one to be present to operate; drive failure requires replacement, but the array is not destroyed by a single drive failure.
- RAID 6: extra redundancy information to guard two disk failures.

RAID (0 + 1) and (1 + 0)



Stable-Storage Implementation

- Write-ahead log scheme requires stable storage.
- To implement stable storage:
 - Replicate information on more than one nonvolatile storage media with independent failure modes.
 - Update information in a controlled manner to ensure that we can recover the stable data after any failure during data transfer or recovery.

Tertiary Storage Devices

- Low cost is the defining characteristic of tertiary storage.
- Generally, tertiary storage is built using removable media
- Common examples of removable media are floppy disks and CD-ROMs; other types are available.

Removable Disks

- Floppy disk thin flexible disk coated with magnetic material, enclosed in a protective plastic case.
 - Most floppies hold about 1 MB; similar technology is used for removable disks that hold more than 1 GB.
 - Removable magnetic disks can be nearly as fast as hard disks, but they are at a greater risk of damage from exposure.

Removable Disks (Cont.)

- A magneto-optic disk records data on a rigid platter coated with magnetic material.
 - Laser heat is used to amplify a large, weak magnetic field to record a bit.
 - Laser light is also used to read data (Kerr effect).
 - The magneto-optic head flies much farther from the disk surface than a magnetic disk head, and the magnetic material is covered with a protective layer of plastic or glass; resistant to head crashes.
- Optical disks do not use magnetism; they employ special materials that are altered by laser light.

WORM Disks

- The data on read-write disks can be modified over and over.
- WORM ("Write Once, Read Many Times") disks can be written only once.
- Thin aluminum film sandwiched between two glass or plastic platters.
- To write a bit, the drive uses a laser light to burn a small hole through the aluminum; information can be destroyed but not altered.
- Very durable and reliable.
- Read Only disks, such ad CD-ROM and DVD, come from the factory with the data pre-recorded.

Tapes

- Compared to a disk, a tape is less expensive and holds more data, but random access is much slower.
- Tape is an economical medium for purposes that do not require fast random access, e.g., backup copies of disk data, holding huge volumes of data.
- Large tape installations typically use robotic tape changers that move tapes between tape drives and storage slots in a tape library.
 - stacker library that holds a few tapes
 - silo library that holds thousands of tapes
- A disk-resident file can be *archived* to tape for low cost storage; the computer can *stage* it back into disk storage for active use.

Tape Library





Operating System Issues

- Major OS jobs are to manage physical devices and to present a virtual machine abstraction to applications
- For hard disks, the OS provides two abstraction:
 - Raw device an array of data blocks.
 - File system the OS queues and schedules the interleaved requests from several applications.

Application Interface

- Most OSs handle removable disks almost exactly like fixed disks a new cartridge is formatted and an empty file system is generated on the disk.
- Tapes are presented as a raw storage medium, i.e., and application does not open a file on the tape, it opens the whole tape drive as a raw device.
- Usually the tape drive is reserved for the exclusive use of that application.
- Since the OS does not provide file system services, the application must decide how to use the array of blocks.
- Since every application makes up its own rules for how to organize a tape, a tape full of data can generally only be used by the program that created it.

Tape Drives

- The basic operations for a tape drive differ from those of a disk drive.
- **locate** positions the tape to a specific logical block, not an entire track (corresponds to **seek**).
- The read position operation returns the logical block number where the tape head is.
- The space operation enables relative motion.
- Tape drives are "append-only" devices; updating a block in the middle of the tape also effectively erases everything beyond that block.
- An EOT mark is placed after a block that is written.

File Naming

- The issue of naming files on removable media is especially difficult when we want to write data on a removable cartridge on one computer, and then use the cartridge in another computer.
- Contemporary OSs generally leave the name space problem unsolved for removable media, and depend on applications and users to figure out how to access and interpret the data.
- Some kinds of removable media (e.g., CDs) are so well standardized that all computers use them the same way.

Hierarchical Storage Management (HSM)

- A hierarchical storage system extends the storage hierarchy beyond primary memory and secondary storage to incorporate tertiary storage — usually implemented as a jukebox of tapes or removable disks.
- Usually incorporate tertiary storage by extending the file system.
 - Small and frequently used files remain on disk.
 - Large, old, inactive files are archived to the jukebox.
- HSM is usually found in supercomputing centers and other large installations that have enormous volumes of data.

A Jukebox





Speed

- Two aspects of speed in tertiary storage are bandwidth and latency.
- Bandwidth is measured in bytes per second.
 - Sustained bandwidth average data rate during a large transfer; # of bytes/transfer time.
 Data rate when the data stream is actually flowing.
 - Effective bandwidth average over the entire I/O time, including seek or locate, and cartridge switching.
 Drive's overall data rate.

Speed (Cont.)

- Access latency amount of time needed to locate data.
 - Access time for a disk move the arm to the selected cylinder and wait for the rotational latency; < 35 milliseconds.
 - Access on tape requires winding the tape reels until the selected block reaches the tape head; tens or hundreds of seconds.
 - Generally say that random access within a tape cartridge is about a thousand times slower than random access on disk.
- The low cost of tertiary storage is a result of having many cheap cartridges share a few expensive drives.
- A removable library is best devoted to the storage of infrequently used data, because the library can only satisfy a relatively small number of I/O requests per hour.


Reliability

- A fixed disk drive is likely to be more reliable than a removable disk or tape drive.
- An optical cartridge is likely to be more reliable than a magnetic disk or tape.
- A head crash in a fixed hard disk generally destroys the data, whereas the failure
 of a tape drive or optical disk drive often leaves the data cartridge unharmed.


Cost

- Main memory is much more expensive than disk storage
- The cost per megabyte of hard disk storage is competitive with magnetic tape if only one tape is used per drive.
- The cheapest tape drives and the cheapest disk drives have had about the same storage capacity over the years.
- Tertiary storage gives a cost savings only when the number of cartridges is considerably larger than the number of drives.


Price per Megabyte of DRAM, From 1981 to 2004



Price per Megabyte of Magnetic Hard Disk, From 1981 to 2004



Price per Megabyte of a Tape Drive, From 1984-2000



Moore's Law being proved...

	1969	2007	Factor
main memory	200 KB	2000 MB	104
cache	20 KB	200 MB	104
cache pages	20	5000	<103
disk size	7.5 MB	200 GB	3*104
disk/memory size	40	100	-2.5
transfer rate	150 KB/s	15 MB/s	102
random access	50 ms	5 ms	10
scanning full disk	130 s	13000 s	-100

As of 2017, a typical 10000 rpm desktop HDD has a sustained "disk-to-buffer" data transfer rate up to 1 Gbits/sec. 4TB/1Gb=32000 s

End of Chapter 12