C++ Core Guidelines

October 12, 2023

Editors:

- Bjarne Stroustrup
- Herb Sutter

This is a living document under continuous improvement. Had it been an open-source (code) project, this would have been release 0.8. Copying, use, modification, and creation of derivative works from this project is licensed under an MIT-style license. Contributing to this project requires agreeing to a Contributor License. See the accompanying LICENSE file for details. We make this project available to "friendly users" to use, copy, modify, and derive from, hoping for constructive input.

Comments and suggestions for improvements are most welcome. We plan to modify and extend this document as our understanding improves and the language and the set of available libraries improve. When commenting, please note the introduction that outlines our aims and general approach. The list of contributors is here.

Problems:

- The sets of rules have not been completely checked for completeness, consistency, or enforceability.
- Triple question marks (???) mark known missing information
- Update reference sections; many pre-C++11 sources are too old.
- For a more-or-less up-to-date to-do list see: To-do: Unclassified proto-rules

You can read an explanation of the scope and structure of this Guide or just jump straight in:

- In: Introduction
- P: Philosophy
- I: Interfaces
- F: Functions
- C: Classes and class hierarchies
- Enum: Enumerations
- R: Resource management
- ES: Expressions and statements
- Per: Performance
- CP: Concurrency and parallelism
- E: Error handling
- Con: Constants and immutability
- T: Templates and generic programming
- CPL: C-style programming
- SF: Source files
- SL: The Standard Library

Supporting sections:

- A: Architectural ideas
- NR: Non-Rules and myths
- RF: References
- Pro: Profiles
- GSL: Guidelines support library
- NL: Naming and layout suggestions
- FAQ: Answers to frequently asked questions
- Appendix A: Libraries
- Appendix B: Modernizing code
- Appendix C: Discussion
- Appendix D: Supporting tools
- Glossary
- To-do: Unclassified proto-rules

You can sample rules for specific language features:

- assignment: regular types -- prefer initialization -- copy -- move -- other operations -- default
- class: data -- invariant -- members -- helpers -- concrete types -- ctors, =, and dtors -- hierarchy -- operators
- concept: rules -- in generic programming -- template arguments -- semantics
- constructor: invariant -- establish invariant -- throw -- default -- not needed -- explicit -- delegating -- virtual
- derived class: when to use -- as interface -- destructors -- copy -- getters and setters -- multiple inheritance -- overloading -- slicing -- dynamic_cast
- destructor: and constructors -- when needed? -- must not fail
- exception: errors -- throw -- for errors only -- noexcept -- minimize try -- what if no exceptions?
- for: range-for and for -- for and while -- for-initializer -- empty body -- loop variable -- loop variable type ???
- function: naming -- single operation -- no throw -- arguments -- argument passing -- multiple return values -pointers -- lambdas
- inline: small functions -- in headers
- initialization: always -- prefer {} -- lambdas -- in-class initializers -- class members -- factory functions
- lambda expression: when to use
- operator: conventional -- avoid conversion operators -- and lambdas
- public, private, and protected: information hiding -- consistency -- protected
- static_assert: compile-time checking -- and concepts
- struct: for organizing data -- use if no invariant -- no private members
- template: abstraction -- containers -- concepts
- unsigned: and signed -- bit manipulation
- virtual: interfaces -- not virtual -- destructor -- never fail

You can look at design concepts used to express the rules:

- assertion: ???
- error: ???
- exception: exception guarantee (???)
- failure: ???invariant: ???
- leak: ???library: ???
- precondition: ???postcondition: ???
- resource: ???

Abstract

This document is a set of guidelines for using C++ well. The aim of this document is to help people to use modern C++ effectively. By "modern C++" we mean effective use of the ISO C++ standard (currently C++20, but almost all of our recommendations also apply to C++17, C++14 and C++11). In other words, what would you like your code to look like in 5 years' time, given that you can start now? In 10 years' time?

The guidelines are focused on relatively high-level issues, such as interfaces, resource management, memory management, and concurrency. Such rules affect application architecture and library design. Following the rules will lead to code that is statically type safe, has no resource leaks, and catches many more programming logic errors than is common in code today. And it will run fast -- you can afford to do things right.

We are less concerned with low-level issues, such as naming conventions and indentation style. However, no topic that can help a programmer is out of bounds.

Our initial set of rules emphasizes safety (of various forms) and simplicity. They might very well be too strict. We expect to have to introduce more exceptions to better accommodate real-world needs. We also need more rules.

You will find some of the rules contrary to your expectations or even contrary to your experience. If we haven't suggested you change your coding style in any way, we have failed! Please try to verify or disprove rules! In particular, we'd really like to have some of our rules backed up with measurements or better examples.

You will find some of the rules obvious or even trivial. Please remember that one purpose of a guideline is to help someone who is less experienced or coming from a different background or language to get up to speed.

Many of the rules are designed to be supported by an analysis tool. Violations of rules will be flagged with references (or links) to the relevant rule. We do not expect you to memorize all the rules before trying to write code. One way of thinking about these guidelines is as a specification for tools that happens to be readable by humans.

The rules are meant for gradual introduction into a code base. We plan to build tools for that and hope others will too.

Comments and suggestions for improvements are most welcome. We plan to modify and extend this document as our understanding improves and the language and the set of available libraries improve.

In: Introduction

This is a set of core guidelines for modern C++ (currently C++20 and C++17) taking likely future enhancements and ISO Technical Specifications (TSs) into account. The aim is to help C++ programmers to write simpler, more efficient, more maintainable code.

Introduction summary:

In.target: Target readership

In.aims: AimsIn.not: Non-aims

- In.force: Enforcement
- In.struct: The structure of this document
- In.sec: Major sections

In.target: Target readership

All C++ programmers. This includes programmers who might consider C.

In.aims: Aims

The purpose of this document is to help developers to adopt modern C++ (currently C++20 and C++17) and to achieve a more uniform style across code bases.

We do not suffer the delusion that every one of these rules can be effectively applied to every code base. Upgrading old systems is hard. However, we do believe that a program that uses a rule is less error-prone and more maintainable than one that does not. Often, rules also lead to faster/easier initial development. As far as we can tell, these rules lead to code that performs as well or better than older, more conventional techniques; they are meant to follow the zero-overhead principle ("what you don't use, you don't pay for" or "when you use an abstraction mechanism appropriately, you get at least as good performance as if you had handcoded using lower-level language constructs"). Consider these rules ideals for new code, opportunities to exploit when working on older code, and try to approximate these ideals as closely as feasible. Remember:

In.0: Don't panic!

Take the time to understand the implications of a guideline rule on your program.

These guidelines are designed according to the "subset of superset" principle (Stroustrup05). They do not simply define a subset of C++ to be used (for reliability, safety, performance, or whatever). Instead, they strongly recommend the use of a few simple "extensions" (library components) that make the use of the most error-prone features of C++ redundant, so that they can be banned (in our set of rules).

The rules emphasize static type safety and resource safety. For that reason, they emphasize possibilities for range checking, for avoiding dereferencing nullptr, for avoiding dangling pointers, and the systematic use of exceptions (via RAII). Partly to achieve that and partly to minimize obscure code as a source of errors, the rules also emphasize simplicity and the hiding of necessary complexity behind well-specified interfaces.

Many of the rules are prescriptive. We are uncomfortable with rules that simply state "don't do that!" without offering an alternative. One consequence of that is that some rules can be supported only by heuristics, rather than precise and mechanically verifiable checks. Other rules articulate general principles. For these more general rules, more detailed and specific rules provide partial checking.

These guidelines address the core of C++ and its use. We expect that most large organizations, specific application areas, and even large projects will need further rules, possibly further restrictions, and further library support. For example, hard-real-time programmers typically can't use free store (dynamic memory) freely and will be restricted in their choice of libraries. We encourage the development of such more specific rules as addenda to these core guidelines. Build your ideal small foundation library and use that, rather than lowering your level of programming to glorified assembly code.

The rules are designed to allow gradual adoption.

Some rules aim to increase various forms of safety while others aim to reduce the likelihood of accidents, many do both. The guidelines aimed at preventing accidents often ban perfectly legal C++. However, when there are two ways of expressing an idea and one has shown itself a common source of errors and the other has not, we try to guide programmers towards the latter.

In.not: Non-aims

The rules are not intended to be minimal or orthogonal. In particular, general rules can be simple, but unenforceable. Also, it is often hard to understand the implications of a general rule. More specialized rules are often easier to understand and to enforce, but without general rules, they would just be a long list of special cases. We provide rules aimed at helping novices as well as rules supporting expert use. Some rules can be completely enforced, but others are based on heuristics.

These rules are not meant to be read serially, like a book. You can browse through them using the links. However, their main intended use is to be targets for tools. That is, a tool looks for violations and the tool returns links to violated rules. The rules then provide reasons, examples of potential consequences of the violation, and suggested remedies.

These guidelines are not intended to be a substitute for a tutorial treatment of C++. If you need a tutorial for some given level of experience, see the references.

This is not a guide on how to convert old C++ code to more modern code. It is meant to articulate ideas for new code in a concrete fashion. However, see the modernization section for some possible approaches to modernizing/rejuvenating/upgrading. Importantly, the rules support gradual adoption: It is typically infeasible to completely convert a large code base all at once.

These guidelines are not meant to be complete or exact in every language-technical detail. For the final word on language definition issues, including every exception to general rules and every feature, see the ISO C++ standard.

The rules are not intended to force you to write in an impoverished subset of C++. They are *emphatically* not meant to define a, say, Java-like subset of C++. They are not meant to define a single "one true C++" language. We value expressiveness and uncompromised performance.

The rules are not value-neutral. They are meant to make code simpler and more correct/safer than most existing C++ code, without loss of performance. They are meant to inhibit perfectly valid C++ code that correlates with errors, spurious complexity, and poor performance.

The rules are not precise to the point where a person (or machine) can follow them without thinking. The enforcement parts try to be that, but we would rather leave a rule or a definition a bit vague and open to interpretation than specify something precisely and wrong. Sometimes, precision comes only with time and experience. Design is not (yet) a form of Math.

The rules are not perfect. A rule can do harm by prohibiting something that is useful in a given situation. A rule can do harm by failing to prohibit something that enables a serious error in a given situation. A rule can do a lot of harm by being vague, ambiguous, unenforceable, or by enabling every solution to a problem. It is impossible to completely meet the "do no harm" criteria. Instead, our aim is the less ambitious: "Do the most good for most programmers"; if you cannot live with a rule, object to it, ignore it, but don't water it down until it becomes meaningless. Also, suggest an improvement.

In.force: Enforcement

Rules with no enforcement are unmanageable for large code bases. Enforcement of all rules is possible only for a small weak set of rules or for a specific user community.

- But we want lots of rules, and we want rules that everybody can use.
- But different people have different needs.
- But people don't like to read lots of rules.
- But people can't remember many rules.

So, we need subsetting to meet a variety of needs.

But arbitrary subsetting leads to chaos.

We want guidelines that help a lot of people, make code more uniform, and strongly encourage people to modernize their code. We want to encourage best practices, rather than leave all to individual choices and management pressures. The ideal is to use all rules; that gives the greatest benefits.

This adds up to quite a few dilemmas. We try to resolve those using tools. Each rule has an **Enforcement** section listing ideas for enforcement. Enforcement might be done by code review, by static analysis, by compiler, or by run-time checks. Wherever possible, we prefer "mechanical" checking (humans are slow, inaccurate, and bore easily) and static checking. Run-time checks are suggested only rarely where no alternative exists; we do not want to introduce "distributed bloat". Where appropriate, we label a rule (in the **Enforcement** sections) with the name of groups of related rules (called "profiles"). A rule can be part of several profiles, or none. For a start, we have a few profiles corresponding to common needs (desires, ideals):

- type: No type violations (reinterpreting a T as a U through casts, unions, or varargs)
- **bounds**: No bounds violations (accessing beyond the range of an array)
- **lifetime**: No leaks (failing to delete or multiple delete) and no access to invalid objects (dereferencing nullptr, using a dangling reference).

The profiles are intended to be used by tools, but also serve as an aid to the human reader. We do not limit our comment in the **Enforcement** sections to things we know how to enforce; some comments are mere wishes that might inspire some tool builder.

Tools that implement these rules shall respect the following syntax to explicitly suppress a rule:

[[gsl::suppress(tag)]]

and optionally with a message (following usual C++11 standard attribute syntax):

```
[[gsl::suppress(tag, justification: "message")]]
```

where

- tag is the anchor name of the item where the Enforcement rule appears (e.g., for C.134 it is "Rh-public"), the name of a profile group-of-rules ("type", "bounds", or "lifetime"), or a specific rule in a profile (type.4, or bounds.2)
- "message" is a string literal

In.struct: The structure of this document

Each rule (guideline, suggestion) can have several parts:

- The rule itself -- e.g., no naked new
- A rule reference number -- e.g., C.7 (the 7th rule related to classes). Since the major sections are not inherently ordered, we use letters as the first part of a rule reference "number". We leave gaps in the numbering to minimize "disruption" when we add or remove rules.
- Reasons (rationales) -- because programmers find it hard to follow rules they don't understand
- Examples -- because rules are hard to understand in the abstract; can be positive or negative
- Alternatives -- for "don't do this" rules
- Exceptions -- we prefer simple general rules. However, many rules apply widely, but not universally, so exceptions must be listed
- Enforcement -- ideas about how the rule might be checked "mechanically"
- See alsos -- references to related rules and/or further discussion (in this document or elsewhere)
- Notes (comments) -- something that needs saying that doesn't fit the other classifications
- **Discussion** -- references to more extensive rationale and/or examples placed outside the main lists of rules

Some rules are hard to check mechanically, but they all meet the minimal criteria that an expert programmer can spot many violations without too much trouble. We hope that "mechanical" tools will improve with time to approximate what such an expert programmer notices. Also, we assume that the rules will be refined over time to make them more precise and checkable.

A rule is aimed at being simple, rather than carefully phrased to mention every alternative and special case. Such information is found in the **Alternative** paragraphs and the Discussion sections. If you don't understand a rule or disagree with it, please visit its **Discussion**. If you feel that a discussion is missing or incomplete, enter an Issue explaining your concerns and possibly a corresponding PR.

Examples are written to illustrate rules.

- Examples are not intended to be production quality or to cover all tutorial dimensions. For example, many examples are language-technical and use names like f, base, and x.
- We try to ensure that "good" examples follow the Core Guidelines.
- Comments are often illustrating rules where they would be unnecessary and/or distracting in "real code."
- We assume knowledge of the standard library. For example, we use plain vector rather than std::vector.

This is not a language manual. It is meant to be helpful, rather than complete, fully accurate on technical details, or a guide to existing code. Recommended information sources can be found in the references.

In.sec: Major sections

- In: Introduction
- P: Philosophy
- I: Interfaces
- F: Functions
- C: Classes and class hierarchies
- Enum: Enumerations
- R: Resource management
- ES: Expressions and statements
- Per: Performance
- CP: Concurrency and parallelism
- E: Error handling
- Con: Constants and immutability
- T: Templates and generic programming
- CPL: C-style programming
- SF: Source files
- SL: The Standard Library

Supporting sections:

- A: Architectural ideas
- NR: Non-Rules and myths
- RF: References
- Pro: Profiles
- GSL: Guidelines support library
- NL: Naming and layout suggestions
- FAQ: Answers to frequently asked questions
- Appendix A: Libraries
- Appendix B: Modernizing code
- Appendix C: Discussion
- Appendix D: Supporting tools
- Glossary
- To-do: Unclassified proto-rules

These sections are not orthogonal.

Each section (e.g., "P" for "Philosophy") and each subsection (e.g., "C.hier" for "Class Hierarchies (OOP)") have an abbreviation for ease of searching and reference. The main section abbreviations are also used in rule numbers (e.g., "C.11" for "Make concrete types regular").

P: Philosophy

The rules in this section are very general.

Philosophy rules summary:

- P.1: Express ideas directly in code
- P.2: Write in ISO Standard C++
- P.3: Express intent
- P.4: Ideally, a program should be statically type safe
- P.5: Prefer compile-time checking to run-time checking
- P.6: What cannot be checked at compile time should be checkable at run time
- P.7: Catch run-time errors early
- P.8: Don't leak any resources
- P.9: Don't waste time or space
- P.10: Prefer immutable data to mutable data
- P.11: Encapsulate messy constructs, rather than spreading through the code
- P.12: Use supporting tools as appropriate
- P.13: Use support libraries as appropriate

Philosophical rules are generally not mechanically checkable. However, individual rules reflecting these philosophical themes are. Without a philosophical basis, the more concrete/specific/checkable rules lack rationale.

P.1: Express ideas directly in code

Reason

Compilers don't read comments (or design documents) and neither do many programmers (consistently). What is expressed in code has defined semantics and can (in principle) be checked by compilers and other tools.

Example

```
class Date {
public:
    Month month() const; // do
    int month(); // don't
    // ...
};
```

The first declaration of month is explicit about returning a Month and about not modifying the state of the Date object. The second version leaves the reader guessing and opens more possibilities for uncaught bugs.

Example, bad

This loop is a restricted form of std::find:

Example, good

A much clearer expression of intent would be:

```
void f(vector<string>& v)
{
    string val;
    cin >> val;
    // ...
    auto p = find(begin(v), end(v), val); // better
    // ...
}
```

A well-designed library expresses intent (what is to be done, rather than just how something is being done) far better than direct use of language features.

A C++ programmer should know the basics of the standard library, and use it where appropriate. Any programmer should know the basics of the foundation libraries of the project being worked on, and use them appropriately. Any programmer using these guidelines should know the guidelines support library, and use it appropriately.

Example

```
change_speed(double s); // bad: what does s signify?
// ...
change_speed(2.3);
```

A better approach is to be explicit about the meaning of the double (new speed or delta on old speed?) and the unit used:

```
change_speed(Speed s);  // better: the meaning of s is specified
// ...
change_speed(2.3);  // error: no unit
change_speed(23_m / 10s);  // meters per second
```

We could have accepted a plain (unit-less) double as a delta, but that would have been error-prone. If we wanted both absolute speed and deltas, we would have defined a Delta type.

Enforcement

Very hard in general.

- use const consistently (check if member functions modify their object; check if functions modify arguments passed by pointer or reference)
- flag uses of casts (casts neuter the type system)
- detect code that mimics the standard library (hard)

P.2: Write in ISO Standard C++

Reason

This is a set of guidelines for writing ISO Standard C++.

Note

There are environments where extensions are necessary, e.g., to access system resources. In such cases, localize the use of necessary extensions and control their use with non-core Coding Guidelines. If possible, build interfaces that encapsulate the extensions so they can be turned off or compiled away on systems that do not support those extensions.

Extensions often do not have rigorously defined semantics. Even extensions that are common and implemented by multiple compilers might have slightly different behaviors and edge case behavior as a direct result of *not* having a rigorous standard definition. With sufficient use of any such extension, expected portability will be impacted.

Note

Using valid ISO C++ does not guarantee portability (let alone correctness). Avoid dependence on undefined behavior (e.g., undefined order of evaluation) and be aware of constructs with implementation defined meaning (e.g., sizeof(int)).

Note

There are environments where restrictions on use of standard C++ language or library features are necessary, e.g., to avoid dynamic memory allocation as required by aircraft control software standards. In such cases, control their (dis)use with an extension of these Coding Guidelines customized to the specific environment.

Enforcement

Use an up-to-date C++ compiler (currently C++20 or C++17) with a set of options that do not accept extensions.

P.3: Express intent

Reason

Unless the intent of some code is stated (e.g., in names or comments), it is impossible to tell whether the code does what it is supposed to do.

Example

```
gsl::index i = 0;
while (i < v.size()) {
    // ... do something with v[i] ...
}</pre>
```

The intent of "just" looping over the elements of v is not expressed here. The implementation detail of an index is exposed (so that it might be misused), and i outlives the scope of the loop, which might or might not be intended. The reader cannot know from just this section of code.

Better:

```
for (const auto& x : v) { /* do something with the value of x */ }
```

Now, there is no explicit mention of the iteration mechanism, and the loop operates on a reference to const elements so that accidental modification cannot happen. If modification is desired, say so:

```
for (auto& x : v) { /* modify x */ }
```

For more details about for-statements, see ES.71. Sometimes better still, use a named algorithm. This example uses the for_each from the Ranges TS because it directly expresses the intent:

```
for_each(v, [](int x) { /* do something with the value of x */ }); for_each(par, v, [](int x) { /* do something with the value of x */ });
```

The last variant makes it clear that we are not interested in the order in which the elements of v are handled.

A programmer should be familiar with

- The guidelines support library
- The ISO C++ Standard Library
- Whatever foundation libraries are used for the current project(s)

Note

Alternative formulation: Say what should be done, rather than just how it should be done.

Note

Some language constructs express intent better than others.

Example

If two ints are meant to be the coordinates of a 2D point, say so:

Enforcement

Look for common patterns for which there are better alternatives

- simple for loops vs. range-for loops
- f(T*, int) interfaces vs. f(span<T>) interfaces
- loop variables in too large a scope
- naked new and delete
- functions with many parameters of built-in types

There is a huge scope for cleverness and semi-automated program transformation.

P.4: Ideally, a program should be statically type safe

Reason

Ideally, a program would be completely statically (compile-time) type safe. Unfortunately, that is not possible. Problem areas:

- unions
- casts
- array decay
- range errors
- narrowing conversions

Note

These areas are sources of serious problems (e.g., crashes and security violations). We try to provide alternative techniques.

Enforcement

We can ban, restrain, or detect the individual problem categories separately, as required and feasible for individual programs. Always suggest an alternative. For example:

- unions -- use variant (in C++17)
- casts -- minimize their use; templates can help
- array decay -- use span (from the GSL)
- range errors -- use span
- narrowing conversions -- minimize their use and use narrow or narrow_cast (from the GSL) where they are necessary

P.5: Prefer compile-time checking to run-time checking

Reason

Code clarity and performance. You don't need to write error handlers for errors caught at compile time.

Example

This example fails to achieve what it is trying to achieve (because overflow is undefined) and should be replaced with a simple static_assert:

```
// Int is an alias used for integers
static_assert(sizeof(Int) >= 4);  // do: compile-time check
```

Or better still just use the type system and replace Int with int32_t.

Example

```
void read(int* p, int n); // read max n integers into *p
int a[100];
read(a, 1000); // bad, off the end
```

better

```
void read(span<int> r); // read into the range of integers r
int a[100];
read(a); // better: let the compiler figure out the number of elements
```

Alternative formulation: Don't postpone to run time what can be done well at compile time.

Enforcement

- Look for pointer arguments.
- Look for run-time checks for range violations.

P.6: What cannot be checked at compile time should be checkable at run time

Reason

Leaving hard-to-detect errors in a program is asking for crashes and bad results.

Note

Ideally, we catch all errors (that are not errors in the programmer's logic) at either compile time or run time. It is impossible to catch all errors at compile time and often not affordable to catch all remaining errors at run time. However, we should endeavor to write programs that in principle can be checked, given sufficient resources (analysis programs, run-time checks, machine resources, time).

Example, bad

```
// separately compiled, possibly dynamically loaded
extern void f(int* p);

void g(int n)
{
    // bad: the number of elements is not passed to f()
    f(new int[n]);
}
```

Here, a crucial bit of information (the number of elements) has been so thoroughly "obscured" that static analysis is probably rendered infeasible and dynamic checking can be very difficult when f() is part of an ABI so that we cannot "instrument" that pointer. We could embed helpful information into the free store, but that requires global changes to a system and maybe to the compiler. What we have here is a design that makes error detection very hard.

Example, bad

We can of course pass the number of elements along with the pointer:

```
// separately compiled, possibly dynamically loaded
extern void f2(int* p, int n);

void g2(int n)
{
   f2(new int[n], m); // bad: a wrong number of elements can be passed to f()
}
```

Passing the number of elements as an argument is better (and far more common) than just passing the pointer and relying on some (unstated) convention for knowing or discovering the number of elements. However (as shown), a simple typo can introduce a serious error. The connection between the two arguments of f2() is conventional, rather than explicit.

Also, it is implicit that f2() is supposed to delete its argument (or did the caller make a second mistake?).

Example, bad

The standard library resource management pointers fail to pass the size when they point to an object:

```
// separately compiled, possibly dynamically loaded
// NB: this assumes the calling code is ABI-compatible, using a
// compatible C++ compiler and the same stdlib implementation
extern void f3(unique_ptr<int[]>, int n);

void g3(int n)
{
   f3(make_unique<int[]>(n), m);  // bad: pass ownership and size separately
}
```

Example

We need to pass the pointer and the number of elements as an integral object:

This design carries the number of elements along as an integral part of an object, so that errors are unlikely and dynamic (run-time) checking is always feasible, if not always affordable.

Example

How do we transfer both ownership and all information needed for validating use?

```
// OK: move
vector<int> f5(int n)
{
   vector<int> v(n);
   // ... initialize v ...
   return v;
}
unique_ptr<int[]> f6(int n)
                               // bad: loses n
    auto p = make_unique<int[]>(n);
   // ... initialize *p ...
   return p;
}
owner<int*> f7(int n) // bad: loses n and we might forget to delete
{
   owner<int*> p = new int[n];
   // ... initialize *p ...
   return p;
}
```

Example

- **???**
- show how possible checks are avoided by interfaces that pass polymorphic base classes around, when they actually know what they need? Or strings as "free-style" options

Enforcement

- Flag (pointer, count)-style interfaces (this will flag a lot of examples that can't be fixed for compatibility reasons)
- **???**

P.7: Catch run-time errors early

Reason

Avoid "mysterious" crashes. Avoid errors leading to (possibly unrecognized) wrong results.

Example

Here we made a small error in use1 that will lead to corrupted data or a crash. The (pointer, count)-style interface leaves increment1() with no realistic way of defending itself against out-of-range errors. If we could check subscripts for out of range access, then the error would not be discovered until p[10] was accessed. We could check earlier and improve the code:

```
void increment2(span<int> p)
{
    for (int& x : p) ++x;
}

void use2(int m)
{
    const int n = 10;
    int a[n] = {};
    // ...
    increment2({a, m});    // maybe typo, maybe m <= n is supposed
    // ...
}</pre>
```

Now, $m \le n$ can be checked at the point of call (early) rather than later. If all we had was a typo so that we meant to use n as the bound, the code could be further simplified (eliminating the possibility of an error):

```
void use3(int m)
{
   const int n = 10;
   int a[n] = {};
   // ...
   increment2(a); // the number of elements of a need not be repeated
   // ...
}
```

Example, bad

Don't repeatedly check the same value. Don't pass structured data as strings:

```
Date read_date(istream& is);  // read date from istream

Date extract_date(const string& s);  // extract date from string

void user1(const string& date)  // manipulate date
{
    auto d = extract_date(date);
    // ...
}

void user2()
{
    Date d = read_date(cin);
    // ...
    user1(d.to_string());
    // ...
}
```

The date is validated twice (by the Date constructor) and passed as a character string (unstructured data).

Example

Excess checking can be costly. There are cases where checking early is inefficient because you might never need the value, or might only need part of the value that is more easily checked than the whole. Similarly, don't add validity checks that change the asymptotic behavior of your interface (e.g., don't add a O(n) check to an interface with an average complexity of O(1)).

```
class Jet {
               // Physics says: e * e < x * x + y * y + z * z
   float x;
   float y;
   float z;
   float e;
    Jet(float x, float y, float z, float e)
        :x(x), y(y), z(z), e(e)
    {
        // Should I check here that the values are physically meaningful?
    }
   float m() const
        // Should I handle the degenerate case here?
        return sqrt(x * x + y * y + z * z - e * e);
    }
    ???
};
```

The physical law for a jet (e * e < x * x + y * y + z * z) is not an invariant because of the possibility for measurement errors.

???

Enforcement

- Look at pointers and arrays: Do range-checking early and not repeatedly
- Look at conversions: Eliminate or mark narrowing conversions
- Look for unchecked values coming from input
- Look for structured data (objects of classes with invariants) being converted into strings
- **???**

P.8: Don't leak any resources

Reason

Even a slow growth in resources will, over time, exhaust the availability of those resources. This is particularly important for long-running programs, but is an essential piece of responsible programming behavior.

Example, bad

```
void f(char* name)
{
    FILE* input = fopen(name, "r");
    // ...
    if (something) return; // bad: if something == true, a file handle is leaked
    // ...
    fclose(input);
}
```

Prefer RAII:

```
void f(char* name)
{
   ifstream input {name};
   // ...
   if (something) return; // OK: no leak
   // ...
}
```

See also: The resource management section

Note

A leak is colloquially "anything that isn't cleaned up." The more important classification is "anything that can no longer be cleaned up." For example, allocating an object on the heap and then losing the last pointer that points to that allocation. This rule should not be taken as requiring that allocations within long-lived objects must be returned during program shutdown. For example, relying on system guaranteed cleanup such as file closing and memory deallocation upon process shutdown can simplify code. However, relying on abstractions that implicitly clean up can be as simple, and often safer.

Note

Enforcing the lifetime safety profile eliminates leaks. When combined with resource safety provided by RAII, it eliminates the need for "garbage collection" (by generating no garbage). Combine this with enforcement of the type and bounds profiles and you get complete type- and resource-safety, guaranteed by tools.

Enforcement

- Look at pointers: Classify them into non-owners (the default) and owners. Where feasible, replace owners with standard-library resource handles (as in the example above). Alternatively, mark an owner as such using owner from the GSL.
- Look for naked new and delete
- Look for known resource allocating functions returning raw pointers (such as fopen, malloc, and strdup)

P.9: Don't waste time or space

Reason

This is C++.

Note

Time and space that you spend well to achieve a goal (e.g., speed of development, resource safety, or simplification of testing) is not wasted. "Another benefit of striving for efficiency is that the process forces you to understand the problem in more depth." - Alex Stepanov

Example, bad

```
struct X {
   char ch;
   int i;
   string s;
   char ch2;

   X& operator=(const X& a);
   X(const X&);
};

X waste(const char* p)
{
```

```
if (!p) throw Nullptr_error{};
    int n = strlen(p);
    auto buf = new char[n];
    if (!buf) throw Allocation error{};
    for (int i = 0; i < n; ++i) buf[i] = p[i];
    // ... manipulate buffer ...
   X x;
   x.ch = 'a';
                       // give x.s space for *p
   x.s = string(n);
   for (gsl::index i = 0; i < x.s.size(); ++i) x.s[i] = buf[i]; // copy buf into x.s
   delete[] buf;
    return x;
}
void driver()
{
   X x = waste("Typical argument");
    // ...
}
```

Yes, this is a caricature, but we have seen every individual mistake in production code, and worse. Note that the layout of X guarantees that at least 6 bytes (and most likely more) are wasted. The spurious definition of copy operations disables move semantics so that the return operation is slow (please note that the Return Value Optimization, RVO, is not guaranteed here). The use of new and delete for buf is redundant; if we really needed a local string, we should use a local string. There are several more performance bugs and gratuitous complication.

Example, bad

```
void lower(zstring s)
{
   for (int i = 0; i < strlen(s); ++i) s[i] = tolower(s[i]);
}</pre>
```

This is actually an example from production code. We can see that in our condition we have i < strlen(s). This expression will be evaluated on every iteration of the loop, which means that strlen must walk through string every loop to discover its length. While the string contents are changing, it's assumed that tolower will not affect the length of the string, so it's better to cache the length outside the loop and not incur that cost each iteration.

Note

An individual example of waste is rarely significant, and where it is significant, it is typically easily eliminated by an expert. However, waste spread liberally across a code base can easily be significant and experts are not always as available as we would like. The aim of this rule (and the more specific rules that support it) is to eliminate most waste related to the use of C++ before it happens. After that, we can look at waste related to algorithms and requirements, but that is beyond the scope of these guidelines.

Enforcement

Many more specific rules aim at the overall goals of simplicity and elimination of gratuitous waste.

• Flag an unused return value from a user-defined non-defaulted postfix operator++ or operator-- function. Prefer using the prefix form instead. (Note: "User-defined non-defaulted" is intended to reduce noise. Review this enforcement if it's still too noisy in practice.)

P.10: Prefer immutable data to mutable data

Reason

It is easier to reason about constants than about variables. Something immutable cannot change unexpectedly. Sometimes immutability enables better optimization. You can't have a data race on a constant.

See Con: Constants and immutability

P.11: Encapsulate messy constructs, rather than spreading through the code

Reason

Messy code is more likely to hide bugs and harder to write. A good interface is easier and safer to use. Messy, low-level code breeds more such code.

Example

```
int sz = 100;
int* p = (int*) malloc(sizeof(int) * sz);
int count = 0;
// ...
for (;;) {
    // ... read an int into x, exit loop if end of file is reached ...
    // ... check that x is valid ...
    if (count == sz)
        p = (int*) realloc(p, sizeof(int) * sz * 2);
    p[count++] = x;
    // ...
}
```

This is low-level, verbose, and error-prone. For example, we "forgot" to test for memory exhaustion. Instead, we could use vector:

Note

The standards library and the GSL are examples of this philosophy. For example, instead of messing with the arrays, unions, cast, tricky lifetime issues, gsl::owner, etc., that are needed to implement key abstractions, such as vector, span, lock_guard, and future, we use the libraries designed and implemented by people with more time and expertise than we usually have. Similarly, we can and should design and implement more specialized libraries, rather than leaving the users (often ourselves) with the challenge of repeatedly getting low-level code well. This is a variant of the subset of superset principle that underlies these guidelines.

Enforcement

■ Look for "messy code" such as complex pointer manipulation and casting outside the implementation of abstractions.

P.12: Use supporting tools as appropriate

Reason

There are many things that are done better "by machine". Computers don't tire or get bored by repetitive tasks. We typically have better things to do than repeatedly do routine tasks.

Example

Run a static analyzer to verify that your code follows the guidelines you want it to follow.

Note

See

- Static analysis tools
- Concurrency tools
- Testing tools

There are many other kinds of tools, such as source code repositories, build tools, etc., but those are beyond the scope of these guidelines.

Note

Be careful not to become dependent on over-elaborate or over-specialized tool chains. Those can make your otherwise portable code non-portable.

P.13: Use support libraries as appropriate

Reason

Using a well-designed, well-documented, and well-supported library saves time and effort; its quality and documentation are likely to be greater than what you could do if the majority of your time must be spent on an implementation. The cost (time, effort, money, etc.) of a library can be shared over many users. A widely used library is more likely to be kept up-to-date and ported to new systems than an individual application. Knowledge of a widely-used library can save time on other/future projects. So, if a suitable library exists for your application domain, use it.

Example

```
std::sort(begin(v), end(v), std::greater<>());
```

Unless you are an expert in sorting algorithms and have plenty of time, this is more likely to be correct and to run faster than anything you write for a specific application. You need a reason not to use the standard library (or whatever foundational libraries your application uses) rather than a reason to use it.

Note

By default use

- The ISO C++ Standard Library
- The Guidelines Support Library

Note

If no well-designed, well-documented, and well-supported library exists for an important domain, maybe you should design and implement it, and then use it.

I: Interfaces

An interface is a contract between two parts of a program. Precisely stating what is expected of a supplier of a service and a user of that service is essential. Having good (easy-to-understand, encouraging efficient use, not error-prone, supporting testing, etc.) interfaces is probably the most important single aspect of code organization.

Interface rule summary:

- I.1: Make interfaces explicit
- I.2: Avoid non-const global variables
- I.3: Avoid singletons
- I.4: Make interfaces precisely and strongly typed
- I.5: State preconditions (if any)
- I.6: Prefer Expects() for expressing preconditions
- I.7: State postconditions
- I.8: Prefer Ensures() for expressing postconditions
- I.9: If an interface is a template, document its parameters using concepts
- I.10: Use exceptions to signal a failure to perform a required task
- I.11: Never transfer ownership by a raw pointer (T*) or reference (T&)
- I.12: Declare a pointer that must not be null as not_null
- I.13: Do not pass an array as a single pointer
- I.22: Avoid complex initialization of global objects
- I.23: Keep the number of function arguments low
- I.24: Avoid adjacent parameters that can be invoked by the same arguments in either order with different meaning
- I.25: Prefer empty abstract classes as interfaces to class hierarchies
- I.26: If you want a cross-compiler ABI, use a C-style subset
- I.27: For stable library ABI, consider the Pimpl idiom
- I.30: Encapsulate rule violations

See also:

- F: Functions
- C.concrete: Concrete types
- C.hier: Class hierarchies
- C.over: Overloading and overloaded operators
- C.con: Containers and other resource handles
- E: Error handling
- T: Templates and generic programming

I.1: Make interfaces explicit

Reason

Correctness. Assumptions not stated in an interface are easily overlooked and hard to test.

Example, bad

Controlling the behavior of a function through a global (namespace scope) variable (a call mode) is implicit and potentially confusing. For example:

```
int round(double d)
{
   return (round_up) ? ceil(d) : d; // don't: "invisible" dependency
}
```

It will not be obvious to a caller that the meaning of two calls of round(7.2) might give different results.

Exception

Sometimes we control the details of a set of operations by an environment variable, e.g., normal vs. verbose output or debug vs. optimized. The use of a non-local control is potentially confusing, but controls only implementation details of otherwise fixed semantics.

Example, bad

Reporting through non-local variables (e.g., errno) is easily ignored. For example:

```
// don't: no test of fprintf's return value
fprintf(connection, "logging: %d %d %d\n", x, y, s);
```

What if the connection goes down so that no logging output is produced? See I.???.

Alternative: Throw an exception. An exception cannot be ignored.

Alternative formulation: Avoid passing information across an interface through non-local or implicit state. Note that non-const member functions pass information to other member functions through their object's state.

Alternative formulation: An interface should be a function or a set of functions. Functions can be function templates and sets of functions can be classes or class templates.

Enforcement

- (Simple) A function should not make control-flow decisions based on the values of variables declared at namespace scope.
- (Simple) A function should not write to variables declared at namespace scope.

I.2: Avoid non-const global variables

Reason

Non-const global variables hide dependencies and make the dependencies subject to unpredictable changes.

Example

```
struct Data {
    // ... lots of stuff ...
} data;    // non-const data

void compute()    // don't
{
    // ... use data ...
}

void output()    // don't
{
    // ... use data ...
}
```

Who else might modify data?

Warning: The initialization of global objects is not totally ordered. If you use a global object initialize it with a constant. Note that it is possible to get undefined initialization order even for const objects.

Exception

A global object is often better than a singleton.

Note

Global constants are useful.

Note

The rule against global variables applies to namespace scope variables as well.

Alternative: If you use global (more generally namespace scope) data to avoid copying, consider passing the data as an object by reference to const. Another solution is to define the data as the state of some object and the operations as member functions.

Warning: Beware of data races: If one thread can access non-local data (or data passed by reference) while another thread executes the callee, we can have a data race. Every pointer or reference to mutable data is a potential data race.

Using global pointers or references to access and change non-const, and otherwise non-global, data isn't a better alternative to non-const global variables since that doesn't solve the issues of hidden dependencies or potential race conditions.

Note

You cannot have a race condition on immutable data.

References: See the rules for calling functions.

Note

The rule is "avoid", not "don't use." Of course there will be (rare) exceptions, such as cin, cout, and cerr.

Enforcement

(Simple) Report all non-const variables declared at namespace scope and global pointers/references to non-const data.

I.3: Avoid singletons

Reason

Singletons are basically complicated global objects in disguise.

Example

```
class Singleton {
    // ... lots of stuff to ensure that only one Singleton object is created,
    // that it is initialized properly, etc.
};
```

There are many variants of the singleton idea. That's part of the problem.

Note

If you don't want a global object to change, declare it const or constexpr.

Exception

You can use the simplest "singleton" (so simple that it is often not considered a singleton) to get initialization on first use, if any:

```
X& myX()
{
    static X my_x {3};
    return my_x;
}
```

This is one of the most effective solutions to problems related to initialization order. In a multi-threaded environment, the initialization of the static object does not introduce a race condition (unless you carelessly access a shared object from within its constructor).

Note that the initialization of a local static does not imply a race condition. However, if the destruction of X involves an operation that needs to be synchronized we must use a less simple solution. For example:

```
X& myX()
{
    static auto p = new X {3};
    return *p; // potential leak
}
```

Now someone must delete that object in some suitably thread-safe way. That's error-prone, so we don't use that technique unless

- myX is in multi-threaded code,
- that X object needs to be destroyed (e.g., because it releases a resource), and
- X's destructor's code needs to be synchronized.

If you, as many do, define a singleton as a class for which only one object is created, functions like myX are not singletons, and this useful technique is not an exception to the no-singleton rule.

Enforcement

Very hard in general.

- Look for classes with names that include singleton.
- Look for classes for which only a single object is created (by counting objects or by examining constructors).
- If a class X has a public static function that contains a function-local static of the class' type X and returns a pointer or reference to it, ban that.

I.4: Make interfaces precisely and strongly typed

Reason

Types are the simplest and best documentation, improve legibility due to their well-defined meaning, and are checked at compile time. Also, precisely typed code is often optimized better.

Example, don't

Consider:

```
void pass(void* data); // weak and under qualified type void* is suspicious
```

Callers are unsure what types are allowed and if the data may be mutated as const is not specified. Note all pointer types implicitly convert to void*, so it is easy for callers to provide this value.

The callee must static_cast data to an unverified type to use it. That is error-prone and verbose.

Only use const void* for passing in data in designs that are indescribable in C++. Consider using a variant or a pointer to base instead.

Alternative: Often, a template parameter can eliminate the void* turning it into a T* or T&. For generic code these Ts can be general or concept constrained template parameters.

Example, bad

Consider:

```
draw_rect(100, 200, 100, 500); // what do the numbers specify?
draw_rect(p.x, p.y, 10, 20); // what units are 10 and 20 in?
```

It is clear that the caller is describing a rectangle, but it is unclear what parts they relate to. Also, an int can carry arbitrary forms of information, including values of many units, so we must guess about the meaning of the four ints. Most likely, the first two are an x,y coordinate pair, but what are the last two?

Comments and parameter names can help, but we could be explicit:

```
void draw_rectangle(Point top_left, Point bottom_right);
void draw_rectangle(Point top_left, Size height_width);

draw_rectangle(p, Point{10, 20}); // two corners
draw_rectangle(p, Size{10, 20}); // one corner and a (height, width) pair
```

Obviously, we cannot catch all errors through the static type system (e.g., the fact that a first argument is supposed to be a top-left point is left to convention (naming and comments)).

Example, bad

Consider:

```
set_settings(true, false, 42); // what do the numbers specify?
```

The parameter types and their values do not communicate what settings are being specified or what those values mean.

This design is more explicit, safe and legible:

```
alarm_settings s{};
s.enabled = true;
s.displayMode = alarm_settings::mode::spinning_light;
s.frequency = alarm_settings::every_10_seconds;
set_settings(s);
```

For the case of a set of boolean values consider using a flags enum; a pattern that expresses a set of boolean values.

```
enable_lamp_options(lamp_option::on | lamp_option::animate_state_transitions);
```

Example, bad

In the following example, it is not clear from the interface what time_to_blink means: Seconds? Milliseconds?

```
void blink_led(int time_to_blink) // bad -- the unit is ambiguous
{
    // ...
    // do something with time_to_blink
    // ...
}

void use()
{
    blink_led(2);
}
```

Example, good

std::chrono::duration types helps making the unit of time duration explicit.

```
void blink_led(milliseconds time_to_blink) // good -- the unit is explicit
{
          // ...
          // do something with time_to_blink
          // ...
}

void use()
{
         blink_led(1500ms);
}
```

The function can also be written in such a way that it will accept any time duration unit.

```
template<class rep, class period>
void blink_led(duration<rep, period> time_to_blink) // good -- accepts any unit
{
    // assuming that millisecond is the smallest relevant unit
    auto milliseconds_to_blink = duration_cast<milliseconds>(time_to_blink);
    // ...
    // do something with milliseconds_to_blink
    // ...
}

void use()
{
    blink_led(2s);
    blink_led(1500ms);
}
```

Enforcement

- (Simple) Report the use of void* as a parameter or return type.
- (Simple) Report the use of more than one bool parameter.
- (Hard to do well) Look for functions that use too many primitive type arguments.

I.5: State preconditions (if any)

Reason

Arguments have meaning that might constrain their proper use in the callee.

Example

Consider:

```
double sqrt(double x);
```

Here x must be non-negative. The type system cannot (easily and naturally) express that, so we must use other means. For example:

```
double sqrt(double x); // x must be non-negative
```

Some preconditions can be expressed as assertions. For example:

```
double sqrt(double x) { Expects(x >= 0); /* ... */ }
```

Ideally, that Expects(x >= 0) should be part of the interface of sqrt() but that's not easily done. For now, we place it in the definition (function body).

References: Expects() is described in GSL.

Note

Prefer a formal specification of requirements, such as Expects(p); If that is infeasible, use English text in comments, such as // the sequence [p:q) is ordered using <.

Note

Most member functions have as a precondition that some class invariant holds. That invariant is established by a constructor and must be reestablished upon exit by every member function called from outside the class. We don't need to mention it for each member function.

Enforcement

(Not enforceable)

See also: The rules for passing pointers. ???

I.6: Prefer Expects() for expressing preconditions

Reason

To make it clear that the condition is a precondition and to enable tool use.

Example

Note

Preconditions can be stated in many ways, including comments, if-statements, and assert(). This can make them hard to distinguish from ordinary code, hard to update, hard to manipulate by tools, and might have the wrong semantics (do you always want to abort in debug mode and check nothing in productions runs?).

Note

Preconditions should be part of the interface rather than part of the implementation, but we don't yet have the language facilities to do that. Once language support becomes available (e.g., see the contract proposal) we will adopt the standard version of preconditions, postconditions, and assertions.

Note

Expects() can also be used to check a condition in the middle of an algorithm.

Note

No, using unsigned is not a good way to sidestep the problem of ensuring that a value is non-negative.

Enforcement

(Not enforceable) Finding the variety of ways preconditions can be asserted is not feasible. Warning about those that can be easily identified (assert()) has questionable value in the absence of a language facility.

I.7: State postconditions

Reason

To detect misunderstandings about the result and possibly catch erroneous implementations.

Example, bad

Consider:

```
int area(int height, int width) { return height * width; } // bad
```

Here, we (incautiously) left out the precondition specification, so it is not explicit that height and width must be positive. We also left out the postcondition specification, so it is not obvious that the algorithm (height * width) is wrong for areas larger than the largest integer. Overflow can happen. Consider using:

```
int area(int height, int width)
{
   auto res = height * width;
   Ensures(res > 0);
   return res;
}
```

Example, bad

Consider a famous security bug:

```
void f() // problematic
{
   char buffer[MAX];
   // ...
   memset(buffer, 0, sizeof(buffer));
}
```

There was no postcondition stating that the buffer should be cleared and the optimizer eliminated the apparently redundant memset() call:

```
void f() // better
{
    char buffer[MAX];
    // ...
    memset(buffer, 0, sizeof(buffer));
    Ensures(buffer[0] == 0);
}
```

Note

Postconditions are often informally stated in a comment that states the purpose of a function; Ensures() can be used to make this more systematic, visible, and checkable.

Note

Postconditions are especially important when they relate to something that is not directly reflected in a returned result, such as a state of a data structure used.

Example

Consider a function that manipulates a Record, using a mutex to avoid race conditions:

```
mutex m;

void manipulate(Record& r) // don't
{
    m.lock();
    // ... no m.unlock() ...
}
```

Here, we "forgot" to state that the mutex should be released, so we don't know if the failure to ensure release of the mutex was a bug or a feature. Stating the postcondition would have made it clear:

```
void manipulate(Record& r) // postcondition: m is unlocked upon exit
{
    m.lock();
    // ... no m.unlock() ...
}
```

The bug is now obvious (but only to a human reading comments).

Better still, use RAII to ensure that the postcondition ("the lock must be released") is enforced in code:

```
void manipulate(Record& r) // best
{
    lock_guard<mutex> _ {m};
    // ...
}
```

Note

Ideally, postconditions are stated in the interface/declaration so that users can easily see them. Only postconditions related to the users can be stated in the interface. Postconditions related only to internal state belongs in the definition/implementation.

(Not enforceable) This is a philosophical guideline that is infeasible to check directly in the general case. Domain specific checkers (like lock-holding checkers) exist for many toolchains.

I.8: Prefer Ensures() for expressing postconditions

Reason

To make it clear that the condition is a postcondition and to enable tool use.

Example

```
void f()
{
    char buffer[MAX];
    // ...
    memset(buffer, 0, MAX);
    Ensures(buffer[0] == 0);
}
```

Note

Postconditions can be stated in many ways, including comments, if-statements, and assert(). This can make them hard to distinguish from ordinary code, hard to update, hard to manipulate by tools, and might have the wrong semantics.

Alternative: Postconditions of the form "this resource must be released" are best expressed by RAII.

Note

Ideally, that Ensures should be part of the interface, but that's not easily done. For now, we place it in the definition (function body). Once language support becomes available (e.g., see the contract proposal) we will adopt the standard version of preconditions, postconditions, and assertions.

Enforcement

(Not enforceable) Finding the variety of ways postconditions can be asserted is not feasible. Warning about those that can be easily identified (assert()) has questionable value in the absence of a language facility.

I.9: If an interface is a template, document its parameters using concepts

Reason

Make the interface precisely specified and compile-time checkable in the (not so distant) future.

Example

Use the C++20 style of requirements specification. For example:

```
template<typename Iter, typename Val>
    requires input_iterator<Iter> && equality_comparable_with<iter_value_t<Iter>, Val>
Iter find(Iter first, Iter last, Val v)
{
    // ...
}
```

See also: Generic programming and concepts.

Enforcement

Warn if any non-variadic template parameter is not constrained by a concept (in its declaration or mentioned in a requires clause).

I.10: Use exceptions to signal a failure to perform a required task

Reason

It should not be possible to ignore an error because that could leave the system or a computation in an undefined (or unexpected) state. This is a major source of errors.

Example

```
int printf(const char* ...);  // bad: return negative number if output fails

template<class F, class ...Args>
// good: throw system_error if unable to start the new thread
explicit thread(F&& f, Args&&... args);
```

Note

What is an error?

An error means that the function cannot achieve its advertised purpose (including establishing postconditions). Calling code that ignores an error could lead to wrong results or undefined systems state. For example, not being able to connect to a remote server is not by itself an error: the server can refuse a connection for all kinds of reasons, so the natural thing is to return a result that the caller should always check. However, if failing to make a

connection is considered an error, then a failure should throw an exception.

Exception

Many traditional interface functions (e.g., UNIX signal handlers) use error codes (e.g., errno) to report what are really status codes, rather than errors. You don't have a good alternative to using such, so calling these does not violate the rule.

Alternative

If you can't use exceptions (e.g., because your code is full of old-style raw-pointer use or because there are hard-real-time constraints), consider using a style that returns a pair of values:

```
int val;
int error_code;
tie(val, error_code) = do_something();
if (error_code) {
    // ... handle the error or exit ...
}
// ... use val ...
```

This style unfortunately leads to uninitialized variables. Since C++17 the "structured bindings" feature can be used to initialize variables directly from the return value:

```
auto [val, error_code] = do_something();
if (error_code) {
    // ... handle the error or exit ...
}
// ... use val ...
```

Note

We don't consider "performance" a valid reason not to use exceptions.

- Often, explicit error checking and handling consume as much time and space as exception handling.
- Often, cleaner code yields better performance with exceptions (simplifying the tracing of paths through the program and their optimization).
- A good rule for performance critical code is to move checking outside the critical part of the code.
- In the longer term, more regular code gets better optimized.
- Always carefully measure before making performance claims.

See also: I.5 and I.7 for reporting precondition and postcondition violations.

Enforcement

- (Not enforceable) This is a philosophical guideline that is infeasible to check directly.
- Look for errno.

I.11: Never transfer ownership by a raw pointer (T*) or reference (T&)

Reason

If there is any doubt whether the caller or the callee owns an object, leaks or premature destruction will occur.

Example

Consider:

Who deletes the returned X? The problem would be harder to spot if compute returned a reference. Consider returning the result by value (use move semantics if the result is large):

```
vector<double> compute(args) // good
{
    vector<double> res(10000);
    // ...
    return res;
}
```

Alternative: Pass ownership using a "smart pointer", such as unique_ptr (for exclusive ownership) and shared_ptr (for shared ownership). However, that is less elegant and often less efficient than returning the object itself, so use smart pointers only if reference semantics are needed.

Alternative: Sometimes older code can't be modified because of ABI compatibility requirements or lack of resources. In that case, mark owning pointers using owner from the guidelines support library:

```
owner<X*> compute(args)  // It is now clear that ownership is transferred
{
   owner<X*> res = new X{};
   // ...
   return res;
}
```

This tells analysis tools that res is an owner. That is, its value must be deleted or transferred to another owner, as is done here by the return.

owner is used similarly in the implementation of resource handles.

Note

Every object passed as a raw pointer (or iterator) is assumed to be owned by the caller, so that its lifetime is handled by the caller. Viewed another way: ownership transferring APIs are relatively rare compared to pointerpassing APIs, so the default is "no ownership transfer."

See also: Argument passing, use of smart pointer arguments, and value return.

Enforcement

- (Simple) Warn on delete of a raw pointer that is not an owner<T>. Suggest use of standard-library resource handle or use of owner<T>.
- (Simple) Warn on failure to either reset or explicitly delete an owner pointer on every code path.
- (Simple) Warn if the return value of new or a function call with an owner return value is assigned to a raw pointer or non-owner reference.

I.12: Declare a pointer that must not be null as not_null

Reason

To help avoid dereferencing nullptr errors. To improve performance by avoiding redundant checks for nullptr.

Example

By stating the intent in source, implementers and tools can provide better diagnostics, such as finding some classes of errors through static analysis, and perform optimizations, such as removing branches and null tests.

Note

not_null is defined in the guidelines support library.

Note

The assumption that the pointer to char pointed to a C-style string (a zero-terminated string of characters) was still implicit, and a potential source of confusion and errors. Use czstring in preference to const char*.

```
// we can assume that p cannot be nullptr
// we can assume that p points to a zero-terminated array of characters
int length(not_null<czstring> p);
```

Note: length() is, of course, std::strlen() in disguise.

Enforcement

- (Simple) ((Foundation)) If a function checks a pointer parameter against nullptr before access, on all control-flow paths, then warn it should be declared not_null.
- (Complex) If a function with pointer return value ensures it is not nullptr on all return paths, then warn the return type should be declared not_null.

I.13: Do not pass an array as a single pointer

Reason

(pointer, size)-style interfaces are error-prone. Also, a plain pointer (to array) must rely on some convention to allow the callee to determine the size.

Example

Consider:

```
void copy_n(const T* p, T* q, int n); // copy from [p:p+n) to [q:q+n)
```

What if there are fewer than n elements in the array pointed to by q? Then, we overwrite some probably unrelated memory. What if there are fewer than n elements in the array pointed to by p? Then, we read some probably unrelated memory. Either is undefined behavior and a potentially very nasty bug.

Alternative

Consider using explicit spans:

```
void copy(span<const T> r, span<T> r2); // copy r to r2
```

Example, bad

Consider:

```
void draw(Shape* p, int n); // poor interface; poor code
Circle arr[10];
// ...
draw(arr, 10);
```

Passing 10 as the n argument might be a mistake: the most common convention is to assume [0:n) but that is nowhere stated. Worse is that the call of draw() compiled at all: there was an implicit conversion from array to pointer (array decay) and then another implicit conversion from Circle to Shape. There is no way that draw() can safely iterate through that array: it has no way of knowing the size of the elements.

Alternative: Use a support class that ensures that the number of elements is correct and prevents dangerous implicit conversions. For example:

```
void draw2(span<Circle>);
Circle arr[10];
// ...
draw2(span<Circle>(arr)); // deduce the number of elements
draw2(arr); // deduce the element type and array size

void draw3(span<Shape>);
draw3(arr); // error: cannot convert Circle[10] to span<Shape>
```

This draw2() passes the same amount of information to draw(), but makes the fact that it is supposed to be a range of Circles explicit. See ???.

Exception

Use zstring and czstring to represent C-style, zero-terminated strings. But when doing so, use std::string_view or span<char> from the GSL to prevent range errors.

Enforcement

- (Simple) ((Bounds)) Warn for any expression that would rely on implicit conversion of an array type to a pointer type. Allow exception for zstring/czstring pointer types.
- (Simple) ((Bounds)) Warn for any arithmetic operation on an expression of pointer type that results in a value of pointer type. Allow exception for zstring/czstring pointer types.

I.22: Avoid complex initialization of global objects

Reason

Complex initialization can lead to undefined order of execution.

Example

```
// file1.c
extern const X x;
const Y y = f(x); // read x; write y
// file2.c
extern const Y y;
const X x = g(y); // read y; write x
```

Since x and y are in different translation units the order of calls to f() and g() is undefined; one will access an uninitialized const. This shows that the order-of-initialization problem for global (namespace scope) objects is not limited to global *variables*.

Note

Order of initialization problems become particularly difficult to handle in concurrent code. It is usually best to avoid global (namespace scope) objects altogether.

Enforcement

- Flag initializers of globals that call non-constexpr functions
- Flag initializers of globals that access extern objects

I.23: Keep the number of function arguments low

Reason

Having many arguments opens opportunities for confusion. Passing lots of arguments is often costly compared to alternatives.

Discussion

The two most common reasons why functions have too many parameters are:

- 1. *Missing an abstraction*. There is an abstraction missing, so that a compound value is being passed as individual elements instead of as a single object that enforces an invariant. This not only expands the parameter list, but it leads to errors because the component values are no longer protected by an enforced invariant.
- 2. *Violating "one function, one responsibility."* The function is trying to do more than one job and should probably be refactored.

Example

The standard-library merge() is at the limit of what we can comfortably handle:

Note that this is because of problem 1 above -- missing abstraction. Instead of passing a range (abstraction), STL passed iterator pairs (unencapsulated component values).

Here, we have four template arguments and six function arguments. To simplify the most frequent and simplest uses, the comparison argument can be defaulted to <:

This doesn't reduce the total complexity, but it reduces the surface complexity presented to many users. To really reduce the number of arguments, we need to bundle the arguments into higher-level abstractions:

```
template<class InputRange1, class InputRange2, class OutputIterator>
OutputIterator merge(InputRange1 r1, InputRange2 r2, OutputIterator result);
```

Grouping arguments into "bundles" is a general technique to reduce the number of arguments and to increase the opportunities for checking.

Alternatively, we could use a standard library concept to define the notion of three types that must be usable for merging:

```
template<class In1, class In2, class Out>
  requires mergeable<In1, In2, Out>
Out merge(In1 r1, In2 r2, Out result);
```

Example

The safety Profiles recommend replacing

```
void f(int* some_ints, int some_ints_length); // BAD: C style, unsafe
```

with

Here, using an abstraction has safety and robustness benefits, and naturally also reduces the number of parameters.

Note

How many parameters are too many? Try to use fewer than four (4) parameters. There are functions that are best expressed with four individual parameters, but not many.

Alternative: Use better abstraction: Group arguments into meaningful objects and pass the objects (by value or by reference).

Alternative: Use default arguments or overloads to allow the most common forms of calls to be done with fewer arguments.

- Warn when a function declares two iterators (including pointers) of the same type instead of a range or a view.
- (Not enforceable) This is a philosophical guideline that is infeasible to check directly.

I.24: Avoid adjacent parameters that can be invoked by the same arguments in either order with different meaning

Reason

Adjacent arguments of the same type are easily swapped by mistake.

Example, bad

Consider:

```
void copy_n(T* p, T* q, int n); // copy from [p:p + n) to [q:q + n)
```

This is a nasty variant of a K&R C-style interface. It is easy to reverse the "to" and "from" arguments.

Use const for the "from" argument:

```
void copy_n(const T* p, T* q, int n); // copy from [p:p + n) to [q:q + n)
```

Exception

If the order of the parameters is not important, there is no problem:

```
int max(int a, int b);
```

Alternative

Don't pass arrays as pointers, pass an object representing a range (e.g., a span):

```
void copy_n(span<const T> p, span<T> q); // copy from p to q
```

Alternative

Define a struct as the parameter type and name the fields for those parameters accordingly:

```
struct SystemParams {
    string config_file;
    string output_path;
    seconds timeout;
};
void initialize(SystemParams p);
```

This tends to make invocations of this clear to future readers, as the parameters are often filled in by name at the call site.

Note

Only the interface's designer can adequately address the source of violations of this guideline.

Enforcement strategy

(Simple) Warn if two consecutive parameters share the same type

We are still looking for a less-simple enforcement.

I.25: Prefer empty abstract classes as interfaces to class hierarchies

Reason

Abstract classes that are empty (have no non-static member data) are more likely to be stable than base classes with state.

Example, bad

You just knew that Shape would turn up somewhere :-)

```
class Shape { // bad: interface class loaded with data
public:
    Point center() const { return c; }
    virtual void draw() const;
    virtual void rotate(int);
    // ...
private:
    Point c;
    vector<Point> outline;
    Color col;
};
```

This will force every derived class to compute a center -- even if that's non-trivial and the center is never used. Similarly, not every Shape has a Color, and many Shapes are best represented without an outline defined as a sequence of Points. Using an abstract class is better:

```
class Shape {    // better: Shape is a pure interface
public:
    virtual Point center() const = 0;    // pure virtual functions
    virtual void draw() const = 0;
    virtual void rotate(int) = 0;
    // ...
    // ...
    // ...
    virtual ~Shape() = default;
};
```

(Simple) Warn if a pointer/reference to a class C is assigned to a pointer/reference to a base of C and the base class contains data members.

I.26: If you want a cross-compiler ABI, use a C-style subset

Reason

Different compilers implement different binary layouts for classes, exception handling, function names, and other implementation details.

Exception

Common ABIs are emerging on some platforms freeing you from the more draconian restrictions.

Note

If you use a single compiler, you can use full C++ in interfaces. That might require recompilation after an upgrade to a new compiler version.

Enforcement

(Not enforceable) It is difficult to reliably identify where an interface forms part of an ABI.

I.27: For stable library ABI, consider the Pimpl idiom

Reason

Because private data members participate in class layout and private member functions participate in overload resolution, changes to those implementation details require recompilation of all users of a class that uses them. A non-polymorphic interface class holding a pointer to implementation (Pimpl) can isolate the users of a class from changes in its implementation at the cost of an indirection.

Example

interface (widget.h)

```
class widget {
    class impl;
    std::unique_ptr<impl> pimpl;
public:
    void draw(); // public API that will be forwarded to the implementation
    widget(int); // defined in the implementation file
    ~widget(); // defined in the implementation file, where impl is a complete type
    widget(widget&&) noexcept; // defined in the implementation file
    widget(const widget&) = delete;
    widget& operator=(widget&&) noexcept; // defined in the implementation file
    widget& operator=(const widget&) = delete;
};
```

implementation (widget.cpp)

```
class widget::impl {
    int n; // private data
public:
    void draw(const widget& w) { /* ... */ }
    impl(int n) : n(n) {}
};
void widget::draw() { pimpl->draw(*this); }
widget::widget(int n) : pimpl{std::make_unique<impl>(n)} {}
widget::widget(widget&&) noexcept = default;
widget::~widget() = default;
widget& widget::operator=(widget&&) noexcept = default;
```

Notes

See GOTW #100 and cppreference for the trade-offs and additional implementation details associated with this idiom.

Enforcement

(Not enforceable) It is difficult to reliably identify where an interface forms part of an ABI.

I.30: Encapsulate rule violations

Reason

To keep code simple and safe. Sometimes, ugly, unsafe, or error-prone techniques are necessary for logical or performance reasons. If so, keep them local, rather than "infecting" interfaces so that larger groups of programmers have to be aware of the subtleties. Implementation complexity should, if at all possible, not leak through interfaces into user code.

Example

Consider a program that, depending on some form of input (e.g., arguments to main), should consume input from a file, from the command line, or from standard input. We might write

This violated the rule against uninitialized variables, the rule against ignoring ownership, and the rule against magic constants. In particular, someone has to remember to somewhere write

```
if (owned) delete inp;
```

We could handle this particular example by using unique_ptr with a special deleter that does nothing for cin, but that's complicated for novices (who can easily encounter this problem) and the example is an example of a more general problem where a property that we would like to consider static (here, ownership) needs infrequently be addressed at run time. The common, most frequent, and safest examples can be handled statically, so we don't want to add cost and complexity to those. But we must also cope with the uncommon, less-safe, and necessarily more expensive cases. Such examples are discussed in [Str15].

So, we write a class

```
class Istream { [[gsl::suppress(lifetime)]]
public:
    enum Opt { from_line = 1 };
    Istream() { }
    Istream(czstring p) : owned{true}, inp{new ifstream{p}} {} // read from file
    Istream(czstring p, Opt) : owned{true}, inp{new istringstream{p}} {} // read from command
line
    ~Istream() { if (owned) delete inp; }
    operator istream&() { return *inp; }

private:
    bool owned = false;
    istream* inp = &cin;
};
```

Now, the dynamic nature of istream ownership has been encapsulated. Presumably, a bit of checking for potential errors would be added in real code.

Enforcement

- Hard, it is hard to decide what rule-breaking code is essential
- Flag rule suppression that enable rule-violations to cross interfaces

F: Functions

A function specifies an action or a computation that takes the system from one consistent state to the next. It is the fundamental building block of programs.

It should be possible to name a function meaningfully, to specify the requirements of its argument, and clearly state the relationship between the arguments and the result. An implementation is not a specification. Try to think about what a function does as well as about how it does it. Functions are the most critical part in most interfaces, so see the interface rules.

Function rule summary:

Function definition rules:

- F.1: "Package" meaningful operations as carefully named functions
- F.2: A function should perform a single logical operation
- F.3: Keep functions short and simple
- F.4: If a function might have to be evaluated at compile time, declare it constexpr
- F.5: If a function is very small and time-critical, declare it inline
- F.6: If your function must not throw, declare it noexcept
- F.7: For general use, take T* or T& arguments rather than smart pointers
- F.8: Prefer pure functions
- F.9: Unused parameters should be unnamed
- F.10: If an operation can be reused, give it a name
- F.11: Use an unnamed lambda if you need a simple function object in one place only

Parameter passing expression rules:

- F.15: Prefer simple and conventional ways of passing information
- F.16: For "in" parameters, pass cheaply-copied types by value and others by reference to const
- F.17: For "in-out" parameters, pass by reference to non-const
- F.18: For "will-move-from" parameters, pass by X&& and std::move the parameter
- F.19: For "forward" parameters, pass by TP&& and only std::forward the parameter
- F.20: For "out" output values, prefer return values to output parameters
- F.21: To return multiple "out" values, prefer returning a struct or tuple
- F.60: Prefer T* over T& when "no argument" is a valid option

Parameter passing semantic rules:

■ F.22: Use T* or owner<T*> to designate a single object

- F.23: Use a not null<T> to indicate that "null" is not a valid value
- F.24: Use a span<T> or a span_p<T> to designate a half-open sequence
- F.25: Use a zstring or a not null<zstring> to designate a C-style string
- F.26: Use a unique_ptr<T> to transfer ownership where a pointer is needed
- F.27: Use a shared_ptr<T> to share ownership

Value return semantic rules:

- F.42: Return a T* to indicate a position (only)
- F.43: Never (directly or indirectly) return a pointer or a reference to a local object
- F.44: Return a T& when copy is undesirable and "returning no object" isn't needed
- F.45: Don't return a T&&
- F.46: int is the return type for main()
- F.47: Return T& from assignment operators
- F.48: Don't return std::move(local)
- F.49: Don't return const T

Other function rules:

- F.50: Use a lambda when a function won't do (to capture local variables, or to write a local function)
- F.51: Where there is a choice, prefer default arguments over overloading
- F.52: Prefer capturing by reference in lambdas that will be used locally, including passed to algorithms
- F.53: Avoid capturing by reference in lambdas that will be used non-locally, including returned, stored on the heap, or passed to another thread
- F.54: When writing a lambda that captures this or any class data member, don't use [=] default capture
- F.55: Don't use va_arg arguments
- F.56: Avoid unnecessary condition nesting

Functions have strong similarities to lambdas and function objects.

See also: C.lambdas: Function objects and lambdas

F.def: Function definitions

A function definition is a function declaration that also specifies the function's implementation, the function body.

F.1: "Package" meaningful operations as carefully named functions

Reason

Factoring out common code makes code more readable, more likely to be reused, and limit errors from complex code. If something is a well-specified action, separate it out from its surrounding code and give it a name.

Example, don't

```
void read_and_print(istream& is)  // read and print an int
{
   int x;
   if (is >> x)
      cout << "the int is " << x << '\n';
   else
      cerr << "no int on input\n";
}</pre>
```

Almost everything is wrong with read_and_print. It reads, it writes (to a fixed ostream), it writes error messages (to a fixed ostream), it handles only ints. There is nothing to reuse, logically separate operations are intermingled and local variables are in scope after the end of their logical use. For a tiny example, this looks OK, but if the input operation, the output operation, and the error handling had been more complicated the tangled mess could become hard to understand.

Note

If you write a non-trivial lambda that potentially can be used in more than one place, give it a name by assigning it to a (usually non-local) variable.

Example

```
sort(a, b, [](T x, T y) { return x.rank() < y.rank() && x.value() < y.value(); });</pre>
```

Naming that lambda breaks up the expression into its logical parts and provides a strong hint to the meaning of the lambda.

```
auto lessT = [](T x, T y) { return x.rank() < y.rank() && x.value() < y.value(); };
sort(a, b, lessT);</pre>
```

The shortest code is not always the best for performance or maintainability.

Exception

Loop bodies, including lambdas used as loop bodies, rarely need to be named. However, large loop bodies (e.g., dozens of lines or dozens of pages) can be a problem. The rule Keep functions short and simple implies "Keep loop bodies short." Similarly, lambdas used as callback arguments are sometimes non-trivial, yet unlikely to be reusable.

Enforcement

- See Keep functions short and simple
- Flag identical and very similar lambdas used in different places.

F.2: A function should perform a single logical operation

Reason

A function that performs a single operation is simpler to understand, test, and reuse.

Example

Consider:

```
void read_and_print()  // bad
{
   int x;
   cin >> x;
   // check for errors
   cout << x << "\n";
}</pre>
```

This is a monolith that is tied to a specific input and will never find another (different) use. Instead, break functions up into suitable logical parts and parameterize:

```
int read(istream& is)  // better
{
   int x;
   is >> x;
   // check for errors
   return x;
}

void print(ostream& os, int x)
{
   os << x << "\n";
}</pre>
```

These can now be combined where needed:

```
void read_and_print()
{
    auto x = read(cin);
    print(cout, x);
}
```

If there was a need, we could further templatize read() and print() on the data type, the I/O mechanism, the response to errors, etc. Example:

```
auto read = [](auto& input, auto& value) // better
{
    input >> value;
    // check for errors
};

void print(auto& output, const auto& value)
{
    output << value << "\n";
}</pre>
```

- Consider functions with more than one "out" parameter suspicious. Use return values instead, including tuple for multiple return values.
- Consider "large" functions that don't fit on one editor screen suspicious. Consider factoring such a function into smaller well-named suboperations.
- Consider functions with 7 or more parameters suspicious.

F.3: Keep functions short and simple

Reason

Large functions are hard to read, more likely to contain complex code, and more likely to have variables in larger than minimal scopes. Functions with complex control structures are more likely to be long and more likely to hide logical errors

Example

Consider:

```
double simple_func(double val, int flag1, int flag2)
   // simple_func: takes a value and calculates the expected ASIC output,
   // given the two mode flags.
{
   double intermediate;
   if (flag1 > 0) {
      intermediate = func1(val);
      if (flag2 % 2)
            intermediate = sqrt(intermediate);
   }
   else if (flag1 == -1) {
      intermediate = func1(-val);
      if (flag2 % 2)
            intermediate = sqrt(-intermediate);
      flag1 = -flag1;
   }
   if (abs(flag2) > 10) {
```

This is too complex. How would you know if all possible alternatives have been correctly handled? Yes, it breaks other rules also.

We can refactor:

```
double func1_muon(double val, int flag)
   // ???
}
double func1_tau(double val, int flag1, int flag2)
    // ???
}
double simple_func(double val, int flag1, int flag2)
   // simple_func: takes a value and calculates the expected ASIC output,
   // given the two mode flags.
{
   if (flag1 > 0)
        return func1_muon(val, flag2);
   if (flag1 == -1)
        // handled by func1_tau: flag1 = -flag1;
        return func1_tau(-val, flag1, flag2);
   return 0.;
}
```

Note

"It doesn't fit on a screen" is often a good practical definition of "far too large." One-to-five-line functions should be considered normal.

Note

Break large functions up into smaller cohesive and named functions. Small simple functions are easily inlined where the cost of a function call is significant.

- Flag functions that do not "fit on a screen." How big is a screen? Try 60 lines by 140 characters; that's roughly the maximum that's comfortable for a book page.
- Flag functions that are too complex. How complex is too complex? You could use cyclomatic complexity. Try "more than 10 logical paths through." Count a simple switch as one path.

F.4: If a function might have to be evaluated at compile time, declare it constexpr

Reason

constexpr is needed to tell the compiler to allow compile-time evaluation.

Example

The (in)famous factorial:

This is C++14. For C++11, use a recursive formulation of fac().

Note

constexpr does not guarantee compile-time evaluation; it just guarantees that the function can be evaluated at compile time for constant expression arguments if the programmer requires it or the compiler decides to do so to optimize.

Note

Don't try to make all functions constexpr. Most computation is best done at run time.

Note

Any API that might eventually depend on high-level run-time configuration or business logic should not be made constexpr. Such customization can not be evaluated by the compiler, and any constexpr functions that depended upon that API would have to be refactored or drop constexpr.

Enforcement

Impossible and unnecessary. The compiler gives an error if a non-constexpr function is called where a constant is required.

F.5: If a function is very small and time-critical, declare it inline

Reason

Some optimizers are good at inlining without hints from the programmer, but don't rely on it. Measure! Over the last 40 years or so, we have been promised compilers that can inline better than humans without hints from humans. We are still waiting. Specifying inline (explicitly, or implicitly when writing member functions inside a class definition) encourages the compiler to do a better job.

Example

```
inline string cat(const string& s, const string& s2) { return s + s2; }
```

Exception

Do not put an inline function in what is meant to be a stable interface unless you are certain that it will not change. An inline function is part of the ABI.

Note

constexpr implies inline.

Note

Member functions defined in-class are inline by default.

Exception

Function templates (including member functions of class templates A<T>::function() and member function templates A::function<T>()) are normally defined in headers and therefore inline.

Flag inline functions that are more than three statements and could have been declared out of line (such as class member functions).

F.6: If your function must not throw, declare it noexcept

Reason

If an exception is not supposed to be thrown, the program cannot be assumed to cope with the error and should be terminated as soon as possible. Declaring a function noexcept helps optimizers by reducing the number of alternative execution paths. It also speeds up the exit after failure.

Example

Put noexcept on every function written completely in C or in any other language without exceptions. The C++ Standard Library does that implicitly for all functions in the C Standard Library.

Note

constexpr functions can throw when evaluated at run time, so you might need conditional noexcept for some of those

Example

You can use noexcept even on functions that can throw:

```
vector<string> collect(istream& is) noexcept
{
   vector<string> res;
   for (string s; is >> s;)
      res.push_back(s);
   return res;
}
```

If collect() runs out of memory, the program crashes. Unless the program is crafted to survive memory exhaustion, that might be just the right thing to do; terminate() might generate suitable error log information (but after memory runs out it is hard to do anything clever).

Note

You must be aware of the execution environment that your code is running when deciding whether to tag a function noexcept, especially because of the issue of throwing and allocation. Code that is intended to be perfectly general (like the standard library and other utility code of that sort) needs to support environments where a bad_alloc exception could be handled meaningfully. However, most programs and execution environments cannot meaningfully handle a failure to allocate, and aborting the program is the cleanest and simplest response to an allocation failure in those cases. If you know that your application code cannot respond to an allocation failure, it could be appropriate to add noexcept even on functions that allocate.

Put another way: In most programs, most functions can throw (e.g., because they use new, call functions that do, or use library functions that reports failure by throwing), so don't just sprinkle noexcept all over the place without considering whether the possible exceptions can be handled.

noexcept is most useful (and most clearly correct) for frequently used, low-level functions.

Note

Destructors, swap functions, move operations, and default constructors should never throw. See also C.44.

Enforcement

- Flag functions that are not noexcept, yet cannot throw.
- Flag throwing swap, move, destructors, and default constructors.

F.7: For general use, take T* or T& arguments rather than smart pointers

Reason

Passing a smart pointer transfers or shares ownership and should only be used when ownership semantics are intended. A function that does not manipulate lifetime should take raw pointers or references instead.

Passing by smart pointer restricts the use of a function to callers that use smart pointers. A function that needs a widget should be able to accept any widget object, not just ones whose lifetimes are managed by a particular kind of smart pointer.

Passing a shared smart pointer (e.g., std::shared_ptr) implies a run-time cost.

Example

```
// accepts any int*
void f(int*);

// can only accept ints for which you want to transfer ownership
void g(unique_ptr<int>);

// can only accept ints for which you are willing to share ownership
void g(shared_ptr<int>);

// doesn't change ownership, but requires a particular ownership of the caller
void h(const unique_ptr<int>&);

// accepts any int
void h(int&);
```

Example, bad

```
// callee
void f(shared_ptr<widget>& w)
{
    // ...
    use(*w); // only use of w -- the lifetime is not used at all
    // ...
};

// caller
shared_ptr<widget> my_widget = /* ... */;
f(my_widget);

widget stack_widget;
f(stack_widget); // error
```

Example, good

```
// callee
void f(widget& w)
{
    // ...
    use(w);
    // ...
};

// caller
shared_ptr<widget> my_widget = /* ... */;
f(*my_widget);

widget stack_widget;
f(stack_widget); // ok -- now this works
```

Note

We can catch many common cases of dangling pointers statically (see <u>lifetime safety profile</u>). Function arguments naturally live for the lifetime of the function call, and so have fewer lifetime problems.

Enforcement

- (Simple) Warn if a function takes a parameter of a smart pointer type (that overloads operator-> or operator*) that is copyable but the function only calls any of: operator*, operator-> or get(). Suggest using a T* or T& instead.
- Flag a parameter of a smart pointer type (a type that overloads operator-> or operator*) that is copyable/movable but never copied/moved from in the function body, and that is never modified, and that is not passed along to another function that could do so. That means the ownership semantics are not used. Suggest using a T* or T& instead.

See also:

- Prefer T* over T& when "no argument" is a valid option
- Smart pointer rule summary

F.8: Prefer pure functions

Reason

Pure functions are easier to reason about, sometimes easier to optimize (and even parallelize), and sometimes can be memoized.

Example

```
template<class T>
auto square(T t) { return t * t; }
```

Enforcement

Not possible.

F.9: Unused parameters should be unnamed

Reason

Readability. Suppression of unused parameter warnings.

Example

```
widget* find(const set<widget>& s, const widget& w, Hint); // once upon a time, a hint was
used
```

Note

Allowing parameters to be unnamed was introduced in the early 1980s to address this problem.

If parameters are conditionally unused, declare them with the [[maybe_unused]] attribute. For example:

```
template <typename Value>
Value* find(const set<Value>& s, const Value& v, [[maybe_unused]] Hint h)
{
   if constexpr (sizeof(Value) > CacheSize)
   {
      // a hint is used only if Value is of a certain size
   }
}
```

Flag named unused parameters.

F.10: If an operation can be reused, give it a name

Reason

Documentation, readability, opportunity for reuse.

Example

```
struct Rec {
    string name;
    string addr;
    int id;
                  // unique identifier
};
bool same(const Rec& a, const Rec& b)
   return a.id == b.id;
}
vector<Rec*> find_id(const string& name);  // find all records for "name"
auto x = find_if(vr.begin(), vr.end(),
    [&](Rec& r) {
        if (r.name.size() != n.size()) return false; // name to compare to is in n
        for (int i = 0; i < r.name.size(); ++i)</pre>
            if (tolower(r.name[i]) != tolower(n[i])) return false;
        return true;
   }
);
```

There is a useful function lurking here (case insensitive string comparison), as there often is when lambda arguments get large.

```
bool compare_insensitive(const string& a, const string& b)
{
    if (a.size() != b.size()) return false;
    for (int i = 0; i < a.size(); ++i) if (tolower(a[i]) != tolower(b[i])) return false;
    return true;
}
auto x = find_if(vr.begin(), vr.end(),
    [&](Rec& r) { return compare_insensitive(r.name, n); }
);</pre>
```

Or maybe (if you prefer to avoid the implicit name binding to n):

```
auto cmp_to_n = [&n](const string& a) { return compare_insensitive(a, n); };
auto x = find_if(vr.begin(), vr.end(),
    [](const Rec& r) { return cmp_to_n(r.name); }
);
```

Note

whether functions, lambdas, or operators.

Exception

- Lambdas logically used only locally, such as an argument to for_each and similar control flow algorithms.
- Lambdas as initializers

Enforcement

- (hard) flag similar lambdas
- **???**

F.11: Use an unnamed lambda if you need a simple function object in one place only

Reason

That makes the code concise and gives better locality than alternatives.

Example

Exception

Naming a lambda can be useful for clarity even if it is used only once.

Enforcement

• Look for identical and near identical lambdas (to be replaced with named functions or named lambdas).

F.call: Parameter passing

There are a variety of ways to pass parameters to a function and to return values.

F.15: Prefer simple and conventional ways of passing information

Reason

Using "unusual and clever" techniques causes surprises, slows understanding by other programmers, and encourages bugs. If you really feel the need for an optimization beyond the common techniques, measure to ensure that it really is an improvement, and document/comment because the improvement might not be portable.


The following tables summarize the advice in the following Guidelines, F.16-21.

Normal parameter passing:

	Cheap or impossible to copy (e.g., int, unique_ptr)	Cheap to move (e.g., vector <t>, string) or Moderate cost to move (e.g., array<vector>, BigPOD) or Don't know (e.g., unfamiliar type, template)</vector></t>	Expensive to move (e.g., BigPOD[], array <bigpod>)</bigpod>
Out		X f()	
In/Out		f(X&)	
In	f(X)	f(const X&)	
In & retain "copy"			

"Cheap" \approx a handful of hot int copies "Moderate cost" \approx memcpy hot/contiguous ~1KB and no allocation

Advanced parameter passing:



^{*} or return unique_ptr<X>/make_shared_<X> at the cost of a dynamic allocation

Use the advanced techniques only after demonstrating need, and document that need in a comment.

For passing sequences of characters see String.

^{*} or return unique_ptr<X>/make_shared_<X> at the cost of a dynamic allocation

^{**} special cases can also use perfect forwarding (e.g., multiple in+copy params, conversions)

Exception

To express shared ownership using shared_ptr types, rather than following guidelines F.16-21, follow R.34, R.35, and R.36.

F.16: For "in" parameters, pass cheaply-copied types by value and others by reference to const

Reason

Both let the caller know that a function will not modify the argument, and both allow initialization by rvalues.

What is "cheap to copy" depends on the machine architecture, but two or three words (doubles, pointers, references) are usually best passed by value. When copying is cheap, nothing beats the simplicity and safety of copying, and for small objects (up to two or three words) it is also faster than passing by reference because it does not require an extra indirection to access from the function.

Example

```
void f1(const string& s); // OK: pass by reference to const; always cheap

void f2(string s); // bad: potentially expensive

void f3(int x); // OK: Unbeatable

void f4(const int& x); // bad: overhead on access in f4()
```

For advanced uses (only), where you really need to optimize for rvalues passed to "input-only" parameters:

- If the function is going to unconditionally move from the argument, take it by &&. See F.18.
- If the function is going to keep a copy of the argument, in addition to passing by const& (for Ivalues), add an overload that passes the parameter by && (for rvalues) and in the body std::moves it to its destination. Essentially this overloads a "will-move-from"; see F.18.
- In special cases, such as multiple "input + copy" parameters, consider using perfect forwarding. See F.19.

Example

```
int multiply(int, int); // just input ints, pass by value

// suffix is input-only but not as cheap as an int, pass by const&
string& concatenate(string&, const string& suffix);

void sink(unique_ptr<widget>); // input only, and moves ownership of the widget
```

Avoid "esoteric techniques" such as passing arguments as T&& "for efficiency". Most rumors about performance advantages from passing by && are false or brittle (but see F.18 and F.19).

Notes

A reference can be assumed to refer to a valid object (language rule). There is no (legitimate) "null reference." If you need the notion of an optional value, use a pointer, std::optional, or a special value used to denote "no value."

Enforcement

- (Simple) ((Foundation)) Warn when a parameter being passed by value has a size greater than 2 * sizeof(void*). Suggest using a reference to const instead.
- (Simple) ((Foundation)) Warn when a parameter passed by reference to const has a size less or equal than 2 * sizeof(void*). Suggest passing by value instead.
- (Simple) ((Foundation)) Warn when a parameter passed by reference to const is moved.

Exception

To express shared ownership using shared_ptr types, follow R.34 or R.36, depending on whether or not the function unconditionally takes a reference to the argument.

F.17: For "in-out" parameters, pass by reference to non-const

Reason

This makes it clear to callers that the object is assumed to be modified.

Example

```
void update(Record& r); // assume that update writes to r
```

Note

Some user-defined and standard library types, such as span<T> or the iterators are cheap to copy and may be passed by value, while doing so has mutable (in-out) reference semantics:

```
void increment_all(span<int> a)
{
  for (auto&& e : a)
   ++e;
}
```

Note

A T& argument can pass information into a function as well as out of it. Thus T& could be an in-out-parameter. That can in itself be a problem and a source of errors:

```
void f(string& s)
{
    s = "New York"; // non-obvious error
}

void g()
{
    string buffer = "......";
    f(buffer);
    // ...
}
```

Here, the writer of g() is supplying a buffer for f() to fill, but f() simply replaces it (at a somewhat higher cost than a simple copy of the characters). A bad logic error can happen if the writer of g() incorrectly assumes the size of the buffer.

Enforcement

- (Moderate) ((Foundation)) Warn about functions regarding reference to non-const parameters that do *not* write to them.
- (Simple) ((Foundation)) Warn when a non-const parameter being passed by reference is moved.

F.18: For "will-move-from" parameters, pass by X&& and std::move the parameter

Reason

It's efficient and eliminates bugs at the call site: X&& binds to rvalues, which requires an explicit std::move at the call site if passing an Ivalue.

Example

```
void sink(vector<int>&& v) // sink takes ownership of whatever the argument owned
{
    // usually there might be const accesses of v here
    store_somewhere(std::move(v));
    // usually no more use of v here; it is moved-from
}
```

Note that the std::move(v) makes it possible for store_somewhere() to leave v in a moved-from state. That could be dangerous.

Exception

Unique owner types that are move-only and cheap-to-move, such as unique_ptr, can also be passed by value which is simpler to write and achieves the same effect. Passing by value does generate one extra (cheap) move operation, but prefer simplicity and clarity first.

For example:

```
template<class T>
void sink(std::unique_ptr<T> p)
{
    // use p ... possibly std::move(p) onward somewhere else
}    // p gets destroyed
```

Exception

If the "will-move-from" parameter is a shared_ptr follow R.34 and pass the shared_ptr by value.

Enforcement

- Flag all X&& parameters (where X is not a template type parameter name) where the function body uses them without std::move.
- Flag access to moved-from objects.
- Don't conditionally move from objects

F.19: For "forward" parameters, pass by TP&& and only std::forward the parameter

Reason

If the object is to be passed onward to other code and not directly used by this function, we want to make this function agnostic to the argument const-ness and rvalue-ness.

In that case, and only that case, make the parameter TP&& where TP is a template type parameter -- it both *ignores* and *preserves* const-ness and rvalue-ness. Therefore any code that uses a TP&& is implicitly declaring that it itself doesn't care about the variable's const-ness and rvalue-ness (because it is ignored), but that intends to pass the value onward to other code that does care about const-ness and rvalue-ness (because it is preserved). When used as a parameter TP&& is safe because any temporary objects passed from the caller will live for the duration of the function call. A parameter of type TP&& should essentially always be passed onward via std::forward in the body of the function.

Example

Usually you forward the entire parameter (or parameter pack, using ...) exactly once on every static control flow path:

```
template<class F, class... Args>
inline auto invoke(F f, Args&&... args)
{
    return f(forward<Args>(args)...);
}
```

Example

Sometimes you may forward a composite parameter piecewise, each subobject once on every static control flow path:

Enforcement

• Flag a function that takes a TP&& parameter (where TP is a template type parameter name) and does anything with it other than std::forwarding it exactly once on every static path, or std::forwarding it more than once but qualified with a different data member exactly once on every static path.

F.20: For "out" output values, prefer return values to output parameters

Reason

A return value is self-documenting, whereas a & could be either in-out or out-only and is liable to be misused.

This includes large objects like standard containers that use implicit move operations for performance and to avoid explicit memory management.

If you have multiple values to return, use a tuple or similar multi-member type.

Example

```
// OK: return pointers to elements with the value x
vector<const int*> find_all(const vector<int>&, int x);

// Bad: place pointers to elements with value x in-out
void find_all(const vector<int>&, vector<const int*>& out, int x);
```

Note

A struct of many (individually cheap-to-move) elements might be in aggregate expensive to move.

Exceptions

- For non-concrete types, such as types in an inheritance hierarchy, return the object by unique_ptr or shared_ptr.
- If a type is expensive to move (e.g., array<BigTrivial>), consider allocating it on the free store and return a handle (e.g., unique_ptr), or passing it in a reference to non-const target object to fill (to be used as an outparameter).
- To reuse an object that carries capacity (e.g., std::string, std::vector) across multiple calls to the function in an inner loop: treat it as an in/out parameter and pass by reference.

Example

Assuming that Matrix has move operations (possibly by keeping its elements in a std::vector):

```
Matrix operator+(const Matrix& a, const Matrix& b)
{
    Matrix res;
    // ... fill res with the sum ...
    return res;
}

Matrix x = m1 + m2; // move constructor

y = m3 + m3; // move assignment
```

Note

The return value optimization doesn't handle the assignment case, but the move assignment does.

Example

• Flag reference to non-const parameters that are not read before being written to and are a type that could be cheaply returned; they should be "out" return values.

F.21: To return multiple "out" values, prefer returning a struct or tuple

Reason

A return value is self-documenting as an "output-only" value. Note that C++ does have multiple return values, by convention of using a tuple (including pair), possibly with the extra convenience of tie or structured bindings (C++17) at the call site. Prefer using a named struct where there are semantics to the returned value. Otherwise, a nameless tuple is useful in generic code.

Example

```
// BAD: output-only parameter documented in a comment
int f(const string& input, /*output only*/ string& output_data)
{
    // ...
    output_data = something();
    return status;
}

// GOOD: self-documenting
tuple<int, string> f(const string& input)
{
    // ...
    return {status, something()};
}
```

C++98's standard library already used this style, because a pair is like a two-element tuple. For example, given a set<string> my set, consider:

```
// C++98
result = my_set.insert("Hello");
if (result.second) do_something_with(result.first); // workaround
```

With C++11 we can write this, putting the results directly in existing local variables:

With C++17 we are able to use "structured bindings" to declare and initialize the multiple variables:

```
if (auto [ iter, success ] = my_set.insert("Hello"); success) do_something_with(iter);
```

Exception

Sometimes, we need to pass an object to a function to manipulate its state. In such cases, passing the object by reference T& is usually the right technique. Explicitly passing an in-out parameter back out again as a return value is often not necessary. For example:

```
istream& operator>>(istream& in, string& s);  // much like std::operator>>()

for (string s; in >> s; ) {
    // do something with line
}
```

Here, both s and in are used as in-out parameters. We pass in by (non-const) reference to be able to manipulate its state. We pass s to avoid repeated allocations. By reusing s (passed by reference), we allocate new memory only when we need to expand s's capacity. This technique is sometimes called the "caller-allocated out" pattern and is particularly useful for types, such as string and vector, that needs to do free store allocations.

To compare, if we passed out all values as return values, we would something like this:

```
pair<istream&, string> get_string(istream& in) // not recommended
{
    string s;
    in >> s;
    return {in, move(s)};
}

for (auto p = get_string(cin); p.first; p.second = get_string(p.first).second) {
    // do something with p.second
}
```

We consider that significantly less elegant with significantly less performance.

For a truly strict reading of this rule (F.21), the exception isn't really an exception because it relies on in-out parameters, rather than the plain out parameters mentioned in the rule. However, we prefer to be explicit, rather than subtle.

Note

In many cases, it can be useful to return a specific, user-defined type. For example:

The overly-generic pair and tuple should be used only when the value returned represents independent entities rather than an abstraction.

Another example, use a specific type along the lines of variant<T, error_code>, rather than using the generic tuple.

Note

When the tuple to be returned is initialized from local variables that are expensive to copy, explicit move may be helpful to avoid copying:

```
pair<LargeObject, LargeObject> f(const string& input)
{
    LargeObject large1 = g(input);
    LargeObject large2 = h(input);
    // ...
    return { move(large1), move(large2) }; // no copies
}
```

Alternatively,

```
pair<LargeObject, LargeObject> f(const string& input)
{
    // ...
    return { g(input), h(input) }; // no copies, no moves
}
```

Note this is different from the return move(...) anti-pattern from ES.56

Enforcement

• Output parameters should be replaced by return values. An output parameter is one that the function writes to, invokes a non-const member function, or passes on as a non-const.

F.60: Prefer T* over T& when "no argument" is a valid option

Reason

A pointer (T*) can be a nullptr and a reference (T&) cannot, there is no valid "null reference". Sometimes having nullptr as an alternative to indicated "no object" is useful, but if it is not, a reference is notationally simpler and might yield better code.

Example

Note

It is possible, but not valid C++ to construct a reference that is essentially a nullptr (e.g., T* p = nullptr; T& r = *p;). That error is very uncommon.

Note

If you prefer the pointer notation (-> and/or * vs. .), not_null<T*> provides the same guarantee as T&.

Enforcement

■ Flag ???

F.22: Use T* or owner<T*> to designate a single object

Reason

Readability: it makes the meaning of a plain pointer clear. Enables significant tool support.

Note

In traditional C and C++ code, plain T* is used for many weakly-related purposes, such as:

- Identify a (single) object (not to be deleted by this function)
- Point to an object allocated on the free store (and delete it later)
- Hold the nullptr
- Identify a C-style string (zero-terminated array of characters)

- Identify an array with a length specified separately
- Identify a location in an array

This makes it hard to understand what the code does and is supposed to do. It complicates checking and tool support.

Example

better

```
void use2(span<int> p, zstring s, owner<int*> q)
{
   p[p.size() - 1] = 666; // OK, a range error can be caught
   cout << s; // OK
   delete q; // OK
}</pre>
```

Note

owner<T*> represents ownership, zstring represents a C-style string.

Also: Assume that a T* obtained from a smart pointer to T (e.g., unique_ptr<T>) points to a single element.

See also: Support library

See also: Do not pass an array as a single pointer

Enforcement

• (Simple) ((Bounds)) Warn for any arithmetic operation on an expression of pointer type that results in a value of pointer type.

F.23: Use a not_null<T> to indicate that "null" is not a valid value

Reason

Clarity. A function with a not_null<T> parameter makes it clear that the caller of the function is responsible for any nullptr checks that might be necessary. Similarly, a function with a return value of not_null<T> makes it clear that the caller of the function does not need to check for nullptr.

Example

not_null<T*> makes it obvious to a reader (human or machine) that a test for nullptr is not necessary before dereference. Additionally, when debugging, owner<T*> and not_null<T> can be instrumented to check for correctness.

Consider:

```
int length(Record* p);
```

When I call length(p) should I check if p is nullptr first? Should the implementation of length() check if p is nullptr?

```
// it is the caller's job to make sure p != nullptr
int length(not_null<Record*> p);

// the implementor of length() must assume that p == nullptr is possible
int length(Record* p);
```

Note

A not_null<T*> is assumed not to be the nullptr; a T* might be the nullptr; both can be represented in memory as a T* (so no run-time overhead is implied).

Note

not_null is not just for built-in pointers. It works for unique_ptr, shared_ptr, and other pointer-like types.

Enforcement

- (Simple) Warn if a raw pointer is dereferenced without being tested against nullptr (or equivalent) within a function, suggest it is declared not_null instead.
- (Simple) Error if a raw pointer is sometimes dereferenced after first being tested against nullptr (or equivalent) within the function and sometimes is not.
- (Simple) Warn if a not_null pointer is tested against nullptr within a function.

F.24: Use a span<T> or a span_p<T> to designate a half-open sequence

Reason

Informal/non-explicit ranges are a source of errors.

Example

```
X* find(span<X> r, const X& v);  // find v in r

vector<X> vec;
// ...
auto p = find({vec.begin(), vec.end()}, X{});  // find X{} in vec
```

Note

Ranges are extremely common in C++ code. Typically, they are implicit and their correct use is very hard to ensure. In particular, given a pair of arguments (p, n) designating an array [p:p+n), it is in general impossible to know if there really are n elements to access following *p. span<T> and span_p<T> are simple helper classes designating a [p:q) range and a range starting with p and ending with the first element for which a predicate is true, respectively.

Example

A span represents a range of elements, but how do we manipulate elements of that range?

```
void f(span<int> s)
{
    // range traversal (guaranteed correct)
    for (int x : s) cout << x << '\n';

    // C-style traversal (potentially checked)
    for (gsl::index i = 0; i < s.size(); ++i) cout << s[i] << '\n';

    // random access (potentially checked)
    s[7] = 9;

    // extract pointers (potentially checked)
    std::sort(&s[0], &s[s.size() / 2]);
}</pre>
```

Note

A span<T> object does not own its elements and is so small that it can be passed by value.

Passing a span object as an argument is exactly as efficient as passing a pair of pointer arguments or passing a pointer and an integer count.

See also: Support library

Enforcement

(Complex) Warn where accesses to pointer parameters are bounded by other parameters that are integral types and suggest they could use span instead.

F.25: Use a zstring or a not_null<zstring> to designate a C-style string

Reason

C-style strings are ubiquitous. They are defined by convention: zero-terminated arrays of characters. We must distinguish C-style strings from a pointer to a single character or an old-fashioned pointer to an array of characters.

If you don't need null termination, use string_view.

Example

Consider:

```
int length(const char* p);
```

When I call length(s) should I check if s is nullptr first? Should the implementation of length() check if p is nullptr?

```
// the implementor of length() must assume that p == nullptr is possible
int length(zstring p);

// it is the caller's job to make sure p != nullptr
int length(not_null<zstring> p);
```

Note

zstring does not represent ownership.

See also: Support library

F.26: Use a unique_ptr<T> to transfer ownership where a pointer is needed

Reason

Using unique_ptr is the cheapest way to pass a pointer safely.

See also: C.50 regarding when to return a shared_ptr from a factory.

Example

```
unique_ptr<Shape> get_shape(istream& is) // assemble shape from input stream
{
    auto kind = read_header(is); // read header and identify the next shape on input
    switch (kind) {
    case kCircle:
        return make_unique<Circle>(is);
    case kTriangle:
        return make_unique<Triangle>(is);
    // ...
    }
}
```

Note

You need to pass a pointer rather than an object if what you are transferring is an object from a class hierarchy that is to be used through an interface (base class).

Enforcement

(Simple) Warn if a function returns a locally allocated raw pointer. Suggest using either unique_ptr or shared_ptr instead.

F.27: Use a shared_ptr<T> to share ownership

Reason

Using std::shared_ptr is the standard way to represent shared ownership. That is, the last owner deletes the object.

Example

```
shared_ptr<const Image> im { read_image(somewhere) };

std::thread t0 {shade, args0, top_left, im};

std::thread t1 {shade, args1, top_right, im};

std::thread t2 {shade, args2, bottom_left, im};

std::thread t3 {shade, args3, bottom_right, im};

// detach threads
// last thread to finish deletes the image
```

Note

Prefer a unique_ptr over a shared_ptr if there is never more than one owner at a time. shared_ptr is for shared ownership.

Note that pervasive use of shared_ptr has a cost (atomic operations on the shared_ptr's reference count have a measurable aggregate cost).

Alternative

Have a single object own the shared object (e.g. a scoped object) and destroy that (preferably implicitly) when all users have completed.

Enforcement

(Not enforceable) This is a too complex pattern to reliably detect.

F.42: Return a T to indicate a position (only)*

Reason

That's what pointers are good for. Returning a T* to transfer ownership is a misuse.

Example

```
Node* find(Node* t, const string& s) // find s in a binary tree of Nodes
{
    if (!t || t->name == s) return t;
    if ((auto p = find(t->left, s))) return p;
    if ((auto p = find(t->right, s))) return p;
    return nullptr;
}
```

If it isn't the nullptr, the pointer returned by find indicates a Node holding s. Importantly, that does not imply a transfer of ownership of the pointed-to object to the caller.

Note

Positions can also be transferred by iterators, indices, and references. A reference is often a superior alternative to a pointer if there is no need to use nullptr or if the object referred to should not change.

Note

Do not return a pointer to something that is not in the caller's scope; see F.43.

See also: discussion of dangling pointer prevention

Enforcement

- Flag delete, std::free(), etc. applied to a plain T*. Only owners should be deleted.
- Flag new, malloc(), etc. assigned to a plain T*. Only owners should be responsible for deletion.

F.43: Never (directly or indirectly) return a pointer or a reference to a local object

Reason

To avoid the crashes and data corruption that can result from the use of such a dangling pointer.

Example, bad

After the return from a function its local objects no longer exist:

```
int* f()
{
   int fx = 9;
   return &fx; // BAD
}
void g(int* p) // looks innocent enough
    int gx;
    cout << "*p == " << *p << '\n';
   *p = 999;
   cout << "gx == " << gx << '\n';
}
void h()
   int* p = f();
   int z = *p; // read from abandoned stack frame (bad)
                // pass pointer to abandoned stack frame to function (bad)
}
```

Here on one popular implementation I got the output:

```
*p == 999
gx == 999
```

I expected that because the call of g() reuses the stack space abandoned by the call of f() so *p refers to the space now occupied by gx.

- Imagine what would happen if fx and gx were of different types.
- Imagine what would happen if fx or gx was a type with an invariant.

- Imagine what would happen if more that dangling pointer was passed around among a larger set of functions.
- Imagine what a cracker could do with that dangling pointer.

Fortunately, most (all?) modern compilers catch and warn against this simple case.

Note

This applies to references as well:

```
int& f()
{
   int x = 7;
   // ...
   return x; // Bad: returns reference to object that is about to be destroyed
}
```

Note

This applies only to non-static local variables. All static variables are (as their name indicates) statically allocated, so that pointers to them cannot dangle.

Example, bad

Not all examples of leaking a pointer to a local variable are that obvious:

Here I managed to read the location abandoned by the call of f. The pointer stored in glob could be used much later and cause trouble in unpredictable ways.

Note

The address of a local variable can be "returned"/leaked by a return statement, by a T& out-parameter, as a member of a returned object, as an element of a returned array, and more.

Note

Similar examples can be constructed "leaking" a pointer from an inner scope to an outer one; such examples are handled equivalently to leaks of pointers out of a function.

A slightly different variant of the problem is placing pointers in a container that outlives the objects pointed to.

See also: Another way of getting dangling pointers is pointer invalidation. It can be detected/prevented with similar techniques.

Enforcement

- Compilers tend to catch return of reference to locals and could in many cases catch return of pointers to locals.
- Static analysis can catch many common patterns of the use of pointers indicating positions (thus eliminating dangling pointers)

F.44: Return a **T&** when copy is undesirable and "returning no object" isn't needed

Reason

The language guarantees that a T& refers to an object, so that testing for nullptr isn't necessary.

See also: The return of a reference must not imply transfer of ownership: discussion of dangling pointer prevention and discussion of ownership.

Example

```
class Car
{
    array<wheel, 4> w;
    // ...
public:
    wheel& get_wheel(int i) { Expects(i < w.size()); return w[i]; }
    // ...
};

void use()
{
    Car c;
    wheel& w0 = c.get_wheel(0); // w0 has the same lifetime as c
}</pre>
```

Enforcement

Flag functions where no return expression could yield nullptr

F.45: Don't return a T&&

Reason

It's asking to return a reference to a destroyed temporary object. A && is a magnet for temporary objects.

Example

A returned rvalue reference goes out of scope at the end of the full expression to which it is returned:

```
auto&& x = max(0, 1); // OK, so far foo(x); // Undefined behavior
```

This kind of use is a frequent source of bugs, often incorrectly reported as a compiler bug. An implementer of a function should avoid setting such traps for users.

The lifetime safety profile will (when completely implemented) catch such problems.

Example

Returning an rvalue reference is fine when the reference to the temporary is being passed "downward" to a callee; then, the temporary is guaranteed to outlive the function call (see F.18 and F.19). However, it's not fine when passing such a reference "upward" to a larger caller scope. For passthrough functions that pass in parameters (by ordinary reference or by perfect forwarding) and want to return values, use simple auto return type deduction (not auto&&).

Assume that F returns by value:

```
template<class F>
auto&& wrapper(F f)
{
   log_call(typeid(f)); // or whatever instrumentation
   return f(); // BAD: returns a reference to a temporary
}
```

Better:

```
template<class F>
auto wrapper(F f)
{
    log_call(typeid(f)); // or whatever instrumentation
    return f(); // OK
}
```

Exception

std::move and std::forward do return &&, but they are just casts -- used by convention only in expression contexts where a reference to a temporary object is passed along within the same expression before the temporary is destroyed. We don't know of any other good examples of returning &&.

Enforcement

Flag any use of && as a return type, except in std::move and std::forward.

F.46: int is the return type for main()

Reason

It's a language rule, but violated through "language extensions" so often that it is worth mentioning. Declaring main (the one global main of a program) void limits portability.

Example

```
void main() { /* ... */ }; // bad, not C++

int main()
{
    std::cout << "This is the way to do it\n";
}</pre>
```

Note

We mention this only because of the persistence of this error in the community. Note that despite its non-void return type, the main function does not require an explicit return statement.

Enforcement

- The compiler should do it
- If the compiler doesn't do it, let tools flag it

F.47: Return T& from assignment operators

Reason

The convention for operator overloads (especially on concrete types) is for operator=(const T&) to perform the assignment and then return (non-const) *this. This ensures consistency with standard-library types and follows the principle of "do as the ints do."

Note

Historically there was some guidance to make the assignment operator return const T8. This was primarily to avoid code of the form (a = b) = c -- such code is not common enough to warrant violating consistency with standard types.

Example

```
class Foo
{
  public:
    ...
    Foo& operator=(const Foo& rhs)
    {
        // Copy members.
        ...
        return *this;
    }
};
```

Enforcement

This should be enforced by tooling by checking the return type (and return value) of any assignment operator.

```
F.48: Don't return std::move(local)
```

Reason

With guaranteed copy elision, it is now almost always a pessimization to expressly use std::move in a return statement.

Example, bad

```
S f()
{
   S result;
   return std::move(result);
}
```

Example, good

```
S f()
{
   S result;
   return result;
}
```

Enforcement

This should be enforced by tooling by checking the return expression .

F.49: Don't return const T

Reason

It is not recommended to return a const value. Such older advice is now obsolete; it does not add value, and it interferes with move semantics.

Example

The argument for adding const to a return value is that it prevents (very rare) accidental access to a temporary. The argument against is that it prevents (very frequent) use of move semantics.

See also: F.20, the general item about "out" output values

Enforcement

• Flag returning a const value. To fix: Remove const to return a non-const value instead.

F.50: Use a lambda when a function won't do (to capture local variables, or to write a local function)

Reason

Functions can't capture local variables or be defined at local scope; if you need those things, prefer a lambda where possible, and a handwritten function object where not. On the other hand, lambdas and function objects don't overload; if you need to overload, prefer a function (the workarounds to make lambdas overload are ornate). If either will work, prefer writing a function; use the simplest tool necessary.

Example

```
// writing a function that should only take an int or a string
// -- overloading is natural
void f(int);
void f(const string&);
// writing a function object that needs to capture local state and appear
// at statement or expression scope -- a lambda is natural
vector<work> v = lots_of_work();
for (int tasknum = 0; tasknum < max; ++tasknum) {</pre>
    pool.run([=, &v] {
        /*
        \dots process 1 / max - th of v, the tasknum - th chunk
        . . .
        */
    });
}
pool.join();
```

Exception

Generic lambdas offer a concise way to write function templates and so can be useful even when a normal function template would do equally well with a little more syntax. This advantage will probably disappear in the future once all functions gain the ability to have Concept parameters.

Enforcement

• Warn on use of a named non-generic lambda (e.g., auto $x = [](int i) \{ /*...*/; \};$) that captures nothing and appears at global scope. Write an ordinary function instead.

F.51: Where there is a choice, prefer default arguments over overloading

Reason

Default arguments simply provide alternative interfaces to a single implementation. There is no guarantee that a set of overloaded functions all implement the same semantics. The use of default arguments can avoid code replication.

Note

There is a choice between using default argument and overloading when the alternatives are from a set of arguments of the same types. For example:

```
void print(const string& s, format f = {});
```

as opposed to

```
void print(const string& s); // use default format
void print(const string& s, format f);
```

There is not a choice when a set of functions are used to do a semantically equivalent operation to a set of types. For example:

```
void print(const char&);
void print(int);
void print(zstring);
```

See also

Default arguments for virtual functions

Enforcement

■ Warn on an overload set where the overloads have a common prefix of parameters (e.g., f(int), f(int, const string&), f(int, const string&, double)). (Note: Review this enforcement if it's too noisy in practice.)

F.52: Prefer capturing by reference in lambdas that will be used locally, including passed to algorithms

Reason

For efficiency and correctness, you nearly always want to capture by reference when using the lambda locally. This includes when writing or calling parallel algorithms that are local because they join before returning.

Discussion

The efficiency consideration is that most types are cheaper to pass by reference than by value.

The correctness consideration is that many calls want to perform side effects on the original object at the call site (see example below). Passing by value prevents this.

Note

Unfortunately, there is no simple way to capture by reference to const to get the efficiency for a local call but also prevent side effects.

Example

Here, a large object (a network message) is passed to an iterative algorithm, and it is not efficient or correct to copy the message (which might not be copyable):

```
std::for_each(begin(sockets), end(sockets), [&message](auto& socket)
{
    socket.send(message);
});
```

Example

This is a simple three-stage parallel pipeline. Each stage object encapsulates a worker thread and a queue, has a process function to enqueue work, and in its destructor automatically blocks waiting for the queue to empty before ending the thread.

```
void send_packets(buffers& bufs)
{
    stage encryptor([](buffer& b) { encrypt(b); });
    stage compressor([&](buffer& b) { compress(b); encryptor.process(b); });
    stage decorator([&](buffer& b) { decorate(b); compressor.process(b); });
    for (auto& b : bufs) { decorator.process(b); }
} // automatically blocks waiting for pipeline to finish
```

Enforcement

Flag a lambda that captures by reference, but is used other than locally within the function scope or passed to a function by reference. (Note: This rule is an approximation, but does flag passing by pointer as those are more likely to be stored by the callee, writing to a heap location accessed via a parameter, returning the lambda, etc. The Lifetime rules will also provide general rules that flag escaping pointers and references including via lambdas.)

F.53: Avoid capturing by reference in lambdas that will be used non-locally, including returned, stored on the heap, or passed to another thread

Reason

Pointers and references to locals shouldn't outlive their scope. Lambdas that capture by reference are just another place to store a reference to a local object, and shouldn't do so if they (or a copy) outlive the scope.

Example, bad

```
int local = 42;

// Want a reference to local.

// Note, that after program exits this scope,

// local no longer exists, therefore

// process() call will have undefined behavior!

thread_pool.queue_work([&] { process(local); });
```

Example, good

```
int local = 42;
// Want a copy of local.
// Since a copy of local is made, it will
// always be available for the call.
thread_pool.queue_work([=] { process(local); });
```

Note

If a non-local pointer must be captured, consider using unique_ptr; this handles both lifetime and synchronization.

If the this pointer must be captured, consider using [*this] capture, which creates a copy of the entire object.

Enforcement

- (Simple) Warn when capture-list contains a reference to a locally declared variable
- (Complex) Flag when capture-list contains a reference to a locally declared variable and the lambda is passed to a non-const and non-local context

F.54: When writing a lambda that captures this or any class data member, don't use [=] default capture

Reason

It's confusing. Writing [=] in a member function appears to capture by value, but actually captures data members by reference because it actually captures the invisible this pointer by value. If you meant to do that, write this explicitly.

Example

```
class My_class {
  int x = 0;
  // ...

void f()
{
  int i = 0;
  // ...

auto lambda = [=] { use(i, x); }; // BAD: "looks like" copy/value capture
  // [&] has identical semantics and copies the this pointer under the current rules
  // [=,this] and [&,this] are not much better, and confusing

x = 42;
  lambda(); // calls use(0, 42);
```

```
x = 43;
lambda(); // calls use(0, 43);

// ...

auto lambda2 = [i, this] { use(i, x); }; // ok, most explicit and least confusing

// ...
}
};
```

Note

If you intend to capture a copy of all class data members, consider C++17 [*this].

Enforcement

• Flag any lambda capture-list that specifies a capture-default of [=] and also captures this (whether explicitly or via the default capture and a use of this in the body)

F.55: Don't use va_arg arguments

Reason

Reading from a va_arg assumes that the correct type was actually passed. Passing to varargs assumes the correct type will be read. This is fragile because it cannot generally be enforced to be safe in the language and so relies on programmer discipline to get it right.

Example

```
int sum(...)
{
    // ...
    while (/*...*/)
        result += va_arg(list, int); // BAD, assumes it will be passed ints
    // ...
}

sum(3, 2); // ok
sum(3.14159, 2.71828); // BAD, undefined

template<class ...Args>
auto sum(Args... args) // GOOD, and much more flexible
{
    return (... + args); // note: C++17 "fold expression"
}

sum(3, 2); // ok: 5
```

Alternatives

- overloading
- variadic templates
- variant arguments
- initializer_list (homogeneous)

Note

Declaring a ... parameter is sometimes useful for techniques that don't involve actual argument passing, notably to declare "take-anything" functions so as to disable "everything else" in an overload set or express a catchall case in a template metaprogram.

Enforcement

- Issue a diagnostic for using va_list, va_start, or va_arg.
- Issue a diagnostic for passing an argument to a vararg parameter of a function that does not offer an overload for a more specific type in the position of the vararg. To fix: Use a different function, or [[suppress(types)]].

F.56: Avoid unnecessary condition nesting

Reason

Shallow nesting of conditions makes the code easier to follow. It also makes the intent clearer. Strive to place the essential code at outermost scope, unless this obscures intent.

Example

Use a guard-clause to take care of exceptional cases and return early.

```
// Bad: Deep nesting
void foo() {
    ...
    if (x) {
        computeImportantThings(x);
    }
}

// Bad: Still a redundant else.
void foo() {
    ...
    if (!x) {
        return;
    }
    else {
        computeImportantThings(x);
}
```

```
}
}

// Good: Early return, no redundant else
void foo() {
    ...
    if (!x)
        return;

    computeImportantThings(x);
}
```

Example

```
// Bad: Unnecessary nesting of conditions
void foo() {
    ...
    if (x) {
        if (y) {
            computeImportantThings(x);
        }
    }
}

// Good: Merge conditions + return early
void foo() {
    ...
    if (!(x && y))
        return;

computeImportantThings(x);
}
```

Enforcement

Flag a redundant else. Flag a functions whose body is simply a conditional statement enclosing a block.

C: Classes and class hierarchies

A class is a user-defined type, for which a programmer can define the representation, operations, and interfaces. Class hierarchies are used to organize related classes into hierarchical structures.

Class rule summary:

- C.1: Organize related data into structures (structs or classes)
- C.2: Use class if the class has an invariant; use struct if the data members can vary independently

- C.3: Represent the distinction between an interface and an implementation using a class
- C.4: Make a function a member only if it needs direct access to the representation of a class
- C.5: Place helper functions in the same namespace as the class they support
- C.7: Don't define a class or enum and declare a variable of its type in the same statement
- C.8: Use class rather than struct if any member is non-public
- C.9: Minimize exposure of members

Subsections:

- C.concrete: Concrete types
- C.ctor: Constructors, assignments, and destructors
- C.con: Containers and other resource handles
- C.lambdas: Function objects and lambdas
- C.hier: Class hierarchies (OOP)
- C.over: Overloading and overloaded operators
- C.union: Unions

C.1: Organize related data into structures (structs or classes)

Reason

Ease of comprehension. If data is related (for fundamental reasons), that fact should be reflected in code.

Example

```
void draw(int x, int y, int x2, int y2); // BAD: unnecessary implicit relationships
void draw(Point from, Point to); // better
```

Note

A simple class without virtual functions implies no space or time overhead.

Note

From a language perspective class and struct differ only in the default visibility of their members.

Enforcement

Probably impossible. Maybe a heuristic looking for data items used together is possible.

C.2: Use class if the class has an invariant; use struct if the data members can vary independently

Reason

Readability. Ease of comprehension. The use of class alerts the programmer to the need for an invariant. This is a useful convention.

Note

An invariant is a logical condition for the members of an object that a constructor must establish for the public member functions to assume. After the invariant is established (typically by a constructor) every member function can be called for the object. An invariant can be stated informally (e.g., in a comment) or more formally using Expects.

If all data members can vary independently of each other, no invariant is possible.

Example

```
struct Pair { // the members can vary independently
    string name;
    int volume;
};
```

but:

```
class Date {
public:
    // validate that {yy, mm, dd} is a valid date and initialize
    Date(int yy, Month mm, char dd);
    // ...
private:
    int y;
    Month m;
    char d;    // day
};
```

Note

If a class has any private data, a user cannot completely initialize an object without the use of a constructor. Hence, the class definer will provide a constructor and must specify its meaning. This effectively means the definer need to define an invariant.

See also:

- define a class with private data as class
- Prefer to place the interface first in a class
- minimize exposure of members
- Avoid protected data

Enforcement

Look for structs with all data private and classes with public members.

C.3: Represent the distinction between an interface and an implementation using a class

Reason

An explicit distinction between interface and implementation improves readability and simplifies maintenance.

Example

```
class Date {
public:
    Date();
    // validate that {yy, mm, dd} is a valid date and initialize
    Date(int yy, Month mm, char dd);

int day() const;
    Month month() const;
    // ...
private:
    // ... some representation ...
};
```

For example, we can now change the representation of a Date without affecting its users (recompilation is likely, though).

Note

Using a class in this way to represent the distinction between interface and implementation is of course not the only way. For example, we can use a set of declarations of freestanding functions in a namespace, an abstract base class, or a function template with concepts to represent an interface. The most important issue is to explicitly distinguish between an interface and its implementation "details." Ideally, and typically, an interface is far more stable than its implementation(s).

Enforcement

C.4: Make a function a member only if it needs direct access to the representation of a class

Reason

Less coupling than with member functions, fewer functions that can cause trouble by modifying object state, reduces the number of functions that needs to be modified after a change in representation.

Example

```
class Date {
    // ... relatively small interface ...
};

// helper functions:
Date next_weekday(Date);
bool operator==(Date, Date);
```

The "helper functions" have no need for direct access to the representation of a Date.

Note

This rule becomes even better if C++ gets "uniform function call".

Exception

The language requires virtual functions to be members, and not all virtual functions directly access data. In particular, members of an abstract class rarely do.

Note multi-methods.

Exception

The language requires operators =, (), [], and -> to be members.

Exception

An overload set could have some members that do not directly access private data:

```
class Foobar {
public:
    void foo(long x) { /* manipulate private data */ }
    void foo(double x) { foo(std::lround(x)); }
    // ...
private:
    // ...
};
```

Exception

Similarly, a set of functions could be designed to be used in a chain:

```
x.scale(0.5).rotate(45).set_color(Color::red);
```

Typically, some but not all of such functions directly access private data.

Enforcement

- Look for non-virtual member functions that do not touch data members directly. The snag is that many member functions that do not need to touch data members directly do.
- Ignore virtual functions.
- Ignore functions that are part of an overload set out of which at least one function accesses private members.
- Ignore functions returning this.

C.5: Place helper functions in the same namespace as the class they support

Reason

A helper function is a function (usually supplied by the writer of a class) that does not need direct access to the representation of the class, yet is seen as part of the useful interface to the class. Placing them in the same namespace as the class makes their relationship to the class obvious and allows them to be found by argument dependent lookup.

Example

```
namespace Chrono { // here we keep time-related services

class Time { /* ... */ };
 class Date { /* ... */ };

// helper functions:
bool operator==(Date, Date);
Date next_weekday(Date);
// ...
}
```

Note

This is especially important for overloaded operators.

Enforcement

• Flag global functions taking argument types from a single namespace.

C.7: Don't define a class or enum and declare a variable of its type in the same statement

Reason

Mixing a type definition and the definition of another entity in the same declaration is confusing and unnecessary.

Example, bad

```
struct Data { /*...*/ } data{ /*...*/ };
```

Example, good

```
struct Data { /*...*/ };
Data data{ /*...*/ };
```

Enforcement

• Flag if the } of a class or enumeration definition is not followed by a ;. The ; is missing.

C.8: Use class rather than struct if any member is non-public

Reason

Readability. To make it clear that something is being hidden/abstracted. This is a useful convention.

Example, bad

```
struct Date {
   int d, m;

Date(int i, Month m);
   // ... lots of functions ...

private:
   int y; // year
};
```

There is nothing wrong with this code as far as the C++ language rules are concerned, but nearly everything is wrong from a design perspective. The private data is hidden far from the public data. The data is split in different parts of the class declaration. Different parts of the data have different access. All of this decreases readability and complicates maintenance.

Note

Prefer to place the interface first in a class, see NL.16.

Enforcement

Flag classes declared with struct if there is a private or protected member.

C.9: Minimize exposure of members

Reason

Encapsulation. Information hiding. Minimize the chance of unintended access. This simplifies maintenance.

Example

```
template<typename T, typename U>
struct pair {
    T a;
    U b;
    // ...
};
```

Whatever we do in the //-part, an arbitrary user of a pair can arbitrarily and independently change its a and b. In a large code base, we cannot easily find which code does what to the members of pair. This might be exactly what we want, but if we want to enforce a relation among members, we need to make them private and enforce that relation (invariant) through constructors and member functions. For example:

Note

If the set of direct users of a set of variables cannot be easily determined, the type or usage of that set cannot be (easily) changed/improved. For public and protected data, that's usually the case.

Example

A class can provide two interfaces to its users. One for derived classes (protected) and one for general users (public). For example, a derived class might be allowed to skip a run-time check because it has already guaranteed correctness:

```
class Foo {
public:
    int bar(int x) { check(x); return do_bar(x); }
   // ...
protected:
   int do_bar(int x); // do some operation on the data
   // ...
private:
   // ... data ...
};
class Dir : public Foo {
   //...
   int mem(int x, int y)
        /* ... do something ... */
        return do_bar(x + y); // OK: derived class can bypass check
    }
};
void user(Foo& x)
   int r1 = x.bar(1); // OK, will check
   int r2 = x.do_bar(2); // error: would bypass check
   // ...
}
```

Note

protected data is a bad idea.

Note

Prefer the order public members before protected members before private members; see NL.16.

Enforcement

- Flag protected data.
- Flag mixtures of public and private data

C.concrete: Concrete types

Concrete type rule summary:

- C.10: Prefer concrete types over class hierarchies
- C.11: Make concrete types regular
- C.12: Don't make data members const or references in a copyable or movable type

C.10: Prefer concrete types over class hierarchies

Reason

A concrete type is fundamentally simpler than a type in a class hierarchy: easier to design, easier to implement, easier to use, easier to reason about, smaller, and faster. You need a reason (use cases) for using a hierarchy.

Example

```
class Point1 {
    int x, y;
    // ... operations ...
    // ... no virtual functions ...
};
class Point2 {
    int x, y;
    // ... operations, some virtual ...
    virtual ~Point2();
};
void use()
    Point1 p11 {1, 2}; // make an object on the stack
    Point1 p12 {p11}; // a copy
    auto p21 = make_unique<Point2>(1, 2); // make an object on the free store
    auto p22 = p21->clone();
                                           // make a copy
    // ...
}
```

If a class is part of a hierarchy, we (in real code if not necessarily in small examples) must manipulate its objects through pointers or references. That implies more memory overhead, more allocations and deallocations, and more run-time overhead to perform the resulting indirections.

Note

Concrete types can be stack-allocated and be members of other classes.

Note

The use of indirection is fundamental for run-time polymorphic interfaces. The allocation/deallocation overhead is not (that's just the most common case). We can use a base class as the interface of a scoped object of a derived class. This is done where dynamic allocation is prohibited (e.g. hard-real-time) and to provide a stable interface to some kinds of plug-ins.

Enforcement

???

C.11: Make concrete types regular

Reason

Regular types are easier to understand and reason about than types that are not regular (irregularities requires extra effort to understand and use).

The C++ built-in types are regular, and so are standard-library classes such as string, vector, and map. Concrete classes without assignment and equality can be defined, but they are (and should be) rare.

Example

```
struct Bundle {
    string name;
    vector<Record> vr;
};

bool operator==(const Bundle& a, const Bundle& b)
{
    return a.name == b.name && a.vr == b.vr;
}

Bundle b1 { "my bundle", {r1, r2, r3}};
Bundle b2 = b1;
if (!(b1 == b2)) error("impossible!");
b2.name = "the other bundle";
if (b1 == b2) error("No!");
```

In particular, if a concrete type is copyable, prefer to also give it an equality comparison operator, and ensure that a = b implies a == b.

Note

For structs intended to be shared with C code, defining operator== may not be feasible.

Note

Handles for resources that cannot be cloned, e.g., a scoped_lock for a mutex, are concrete types but typically cannot be copied (instead, they can usually be moved), so they can't be regular; instead, they tend to be move-only.

Enforcement

???

C.12: Don't make data members const or references in a copyable or movable type

Reason

const and reference data members are not useful in a copyable or movable type, and make such types difficult to use by making them at least partly uncopyable/unmovable for subtle reasons.

Example; bad

```
class bad {
   const int i;  // bad
   string& s;  // bad
   // ...
};
```

The const and & data members make this class "only-sort-of-copyable" -- copy-constructible but not copyassignable.

Note

If you need a member to point to something, use a pointer (raw or smart, and gsl::not_null if it should not be null) instead of a reference.

Enforcement

Flag a data member that is const, &, or && in a type that has any copy or move operation.

C.ctor: Constructors, assignments, and destructors

These functions control the lifecycle of objects: creation, copy, move, and destruction. Define constructors to guarantee and simplify initialization of classes.

These are *default operations*:

- a default constructor: X()
- a copy constructor: X(const X&)
- a copy assignment: operator=(const X&)
- a move constructor: X(X&&)
- a move assignment: operator=(X&&)
- a destructor: ~X()

By default, the compiler defines each of these operations if it is used, but the default can be suppressed.

The default operations are a set of related operations that together implement the lifecycle semantics of an object. By default, C++ treats classes as value-like types, but not all types are value-like.

Set of default operations rules:

- C.20: If you can avoid defining any default operations, do
- C.21: If you define or =delete any copy, move, or destructor function, define or =delete them all
- C.22: Make default operations consistent

Destructor rules:

- C.30: Define a destructor if a class needs an explicit action at object destruction
- C.31: All resources acquired by a class must be released by the class's destructor
- C.32: If a class has a raw pointer (T*) or reference (T&), consider whether it might be owning
- C.33: If a class has an owning pointer member, define a destructor
- C.35: A base class destructor should be either public and virtual, or protected and non-virtual
- C.36: A destructor must not fail
- C.37: Make destructors noexcept

Constructor rules:

- C.40: Define a constructor if a class has an invariant
- C.41: A constructor should create a fully initialized object
- C.42: If a constructor cannot construct a valid object, throw an exception
- C.43: Ensure that a copyable class has a default constructor
- C.44: Prefer default constructors to be simple and non-throwing
- C.45: Don't define a default constructor that only initializes data members; use member initializers instead
- C.46: By default, declare single-argument constructors explicit
- C.47: Define and initialize member variables in the order of member declaration
- C.48: Prefer in-class initializers to member initializers in constructors for constant initializers
- C.49: Prefer initialization to assignment in constructors
- C.50: Use a factory function if you need "virtual behavior" during initialization
- C.51: Use delegating constructors to represent common actions for all constructors of a class
- C.52: Use inheriting constructors to import constructors into a derived class that does not need further explicit initialization

Copy and move rules:

C.60: Make copy assignment non-virtual, take the parameter by const&, and return by non-const&

- C.61: A copy operation should copy
- C.62: Make copy assignment safe for self-assignment
- C.63: Make move assignment non-virtual, take the parameter by &&, and return by non-const&
- C.64: A move operation should move and leave its source in a valid state
- C.65: Make move assignment safe for self-assignment
- C.66: Make move operations noexcept
- C.67: A polymorphic class should suppress public copy/move

Other default operations rules:

- C.80: Use =default if you have to be explicit about using the default semantics
- C.81: Use =delete when you want to disable default behavior (without wanting an alternative)
- C.82: Don't call virtual functions in constructors and destructors
- C.83: For value-like types, consider providing a noexcept swap function
- C.84: A swap must not fail
- C.85: Make swap noexcept
- C.86: Make == symmetric with respect of operand types and noexcept
- C.87: Beware of == on base classes
- C.89: Make a hash noexcept
- C.90: Rely on constructors and assignment operators, not memset and memcpy

C.defop: Default Operations

By default, the language supplies the default operations with their default semantics. However, a programmer can disable or replace these defaults.

C.20: If you can avoid defining default operations, do

Reason

It's the simplest and gives the cleanest semantics.

Example

```
struct Named_map {
public:
    // ... no default operations declared ...
private:
    string name;
    map<int, int> rep;
};

Named_map nm;    // default construct
Named_map nm2 {nm};    // copy construct
```

Since std::map and string have all the special functions, no further work is needed.

This is known as "the rule of zero".

Enforcement

(Not enforceable) While not enforceable, a good static analyzer can detect patterns that indicate a possible improvement to meet this rule. For example, a class with a (pointer, size) pair of members and a destructor that deletes the pointer could probably be converted to a vector.

C.21: If you define or =delete any copy, move, or destructor function, define or =delete them all

Reason

The semantics of copy, move, and destruction are closely related, so if one needs to be declared, the odds are that others need consideration too.

Declaring any copy/move/destructor function, even as =default or =delete, will suppress the implicit declaration of a move constructor and move assignment operator. Declaring a move constructor or move assignment operator, even as =default or =delete, will cause an implicitly generated copy constructor or implicitly generated copy assignment operator to be defined as deleted. So as soon as any of these are declared, the others should all be declared to avoid unwanted effects like turning all potential moves into more expensive copies, or making a class move-only.

Example, bad

```
struct M2 {
              // bad: incomplete set of copy/move/destructor operations
public:
   // ...
   // ... no copy or move operations ...
   ~M2() { delete[] rep; }
private:
    pair<int, int>* rep; // zero-terminated set of pairs
};
void use()
   M2 x;
   M2 y;
   // ...
           // the default assignment
   x = y;
   // ...
}
```

Given that "special attention" was needed for the destructor (here, to deallocate), the likelihood that the implicitly-defined copy and move assignment operators will be correct is low (here, we would get double deletion).

This is known as "the rule of five."

Note

If you want a default implementation (while defining another), write =default to show you're doing so intentionally for that function. If you don't want a generated default function, suppress it with =delete.

Example, good

When a destructor needs to be declared just to make it virtual, it can be defined as defaulted.

```
class AbstractBase {
public:
    virtual void foo() = 0; // at least one abstract method to make the class abstract
    virtual ~AbstractBase() = default;
    // ...
};
```

To prevent slicing as per C.67, make the copy and move operations protected or =deleted, and add a clone:

```
class CloneableBase {
public:
    virtual unique_ptr<CloneableBase> clone() const;
    virtual ~CloneableBase() = default;
    CloneableBase() = default;
    CloneableBase(const CloneableBase&) = delete;
    CloneableBase& operator=(const CloneableBase&) = delete;
    CloneableBase(CloneableBase&&) = delete;
    CloneableBase& operator=(CloneableBase&&) = delete;
    // ... other constructors and functions ...
};
```

Defining only the move operations or only the copy operations would have the same effect here, but stating the intent explicitly for each special member makes it more obvious to the reader.

Note

Compilers enforce much of this rule and ideally warn about any violation.

Note

Relying on an implicitly generated copy operation in a class with a destructor is deprecated.

Note

Writing these functions can be error-prone. Note their argument types:

A minor mistake (such as a misspelling, leaving out a const, using & instead of &&, or leaving out a special function) can lead to errors or warnings. To avoid the tedium and the possibility of errors, try to follow the rule of zero.

Enforcement

(Simple) A class should have a declaration (even a =delete one) for either all or none of the copy/move/destructor functions.

C.22: Make default operations consistent

Reason

The default operations are conceptually a matched set. Their semantics are interrelated. Users will be surprised if copy/move construction and copy/move assignment do logically different things. Users will be surprised if constructors and destructors do not provide a consistent view of resource management. Users will be surprised if copy and move don't reflect the way constructors and destructors work.

Example, bad

```
class Silly {    // BAD: Inconsistent copy operations
    class Impl {
        // ...
};
shared_ptr<Impl> p;
public:
    Silly(const Silly& a) : p(make_shared<Impl>()) { *p = *a.p; } // deep copy
    Silly& operator=(const Silly& a) { p = a.p; return *this; } // shallow copy
    // ...
};
```

These operations disagree about copy semantics. This will lead to confusion and bugs.

Enforcement

- (Complex) A copy/move constructor and the corresponding copy/move assignment operator should write to the same member variables at the same level of dereference.
- (Complex) Any member variables written in a copy/move constructor should also be initialized by all other constructors.
- (Complex) If a copy/move constructor performs a deep copy of a member variable, then the destructor should modify the member variable.
- (Complex) If a destructor is modifying a member variable, that member variable should be written in any copy/move constructors or assignment operators.

C.dtor: Destructors

"Does this class need a destructor?" is a surprisingly insightful design question. For most classes the answer is "no" either because the class holds no resources or because destruction is handled by the rule of zero; that is, its members can take care of themselves as concerns destruction. If the answer is "yes", much of the design of the class follows (see the rule of five).

C.30: Define a destructor if a class needs an explicit action at object destruction

Reason

A destructor is implicitly invoked at the end of an object's lifetime. If the default destructor is sufficient, use it. Only define a non-default destructor if a class needs to execute code that is not already part of its members' destructors.

Example

```
template<typename A>
struct final_action {    // slightly simplified
    A act;
    final_action(A a) : act{a} {}
    ~final_action() { act(); }
};

template<typename A>
final_action<A> finally(A act)    // deduce action type
{
    return final_action<A>{act};
}

void test()
{
    auto act = finally([] { cout << "Exit test\n"; });    // establish exit action</pre>
```

```
// ...
if (something) return; // act done here
// ...
} // act done here
```

The whole purpose of final_action is to get a piece of code (usually a lambda) executed upon destruction.

Note

There are two general categories of classes that need a user-defined destructor:

- A class with a resource that is not already represented as a class with a destructor, e.g., a vector or a transaction class.
- A class that exists primarily to execute an action upon destruction, such as a tracer or final_action.

Example, bad

```
class Foo { // bad; use the default destructor
public:
    // ...
    ~Foo() { s = ""; i = 0; vi.clear(); } // clean up
private:
    string s;
    int i;
    vector<int> vi;
};
```

The default destructor does it better, more efficiently, and can't get it wrong.

Note

If the default destructor is needed, but its generation has been suppressed (e.g., by defining a move constructor), use =default.

Enforcement

Look for likely "implicit resources", such as pointers and references. Look for classes with destructors even though all their data members have destructors.

C.31: All resources acquired by a class must be released by the class's destructor

Reason

Prevention of resource leaks, especially in error cases.

Note

For resources represented as classes with a complete set of default operations, this happens automatically.

Example

```
class X {
   ifstream f; // might own a file
   // ... no default operations defined or =deleted ...
};
```

X's ifstream implicitly closes any file it might have open upon destruction of its X.

Example, bad

```
class X2 {      // bad
    FILE* f;      // might own a file
    // ... no default operations defined or =deleted ...
};
```

X2 might leak a file handle.

Note

What about a socket that won't close? A destructor, close, or cleanup operation should never fail. If it does nevertheless, we have a problem that has no really good solution. For starters, the writer of a destructor does not know why the destructor is called and cannot "refuse to act" by throwing an exception. See discussion. To make the problem worse, many "close/release" operations are not retryable. Many have tried to solve this problem, but no general solution is known. If at all possible, consider failure to close/cleanup a fundamental design error and terminate.

Note

A class can hold pointers and references to objects that it does not own. Obviously, such objects should not be deleted by the class's destructor. For example:

```
Preprocessor pp { /* ... */ };

Parser p { pp, /* ... */ };

Type_checker tc { p, /* ... */ };
```

Here p refers to pp but does not own it.

Enforcement

- (Simple) If a class has pointer or reference member variables that are owners (e.g., deemed owners by using gsl::owner), then they should be referenced in its destructor.
- (Hard) Determine if pointer or reference member variables are owners when there is no explicit statement of ownership (e.g., look into the constructors).

C.32: If a class has a raw pointer (T*) or reference (T&), consider whether it might be owning

Reason

There is a lot of code that is non-specific about ownership.

Example

```
class legacy_class
{
   foo* m_owning; // Bad: change to unique_ptr<T> or owner<T*>
   bar* m_observer; // OK: keep
}
```

The only way to determine ownership may be code analysis.

Note

Ownership should be clear in new code (and refactored legacy code) according to R.20 for owning pointers and R.3 for non-owning pointers. References should never own R.4.

Enforcement

Look at the initialization of raw member pointers and member references and see if an allocation is used.

C.33: If a class has an owning pointer member, define a destructor

Reason

An owned object must be deleted upon destruction of the object that owns it.

Example

A pointer member could represent a resource. A T* should not do so, but in older code, that's common. Consider a T* a possible owner and therefore suspect.

```
template<typename T>
class Smart_ptr {
    T* p;  // BAD: vague about ownership of *p
    // ...
public:
    // ... no user-defined default operations ...
};

void use(Smart_ptr<int> p1)
{
    // error: p2.p leaked (if not nullptr and not owned by some other code)
    auto p2 = p1;
}
```

Note that if you define a destructor, you must define or delete all default operations:

```
template<typename T>
class Smart_ptr2 {
    T* p;    // BAD: vague about ownership of *p
    // ...
public:
    // ... no user-defined copy operations ...
    ~Smart_ptr2() { delete p; }    // p is an owner!
};

void use(Smart_ptr2<int> p1)
{
    auto p2 = p1;    // error: double deletion
}
```

The default copy operation will just copy the p1.p into p2.p leading to a double destruction of p1.p. Be explicit about ownership:

```
template<typename T>
class Smart_ptr3 {
   owner<T*> p; // OK: explicit about ownership of *p
   // ...
public:
   // ...
   // ... copy and move operations ...
   ~Smart_ptr3() { delete p; }
};

void use(Smart_ptr3<int> p1)
{
   auto p2 = p1; // OK: no double deletion
```

Often the simplest way to get a destructor is to replace the pointer with a smart pointer (e.g., std::unique_ptr) and let the compiler arrange for proper destruction to be done implicitly.

Note

Why not just require all owning pointers to be "smart pointers"? That would sometimes require non-trivial code changes and might affect ABIs.

Enforcement

- A class with a pointer data member is suspect.
- A class with an owner<T> should define its default operations.

C.35: A base class destructor should be either public and virtual, or protected and non-virtual

Reason

To prevent undefined behavior. If the destructor is public, then calling code can attempt to destroy a derived class object through a base class pointer, and the result is undefined if the base class's destructor is non-virtual. If the destructor is protected, then calling code cannot destroy through a base class pointer and the destructor does not need to be virtual; it does need to be protected, not private, so that derived destructors can invoke it. In general, the writer of a base class does not know the appropriate action to be done upon destruction.

Discussion

See this in the Discussion section.

Example, bad

```
struct Base { // BAD: implicitly has a public non-virtual destructor
    virtual void f();
};

struct D: Base {
    string s {"a resource needing cleanup"};
    ~D() { /* ... do some cleanup ... */ }
    // ...
};

void use()
{
    unique_ptr<Base> p = make_unique<D>();
    // ...
```

```
} // p's destruction calls ~Base(), not ~D(), which leaks D::s and possibly more
```

A virtual function defines an interface to derived classes that can be used without looking at the derived classes. If the interface allows destroying, it should be safe to do so.

Note

A destructor must be non-private or it will prevent using the type:

Exception

We can imagine one case where you could want a protected virtual destructor: When an object of a derived type (and only of such a type) should be allowed to destroy *another* object (not itself) through a pointer to base. We haven't seen such a case in practice, though.

Enforcement

- A class with any virtual functions should have a destructor that is either public and virtual or else protected and non-virtual.
- If a class inherits publicly from a base class, the base class should have a destructor that is either public and virtual or else protected and non-virtual.

C.36: A destructor must not fail

Reason

In general we do not know how to write error-free code if a destructor should fail. The standard library requires that all classes it deals with have destructors that do not exit by throwing.

Example

```
class X {
public:
    ~X() noexcept;
    // ...
};

X::~X() noexcept
{
    // ...
    if (cannot_release_a_resource) terminate();
    // ...
}
```

Note

Many have tried to devise a fool-proof scheme for dealing with failure in destructors. None have succeeded to come up with a general scheme. This can be a real practical problem: For example, what about a socket that won't close? The writer of a destructor does not know why the destructor is called and cannot "refuse to act" by throwing an exception. See discussion. To make the problem worse, many "close/release" operations are not retryable. If at all possible, consider failure to close/cleanup a fundamental design error and terminate.

Note

Declare a destructor noexcept. That will ensure that it either completes normally or terminates the program.

Note

If a resource cannot be released and the program must not fail, try to signal the failure to the rest of the system somehow (maybe even by modifying some global state and hope something will notice and be able to take care of the problem). Be fully aware that this technique is special-purpose and error-prone. Consider the "my connection will not close" example. Probably there is a problem at the other end of the connection and only a piece of code responsible for both ends of the connection can properly handle the problem. The destructor could send a message (somehow) to the responsible part of the system, consider that to have closed the connection, and return normally.

Note

If a destructor uses operations that could fail, it can catch exceptions and in some cases still complete successfully (e.g., by using a different clean-up mechanism from the one that threw an exception).

Enforcement

(Simple) A destructor should be declared noexcept if it could throw.

C.37: Make destructors noexcept

Reason

A destructor must not fail. If a destructor tries to exit with an exception, it's a bad design error and the program had better terminate.

Note

A destructor (either user-defined or compiler-generated) is implicitly declared noexcept (independently of what code is in its body) if all of the members of its class have noexcept destructors. By explicitly marking destructors noexcept, an author guards against the destructor becoming implicitly noexcept(false) through the addition or modification of a class member.

Example

Not all destructors are no except by default; one throwing member poisons the whole class hierarchy

```
struct X {
    Details x; // happens to have a throwing destructor
    // ...
    ~X() { } // implicitly noexcept(false); aka can throw
};
```

So, if in doubt, declare a destructor noexcept.

Note

Why not then declare all destructors noexcept? Because that would in many cases -- especially simple cases -- be distracting clutter.

Enforcement

(Simple) A destructor should be declared noexcept if it could throw.

C.ctor: Constructors

A constructor defines how an object is initialized (constructed).

C.40: Define a constructor if a class has an invariant

Reason

That's what constructors are for.

Example

It is often a good idea to express the invariant as an Ensures on the constructor.

Note

A constructor can be used for convenience even if a class does not have an invariant. For example:

```
struct Rec {
    string s;
    int i {0};
    Rec(const string& ss) : s{ss} {}
    Rec(int ii) :i{ii} {}
};

Rec r1 {7};
Rec r2 {"Foo bar"};
```

Note

The C++11 initializer list rule eliminates the need for many constructors. For example:

```
struct Rec2{
    string s;
    int i;
    Rec2(const string& ss, int ii = 0) :s{ss}, i{ii} {} // redundant
};

Rec2 r1 {"Foo", 7};
Rec2 r2 {"Bar"};
```

The Rec2 constructor is redundant. Also, the default for int would be better done as a member initializer.

See also: construct valid object and constructor throws.

Enforcement

• Flag classes with user-defined copy operations but no constructor (a user-defined copy is a good indicator that the class has an invariant)

C.41: A constructor should create a fully initialized object

Reason

A constructor establishes the invariant for a class. A user of a class should be able to assume that a constructed object is usable.

Example, bad

```
class X1 {
   FILE* f; // call init() before any other function
   // ...
public:
   X1() {}
   void init(); // initialize f
   void read(); // read from f
   // ...
};
void f()
   X1 file;
   file.read(); // crash or bad read!
   // ...
   file.init(); // too late
   // ...
}
```

Compilers do not read comments.

Exception

If a valid object cannot conveniently be constructed by a constructor, use a factory function.

Enforcement

- (Simple) Every constructor should initialize every member variable (either explicitly, via a delegating ctor call or via default construction).
- (Unknown) If a constructor has an Ensures contract, try to see if it holds as a postcondition.

If a constructor acquires a resource (to create a valid object), that resource should be released by the destructor. The idiom of having constructors acquire resources and destructors release them is called RAII ("Resource Acquisition Is Initialization").

C.42: If a constructor cannot construct a valid object, throw an exception

Reason

Leaving behind an invalid object is asking for trouble.

Example

```
class X2 {
   FILE* f;
   // ...
public:
   X2(const string& name)
       :f{fopen(name.c_str(), "r")}
   {
       if (!f) throw runtime_error{"could not open" + name};
   }
   void read(); // read from f
   // ...
};
void f()
   X2 file {"Zeno"}; // throws if file isn't open
   file.read(); // fine
   // ...
}
```

Example, bad

```
}
    bool is_valid() { return valid; }
    void read(); // read from f
    // ...
};
void f()
{
    X3 file {"Heraclides"};
    file.read(); // crash or bad read!
    // ...
    if (file.is_valid()) {
        file.read();
        // ...
    }
    else {
        // ... handle error ...
    }
    // ...
}
```

For a variable definition (e.g., on the stack or as a member of another object) there is no explicit function call from which an error code could be returned. Leaving behind an invalid object and relying on users to consistently check an is_valid() function before use is tedious, error-prone, and inefficient.

Exception

There are domains, such as some hard-real-time systems (think airplane controls) where (without additional tool support) exception handling is not sufficiently predictable from a timing perspective. There the <code>is_valid()</code> technique must be used. In such cases, check <code>is_valid()</code> consistently and immediately to simulate RAII.

Alternative

If you feel tempted to use some "post-constructor initialization" or "two-stage initialization" idiom, try not to do that. If you really have to, look at factory functions.

Note

One reason people have used init() functions rather than doing the initialization work in a constructor has been to avoid code replication. Delegating constructors and default member initialization do that better. Another reason has been to delay initialization until an object is needed; the solution to that is often not to declare a variable until it can be properly initialized

C.43: Ensure that a copyable class has a default constructor

Reason

That is, ensure that if a concrete class is copyable it also satisfies the rest of "semiregular."

Many language and library facilities rely on default constructors to initialize their elements, e.g. T a[10] and std::vector<T> v(10). A default constructor often simplifies the task of defining a suitable moved-from state for a type that is also copyable.

Example

```
class Date { // BAD: no default constructor
public:
    Date(int dd, int mm, int yyyy);
    // ...
};

vector<Date> vd1(1000); // default Date needed here
vector<Date> vd2(1000, Date{7, Month::October, 1885}); // alternative
```

The default constructor is only auto-generated if there is no user-declared constructor, hence it's impossible to initialize the vector vd1 in the example above. The absence of a default value can cause surprises for users and complicate its use, so if one can be reasonably defined, it should be.

Date is chosen to encourage thought: There is no "natural" default date (the big bang is too far back in time to be useful for most people), so this example is non-trivial. {0, 0, 0} is not a valid date in most calendar systems, so choosing that would be introducing something like floating-point's NaN. However, most realistic Date classes have a "first date" (e.g. January 1, 1970 is popular), so making that the default is usually trivial.

```
class Date {
public:
    Date(int dd, int mm, int yyyy);
    Date() = default; // [See also](#Rc-default)
    // ...
private:
    int dd {1};
    int mm {1};
    int yyyy {1970};
    // ...
};
vector<Date> vd1(1000);
```

A class with members that all have default constructors implicitly gets a default constructor:

```
struct X {
    string s;
    vector<int> v;
};

X x; // means X{{}, {}}; that is the empty string and the empty vector
```

Beware that built-in types are not properly default constructed:

Statically allocated objects of built-in types are by default initialized to 0, but local built-in variables are not. Beware that your compiler might default initialize local built-in variables, whereas an optimized build will not. Thus, code like the example above might appear to work, but it relies on undefined behavior. Assuming that you want initialization, an explicit default initialization can help:

```
struct X {
   string s;
   int i {}; // default initialize (to 0)
};
```

Notes

Classes that don't have a reasonable default construction are usually not copyable either, so they don't fall under this guideline.

For example, a base class should not be copyable, and so does not necessarily need a default constructor:

```
// Shape is an abstract base class, not a copyable type.
// It might or might not need a default constructor.
struct Shape {
    virtual void draw() = 0;
    virtual void rotate(int) = 0;
    // =delete copy/move functions
    // ...
};
```

A class that must acquire a caller-provided resource during construction often cannot have a default constructor, but it does not fall under this guideline because such a class is usually not copyable anyway:

```
// std::lock_guard is not a copyable type.
// It does not have a default constructor.
lock_guard g {mx}; // guard the mutex mx
lock_guard g2; // error: guarding nothing
```

A class that has a "special state" that must be handled separately from other states by member functions or users causes extra work (and most likely more errors). Such a type can naturally use the special state as a default constructed value, whether or not it is copyable:

```
// std::ofstream is not a copyable type.
// It does happen to have a default constructor
// that goes along with a special "not open" state.
ofstream out {"Foobar"};
// ...
out << log(time, transaction);</pre>
```

Similar special-state types that are copyable, such as copyable smart pointers that have the special state "==nullptr", should use the special state as their default constructed value.

However, it is preferable to have a default constructor default to a meaningful state such as std::strings "" and std::vectors {}.

Enforcement

- Flag classes that are copyable by = without a default constructor
- Flag classes that are comparable with == but not copyable

C.44: Prefer default constructors to be simple and non-throwing

Reason

Being able to set a value to "the default" without operations that might fail simplifies error handling and reasoning about move operations.

Example, problematic

```
template<typename T>
// elem points to space-elem element allocated using new
class Vector0 {
public:
    Vector0() :Vector0{0} {}
    Vector0(int n) :elem{new T[n]}, space{elem + n}, last{elem} {}
    // ...
private:
    own<T*> elem;
    T* space;
    T* last;
};
```

This is nice and general, but setting a Vector0 to empty after an error involves an allocation, which might fail. Also, having a default Vector represented as $\{new\ T[0],\ 0,\ 0\}$ seems wasteful. For example, Vector0<int>v[100] costs 100 allocations.

Example

```
template<typename T>
// elem is nullptr or elem points to space-elem element allocated using new
class Vector1 {
public:
    // sets the representation to {nullptr, nullptr, nullptr}; doesn't throw
    Vector1() noexcept {}
    Vector1(int n) :elem{new T[n]}, space{elem + n}, last{elem} {}
    // ...
private:
    own<T*> elem {};
    T* space {};
    T* last {};
};
```

Using {nullptr, nullptr} makes Vector1{} cheap, but a special case and implies run-time checks. Setting a Vector1 to empty after detecting an error is trivial.

Enforcement

Flag throwing default constructors

C.45: Don't define a default constructor that only initializes data members; use in-class member initializers instead

Reason

Using in-class member initializers lets the compiler generate the function for you. The compiler-generated function can be more efficient.

Example, bad

```
class X1 { // BAD: doesn't use member initializers
    string s;
    int i;
public:
    X1() :s{"default"}, i{1} { }
    // ...
};
```

Example

```
class X2 {
    string s {"default"};
    int i {1};
public:
    // use compiler-generated default constructor
    // ...
};
```

Enforcement

(Simple) A default constructor should do more than just initialize member variables with constants.

C.46: By default, declare single-argument constructors explicit

Reason

To avoid unintended conversions.

Example, bad

```
class String {
public:
    String(int); // BAD
    // ...
};

String s = 10; // surprise: string of size 10
```

Exception

If you really want an implicit conversion from the constructor argument type to the class type, don't use explicit:

```
class Complex {
public:
    Complex(double d);    // OK: we want a conversion from d to {d, 0}
    // ...
};
Complex z = 10.7;    // unsurprising conversion
```

See also: Discussion of implicit conversions

Note

Copy and move constructors should not be made explicit because they do not perform conversions. Explicit copy/move constructors make passing and returning by value difficult.

Enforcement

(Simple) Single-argument constructors should be declared explicit. Good single argument non-explicit constructors are rare in most code bases. Warn for all that are not on a "positive list".

C.47: Define and initialize member variables in the order of member declaration

Reason

To minimize confusion and errors. That is the order in which the initialization happens (independent of the order of member initializers).

Example, bad

```
class Foo {
    int m1;
    int m2;
public:
    Foo(int x) :m2{x}, m1{++x} { } // BAD: misleading initializer order
    // ...
};
Foo x(1); // surprise: x.m1 == x.m2 == 2
```

Enforcement

(Simple) A member initializer list should mention the members in the same order they are declared.

See also: Discussion

C.48: Prefer in-class initializers to member initializers in constructors for constant initializers

Reason

Makes it explicit that the same value is expected to be used in all constructors. Avoids repetition. Avoids maintenance problems. It leads to the shortest and most efficient code.

Example, bad

How would a maintainer know whether j was deliberately uninitialized (probably a bad idea anyway) and whether it was intentional to give s the default value "" in one case and qqq in another (almost certainly a bug)? The problem with j (forgetting to initialize a member) often happens when a new member is added to an existing class.

Example

Alternative: We can get part of the benefits from default arguments to constructors, and that is not uncommon in older code. However, that is less explicit, causes more arguments to be passed, and is repetitive when there is more than one constructor:

Enforcement

- (Simple) Every constructor should initialize every member variable (either explicitly, via a delegating ctor call or via default construction).
- (Simple) Default arguments to constructors suggest an in-class initializer might be more appropriate.

C.49: Prefer initialization to assignment in constructors

Reason

An initialization explicitly states that initialization, rather than assignment, is done and can be more elegant and efficient. Prevents "use before set" errors.

Example, good

```
class A {  // Good
    string s1;
public:
    A(czstring p) : s1{p} { }  // GOOD: directly construct (and the C-string is explicitly
named)
    // ...
};
```

Example, bad

```
class B {  // BAD
    string s1;
public:
    B(const char* p) { s1 = p; }  // BAD: default constructor followed by assignment
    // ...
};

class C {  // UGLY, aka very bad
    int* p;
public:
    C() { cout << *p; p = new int{10}; }  // accidental use before initialized
    // ...
};</pre>
```

Example, better still

Instead of those const char*s we could use C++17 std::string_view or gsl::span<char> as a more general way to present arguments to a function:

```
class D { // Good
    string s1;
public:
    D(string_view v) : s1{v} { } // GOOD: directly construct
    // ...
};
```

C.50: Use a factory function if you need "virtual behavior" during initialization

Reason

If the state of a base class object must depend on the state of a derived part of the object, we need to use a virtual function (or equivalent) while minimizing the window of opportunity to misuse an imperfectly constructed object.

The return type of the factory should normally be unique_ptr by default; if some uses are shared, the caller can move the unique_ptr into a shared_ptr. However, if the factory author knows that all uses of the returned object will be shared uses, return shared_ptr and use make_shared in the body to save an allocation.

Example, bad

```
class B {
public:
    B()
    {
        /* ... */
        f(); // BAD: C.82: Don't call virtual functions in constructors and destructors
        /* ... */
    }
    virtual void f() = 0;
};
```

Example

```
class B {
protected:
   class Token {};
public:
    explicit B(Token) { /* ... */ } // create an imperfectly initialized object
   virtual void f() = 0;
   template<class T>
   static shared_ptr<T> create() // interface for creating shared objects
        auto p = make_shared<T>(typename T::Token{});
        p->post_initialize();
        return p;
    }
protected:
   virtual void post_initialize() // called right after construction
        { /* \ldots */ f(); /* \ldots */ } // GOOD: virtual dispatch is safe
};
class D : public B {
                                    // some derived class
protected:
   class Token {};
public:
   explicit D(Token) : B{ B::Token{} } {}
   void f() override { /* ... */ };
```

```
protected:
    template<class T>
    friend shared_ptr<T> B::create();
};
shared_ptr<D> p = D::create<D>(); // creating a D object
```

make_shared requires that the constructor is public. By requiring a protected Token the constructor cannot be publicly called anymore, so we avoid an incompletely constructed object escaping into the wild. By providing the factory function create(), we make construction (on the free store) convenient.

Note

Conventional factory functions allocate on the free store, rather than on the stack or in an enclosing object.

See also: Discussion

C.51: Use delegating constructors to represent common actions for all constructors of a class

Reason

To avoid repetition and accidental differences.

Example, bad

```
class Date { // BAD: repetitive
   int d;
   Month m;
   int y;
public:
   Date(int dd, Month mm, year yy)
       :d{dd}, m{mm}, y{yy}
       { if (!valid(d, m, y)) throw Bad_date{}; }

   Date(int dd, Month mm)
      :d{dd}, m{mm} y{current_year()}
       { if (!valid(d, m, y)) throw Bad_date{}; }

   // ...
};
```

The common action gets tedious to write and might accidentally not be common.

Example

```
class Date2 {
   int d;
   Month m;
   int y;
public:
   Date2(int dd, Month mm, year yy)
       :d{dd}, m{mm}, y{yy}
       { if (!valid(d, m, y)) throw Bad_date{}; }

   Date2(int dd, Month mm)
       :Date2{dd, mm, current_year()} {}
   // ...
};
```

See also: If the "repeated action" is a simple initialization, consider an in-class member initializer.

Enforcement

(Moderate) Look for similar constructor bodies.

C.52: Use inheriting constructors to import constructors into a derived class that does not need further explicit initialization

Reason

If you need those constructors for a derived class, re-implementing them is tedious and error-prone.

Example

std::vector has a lot of tricky constructors, so if I want my own vector, I don't want to reimplement them:

```
class Rec {
    // ... data and lots of nice constructors ...
};

class Oper : public Rec {
    using Rec::Rec;
    // ... no data members ...
    // ... lots of nice utility functions ...
};
```

Example, bad

```
struct Rec2 : public Rec {
   int x;
   using Rec::Rec;
};

Rec2 r {"foo", 7};
int val = r.x; // uninitialized
```

Enforcement

Make sure that every member of the derived class is initialized.

C.copy: Copy and move

Concrete types should generally be copyable, but interfaces in a class hierarchy should not. Resource handles might or might not be copyable. Types can be defined to move for logical as well as performance reasons.

C.60: Make copy assignment non-virtual, take the parameter by const&, and return by non-const&

Reason

It is simple and efficient. If you want to optimize for rvalues, provide an overload that takes a && (see F.18).

Example

```
a = f(); // assign rvalue: potentially move
```

The swap implementation technique offers the strong guarantee.

Example

But what if you can get significantly better performance by not making a temporary copy? Consider a simple Vector intended for a domain where assignment of large, equal-sized Vectors is common. In this case, the copy of elements implied by the swap implementation technique could cause an order of magnitude increase in cost:

```
template<typename T>
class Vector {
public:
    Vector& operator=(const Vector&);
    // ...
private:
    T* elem;
    int sz;
};
Vector& Vector::operator=(const Vector& a)
{
    if (a.sz > sz) {
        // ... use the swap technique, it can't be bettered ...
        return *this;
    }
    // ... copy sz elements from *a.elem to elem ...
    if (a.sz < sz) {
        // ... destroy the surplus elements in *this and adjust size ...
    }
    return *this;
}
```

By writing directly to the target elements, we will get only the basic guarantee rather than the strong guarantee offered by the swap technique. Beware of self-assignment.

Alternatives: If you think you need a virtual assignment operator, and understand why that's deeply problematic, don't call it operator=. Make it a named function like virtual void assign(const Foo&). See copy constructor vs. clone().

Enforcement

- (Simple) An assignment operator should not be virtual. Here be dragons!
- (Simple) An assignment operator should return T& to enable chaining, not alternatives like const T& which interfere with composability and putting objects in containers.
- (Moderate) An assignment operator should (implicitly or explicitly) invoke all base and member assignment operators. Look at the destructor to determine if the type has pointer semantics or value semantics.

C.61: A copy operation should copy

Reason

That is the generally assumed semantics. After x = y, we should have x == y. After a copy x and y can be independent objects (value semantics, the way non-pointer built-in types and the standard-library types work) or refer to a shared object (pointer semantics, the way pointers work).

Example

```
class X { // OK: value semantics
public:
   X();
   X(const X&); // copy X
   void modify(); // change the value of X
   // ...
   ~X() { delete[] p; }
private:
   T* p;
   int sz;
};
bool operator==(const X& a, const X& b)
   return a.sz == b.sz && equal(a.p, a.p + a.sz, b.p, b.p + b.sz);
}
X::X(const X& a)
    :p{new T[a.sz]}, sz{a.sz}
{
   copy(a.p, a.p + sz, p);
}
X x;
X y = x;
if (x != y) throw Bad{};
x.modify();
if (x == y) throw Bad{}; // assume value semantics
```

Example

```
int sz;
};

bool operator==(const X2& a, const X2& b)
{
    return a.sz == b.sz && a.p == b.p;
}

X2 x;
X2 y = x;
if (x != y) throw Bad{};
x.modify();
if (x != y) throw Bad{}; // assume pointer semantics
```

Prefer value semantics unless you are building a "smart pointer". Value semantics is the simplest to reason about and what the standard-library facilities expect.

Enforcement

(Not enforceable)

C.62: Make copy assignment safe for self-assignment

Reason

If x = x changes the value of x, people will be surprised and bad errors will occur (often including leaks).

Example

The standard-library containers handle self-assignment elegantly and efficiently:

```
std::vector<int> v = {3, 1, 4, 1, 5, 9};
v = v;
// the value of v is still {3, 1, 4, 1, 5, 9}
```

Note

The default assignment generated from members that handle self-assignment correctly handles self-assignment.

```
struct Bar {
    vector<pair<int, int>> v;
    map<string, int> m;
    string s;
};

Bar b;
// ...
b = b; // correct and efficient
```

You can handle self-assignment by explicitly testing for self-assignment, but often it is faster and more elegant to cope without such a test (e.g., using swap).

```
class Foo {
    string s;
    int i;
public:
    Foo& operator=(const Foo& a);
    // ...
};

Foo& Foo::operator=(const Foo& a) // OK, but there is a cost
{
    if (this == &a) return *this;
    s = a.s;
    i = a.i;
    return *this;
}
```

This is obviously safe and apparently efficient. However, what if we do one self-assignment per million assignments? That's about a million redundant tests (but since the answer is essentially always the same, the computer's branch predictor will guess right essentially every time). Consider:

```
Foo& Foo::operator=(const Foo& a) // simpler, and probably much better
{
    s = a.s;
    i = a.i;
    return *this;
}
```

std::string is safe for self-assignment and so are int. All the cost is carried by the (rare) case of self-assignment.

Enforcement

(Simple) Assignment operators should not contain the pattern if (this == &a) return *this; ???

C.63: Make move assignment non-virtual, take the parameter by &&, and return by non-const&

Reason

It is simple and efficient.

See: The rule for copy-assignment.

Enforcement

Equivalent to what is done for copy-assignment.

- (Simple) An assignment operator should not be virtual. Here be dragons!
- (Simple) An assignment operator should return T& to enable chaining, not alternatives like const T& which interfere with composability and putting objects in containers.
- (Moderate) A move assignment operator should (implicitly or explicitly) invoke all base and member move assignment operators.

C.64: A move operation should move and leave its source in a valid state

Reason

That is the generally assumed semantics. After y = std::move(x) the value of y should be the value x had and x should be in a valid state.

Example

```
class X {    // OK: value semantics
public:
    X();
    X(X&& a) noexcept;    // move X
    X& operator=(X&& a) noexcept;    // move-assign X
    void modify();    // change the value of X
    // ...
    ~X() { delete[] p; }
private:
    T* p;
    int sz;
};
```

Ideally, that moved-from should be the default value of the type. Ensure that unless there is an exceptionally good reason not to. However, not all types have a default value and for some types establishing the default value can be expensive. The standard requires only that the moved-from object can be destroyed. Often, we can easily and cheaply do better: The standard library assumes that it is possible to assign to a moved-from object. Always leave the moved-from object in some (necessarily specified) valid state.

Note

Unless there is an exceptionally strong reason not to, make x = std::move(y); y = z; work with the conventional semantics.

Enforcement

(Not enforceable) Look for assignments to members in the move operation. If there is a default constructor, compare those assignments to the initializations in the default constructor.

C.65: Make move assignment safe for self-assignment

Reason

If x = x changes the value of x, people will be surprised and bad errors can occur. However, people don't usually directly write a self-assignment that turn into a move, but it can occur. However, std::swap is implemented using move operations so if you accidentally do swap(a, b) where a and b refer to the same object, failing to handle self-move could be a serious and subtle error.

Example

```
class Foo {
    string s;
    int i;
public:
```

```
Foo& operator=(Foo&& a) noexcept;
// ...
};

Foo& Foo::operator=(Foo&& a) noexcept // OK, but there is a cost
{
   if (this == &a) return *this; // this line is redundant
   s = std::move(a.s);
   i = a.i;
   return *this;
}
```

The one-in-a-million argument against if (this == &a) return *this; tests from the discussion of self-assignment is even more relevant for self-move.

Note

There is no known general way of avoiding an if (this == &a) return *this; test for a move assignment and still get a correct answer (i.e., after x = x the value of x is unchanged).

Note

The ISO standard guarantees only a "valid but unspecified" state for the standard-library containers. Apparently this has not been a problem in about 10 years of experimental and production use. Please contact the editors if you find a counter example. The rule here is more caution and insists on complete safety.

Example

Here is a way to move a pointer without a test (imagine it as code in the implementation a move assignment):

```
// move from other.ptr to this->ptr
T* temp = other.ptr;
other.ptr = nullptr;
delete ptr; // in self-move, this->ptr is also null; delete is a no-op
ptr = temp; // in self-move, the original ptr is restored
```

Enforcement

- (Moderate) In the case of self-assignment, a move assignment operator should not leave the object holding pointer members that have been deleted or set to nullptr.
- (Not enforceable) Look at the use of standard-library container types (incl. string) and consider them safe for ordinary (not life-critical) uses.

C.66: Make move operations noexcept

Reason

A throwing move violates most people's reasonable assumptions. A non-throwing move will be used more efficiently by standard-library and language facilities.

Example

```
template<typename T>
class Vector {
public:
   Vector(Vector&& a) noexcept :elem{a.elem}, sz{a.sz} { a.elem = nullptr; a.sz = 0; }
   Vector& operator=(Vector&& a) noexcept {
        if (&a != this) {
           delete elem;
            elem = a.elem; a.elem = nullptr;
            sz = a.sz; a.sz = 0;
       }
       return *this;
    }
   // ...
private:
   T* elem;
   int sz;
};
```

These operations do not throw.

Example, bad

This Vector2 is not just inefficient, but since a vector copy requires allocation, it can throw.

Enforcement

(Simple) A move operation should be marked noexcept.

C.67: A polymorphic class should suppress public copy/move

Reason

A *polymorphic class* is a class that defines or inherits at least one virtual function. It is likely that it will be used as a base class for other derived classes with polymorphic behavior. If it is accidentally passed by value, with the implicitly generated copy constructor and assignment, we risk slicing: only the base portion of a derived object will be copied, and the polymorphic behavior will be corrupted.

If the class has no data, =delete the copy/move functions. Otherwise, make them protected.

Example, bad

```
class B { // BAD: polymorphic base class doesn't suppress copying
public:
    virtual char m() { return 'B'; }
    // ... nothing about copy operations, so uses default ...
};

class D : public B {
public:
    char m() override { return 'D'; }
    // ...
};

void f(B& b)
{
    auto b2 = b; // oops, slices the object; b2.m() will return 'B'
}

D d;
f(d);
```

Example

```
class B { // GOOD: polymorphic class suppresses copying
public:
    B() = default;
    B(const B&) = delete;
    B& operator=(const B&) = delete;
    virtual char m() { return 'B'; }
    // ...
};
```

```
class D : public B {
public:
    char m() override { return 'D'; }
    // ...
};

void f(B& b)
{
    auto b2 = b; // ok, compiler will detect inadvertent copying, and protest
}

D d;
f(d);
```

Note

If you need to create deep copies of polymorphic objects, use clone() functions: see C.130.

Exception

Classes that represent exception objects need both to be polymorphic and copy-constructible.

Enforcement

- Flag a polymorphic class with a public copy operation.
- Flag an assignment of polymorphic class objects.

C.other: Other default operation rules

In addition to the operations for which the language offers default implementations, there are a few operations that are so foundational that specific rules for their definition are needed: comparisons, swap, and hash.

C.80: Use **=default** if you have to be explicit about using the default semantics

Reason

The compiler is more likely to get the default semantics right and you cannot implement these functions better than the compiler.

Example

```
class Tracer {
    string message;
public:
    Tracer(const string& m) : message{m} { cerr << "entering " << message << '\n'; }
    ~Tracer() { cerr << "exiting " << message << '\n'; }

Tracer(const Tracer&) = default;
    Tracer& operator=(const Tracer&) = default;
    Tracer(Tracer&&) noexcept = default;
    Tracer& operator=(Tracer&&) noexcept = default;
};</pre>
```

Because we defined the destructor, we must define the copy and move operations. The = default is the best and simplest way of doing that.

Example, bad

```
class Tracer2 {
    string message;
public:
    Tracer2(const string& m) : message{m} { cerr << "entering " << message << '\n'; }
    ~Tracer2() { cerr << "exiting " << message << '\n'; }

Tracer2(const Tracer2& a) : message{a.message} {}
    Tracer2& operator=(const Tracer2& a) { message = a.message; return *this; }
    Tracer2(Tracer2&& a) noexcept :message{a.message} {}
    Tracer2& operator=(Tracer2&& a) noexcept { message = a.message; return *this; }
};</pre>
```

Writing out the bodies of the copy and move operations is verbose, tedious, and error-prone. A compiler does it better.

Enforcement

(Moderate) The body of a special operation should not have the same accessibility and semantics as the compiler-generated version, because that would be redundant

C.81: Use =delete when you want to disable default behavior (without wanting an alternative)

Reason

In a few cases, a default operation is not desirable.

Example

```
class Immortal {
public:
    ~Immortal() = delete; // do not allow destruction
    // ...
};

void use()
{
    Immortal ugh; // error: ugh cannot be destroyed
    Immortal* p = new Immortal{};
    delete p; // error: cannot destroy *p
}
```

Example

A unique_ptr can be moved, but not copied. To achieve that its copy operations are deleted. To avoid copying it is necessary to =delete its copy operations from lvalues:

```
template<class T, class D = default_delete<T>> class unique_ptr {
public:
   // ...
   constexpr unique_ptr() noexcept;
    explicit unique_ptr(pointer p) noexcept;
   // ...
   unique_ptr(unique_ptr&& u) noexcept; // move constructor
   // ...
   unique_ptr(const unique_ptr&) = delete; // disable copy from lvalue
   // ...
};
unique_ptr<int> make(); // make "something" and return it by moving
void f()
    unique_ptr<int> pi {};
    auto pi2 {pi};  // error: no move constructor from lvalue
    auto pi3 {make()}; // OK, move: the result of make() is an rvalue
}
```

Note that deleted functions should be public.

Enforcement

The elimination of a default operation is (should be) based on the desired semantics of the class. Consider such classes suspect, but maintain a "positive list" of classes where a human has asserted that the semantics is correct.

C.82: Don't call virtual functions in constructors and destructors

Reason

The function called will be that of the object constructed so far, rather than a possibly overriding function in a derived class. This can be most confusing. Worse, a direct or indirect call to an unimplemented pure virtual function from a constructor or destructor results in undefined behavior.

Example, bad

```
class Base {
public:
   virtual void f() = 0; // not implemented
   virtual void g();
                           // implemented with Base version
   virtual void h();
                          // implemented with Base version
   virtual ~Base();
                           // implemented with Base version
};
class Derived : public Base {
public:
   void g() override; // provide Derived implementation
   void h() final;
                      // provide Derived implementation
   Derived()
       // BAD: attempt to call an unimplemented virtual function
       f();
       // BAD: will call Derived::g, not dispatch further virtually
       g();
       // GOOD: explicitly state intent to call only the visible version
       Derived::g();
       // ok, no qualification needed, h is final
       h();
   }
};
```

Note that calling a specific explicitly qualified function is not a virtual call even if the function is virtual.

See also factory functions for how to achieve the effect of a call to a derived class function without risking undefined behavior.

Note

There is nothing inherently wrong with calling virtual functions from constructors and destructors. The semantics of such calls is type safe. However, experience shows that such calls are rarely needed, easily confuse maintainers, and become a source of errors when used by novices.

Enforcement

Flag calls of virtual functions from constructors and destructors.

C.83: For value-like types, consider providing a noexcept swap function

Reason

A swap can be handy for implementing a number of idioms, from smoothly moving objects around to implementing assignment easily to providing a guaranteed commit function that enables strongly error-safe calling code. Consider using swap to implement copy assignment in terms of copy construction. See also destructors, deallocation, and swap must never fail.

Example, good

```
class Foo {
  public:
    void swap(Foo& rhs) noexcept
    {
        m1.swap(rhs.m1);
        std::swap(m2, rhs.m2);
    }
  private:
    Bar m1;
    int m2;
};
```

Providing a non-member swap function in the same namespace as your type for callers' convenience.

```
void swap(Foo& a, Foo& b)
{
    a.swap(b);
}
```

Enforcement

- Non-trivially copyable types should provide a member swap or a free swap overload.
- (Simple) When a class has a swap member function, it should be declared noexcept.

C.84: A swap function must not fail

Reason

swap is widely used in ways that are assumed never to fail and programs cannot easily be written to work correctly in the presence of a failing swap. The standard-library containers and algorithms will not work correctly if a swap of an element type fails.

Example, bad

```
void swap(My_vector& x, My_vector& y)
{
   auto tmp = x; // copy elements
   x = y;
   y = tmp;
}
```

This is not just slow, but if a memory allocation occurs for the elements in tmp, this swap could throw and would make STL algorithms fail if used with them.

Enforcement

(Simple) When a class has a swap member function, it should be declared noexcept.

C.85: Make swap noexcept

Reason

A swap must not fail. If a swap tries to exit with an exception, it's a bad design error and the program had better terminate.

Enforcement

(Simple) When a class has a swap member function, it should be declared noexcept.

C.86: Make == symmetric with respect to operand types and noexcept

Reason

Asymmetric treatment of operands is surprising and a source of errors where conversions are possible. == is a fundamental operation and programmers should be able to use it without fear of failure.

Example

```
struct X {
    string name;
    int number;
};

bool operator==(const X& a, const X& b) noexcept {
    return a.name == b.name && a.number == b.number;
}
```

Example, bad

```
class B {
    string name;
    int number;
    bool operator==(const B& a) const {
        return name == a.name && number == a.number;
    }
    // ...
};
```

B's comparison accepts conversions for its second operand, but not its first.

Note

If a class has a failure state, like double's NaN, there is a temptation to make a comparison against the failure state throw. The alternative is to make two failure states compare equal and any valid state compare false against the failure state.

Note

This rule applies to all the usual comparison operators: !=, <, <=, >, and >=.

Enforcement

- Flag an operator==() for which the argument types differ; same for other comparison operators: !=, <, <=, >, and >=.
- Flag member operator==()s; same for other comparison operators: !=, <, <=, >, and >=.

C.87: Beware of == on base classes

Reason

It is really hard to write a foolproof and useful == for a hierarchy.

Example, bad

```
class B {
    string name;
    int number;
public:
    virtual bool operator==(const B& a) const
    {
        return name == a.name && number == a.number;
    }
    // ...
};
```

B's comparison accepts conversions for its second operand, but not its first.

```
class D : public B {
   char character;
public:
   virtual bool operator==(const D& a) const
        return B::operator==(a) && character == a.character;
    }
   // ...
};
B b = \dots
D d = \dots
b == d;
          // compares name and number, ignores d's character
d == b; // compares name and number, ignores d's character
D d2;
d == d2; // compares name, number, and character
B& b2 = d2;
b2 == d; // compares name and number, ignores d2's and d's character
```

Of course there are ways of making == work in a hierarchy, but the naive approaches do not scale

Note

This rule applies to all the usual comparison operators: !=, <, <=, >=, and <=>.

Enforcement

■ Flag a virtual operator==(); same for other comparison operators: !=, <, <=, >, >=, and <=>.

C.89: Make a hash noexcept

Reason

Users of hashed containers use hash indirectly and don't expect simple access to throw. It's a standard-library requirement.

Example, bad

```
template<>
struct hash<My_type> { // thoroughly bad hash specialization
    using result_type = size_t;
    using argument_type = My_type;
    size_t operator()(const My_type & x) const
        size t xs = x.s.size();
        if (xs < 4) throw Bad_My_type{};</pre>
                                            // "Nobody expects the Spanish inquisition!"
        return hash<size_t>()(x.s.size()) ^ trim(x.s);
    }
};
int main()
    unordered_map<My_type, int> m;
    My_type mt{ "asdfg" };
    m[mt] = 7;
    cout << m[My_type{ "asdfg" }] << '\n';</pre>
}
```

If you have to define a hash specialization, try simply to let it combine standard-library hash specializations with ^ (xor). That tends to work better than "cleverness" for non-specialists.

Enforcement

Flag throwing hashes.

C.90: Rely on constructors and assignment operators, not memset and memcpy

Reason

The standard C++ mechanism to construct an instance of a type is to call its constructor. As specified in guideline C.41: a constructor should create a fully initialized object. No additional initialization, such as by memcpy, should be required. A type will provide a copy constructor and/or copy assignment operator to appropriately make a copy of the class, preserving the type's invariants. Using memcpy to copy a non-trivially copyable type has undefined behavior. Frequently this results in slicing, or data corruption.

Example, good

```
struct base {
    virtual void update() = 0;
    std::shared_ptr<int> sp;
};

struct derived : public base {
    void update() override {}
};
```

Example, bad

```
void init(derived& a)
{
    memset(&a, 0, sizeof(derived));
}
```

This is type-unsafe and overwrites the vtable.

Example, bad

```
void copy(derived& a, derived& b)
{
    memcpy(&a, &b, sizeof(derived));
}
```

This is also type-unsafe and overwrites the vtable.

Enforcement

• Flag passing a non-trivially-copyable type to memset or memcpy.

C.con: Containers and other resource handles

A container is an object holding a sequence of objects of some type; std::vector is the archetypical container. A resource handle is a class that owns a resource; std::vector is the typical resource handle; its resource is its sequence of elements.

Summary of container rules:

- C.100: Follow the STL when defining a container
- C.101: Give a container value semantics
- C.102: Give a container move operations
- C.103: Give a container an initializer list constructor
- C.104: Give a container a default constructor that sets it to empty
- **???**

C.109: If a resource handle has pointer semantics, provide * and ->

See also: Resources

C.100: Follow the STL when defining a container

Reason

The STL containers are familiar to most C++ programmers and a fundamentally sound design.

Note

There are of course other fundamentally sound design styles and sometimes reasons to depart from the style of the standard library, but in the absence of a solid reason to differ, it is simpler and easier for both implementers and users to follow the standard.

In particular, std::vector and std::map provide useful relatively simple models.

Example

```
// simplified (e.g., no allocators):
template<typename T>
class Sorted_vector {
   using value_type = T;
   // ... iterator types ...
   Sorted vector() = default;
   Sorted vector(initializer list<T>); // initializer-list constructor: sort and store
   Sorted_vector(const Sorted_vector&) = default;
   Sorted_vector(Sorted_vector&&) noexcept = default;
   Sorted_vector& operator=(const Sorted_vector&) = default;
                                                                // copy assignment
   Sorted_vector& operator=(Sorted_vector&&) noexcept = default; // move assignment
   ~Sorted_vector() = default;
   Sorted_vector(const std::vector<T>& v); // store and sort
   Sorted_vector(std::vector<T>&& v);
                                            // sort and "steal representation"
    const T& operator[](int i) const { return rep[i]; }
   // no non-const direct access to preserve order
   void push_back(const T&); // insert in the right place (not necessarily at back)
   void push_back(T&&);  // insert in the right place (not necessarily at back)
   // ... cbegin(), cend() ...
    std::vector<T> rep; // use a std::vector to hold elements
};
```

```
template<typename T> bool operator==(const Sorted_vector<T>&, const Sorted_vector<T>&);
template<typename T> bool operator!=(const Sorted_vector<T>&, const Sorted_vector<T>&);
// ...
```

Here, the STL style is followed, but incompletely. That's not uncommon. Provide only as much functionality as makes sense for a specific container. The key is to define the conventional constructors, assignments, destructors, and iterators (as meaningful for the specific container) with their conventional semantics. From that base, the container can be expanded as needed. Here, special constructors from std::vector were added.

Enforcement

???

C.101: Give a container value semantics

Reason

Regular objects are simpler to think and reason about than irregular ones. Familiarity.

Note

If meaningful, make a container Regular (the concept). In particular, ensure that an object compares equal to its copy.

Example

```
void f(const Sorted_vector<string>& v)
{
    Sorted_vector<string> v2 {v};
    if (v != v2)
        cout << "Behavior against reason and logic.\n";
    // ...
}</pre>
```

Enforcement

???

C.102: Give a container move operations

Reason

Containers tend to get large; without a move constructor and a copy constructor an object can be expensive to move around, thus tempting people to pass pointers to it around and getting into resource management problems.

Example

A user can reasonably assume that returning a standard-like container is cheap.

Enforcement

???

C.103: Give a container an initializer list constructor

Reason

People expect to be able to initialize a container with a set of values. Familiarity.

Example

```
Sorted_vector<int> sv {1, 3, -1, 7, 0, 0}; // Sorted_vector sorts elements as needed
```

Enforcement

???

C.104: Give a container a default constructor that sets it to empty

Reason

To make it Regular.

Example

vector<Sorted_sequence<string>> vs(100); // 100 Sorted_sequences each with the value ""

Enforcement

???

C.109: If a resource handle has pointer semantics, provide * and ->

Reason

That's what is expected from pointers. Familiarity.

Example

???

Enforcement

???

C.lambdas: Function objects and lambdas

A function object is an object supplying an overloaded () so that you can call it. A lambda expression (colloquially often shortened to "a lambda") is a notation for generating a function object. Function objects should be cheap to copy (and therefore passed by value).

Summary:

- F.10: If an operation can be reused, give it a name
- F.11: Use an unnamed lambda if you need a simple function object in one place only
- F.50: Use a lambda when a function won't do (to capture local variables, or to write a local function)
- F.52: Prefer capturing by reference in lambdas that will be used locally, including passed to algorithms
- F.53: Avoid capturing by reference in lambdas that will be used non-locally, including returned, stored on the heap, or passed to another thread
- ES.28: Use lambdas for complex initialization, especially of const variables

C.hier: Class hierarchies (OOP)

A class hierarchy is constructed to represent a set of hierarchically organized concepts (only). Typically base classes act as interfaces. There are two major uses for hierarchies, often named implementation inheritance and interface inheritance.

Class hierarchy rule summary:

- C.120: Use class hierarchies to represent concepts with inherent hierarchical structure (only)
- C.121: If a base class is used as an interface, make it a pure abstract class
- C.122: Use abstract classes as interfaces when complete separation of interface and implementation is needed

Designing rules for classes in a hierarchy summary:

- C.126: An abstract class typically doesn't need a user-written constructor
- C.127: A class with a virtual function should have a virtual or protected destructor
- C.128: Virtual functions should specify exactly one of virtual, override, or final
- C.129: When designing a class hierarchy, distinguish between implementation inheritance and interface inheritance
- C.130: For making deep copies of polymorphic classes prefer a virtual clone function instead of public copy construction/assignment
- C.131: Avoid trivial getters and setters
- C.132: Don't make a function virtual without reason
- C.133: Avoid protected data
- C.134: Ensure all non-const data members have the same access level
- C.135: Use multiple inheritance to represent multiple distinct interfaces
- C.136: Use multiple inheritance to represent the union of implementation attributes
- C.137: Use virtual bases to avoid overly general base classes
- C.138: Create an overload set for a derived class and its bases with using
- C.139: Use final on classes sparingly
- C.140: Do not provide different default arguments for a virtual function and an overrider

Accessing objects in a hierarchy rule summary:

- C.145: Access polymorphic objects through pointers and references
- C.146: Use dynamic_cast where class hierarchy navigation is unavoidable
- C.147: Use dynamic_cast to a reference type when failure to find the required class is considered an error
- C.148: Use dynamic_cast to a pointer type when failure to find the required class is considered a valid alternative
- C.149: Use unique_ptr or shared_ptr to avoid forgetting to delete objects created using new
- C.150: Use make_unique() to construct objects owned by unique_ptrs
- C.151: Use make_shared() to construct objects owned by shared_ptrs
- C.152: Never assign a pointer to an array of derived class objects to a pointer to its base
- C.153: Prefer virtual function to casting

C.120: Use class hierarchies to represent concepts with inherent hierarchical structure (only)

Reason

Direct representation of ideas in code eases comprehension and maintenance. Make sure the idea represented in the base class exactly matches all derived types and there is not a better way to express it than using the tight coupling of inheritance.

Do *not* use inheritance when simply having a data member will do. Usually this means that the derived type needs to override a base virtual function or needs access to a protected member.

Example

```
class DrawableUIElement {
public:
   virtual void render() const = 0;
   // ...
};
class AbstractButton : public DrawableUIElement {
   virtual void onClick() = 0;
   // ...
};
class PushButton : public AbstractButton {
   void render() const override;
   void onClick() override;
   // ...
};
class Checkbox : public AbstractButton {
// ...
};
```

Example, bad

Do *not* represent non-hierarchical domain concepts as class hierarchies.

```
template<typename T>
class Container {
public:
    // list operations:
    virtual T& get() = 0;
    virtual void put(T&) = 0;
    virtual void insert(Position) = 0;
    // ...
    // vector operations:
    virtual T& operator[](int) = 0;
```

```
virtual void sort() = 0;
// ...
// tree operations:
virtual void balance() = 0;
// ...
};
```

Here most overriding classes cannot implement most of the functions required in the interface well. Thus the base class becomes an implementation burden. Furthermore, the user of Container cannot rely on the member functions actually performing meaningful operations reasonably efficiently; it might throw an exception instead. Thus users have to resort to run-time checking and/or not using this (over)general interface in favor of a particular interface found by a run-time type inquiry (e.g., a dynamic_cast).

Enforcement

- Look for classes with lots of members that do nothing but throw.
- Flag every use of a non-public base class B where the derived class D does not override a virtual function or access a protected member in B, and B is not one of the following: empty, a template parameter or parameter pack of D, a class template specialized with D.

C.121: If a base class is used as an interface, make it a pure abstract class

Reason

A class is more stable (less brittle) if it does not contain data. Interfaces should normally be composed entirely of public pure virtual functions and a default/empty virtual destructor.

Example

```
class My_interface {
public:
    // ...only pure virtual functions here ...
    virtual ~My_interface() {} // or =default
};
```

Example, bad

```
class Goof {
public:
    // ...only pure virtual functions here ...
    // no virtual destructor
};

class Derived : public Goof {
    string s;
    // ...
};
```

```
void use()
{
    unique_ptr<Goof> p {new Derived{"here we go"}};
    f(p.get()); // use Derived through the Goof interface
    g(p.get()); // use Derived through the Goof interface
} // leak
```

The Derived is deleted through its Goof interface, so its string is leaked. Give Goof a virtual destructor and all is well.

Enforcement

 Warn on any class that contains data members and also has an overridable (non-final) virtual function that wasn't inherited from a base class.

C.122: Use abstract classes as interfaces when complete separation of interface and implementation is needed

Reason

Such as on an ABI (link) boundary.

Example

```
struct Device {
    virtual ~Device() = default;
    virtual void write(span<const char> outbuf) = 0;
    virtual void read(span<char> inbuf) = 0;
};

class D1 : public Device {
    // ... data ...

    void write(span<const char> outbuf) override;
    void read(span<char> inbuf) override;
};

class D2 : public Device {
    // ... different data ...

    void write(span<const char> outbuf) override;
    void read(span<const char> outbuf) override;
    void read(span<const char> inbuf) override;
    void read(span<const char> inbuf) override;
};
```

A user can now use D1s and D2s interchangeably through the interface provided by Device. Furthermore, we can update D1 and D2 in ways that are not binary compatible with older versions as long as all access goes through Device.

Enforcement

```
???
```

C.hierclass: Designing classes in a hierarchy:

C.126: An abstract class typically doesn't need a user-written constructor

Reason

An abstract class typically does not have any data for a constructor to initialize.

Example

Exception

- A base class constructor that does work, such as registering an object somewhere, might need a constructor.
- In extremely rare cases, you might find it reasonable for an abstract class to have a bit of data shared by all derived classes (e.g., use statistics data, debug information, etc.); such classes tend to have constructors. But be warned: Such classes also tend to be prone to requiring virtual inheritance.

Enforcement

Flag abstract classes with constructors.

C.127: A class with a virtual function should have a virtual or protected destructor

Reason

A class with a virtual function is usually (and in general) used via a pointer to base. Usually, the last user has to call delete on a pointer to base, often via a smart pointer to base, so the destructor should be public and virtual. Less commonly, if deletion through a pointer to base is not intended to be supported, the destructor should be protected and non-virtual; see C.35.

Example, bad

```
struct B {
    virtual int f() = 0;
    // ... no user-written destructor, defaults to public non-virtual ...
};

// bad: derived from a class without a virtual destructor
struct D : B {
    string s {"default"};
    // ...
};

void use()
{
    unique_ptr<B> p = make_unique<D>();
    // ...
} // undefined behavior, might call B::~B only and leak the string
```

Note

There are people who don't follow this rule because they plan to use a class only through a shared_ptr: std::shared_ptr p = std::make_shared<D>(args); Here, the shared pointer will take care of deletion, so no leak will occur from an inappropriate delete of the base. People who do this consistently can get a false positive, but the rule is important -- what if one was allocated using make_unique? It's not safe unless the author of B ensures that it can never be misused, such as by making all constructors private and providing a factory function to enforce the allocation with make_shared.

Enforcement

- A class with any virtual functions should have a destructor that is either public and virtual or else protected and non-virtual.
- Flag delete of a class with a virtual function but no virtual destructor.

C.128: Virtual functions should specify exactly one of virtual, override, or final

Reason

Readability. Detection of mistakes. Writing explicit virtual, override, or final is self-documenting and enables the compiler to catch mismatch of types and/or names between base and derived classes. However, writing more than one of these three is both redundant and a potential source of errors.

It's simple and clear:

- virtual means exactly and only "this is a new virtual function."
- override means exactly and only "this is a non-final overrider."
- final means exactly and only "this is a final overrider."

Example, bad

Example, good

Discussion

We want to eliminate two particular classes of errors:

- **implicit virtual**: the programmer intended the function to be implicitly virtual and it is (but readers of the code can't tell); or the programmer intended the function to be implicitly virtual but it isn't (e.g., because of a subtle parameter list mismatch); or the programmer did not intend the function to be virtual but it is (because it happens to have the same signature as a virtual in the base class)
- implicit override: the programmer intended the function to be implicitly an overrider and it is (but readers of

the code can't tell); or the programmer intended the function to be implicitly an overrider but it isn't (e.g., because of a subtle parameter list mismatch); or the programmer did not intend the function to be an overrider but it is (because it happens to have the same signature as a virtual in the base class -- note this problem arises whether or not the function is explicitly declared virtual, because the programmer might have intended to create either a new virtual function or a new non-virtual function)

Note: On a class defined as final, it doesn't matter whether you put override or final on an individual virtual function.

Note: Use final on functions sparingly. It does not necessarily lead to optimization, and it precludes further overriding.

Enforcement

- Compare virtual function names in base and derived classes and flag uses of the same name that does not override.
- Flag overrides with neither override nor final.
- Flag function declarations that use more than one of virtual, override, and final.

C.129: When designing a class hierarchy, distinguish between implementation inheritance and interface inheritance

Reason

Implementation details in an interface make the interface brittle; that is, make its users vulnerable to having to recompile after changes in the implementation. Data in a base class increases the complexity of implementing the base and can lead to replication of code.

Note

Definition:

- interface inheritance is the use of inheritance to separate users from implementations, in particular to allow derived classes to be added and changed without affecting the users of base classes.
- implementation inheritance is the use of inheritance to simplify implementation of new facilities by making useful operations available for implementers of related new operations (sometimes called "programming by difference").

A pure interface class is simply a set of pure virtual functions; see I.25.

In early OOP (e.g., in the 1980s and 1990s), implementation inheritance and interface inheritance were often mixed and bad habits die hard. Even now, mixtures are not uncommon in old code bases and in old-style teaching material.

The importance of keeping the two kinds of inheritance increases

- with the size of a hierarchy (e.g., dozens of derived classes),
- with the length of time the hierarchy is used (e.g., decades), and
- with the number of distinct organizations in which a hierarchy is used (e.g., it can be difficult to distribute an

Example, bad

```
class Shape {    // BAD, mixed interface and implementation
public:
    Shape();
    Shape(Point ce = \{0, 0\}, Color co = none): cent\{ce\}, col \{co\} \{\ /^* \dots ^*/\}
    Point center() const { return cent; }
    Color color() const { return col; }
    virtual void rotate(int) = 0;
    virtual void move(Point p) { cent = p; redraw(); }
    virtual void redraw();
    // ...
private:
    Point cent;
    Color col;
};
class Circle : public Shape {
public:
    Circle(Point c, int r) : Shape\{c\}, rad\{r\} \{ /* ... */ \}
    // ...
private:
    int rad;
};
class Triangle : public Shape {
public:
    Triangle(Point p1, Point p2, Point p3); // calculate center
    // ...
};
```

Problems:

- As the hierarchy grows and more data is added to Shape, the constructors get harder to write and maintain.
- Why calculate the center for the Triangle? we might never use it.
- Add a data member to Shape (e.g., drawing style or canvas) and all classes derived from Shape and all code using Shape will need to be reviewed, possibly changed, and probably recompiled.

The implementation of Shape::move() is an example of implementation inheritance: we have defined move() once and for all, for all derived classes. The more code there is in such base class member function implementations and the more data is shared by placing it in the base, the more benefits we gain - and the less stable the hierarchy is.

Example

This Shape hierarchy can be rewritten using interface inheritance:

```
class Shape { // pure interface
public:
    virtual Point center() const = 0;
    virtual Color color() const = 0;

    virtual void rotate(int) = 0;
    virtual void move(Point p) = 0;

    virtual void redraw() = 0;

// ...
};
```

Note that a pure interface rarely has constructors: there is nothing to construct.

```
class Circle : public Shape {
public:
    Circle(Point c, int r, Color c) : cent{c}, rad{r}, col{c} { /* ... */ }

    Point center() const override { return cent; }
    Color color() const override { return col; }

    // ...
private:
    Point cent;
    int rad;
    Color col;
};
```

The interface is now less brittle, but there is more work in implementing the member functions. For example, center has to be implemented by every class derived from Shape.

Example, dual hierarchy

How can we gain the benefit of stable hierarchies from interface hierarchies and the benefit of implementation reuse from implementation inheritance? One popular technique is dual hierarchies. There are many ways of implementing the idea of dual hierarchies; here, we use a multiple-inheritance variant.

First we devise a hierarchy of interface classes:

```
class Shape { // pure interface
public:
    virtual Point center() const = 0;
    virtual Color color() const = 0;

    virtual void rotate(int) = 0;
    virtual void move(Point p) = 0;
```

```
virtual void redraw() = 0;

// ...
};

class Circle : public virtual Shape { // pure interface
public:
    virtual int radius() = 0;
    // ...
};
```

To make this interface useful, we must provide its implementation classes (here, named equivalently, but in the Impl namespace):

```
class Impl::Shape : public virtual ::Shape { // implementation
public:
    // constructors, destructor
    // ...
    Point center() const override { /* ... */ }
    Color color() const override { /* ... */ }

    void rotate(int) override { /* ... */ }

    void move(Point p) override { /* ... */ }

    void redraw() override { /* ... */ }

// ...
};
```

Now Shape is a poor example of a class with an implementation, but bear with us because this is just a simple example of a technique aimed at more complex hierarchies.

And we could extend the hierarchies by adding a Smiley class (:-)):

There are now two hierarchies:

- interface: Smiley -> Circle -> Shape
- implementation: Impl::Smiley -> Impl::Circle -> Impl::Shape

Since each implementation is derived from its interface as well as its implementation base class we get a lattice (DAG):

As mentioned, this is just one way to construct a dual hierarchy.

The implementation hierarchy can be used directly, rather than through the abstract interface.

This can be useful when the implementation class has members that are not offered in the abstract interface or if direct use of a member offers optimization opportunities (e.g., if an implementation member function is final)

Note

Another (related) technique for separating interface and implementation is Pimpl.

Note

There is often a choice between offering common functionality as (implemented) base class functions and freestanding functions (in an implementation namespace). Base classes give a shorter notation and easier access to shared data (in the base) at the cost of the functionality being available only to users of the hierarchy.

Enforcement

- Flag a derived to base conversion to a base with both data and virtual functions (except for calls from a derived class member to a base class member)
- **???**

C.130: For making deep copies of polymorphic classes prefer a virtual clone function instead of public copy construction/assignment

Reason

Copying a polymorphic class is discouraged due to the slicing problem, see C.67. If you really need copy semantics, copy deeply: Provide a virtual clone function that will copy the actual most-derived type and return an owning pointer to the new object, and then in derived classes return the derived type (use a covariant return type).

Example

```
class B {
public:
    B() = default;
    virtual ~B() = default;
    virtual gsl::owner<B*> clone() const = 0;
protected:
     B(const B&) = default;
     B& operator=(const B&) = default;
     B(B&&) noexcept = default;
     B& operator=(B&&) noexcept = default;
    // ...
};
class D : public B {
public:
    gsl::owner<D*> clone() const override
        return new D{*this};
    };
};
```

Generally, it is recommended to use smart pointers to represent ownership (see R.20). However, because of language rules, the covariant return type cannot be a smart pointer: D::clone can't return a unique_ptr<D> while B::clone returns unique_ptr. Therefore, you either need to consistently return unique_ptr in all overrides, or use owner<> utility from the Guidelines Support Library.

C.131: Avoid trivial getters and setters

Reason

A trivial getter or setter adds no semantic value; the data item could just as well be public.

Example

```
class Point {    // Bad: verbose
    int x;
    int y;
public:
    Point(int xx, int yy) : x{xx}, y{yy} { }
    int get_x() const { return x; }
    void set_x(int xx) { x = xx; }
    int get_y() const { return y; }
    void set_y(int yy) { y = yy; }
    // no behavioral member functions
};
```

Consider making such a class a struct -- that is, a behaviorless bunch of variables, all public data and no member functions.

```
struct Point {
   int x {0};
   int y {0};
};
```

Note that we can put default initializers on member variables: C.49: Prefer initialization to assignment in constructors.

Note

The key to this rule is whether the semantics of the getter/setter are trivial. While it is not a complete definition of "trivial", consider whether there would be any difference beyond syntax if the getter/setter was a public data member instead. Examples of non-trivial semantics would be: maintaining a class invariant or converting between an internal type and an interface type.

Enforcement

Flag multiple get and set member functions that simply access a member without additional semantics.

C.132: Don't make a function virtual without reason

Reason

Redundant virtual increases run-time and object-code size. A virtual function can be overridden and is thus open to mistakes in a derived class. A virtual function ensures code replication in a templated hierarchy.

Example, bad

```
template<class T>
class Vector {
public:
    // ...
    virtual int size() const { return sz; } // bad: what good could a derived class do?
private:
    T* elem; // the elements
    int sz; // number of elements
};
```

This kind of "vector" isn't meant to be used as a base class at all.

Enforcement

- Flag a class with virtual functions but no derived classes.
- Flag a class where all member functions are virtual and have implementations.

C.133: Avoid protected data

Reason

protected data is a source of complexity and errors. protected data complicates the statement of invariants. protected data inherently violates the guidance against putting data in base classes, which usually leads to having to deal with virtual inheritance as well.

Example, bad

```
class Shape {
public:
    // ... interface functions ...
protected:
    // data for use in derived classes:
    Color fill_color;
    Color edge_color;
    Style st;
};
```

Now it is up to every derived Shape to manipulate the protected data correctly. This has been popular, but also a major source of maintenance problems. In a large class hierarchy, the consistent use of protected data is hard to maintain because there can be a lot of code, spread over a lot of classes. The set of classes that can touch that data is open: anyone can derive a new class and start manipulating the protected data. Often, it is not possible to examine the complete set of classes, so any change to the representation of the class becomes infeasible. There is no enforced invariant for the protected data; it is much like a set of global variables. The protected data has de facto become global to a large body of code.

Note

Protected data often looks tempting to enable arbitrary improvements through derivation. Often, what you get is unprincipled changes and errors. Prefer private data with a well-specified and enforced invariant. Alternative, and often better, keep data out of any class used as an interface.

Note

Protected member function can be just fine.

Enforcement

Flag classes with protected data.

C.134: Ensure all non-const data members have the same access level

Reason

Prevention of logical confusion leading to errors. If the non-const data members don't have the same access level, the type is confused about what it's trying to do. Is it a type that maintains an invariant or simply a collection of values?

Discussion

The core question is: What code is responsible for maintaining a meaningful/correct value for that variable?

There are exactly two kinds of data members:

- A: Ones that don't participate in the object's invariant. Any combination of values for these members is valid.
- B: Ones that do participate in the object's invariant. Not every combination of values is meaningful (else there'd
 be no invariant). Therefore all code that has write access to these variables must know about the invariant,

know the semantics, and know (and actively implement and enforce) the rules for keeping the values correct.

Data members in category A should just be public (or, more rarely, protected if you only want derived classes to see them). They don't need encapsulation. All code in the system might as well see and manipulate them.

Data members in category B should be private or const. This is because encapsulation is important. To make them non-private and non-const would mean that the object can't control its own state: An unbounded amount of code beyond the class would need to know about the invariant and participate in maintaining it accurately -- if these data members were public, that would be all calling code that uses the object; if they were protected, it would be all the code in current and future derived classes. This leads to brittle and tightly coupled code that quickly becomes a nightmare to maintain. Any code that inadvertently sets the data members to an invalid or unexpected combination of values would corrupt the object and all subsequent uses of the object.

Most classes are either all A or all B:

- *All public*: If you're writing an aggregate bundle-of-variables without an invariant across those variables, then all the variables should be public. By convention, declare such classes struct rather than class
- *All private*: If you're writing a type that maintains an invariant, then all the non-const variables should be private -- it should be encapsulated.

Exception

Occasionally classes will mix A and B, usually for debug reasons. An encapsulated object might contain something like non-const debug instrumentation that isn't part of the invariant and so falls into category A — it isn't really part of the object's value or meaningful observable state either. In that case, the A parts should be treated as A's (made public, or in rarer cases protected if they should be visible only to derived classes) and the B parts should still be treated like B's (private or const).

Enforcement

Flag any class that has non-const data members with different access levels.

C.135: Use multiple inheritance to represent multiple distinct interfaces

Reason

Not all classes will necessarily support all interfaces, and not all callers will necessarily want to deal with all operations. Especially to break apart monolithic interfaces into "aspects" of behavior supported by a given derived class.

Example

```
class iostream : public istream, public ostream { // very simplified
    // ...
};
```

istream provides the interface to input operations; ostream provides the interface to output operations. iostream provides the union of the istream and ostream interfaces and the synchronization needed to allow both on a single stream.

Note

This is a very common use of inheritance because the need for multiple different interfaces to an implementation is common and such interfaces are often not easily or naturally organized into a single-rooted hierarchy.

Note

Such interfaces are typically abstract classes.

Enforcement

???

C.136: Use multiple inheritance to represent the union of implementation attributes

Reason

Some forms of mixins have state and often operations on that state. If the operations are virtual the use of inheritance is necessary, if not using inheritance can avoid boilerplate and forwarding.

Example

```
class iostream : public istream, public ostream {    // very simplified
    // ...
};
```

istream provides the interface to input operations (and some data); ostream provides the interface to output operations (and some data). iostream provides the union of the istream and ostream interfaces and the synchronization needed to allow both on a single stream.

Note

This a relatively rare use because implementation can often be organized into a single-rooted hierarchy.

Example

Sometimes, an "implementation attribute" is more like a "mixin" that determine the behavior of an implementation and inject members to enable the implementation of the policies it requires. For example, see std::enable_shared_from_this or various bases from boost.intrusive (e.g. list_base_hook or intrusive_ref_counter).

C.137: Use virtual bases to avoid overly general base classes

Reason

Allow separation of shared data and interface. To avoid all shared data to being put into an ultimate base class.

Example

```
struct Interface {
   virtual void f();
   virtual int g();
   // ... no data here ...
};
class Utility { // with data
   void utility1();
   virtual void utility2(); // customization point
public:
   int x;
    int y;
};
class Derive1 : public Interface, virtual protected Utility {
   // override Interface functions
    // Maybe override Utility virtual functions
   // ...
};
class Derive2 : public Interface, virtual protected Utility {
   // override Interface functions
   // Maybe override Utility virtual functions
   // ...
};
```

Factoring out Utility makes sense if many derived classes share significant "implementation details."

Note

Obviously, the example is too "theoretical", but it is hard to find a *small* realistic example. Interface is the root of an interface hierarchy and Utility is the root of an implementation hierarchy. Here is a slightly more realistic example with an explanation.

Note

Often, linearization of a hierarchy is a better solution.

Enforcement

Flag mixed interface and implementation hierarchies.

C.138: Create an overload set for a derived class and its bases with using

Reason

Without a using declaration, member functions in the derived class hide the entire inherited overload sets.

Example, bad

```
#include <iostream>
class B {
public:
    virtual int f(int i) { std::cout << "f(int): "; return i; }</pre>
    virtual double f(double d) { std::cout << "f(double): "; return d; }</pre>
    virtual ~B() = default;
};
class D: public B {
public:
    int f(int i) override { std::cout << "f(int): "; return i + 1; }</pre>
};
int main()
{
    D d;
    std::cout << d.f(2) << '\n'; // prints "f(int): 3"
    std::cout << d.f(2.3) << '\n'; // prints "f(int): 3"
}
```

Example, good

```
class D: public B {
public:
    int f(int i) override { std::cout << "f(int): "; return i + 1; }
    using B::f; // exposes f(double)
};</pre>
```

Note

This issue affects both virtual and non-virtual member functions

For variadic bases, C++17 introduced a variadic form of the using-declaration,

```
template<class... Ts>
struct Overloader : Ts... {
   using Ts::operator()...; // exposes operator() from every base
};
```

Enforcement

Diagnose name hiding

C.139: Use final on classes sparingly

Reason

Capping a hierarchy with final classes is rarely needed for logical reasons and can be damaging to the extensibility of a hierarchy.

Example, bad

```
class Widget { /* ... */ };

// nobody will ever want to improve My_widget (or so you thought)

class My_widget final : public Widget { /* ... */ };

class My_improved_widget : public My_widget { /* ... */ }; // error: can't do that
```

Note

Not every class is meant to be a base class. Most standard-library classes are examples of that (e.g., std::vector and std::string are not designed to be derived from). This rule is about using final on classes with virtual functions meant to be interfaces for a class hierarchy.

Note

Capping an individual virtual function with final is error-prone as final can easily be overlooked when defining/overriding a set of functions. Fortunately, the compiler catches such mistakes: You cannot re-declare/reopen a final member in a derived class.

Note

Claims of performance improvements from final should be substantiated. Too often, such claims are based on conjecture or experience with other languages.

There are examples where final can be important for both logical and performance reasons. One example is a performance-critical AST hierarchy in a compiler or language analysis tool. New derived classes are not added every year and only by library implementers. However, misuses are (or at least have been) far more common.

Enforcement

Flag uses of final on classes.

C.140: Do not provide different default arguments for a virtual function and an overrider

Reason

That can cause confusion: An overrider does not inherit default arguments.

Example, bad

```
class Base {
public:
    virtual int multiply(int value, int factor = 2) = 0;
    virtual ~Base() = default;
};

class Derived : public Base {
public:
    int multiply(int value, int factor = 10) override;
};

Derived d;
Base& b = d;

b.multiply(10); // these two calls will call the same function but
d.multiply(10); // with different arguments and so different results
```

Enforcement

Flag default arguments on virtual functions if they differ between base and derived declarations.

C.hier-access: Accessing objects in a hierarchy

C.145: Access polymorphic objects through pointers and references

Reason

If you have a class with a virtual function, you don't (in general) know which class provided the function to be used.

Example

```
struct B { int a; virtual int f(); virtual ~B() = default };
struct D : B { int b; int f() override; };

void use(B b)
{
    D d;
    B b2 = d; // slice
    B b3 = b;
}

void use2()
{
    D d;
    use(d); // slice
}
```

Both ds are sliced.

Exception

You can safely access a named polymorphic object in the scope of its definition, just don't slice it.

```
void use3()
{
    D d;
    d.f(); // OK
}
```

See also

A polymorphic class should suppress copying

Enforcement

Flag all slicing.

Reason

dynamic_cast is checked at run time.

Example

```
struct B { // an interface
   virtual void f();
   virtual void g();
   virtual ~B();
};
struct D : B { // a wider interface
   void f() override;
   virtual void h();
};
void user(B* pb)
   if (D* pd = dynamic_cast<D*>(pb)) {
        // ... use D's interface ...
    }
   else {
       // ... make do with B's interface ...
   }
}
```

Use of the other casts can violate type safety and cause the program to access a variable that is actually of type X to be accessed as if it were of an unrelated type Z:

```
void user2(B* pb) // bad
                                 // I know that pb really points to a D; trust me
   D* pd = static_cast<D*>(pb);
   // ... use D's interface ...
}
void user3(B* pb)
                  // unsafe
{
   if (some_condition) {
       D* pd = static_cast<D*>(pb); // I know that pb really points to a D; trust me
       // ... use D's interface ...
   }
   else {
       // ... make do with B's interface ...
}
void f()
{
```

```
B b;
user(&b); // OK
user2(&b); // bad error
user3(&b); // OK *if* the programmer got the some_condition check right
}
```

Note

Like other casts, dynamic_cast is overused. Prefer virtual functions to casting. Prefer static polymorphism to hierarchy navigation where it is possible (no run-time resolution necessary) and reasonably convenient.

Note

Some people use dynamic_cast where a typeid would have been more appropriate; dynamic_cast is a general "is kind of" operation for discovering the best interface to an object, whereas typeid is a "give me the exact type of this object" operation to discover the actual type of an object. The latter is an inherently simpler operation that ought to be faster. The latter (typeid) is easily hand-crafted if necessary (e.g., if working on a system where RTTI is -- for some reason -- prohibited), the former (dynamic_cast) is far harder to implement correctly in general.

Consider:

```
struct B {
    const char* name {"B"};
    // if pb1->id() == pb2->id() *pb1 is the same type as *pb2
    virtual const char* id() const { return name; }
    // ...
};

struct D : B {
    const char* name {"D"};
    const char* id() const override { return name; }
    // ...
};

void use()
{
    B* pb1 = new B;
    B* pb2 = new D;

    cout << pb1->id(); // "B"
    cout << pb2->id(); // "D"
```

The result of pb2->id() == "D" is actually implementation defined. We added it to warn of the dangers of homebrew RTTI. This code might work as expected for years, just to fail on a new machine, new compiler, or a new linker that does not unify character literals.

If you implement your own RTTI, be careful.

Exception

If your implementation provided a really slow dynamic_cast, you might have to use a workaround. However, all workarounds that cannot be statically resolved involve explicit casting (typically static_cast) and are error-prone. You will basically be crafting your own special-purpose dynamic_cast. So, first make sure that your dynamic_cast really is as slow as you think it is (there are a fair number of unsupported rumors about) and that your use of dynamic_cast is really performance critical.

We are of the opinion that current implementations of dynamic_cast are unnecessarily slow. For example, under suitable conditions, it is possible to perform a dynamic_cast in fast constant time. However, compatibility makes changes difficult even if all agree that an effort to optimize is worthwhile.

In very rare cases, if you have measured that the dynamic_cast overhead is material, you have other means to statically guarantee that a downcast will succeed (e.g., you are using CRTP carefully), and there is no virtual inheritance involved, consider tactically resorting static_cast with a prominent comment and disclaimer summarizing this paragraph and that human attention is needed under maintenance because the type system can't verify correctness. Even so, in our experience such "I know what I'm doing" situations are still a known bug source.

Exception

Consider:

```
template<typename B>
class Dx : B {
    // ...
};
```

Enforcement

- Flag all uses of static_cast for downcasts, including C-style casts that perform a static_cast.
- This rule is part of the type-safety profile.

C.147: Use dynamic_cast to a reference type when failure to find the required class is considered an error

Reason

Casting to a reference expresses that you intend to end up with a valid object, so the cast must succeed. dynamic_cast will then throw if it does not succeed.

Example

```
std::string f(Base& b)
{
    return dynamic_cast<Derived&>(b).to_string();
}
```

Enforcement

???

C.148: Use dynamic_cast to a pointer type when failure to find the required class is considered a valid alternative

Reason

The dynamic_cast conversion allows to test whether a pointer is pointing at a polymorphic object that has a given class in its hierarchy. Since failure to find the class merely returns a null value, it can be tested during run time. This allows writing code that can choose alternative paths depending on the results.

Contrast with C.147, where failure is an error, and should not be used for conditional execution.

Example

The example below describes the add function of a Shape_owner that takes ownership of constructed Shape objects. The objects are also sorted into views, according to their geometric attributes. In this example, Shape does not inherit from Geometric_attributes. Only its subclasses do.

```
void add(Shape* const item)
{
   // Ownership is always taken
   owned_shapes.emplace_back(item);

   // Check the Geometric_attributes and add the shape to none/one/some/all of the views

if (auto even = dynamic_cast<Even_sided*>(item))
{
   view_of_evens.emplace_back(even);
}

if (auto trisym = dynamic_cast<Trilaterally_symmetrical*>(item))
{
```

```
view_of_trisyms.emplace_back(trisym);
}
```

Notes

A failure to find the required class will cause <code>dynamic_cast</code> to return a null value, and de-referencing a null-valued pointer will lead to undefined behavior. Therefore the result of the <code>dynamic_cast</code> should always be treated as if it might contain a null value, and tested.

Enforcement

• (Complex) Unless there is a null test on the result of a dynamic_cast of a pointer type, warn upon dereference of the pointer.

C.149: Use unique_ptr or shared_ptr to avoid forgetting to delete objects created using new

Reason

Avoid resource leaks.

Example

Enforcement

- Flag initialization of a naked pointer with the result of a new
- Flag delete of local variable

C.150: Use make_unique() to construct objects owned by unique_ptrs

See R.22

C.152: Never assign a pointer to an array of derived class objects to a pointer to its base

Reason

Subscripting the resulting base pointer will lead to invalid object access and probably to memory corruption.

Example

Enforcement

- Flag all combinations of array decay and base to derived conversions.
- Pass an array as a span rather than as a pointer, and don't let the array name suffer a derived-to-base conversion before getting into the span

C.153: Prefer virtual function to casting

Reason

A virtual function call is safe, whereas casting is error-prone. A virtual function call reaches the most derived function, whereas a cast might reach an intermediate class and therefore give a wrong result (especially as a hierarchy is modified during maintenance).

Example

```
???
```

Enforcement

See C.146 and ???

C.over: Overloading and overloaded operators

You can overload ordinary functions, function templates, and operators. You cannot overload function objects.

Overload rule summary:

- C.160: Define operators primarily to mimic conventional usage
- C.161: Use non-member functions for symmetric operators
- C.162: Overload operations that are roughly equivalent
- C.163: Overload only for operations that are roughly equivalent
- C.164: Avoid implicit conversion operators
- C.165: Use using for customization points
- C.166: Overload unary & only as part of a system of smart pointers and references
- C.167: Use an operator for an operation with its conventional meaning
- C.168: Define overloaded operators in the namespace of their operands
- C.170: If you feel like overloading a lambda, use a generic lambda

C.160: Define operators primarily to mimic conventional usage

Reason

Minimize surprises.

Example

Here, the conventional semantics is maintained: Copies compare equal.

Example, bad

```
X operator+(X a, X b) { return a.v - b.v; } // bad: makes + subtract
```

Note

Non-member operators should be either friends or defined in the same namespace as their operands. Binary operators should treat their operands equivalently.

Enforcement

Possibly impossible.

C.161: Use non-member functions for symmetric operators

Reason

If you use member functions, you need two. Unless you use a non-member function for (say) ==, a == b and b == a will be subtly different.

Example

```
bool operator==(Point a, Point b) { return a.x == b.x && a.y == b.y; }
```

Enforcement

Flag member operator functions.

C.162: Overload operations that are roughly equivalent

Reason

Having different names for logically equivalent operations on different argument types is confusing, leads to encoding type information in function names, and inhibits generic programming.

Example

Consider:

```
void print(int a);
void print(int a, int base);
void print(const string&);
```

These three functions all print their arguments (appropriately). Conversely:

```
void print_int(int a);
void print_based(int a, int base);
void print_string(const string&);
```

These three functions all print their arguments (appropriately). Adding to the name just introduced verbosity and inhibits generic code.

Enforcement

???

C.163: Overload only for operations that are roughly equivalent

Reason

Having the same name for logically different functions is confusing and leads to errors when using generic programming.

Example

Consider:

```
void open_gate(Gate& g); // remove obstacle from garage exit lane
void fopen(const char* name, const char* mode); // open file
```

The two operations are fundamentally different (and unrelated) so it is good that their names differ. Conversely:

```
void open(Gate& g); // remove obstacle from garage exit lane
void open(const char* name, const char* mode ="r"); // open file
```

The two operations are still fundamentally different (and unrelated) but the names have been reduced to their (common) minimum, opening opportunities for confusion. Fortunately, the type system will catch many such mistakes.

Note

Be particularly careful about common and popular names, such as open, move, +, and ==.

Enforcement

???

C.164: Avoid implicit conversion operators

Reason

Implicit conversions can be essential (e.g., double to int) but often cause surprises (e.g., String to C-style string).

Note

Prefer explicitly named conversions until a serious need is demonstrated. By "serious need" we mean a reason that is fundamental in the application domain (such as an integer to complex number conversion) and frequently needed. Do not introduce implicit conversions (through conversion operators or non-explicit constructors) just to gain a minor convenience.

Example

```
struct S1 {
   string s;
   // ...
   operator char*() { return s.data(); } // BAD, likely to cause surprises
};
struct S2 {
    string s;
   // ...
   explicit operator char*() { return s.data(); }
};
void f(S1 s1, S2 s2)
    char* x1 = s1; // OK, but can cause surprises in many contexts
    char* x2 = s2;
                     // error (and that's usually a good thing)
    char* x3 = static_cast<char*>(s2); // we can be explicit (on your head be it)
}
```

The surprising and potentially damaging implicit conversion can occur in arbitrarily hard-to spot contexts, e.g.,

```
S1 ff();
char* g()
{
   return ff();
}
```

The string returned by ff() is destroyed before the returned pointer into it can be used.

Flag all non-explicit conversion operators.

C.165: Use using for customization points

Reason

To find function objects and functions defined in a separate namespace to "customize" a common function.

Example

Consider swap. It is a general (standard-library) function with a definition that will work for just about any type. However, it is desirable to define specific swap()s for specific types. For example, the general swap() will copy the elements of two vectors being swapped, whereas a good specific implementation will not copy elements at all.

The std::swap() in f1() does exactly what we asked it to do: it calls the swap() in namespace std. Unfortunately, that's probably not what we wanted. How do we get N::X considered?

```
void f2(N::X& a, N::X& b)
{
    swap(a, b); // calls N::swap
}
```

But that might not be what we wanted for generic code. There, we typically want the specific function if it exists and the general function if not. This is done by including the general function in the lookup for the function:

```
void f3(N::X& a, N::X& b)
{
   using std::swap; // make std::swap available
   swap(a, b); // calls N::swap if it exists, otherwise std::swap
}
```

Unlikely, except for known customization points, such as swap. The problem is that the unqualified and qualified lookups both have uses.

C.166: Overload unary & only as part of a system of smart pointers and references

Reason

The & operator is fundamental in C++. Many parts of the C++ semantics assume its default meaning.

Example

```
class Ptr { // a somewhat smart pointer
   Ptr(X* pp) : p(pp) { /* check */ }
   X* operator->() { /* check */ return p; }
   X operator[](int i);
   X operator*();
private:
   T* p;
};

class X {
   Ptr operator&() { return Ptr{this}; }
   // ...
};
```

Note

If you "mess with" operator & be sure that its definition has matching meanings for ->, [], *, and . on the result type. Note that operator . currently cannot be overloaded so a perfect system is impossible. We hope to remedy that: Operator Dot (R2). Note that std::addressof() always yields a built-in pointer.

Enforcement

Tricky. Warn if & is user-defined without also defining -> for the result type.

C.167: Use an operator for an operation with its conventional meaning

Reason

Readability. Convention. Reusability. Support for generic code

Example

```
void cout_my_class(const My_class& c) // confusing, not conventional,not generic
{
    std::cout << /* class members here */;
}
std::ostream& operator<<(std::ostream& os, const my_class& c) // OK
{
    return os << /* class members here */;
}</pre>
```

By itself, cout_my_class would be OK, but it is not usable/composable with code that rely on the << convention for output:

```
My_class var { /* ... */ };
// ...
cout << "var = " << var << '\n';</pre>
```

Note

There are strong and vigorous conventions for the meaning of most operators, such as

- comparisons (==, !=, <, <=, >, >=, and <=>),
- arithmetic operations (+, -, *, /, and %)
- access operations (., ->, unary *, and [])
- assignment (=)

Don't define those unconventionally and don't invent your own names for them.

Enforcement

Tricky. Requires semantic insight.

C.168: Define overloaded operators in the namespace of their operands

Reason

Readability. Ability for find operators using ADL. Avoiding inconsistent definition in different namespaces

Example

```
struct S { };
S operator+(S, S);  // OK: in the same namespace as S, and even next to S
S s;
S r = s + s;
```

Example

Example, bad

```
struct S { };
S s;

namespace N {
    bool operator!(S a) { return true; }
    bool not_s = !s;
}

namespace M {
    bool operator!(S a) { return false; }
    bool not_s = !s;
}
```

Here, the meaning of !s differs in N and M. This can be most confusing. Remove the definition of namespace M and the confusion is replaced by an opportunity to make the mistake.

Note

If a binary operator is defined for two types that are defined in different namespaces, you cannot follow this rule. For example:

```
Vec::Vector operator*(const Vec::Vector&, const Mat::Matrix&);
```

This might be something best avoided.

See also

This is a special case of the rule that helper functions should be defined in the same namespace as their class.

Enforcement

• Flag operator definitions that are not in the namespace of their operands

C.170: If you feel like overloading a lambda, use a generic lambda

Reason

You cannot overload by defining two different lambdas with the same name.

Example

```
void f(int);
void f(double);
auto f = [](char);  // error: cannot overload variable and function

auto g = [](int) { /* ... */ };
auto g = [](double) { /* ... */ };  // error: cannot overload variables

auto h = [](auto) { /* ... */ };  // OK
```

Enforcement

The compiler catches the attempt to overload a lambda.

C.union: Unions

A union is a struct where all members start at the same address so that it can hold only one member at a time. A union does not keep track of which member is stored so the programmer has to get it right; this is inherently error-prone, but there are ways to compensate.

A type that is a union plus an indicator of which member is currently held is called a *tagged union*, a *discriminated union*, or a *variant*.

Union rule summary:

- C.180: Use unions to save Memory
- C.181: Avoid "naked" unions
- C.182: Use anonymous unions to implement tagged unions
- C.183: Don't use a union for type punning
- ???

C.180: Use unions to save memory

Reason

A union allows a single piece of memory to be used for different types of objects at different times. Consequently, it can be used to save memory when we have several objects that are never used at the same time.

Example

```
union Value {
    int x;
    double d;
};

Value v = { 123 }; // now v holds an int
    cout << v.x << '\n'; // write 123
    v.d = 987.654; // now v holds a double
    cout << v.d << '\n'; // write 987.654</pre>
```

But heed the warning: Avoid "naked" unions

Example

```
// Short-string optimization
constexpr size_t buffer_size = 16; // Slightly larger than the size of a pointer
class Immutable_string {
public:
    Immutable_string(const char* str) :
        size(strlen(str))
        if (size < buffer_size)</pre>
            strcpy_s(string_buffer, buffer_size, str);
            string_ptr = new char[size + 1];
            strcpy_s(string_ptr, size + 1, str);
        }
    }
    ~Immutable_string()
        if (size >= buffer_size)
            delete[] string_ptr;
    }
    const char* get_str() const
        return (size < buffer_size) ? string_buffer : string_ptr;</pre>
    }
```

```
private:
    // If the string is short enough, we store the string itself
    // instead of a pointer to the string.
    union {
        char* string_ptr;
        char string_buffer[buffer_size];
    };

const size_t size;
};
```

???

C.181: Avoid "naked" unions

Reason

A *naked union* is a union without an associated indicator which member (if any) it holds, so that the programmer has to keep track. Naked unions are a source of type errors.

Example, bad

```
union Value {
   int x;
   double d;
};

Value v;
v.d = 987.654; // v holds a double
```

So far, so good, but we can easily misuse the union:

```
cout << v.x << '\n'; // BAD, undefined behavior: v holds a double, but we read it as an int
```

Note that the type error happened without any explicit cast. When we tested that program the last value printed was 1683627180 which is the integer value for the bit pattern for 987.654. What we have here is an "invisible" type error that happens to give a result that could easily look innocent.

And, talking about "invisible", this code produced no output:

```
v.x = 123;
cout << v.d << '\n';  // BAD: undefined behavior</pre>
```

Alternative

Wrap a union in a class together with a type field.

The C++17 variant type (found in <variant>) does that for you:

Enforcement

???

C.182: Use anonymous unions to implement tagged unions

Reason

A well-designed tagged union is type safe. An *anonymous* union simplifies the definition of a class with a (tag, union) pair.

Example

This example is mostly borrowed from TC++PL4 pp216-218. You can look there for an explanation.

The code is somewhat elaborate. Handling a type with user-defined assignment and destructor is tricky. Saving programmers from having to write such code is one reason for including variant in the standard.

```
class Value { // two alternative representations represented as a union
private:
    enum class Tag { number, text };
    Tag type; // discriminant

union { // representation (note: anonymous union)
        int i;
        string s; // string has default constructor, copy operations, and destructor
    };
public:
    struct Bad_entry { }; // used for exceptions

~Value();
    Value& operator=(const Value&); // necessary because of the string variant
    Value(const Value&);
    // ...
    int number() const;
    string text() const;
```

```
void set_number(int n);
    void set_text(const string&);
    // ...
};
int Value::number() const
    if (type != Tag::number) throw Bad_entry{};
    return i;
}
string Value::text() const
    if (type != Tag::text) throw Bad_entry{};
    return s;
}
void Value::set number(int n)
    if (type == Tag::text) {
       s.~string();
                        // explicitly destroy string
       type = Tag::number;
    }
   i = n;
}
void Value::set_text(const string& ss)
    if (type == Tag::text)
        s = ss;
    else {
        new(&s) string{ss}; // placement new: explicitly construct string
       type = Tag::text;
    }
}
Value& Value::operator=(const Value& e) // necessary because of the string variant
{
    if (type == Tag::text && e.type == Tag::text) {
       s = e.s; // usual string assignment
        return *this;
    }
    if (type == Tag::text) s.~string(); // explicit destroy
    switch (e.type) {
    case Tag::number:
        i = e.i;
       break;
    case Tag::text:
        new(&s) string(e.s); // placement new: explicit construct
    }
```

```
type = e.type;
  return *this;
}

Value::~Value()
{
   if (type == Tag::text) s.~string(); // explicit destroy
}
```

???

C.183: Don't use a union for type punning

Reason

It is undefined behavior to read a union member with a different type from the one with which it was written. Such punning is invisible, or at least harder to spot than using a named cast. Type punning using a union is a source of errors.

Example, bad

```
union Pun {
   int x;
   unsigned char c[sizeof(int)];
};
```

The idea of Pun is to be able to look at the character representation of an int.

If you wanted to see the bytes of an int, use a (named) cast:

Accessing the result of a reinterpret_cast from the object's declared type to char*, unsigned char*, or std::byte* is defined behavior. (Using reinterpret_cast is discouraged, but at least we can see that something tricky is going on.)

Note

Unfortunately, unions are commonly used for type punning. We don't consider "sometimes, it works as expected" a conclusive argument.

C++17 introduced a distinct type std::byte to facilitate operations on raw object representation. Use that type instead of unsigned char or char for these operations.

Enforcement

???

Enum: Enumerations

Enumerations are used to define sets of integer values and for defining types for such sets of values. There are two kinds of enumerations, "plain" enums and class enums.

Enumeration rule summary:

- Enum.1: Prefer enumerations over macros
- Enum.2: Use enumerations to represent sets of related named constants
- Enum.3: Prefer enum classes over "plain" enums
- Enum.4: Define operations on enumerations for safe and simple use
- Enum.5: Don't use ALL CAPS for enumerators
- Enum.6: Avoid unnamed enumerations
- Enum.7: Specify the underlying type of an enumeration only when necessary
- Enum.8: Specify enumerator values only when necessary

Enum.1: Prefer enumerations over macros

Reason

Macros do not obey scope and type rules. Also, macro names are removed during preprocessing and so usually don't appear in tools like debuggers.

Example

First some bad old code:

Instead use an enum:

```
enum class Web_color { red = 0xFF0000, green = 0x00FF00, blue = 0x0000FF };
enum class Product_info { red = 0, purple = 1, blue = 2 };
int webby = blue;  // error: be specific
Web_color webby = Web_color::blue;
```

We used an enum class to avoid name clashes.

Note

Also consider constexpr and const inline variables.

Enforcement

Flag macros that define integer values. Use enum or const inline or another non-macro alternative instead.

Enum.2: Use enumerations to represent sets of related named constants

Reason

An enumeration shows the enumerators to be related and can be a named type.

Example

```
enum class Web_color { red = 0xFF0000, green = 0x00FF00, blue = 0x0000FF };
```

Note

Switching on an enumeration is common and the compiler can warn against unusual patterns of case labels. For example:

```
enum class Product_info { red = 0, purple = 1, blue = 2 };

void print(Product_info inf)
{
    switch (inf) {
    case Product_info::red: cout << "red"; break;
    case Product_info::purple: cout << "purple"; break;
    }
}</pre>
```

Such off-by-one switch-statements are often the results of an added enumerator and insufficient testing.

Enforcement

- Flag switch-statements where the cases cover most but not all enumerators of an enumeration.
- Flag switch-statements where the cases cover a few enumerators of an enumeration, but there is no default.

Enum.3: Prefer class enums over "plain" enums

Reason

To minimize surprises: traditional enums convert to int too readily.

Example

```
void Print_color(int color);
enum Web_color { red = 0xFF0000, green = 0x00FF00, blue = 0x0000FF };
enum Product_info { red = 0, purple = 1, blue = 2 };

Web_color webby = Web_color::blue;

// Clearly at least one of these calls is buggy.
Print_color(webby);
Print_color(Product_info::blue);
```

Instead use an enum class:

```
void Print_color(int color);
enum class Web_color { red = 0xFF0000, green = 0x00FF00, blue = 0x0000FF };
enum class Product_info { red = 0, purple = 1, blue = 2 };

Web_color webby = Web_color::blue;
Print_color(webby); // Error: cannot convert Web_color to int.
Print_color(Product_info::red); // Error: cannot convert Product_info to int.
```

(Simple) Warn on any non-class enum definition.

Enum.4: Define operations on enumerations for safe and simple use

Reason

Convenience of use and avoidance of errors.

Example

```
enum class Day { mon, tue, wed, thu, fri, sat, sun };

Day& operator++(Day& d)
{
    return d = (d == Day::sun) ? Day::mon : static_cast<Day>(static_cast<int>(d)+1);
}

Day today = Day::sat;
Day tomorrow = ++today;
```

The use of a static_cast is not pretty, but

```
Day& operator++(Day& d)
{
    return d = (d == Day::sun) ? Day::mon : Day{++d}; // error
}
```

is an infinite recursion, and writing it without a cast, using a switch on all cases is long-winded.

Enforcement

Flag repeated expressions cast back into an enumeration.

Enum.5: Don't use ALL_CAPS for enumerators

Reason

Avoid clashes with macros.

Example, bad

Enforcement

Flag ALL_CAPS enumerators.

Enum.6: Avoid unnamed enumerations

Reason

If you can't name an enumeration, the values are not related

Example, bad

```
enum { red = 0xFF0000, scale = 4, is_signed = 1 };
```

Such code is not uncommon in code written before there were convenient alternative ways of specifying integer constants.

Alternative

Use constexpr values instead. For example:

```
constexpr int red = 0xFF0000;
constexpr short scale = 4;
constexpr bool is_signed = true;
```

Flag unnamed enumerations.

Enum.7: Specify the underlying type of an enumeration only when necessary

Reason

The default is the easiest to read and write. int is the default integer type. int is compatible with C enums.

Example

Note

Specifying the underlying type is necessary to forward-declare an enum or enum class:

```
enum Flags : char;

void f(Flags);

// ....
enum Flags : char { /* ... */ };
```

or to ensure that values of that type have a specified bit-precision:

```
enum Bitboard : uint64_t { /* ... */ };
```

Enforcement

????

Enum.8: Specify enumerator values only when necessary

Reason

It's the simplest. It avoids duplicate enumerator values. The default gives a consecutive set of values that is good for switch-statement implementations.

Example

Specifying values is necessary to match conventional values (e.g., Month) and where consecutive values are undesirable (e.g., to get separate bits as in Base_flag).

Enforcement

- Flag duplicate enumerator values
- Flag explicitly specified all-consecutive enumerator values

R: Resource management

This section contains rules related to resources. A resource is anything that must be acquired and (explicitly or implicitly) released, such as memory, file handles, sockets, and locks. The reason it must be released is typically that it can be in short supply, so even delayed release might do harm. The fundamental aim is to ensure that we don't leak any resources and that we don't hold a resource longer than we need to. An entity that is responsible for releasing a resource is called an owner.

There are a few cases where leaks can be acceptable or even optimal: If you are writing a program that simply produces an output based on an input and the amount of memory needed is proportional to the size of the input, the optimal strategy (for performance and ease of programming) is sometimes simply never to delete anything. If you have enough memory to handle your largest input, leak away, but be sure to give a good error message if you are wrong. Here, we ignore such cases.

- Resource management rule summary:
 - R.1: Manage resources automatically using resource handles and RAII (Resource Acquisition Is Initialization)
 - R.2: In interfaces, use raw pointers to denote individual objects (only)
 - R.3: A raw pointer (a T*) is non-owning
 - R.4: A raw reference (a T&) is non-owning
 - R.5: Prefer scoped objects, don't heap-allocate unnecessarily
 - R.6: Avoid non-const global variables
- Allocation and deallocation rule summary:

- R.10: Avoid malloc() and free()
- R.11: Avoid calling new and delete explicitly
- R.12: Immediately give the result of an explicit resource allocation to a manager object
- R.13: Perform at most one explicit resource allocation in a single expression statement
- R.14: Avoid [] parameters, prefer span
- R.15: Always overload matched allocation/deallocation pairs
- Smart pointer rule summary:
 - R.20: Use unique_ptr or shared_ptr to represent ownership
 - R.21: Prefer unique_ptr over shared_ptr unless you need to share ownership
 - R.22: Use make_shared() to make shared_ptrs
 - R.23: Use make_unique() to make unique_ptrs
 - R.24: Use std::weak_ptr to break cycles of shared_ptrs
 - R.30: Take smart pointers as parameters only to explicitly express lifetime semantics
 - R.31: If you have non-std smart pointers, follow the basic pattern from std
 - R.32: Take a unique_ptr<widget> parameter to express that a function assumes ownership of a widget
 - R.33: Take a unique_ptr<widget>& parameter to express that a function reseats the widget
 - R.34: Take a shared_ptr<widget> parameter to express shared ownership
 - R.35: Take a shared ptr<widget>& parameter to express that a function might reseat the shared pointer
 - R.36: Take a const shared_ptr<widget>& parameter to express that it might retain a reference count to the object ???
 - R.37: Do not pass a pointer or reference obtained from an aliased smart pointer

R.1: Manage resources automatically using resource handles and RAII (Resource Acquisition Is Initialization)

Reason

To avoid leaks and the complexity of manual resource management. C++'s language-enforced constructor/destructor symmetry mirrors the symmetry inherent in resource acquire/release function pairs such as fopen/fclose, lock/unlock, and new/delete. Whenever you deal with a resource that needs paired acquire/release function calls, encapsulate that resource in an object that enforces pairing for you -- acquire the resource in its constructor, and release it in its destructor.

Example, bad

Consider:

```
void send(X* x, string_view destination)
{
    auto port = open_port(destination);
    my_mutex.lock();
    // ...
    send(port, x);
    // ...
    my_mutex.unlock();
    close_port(port);
    delete x;
}
```

In this code, you have to remember to unlock, close_port, and delete on all paths, and do each exactly once. Further, if any of the code marked ... throws an exception, then x is leaked and my_mutex remains locked.

Example

Consider:

Now all resource cleanup is automatic, performed once on all paths whether or not there is an exception. As a bonus, the function now advertises that it takes over ownership of the pointer.

What is Port? A handy wrapper that encapsulates the resource:

```
class Port {
    PortHandle port;
public:
    Port(string_view destination) : port{open_port(destination)} { }
    ~Port() { close_port(port); }
    operator PortHandle() { return port; }

    // port handles can't usually be cloned, so disable copying and assignment if necessary
    Port(const Port&) = delete;
    Port& operator=(const Port&) = delete;
};
```

Note

Where a resource is "ill-behaved" in that it isn't represented as a class with a destructor, wrap it in a class or use finally

See also: RAII

R.2: In interfaces, use raw pointers to denote individual objects (only)

Reason

Arrays are best represented by a container type (e.g., vector (owning)) or a span (non-owning). Such containers and views hold sufficient information to do range checking.

Example, bad

```
void f(int* p, int n) // n is the number of elements in p[]
{
    // ...
    p[2] = 7; // bad: subscript raw pointer
    // ...
}
```

The compiler does not read comments, and without reading other code you do not know whether p really points to n elements. Use a span instead.

Example

```
void g(int* p, int fmt) // print *p using format #fmt
{
    // ... uses *p and p[0] only ...
}
```

Exception

C-style strings are passed as single pointers to a zero-terminated sequence of characters. Use zstring rather than char* to indicate that you rely on that convention.

Note

Many current uses of pointers to a single element could be references. However, where nullptr is a possible value, a reference might not be a reasonable alternative.

- Flag pointer arithmetic (including ++) on a pointer that is not part of a container, view, or iterator. This rule would generate a huge number of false positives if applied to an older code base.
- Flag array names passed as simple pointers

R.3: A raw pointer (a T*) is non-owning

Reason

There is nothing (in the C++ standard or in most code) to say otherwise and most raw pointers are non-owning. We want owning pointers identified so that we can reliably and efficiently delete the objects pointed to by owning pointers.

Example

The unique_ptr protects against leaks by guaranteeing the deletion of its object (even in the presence of exceptions). The T* does not.

Example

```
template<typename T>
class X {
public:
    T* p; // bad: it is unclear whether p is owning or not
    T* q; // bad: it is unclear whether q is owning or not
    // ...
};
```

We can fix that problem by making ownership explicit:

```
template<typename T>
class X2 {
public:
    owner<T*> p; // OK: p is owning
    T* q; // OK: q is not owning
    // ...
};
```

Exception

A major class of exception is legacy code, especially code that must remain compilable as C or interface with C and C-style C++ through ABIs. The fact that there are billions of lines of code that violate this rule against owning T*s cannot be ignored. We'd love to see program transformation tools turning 20-year-old "legacy" code into shiny modern code, we encourage the development, deployment and use of such tools, we hope the guidelines will help the development of such tools, and we even contributed (and contribute) to the research and development in this area. However, it will take time: "legacy code" is generated faster than we can renovate old code, and so it will be for a few years.

This code cannot all be rewritten (even assuming good code transformation software), especially not soon. This problem cannot be solved (at scale) by transforming all owning pointers to unique_ptrs and shared_ptrs, partly because we need/use owning "raw pointers" as well as simple pointers in the implementation of our fundamental resource handles. For example, common vector implementations have one owning pointer and two non-owning pointers. Many ABIs (and essentially all interfaces to C code) use T*s, some of them owning. Some interfaces cannot be simply annotated with owner because they need to remain compilable as C (although this would be a rare good use for a macro, that expands to owner in C++ mode only).

Note

owner<T*> has no default semantics beyond T*. It can be used without changing any code using it and without affecting ABIs. It is simply an indicator to programmers and analysis tools. For example, if an owner<T*> is a member of a class, that class better have a destructor that deletes it.

Example, bad

Returning a (raw) pointer imposes a lifetime management uncertainty on the caller; that is, who deletes the pointed-to object?

```
Gadget* make_gadget(int n)
{
    auto p = new Gadget{n};
    // ...
    return p;
}

void caller(int n)
{
    auto p = make_gadget(n); // remember to delete p
    // ...
    delete p;
}
```

In addition to suffering from the problem from leak, this adds a spurious allocation and deallocation operation, and is needlessly verbose. If Gadget is cheap to move out of a function (i.e., is small or has an efficient move operation), just return it "by value" (see "out" return values):

```
Gadget make_gadget(int n)
{
    Gadget g{n};
    // ...
    return g;
}
```

Note

This rule applies to factory functions.

Note

If pointer semantics are required (e.g., because the return type needs to refer to a base class of a class hierarchy (an interface)), return a "smart pointer."

Enforcement

- (Simple) Warn on delete of a raw pointer that is not an owner<T>.
- (Moderate) Warn on failure to either reset or explicitly delete an owner<T> pointer on every code path.
- (Simple) Warn if the return value of new is assigned to a raw pointer.
- (Simple) Warn if a function returns an object that was allocated within the function but has a move constructor. Suggest considering returning it by value instead.

R.4: A raw reference (a T&) is non-owning

Reason

There is nothing (in the C++ standard or in most code) to say otherwise and most raw references are non-owning. We want owners identified so that we can reliably and efficiently delete the objects pointed to by owning pointers.

Example

```
void f()
{
   int& r = *new int{7}; // bad: raw owning reference
   // ...
   delete &r; // bad: violated the rule against deleting raw pointers
}
```

See also: The raw pointer rule

See the raw pointer rule

R.5: Prefer scoped objects, don't heap-allocate unnecessarily

Reason

A scoped object is a local object, a global object, or a member. This implies that there is no separate allocation and deallocation cost in excess of that already used for the containing scope or object. The members of a scoped object are themselves scoped and the scoped object's constructor and destructor manage the members' lifetimes.

Example

The following example is inefficient (because it has unnecessary allocation and deallocation), vulnerable to exception throws and returns in the ... part (leading to leaks), and verbose:

```
void f(int n)
{
    auto p = new Gadget{n};
    // ...
    delete p;
}
```

Instead, use a local variable:

```
void f(int n)
{
    Gadget g{n};
    // ...
}
```

Enforcement

- (Moderate) Warn if an object is allocated and then deallocated on all paths within a function. Suggest it should be a local stack object instead.
- (Simple) Warn if a local Unique_pointer or Shared_pointer that is not moved, copied, reassigned or reset before its lifetime ends is not declared const. Exception: Do not produce such a warning on a local Unique_pointer to an unbounded array. (See below.)

Exception

It is OK to create a local const unique_ptr<T[]> to a heap-allocated buffer, as this is a valid way to represent a scoped dynamic array.

Example

A valid use case for a local const $unique_ptr<T[]> variable:$

```
int get_median_value(const std::list<int>& integers)
{
  const auto size = integers.size();

  // OK: declaring a local unique_ptr<T[]>.
  const auto local_buffer = std::make_unique_for_overwrite<int[]>(size);

  std::copy_n(begin(integers), size, local_buffer.get());
  std::nth_element(local_buffer.get(), local_buffer.get() + size/2, local_buffer.get() + size);

  return local_buffer[size/2];
}
```

R.6: Avoid non-const global variables

See I.2

R.alloc: Allocation and deallocation

R.10: Avoid malloc() and free()

Reason

malloc() and free() do not support construction and destruction, and do not mix well with new and delete.

Example

```
class Record {
   int id;
   string name;
   // ...
};

void use()
{
   // p1 might be nullptr
   // *p1 is not initialized; in particular,
   // that string isn't a string, but a string-sized bag of bits
   Record* p1 = static_cast<Record*>(malloc(sizeof(Record)));
```

```
auto p2 = new Record;

// unless an exception is thrown, *p2 is default initialized
auto p3 = new(nothrow) Record;

// p3 might be nullptr; if not, *p3 is default initialized

// ...

delete p1;  // error: cannot delete object allocated by malloc()
free(p2);  // error: cannot free() object allocated by new
}
```

In some implementations that delete and that free() might work, or maybe they will cause run-time errors.

Exception

There are applications and sections of code where exceptions are not acceptable. Some of the best such examples are in life-critical hard-real-time code. Beware that many bans on exception use are based on superstition (bad) or by concerns for older code bases with unsystematic resource management (unfortunately, but sometimes necessary). In such cases, consider the nothrow versions of new.

Enforcement

Flag explicit use of malloc and free.

R.11: Avoid calling new and delete explicitly

Reason

The pointer returned by new should belong to a resource handle (that can call delete). If the pointer returned by new is assigned to a plain/naked pointer, the object can be leaked.

Note

In a large program, a naked delete (that is a delete in application code, rather than part of code devoted to resource management) is a likely bug: if you have N deletes, how can you be certain that you don't need N+1 or N-1? The bug might be latent: it might emerge only during maintenance. If you have a naked new, you probably need a naked delete somewhere, so you probably have a bug.

Enforcement

(Simple) Warn on any explicit use of new and delete. Suggest using make_unique instead.

R.12: Immediately give the result of an explicit resource allocation to a manager object

Reason

If you don't, an exception or a return might lead to a leak.

Example, bad

The allocation of buf might fail and leak the file handle.

Example

```
void func(const string& name)
{
   ifstream f{name}; // open the file
   vector<char> buf(1024);
   // ...
}
```

The use of the file handle (in ifstream) is simple, efficient, and safe.

Enforcement

• Flag explicit allocations used to initialize pointers (problem: how many direct resource allocations can we recognize?)

R.13: Perform at most one explicit resource allocation in a single expression statement

Reason

If you perform two explicit resource allocations in one statement, you could leak resources because the order of evaluation of many subexpressions, including function arguments, is unspecified.

Example

```
void fun(shared_ptr<Widget> sp1, shared_ptr<Widget> sp2);
```

This fun can be called like this:

```
// BAD: potential leak
fun(shared_ptr<Widget>(new Widget(a, b)), shared_ptr<Widget>(new Widget(c, d)));
```

This is exception-unsafe because the compiler might reorder the two expressions building the function's two arguments. In particular, the compiler can interleave execution of the two expressions: Memory allocation (by calling operator new) could be done first for both objects, followed by attempts to call the two Widget constructors. If one of the constructor calls throws an exception, then the other object's memory will never be released!

This subtle problem has a simple solution: Never perform more than one explicit resource allocation in a single expression statement. For example:

```
shared_ptr<Widget> sp1(new Widget(a, b)); // Better, but messy
fun(sp1, new Widget(c, d));
```

The best solution is to avoid explicit allocation entirely use factory functions that return owning objects:

```
fun(make_shared<Widget>(a, b), make_shared<Widget>(c, d)); // Best
```

Write your own factory wrapper if there is not one already.

Enforcement

• Flag expressions with multiple explicit resource allocations (problem: how many direct resource allocations can we recognize?)

R.14: Avoid [] parameters, prefer span

Reason

An array decays to a pointer, thereby losing its size, opening the opportunity for range errors. Use span to preserve size information.

Example

Flag [] parameters. Use span instead.

R.15: Always overload matched allocation/deallocation pairs

Reason

Otherwise you get mismatched operations and chaos.

Example

```
class X {
    // ...
    void* operator new(size_t s);
    void operator delete(void*);
    // ...
};
```

Note

If you want memory that cannot be deallocated, =delete the deallocation operation. Don't leave it undeclared.

Enforcement

Flag incomplete pairs.

R.smart: Smart pointers

R.20: Use unique_ptr or shared_ptr to represent ownership

Reason

They can prevent resource leaks.

Example

Consider:

This will leak the object used to initialize p1 (only).

Enforcement

- (Simple) Warn if the return value of new is assigned to a raw pointer.
- (Simple) Warn if the result of a function returning a raw owning pointer is assigned to a raw pointer.

R.21: Prefer unique_ptr over shared_ptr unless you need to share ownership

Reason

A unique_ptr is conceptually simpler and more predictable (you know when destruction happens) and faster (you don't implicitly maintain a use count).

Example, bad

This needlessly adds and maintains a reference count.

```
void f()
{
    shared_ptr<Base> base = make_shared<Derived>();
    // use base locally, without copying it -- refcount never exceeds 1
} // destroy base
```

Example

This is more efficient:

```
void f()
{
    unique_ptr<Base> base = make_unique<Derived>();
    // use base locally
} // destroy base
```

(Simple) Warn if a function uses a Shared_pointer with an object allocated within the function, but never returns the Shared_pointer or passes it to a function requiring a Shared_pointer&. Suggest using unique_ptr instead.

R.22: Use make_shared() to make shared_ptrs

Reason

make_shared gives a more concise statement of the construction. It also gives an opportunity to eliminate a separate allocation for the reference counts, by placing the shared_ptr's use counts next to its object.

Example

Consider:

```
shared_ptr<X> p1 { new X{2} }; // bad
auto p = make_shared<X>(2); // good
```

The make_shared() version mentions X only once, so it is usually shorter (as well as faster) than the version with the explicit new.

Enforcement

(Simple) Warn if a shared_ptr is constructed from the result of new rather than make_shared.

Reason

make_unique gives a more concise statement of the construction. It also ensures exception safety in complex expressions.

Example

```
unique_ptr<Foo> p {new Foo{7}};  // OK: but repetitive

auto q = make_unique<Foo>(7);  // Better: no repetition of Foo
```

(Simple) Warn if a unique_ptr is constructed from the result of new rather than make_unique.

R.24: Use std::weak_ptr to break cycles of shared_ptrs

Reason

shared_ptr's rely on use counting and the use count for a cyclic structure never goes to zero, so we need a mechanism to be able to destroy a cyclic structure.

Example

```
#include <memory>
class bar;
class foo {
public:
 explicit foo(const std::shared_ptr<bar>& forward_reference)
    : forward_reference_(forward_reference)
 { }
private:
 std::shared_ptr<bar> forward_reference_;
};
class bar {
public:
 explicit bar(const std::weak_ptr<foo>& back_reference)
    : back_reference_(back_reference)
 { }
 void do_something()
   if (auto shared_back_reference = back_reference_.lock()) {
      // Use *shared_back_reference
    }
 }
private:
 std::weak_ptr<foo> back_reference_;
};
```

Note

??? (HS: A lot of people say "to break cycles", while I think "temporary shared ownership" is more to the point.) ???(BS: breaking cycles is what you must do; temporarily sharing ownership is how you do it. You could "temporarily share ownership" simply by using another shared_ptr.)

??? probably impossible. If we could statically detect cycles, we wouldn't need weak_ptr

R.30: Take smart pointers as parameters only to explicitly express lifetime semantics

See F.7.

R.31: If you have non-std smart pointers, follow the basic pattern from std

Reason

The rules in the following section also work for other kinds of third-party and custom smart pointers and are very useful for diagnosing common smart pointer errors that cause performance and correctness problems. You want the rules to work on all the smart pointers you use.

Any type (including primary template or specialization) that overloads unary * and -> is considered a smart pointer:

- If it is copyable, it is recognized as a reference-counted shared_ptr.
- If it is not copyable, it is recognized as a unique unique_ptr.

Example, bad

```
// use Boost's intrusive_ptr
#include <boost/intrusive_ptr.hpp>
void f(boost::intrusive_ptr<widget> p) // error under rule 'sharedptrparam'
{
    p->foo();
}

// use Microsoft's CComPtr
#include <atlbase.h>
void f(CComPtr<widget> p) // error under rule 'sharedptrparam'
{
    p->foo();
}
```

Both cases are an error under the sharedptrparam guideline: p is a Shared_pointer, but nothing about its sharedness is used here and passing it by value is a silent pessimization; these functions should accept a smart pointer only if they need to participate in the widget's lifetime management. Otherwise they should accept a widget*, if it can be nullptr. Otherwise, and ideally, the function should accept a widget&. These smart pointers match the Shared_pointer concept, so these guideline enforcement rules work on them out of the box and expose

this common pessimization.

R.32: Take a unique_ptr<widget> parameter to express that a function assumes ownership of a widget

Reason

Using unique_ptr in this way both documents and enforces the function call's ownership transfer.

Example

```
void sink(unique_ptr<widget>); // takes ownership of the widget
void uses(widget*); // just uses the widget
```

Example, bad

```
void thinko(const unique_ptr<widget>&); // usually not what you want
```

Enforcement

- (Simple) Warn if a function takes a Unique_pointer<T> parameter by Ivalue reference and does not either assign to it or call reset() on it on at least one code path. Suggest taking a T* or T& instead.
- (Simple) ((Foundation)) Warn if a function takes a Unique_pointer<T> parameter by reference to const. Suggest taking a const T* or const T& instead.

R.33: Take a unique_ptr<widget>& parameter to express that a function reseats the widget

Reason

Using unique_ptr in this way both documents and enforces the function call's reseating semantics.

Note

"reseat" means "making a pointer or a smart pointer refer to a different object."

Example

```
void reseat(unique_ptr<widget>&); // "will" or "might" reseat pointer
```

Example, bad

```
void thinko(const unique_ptr<widget>&); // usually not what you want
```

Enforcement

- (Simple) Warn if a function takes a Unique_pointer<T> parameter by Ivalue reference and does not either assign to it or call reset() on it on at least one code path. Suggest taking a T* or T& instead.
- (Simple) ((Foundation)) Warn if a function takes a Unique_pointer<T> parameter by reference to const. Suggest taking a const T* or const T& instead.

R.34: Take a shared_ptr<widget> parameter to express shared ownership

Reason

This makes the function's ownership sharing explicit.

Example, good

```
class WidgetUser
{
  public:
    // WidgetUser will share ownership of the widget
    explicit WidgetUser(std::shared_ptr<widget> w) noexcept:
        m_widget{std::move(w)} {}
    // ...
private:
    std::shared_ptr<widget> m_widget;
};
```

Enforcement

- (Simple) Warn if a function takes a Shared_pointer<T> parameter by Ivalue reference and does not either assign to it or call reset() on it on at least one code path. Suggest taking a T* or T& instead.
- (Simple) ((Foundation)) Warn if a function takes a Shared_pointer<T> by value or by reference to const and
 does not copy or move it to another Shared_pointer on at least one code path. Suggest taking a T* or T&
 instead.
- (Simple) ((Foundation)) Warn if a function takes a Shared_pointer<T> by rvalue reference. Suggesting taking it by value instead.

R.35: Take a shared_ptr<widget>& parameter to express that a function might reseat the shared pointer

Reason

This makes the function's reseating explicit.

Note

"reseat" means "making a reference or a smart pointer refer to a different object."

Example, good

```
void ChangeWidget(std::shared_ptr<widget>& w)
{
    // This will change the callers widget
    w = std::make_shared<widget>(widget{});
}
```

Enforcement

- (Simple) Warn if a function takes a Shared_pointer<T> parameter by Ivalue reference and does not either assign to it or call reset() on it on at least one code path. Suggest taking a T* or T& instead.
- (Simple) ((Foundation)) Warn if a function takes a Shared_pointer<T> by value or by reference to const and does not copy or move it to another Shared_pointer on at least one code path. Suggest taking a T* or T& instead.
- (Simple) ((Foundation)) Warn if a function takes a Shared_pointer<T> by rvalue reference. Suggesting taking it by value instead.

R.36: Take a const shared_ptr<widget>& parameter to express that it might retain a reference count to the object???

Reason

This makes the function's ??? explicit.

Example, good

- (Simple) Warn if a function takes a Shared_pointer<T> parameter by Ivalue reference and does not either assign to it or call reset() on it on at least one code path. Suggest taking a T* or T& instead.
- (Simple) ((Foundation)) Warn if a function takes a Shared_pointer<T> by value or by reference to const and
 does not copy or move it to another Shared_pointer on at least one code path. Suggest taking a T* or T&
 instead.
- (Simple) ((Foundation)) Warn if a function takes a Shared_pointer<T> by rvalue reference. Suggesting taking it by value instead.

R.37: Do not pass a pointer or reference obtained from an aliased smart pointer

Reason

Violating this rule is the number one cause of losing reference counts and finding yourself with a dangling pointer. Functions should prefer to pass raw pointers and references down call chains. At the top of the call tree where you obtain the raw pointer or reference from a smart pointer that keeps the object alive. You need to be sure that the smart pointer cannot inadvertently be reset or reassigned from within the call tree below.

Note

To do this, sometimes you need to take a local copy of a smart pointer, which firmly keeps the object alive for the duration of the function and the call tree.

Example

Consider this code:

```
// global (static or heap), or aliased local ...
shared_ptr<widget> g_p = ...;

void f(widget& w)
{
    g();
    use(w); // A
}

void g()
{
    g_p = ...; // oops, if this was the last shared_ptr to that widget, destroys the widget
}
```

The following should not pass code review:

```
void my_code()
{
    // BAD: passing pointer or reference obtained from a non-local smart pointer
    // that could be inadvertently reset somewhere inside f or its callees
    f(*g_p);

// BAD: same reason, just passing it as a "this" pointer
    g_p->func();
}
```

The fix is simple -- take a local copy of the pointer to "keep a ref count" for your call tree:

```
void my_code()
{
    // cheap: 1 increment covers this entire function and all the call trees below us
    auto pin = g_p;

    // GOOD: passing pointer or reference obtained from a local unaliased smart pointer
    f(*pin);

    // GOOD: same reason
    pin->func();
}
```

Enforcement

(Simple) Warn if a pointer or reference obtained from a smart pointer variable (Unique_pointer or Shared_pointer) that is non-local, or that is local but potentially aliased, is used in a function call. If the smart pointer is a Shared_pointer then suggest taking a local copy of the smart pointer and obtain a pointer or reference from that instead.

ES: Expressions and statements

Expressions and statements are the lowest and most direct way of expressing actions and computation. Declarations in local scopes are statements.

For naming, commenting, and indentation rules, see NL: Naming and layout.

General rules:

- ES.1: Prefer the standard library to other libraries and to "handcrafted code"
- ES.2: Prefer suitable abstractions to direct use of language features
- ES.3: Don't repeat yourself, avoid redundant code

Declaration rules:

■ ES.5: Keep scopes small

- ES.6: Declare names in for-statement initializers and conditions to limit scope
- ES.7: Keep common and local names short, and keep uncommon and non-local names longer
- ES.8: Avoid similar-looking names
- ES.9: Avoid ALL CAPS names
- ES.10: Declare one name (only) per declaration
- ES.11: Use auto to avoid redundant repetition of type names
- ES.12: Do not reuse names in nested scopes
- ES.20: Always initialize an object
- ES.21: Don't introduce a variable (or constant) before you need to use it
- ES.22: Don't declare a variable until you have a value to initialize it with
- ES.23: Prefer the {}-initializer syntax
- ES.24: Use a unique_ptr<T> to hold pointers
- ES.25: Declare an object const or constexpr unless you want to modify its value later on
- ES.26: Don't use a variable for two unrelated purposes
- ES.27: Use std::array or stack_array for arrays on the stack
- ES.28: Use lambdas for complex initialization, especially of const variables
- ES.30: Don't use macros for program text manipulation
- ES.31: Don't use macros for constants or "functions"
- ES.32: Use ALL CAPS for all macro names
- ES.33: If you must use macros, give them unique names
- ES.34: Don't define a (C-style) variadic function

Expression rules:

- ES.40: Avoid complicated expressions
- ES.41: If in doubt about operator precedence, parenthesize
- ES.42: Keep use of pointers simple and straightforward
- ES.43: Avoid expressions with undefined order of evaluation
- ES.44: Don't depend on order of evaluation of function arguments
- ES.45: Avoid "magic constants"; use symbolic constants
- ES.46: Avoid narrowing conversions
- ES.47: Use nullptr rather than 0 or NULL
- ES.48: Avoid casts
- ES.49: If you must use a cast, use a named cast
- ES.50: Don't cast away const
- ES.55: Avoid the need for range checking
- ES.56: Write std::move() only when you need to explicitly move an object to another scope
- ES.60: Avoid new and delete outside resource management functions
- ES.61: Delete arrays using delete[] and non-arrays using delete
- ES.62: Don't compare pointers into different arrays
- ES.63: Don't slice
- ES.64: Use the T{e}notation for construction
- ES.65: Don't dereference an invalid pointer

Statement rules:

- ES.70: Prefer a switch-statement to an if-statement when there is a choice
- ES.71: Prefer a range-for-statement to a for-statement when there is a choice
- ES.72: Prefer a for-statement to a while-statement when there is an obvious loop variable
- ES.73: Prefer a while-statement to a for-statement when there is no obvious loop variable
- ES.74: Prefer to declare a loop variable in the initializer part of a for-statement

- ES.75: Avoid do-statements
- ES.76: Avoid goto
- ES.77: Minimize the use of break and continue in loops
- ES.78: Don't rely on implicit fallthrough in switch statements
- ES.79: Use default to handle common cases (only)
- ES.84: Don't try to declare a local variable with no name
- ES.85: Make empty statements visible
- ES.86: Avoid modifying loop control variables inside the body of raw for-loops
- ES.87: Don't add redundant == or != to conditions

Arithmetic rules:

- ES.100: Don't mix signed and unsigned arithmetic
- ES.101: Use unsigned types for bit manipulation
- ES.102: Use signed types for arithmetic
- ES.103: Don't overflow
- ES.104: Don't underflow
- ES.105: Don't divide by integer zero
- ES.106: Don't try to avoid negative values by using unsigned
- ES.107: Don't use unsigned for subscripts, prefer gsl::index

ES.1: Prefer the standard library to other libraries and to "handcrafted code"

Reason

Code using a library can be much easier to write than code working directly with language features, much shorter, tend to be of a higher level of abstraction, and the library code is presumably already tested. The ISO C++ Standard Library is among the most widely known and best tested libraries. It is available as part of all C++ implementations.

Example

```
auto sum = accumulate(begin(a), end(a), 0.0); // good
```

a range version of accumulate would be even better:

```
auto sum = accumulate(v, 0.0); // better
```

but don't hand-code a well-known algorithm:

```
int max = v.size();  // bad: verbose, purpose unstated
double sum = 0.0;
for (int i = 0; i < max; ++i)
    sum = sum + v[i];</pre>
```

Exception

Large parts of the standard library rely on dynamic allocation (free store). These parts, notably the containers but not the algorithms, are unsuitable for some hard-real-time and embedded applications. In such cases, consider providing/using similar facilities, e.g., a standard-library-style container implemented using a pool allocator.

Enforcement

Not easy. ??? Look for messy loops, nested loops, long functions, absence of function calls, lack of use of built-in types. Cyclomatic complexity?

ES.2: Prefer suitable abstractions to direct use of language features

Reason

A "suitable abstraction" (e.g., library or class) is closer to the application concepts than the bare language, leads to shorter and clearer code, and is likely to be better tested.

Example

```
vector<string> read1(istream& is) // good
{
    vector<string> res;
    for (string s; is >> s;)
        res.push_back(s);
    return res;
}
```

The more traditional and lower-level near-equivalent is longer, messier, harder to get right, and most likely slower:

```
char** read2(istream& is, int maxelem, int maxstring, int* nread)  // bad: verbose and
incomplete
{
    auto res = new char*[maxelem];
    int elemcount = 0;
    while (is && elemcount < maxelem) {
        auto s = new char[maxstring];
        is.read(s, maxstring);
        res[elemcount++] = s;
    }
    *nread = elemcount;
    return res;
}</pre>
```

Once the checking for overflow and error handling has been added that code gets quite messy, and there is the problem remembering to delete the returned pointer and the C-style strings that array contains.

Not easy. ??? Look for messy loops, nested loops, long functions, absence of function calls, lack of use of built-in types. Cyclomatic complexity?

ES.3: Don't repeat yourself, avoid redundant code

Duplicated or otherwise redundant code obscures intent, makes it harder to understand the logic, and makes maintenance harder, among other problems. It often arises from cut-and-paste programming.

Use standard algorithms where appropriate, instead of writing some own implementation.

See also: SL.1, ES.11

Example

```
void func(bool flag)
                        // Bad, duplicated code.
    if (flag) {
        x();
        y();
    else {
        x();
        z();
    }
}
void func(bool flag) // Better, no duplicated code.
    x();
    if (flag)
        y();
    else
        z();
}
```

Enforcement

- Use a static analyzer. It will catch at least some redundant constructs.
- Code review

ES.dcl: Declarations

A declaration is a statement. A declaration introduces a name into a scope and might cause the construction of a named object.

ES.5: Keep scopes small

Reason

Readability. Minimize resource retention. Avoid accidental misuse of value.

Alternative formulation: Don't declare a name in an unnecessarily large scope.

Example

Example, bad

```
void use(const string& name)
{
    string fn = name + ".txt";
    ifstream is {fn};
    Record r;
    is >> r;
    // ... 200 lines of code without intended use of fn or is ...
}
```

This function is by most measures too long anyway, but the point is that the resources used by fn and the file handle held by is are retained for much longer than needed and that unanticipated use of is and fn could happen later in the function. In this case, it might be a good idea to factor out the read:

```
Record load_record(const string& name)
{
    string fn = name + ".txt";
    ifstream is {fn};
```

```
Record r;
is >> r;
return r;
}

void use(const string& name)
{
    Record r = load_record(name);
    // ... 200 lines of code ...
}
```

- Flag loop variable declared outside a loop and not used after the loop
- Flag when expensive resources, such as file handles and locks are not used for N-lines (for some suitable N)

ES.6: Declare names in for-statement initializers and conditions to limit scope

Reason

Readability. Limit the loop variable visibility to the scope of the loop. Avoid using the loop variable for other purposes after the loop. Minimize resource retention.

Example

```
void use()
{
   for (string s; cin >> s;)
      v.push_back(s);

   for (int i = 0; i < 20; ++i) { // good: i is local to for-loop
      // ...
}

if (auto pc = dynamic_cast<Circle*>(ps)) { // good: pc is local to if-statement
      // ... deal with Circle ...
}
else {
      // ... handle error ...
}
```

Example, don't

See also: Don't use a variable for two unrelated purposes

Enforcement

- Warn when a variable modified inside the for-statement is declared outside the loop and not being used outside the loop.
- (hard) Flag loop variables declared before the loop and used after the loop for an unrelated purpose.

Discussion: Scoping the loop variable to the loop body also helps code optimizers greatly. Recognizing that the induction variable is only accessible in the loop body unblocks optimizations such as hoisting, strength reduction, loop-invariant code motion, etc.

C++17 and C++20 example

Note: C++17 and C++20 also add if, switch, and range-for initializer statements. These require C++17 and C++20 support.

```
map<int, string> mymap;

if (auto result = mymap.insert(value); result.second) {
    // insert succeeded, and result is valid for this block
    use(result.first); // ok
    // ...
} // result is destroyed here
```

C++17 and C++20 enforcement (if using a C++17 or C++20 compiler)

- Flag selection/loop variables declared before the body and not used after the body
- (hard) Flag selection/loop variables declared before the body and used after the body for an unrelated purpose.

ES.7: Keep common and local names short, and keep uncommon and nonlocal names longer

Reason

Readability. Lowering the chance of clashes between unrelated non-local names.

Example

Conventional short, local names increase readability:

An index is conventionally called i and there is no hint about the meaning of the vector in this generic function, so v is as good name as any. Compare

```
template<typename Element_type> // bad: verbose, hard to read
void print(ostream& target_stream, const vector<Element_type>& current_vector)
{
    for (gsl::index current_element_index = 0;
        current_element_index < current_vector.size();
        ++current_element_index
    )
    target_stream << current_vector[current_element_index] << '\n';
}</pre>
```

Yes, it is a caricature, but we have seen worse.

Example

Unconventional and short non-local names obscure code:

```
void use1(const string& s)
{
    // ...
    tt(s);    // bad: what is tt()?
    // ...
}
```

Better, give non-local entities readable names:

Here, there is a chance that the reader knows what trim_tail means and that the reader can remember it after looking it up.

Example, bad

Argument names of large functions are de facto non-local and should be meaningful:

We recommend keeping functions short, but that rule isn't universally adhered to and naming should reflect that.

Enforcement

Check length of local and non-local names. Also take function length into account.

ES.8: Avoid similar-looking names

Reason

Code clarity and readability. Too-similar names slow down comprehension and increase the likelihood of error.

Example, bad

```
if (readable(i1 + l1 + ol + o1 + o0 + ol + o1 + I0 + l0)) surprise();
```

Example, bad

Do not declare a non-type with the same name as a type in the same scope. This removes the need to disambiguate with a keyword such as struct or enum. It also removes a source of errors, as struct X can implicitly declare X if lookup fails.

Exception

Antique header files might declare non-types and types with the same name in the same scope.

- Check names against a list of known confusing letter and digit combinations.
- Flag a declaration of a variable, function, or enumerator that hides a class or enumeration declared in the same scope.

ES.9: Avoid ALL_CAPS names

Reason

Such names are commonly used for macros. Thus, ALL_CAPS name are vulnerable to unintended macro substitution.

Example

```
// somewhere in some header:
#define NE !=

// somewhere else in some other header:
enum Coord { N, NE, NW, S, SE, SW, E, W };

// somewhere third in some poor programmer's .cpp:
switch (direction) {
case N:
    // ...
case NE:
    // ...
// ...
}
```

Note

Do not use ALL_CAPS for constants just because constants used to be macros.

Enforcement

Flag all uses of ALL CAPS. For older code, accept ALL CAPS for macro names and flag all non-ALL-CAPS macro names.

ES.10: Declare one name (only) per declaration

Reason

One declaration per line increases readability and avoids mistakes related to the C/C++ grammar. It also leaves room for a more descriptive end-of-line comment.

Example, bad

```
char *p, c, a[7], *pp[7], **aa[10]; // yuck!
```

Exception

A function declaration can contain several function argument declarations.

Exception

A structured binding (C++17) is specifically designed to introduce several variables:

```
auto [iter, inserted] = m.insert_or_assign(k, val);
if (inserted) { /* new entry was inserted */ }
```

Example

```
template<class InputIterator, class Predicate>
bool any_of(InputIterator first, InputIterator last, Predicate pred);
```

or better using concepts:

```
bool any_of(input_iterator auto first, input_iterator auto last, predicate auto pred);
```

Example

```
double scalbn(double x, int n); // OK: x * pow(FLT_RADIX, n); FLT_RADIX is usually 2
```

or:

or:

```
// better: base * pow(FLT_RADIX, exponent); FLT_RADIX is usually 2
double scalbn(double base, int exponent);
```

Example

```
int a = 10, b = 11, c = 12, d, e = 14, f = 15;
```

In a long list of declarators it is easy to overlook an uninitialized variable.

Enforcement

Flag variable and constant declarations with multiple declarators (e.g., int* p, q;)

ES.11: Use auto to avoid redundant repetition of type names

Reason

- Simple repetition is tedious and error-prone.
- When you use auto, the name of the declared entity is in a fixed position in the declaration, increasing readability.
- In a function template declaration the return type can be a member type.

Example

Consider:

In each case, we save writing a longish, hard-to-remember type that the compiler already knows but a programmer could get wrong.

Example

```
template<class T>
auto Container<T>::first() -> Iterator; // Container<T>::Iterator
```

Exception

Avoid auto for initializer lists and in cases where you know exactly which type you want and where an initializer might require conversion.

Example

```
auto lst = { 1, 2, 3 };  // lst is an initializer list
auto x{1};  // x is an int (in C++17; initializer_list in C++11)
```

Note

As of C++20, we can (and should) use concepts to be more specific about the type we are deducing:

```
// ...
forward_iterator auto p = algo(x, y, z);
```

Example (C++17)

```
std::set<int> values;
// ...
auto [ position, newly_inserted ] = values.insert(5); // break out the members of the
std::pair
```

Enforcement

Flag redundant repetition of type names in a declaration.

ES.12: Do not reuse names in nested scopes

Reason

It is easy to get confused about which variable is used. Can cause maintenance problems.

Example, bad

```
int d = 0;
// ...
if (cond) {
    // ...
    d = 9;
    // ...
}
else {
    // ...
    int d = 7;
    // ...
    d = value_to_be_returned;
    // ...
}
```

```
return d;
```

If this is a large if-statement, it is easy to overlook that a new d has been introduced in the inner scope. This is a known source of bugs. Sometimes such reuse of a name in an inner scope is called "shadowing".

Note

Shadowing is primarily a problem when functions are too large and too complex.

Example

Shadowing of function arguments in the outermost block is disallowed by the language:

```
void f(int x)
{
  int x = 4; // error: reuse of function argument name

if (x) {
  int x = 7; // allowed, but bad
  // ...
}
```

Example, bad

Reuse of a member name as a local variable can also be a problem:

Exception

We often reuse function names from a base class in a derived class:

```
struct B {
    void f(int);
};

struct D : B {
    void f(double);
    using B::f;
};
```

This is error-prone. For example, had we forgotten the using declaration, a call d.f(1) would not have found the int version of f.

??? Do we need a specific rule about shadowing/hiding in class hierarchies?

Enforcement

- Flag reuse of a name in nested local scopes
- Flag reuse of a member name as a local variable in a member function
- Flag reuse of a global name as a local variable or a member name
- Flag reuse of a base class member name in a derived class (except for function names)

ES.20: Always initialize an object

Reason

Avoid used-before-set errors and their associated undefined behavior. Avoid problems with comprehension of complex initialization. Simplify refactoring.

Example

```
void use(int arg)
{
   int i; // bad: uninitialized variable
   // ...
   i = 7; // initialize i
}
```

No, i = 7 does not initialize i; it assigns to it. Also, i can be read in the ... part. Better:

```
void use(int arg) // OK
{
   int i = 7; // OK: initialized
   string s; // OK: default initialized
   // ...
}
```

Note

The *always initialize* rule is deliberately stronger than the *an object must be set before used* language rule. The latter, more relaxed rule, catches the technical bugs, but:

- It leads to less readable code
- It encourages people to declare names in greater than necessary scopes
- It leads to harder to read code
- It leads to logic bugs by encouraging complex code
- It hampers refactoring

The *always initialize* rule is a style rule aimed to improve maintainability as well as a rule protecting against used-before-set errors.

Example

Here is an example that is often considered to demonstrate the need for a more relaxed rule for initialization

```
widget i;  // "widget" a type that's expensive to initialize, possibly a large trivial type
widget j;

if (cond) {    // bad: i and j are initialized "late"
    i = f1();
    j = f2();
}
else {
    i = f3();
    j = f4();
}
```

This cannot trivially be rewritten to initialize i and j with initializers. Note that for types with a default constructor, attempting to postpone initialization simply leads to a default initialization followed by an assignment. A popular reason for such examples is "efficiency", but a compiler that can detect whether we made a used-before-set error can also eliminate any redundant double initialization.

Assuming that there is a logical connection between i and j, that connection should probably be expressed in code:

```
pair<widget, widget> make_related_widgets(bool x)
{
    return (x) ? {f1(), f2()} : {f3(), f4()};
}
auto [i, j] = make_related_widgets(cond); // C++17
```

If the make_related_widgets function is otherwise redundant, we can eliminate it by using a lambda ES.28:

```
auto [i, j] = [x] { return (x) ? pair{f1(), f2()} : pair{f3(), f4()} }(); // C++17
```

Using a value representing "uninitialized" is a symptom of a problem and not a solution:

Now the compiler cannot even simply detect a used-before-set. Further, we've introduced complexity in the state space for widget: which operations are valid on an uninit widget and which are not?

Note

Complex initialization has been popular with clever programmers for decades. It has also been a major source of errors and complexity. Many such errors are introduced during maintenance years after the initial implementation.

Example

This rule covers member variables.

```
class X {
public:
    X(int i, int ci) : m2{i}, cm2{ci} {}
    // ...

private:
    int m1 = 7;
    int m2;
    int m3;

    const int cm1 = 7;
    const int cm2;
    const int cm3;
};
```

The compiler will flag the uninitialized cm3 because it is a const, but it will not catch the lack of initialization of m3. Usually, a rare spurious member initialization is worth the absence of errors from lack of initialization and often an optimizer can eliminate a redundant initialization (e.g., an initialization that occurs immediately before an assignment).

Exception

If you are declaring an object that is just about to be initialized from input, initializing it would cause a double initialization. However, beware that this might leave uninitialized data beyond the input -- and that has been a fertile source of errors and security breaches:

The cost of initializing that array could be significant in some situations. However, such examples do tend to leave uninitialized variables accessible, so they should be treated with suspicion.

```
constexpr int max = 8 * 1024;
int buf[max] = {};  // zero all elements; better in some situations
f.read(buf, max);
```

Because of the restrictive initialization rules for arrays and std::array, they offer the most compelling examples of the need for this exception.

When feasible use a library function that is known not to overflow. For example:

```
string s; // s is default initialized to ""
cin >> s; // s expands to hold the string
```

Don't consider simple variables that are targets for input operations exceptions to this rule:

```
int i; // bad
// ...
cin >> i;
```

In the not uncommon case where the input target and the input operation get separated (as they should not) the possibility of used-before-set opens up.

```
int i2 = 0;  // better, assuming that zero is an acceptable value for i2
// ...
cin >> i2;
```

A good optimizer should know about input operations and eliminate the redundant operation.

Note

Sometimes, a lambda can be used as an initializer to avoid an uninitialized variable:

or maybe:

See also: ES.28

Enforcement

- Flag every uninitialized variable. Don't flag variables of user-defined types with default constructors.
- Check that an uninitialized buffer is written into *immediately* after declaration. Passing an uninitialized variable as a reference to non-const argument can be assumed to be a write into the variable.

ES.21: Don't introduce a variable (or constant) before you need to use it

Reason

Readability. To limit the scope in which the variable can be used.

Example

```
int x = 7;
// ... no use of x here ...
++x;
```

Enforcement

Flag declarations that are distant from their first use.

ES.22: Don't declare a variable until you have a value to initialize it with

Reason

Readability. Limit the scope in which a variable can be used. Don't risk used-before-set. Initialization is often more efficient than assignment.

Example, bad

```
string s;
// ... no use of s here ...
s = "what a waste";
```

Example, bad

```
SomeLargeType var; // Hard-to-read CaMeLcAsEvArIaBlE

if (cond) // some non-trivial condition
    Set(&var);
else if (cond2 || !cond3) {
    var = Set2(3.14);
}
else {
    var = 0;
    for (auto& e : something)
        var += e;
}

// use var; that this isn't done too early can be enforced statically with only control flow
```

This would be fine if there was a default initialization for SomeLargeType that wasn't too expensive. Otherwise, a programmer might very well wonder if every possible path through the maze of conditions has been covered. If not, we have a "use before set" bug. This is a maintenance trap.

For initializers of moderate complexity, including for const variables, consider using a lambda to express the initializer; see ES.28.

Enforcement

- Flag declarations with default initialization that are assigned to before they are first read.
- Flag any complicated computation after an uninitialized variable and before its use.

ES.23: Prefer the {}-initializer syntax

Reason

Prefer {}. The rules for {} initialization are simpler, more general, less ambiguous, and safer than for other forms of initialization.

Use = only when you are sure that there can be no narrowing conversions. For built-in arithmetic types, use = only with auto.

Avoid () initialization, which allows parsing ambiguities.

Example

```
int x {f(99)};
int y = x;
vector<int> v = {1, 2, 3, 4, 5, 6};
```

Exception

For containers, there is a tradition for using $\{\ldots\}$ for a list of elements and (\ldots) for sizes:

```
vector<int> v1(10);  // vector of 10 elements with the default value 0
vector<int> v2{10};  // vector of 1 element with the value 10

vector<int> v3(1, 2);  // vector of 1 element with the value 2
vector<int> v4{1, 2};  // vector of 2 elements with the values 1 and 2
```

Note

{}-initializers do not allow narrowing conversions (and that is usually a good thing) and allow explicit constructors (which is fine, we're intentionally initializing a new variable).

Example

```
int x {7.9};  // error: narrowing
int y = 7.9;  // OK: y becomes 7. Hope for a compiler warning
int z {gsl::narrow_cast<int>(7.9)};  // OK: you asked for it
auto zz = gsl::narrow_cast<int>(7.9);  // OK: you asked for it
```

Note

{} initialization can be used for nearly all initialization; other forms of initialization can't:

```
auto p = new vector<int> {1, 2, 3, 4, 5};  // initialized vector
D::D(int a, int b) :m{a, b} {    // member initializer (e.g., m might be a pair)
    // ...
};
X var {};  // initialize var to be empty
struct S {
    int m {7};    // default initializer for a member
    // ...
};
```

For that reason, {}-initialization is often called "uniform initialization" (though there unfortunately are a few irregularities left).

Note

Initialization of a variable declared using auto with a single value, e.g., $\{v\}$, had surprising results until C++17. The C++17 rules are somewhat less surprising:

Use ={...} if you really want an initializer_list<T>

```
auto fib10 = {1, 1, 2, 3, 5, 8, 13, 21, 34, 55}; // fib10 is a list
```

Note

={} gives copy initialization whereas {} gives direct initialization. Like the distinction between copy-initialization and direct-initialization itself, this can lead to surprises. {} accepts explicit constructors; ={} does not. For example:

```
struct Z { explicit Z() {} };

Z z1{};  // OK: direct initialization, so we use explicit constructor
Z z2 = {};  // error: copy initialization, so we cannot use the explicit constructor
```

Use plain {}-initialization unless you specifically want to disable explicit constructors.

Example

```
template<typename T>
void f()
{
    T x1(1);    // T initialized with 1
    T x0();    // bad: function declaration (often a mistake)

    T y1 {1};    // T initialized with 1
    T y0 {};    // default initialized T
    // ...
}
```

See also: Discussion

Enforcement

- Flag uses of = to initialize arithmetic types where narrowing occurs.
- Flag uses of () initialization syntax that are actually declarations. (Many compilers should warn on this already.)

ES.24: Use a unique_ptr<T> to hold pointers

Reason

Using std::unique_ptr is the simplest way to avoid leaks. It is reliable, it makes the type system do much of the work to validate ownership safety, it increases readability, and it has zero or near zero run-time cost.

Example

If leak == true the object pointed to by p2 is leaked and the object pointed to by p1 is not. The same is the case when at() throws. In both cases, the delete p2 statement is not reached.

Enforcement

Look for raw pointers that are targets of new, malloc(), or functions that might return such pointers.

ES.25: Declare an object const or constexpr unless you want to modify its value later on

Reason

That way you can't change the value by mistake. That way might offer the compiler optimization opportunities.

Example

```
void f(int n)
{
   const int bufmax = 2 * n + 2; // good: we can't change bufmax by accident
   int xmax = n; // suspicious: is xmax intended to change?
   // ...
}
```

Enforcement

Look to see if a variable is actually mutated, and flag it if not. Unfortunately, it might be impossible to detect when a non-const was not *intended* to vary (vs when it merely did not vary).

ES.26: Don't use a variable for two unrelated purposes

Reason

Readability and safety.

Example, bad

```
void use()
{
   int i;
   for (i = 0; i < 20; ++i) { /* ... */ }
   for (i = 0; i < 200; ++i) { /* ... */ } // bad: i recycled
}</pre>
```

Note

As an optimization, you might want to reuse a buffer as a scratch pad, but even then prefer to limit the variable's scope as much as possible and be careful not to cause bugs from data left in a recycled buffer as this is a common source of security bugs.

Enforcement

Flag recycled variables.

ES.27: Use std::array or stack_array for arrays on the stack

Reason

They are readable and don't implicitly convert to pointers. They are not confused with non-standard extensions of built-in arrays.

Example, bad

Note

The definition of a1 is legal C++ and has always been. There is a lot of such code. It is error-prone, though, especially when the bound is non-local. Also, it is a "popular" source of errors (buffer overflow, pointers from array decay, etc.). The definition of a2 is C but not C++ and is considered a security risk

Example

```
const int n = 7;
int m = 9;

void f()
{
    array<int, n> a1;
    stack_array<int> a2(m);
    // ...
}
```

Enforcement

- Flag arrays with non-constant bounds (C-style VLAs)
- Flag arrays with non-local constant bounds

ES.28: Use lambdas for complex initialization, especially of const variables

Reason

It nicely encapsulates local initialization, including cleaning up scratch variables needed only for the initialization, without needing to create a needless non-local yet non-reusable function. It also works for variables that should be const but only after some initialization work.

Example, bad

Example, good

If at all possible, reduce the conditions to a simple set of alternatives (e.g., an enum) and don't mix up selection and initialization.

Enforcement

Hard. At best a heuristic. Look for an uninitialized variable followed by a loop assigning to it.

ES.30: Don't use macros for program text manipulation

Reason

Macros are a major source of bugs. Macros don't obey the usual scope and type rules. Macros ensure that the human reader sees something different from what the compiler sees. Macros complicate tool building.

Example, bad

```
#define Case break; case /* BAD */
```

This innocuous-looking macro makes a single lower case c instead of a C into a bad flow-control bug.

Note

This rule does not ban the use of macros for "configuration control" use in #ifdefs, etc.

In the future, modules are likely to eliminate the need for macros in configuration control.

Note

This rule is meant to also discourage use of # for stringification and ## for concatenation. As usual for macros, there are uses that are "mostly harmless", but even these can create problems for tools, such as auto completers, static analyzers, and debuggers. Often the desire to use fancy macros is a sign of an overly complex design. Also, # and ## encourages the definition and use of macros:

```
#define CAT(a, b) a ## b
#define STRINGIFY(a) #a

void f(int x, int y)
{
    string CAT(x, y) = "asdf"; // BAD: hard for tools to handle (and ugly)
    string sx2 = STRINGIFY(x);
    // ...
}
```

There are workarounds for low-level string manipulation using macros. For example:

```
enum E { a, b };

template<int x>
constexpr const char* stringify()
{
    switch (x) {
    case a: return "a";
    case b: return "b";
    }
}

void f()
{
    string s1 = stringify<a>();
    string s2 = stringify<b>();
    // ...
}
```

This is not as convenient as a macro to define, but as easy to use, has zero overhead, and is typed and scoped.

In the future, static reflection is likely to eliminate the last needs for the preprocessor for program text manipulation.

Enforcement

Scream when you see a macro that isn't just used for source control (e.g., #ifdef)

ES.31: Don't use macros for constants or "functions"

Reason

Macros are a major source of bugs. Macros don't obey the usual scope and type rules. Macros don't obey the usual rules for argument passing. Macros ensure that the human reader sees something different from what the compiler sees. Macros complicate tool building.

Example, bad

```
#define PI 3.14
#define SQUARE(a, b) (a * b)
```

Even if we hadn't left a well-known bug in SQUARE there are much better behaved alternatives; for example:

```
constexpr double pi = 3.14;
template<typename T> T square(T a, T b) { return a * b; }
```

Enforcement

Scream when you see a macro that isn't just used for source control (e.g., #ifdef)

ES.32: Use ALL_CAPS for all macro names

Reason

Convention. Readability. Distinguishing macros.

Example

```
#define forever for (;;) /* very BAD */
#define FOREVER for (;;) /* Still evil, but at least visible to humans */
```

Enforcement

Scream when you see a lower case macro.

ES.33: If you must use macros, give them unique names

Reason

Macros do not obey scope rules.

Example

Note

Avoid macros if you can: ES.30, ES.31, and ES.32. However, there are billions of lines of code littered with macros and a long tradition for using and overusing macros. If you are forced to use macros, use long names and supposedly unique prefixes (e.g., your organization's name) to lower the likelihood of a clash.

Enforcement

Warn against short macro names.

ES.34: Don't define a (C-style) variadic function

Reason

Not type safe. Requires messy cast-and-macro-laden code to get working right.

Example

```
#include <cstdarg>
// "severity" followed by a zero-terminated list of char*s; write the C-style strings to cerr
void error(int severity ...)
{
   va list ap;
                            // a magic type for holding arguments
   va_start(ap, severity); // arg startup: "severity" is the first argument of error()
   for (;;) {
        // treat the next var as a char*; no checking: a cast in disguise
        char* p = va_arg(ap, char*);
        if (!p) break;
        cerr << p << ' ';
    }
   va_end(ap);
                           // arg cleanup (don't forget this)
   cerr << '\n';</pre>
   if (severity) exit(severity);
}
void use()
{
   error(7, "this", "is", "an", "error", nullptr);
   error(7); // crash
   error(7, "this", "is", "an", "error"); // crash
    const char* is = "is";
    string an = "an";
   error(7, "this", is, an, "error"); // crash
}
```

Alternative: Overloading. Templates. Variadic templates.

```
#include <iostream>
void error(int severity)
    std::cerr << '\n';
    std::exit(severity);
}
template<typename T, typename... Ts>
constexpr void error(int severity, T head, Ts... tail)
    std::cerr << head;</pre>
    error(severity, tail...);
}
void use()
{
    error(7); // No crash!
    error(5, "this", "is", "not", "an", "error"); // No crash!
    std::string an = "an";
    error(7, "this", "is", "not", an, "error"); // No crash!
   error(5, "oh", "no", nullptr); // Compile error! No need for nullptr.
}
```

Note

This is basically the way printf is implemented.

Enforcement

- Flag definitions of C-style variadic functions.
- Flag #include <cstdarg> and #include <stdarg.h>

ES.expr: Expressions

Expressions manipulate values.

ES.40: Avoid complicated expressions

Reason

Complicated expressions are error-prone.

Example

```
// bad: assignment hidden in subexpression
while ((c = getc()) != -1)
// bad: two non-local variables assigned in sub-expressions
while ((cin >> c1, cin >> c2), c1 == c2)
// better, but possibly still too complicated
for (char c1, c2; cin >> c1 >> c2 && c1 == c2;)
// OK: if i and j are not aliased
int x = ++i + ++j;
// OK: if i != j and i != k
v[i] = v[j] + v[k];
// bad: multiple assignments "hidden" in subexpressions
x = a + (b = f()) + (c = g()) * 7;
// bad: relies on commonly misunderstood precedence rules
x = a \& b + c * d \&\& e ^ f == 7;
// bad: undefined behavior
X = X++ + X++ + ++X;
```

Some of these expressions are unconditionally bad (e.g., they rely on undefined behavior). Others are simply so complicated and/or unusual that even good programmers could misunderstand them or overlook a problem when in a hurry.

Note

C++17 tightens up the rules for the order of evaluation (left-to-right except right-to-left in assignments, and the order of evaluation of function arguments is unspecified; see ES.43), but that doesn't change the fact that complicated expressions are potentially confusing.

Note

A programmer should know and use the basic rules for expressions.

Example

Enforcement

Tricky. How complicated must an expression be to be considered complicated? Writing computations as statements with one operation each is also confusing. Things to consider:

- side effects: side effects on multiple non-local variables (for some definition of non-local) can be suspect, especially if the side effects are in separate subexpressions
- writes to aliased variables
- more than N operators (and what should N be?)
- reliance of subtle precedence rules
- uses undefined behavior (can we catch all undefined behavior?)
- implementation defined behavior?
- ???

ES.41: If in doubt about operator precedence, parenthesize

Reason

Avoid errors. Readability. Not everyone has the operator table memorized.

Example

```
const unsigned int flag = 2;
unsigned int a = flag;
if (a & flag != 0) // bad: means a&(flag != 0)
```

Note: We recommend that programmers know their precedence table for the arithmetic operations, the logical operations, but consider mixing bitwise logical operations with other operators in need of parentheses.

```
if ((a & flag) != 0) // OK: works as intended
```

Note

You should know enough not to need parentheses for:

```
if (a < 0 || a <= max) {
    // ...
}</pre>
```

Enforcement

- Flag combinations of bitwise-logical operators and other operators.
- Flag assignment operators not as the leftmost operator.
- = ???

ES.42: Keep use of pointers simple and straightforward

Reason

Complicated pointer manipulation is a major source of errors.

Note

Use gsl::span instead. Pointers should only refer to single objects. Pointer arithmetic is fragile and easy to get wrong, the source of many, many bad bugs and security violations. span is a bounds-checked, safe type for accessing arrays of data. Access into an array with known bounds using a constant as a subscript can be validated by the compiler.

Example, bad

```
use(&p[0], 3); // BAD
}
```

Example, good

Note

Subscripting with a variable is difficult for both tools and humans to validate as safe. span is a run-time bounds-checked, safe type for accessing arrays of data. at() is another alternative that ensures single accesses are bounds-checked. If iterators are needed to access an array, use the iterators from a span constructed over the array.

Example, bad

```
void f(array<int, 10> a, int pos)
{
    a[pos / 2] = 1; // BAD
    a[pos - 1] = 2; // BAD
    a[-1] = 3; // BAD (but easily caught by tools) -- no replacement, just don't do this
    a[10] = 4; // BAD (but easily caught by tools) -- no replacement, just don't do this
}
```

Example, good

Use a span:

```
void f1(span<int, 10> a, int pos) // A1: Change parameter type to use span
{
    a[pos / 2] = 1; // OK
    a[pos - 1] = 2; // OK
}

void f2(array<int, 10> arr, int pos) // A2: Add local span and use that
{
    span<int> a = {arr.data(), pos};
    a[pos / 2] = 1; // OK
    a[pos - 1] = 2; // OK
}
```

Use at():

```
void f3(array<int, 10> a, int pos) // ALTERNATIVE B: Use at() for access
{
    at(a, pos / 2) = 1; // OK
    at(a, pos - 1) = 2; // OK
}
```

Example, bad

```
void f()
{
   int arr[COUNT];
   for (int i = 0; i < COUNT; ++i)
      arr[i] = i; // BAD, cannot use non-constant indexer
}</pre>
```

Example, good

Use a span:

```
void f1()
{
    int arr[COUNT];
    span<int> av = arr;
    for (int i = 0; i < COUNT; ++i)
        av[i] = i;
}</pre>
```

Use a span and range-for:

```
void f1a()
{
    int arr[COUNT];
    span<int, COUNT> av = arr;
    int i = 0;
    for (auto& e : av)
        e = i++;
}
```

Use at() for access:

```
void f2()
{
   int arr[COUNT];
   for (int i = 0; i < COUNT; ++i)
      at(arr, i) = i;
}</pre>
```

Use a range-for:

```
void f3()
{
   int arr[COUNT];
   int i = 0;
   for (auto& e : arr)
        e = i++;
}
```

Note

Tooling can offer rewrites of array accesses that involve dynamic index expressions to use at() instead:

Example

Turning an array into a pointer (as the language does essentially always) removes opportunities for checking, so avoid it

If you want to pass an array, say so:

```
void g(int* p, size_t length); // old (dangerous) code

void g1(span<int> av); // BETTER: get g() changed.

void f2()
{
   int a[5];
   span<int> av = a;

   g(av.data(), av.size()); // OK, if you have no choice
   g1(a); // OK -- no decay here, instead use implicit span ctor
}
```

Enforcement

- Flag any arithmetic operation on an expression of pointer type that results in a value of pointer type.
- Flag any indexing expression on an expression or variable of array type (either static array or std::array) where the indexer is not a compile-time constant expression with a value between 0 and the upper bound of the array.
- Flag any expression that would rely on implicit conversion of an array type to a pointer type.

This rule is part of the bounds-safety profile.

ES.43: Avoid expressions with undefined order of evaluation

Reason

You have no idea what such code does. Portability. Even if it does something sensible for you, it might do something different on another compiler (e.g., the next release of your compiler) or with a different optimizer setting.

Note

C++17 tightens up the rules for the order of evaluation: left-to-right except right-to-left in assignments, and the order of evaluation of function arguments is unspecified.

However, remember that your code might be compiled with a pre-C++17 compiler (e.g., through cut-and-paste) so don't be too clever.

Example

```
v[i] = ++i; // the result is undefined
```

A good rule of thumb is that you should not read a value twice in an expression where you write to it.

Enforcement

Can be detected by a good analyzer.

ES.44: Don't depend on order of evaluation of function arguments

Reason

Because that order is unspecified.

Note

C++17 tightens up the rules for the order of evaluation, but the order of evaluation of function arguments is still unspecified.

Example

```
int i = 0;
f(++i, ++i);
```

Before C++17, the behavior is undefined, so the behavior could be anything (e.g., f(2, 2)). Since C++17, this code does not have undefined behavior, but it is still not specified which argument is evaluated first. The call will be f(1, 2) or f(2, 1), but you don't know which.

Example

Overloaded operators can lead to order of evaluation problems:

```
f1()->m(f2());  // m(f1(), f2())
cout << f1() << f2();  // operator<<(cout, f1()), f2())
```

In C++17, these examples work as expected (left to right) and assignments are evaluated right to left (just as ='s binding is right-to-left)

```
f1() = f2(); // undefined behavior in C++14; in C++17, f2() is evaluated before f1()
```

Enforcement

Can be detected by a good analyzer.

ES.45: Avoid "magic constants"; use symbolic constants

Reason

Unnamed constants embedded in expressions are easily overlooked and often hard to understand:

Example

```
for (int m = 1; m <= 12; ++m)  // don't: magic constant 12
  cout << month[m] << '\n';</pre>
```

No, we don't all know that there are 12 months, numbered 1..12, in a year. Better:

```
// months are indexed 1..12
constexpr int first_month = 1;
constexpr int last_month = 12;

for (int m = first_month; m <= last_month; ++m) // better
    cout << month[m] << '\n';</pre>
```

Better still, don't expose constants:

```
for (auto m : month)
  cout << m << '\n';</pre>
```

Enforcement

Flag literals in code. Give a pass to 0, 1, nullptr, \n, "", and others on a positive list.

ES.46: Avoid lossy (narrowing, truncating) arithmetic conversions

Reason

A narrowing conversion destroys information, often unexpectedly so.

Example, bad

A key example is basic narrowing:

```
double d = 7.9;
int i = d;  // bad: narrowing: i becomes 7
i = (int) d;  // bad: we're going to claim this is still not explicit enough

void f(int x, long y, double d)
{
   char c1 = x;  // bad: narrowing
   char c2 = y;  // bad: narrowing
   char c3 = d;  // bad: narrowing
}
```

Note

The guidelines support library offers a narrow_cast operation for specifying that narrowing is acceptable and a narrow ("narrow if") that throws an exception if a narrowing would throw away legal values:

```
i = gsl::narrow_cast<int>(d);  // OK (you asked for it): narrowing: i becomes 7
i = gsl::narrow<int>(d);  // OK: throws narrowing_error
```

We also include lossy arithmetic casts, such as from a negative floating point type to an unsigned integral type:

Note

This rule does not apply to contextual conversions to bool:

```
if (ptr) do_something(*ptr);  // OK: ptr is used as a condition
bool b = ptr;  // bad: narrowing
```

Enforcement

A good analyzer can detect all narrowing conversions. However, flagging all narrowing conversions will lead to a lot of false positives. Suggestions:

• Flag all floating-point to integer conversions (maybe only float->char and double->int. Here be dragons! we need data).

- Flag all long->char (I suspect int->char is very common. Here be dragons! we need data).
- Consider narrowing conversions for function arguments especially suspect.

ES.47: Use nullptr rather than 0 or NULL

Reason

Readability. Minimize surprises: nullptr cannot be confused with an int. nullptr also has a well-specified (very restrictive) type, and thus works in more scenarios where type deduction might do the wrong thing on NULL or 0.

Example

Consider:

```
void f(int);
void f(char*);
f(0);    // call f(int)
f(nullptr);    // call f(char*)
```

Enforcement

Flag uses of 0 and NULL for pointers. The transformation might be helped by simple program transformation.

ES.48: Avoid casts

Reason

Casts are a well-known source of errors and make some optimizations unreliable.

Example, bad

```
double d = 2;
auto p = (long*)&d;
auto q = (long long*)&d;
cout << d << ' ' << *p << ' \n';</pre>
```

What would you think this fragment prints? The result is at best implementation defined. I got

```
2 0 4611686018427387904
```

Adding

```
*q = 666;
cout << d << ' ' << *p << ' ' ' << *q << '\n';
```

I got

```
3.29048e-321 666 666
```

Surprised? I'm just glad I didn't crash the program.

Note

Programmers who write casts typically assume that they know what they are doing, or that writing a cast makes the program "easier to read". In fact, they often disable the general rules for using values. Overload resolution and template instantiation usually pick the right function if there is a right function to pick. If there is not, maybe there ought to be, rather than applying a local fix (cast).

Notes

Casts are necessary in a systems programming language. For example, how else would we get the address of a device register into a pointer? However, casts are seriously overused as well as a major source of errors.

If you feel the need for a lot of casts, there might be a fundamental design problem.

The type profile bans reinterpret_cast and C-style casts.

Never cast to (void) to ignore a [[nodiscard]] return value. If you deliberately want to discard such a result, first think hard about whether that is really a good idea (there is usually a good reason the author of the function or of the return type used [[nodiscard]] in the first place). If you still think it's appropriate and your code reviewer agrees, use std::ignore = to turn off the warning which is simple, portable, and easy to grep.

Alternatives

Casts are widely (mis)used. Modern C++ has rules and constructs that eliminate the need for casts in many contexts, such as

- Use templates
- Use std::variant
- Rely on the well-defined, safe, implicit conversions between pointer types
- Use std::ignore = to ignore [[nodiscard]] values.

Enforcement

- Flag all C-style casts, including to void.
- Flag functional style casts using Type(value). Use Type{value} instead which is not narrowing. (See ES.64.)
- Flag identity casts between pointer types, where the source and target types are the same (#Pro-type-identitycast).
- Flag an explicit pointer cast that could be implicit.

ES.49: If you must use a cast, use a named cast

Reason

Readability. Error avoidance. Named casts are more specific than a C-style or functional cast, allowing the compiler to catch some errors.

The named casts are:

```
static_cast
```

- const_cast
- reinterpret_cast
- dynamic_cast
- std::move // move(x) is an rvalue reference to x
- std::forward // forward<T>(x) is an rvalue or an lvalue reference to x depending on T
- gsl::narrow_cast // narrow_cast<T>(x) is static_cast<T>(x)
- gsl::narrow // narrow<T>(x) is static_cast<T>(x) if static_cast<T>(x) == x or it throws narrowing_error

Example

The example was synthesized from real-world bugs where D used to be derived from B, but someone refactored the hierarchy. The C-style cast is dangerous because it can do any kind of conversion, depriving us of any protection from mistakes (now or in the future).

Note

When converting between types with no information loss (e.g. from float to double or from int32 to int64), brace initialization might be used instead.

```
double d {some_float};
int64_t i {some_int32};
```

This makes it clear that the type conversion was intended and also prevents conversions between types that might result in loss of precision. (It is a compilation error to try to initialize a float from a double in this fashion, for example.)

Note

reinterpret_cast can be essential, but the essential uses (e.g., turning a machine address into pointer) are not type safe:

```
auto p = reinterpret_cast<Device_register>(0x800); // inherently dangerous
```

Enforcement

- Flag all C-style casts, including to void.
- Flag functional style casts using Type(value). Use Type(value) instead which is not narrowing. (See ES.64.)
- The type profile bans reinterpret_cast.
- The type profile warns when using static_cast between arithmetic types.

ES.50: Don't cast away const

Reason

It makes a lie out of const. If the variable is actually declared const, modifying it results in undefined behavior.

Example, bad

```
void f(const int& x)
{
    const_cast<int&>(x) = 42; // BAD
}

static int i = 0;
static const int j = 0;

f(i); // silent side effect
f(j); // undefined behavior
```

Example

Sometimes, you might be tempted to resort to const_cast to avoid code duplication, such as when two accessor functions that differ only in const-ness have similar implementations. For example:

```
class Bar;

class Foo {
public:
    // BAD, duplicates logic
    Bar& get_bar()
    {
        /* complex logic around getting a non-const reference to my_bar */
}
```

```
const Bar& get_bar() const
{
     /* same complex logic around getting a const reference to my_bar */
}
private:
    Bar my_bar;
};
```

Instead, prefer to share implementations. Normally, you can just have the non-const function call the const function. However, when there is complex logic this can lead to the following pattern that still resorts to a const_cast:

```
class Foo {
public:
    // not great, non-const calls const version but resorts to const_cast
    Bar& get_bar()
    {
        return const_cast<Bar&>(static_cast<const Foo&>(*this).get_bar());
    }
    const Bar& get_bar() const
    {
        /* the complex logic around getting a const reference to my_bar */
    }
private:
    Bar my_bar;
};
```

Although this pattern is safe when applied correctly, because the caller must have had a non-const object to begin with, it's not ideal because the safety is hard to enforce automatically as a checker rule.

Instead, prefer to put the common code in a common helper function -- and make it a template so that it deduces const. This doesn't use any const_cast at all:

Note: Don't do large non-dependent work inside a template, which leads to code bloat. For example, a further improvement would be if all or part of get_bar_impl can be non-dependent and factored out into a common non-template function, for a potentially big reduction in code size.

Exception

You might need to cast away const when calling const-incorrect functions. Prefer to wrap such functions in inline const-correct wrappers to encapsulate the cast in one place.

Example

Sometimes, "cast away const" is to allow the updating of some transient information of an otherwise immutable object. Examples are caching, memoization, and precomputation. Such examples are often handled as well or better using mutable or an indirection than with a const_cast.

Consider keeping previously computed results around for a costly operation:

```
int compute(int x); // compute a value for x; assume this to be costly
class Cache { // some type implementing a cache for an int->int operation
public:
   pair<bool, int> find(int x) const; // is there a value for x?
   void set(int x, int v);
                                        // make y the value for x
   // ...
private:
   // ...
};
class X {
public:
   int get_val(int x)
        auto p = cache.find(x);
        if (p.first) return p.second;
        int val = compute(x);
        cache.set(x, val); // insert value for x
        return val;
    }
   // ...
private:
   Cache cache;
};
```

Here, get_val() is logically constant, so we would like to make it a const member. To do this we still need to mutate cache, so people sometimes resort to a const cast:

```
class X {     // Suspicious solution based on casting
public:
    int get_val(int x) const
    {
        auto p = cache.find(x);
        if (p.first) return p.second;
        int val = compute(x);
        const_cast<Cache&>(cache).set(x, val);     // ugly
        return val;
```

```
}
// ...
private:
   Cache cache;
};
```

Fortunately, there is a better solution: State that cache is mutable even for a const object:

```
class X {  // better solution
public:
    int get_val(int x) const
    {
        auto p = cache.find(x);
        if (p.first) return p.second;
        int val = compute(x);
        cache.set(x, val);
        return val;
    }
    // ...
private:
    mutable Cache cache;
};
```

An alternative solution would be to store a pointer to the cache:

```
class X {  // OK, but slightly messier solution
public:
    int get_val(int x) const
    {
        auto p = cache->find(x);
        if (p.first) return p.second;
        int val = compute(x);
        cache->set(x, val);
        return val;
    }
    // ...
private:
    unique_ptr<Cache> cache;
};
```

That solution is the most flexible, but requires explicit construction and destruction of *cache (most likely in the constructor and destructor of X).

In any variant, we must guard against data races on the cache in multi-threaded code, possibly using a std::mutex.

Enforcement

- Flag const_casts.
- This rule is part of the type-safety profile for the related Profile.

ES.55: Avoid the need for range checking

Reason

Constructs that cannot overflow do not overflow (and usually run faster):

Example

Enforcement

Look for explicit range checks and heuristically suggest alternatives.

ES.56: Write std::move() only when you need to explicitly move an object to another scope

Reason

We move, rather than copy, to avoid duplication and for improved performance.

A move typically leaves behind an empty object (C.64), which can be surprising or even dangerous, so we try to avoid moving from lyalues (they might be accessed later).

Notes

Moving is done implicitly when the source is an rvalue (e.g., value in a return treatment or a function result), so don't pointlessly complicate code in those cases by writing move explicitly. Instead, write short functions that return values, and both the function's return and the caller's accepting of the return will be optimized naturally.

In general, following the guidelines in this document (including not making variables' scopes needlessly large, writing short functions that return values, returning local variables) help eliminate most need for explicit std::move.

Explicit move is needed to explicitly move an object to another scope, notably to pass it to a "sink" function and in the implementations of the move operations themselves (move constructor, move assignment operator) and swap operations.

Example, bad

```
void sink(X&& x);  // sink takes ownership of x

void user()
{
    X x;
    // error: cannot bind an lvalue to a rvalue reference
    sink(x);
    // OK: sink takes the contents of x, x must now be assumed to be empty
    sink(std::move(x));

// ...

// probably a mistake
    use(x);
}
```

Usually, a std::move() is used as an argument to a && parameter. And after you do that, assume the object has been moved from (see C.64) and don't read its state again until you first set it to a new value.

Example

```
void sink(unique_ptr<widget> p); // pass ownership of p to sink()

void f()
{
   auto w = make_unique<widget>();
   // ...
   sink(std::move(w)); // ok, give to sink()
   // ...
   sink(w); // Error: unique_ptr is carefully designed so that you cannot copy it
}
```

Notes

std::move() is a cast to && in disguise; it doesn't itself move anything, but marks a named object as a candidate that can be moved from. The language already knows the common cases where objects can be moved from, especially when returning values from functions, so don't complicate code with redundant std::move()'s.

Never write std::move() just because you've heard "it's more efficient." In general, don't believe claims of "efficiency" without data (???). In general, don't complicate your code without reason (??). Never write std::move() on a const object, it is silently transformed into a copy (see Item 23 in Meyers15)

Example, bad

```
vector<int> make_vector()
{
    vector<int> result;
    // ... load result with data
    return std::move(result);    // bad; just write "return result;"
}
```

Never write return move(local_variable);, because the language already knows the variable is a move candidate. Writing move in this code won't help, and can actually be detrimental because on some compilers it interferes with RVO (the return value optimization) by creating an additional reference alias to the local variable.

Example, bad

```
vector<int> v = std::move(make_vector()); // bad; the std::move is entirely redundant
```

Never write move on a returned value such as x = move(f()); where f returns by value. The language already knows that a returned value is a temporary object that can be moved from.

Example

```
void mover(X&& x)
    call_something(std::move(x));
                                         // ok
    call_something(std::forward<X>(x));
                                         // bad, don't std::forward an rvalue reference
    call_something(x);
                                          // suspicious, why not std::move?
}
template<class T>
void forwarder(T&& t)
    call_something(std::move(t));
                                        // bad, don't std::move a forwarding reference
    call_something(std::forward<T>(t));
                                         // ok
   call_something(t);
                                         // suspicious, why not std::forward?
}
```

Enforcement

- Flag use of std::move(x) where x is an rvalue or the language will already treat it as an rvalue, including return std::move(local_variable); and std::move(f()) on a function that returns by value.
- Flag functions taking an S&& parameter if there is no const S& overload to take care of Ivalues.
- Flag a std::moved argument passed to a parameter, except when the parameter type is an X&& rvalue reference or the type is move-only and the parameter is passed by value.
- Flag when std::move is applied to a forwarding reference (T&& where T is a template parameter type). Use std::forward instead.
- Flag when std::move is applied to other than an rvalue reference to non-const. (More general case of the previous rule to cover the non-forwarding cases.)
- Flag when std::forward is applied to an rvalue reference (X&& where X is a non-template parameter type). Use std::move instead.
- Flag when std::forward is applied to other than a forwarding reference. (More general case of the previous rule to cover the non-moving cases.)
- Flag when an object is potentially moved from and the next operation is a const operation; there should first be an intervening non-const operation, ideally assignment, to first reset the object's value.

ES.60: Avoid new and delete outside resource management functions

Reason

Direct resource management in application code is error-prone and tedious.

Note

This is also known as the rule of "No naked new!"

Example, bad

```
void f(int n)
{
   auto p = new X[n]; // n default constructed Xs
   // ...
   delete[] p;
}
```

There can be code in the ... part that causes the delete never to happen.

See also: R: Resource management

Enforcement

Flag naked news and naked deletes.

ES.61: Delete arrays using delete[] and non-arrays using delete

Reason

That's what the language requires, and mismatches can lead to resource release errors and/or memory corruption.

Example, bad

```
void f(int n)
{
   auto p = new X[n]; // n default constructed Xs
   // ...
   delete p; // error: just delete the object p, rather than delete the array p[]
}
```

Note

This example not only violates the no naked new rule as in the previous example, it has many more problems.

Enforcement

- Flag mismatched new and delete if they are in the same scope.
- Flag mismatched new and delete if they are in a constructor/destructor pair.

ES.62: Don't compare pointers into different arrays

Reason

The result of doing so is undefined.

Example, bad

Note

This example has many more problems.

Enforcement

???

ES.63: Don't slice

Reason

Slicing -- that is, copying only part of an object using assignment or initialization -- most often leads to errors because the object was meant to be considered as a whole. In the rare cases where the slicing was deliberate the code can be surprising.

Example

The result will be meaningless because the center and radius will not be copied from c into s. The first defense against this is to define the base class Shape not to allow this.

Alternative

If you mean to slice, define an explicit operation to do so. This saves readers from confusion. For example:

```
class Smiley : public Circle {
    public:
    Circle copy_circle();
    // ...
};

Smiley sm { /* ... */ };
Circle c1 {sm}; // ideally prevented by the definition of Circle
Circle c2 {sm.copy_circle()};
```

Enforcement

Warn against slicing.

ES.64: Use the T{e}notation for construction

Reason

The $T\{e\}$ construction syntax makes it explicit that construction is desired. The $T\{e\}$ construction syntax doesn't allow narrowing. $T\{e\}$ is the only safe and general expression for constructing a value of type T from an expression E. The casts notations T(e) and E0 are neither safe nor general.

Example

For built-in types, the construction notation protects against narrowing and reinterpretation

```
void use(char ch, int i, double d, char* p, long long lng)
{
   int x1 = int{ch};
                       // OK, but redundant
                         // error: double->int narrowing; use a cast if you need to
   int x2 = int\{d\};
                         // error: pointer to->int; use a reinterpret_cast if you really need
   int x3 = int\{p\};
   int x4 = int{lng};
                        // error: long long->int narrowing; use a cast if you need to
   int y1 = int(ch);
                         // OK, but redundant
   int y2 = int(d);
                         // bad: double->int narrowing; use a cast if you need to
   int y3 = int(p);
                         // bad: pointer to->int; use a reinterpret_cast if you really need
to
   int y4 = int(lng);
                         // bad: long long->int narrowing; use a cast if you need to
   int z1 = (int)ch;
                         // OK, but redundant
    int z2 = (int)d;
                         // bad: double->int narrowing; use a cast if you need to
                        // bad: pointer to->int; use a reinterpret_cast if you really need
   int z3 = (int)p;
   int z4 = (int)lng; // bad: long long->int narrowing; use a cast if you need to
}
```

The integer to/from pointer conversions are implementation defined when using the T(e) or (T)e notations, and non-portable between platforms with different integer and pointer sizes.

Note

Avoid casts (explicit type conversion) and if you must prefer named casts.

Note

When unambiguous, the T can be left out of T{e}.

```
complex<double> f(complex<double>);
auto z = f({2*pi, 1});
```

Note

The construction notation is the most general initializer notation.

Exception

std::vector and other containers were defined before we had {} as a notation for construction. Consider:

How do we get a vector of 10 default initialized ints?

```
vector<int> v3(10); // ten elements with value 0
```

The use of () rather than {} for number of elements is conventional (going back to the early 1980s), hard to change, but still a design error: for a container where the element type can be confused with the number of elements, we have an ambiguity that must be resolved. The conventional resolution is to interpret {10} as a list of one element and use (10) to distinguish a size.

This mistake need not be repeated in new code. We can define a type to represent the number of elements:

The main problem left is to find a suitable name for Count.

Enforcement

Flag the C-style (T)e and functional-style T(e) casts.

ES.65: Don't dereference an invalid pointer

Reason

Dereferencing an invalid pointer, such as nullptr, is undefined behavior, typically leading to immediate crashes, wrong results, or memory corruption.

Note

This rule is an obvious and well-known language rule, but can be hard to follow. It takes good coding style, library support, and static analysis to eliminate violations without major overhead. This is a major part of the discussion of C++'s model for type- and resource-safety.

See also:

- Use RAII to avoid lifetime problems.
- Use unique_ptr to avoid lifetime problems.
- Use shared_ptr to avoid lifetime problems.
- Use references when nullptr isn't a possibility.
- Use not_null to catch unexpected nullptr early.
- Use the bounds profile to avoid range errors.

Example

To resolve the problem, either extend the lifetime of the object the pointer is intended to refer to, or shorten the lifetime of the pointer (move the dereference to before the pointed-to object's lifetime ends).

Unfortunately, most invalid pointer problems are harder to spot and harder to fix.

Example

```
void f(int* p)
{
   int x = *p; // BAD: how do we know that p is valid?
}
```

There is a huge amount of such code. Most works -- after lots of testing -- but in isolation it is impossible to tell whether p could be the nullptr. Consequently, this is also a major source of errors. There are many approaches to dealing with this potential problem:

```
void f1(int* p) // deal with nullptr
{
   if (!p) {
      // deal with nullptr (allocate, return, throw, make p point to something, whatever
   }
   int x = *p;
}
```

There are two potential problems with testing for nullptr:

- it is not always obvious what to do if we find nullptr
- the test can be redundant and/or relatively expensive
- it is not obvious if the test is to protect against a violation or part of the required logic.

```
void f2(int* p) // state that p is not supposed to be nullptr { assert(p); int x = *p; }
```

This would carry a cost only when the assertion checking was enabled and would give a compiler/analyzer useful information. This would work even better if/when C++ gets direct support for contracts:

```
void f3(int* p) // state that p is not supposed to be nullptr
  [[expects: p]]
{
  int x = *p;
}
```

Alternatively, we could use gsl::not_null to ensure that p is not the nullptr.

```
void f(not_null<int*> p)
{
    int x = *p;
}
```

These remedies take care of nullptr only. Remember that there are other ways of getting an invalid pointer.

Example

```
void f(int* p) // old code, doesn't use owner
{
    delete p;
}

void g() // old code: uses naked new
{
    auto q = new int{7};
    f(q);
    int x = *q; // BAD: dereferences invalid pointer
}
```

Example

```
void f()
{
    vector<int> v(10);
    int* p = &v[5];
    v.push_back(99); // could reallocate v's elements
    int x = *p; // BAD: dereferences potentially invalid pointer
}
```

This rule is part of the lifetime safety profile

- Flag a dereference of a pointer that points to an object that has gone out of scope
- Flag a dereference of a pointer that might have been invalidated by assigning a nullptr
- Flag a dereference of a pointer that might have been invalidated by a delete
- Flag a dereference to a pointer to a container element that might have been invalidated by dereference

ES.stmt: Statements

Statements control the flow of control (except for function calls and exception throws, which are expressions).

ES.70: Prefer a switch-statement to an if-statement when there is a choice

Reason

- Readability.
- Efficiency: A switch compares against constants and is usually better optimized than a series of tests in an ifthen-else chain.
- A switch enables some heuristic consistency checking. For example, have all values of an enum been covered? If not, is there a default?

Example

rather than:

```
void use2(int n)
{
   if (n == 0) // bad: if-then-else chain comparing against a set of constants
        // ...
   else if (n == 7)
        // ...
}
```

Flag if-then-else chains that check against constants (only).

ES.71: Prefer a range-for-statement to a for-statement when there is a choice

Reason

Readability. Error prevention. Efficiency.

Example

A human or a good static analyzer might determine that there really isn't a side effect on v in f(v, &v[i]) so that the loop can be rewritten.

"Messing with the loop variable" in the body of a loop is typically best avoided.

Note

Don't use expensive copies of the loop variable of a range-for loop:

```
for (string s : vs) // ...
```

This will copy each element of vs into s. Better:

```
for (string& s : vs) // ...
```

Better still, if the loop variable isn't modified or copied:

```
for (const string& s : vs) // ...
```

Enforcement

Look at loops, if a traditional loop just looks at each element of a sequence, and there are no side effects on what it does with the elements, rewrite the loop to a ranged-for loop.

ES.72: Prefer a for-statement to a while-statement when there is an obvious loop variable

Reason

Readability: the complete logic of the loop is visible "up front". The scope of the loop variable can be limited.

Example

```
for (gsl::index i = 0; i < vec.size(); i++) {
    // do work
}</pre>
```

Example, bad

```
int i = 0;
while (i < vec.size()) {
    // do work
    i++;
}</pre>
```

???

ES.73: Prefer a while-statement to a for-statement when there is no obvious loop variable

Reason

Readability.

Example

```
int events = 0;
for (; wait_for_event(); ++events) { // bad, confusing
    // ...
}
```

The "event loop" is misleading because the events counter has nothing to do with the loop condition (wait_for_event()). Better

Enforcement

Flag actions in for-initializers and for-increments that do not relate to the for-condition.

ES.74: Prefer to declare a loop variable in the initializer part of a forstatement

See ES.6

ES.75: Avoid do-statements

Reason

Readability, avoidance of errors. The termination condition is at the end (where it can be overlooked) and the condition is not checked the first time through.

Example

```
int x;
do {
    cin >> x;
    // ...
} while (x < 0);</pre>
```

Note

Yes, there are genuine examples where a do-statement is a clear statement of a solution, but also many bugs.

Enforcement

Flag do-statements.

ES.76: Avoid goto

Reason

Readability, avoidance of errors. There are better control structures for humans; goto is for machine generated code.

Exception

Breaking out of a nested loop. In that case, always jump forwards.

```
for (int i = 0; i < imax; ++i)
    for (int j = 0; j < jmax; ++j) {
        if (a[i][j] > elem_max) goto finished;
        // ...
    }
finished:
// ...
```

Example, bad

There is a fair amount of use of the C goto-exit idiom:

```
void f()
{
    // ...
        goto exit;
    // ...
        goto exit;
    // ...
exit:
    // ... common cleanup code ...
}
```

This is an ad-hoc simulation of destructors. Declare your resources with handles with destructors that clean up. If for some reason you cannot handle all cleanup with destructors for the variables used, consider gsl::finally() as a cleaner and more reliable alternative to goto exit

Enforcement

• Flag goto. Better still flag all gotos that do not jump from a nested loop to the statement immediately after a nest of loops.

ES.77: Minimize the use of break and continue in loops

Reason

In a non-trivial loop body, it is easy to overlook a break or a continue.

A break in a loop has a dramatically different meaning than a break in a switch-statement (and you can have switch-statement in a loop and a loop in a switch-case).

Example

```
switch(x) {
case 1 :
    while (/* some condition */) {
        // ...
    break;
    } // Oops! break switch or break while intended?
case 2 :
    // ...
    break;
}
```

Alternative

Often, a loop that requires a break is a good candidate for a function (algorithm), in which case the break becomes a return.

```
//Original code: break inside loop
void use1()
    std::vector<T> vec = {/* initialized with some values */};
   T value;
   for (const T item : vec) {
        if (/* some condition*/) {
            value = item;
            break;
        }
    /* then do something with value */
}
//BETTER: create a function and return inside loop
T search(const std::vector<T> &vec)
{
   for (const T &item : vec) {
        if (/* some condition*/) return item;
   return T(); //default value
}
void use2()
   std::vector<T> vec = {/* initialized with some values */};
   T value = search(vec);
   /* then do something with value */
}
```

Often, a loop that uses continue can equivalently and as clearly be expressed by an if-statement.

```
for (int item : vec) {  // BAD
    if (item%2 == 0) continue;
    if (item == 5) continue;
    if (item > 10) continue;
    /* do something with item */
}

for (int item : vec) {  // GOOD
    if (item%2 != 0 && item != 5 && item <= 10) {
        /* do something with item */
    }
}</pre>
```

Note

If you really need to break out a loop, a break is typically better than alternatives such as modifying the loop variable or a goto:

Enforcement

???

ES.78: Don't rely on implicit fallthrough in switch statements

Reason

Always end a non-empty case with a break. Accidentally leaving out a break is a fairly common bug. A deliberate fallthrough can be a maintenance hazard and should be rare and explicit.

Example

```
switch (eventType) {
  case Information:
    update_status_bar();
    break;
  case Warning:
    write_event_log();
    // Bad - implicit fallthrough
  case Error:
    display_error_window();
    break;
}
```

Multiple case labels of a single statement is OK:

```
switch (x) {
  case 'a':
   case 'b':
   case 'f':
      do_something(x);
      break;
}
```

Return statements in a case label are also OK:

```
switch (x) {
  case 'a':
     return 1;
  case 'b':
     return 2;
  case 'c':
     return 3;
}
```

Exceptions

In rare cases if fallthrough is deemed appropriate, be explicit and use the [[fallthrough]] annotation:

```
switch (eventType) {
  case Information:
    update_status_bar();
    break;
  case Warning:
    write_event_log();
    [[fallthrough]];
  case Error:
    display_error_window();
    break;
}
```

Note

Enforcement

Flag all implicit fallthroughs from non-empty cases.

ES.79: Use default to handle common cases (only)

Reason

Code clarity. Improved opportunities for error detection.

Example

```
enum E { a, b, c, d };

void f1(E x)
{
    switch (x) {
    case a:
        do_something();
        break;
```

```
case b:
    do_something_else();
    break;
default:
    take_the_default_action();
    break;
}
```

Here it is clear that there is a default action and that cases a and b are special.

Example

But what if there is no default action and you mean to handle only specific cases? In that case, have an empty default or else it is impossible to know if you meant to handle all cases:

```
void f2(E x)
{
    switch (x) {
    case a:
        do_something();
        break;
    case b:
        do_something_else();
        break;
    default:
        // do nothing for the rest of the cases
        break;
}
```

If you leave out the default, a maintainer and/or a compiler might reasonably assume that you intended to handle all cases:

```
void f2(E x)
{
    switch (x) {
    case a:
        do_something();
        break;
    case b:
    case c:
        do_something_else();
        break;
}
```

Did you forget case d or deliberately leave it out? Forgetting a case typically happens when a case is added to an enumeration and the person doing so fails to add it to every switch over the enumerators.

Flag switch-statements over an enumeration that don't handle all enumerators and do not have a default. This might yield too many false positives in some code bases; if so, flag only switches that handle most but not all cases (that was the strategy of the very first C++ compiler).

ES.84: Don't try to declare a local variable with no name

Reason

There is no such thing. What looks to a human like a variable without a name is to the compiler a statement consisting of a temporary that immediately goes out of scope.

Example, bad

```
void f()
{
    lock_guard<mutex>{mx}; // Bad
    // ...
}
```

This declares an unnamed lock_guard object that immediately goes out of scope at the point of the semicolon. This is not an uncommon mistake. In particular, this particular example can lead to hard-to find race conditions.

Note

Unnamed function arguments are fine.

Enforcement

Flag statements that are just a temporary.

ES.85: Make empty statements visible

Reason

Readability.

Example

Flag empty statements that are not blocks and don't contain comments.

ES.86: Avoid modifying loop control variables inside the body of raw forloops

Reason

The loop control up front should enable correct reasoning about what is happening inside the loop. Modifying loop counters in both the iteration-expression and inside the body of the loop is a perennial source of surprises and bugs.

Example

```
for (int i = 0; i < 10; ++i) {
    // no updates to i -- ok
}

for (int i = 0; i < 10; ++i) {
    //
    if (/* something */) ++i; // BAD
    //
}

bool skip = false;
for (int i = 0; i < 10; ++i) {
    if (skip) { skip = false; continue; }
    //
    if (/* something */) skip = true; // Better: using two variables for two concepts.
    //
}</pre>
```

Flag variables that are potentially updated (have a non-const use) in both the loop control iteration-expression and the loop body.

ES.87: Don't add redundant == or != to conditions

Reason

Doing so avoids verbosity and eliminates some opportunities for mistakes. Helps make style consistent and conventional.

Example

By definition, a condition in an if-statement, while-statement, or a for-statement selects between true and false. A numeric value is compared to 0 and a pointer value to nullptr.

Often, if (p) is read as "if p is valid" which is a direct expression of the programmers intent, whereas if (p != nullptr) would be a long-winded workaround.

Example

This rule is especially useful when a declaration is used as a condition

```
if (auto pc = dynamic_cast<Circle>(ps)) { ... } // execute if ps points to a kind of Circle,
good

if (auto pc = dynamic_cast<Circle>(ps); pc != nullptr) { ... } // not recommended
```

Example

Note that implicit conversions to bool are applied in conditions. For example:

```
for (string s; cin >> s; ) v.push_back(s);
```

This invokes istream's operator bool().

Note

Explicit comparison of an integer to 0 is in general not redundant. The reason is that (as opposed to pointers and Booleans) an integer often has more than two reasonable values. Furthermore 0 (zero) is often used to indicate success. Consequently, it is best to be specific about the comparison.

Always remember that an integer can have more than two values.

Example, bad

It has been noted that

```
if(strcmp(p1, p2)) { ... } // are the two C-style strings equal? (mistake!)
```

is a common beginners error. If you use C-style strings, you must know the <cstring> functions well. Being verbose and writing

```
if(strcmp(p1, p2) != 0) { ... } // are the two C-style strings equal? (mistake!)
```

would not in itself save you.

Note

The opposite condition is most easily expressed using a negation:

Enforcement

Easy, just check for redundant use of != and == in conditions.

Arithmetic

ES.100: Don't mix signed and unsigned arithmetic

Reason

Avoid wrong results.

Example

```
int x = -3;
unsigned int y = 7;

cout << x - y << '\n'; // unsigned result, possibly 4294967286
cout << x + y << '\n'; // unsigned result: 4
cout << x * y << '\n'; // unsigned result, possibly 4294967275</pre>
```

It is harder to spot the problem in more realistic examples.

Note

Unfortunately, C++ uses signed integers for array subscripts and the standard library uses unsigned integers for container subscripts. This precludes consistency. Use gsl::index for subscripts; see ES.107.

Enforcement

- Compilers already know and sometimes warn.
- (To avoid noise) Do not flag on a mixed signed/unsigned comparison where one of the arguments is sizeof or a call to container .size() and the other is ptrdiff_t.

ES.101: Use unsigned types for bit manipulation

Reason

Unsigned types support bit manipulation without surprises from sign bits.

Example

```
unsigned char x = 0b1010'1010;
unsigned char y = ~x; // y == 0b0101'0101;
```

Note

Unsigned types can also be useful for modular arithmetic. However, if you want modular arithmetic add comments as necessary noting the reliance on wraparound behavior, as such code can be surprising for many programmers.

- Just about impossible in general because of the use of unsigned subscripts in the standard library
- **???**

ES.102: Use signed types for arithmetic

Reason

Because most arithmetic is assumed to be signed; x - y yields a negative number when y > x except in the rare cases where you really want modular arithmetic.

Example

Unsigned arithmetic can yield surprising results if you are not expecting it. This is even more true for mixed signed and unsigned arithmetic.

```
template<typename T, typename T2>
T subtract(T x, T2 y)
    return x - y;
}
void test()
    int s = 5;
    unsigned int us = 5;
    cout << subtract(s, 7) << '\n';  // -2</pre>
                                          // 4294967294
    cout << subtract(us, 7u) << '\n';</pre>
    cout << subtract(s, 7u) << '\n';</pre>
                                          // -2
    cout << subtract(us, 7) << '\n';</pre>
                                          // 4294967294
    cout << subtract(s, us + 2) << '\n'; // -2</pre>
    cout << subtract(us, s + 2) << '\n'; // 4294967294</pre>
}
```

Here we have been very explicit about what's happening, but if you had seen us - (s + 2) or s += 2; ...; us - s, would you reliably have suspected that the result would print as 4294967294?

Exception

Use unsigned types if you really want modular arithmetic - add comments as necessary noting the reliance on overflow behavior, as such code is going to be surprising for many programmers.

Example

The standard library uses unsigned types for subscripts. The built-in array uses signed types for subscripts. This makes surprises (and bugs) inevitable.

Use gsl::index for subscripts; see ES.107.

Enforcement

- Flag mixed signed and unsigned arithmetic
- Flag results of unsigned arithmetic assigned to or printed as signed.
- Flag negative literals (e.g. -2) used as container subscripts.
- (To avoid noise) Do not flag on a mixed signed/unsigned comparison where one of the arguments is sizeof or a call to container .size() and the other is ptrdiff_t.

ES.103: Don't overflow

Reason

Overflow usually makes your numeric algorithm meaningless. Incrementing a value beyond a maximum value can lead to memory corruption and undefined behavior.

Example, bad

```
int a[10];
a[10] = 7;  // bad, array bounds overflow

for (int n = 0; n <= 10; ++n)
    a[n] = 9;  // bad, array bounds overflow</pre>
```

Example, bad

```
int n = numeric_limits<int>::max();
int m = n + 1;  // bad, numeric overflow
```

Example, bad

```
int area(int h, int w) { return h * w; }
auto a = area(10'000'000, 100'000'000); // bad, numeric overflow
```

Exception

Use unsigned types if you really want modular arithmetic.

Alternative: For critical applications that can afford some overhead, use a range-checked integer and/or floating-point type.

Enforcement

???

ES.104: Don't underflow

Reason

Decrementing a value beyond a minimum value can lead to memory corruption and undefined behavior.

Example, bad

```
int a[10];
a[-2] = 7;  // bad

int n = 101;
while (n--)
a[n - 1] = 9;  // bad (twice)
```

Exception

Use unsigned types if you really want modular arithmetic.

Enforcement

???

ES.105: Don't divide by integer zero

Reason

The result is undefined and probably a crash.

Note

This also applies to %.

Example, bad

```
int divide(int a, int b)
{
    // BAD, should be checked (e.g., in a precondition)
    return a / b;
}
```

Example, good

```
int divide(int a, int b)
{
    // good, address via precondition (and replace with contracts once C++ gets them)
    Expects(b != 0);
    return a / b;
}

double divide(double a, double b)
{
    // good, address via using double instead
    return a / b;
}
```

Alternative: For critical applications that can afford some overhead, use a range-checked integer and/or floating-point type.

Enforcement

• Flag division by an integral value that could be zero

ES.106: Don't try to avoid negative values by using unsigned

Reason

Choosing unsigned implies many changes to the usual behavior of integers, including modular arithmetic, can suppress warnings related to overflow, and opens the door for errors related to signed/unsigned mixes. Using unsigned doesn't actually eliminate the possibility of negative values.

Example

```
unsigned int u1 = -2; // Valid: the value of u1 is 4294967294 int i1 = -2; unsigned int u2 = i1; // Valid: the value of u2 is 4294967294 int i2 = u2; // Valid: the value of i2 is -2
```

These problems with such (perfectly legal) constructs are hard to spot in real code and are the source of many real-world errors. Consider:

```
unsigned area(unsigned height, unsigned width) { return height*width; } // [see also](#Ri-
expects)
// ...
int height;
cin >> height;
auto a = area(height, 2); // if the input is -2 a becomes 4294967292
```

Remember that -1 when assigned to an unsigned int becomes the largest unsigned int. Also, since unsigned arithmetic is modular arithmetic the multiplication didn't overflow, it wrapped around.

Example

```
unsigned max = 100000; // "accidental typo", I mean to say 10'000 unsigned short x = 100; while (x < max) x += 100; // infinite loop
```

Had x been a signed short, we could have warned about the undefined behavior upon overflow.

Alternatives

- use signed integers and check for x >= 0
- use a positive integer type
- use an integer subrange type
- Assert(-1 < x)

For example

```
struct Positive {
   int val;
   Positive(int x) :val{x} { Assert(0 < x); }
   operator int() { return val; }
};

int f(Positive arg) { return arg; }

int r1 = f(2);
   int r2 = f(-2); // throws</pre>
```

Note

???

Enforcement

See ES.100 Enforcements.

ES.107: Don't use unsigned for subscripts, prefer gsl::index

Reason

To avoid signed/unsigned confusion. To enable better optimization. To enable better error detection. To avoid the pitfalls with auto and int.

Example, bad

```
vector<int> vec = /*...*/;
for (int i = 0; i < vec.size(); i += 2)
                                                            // might not be big enough
    cout << vec[i] << '\n';</pre>
for (unsigned i = 0; i < vec.size(); i += 2)</pre>
                                                            // risk wraparound
   cout << vec[i] << '\n';
for (auto i = 0; i < vec.size(); i += 2)</pre>
                                                             // might not be big enough
    cout << vec[i] << '\n';
for (vector<int>::size_type i = 0; i < vec.size(); i += 2) // verbose</pre>
   cout << vec[i] << '\n';
for (auto i = vec.size()-1; i >= 0; i -= 2)
                                                            // bug
    cout << vec[i] << '\n';
for (int i = vec.size()-1; i >= 0; i -= 2)
                                                             // might not be big enough
    cout << vec[i] << '\n';
```

Example, good

Note

The built-in array allows signed subscripts. The standard-library containers use unsigned subscripts. Thus, no perfect and fully compatible solution is possible (unless and until the standard-library containers change to use signed subscripts someday in the future). Given the known problems with unsigned and signed/unsigned mixtures, better stick to (signed) integers of a sufficient size, which is guaranteed by gsl::index.

Example

```
template<typename T>
struct My_container {
public:
    // ...
    T& operator[](gsl::index i);    // not unsigned
    // ...
};
```

Example

```
??? demonstrate improved code generation and potential for error detection ???
```

Alternatives

Alternatives for users

- use algorithms
- use range-for
- use iterators/pointers

Enforcement

- Very tricky as long as the standard-library containers get it wrong.
- (To avoid noise) Do not flag on a mixed signed/unsigned comparison where one of the arguments is sizeof or a call to container .size() and the other is ptrdiff_t.

Per: Performance

??? should this section be in the main guide???

This section contains rules for people who need high performance or low-latency. That is, these are rules that relate to how to use as little time and as few resources as possible to achieve a task in a predictably short time. The rules in this section are more restrictive and intrusive than what is needed for many (most) applications. Do not naïvely try to follow them in general code: achieving the goals of low latency requires extra work.

Performance rule summary:

- Per.1: Don't optimize without reason
- Per.2: Don't optimize prematurely
- Per.3: Don't optimize something that's not performance critical
- Per.4: Don't assume that complicated code is necessarily faster than simple code
- Per.5: Don't assume that low-level code is necessarily faster than high-level code
- Per.6: Don't make claims about performance without measurements
- Per.7: Design to enable optimization
- Per.10: Rely on the static type system
- Per.11: Move computation from run time to compile time
- Per.12: Eliminate redundant aliases
- Per.13: Eliminate redundant indirections
- Per.14: Minimize the number of allocations and deallocations
- Per.15: Do not allocate on a critical branch
- Per.16: Use compact data structures
- Per.17: Declare the most used member of a time-critical struct first
- Per.18: Space is time
- Per.19: Access memory predictably
- Per.30: Avoid context switches on the critical path

Per.1: Don't optimize without reason

Reason

If there is no need for optimization, the main result of the effort will be more errors and higher maintenance costs.

Note

Some people optimize out of habit or because it's fun.

???

Per.2: Don't optimize prematurely

Reason

Elaborately optimized code is usually larger and harder to change than unoptimized code.

???

Per.3: Don't optimize something that's not performance critical

Reason

Optimizing a non-performance-critical part of a program has no effect on system performance.

Note

If your program spends most of its time waiting for the web or for a human, optimization of in-memory computation is probably useless.

Put another way: If your program spends 4% of its processing time doing computation A and 40% of its time doing computation B, a 50% improvement on A is only as impactful as a 5% improvement on B. (If you don't even know how much time is spent on A or B, see Per.1 and Per.2.)

Per.4: Don't assume that complicated code is necessarily faster than simple code

Reason

Simple code can be very fast. Optimizers sometimes do marvels with simple code

Example, good

```
// clear expression of intent, fast execution
vector<uint8_t> v(100000);
for (auto& c : v)
    c = ~c;
```

Example, bad

```
// intended to be faster, but is often slower

vector<uint8_t> v(100000);

for (size_t i = 0; i < v.size(); i += sizeof(uint64_t)) {
    uint64_t& quad_word = *reinterpret_cast<uint64_t*>(&v[i]);
    quad_word = ~quad_word;
}
```

Note

???

???

Per.5: Don't assume that low-level code is necessarily faster than high-level code

Reason

Low-level code sometimes inhibits optimizations. Optimizers sometimes do marvels with high-level code.

Note

???

???

Per.6: Don't make claims about performance without measurements

Reason

The field of performance is littered with myth and bogus folklore. Modern hardware and optimizers defy naive assumptions; even experts are regularly surprised.

Note

Getting good performance measurements can be hard and require specialized tools.

Note

A few simple microbenchmarks using Unix time or the standard-library <chrono> can help dispel the most obvious myths. If you can't measure your complete system accurately, at least try to measure a few of your key operations and algorithms. A profiler can help tell you which parts of your system are performance critical. Often, you will be surprised.

???

Per.7: Design to enable optimization

Reason

Because we often need to optimize the initial design. Because a design that ignores the possibility of later improvement is hard to change.

Example

From the C (and C++) standard:

```
void qsort (void* base, size_t num, size_t size, int (*compar)(const void*, const void*));
```

When did you even want to sort memory? Really, we sort sequences of elements, typically stored in containers. A call to qsort throws away much useful information (e.g., the element type), forces the user to repeat information already known (e.g., the element size), and forces the user to write extra code (e.g., a function to compare doubles). This implies added work for the programmer, is error-prone, and deprives the compiler of information needed for optimization.

```
double data[100];
// ... fill a ...

// 100 chunks of memory of sizeof(double) starting at
// address data using the order defined by compare_doubles
qsort(data, 100, sizeof(double), compare_doubles);
```

From the point of view of interface design, qsort throws away useful information.

We can do better (in C++98)

```
template<typename Iter>
    void sort(Iter b, Iter e); // sort [b:e)
sort(data, data + 100);
```

Here, we use the compiler's knowledge about the size of the array, the type of elements, and how to compare doubles.

```
// sortable specifies that c must be a
// random-access sequence of elements comparable with <
void sort(sortable auto& c);
sort(c);</pre>
```

The key is to pass sufficient information for a good implementation to be chosen. In this, the sort interfaces shown here still have a weakness: They implicitly rely on the element type having less-than (<) defined. To complete the interface, we need a second version that accepts a comparison criterion:

```
// compare elements of c using r
template<random_access_range R, class C> requires sortable<R, C>
void sort(R&& r, C c);
```

The standard-library specification of sort offers those two versions, and more.

Note

Premature optimization is said to be the root of all evil, but that's not a reason to despise performance. It is never premature to consider what makes a design amenable to improvement, and improved performance is a commonly desired improvement. Aim to build a set of habits that by default results in efficient, maintainable, and optimizable code. In particular, when you write a function that is not a one-off implementation detail, consider

- Information passing: Prefer clean interfaces carrying sufficient information for later improvement of implementation. Note that information flows into and out of an implementation through the interfaces we provide.
- Compact data: By default, use compact data, such as std::vector and access it in a systematic fashion. If you think you need a linked structure, try to craft the interface so that this structure isn't seen by users.
- Function argument passing and return: Distinguish between mutable and non-mutable data. Don't impose a resource management burden on your users. Don't impose spurious run-time indirections on your users. Use conventional ways of passing information through an interface; unconventional and/or "optimized" ways of passing data can seriously complicate later reimplementation.
- Abstraction: Don't overgeneralize; a design that tries to cater for every possible use (and misuse) and defers every design decision for later (using compile-time or run-time indirections) is usually a complicated, bloated, hard-to-understand mess. Generalize from concrete examples, preserving performance as we generalize. Do not generalize based on mere speculation about future needs. The ideal is zero-overhead generalization.
- Libraries: Use libraries with good interfaces. If no library is available build one yourself and imitate the interface style from a good library. The standard library is a good first place to look for inspiration.
- Isolation: Isolate your code from messy and/or old-style code by providing an interface of your choosing to it.
 This is sometimes called "providing a wrapper" for the useful/necessary but messy code. Don't let bad designs "bleed into" your code.

Example

Consider:

```
template<class ForwardIterator, class T>
bool binary_search(ForwardIterator first, ForwardIterator last, const T& val);
```

binary_search(begin(c), end(c), 7) will tell you whether 7 is in c or not. However, it will not tell you where that 7 is or whether there are more than one 7.

Sometimes, just passing the minimal amount of information back (here, true or false) is sufficient, but a good interface passes needed information back to the caller. Therefore, the standard library also offers

```
template<class ForwardIterator, class T>
ForwardIterator lower_bound(ForwardIterator first, ForwardIterator last, const T& val);
```

lower_bound returns an iterator to the first match if any, otherwise to the first element greater than val, or last if no such element is found.

However, lower_bound still doesn't return enough information for all uses, so the standard library also offers

```
template<class ForwardIterator, class T>
pair<ForwardIterator, ForwardIterator>
equal_range(ForwardIterator first, ForwardIterator last, const T& val);
```

equal_range returns a pair of iterators specifying the first and one beyond last match.

```
auto r = equal_range(begin(c), end(c), 7);
for (auto p = r.first; p != r.second; ++p)
   cout << *p << '\n';</pre>
```

Obviously, these three interfaces are implemented by the same basic code. They are simply three ways of presenting the basic binary search algorithm to users, ranging from the simplest ("make simple things simple!") to returning complete, but not always needed, information ("don't hide useful information"). Naturally, crafting such a set of interfaces requires experience and domain knowledge.

Note

Do not simply craft the interface to match the first implementation and the first use case you think of. Once your first initial implementation is complete, review it; once you deploy it, mistakes will be hard to remedy.

Note

A need for efficiency does not imply a need for low-level code. High-level code isn't necessarily slow or bloated.

Note

Things have costs. Don't be paranoid about costs (modern computers really are very fast), but have a rough idea of the order of magnitude of cost of what you use. For example, have a rough idea of the cost of a memory access, a function call, a string comparison, a system call, a disk access, and a message through a network.

Note

If you can only think of one implementation, you probably don't have something for which you can devise a stable interface. Maybe, it is just an implementation detail - not every piece of code needs a stable interface - but pause and consider. One question that can be useful is "what interface would be needed if this operation should be implemented using multiple threads? be vectorized?"

Note

This rule does not contradict the Don't optimize prematurely rule. It complements it, encouraging developers to enable later - appropriate and non-premature - optimization, if and where needed.

Enforcement

Tricky. Maybe looking for void* function arguments will find examples of interfaces that hinder later optimization.

Per.10: Rely on the static type system

Reason

Type violations, weak types (e.g. void*s), and low-level code (e.g., manipulation of sequences as individual bytes) make the job of the optimizer much harder. Simple code often optimizes better than hand-crafted complex code.

???

Per.11: Move computation from run time to compile time

Reason

To decrease code size and run time. To avoid data races by using constants. To catch errors at compile time (and thus eliminate the need for error-handling code).

Example

```
double square(double d) { return d*d; }
static double s2 = square(2);  // old-style: dynamic initialization

constexpr double ntimes(double d, int n)  // assume 0 <= n
{
         double m = 1;
         while (n--) m *= d;
         return m;
}
constexpr double s3 {ntimes(2, 3)};  // modern-style: compile-time initialization</pre>
```

Code like the initialization of s2 isn't uncommon, especially for initialization that's a bit more complicated than square(). However, compared to the initialization of s3 there are two problems:

- we suffer the overhead of a function call at run time
- s2 just might be accessed by another thread before the initialization happens.

Note: you can't have a data race on a constant.

Example

Consider a popular technique for providing a handle for storing small objects in the handle itself and larger ones on the heap.

```
constexpr int on_stack_max = 20;
template<typename T>
struct Scoped { // store a T in Scoped
       // ...
   T obj;
};
template<typename T>
struct On_heap {
                 // store a T on the free store
       // ...
       T* objp;
};
template<typename T>
using Handle = typename std::conditional<(sizeof(T) <= on_stack_max),</pre>
                    Scoped<T>, // first alternative
                    On_heap<T> // second alternative
              >::type;
void f()
{
   Handle<double> v1;
                                       // the double goes on the stack
   Handle<std::array<double, 200>> v2; // the array goes on the free store
   // ...
}
```

Assume that Scoped and On_heap provide compatible user interfaces. Here we compute the optimal type to use at compile time. There are similar techniques for selecting the optimal function to call.

Note

The ideal is *not* to try to execute everything at compile time. Obviously, most computations depend on inputs, so they can't be moved to compile time, but beyond that logical constraint is the fact that complex compile-time computation can seriously increase compile times and complicate debugging. It is even possible to slow down code by compile-time computation. This is admittedly rare, but by factoring out a general computation into separate optimal sub-calculations, it is possible to render the instruction cache less effective.

Enforcement

- Look for simple functions that might be constexpr (but are not).
- Look for functions called with all constant-expression arguments.
- Look for macros that could be constexpr.

Per.12: Eliminate redundant aliases

???

Per.13: Fliminate redundant indirections

???

Per.14: Minimize the number of allocations and deallocations

???

Per.15: Do not allocate on a critical branch

Per.16: Use compact data structures

Reason

Performance is typically dominated by memory access times.

???

Per.17: Declare the most used member of a time-critical struct first

???

Per.18: Space is time

Reason

Performance is typically dominated by memory access times.

???

Per.19: Access memory predictably

Reason

Performance is very sensitive to cache performance, and cache algorithms favor simple (usually linear) access to adjacent data.

Example

CP: Concurrency and parallelism

We often want our computers to do many tasks at the same time (or at least appear to do them at the same time). The reasons for doing so vary (e.g., waiting for many events using only a single processor, processing many data streams simultaneously, or utilizing many hardware facilities) and so do the basic facilities for expressing concurrency and parallelism. Here, we articulate principles and rules for using the ISO standard C++ facilities for expressing basic concurrency and parallelism.

Threads are the machine-level foundation for concurrent and parallel programming. Threads allow running multiple sections of a program independently, while sharing the same memory. Concurrent programming is tricky, because protecting shared data between threads is easier said than done. Making existing single-threaded code execute concurrently can be as trivial as adding std::async or std::thread strategically, or it can necessitate a full rewrite, depending on whether the original code was written in a thread-friendly way.

The concurrency/parallelism rules in this document are designed with three goals in mind:

- To help in writing code that is amenable to being used in a threaded environment
- To show clean, safe ways to use the threading primitives offered by the standard library
- To offer guidance on what to do when concurrency and parallelism aren't giving the performance gains needed

It is also important to note that concurrency in C++ is an unfinished story. C++11 introduced many core concurrency primitives, C++14 and C++17 improved on them, and there is much interest in making the writing of concurrent programs in C++ even easier. We expect some of the library-related guidance here to change significantly over time.

This section needs a lot of work (obviously). Please note that we start with rules for relative non-experts. Real experts must wait a bit; contributions are welcome, but please think about the majority of programmers who are struggling to get their concurrent programs correct and performant.

Concurrency and parallelism rule summary:

- CP.1: Assume that your code will run as part of a multi-threaded program
- CP.2: Avoid data races
- CP.3: Minimize explicit sharing of writable data
- CP.4: Think in terms of tasks, rather than threads
- CP.8: Don't try to use volatile for synchronization
- CP.9: Whenever feasible use tools to validate your concurrent code

See also:

- CP.con: Concurrency
- CP.coro: Coroutines
- CP.par: Parallelism
- CP.mess: Message passing

- CP.vec: Vectorization
- CP.free: Lock-free programming
- CP.etc: Etc. concurrency rules

CP.1: Assume that your code will run as part of a multi-threaded program

Reason

It's hard to be certain that concurrency isn't used now or won't be used sometime in the future. Code gets reused. Libraries not using threads might be used from some other part of a program that does use threads. Note that this rule applies most urgently to library code and least urgently to stand-alone applications. However, over time, code fragments can turn up in unexpected places.

Example, bad

```
double cached_computation(int x)
{
    // bad: these statics cause data races in multi-threaded usage
    static int cached_x = 0.0;
    static double cached_result = COMPUTATION_OF_ZERO;

if (cached_x != x) {
    cached_x = x;
    cached_result = computation(x);
    }
    return cached_result;
}
```

Although cached_computation works perfectly in a single-threaded environment, in a multi-threaded environment the two static variables result in data races and thus undefined behavior.

Example, good

```
struct ComputationCache {
   int cached_x = 0;
   double cached_result = COMPUTATION_OF_ZERO;

   double compute(int x) {
      if (cached_x != x) {
        cached_x = x;
        cached_result = computation(x);
      }
      return cached_result;
   }
};
```

Here the cache is stored as member data of a ComputationCache object, rather than as shared static state. This refactoring essentially delegates the concern upward to the caller: a single-threaded program might still choose to have one global ComputationCache, while a multi-threaded program might have one ComputationCache instance per thread, or one per "context" for any definition of "context." The refactored function no longer attempts to manage the allocation of cached_x. In that sense, this is an application of the Single Responsibility Principle.

In this specific example, refactoring for thread-safety also improved reusability in single-threaded programs. It's not hard to imagine that a single-threaded program might want two ComputationCache instances for use in different parts of the program, without having them overwrite each other's cached data.

There are several other ways one might add thread-safety to code written for a standard multi-threaded environment (that is, one where the only form of concurrency is std::thread):

- Mark the state variables as thread_local instead of static.
- Implement concurrency control, for example, protecting access to the two static variables with a static std::mutex.
- Refuse to build and/or run in a multi-threaded environment.
- Provide two implementations: one for single-threaded environments and another for multi-threaded environments.

Exception

Code that is never run in a multi-threaded environment.

Be careful: there are many examples where code that was "known" to never run in a multi-threaded program was run as part of a multi-threaded program, often years later. Typically, such programs lead to a painful effort to remove data races. Therefore, code that is never intended to run in a multi-threaded environment should be clearly labeled as such and ideally come with compile or run-time enforcement mechanisms to catch those usage bugs early.

CP.2: Avoid data races

Reason

Unless you do, nothing is guaranteed to work and subtle errors will persist.

Note

In a nutshell, if two threads can access the same object concurrently (without synchronization), and at least one is a writer (performing a non-const operation), you have a data race. For further information of how to use synchronization well to eliminate data races, please consult a good book about concurrency (See Carefully study the literature).

Example, bad

There are many examples of data races that exist, some of which are running in production software at this very moment. One very simple example:

```
int get_id()
{
   static int id = 1;
   return id++;
}
```

The increment here is an example of a data race. This can go wrong in many ways, including:

- Thread A loads the value of id, the OS context switches A out for some period, during which other threads create hundreds of IDs. Thread A is then allowed to run again, and id is written back to that location as A's read of id plus one.
- Thread A and B load id and increment it simultaneously. They both get the same ID.

Local static variables are a common source of data races.

Example, bad:

Here, we have a (nasty) data race on the elements of buf (sort will both read and write). All data races are nasty. Here, we managed to get a data race on data on the stack. Not all data races are as easy to spot as this one.

Example, bad:

```
// code not controlled by a lock

unsigned val;

if (val < 5) {
    // ... other thread can change val here ...
    switch (val) {
    case 0: // ...
    case 1: // ...
    case 2: // ...
    case 3: // ...
    case 4: // ...
}</pre>
```

Now, a compiler that does not know that val can change will most likely implement that switch using a jump table with five entries. Then, a val outside the [0..4] range will cause a jump to an address that could be anywhere in the program, and execution would proceed there. Really, "all bets are off" if you get a data race. Actually, it can be worse still: by looking at the generated code you might be able to determine where the stray jump will go for a given value; this can be a security risk.

Enforcement

Some is possible, do at least something. There are commercial and open-source tools that try to address this problem, but be aware that solutions have costs and blind spots. Static tools often have many false positives and run-time tools often have a significant cost. We hope for better tools. Using multiple tools can catch more problems than a single one.

There are other ways you can mitigate the chance of data races:

- Avoid global data
- Avoid static variables
- More use of concrete types on the stack (and don't pass pointers around too much)
- More use of immutable data (literals, constexpr, and const)

CP.3: Minimize explicit sharing of writable data

Reason

If you don't share writable data, you can't have a data race. The less sharing you do, the less chance you have to forget to synchronize access (and get data races). The less sharing you do, the less chance you have to wait on a lock (so performance can improve).

Example

```
bool validate(const vector<Reading>&);
Graph<Temp_node> temperature_gradients(const vector<Reading>&);
Image altitude_map(const vector<Reading>&);
// ...

void process_readings(const vector<Reading>& surface_readings)
{
    auto h1 = async([&] { if (!validate(surface_readings)) throw Invalid_data{}; });
    auto h2 = async([&] { return temperature_gradients(surface_readings); });
    auto h3 = async([&] { return altitude_map(surface_readings); });
    // ...
    h1.get();
    auto v2 = h2.get();
    auto v3 = h3.get();
    // ...
}
```

Without those consts, we would have to review every asynchronously invoked function for potential data races on surface_readings. Making surface_readings be const (with respect to this function) allow reasoning using only the function body.

Note

Immutable data can be safely and efficiently shared. No locking is needed: You can't have a data race on a constant. See also CP.mess: Message Passing and CP.31: prefer pass by value.

Enforcement

???

CP.4: Think in terms of tasks, rather than threads

Reason

A thread is an implementation concept, a way of thinking about the machine. A task is an application notion, something you'd like to do, preferably concurrently with other tasks. Application concepts are easier to reason about.

Example

Note

With the exception of async(), the standard-library facilities are low-level, machine-oriented, threads-and-lock level. This is a necessary foundation, but we have to try to raise the level of abstraction: for productivity, for reliability, and for performance. This is a potent argument for using higher level, more applications-oriented libraries (if possible, built on top of standard-library facilities).

Enforcement

???

CP.8: Don't try to use volatile for synchronization

Reason

In C++, unlike some other languages, volatile does not provide atomicity, does not synchronize between threads, and does not prevent instruction reordering (neither compiler nor hardware). It simply has nothing to do with concurrency.

Example, bad:

```
int free_slots = max_slots; // current source of memory for objects

Pool* use()
{
    if (int n = free_slots--) return &pool[n];
}
```

Here we have a problem: This is perfectly good code in a single-threaded program, but have two threads execute this and there is a race condition on free_slots so that two threads might get the same value and free_slots. That's (obviously) a bad data race, so people trained in other languages might try to fix it like this:

```
volatile int free_slots = max_slots; // current source of memory for objects

Pool* use()
{
    if (int n = free_slots--) return &pool[n];
}
```

This has no effect on synchronization: The data race is still there!

The C++ mechanism for this is atomic types:

```
atomic<int> free_slots = max_slots; // current source of memory for objects

Pool* use()
{
    if (int n = free_slots--) return &pool[n];
}
```

Now the -- operation is atomic, rather than a read-increment-write sequence where another thread might get inbetween the individual operations.

Alternative

Use atomic types where you might have used volatile in some other language. Use a mutex for more complicated examples.

See also

(rare) proper uses of volatile

CP.9: Whenever feasible use tools to validate your concurrent code

Experience shows that concurrent code is exceptionally hard to get right and that compile-time checking, run-time checks, and testing are less effective at finding concurrency errors than they are at finding errors in sequential code. Subtle concurrency errors can have dramatically bad effects, including memory corruption, deadlocks, and security vulnerabilities.

Example

???

Note

Thread safety is challenging, often getting the better of experienced programmers: tooling is an important strategy to mitigate those risks. There are many tools "out there", both commercial and open-source tools, both research and production tools. Unfortunately people's needs and constraints differ so dramatically that we cannot make specific recommendations, but we can mention:

- Static enforcement tools: both clang and some older versions of GCC have some support for static annotation of thread safety properties. Consistent use of this technique turns many classes of thread-safety errors into compile-time errors. The annotations are generally local (marking a particular member variable as guarded by a particular mutex), and are usually easy to learn. However, as with many static tools, it can often present false negatives; cases that should have been caught but were allowed.
- dynamic enforcement tools: Clang's Thread Sanitizer (aka TSAN) is a powerful example of dynamic tools: it changes the build and execution of your program to add bookkeeping on memory access, absolutely identifying data races in a given execution of your binary. The cost for this is both memory (5-10x in most cases) and CPU slowdown (2-20x). Dynamic tools like this are best when applied to integration tests, canary pushes, or unit tests that operate on multiple threads. Workload matters: When TSAN identifies a problem, it is effectively always an actual data race, but it can only identify races seen in a given execution.

Enforcement

It is up to an application builder to choose which support tools are valuable for a particular application.

CP.con: Concurrency

This section focuses on relatively ad-hoc uses of multiple threads communicating through shared data.

- For parallel algorithms, see parallelism
- For inter-task communication without explicit sharing, see messaging
- For vector parallel code, see vectorization

• For lock-free programming, see lock free

Concurrency rule summary:

- CP.20: Use RAII, never plain lock()/unlock()
- CP.21: Use std::lock() or std::scoped_lock to acquire multiple mutexes
- CP.22: Never call unknown code while holding a lock (e.g., a callback)
- CP.23: Think of a joining thread as a scoped container
- CP.24: Think of a thread as a global container
- CP.25: Prefer gsl::joining_thread over std::thread
- CP.26: Don't detach() a thread
- CP.31: Pass small amounts of data between threads by value, rather than by reference or pointer
- CP.32: To share ownership between unrelated threads use shared_ptr
- CP.40: Minimize context switching
- CP.41: Minimize thread creation and destruction
- CP.42: Don't wait without a condition
- CP.43: Minimize time spent in a critical section
- CP.44: Remember to name your lock_guards and unique_locks
- CP.50: Define a mutex together with the data it guards. Use synchronized_value<T> where possible
- ??? when to use a spinlock
- ??? when to use try_lock()
- ??? when to prefer lock_guard over unique_lock
- ??? Time multiplexing
- ??? when/how to use new thread

CP.20: Use RAII, never plain Lock()/unlock()

Reason

Avoids nasty errors from unreleased locks.

Example, bad

```
mutex mtx;

void do_stuff()
{
    mtx.lock();
    // ... do stuff ...
    mtx.unlock();
}
```

Sooner or later, someone will forget the mtx.unlock(), place a return in the ... do stuff ..., throw an exception, or something.

```
mutex mtx;

void do_stuff()
{
    unique_lock<mutex> lck {mtx};
    // ... do stuff ...
}
```

Enforcement

Flag calls of member lock() and unlock(). ???

CP.21: Use std::lock() or std::scoped_lock to acquire multiple mutexes

Reason

To avoid deadlocks on multiple mutexes.

Example

This is asking for deadlock:

```
// thread 1
lock_guard<mutex> lck1(m1);
lock_guard<mutex> lck2(m2);

// thread 2
lock_guard<mutex> lck2(m2);
lock_guard<mutex> lck2(m2);
```

Instead, use lock():

```
// thread 1
lock(m1, m2);
lock_guard<mutex> lck1(m1, adopt_lock);
lock_guard<mutex> lck2(m2, adopt_lock);

// thread 2
lock(m2, m1);
lock_guard<mutex> lck2(m2, adopt_lock);
lock_guard<mutex> lck2(m2, adopt_lock);
lock_guard<mutex> lck1(m1, adopt_lock);
```

or (better, but C++17 only):

```
// thread 1
scoped_lock<mutex, mutex> lck1(m1, m2);

// thread 2
scoped_lock<mutex, mutex> lck2(m2, m1);
```

Here, the writers of thread1 and thread2 are still not agreeing on the order of the mutexes, but order no longer matters.

Note

In real code, mutexes are rarely named to conveniently remind the programmer of an intended relation and intended order of acquisition. In real code, mutexes are not always conveniently acquired on consecutive lines.

Note

In C++17 it's possible to write plain

```
lock_guard lck1(m1, adopt_lock);
```

and have the mutex type deduced.

Enforcement

Detect the acquisition of multiple mutexes. This is undecidable in general, but catching common simple examples (like the one above) is easy.

CP.22: Never call unknown code while holding a lock (e.g., a callback)

Reason

If you don't know what a piece of code does, you are risking deadlock.

Example

```
void do_this(Foo* p)
{
    lock_guard<mutex> lck {my_mutex};
    // ... do something ...
    p->act(my_data);
    // ...
}
```

If you don't know what Foo::act does (maybe it is a virtual function invoking a derived class member of a class not yet written), it might call do_this (recursively) and cause a deadlock on my_mutex. Maybe it will lock on a different mutex and not return in a reasonable time, causing delays to any code calling do_this.

Example

A common example of the "calling unknown code" problem is a call to a function that tries to gain locked access to the same object. Such problem can often be solved by using a recursive_mutex. For example:

```
recursive_mutex my_mutex;

template<typename Action>
void do_something(Action f)
{
    unique_lock<recursive_mutex> lck {my_mutex};
    // ... do something ...
    f(this); // f will do something to *this
    // ...
}
```

If, as it is likely, f() invokes operations on *this, we must make sure that the object's invariant holds before the call.

Enforcement

- Flag calling a virtual function with a non-recursive mutex held
- Flag calling a callback with a non-recursive mutex held

CP.23: Think of a joining thread as a scoped container

Reason

To maintain pointer safety and avoid leaks, we need to consider what pointers are used by a thread. If a thread joins, we can safely pass pointers to objects in the scope of the thread and its enclosing scopes.

Example

```
joining_thread t3(f, q.get()); // OK
// ...
}
```

A gsl::joining_thread is a std::thread with a destructor that joins and that cannot be detached(). By "OK" we mean that the object will be in scope ("live") for as long as a thread can use the pointer to it. The fact that threads run concurrently doesn't affect the lifetime or ownership issues here; these threads can be seen as just a function object called from some_fct.

Enforcement

Ensure that joining_threads don't detach(). After that, the usual lifetime and ownership (for local objects) enforcement applies.

CP.24: Think of a thread as a global container

Reason

To maintain pointer safety and avoid leaks, we need to consider what pointers are used by a thread. If a thread is detached, we can safely pass pointers to static and free store objects (only).

Example

```
void f(int* p)
    // ...
    *p = 99;
    // ...
}
int glob = 33;
void some_fct(int* p)
{
    int x = 77;
    std::thread t0(f, &x);
                                      // bad
    std::thread t1(f, p);
                                      // bad
    std::thread t2(f, &glob);
                                      // OK
    auto q = make_unique<int>(99);
    std::thread t3(f, q.get());
                                      // bad
    // ...
    t0.detach();
    t1.detach();
    t2.detach();
    t3.detach();
    // ...
}
```

By "OK" we mean that the object will be in scope ("live") for as long as a thread can use the pointers to it. By "bad" we mean that a thread might use a pointer after the pointed-to object is destroyed. The fact that threads run concurrently doesn't affect the lifetime or ownership issues here; these threads can be seen as just a function object called from some_fct.

Note

Even objects with static storage duration can be problematic if used from detached threads: if the thread continues until the end of the program, it might be running concurrently with the destruction of objects with static storage duration, and thus accesses to such objects might race.

Note

This rule is redundant if you don't detach() and use gsl::joining_thread. However, converting code to follow those guidelines could be difficult and even impossible for third-party libraries. In such cases, the rule becomes essential for lifetime safety and type safety.

In general, it is undecidable whether a detach() is executed for a thread, but simple common cases are easily detected. If we cannot prove that a thread does not detach(), we must assume that it does and that it outlives the scope in which it was constructed; After that, the usual lifetime and ownership (for global objects) enforcement applies.

Enforcement

Flag attempts to pass local variables to a thread that might detach().

CP.25: Prefer gsl::joining_thread over std::thread

Reason

A joining_thread is a thread that joins at the end of its scope. Detached threads are hard to monitor. It is harder to ensure absence of errors in detached threads (and potentially detached threads).

Example, bad

Example

Note

Make "immortal threads" globals, put them in an enclosing scope, or put them on the free store rather than detach(). Don't detach.

Note

Because of old code and third party libraries using std::thread, this rule can be hard to introduce.

Enforcement

Flag uses of std::thread:

- Suggest use of gsl::joining_thread or C++20 std::jthread.
- Suggest "exporting ownership" to an enclosing scope if it detaches.
- Warn if it is not obvious whether a thread joins or detaches.

CP.26: Don't detach() a thread

Reason

Often, the need to outlive the scope of its creation is inherent in the threads task, but implementing that idea by detach makes it harder to monitor and communicate with the detached thread. In particular, it is harder (though not impossible) to ensure that the thread completed as expected or lives for as long as expected.

Example

This is a reasonable use of a thread, for which detach() is commonly used. There are problems, though. How do we monitor the detached thread to see if it is alive? Something might go wrong with the heartbeat, and losing a heartbeat can be very serious in a system for which it is needed. So, we need to communicate with the heartbeat thread (e.g., through a stream of messages or notification events using a condition_variable).

An alternative, and usually superior solution is to control its lifetime by placing it in a scope outside its point of creation (or activation). For example:

```
void heartbeat();
gsl::joining_thread t(heartbeat);  // heartbeat is meant to run "forever"
```

This heartbeat will (barring error, hardware problems, etc.) run for as long as the program does.

Sometimes, we need to separate the point of creation from the point of ownership:

```
void heartbeat();
unique_ptr<gsl::joining_thread> tick_tock {nullptr};

void use()
{
    // heartbeat is meant to run as long as tick_tock lives
    tick_tock = make_unique<gsl::joining_thread>(heartbeat);
    // ...
}
```

Enforcement

Flag detach().

CP.31: Pass small amounts of data between threads by value, rather than by reference or pointer

Reason

A small amount of data is cheaper to copy and access than to share it using some locking mechanism. Copying naturally gives unique ownership (simplifies code) and eliminates the possibility of data races.

Note

Defining "small amount" precisely is impossible.

Example

```
string modify1(string);
void modify2(string&);

void fct(string& s)
{
   auto res = async(modify1, s);
   async(modify2, s);
}
```

The call of modify1 involves copying two string values; the call of modify2 does not. On the other hand, the implementation of modify1 is exactly as we would have written it for single-threaded code, whereas the implementation of modify2 will need some form of locking to avoid data races. If the string is short (say 10 characters), the call of modify1 can be surprisingly fast; essentially all the cost is in the thread switch. If the string is long (say 1,000,000 characters), copying it twice is probably not a good idea.

Note that this argument has nothing to do with async as such. It applies equally to considerations about whether to use message passing or shared memory.

Enforcement

???

CP.32: To share ownership between unrelated threads use shared_ptr

Reason

If threads are unrelated (that is, not known to be in the same scope or one within the lifetime of the other) and they need to share free store memory that needs to be deleted, a shared_ptr (or equivalent) is the only safe way to ensure proper deletion.

Example

???

Note

- A static object (e.g. a global) can be shared because it is not owned in the sense that some thread is responsible for its deletion.
- An object on free store that is never to be deleted can be shared.
- An object owned by one thread can be safely shared with another as long as that second thread doesn't outlive the owner.

Enforcement

???

CP.40: Minimize context switching

Reason

Context switches are expensive.

Example

???

Enforcement

???

CP.41: Minimize thread creation and destruction

Reason

Thread creation is expensive.

Example

```
void worker(Message m)
{
    // process
}

void dispatcher(istream& is)
{
    for (Message m; is >> m; )
        run_list.push_back(new thread(worker, m));
}
```

This spawns a thread per message, and the run_list is presumably managed to destroy those tasks once they are finished.

Instead, we could have a set of pre-created worker threads processing the messages

```
Sync_queue<Message> work;
void dispatcher(istream& is)
   for (Message m; is >> m; )
        work.put(m);
}
void worker()
   for (Message m; m = work.get(); ) {
        // process
    }
}
void workers() // set up worker threads (specifically 4 worker threads)
   joining_thread w1 {worker};
   joining_thread w2 {worker};
   joining_thread w3 {worker};
   joining_thread w4 {worker};
}
```

Note

If your system has a good thread pool, use it. If your system has a good message queue, use it.

Enforcement

CP.42: Don't wait without a condition

Reason

A wait without a condition can miss a wakeup or wake up simply to find that there is no work to do.

Example, bad

```
std::condition_variable cv;
std::mutex mx;
void thread1()
   while (true) {
       // do some work ...
        std::unique_lock<std::mutex> lock(mx);
       cv.notify one();  // wake other thread
   }
}
void thread2()
   while (true) {
        std::unique_lock<std::mutex> lock(mx);
        cv.wait(lock); // might block forever
       // do work ...
   }
}
```

Here, if some other thread consumes thread1's notification, thread2 can wait forever.

Example

```
template<typename T>
class Sync_queue {
public:
   void put(const T& val);
   void put(T&& val);
   void get(T& val);
private:
   mutex mtx;
   condition_variable cond; // this controls access
   list<T> q;
};
template<typename T>
void Sync_queue<T>::put(const T& val)
    lock_guard<mutex> lck(mtx);
    q.push back(val);
    cond.notify_one();
```

```
template<typename T>
void Sync_queue<T>::get(T& val)
{
   unique_lock<mutex> lck(mtx);
   cond.wait(lck, [this] { return !q.empty(); }); // prevent spurious wakeup
   val = q.front();
   q.pop_front();
}
```

Now if the queue is empty when a thread executing get() wakes up (e.g., because another thread has gotten to get() before it), it will immediately go back to sleep, waiting.

Enforcement

Flag all waits without conditions.

CP.43: Minimize time spent in a critical section

Reason

The less time is spent with a mutex taken, the less chance that another thread has to wait, and thread suspension and resumption are expensive.

Example

```
void do_something() // bad
{
    unique_lock<mutex> lck(my_lock);
    do0(); // preparation: does not need lock
    do1(); // transaction: needs locking
    do2(); // cleanup: does not need locking
}
```

Here, we are holding the lock for longer than necessary: We should not have taken the lock before we needed it and should have released it again before starting the cleanup. We could rewrite this to

```
void do_something() // bad
{
    do0(); // preparation: does not need lock
    my_lock.lock();
    do1(); // transaction: needs locking
    my_lock.unlock();
    do2(); // cleanup: does not need locking
}
```

But that compromises safety and violates the use RAII rule. Instead, add a block for the critical section:

```
void do_something() // OK
{
    do0(); // preparation: does not need lock
    {
        unique_lock<mutex> lck(my_lock);
        do1(); // transaction: needs locking
    }
    do2(); // cleanup: does not need locking
}
```

Enforcement

Impossible in general. Flag "naked" lock() and unlock().

CP.44: Remember to name your Lock_guards and unique_Locks

Reason

An unnamed local object is a temporary that immediately goes out of scope.

Example

```
// global mutexes
mutex m1;
mutex m2;

void f()
{
    unique_lock<mutex>(m1); // (A)
    lock_guard<mutex> {m2}; // (B)
    // do work in critical section ...
}
```

This looks innocent enough, but it isn't. At (A), m1 is a default-constructed local unique_lock, which shadows the global ::m1 (and does not lock it). At (B) an unnamed temporary lock_guard is constructed and locks ::m2, but immediately goes out of scope and unlocks ::m2 again. For the rest of the function f() neither mutex is locked.

Enforcement

Flag all unnamed lock_guards and unique_locks.

CP.50: Define a mutex together with the data it guards. Use synchronized_value<T> where possible

Reason

It should be obvious to a reader that the data is to be guarded and how. This decreases the chance of the wrong mutex being locked, or the mutex not being locked.

Using a synchronized_value<T> ensures that the data has a mutex, and the right mutex is locked when the data is accessed. See the WG21 proposal to add synchronized_value to a future TS or revision of the C++ standard.

Example

```
struct Record {
    std::mutex m; // take this mutex before accessing other members
    // ...
};

class MyClass {
    struct DataRecord {
        // ...
    };
    synchronized_value<DataRecord> data; // Protect the data with a mutex
};
```

Enforcement

??? Possible?

CP.coro: Coroutines

This section focuses on uses of coroutines.

Coroutine rule summary:

- CP.51: Do not use capturing lambdas that are coroutines
- CP.52: Do not hold locks or other synchronization primitives across suspension points
- CP.53: Parameters to coroutines should not be passed by reference

CP.51: *Do not use capturing lambdas that are coroutines*

Reason

Usage patterns that are correct with normal lambdas are hazardous with coroutine lambdas. The obvious pattern of capturing variables will result in accessing freed memory after the first suspension point, even for refcounted smart pointers and copyable types.

A lambda results in a closure object with storage, often on the stack, that will go out of scope at some point. When the closure object goes out of scope the captures will also go out of scope. Normal lambdas will have finished executing by this time so it is not a problem. Coroutine lambdas may resume from suspension after the closure object has destructed and at that point all captures will be use-after-free memory access.

Example, Bad

```
int value = get_value();
std::shared_ptr<Foo> sharedFoo = get_foo();
{
   const auto lambda = [value, sharedFoo]() -> std::future<void>
   {
      co_await something();
      // "sharedFoo" and "value" have already been destroyed
      // the "shared" pointer didn't accomplish anything
   };
   lambda();
} // the lambda closure object has now gone out of scope
```

Example, Better

```
int value = get_value();
std::shared_ptr<Foo> sharedFoo = get_foo();
{
    // take as by-value parameter instead of as a capture
    const auto lambda = [](auto sharedFoo, auto value) -> std::future<void>
    {
        co_await something();
        // sharedFoo and value are still valid at this point
    };
    lambda(sharedFoo, value);
} // the lambda closure object has now gone out of scope
```

Example, Best

Use a function for coroutines.

```
std::future<void> Class::do_something(int value, std::shared_ptr<Foo> sharedFoo)
{
   co_await something();
   // sharedFoo and value are still valid at this point
}

void SomeOtherFunction()
{
   int value = get_value();
   std::shared_ptr<Foo> sharedFoo = get_foo();
   do_something(value, sharedFoo);
}
```

Enforcement

Flag a lambda that is a coroutine and has a non-empty capture list.

CP.52: Do not hold locks or other synchronization primitives across suspension points

Reason

This pattern creates a significant risk of deadlocks. Some types of waits will allow the current thread to perform additional work until the asynchronous operation has completed. If the thread holding the lock performs work that requires the same lock then it will deadlock because it is trying to acquire a lock that it is already holding.

If the coroutine completes on a different thread from the thread that acquired the lock then that is undefined behavior. Even with an explicit return to the original thread an exception might be thrown before coroutine resumes and the result will be that the lock guard is not destructed.

Example, Bad

```
std::mutex g_lock;

std::future<void> Class::do_something()
{
    std::lock_guard<std::mutex> guard(g_lock);
    co_await something(); // DANGER: coroutine has suspended execution while holding a lock
    co_await somethingElse();
}
```

Example, Good

Note

This pattern is also bad for performance. When a suspension point is reached, such as co_await, execution of the current function stops and other code begins to run. It may be a long period of time before the coroutine resumes. For that entire duration the lock will be held and cannot be acquired by other threads to perform work.

Enforcement

Flag all lock guards that are not destructed before a coroutine suspends.

CP.53: Parameters to coroutines should not be passed by reference

Reason

Once a coroutine reaches the first suspension point, such as a co_await, the synchronous portion returns. After that point any parameters passed by reference are dangling. Any usage beyond that is undefined behavior which may include writing to freed memory.

Example, Bad

```
std::future<int> Class::do_something(const std::shared_ptr<int>& input)
{
    co_await something();

    // DANGER: the reference to input may no longer be valid and may be freed memory
    co_return *input + 1;
}
```

Example, Good

```
std::future<int> Class::do_something(std::shared_ptr<int> input)
{
    co_await something();
    co_return *input + 1; // input is a copy that is still valid here
}
```

Note

This problem does not apply to reference parameters that are only accessed before the first suspension point. Subsequent changes to the function may add or move suspension points which would reintroduce this class of bug. Some types of coroutines have the suspension point before the first line of code in the coroutine executes, in which case reference parameters are always unsafe. It is safer to always pass by value because the copied parameter will live in the coroutine frame that is safe to access throughout the coroutine.

Note

The same danger applies to output parameters. F.20: For "out" output values, prefer return values to output parameters discourages output parameters. Coroutines should avoid them entirely.

Enforcement

Flag all reference parameters to a coroutine.

CP.par: Parallelism

By "parallelism" we refer to performing a task (more or less) simultaneously ("in parallel with") on many data items.

Parallelism rule summary:

- **???**
- **???**
- Where appropriate, prefer the standard-library parallel algorithms
- Use algorithms that are designed for parallelism, not algorithms with unnecessary dependency on linear evaluation

CP.mess: Message passing

The standard-library facilities are quite low-level, focused on the needs of close-to the hardware critical programming using threads, mutexes, atomic types, etc. Most people shouldn't work at this level: it's error-prone and development is slow. If possible, use a higher level facility: messaging libraries, parallel algorithms, and vectorization. This section looks at passing messages so that a programmer doesn't have to do explicit synchronization.

Message passing rules summary:

- CP.60: Use a future to return a value from a concurrent task
- CP.61: Use async() to spawn concurrent tasks
- message queues
- messaging libraries

???? should there be a "use X rather than std::async" where X is something that would use a better specified thread pool?

??? Is std::async worth using in light of future (and even existing, as libraries) parallelism facilities? What should the guidelines recommend if someone wants to parallelize, e.g., std::accumulate (with the additional precondition of commutativity), or merge sort?

CP.60: Use a future to return a value from a concurrent task

Reason

A future preserves the usual function call return semantics for asynchronous tasks. There is no explicit locking and both correct (value) return and error (exception) return are handled simply.

Example

555

Note

???

Enforcement

???

CP.61: Use async() to spawn concurrent tasks

Reason

Similar to R.12, which tells you to avoid raw owning pointers, you should also avoid raw threads and raw promises where possible. Use a factory function such as std::async, which handles spawning or reusing a thread without exposing raw threads to your own code.

Example

```
int read_value(const std::string& filename)
{
   std::ifstream in(filename);
   in.exceptions(std::ifstream::failbit);
   int value;
   in >> value;
   return value;
}
void async_example()
{
   try {
        std::future<int> f1 = std::async(read_value, "v1.txt");
        std::future<int> f2 = std::async(read_value, "v2.txt");
        std::cout << f1.get() + f2.get() << '\n';
   } catch (const std::ios_base::failure& fail) {
        // handle exception here
    }
}
```

Note

Unfortunately, std::async is not perfect. For example, it doesn't use a thread pool, which means that it might fail due to resource exhaustion, rather than queuing up your tasks to be executed later. However, even if you cannot use std::async, you should prefer to write your own future-returning factory function, rather than using raw promises.

Example (bad)

This example shows two different ways to succeed at using std::future, but to fail at avoiding raw std::thread management.

```
void async_example()
{
    std::promise<int> p1;
    std::future<int> f1 = p1.get_future();
    std::thread t1([p1 = std::move(p1)]() mutable {
        p1.set_value(read_value("v1.txt"));
    });
    t1.detach(); // evil

std::packaged_task<int()> pt2(read_value, "v2.txt");
    std::future<int> f2 = pt2.get_future();
    std::thread(std::move(pt2)).detach();

std::cout << f1.get() + f2.get() << '\n';
}</pre>
```

Example (good)

This example shows one way you could follow the general pattern set by std::async, in a context where std::async itself was unacceptable for use in production.

```
void async_example(WorkQueue& wq)
{
    std::future<int> f1 = wq.enqueue([]() {
        return read_value("v1.txt");
    });
    std::future<int> f2 = wq.enqueue([]() {
        return read_value("v2.txt");
    });
    std::cout << f1.get() + f2.get() << '\n';
}</pre>
```

Any threads spawned to execute the code of read_value are hidden behind the call to WorkQueue::enqueue. The user code deals only with future objects, never with raw thread, promise, or packaged_task objects.

Enforcement

???

CP.vec: Vectorization

Vectorization is a technique for executing a number of tasks concurrently without introducing explicit synchronization. An operation is simply applied to elements of a data structure (a vector, an array, etc.) in parallel. Vectorization has the interesting property of often requiring no non-local changes to a program. However, vectorization works best with simple data structures and with algorithms specifically crafted to enable it.

Vectorization rule summary:

- **???**
- ???

CP.free: Lock-free programming

Synchronization using mutexes and condition_variables can be relatively expensive. Furthermore, it can lead to deadlock. For performance and to eliminate the possibility of deadlock, we sometimes have to use the tricky low-level "lock-free" facilities that rely on briefly gaining exclusive ("atomic") access to memory. Lock-free programming is also used to implement higher-level concurrency mechanisms, such as threads and mutexes.

Lock-free programming rule summary:

- CP.100: Don't use lock-free programming unless you absolutely have to
- CP.101: Distrust your hardware/compiler combination
- CP.102: Carefully study the literature

- how/when to use atomics
- avoid starvation
- use a lock-free data structure rather than hand-crafting specific lock-free access
- CP.110: Do not write your own double-checked locking for initialization
- CP.111: Use a conventional pattern if you really need double-checked locking
- how/when to compare and swap

CP.100: Don't use lock-free programming unless you absolutely have to

Reason

It's error-prone and requires expert level knowledge of language features, machine architecture, and data structures.

Example, bad

Spot the bug. It would be really hard to find through testing. Read up on the ABA problem.

Exception

Atomic variables can be used simply and safely, as long as you are using the sequentially consistent memory model (memory_order_seq_cst), which is the default.

Note

Higher-level concurrency mechanisms, such as threads and mutexes are implemented using lock-free programming.

Alternative: Use lock-free data structures implemented by others as part of some library.

CP.101: Distrust your hardware/compiler combination

Reason

The low-level hardware interfaces used by lock-free programming are among the hardest to implement well and among the areas where the most subtle portability problems occur. If you are doing lock-free programming for performance, you need to check for regressions.

Note

Instruction reordering (static and dynamic) makes it hard for us to think effectively at this level (especially if you use relaxed memory models). Experience, (semi)formal models and model checking can be useful. Testing - often to an extreme extent - is essential. "Don't fly too close to the sun."

Enforcement

Have strong rules for re-testing in place that covers any change in hardware, operating system, compiler, and libraries.

*CP.*102: *Carefully study the literature*

Reason

With the exception of atomics and a few other standard patterns, lock-free programming is really an expert-only topic. Become an expert before shipping lock-free code for others to use.

References

- Anthony Williams: C++ concurrency in action. Manning Publications.
- Boehm, Adve, You Don't Know Jack About Shared Variables or Memory Models, Communications of the ACM, Feb 2012.
- Boehm, "Threads Basics", HPL TR 2009-259.
- Adve, Boehm, "Memory Models: A Case for Rethinking Parallel Languages and Hardware", Communications of the ACM, August 2010.
- Boehm, Adve, "Foundations of the C++ Concurrency Memory Model", PLDI 08.
- Mark Batty, Scott Owens, Susmit Sarkar, Peter Sewell, and Tjark Weber, "Mathematizing C++ Concurrency", POPI 2011
- Damian Dechev, Peter Pirkelbauer, and Bjarne Stroustrup: Understanding and Effectively Preventing the ABA Problem in Descriptor-based Lock-free Designs. 13th IEEE Computer Society ISORC 2010 Symposium. May 2010.
- Damian Dechev and Bjarne Stroustrup: Scalable Non-blocking Concurrent Objects for Mission Critical Code.
 ACM OOPSLA'09. October 2009
- Damian Dechev, Peter Pirkelbauer, Nicolas Rouquette, and Bjarne Stroustrup: Semantically Enhanced Containers for Concurrent Real-Time Systems. Proc. 16th Annual IEEE International Conference and Workshop on the Engineering of Computer Based Systems (IEEE ECBS). April 2009.
- Maurice Herlihy, Nir Shavit, Victor Luchangco, Michael Spear, "The Art of Multiprocessor Programming", 2nd ed. September 2020

CP.110: Do not write your own double-checked locking for initialization

Reason

Since C++11, static local variables are now initialized in a thread-safe way. When combined with the RAII pattern, static local variables can replace the need for writing your own double-checked locking for initialization. std::call_once can also achieve the same purpose. Use either static local variables of C++11 or std::call_once instead of writing your own double-checked locking for initialization.

Example

Example with std::call_once.

```
void f()
{
    static std::once_flag my_once_flag;
    std::call_once(my_once_flag, []()
    {
        // do this only once
    });
    // ...
}
```

Example with thread-safe static local variables of C++11.

Enforcement

??? Is it possible to detect the idiom?

CP.111: Use a conventional pattern if you really need double-checked locking

Reason

Double-checked locking is easy to mess up. If you really need to write your own double-checked locking, in spite of the rules CP.110: Do not write your own double-checked locking for initialization and CP.100: Don't use lock-free programming unless you absolutely have to, then do it in a conventional pattern.

The uses of the double-checked locking pattern that are not in violation of CP.110: Do not write your own double-checked locking for initialization arise when a non-thread-safe action is both hard and rare, and there exists a fast thread-safe test that can be used to guarantee that the action is not needed, but cannot be used to guarantee the converse.

Example, bad

The use of volatile does not make the first check thread-safe, see also CP.200: Use volatile only to talk to non-C++ memory

```
mutex action_mutex;
volatile bool action_needed;

if (action_needed) {
    std::lock_guard<std::mutex> lock(action_mutex);
    if (action_needed) {
        take_action();
        action_needed = false;
    }
}
```

Example, good

```
mutex action_mutex;
atomic<bool> action_needed;

if (action_needed) {
    std::lock_guard<std::mutex> lock(action_mutex);
    if (action_needed) {
        take_action();
        action_needed = false;
    }
}
```

Fine-tuned memory order might be beneficial where acquire load is more efficient than sequentially-consistent load

```
mutex action_mutex;
atomic<bool> action_needed;

if (action_needed.load(memory_order_acquire)) {
    lock_guard<std::mutex> lock(action_mutex);
    if (action_needed.load(memory_order_relaxed)) {
        take_action();
        action_needed.store(false, memory_order_release);
    }
}
```

Enforcement

??? Is it possible to detect the idiom?

CP.etc: Etc. concurrency rules

These rules defy simple categorization:

- CP.200: Use volatile only to talk to non-C++ memory
- CP.201: ??? Signals

CP.200: Use volatile only to talk to non-C++ memory

Reason

volatile is used to refer to objects that are shared with "non-C++" code or hardware that does not follow the C++ memory model.

Example

```
const volatile long clock;
```

This describes a register constantly updated by a clock circuit. clock is volatile because its value will change without any action from the C++ program that uses it. For example, reading clock twice will often yield two different values, so the optimizer had better not optimize away the second read in this code:

```
long t1 = clock;
// ... no use of clock here ...
long t2 = clock;
```

clock is const because the program should not try to write to clock.

Note

Unless you are writing the lowest level code manipulating hardware directly, consider volatile an esoteric feature that is best avoided.

Example

Usually C++ code receives volatile memory that is owned elsewhere (hardware or another language):

```
int volatile* vi = get_hardware_memory_location();
   // note: we get a pointer to someone else's memory here
   // volatile says "treat this with extra respect"
```

Sometimes C++ code allocates the volatile memory and shares it with "elsewhere" (hardware or another language) by deliberately escaping a pointer:

```
static volatile long vl;
please_use_this(&vl); // escape a reference to this to "elsewhere" (not C++)
```

Example, bad

volatile local variables are nearly always wrong -- how can they be shared with other languages or hardware if they're ephemeral? The same applies almost as strongly to member variables, for the same reason.

```
void f()
{
    volatile int i = 0; // bad, volatile local variable
    // etc.
}

class My_type {
    volatile int i = 0; // suspicious, volatile member variable
    // etc.
};
```

Note

In C++, unlike in some other languages, volatile has nothing to do with synchronization.

Enforcement

- Flag volatile T local and member variables; almost certainly you intended to use atomic<T> instead.
- **???**

CP.201: ??? Signals

???UNIX signal handling???. Might be worth reminding how little is async-signal-safe, and how to communicate with a signal handler (best is probably "not at all")

E: Error handling

Error handling involves:

- Detecting an error
- Transmitting information about an error to some handler code
- Preserving a valid state of the program
- Avoiding resource leaks

It is not possible to recover from all errors. If recovery from an error is not possible, it is important to quickly "get out" in a well-defined way. A strategy for error handling must be simple, or it becomes a source of even worse errors. Untested and rarely executed error-handling code is itself the source of many bugs.

The rules are designed to help avoid several kinds of errors:

- Type violations (e.g., misuse of unions and casts)
- Resource leaks (including memory leaks)
- Bounds errors
- Lifetime errors (e.g., accessing an object after it has been deleted)
- Complexity errors (logical errors made likely by overly complex expression of ideas)
- Interface errors (e.g., an unexpected value is passed through an interface)

Error-handling rule summary:

- E.1: Develop an error-handling strategy early in a design
- E.2: Throw an exception to signal that a function can't perform its assigned task
- E.3: Use exceptions for error handling only
- E.4: Design your error-handling strategy around invariants
- E.5: Let a constructor establish an invariant, and throw if it cannot
- E.6: Use RAII to prevent leaks
- E.7: State your preconditions
- E.8: State your postconditions
- E.12: Use noexcept when exiting a function because of a throw is impossible or unacceptable
- E.13: Never throw while being the direct owner of an object
- E.14: Use purpose-designed user-defined types as exceptions (not built-in types)
- E.15: Throw by value, catch exceptions from a hierarchy by reference
- E.16: Destructors, deallocation, swap, and exception type copy/move construction must never fail
- E.17: Don't try to catch every exception in every function
- E.18: Minimize the use of explicit try/catch
- E.19: Use a final_action object to express cleanup if no suitable resource handle is available
- E.25: If you can't throw exceptions, simulate RAII for resource management
- E.26: If you can't throw exceptions, consider failing fast

- E.27: If you can't throw exceptions, use error codes systematically
- E.28: Avoid error handling based on global state (e.g. errno)
- E.30: Don't use exception specifications
- E.31: Properly order your catch-clauses

E.1: Develop an error-handling strategy early in a design

Reason

A consistent and complete strategy for handling errors and resource leaks is hard to retrofit into a system.

E.2: Throw an exception to signal that a function can't perform its assigned task

Reason

To make error handling systematic, robust, and non-repetitive.

Example

```
struct Foo {
   vector<Thing> v;
   File_handle f;
   string s;
};

void use()
{
   Foo bar {{Thing{1}, Thing{2}, Thing{monkey}}, {"my_file", "r"}, "Here we go!"};
   // ...
}
```

Here, vector and strings constructors might not be able to allocate sufficient memory for their elements, vectors constructor might not be able to copy the Things in its initializer list, and File_handle might not be able to open the required file. In each case, they throw an exception for use()'s caller to handle. If use() could handle the failure to construct bar it can take control using try/catch. In either case, Foo's constructor correctly destroys constructed members before passing control to whatever tried to create a Foo. Note that there is no return value that could contain an error code.

The File_handle constructor might be defined like this:

```
File_handle::File_handle(const string& name, const string& mode)
    : f{fopen(name.c_str(), mode.c_str())}
{
    if (!f)
        throw runtime_error{"File_handle: could not open " + name + " as " + mode};
}
```

Note

It is often said that exceptions are meant to signal exceptional events and failures. However, that's a bit circular because "what is exceptional?" Examples:

- A precondition that cannot be met
- A constructor that cannot construct an object (failure to establish its class's invariant)
- An out-of-range error (e.g., v[v.size()] = 7)
- Inability to acquire a resource (e.g., the network is down)

In contrast, termination of an ordinary loop is not exceptional. Unless the loop was meant to be infinite, termination is normal and expected.

Note

Don't use a throw as simply an alternative way of returning a value from a function.

Exception

Some systems, such as hard-real-time systems require a guarantee that an action is taken in a (typically short) constant maximum time known before execution starts. Such systems can use exceptions only if there is tool support for accurately predicting the maximum time to recover from a throw.

See also: RAII

See also: discussion

Note

Before deciding that you cannot afford or don't like exception-based error handling, have a look at the alternatives; they have their own complexities and problems. Also, as far as possible, measure before making claims about efficiency.

E.3: Use exceptions for error handling only

Reason

To keep error handling separated from "ordinary code." C++ implementations tend to be optimized based on the assumption that exceptions are rare.

Example, don't

```
// don't: exception not used for error handling
int find_index(vector<string>& vec, const string& x)
{
    try {
        for (gsl::index i = 0; i < vec.size(); ++i)
            if (vec[i] == x) throw i; // found x
    }
    catch (int i) {
        return i;
    }
    return -1; // not found
}</pre>
```

This is more complicated and most likely runs much slower than the obvious alternative. There is nothing exceptional about finding a value in a vector.

Enforcement

Would need to be heuristic. Look for exception values "leaked" out of catch clauses.

E.4: Design your error-handling strategy around invariants

Reason

To use an object it must be in a valid state (defined formally or informally by an invariant) and to recover from an error every object not destroyed must be in a valid state.

Note

An invariant is a logical condition for the members of an object that a constructor must establish for the public member functions to assume.

Enforcement

???

E.5: Let a constructor establish an invariant, and throw if it cannot

Reason

Leaving an object without its invariant established is asking for trouble. Not all member functions can be called.

Example

```
class Vector { // very simplified vector of doubles
    // if elem != nullptr then elem points to sz doubles
public:
    Vector() : elem{nullptr}, sz{0}{}
    Vector(int s) : elem{new double[s]}, sz{s} { /* initialize elements */ }
    ~Vector() { delete [] elem; }
    double& operator[](int s) { return elem[s]; }
    // ...
private:
    owner<double*> elem;
    int sz;
};
```

The class invariant - here stated as a comment - is established by the constructors. new throws if it cannot allocate the required memory. The operators, notably the subscript operator, rely on the invariant.

See also: If a constructor cannot construct a valid object, throw an exception

Enforcement

Flag classes with private state without a constructor (public, protected, or private).

E.6: Use RAII to prevent leaks

Reason

Leaks are typically unacceptable. Manual resource release is error-prone. RAII ("Resource Acquisition Is Initialization") is the simplest, most systematic way of preventing leaks.

Example

```
void f1(int i)  // Bad: possible leak
{
   int* p = new int[12];
   // ...
   if (i < 17) throw Bad{"in f()", i};
   // ...
}</pre>
```

We could carefully release the resource before the throw:

```
void f2(int i)  // Clumsy and error-prone: explicit release
{
    int* p = new int[12];
    // ...
    if (i < 17) {
        delete[] p;
        throw Bad{"in f()", i};
    }
    // ...
}</pre>
```

This is verbose. In larger code with multiple possible throws explicit releases become repetitive and error-prone.

```
void f3(int i) // OK: resource management done by a handle (but see below)
{
   auto p = make_unique<int[]>(12);
   // ...
   if (i < 17) throw Bad{"in f()", i};
   // ...
}</pre>
```

Note that this works even when the throw is implicit because it happened in a called function:

```
void f4(int i) // OK: resource management done by a handle (but see below)
{
    auto p = make_unique<int[]>(12);
    // ...
    helper(i); // might throw
    // ...
}
```

Unless you really need pointer semantics, use a local resource object:

```
void f5(int i) // OK: resource management done by local object
{
    vector<int> v(12);
    // ...
    helper(i); // might throw
    // ...
}
```

That's even simpler and safer, and often more efficient.

Note

If there is no obvious resource handle and for some reason defining a proper RAII object/handle is infeasible, as a last resort, cleanup actions can be represented by a final_action object.

Note

But what do we do if we are writing a program where exceptions cannot be used? First challenge that assumption; there are many anti-exceptions myths around. We know of only a few good reasons:

- We are on a system so small that the exception support would eat up most of our 2K memory.
- We are in a hard-real-time system and we don't have tools that guarantee us that an exception is handled within the required time.
- We are in a system with tons of legacy code using lots of pointers in difficult-to-understand ways (in particular without a recognizable ownership strategy) so that exceptions could cause leaks.
- Our implementation of the C++ exception mechanisms is unreasonably poor (slow, memory consuming, failing to work correctly for dynamically linked libraries, etc.). Complain to your implementation purveyor; if no user complains, no improvement will happen.
- We get fired if we challenge our manager's ancient wisdom.

Only the first of these reasons is fundamental, so whenever possible, use exceptions to implement RAII, or design your RAII objects to never fail. When exceptions cannot be used, simulate RAII. That is, systematically check that objects are valid after construction and still release all resources in the destructor. One strategy is to add a valid() operation to every resource handle:

Obviously, this increases the size of the code, doesn't allow for implicit propagation of "exceptions" (valid() checks), and valid() checks can be forgotten. Prefer to use exceptions.

See also: Use of noexcept

Enforcement

E.7: State your preconditions

Reason

To avoid interface errors.

See also: precondition rule

E.8: State your postconditions

Reason

To avoid interface errors.

See also: postcondition rule

E.12: Use noexcept when exiting a function because of a throw is impossible or unacceptable

Reason

To make error handling systematic, robust, and efficient.

Example

```
double compute(double d) noexcept
{
    return log(sqrt(d <= 0 ? 1 : d));
}</pre>
```

Here, we know that compute will not throw because it is composed out of operations that don't throw. By declaring compute to be noexcept, we give the compiler and human readers information that can make it easier for them to understand and manipulate compute.

Note

Many standard-library functions are noexcept including all the standard-library functions "inherited" from the C Standard Library.

Example

```
vector<double> munge(const vector<double>& v) noexcept
{
    vector<double> v2(v.size());
    // ... do something ...
}
```

The noexcept here states that I am not willing or able to handle the situation where I cannot construct the local vector. That is, I consider memory exhaustion a serious design error (on par with hardware failures) so that I'm willing to crash the program if it happens.

Note

Do not use traditional exception-specifications.

See also

discussion.

E.13: Never throw while being the direct owner of an object

Reason

That would be a leak.

Example

```
void leak(int x) // don't: might leak
{
   auto p = new int{7};
   if (x < 0) throw Get_me_out_of_here{}; // might leak *p
   // ...
   delete p; // we might never get here
}</pre>
```

One way of avoiding such problems is to use resource handles consistently:

```
void no_leak(int x)
{
   auto p = make_unique<int>(7);
   if (x < 0) throw Get_me_out_of_here{}; // will delete *p if necessary
   // ...
   // no need for delete p
}</pre>
```

Another solution (often better) would be to use a local variable to eliminate explicit use of pointers:

```
void no_leak_simplified(int x)
{
    vector<int> v(7);
    // ...
}
```

Note

If you have a local "thing" that requires cleanup, but is not represented by an object with a destructor, such cleanup must also be done before a throw. Sometimes, finally() can make such unsystematic cleanup a bit more manageable.

E.14: Use purpose-designed user-defined types as exceptions (not built-in types)

Reason

A user-defined type can better transmit information about an error to a handler. Information can be encoded into the type itself and the type is unlikely to clash with other people's exceptions.

Example

```
throw 7; // bad
throw "something bad"; // bad
throw std::exception{}; // bad - no info
```

Deriving from std::exception gives the flexibility to catch the specific exception or handle generally through std::exception:

```
class MyException : public std::runtime_error
{
  public:
    MyException(const string& msg) : std::runtime_error{msg} {}
    // ...
};

// ...
throw MyException{"something bad"}; // good
```

Exceptions do not need to be derived from std::exception:

```
class MyCustomError final {}; // not derived from std::exception

// ...

throw MyCustomError{}; // good - handlers must catch this type (or ...)
```

Library types derived from std::exception can be used as generic exceptions if no useful information can be added at the point of detection:

```
throw std::runtime_error("someting bad"); // good

// ...

throw std::invalid_argument("i is not even"); // good
```

enum classes are also allowed:

```
enum class alert {RED, YELLOW, GREEN};
throw alert::RED; // good
```

Enforcement

Catch throw of built-in types and std::exception.

E.15: Throw by value, catch exceptions from a hierarchy by reference

Reason

Throwing by value (not by pointer) and catching by reference prevents copying, especially slicing base subobjects.

Example; bad

```
void f()
{
    try {
        // ...
        throw new widget{}; // don't: throw by value not by raw pointer
        // ...
    }
    catch (base_class e) { // don't: might slice
        // ...
    }
}
```

Instead, use a reference:

```
catch (base_class& e) { /* ... */ }
```

or - typically better still - a const reference:

```
catch (const base_class& e) { /* ... */ }
```

Most handlers do not modify their exception and in general we recommend use of const.

Note

Catch by value can be appropriate for a small value type such as an enum value.

Note

To rethrow a caught exception use throw; not throw e; Using throw e; would throw a new copy of e (sliced to the static type std::exception, when the exception is caught by catch (const std::exception& e)) instead of rethrowing the original exception of type std::runtime_error. (But keep Don't try to catch every exception in every function and Minimize the use of explicit try/catch in mind.)

Enforcement

- Flag catching by value of a type that has a virtual function.
- Flag throwing raw pointers.

E.16: Destructors, deallocation, swap, and exception type copy/move construction must never fail

Reason

We don't know how to write reliable programs if a destructor, a swap, a memory deallocation, or attempting to copy/move-construct an exception object fails; that is, if it exits by an exception or simply doesn't perform its required action.

Example, don't

```
class Connection {
    // ...
public:
    ~Connection() // Don't: very bad destructor
    {
        if (cannot_disconnect()) throw I_give_up{information};
        // ...
    }
};
```

Note

Many have tried to write reliable code violating this rule for examples, such as a network connection that "refuses to close". To the best of our knowledge nobody has found a general way of doing this. Occasionally, for very specific examples, you can get away with setting some state for future cleanup. For example, we might put a socket that does not want to close on a "bad socket" list, to be examined by a regular sweep of the system state. Every example we have seen of this is error-prone, specialized, and often buggy.

Note

The standard library assumes that destructors, deallocation functions (e.g., operator delete), and swap do not throw. If they do, basic standard-library invariants are broken.

Note

- Deallocation functions, including operator delete, must be noexcept.
- swap functions must be noexcept.
- Most destructors are implicitly noexcept by default.
- Also, make move operations noexcept.
- If writing a type intended to be used as an exception type, ensure its copy constructor is not noexcept. In general we cannot mechanically enforce this, because we do not know whether a type is intended to be used as an exception type.
- Try not to throw a type whose copy constructor is not noexcept. In general we cannot mechanically enforce this, because even throw std::string(...) could throw but does not in practice.

Enforcement

- Catch destructors, deallocation operations, and swaps that throw.
- Catch such operations that are not noexcept.

See also: discussion

E.17: Don't try to catch every exception in every function

Reason

Catching an exception in a function that cannot take a meaningful recovery action leads to complexity and waste. Let an exception propagate until it reaches a function that can handle it. Let cleanup actions on the unwinding path be handled by RAII.

Example, don't

```
void f() // bad
{
    try {
        // ...
    }
    catch (...) {
        // no action
        throw; // propagate exception
    }
}
```

Enforcement

- Flag nested try-blocks.
- Flag source code files with a too high ratio of try-blocks to functions. (??? Problem: define "too high")

E.18: Minimize the use of explicit try/catch

Reason

try/catch is verbose and non-trivial uses are error-prone. try/catch can be a sign of unsystematic and/or low-level resource management or error handling.

Example, Bad

```
void f(zstring s)
{
    Gadget* p;
    try {
        p = new Gadget(s);
        // ...
        delete p;
    }
    catch (Gadget_construction_failure) {
        delete p;
        throw;
    }
}
```

This code is messy. There could be a leak from the naked pointer in the try block. Not all exceptions are handled. deleting an object that failed to construct is almost certainly a mistake. Better:

```
void f2(zstring s)
{
    Gadget g {s};
}
```

Alternatives

- proper resource handles and RAII
- finally

Enforcement

??? hard, needs a heuristic

E.19: Use a final_action object to express cleanup if no suitable resource handle is available

Reason

finally from the GSL is less verbose and harder to get wrong than try/catch.

Example

```
void f(int n)
{
    void* p = malloc(n);
    auto _ = gsl::finally([p] { free(p); });
    // ...
}
```

Note

finally is not as messy as try/catch, but it is still ad-hoc. Prefer proper resource management objects. Consider finally a last resort.

Note

Use of finally is a systematic and reasonably clean alternative to the old goto exit; technique for dealing with cleanup where resource management is not systematic.

Enforcement

Heuristic: Detect goto exit;

E.25: If you can't throw exceptions, simulate RAII for resource management

Reason

Even without exceptions, RAII is usually the best and most systematic way of dealing with resources.

Note

Error handling using exceptions is the only complete and systematic way of handling non-local errors in C++. In particular, non-intrusively signaling failure to construct an object requires an exception. Signaling errors in a way that cannot be ignored requires exceptions. If you can't use exceptions, simulate their use as best you can.

A lot of fear of exceptions is misguided. When used for exceptional circumstances in code that is not littered with pointers and complicated control structures, exception handling is almost always affordable (in time and space) and almost always leads to better code. This, of course, assumes a good implementation of the exception handling mechanisms, which is not available on all systems. There are also cases where the problems above do not apply, but exceptions cannot be used for other reasons. Some hard-real-time systems are an example: An operation has to be completed within a fixed time with an error or a correct answer. In the absence of appropriate time estimation tools, this is hard to guarantee for exceptions. Such systems (e.g. flight control software) typically also ban the use of dynamic (heap) memory.

So, the primary guideline for error handling is "use exceptions and RAII." This section deals with the cases where you either do not have an efficient implementation of exceptions, or have such a rat's nest of old-style code (e.g., lots of pointers, ill-defined ownership, and lots of unsystematic error handling based on tests of error codes) that it is infeasible to introduce simple and systematic exception handling.

Before condemning exceptions or complaining too much about their cost, consider examples of the use of error codes. Consider the cost and complexity of the use of error codes. If performance is your worry, measure.

Example

Assume you wanted to write

```
void func(zstring arg)
{
   Gadget g {arg};
   // ...
}
```

If the gadget isn't correctly constructed, func exits with an exception. If we cannot throw an exception, we can simulate this RAII style of resource handling by adding a valid() member function to Gadget:

```
error_indicator func(zstring arg)
{
   Gadget g {arg};
   if (!g.valid()) return gadget_construction_error;
   // ...
   return 0; // zero indicates "good"
}
```

The problem is of course that the caller now has to remember to test the return value. To encourage doing so, consider adding a [[nodiscard]].

See also: Discussion

Enforcement

Possible (only) for specific versions of this idea: e.g., test for systematic test of valid() after resource handle construction

E.26: If you can't throw exceptions, consider failing fast

Reason

If you can't do a good job at recovering, at least you can get out before too much consequential damage is done.

See also: Simulating RAII

Note

If you cannot be systematic about error handling, consider "crashing" as a response to any error that cannot be handled locally. That is, if you cannot recover from an error in the context of the function that detected it, call abort(), quick_exit(), or a similar function that will trigger some sort of system restart.

In systems where you have lots of processes and/or lots of computers, you need to expect and handle fatal crashes anyway, say from hardware failures. In such cases, "crashing" is simply leaving error handling to the next level of the system.

Example

```
void f(int n)
{
    // ...
    p = static_cast<X*>(malloc(n * sizeof(X)));
    if (!p) abort();    // abort if memory is exhausted
    // ...
}
```

Most programs cannot handle memory exhaustion gracefully anyway. This is roughly equivalent to

```
void f(int n)
{
    // ...
    p = new X[n];    // throw if memory is exhausted (by default, terminate)
    // ...
}
```

Typically, it is a good idea to log the reason for the "crash" before exiting.

Enforcement

Awkward

E.27: If you can't throw exceptions, use error codes systematically

Reason

Systematic use of any error-handling strategy minimizes the chance of forgetting to handle an error.

See also: Simulating RAII

Note

There are several issues to be addressed:

- How do you transmit an error indicator from out of a function?
- How do you release all resources from a function before doing an error exit?
- What do you use as an error indicator?

In general, returning an error indicator implies returning two values: The result and an error indicator. The error indicator can be part of the object, e.g. an object can have a valid() indicator or a pair of values can be returned.

Example

This approach fits with simulated RAII resource management. The valid() function could return an error_indicator (e.g. a member of an error_indicator enumeration).

Example

What if we cannot or do not want to modify the Gadget type? In that case, we must return a pair of values. For example:

```
std::pair<Gadget, error_indicator> make_gadget(int n)
{
```

As shown, std::pair is a possible return type. Some people prefer a specific type. For example:

One reason to prefer a specific return type is to have names for its members, rather than the somewhat cryptic first and second and to avoid confusion with other uses of std::pair.

Example

In general, you must clean up before an error exit. This can be messy:

```
std::pair<int, error_indicator> user()
{
    Gadget g1 = make_gadget(17);
    if (!g1.valid()) {
        return {0, g1_error};
    }

    Gadget g2 = make_gadget(31);
    if (!g2.valid()) {
        cleanup(g1);
        return {0, g2_error};
    }

// ...
```

```
if (all_foobar(g1, g2)) {
    cleanup(g2);
    cleanup(g1);
    return {0, foobar_error};
}

// ...

cleanup(g2);
cleanup(g1);
return {res, 0};
}
```

Simulating RAII can be non-trivial, especially in functions with multiple resources and multiple possible errors. A not uncommon technique is to gather cleanup at the end of the function to avoid repetition (note that the extra scope around g2 is undesirable but necessary to make the goto version compile):

```
std::pair<int, error_indicator> user()
{
    error_indicator err = 0;
    int res = 0;
    Gadget g1 = make_gadget(17);
    if (!g1.valid()) {
        err = g1_error;
        goto g1_exit;
    }
    {
        Gadget g2 = make_gadget(31);
        if (!g2.valid()) {
            err = g2_error;
            goto g2_exit;
        }
        if (all_foobar(g1, g2)) {
            err = foobar_error;
            goto g2_exit;
        }
        // ...
    g2 exit:
        if (g2.valid()) cleanup(g2);
    }
g1_exit:
    if (g1.valid()) cleanup(g1);
    return {res, err};
}
```

The larger the function, the more tempting this technique becomes. finally can ease the pain a bit. Also, the larger the program becomes the harder it is to apply an error-indicator-based error-handling strategy systematically.

We prefer exception-based error handling and recommend keeping functions short.

See also: Discussion

See also: Returning multiple values

Enforcement

Awkward.

E.28: Avoid error handling based on global state (e.g. errno)

Reason

Global state is hard to manage and it is easy to forget to check it. When did you last test the return value of printf()?

See also: Simulating RAII

Example, bad

```
int last_err;

void f(int n)
{
    // ...
    p = static_cast<X*>(malloc(n * sizeof(X)));
    if (!p) last_err = -1;    // error if memory is exhausted
    // ...
}
```

Note

C-style error handling is based on the global variable errno, so it is essentially impossible to avoid this style completely.

Enforcement

Awkward.

E.30: Don't use exception specifications

Reason

Exception specifications make error handling brittle, impose a run-time cost, and have been removed from the C++ standard.

Example

```
int use(int arg)
    throw(X, Y)
{
    // ...
    auto x = f(arg);
    // ...
}
```

If f() throws an exception different from X and Y the unexpected handler is invoked, which by default terminates. That's OK, but say that we have checked that this cannot happen and f is changed to throw a new exception Z, we now have a crash on our hands unless we change use() (and re-test everything). The snag is that f() might be in a library we do not control and the new exception is not anything that use() can do anything about or is in any way interested in. We can change use() to pass Z through, but now use()'s callers probably need to be modified. This quickly becomes unmanageable. Alternatively, we can add a try-catch to use() to map Z into an acceptable exception. This too, quickly becomes unmanageable. Note that changes to the set of exceptions often happens at the lowest level of a system (e.g., because of changes to a network library or some middleware), so changes "bubble up" through long call chains. In a large code base, this could mean that nobody could update to a new version of a library until the last user was modified. If use() is part of a library, it might not be possible to update it because a change could affect unknown clients.

The policy of letting exceptions propagate until they reach a function that potentially can handle it has proven itself over the years.

Note

No. This would not be any better had exception specifications been statically enforced. For example, see Stroustrup94.

Note

If no exception can be thrown, use noexcept.

Enforcement

Flag every exception specification.

E.31: Properly order your catch-clauses

Reason

catch-clauses are evaluated in the order they appear and one clause can hide another.

Example, bad

If Derivedis derived from Base the Derived-handler will never be invoked. The "catch everything" handler ensured that the std::exception-handler will never be invoked.

Enforcement

Flag all "hiding handlers".

Con: Constants and immutability

You can't have a race condition on a constant. It is easier to reason about a program when many of the objects cannot change their values. Interfaces that promise "no change" of objects passed as arguments greatly increase readability.

Constant rule summary:

- Con.1: By default, make objects immutable
- Con.2: By default, make member functions const
- Con.3: By default, pass pointers and references to consts
- Con.4: Use const to define objects with values that do not change after construction
- Con.5: Use constexpr for values that can be computed at compile time

Con.1: By default, make objects immutable

Reason

Immutable objects are easier to reason about, so make objects non-const only when there is a need to change their value. Prevents accidental or hard-to-notice change of value.

Example

```
for (const int i : c) cout << i << '\n';  // just reading: const

for (int i : c) cout << i << '\n';  // BAD: just reading</pre>
```

Exceptions

A local variable that is returned by value and is cheaper to move than copy should not be declared const because it can force an unnecessary copy.

```
std::vector<int> f(int i)
{
    std::vector<int> v{ i, i, i }; // const not needed
    return v;
}
```

Function parameters passed by value are rarely mutated, but also rarely declared const. To avoid confusion and lots of false positives, don't enforce this rule for function parameters.

```
void g(const int i) { ... } // pedantic
```

Note that a function parameter is a local variable so changes to it are local.

Enforcement

• Flag non-const variables that are not modified (except for parameters to avoid many false positives and returned local variables)

Con.2: By default, make member functions const

Reason

A member function should be marked const unless it changes the object's observable state. This gives a more precise statement of design intent, better readability, more errors caught by the compiler, and sometimes more optimization opportunities.

Example, bad

```
class Point {
   int x, y;
public:
   int getx() { return x; } // BAD, should be const as it doesn't modify the object's
state
   // ...
};

void f(const Point& pt)
{
   int x = pt.getx(); // ERROR, doesn't compile because getx was not marked const
}
```

Note

It is not inherently bad to pass a pointer or reference to non-const, but that should be done only when the called function is supposed to modify the object. A reader of code must assume that a function that takes a "plain" T* or T& will modify the object referred to. If it doesn't now, it might do so later without forcing recompilation.

Note

There are code/libraries that offer functions that declare a T* even though those functions do not modify that T. This is a problem for people modernizing code. You can

- update the library to be const-correct; preferred long-term solution
- "cast away const"; best avoided
- provide a wrapper function

Example:

```
void f(int* p); // old code: f() does not modify `*p`
void f(const int* p) { f(const_cast<int*>(p)); } // wrapper
```

Note that this wrapper solution is a patch that should be used only when the declaration of f() cannot be modified, e.g. because it is in a library that you cannot modify.

Note

A const member function can modify the value of an object that is mutable or accessed through a pointer member. A common use is to maintain a cache rather than repeatedly do a complicated computation. For example, here is a Date that caches (memoizes) its string representation to simplify repeated uses:

```
class Date {
public:
    // ...
    const string& string_ref() const
    {
        if (string_val == "") compute_string_rep();
        return string_val;
```

```
}
  // ...
private:
  void compute_string_rep() const;  // compute string representation and place it in
string_val
  mutable string string_val;
  // ...
};
```

Another way of saying this is that constness is not transitive. It is possible for a const member function to change the value of mutable members and the value of objects accessed through non-const pointers. It is the job of the class to ensure such mutation is done only when it makes sense according to the semantics (invariants) it offers to its users.

See also: Pimpl

Enforcement

• Flag a member function that is not marked const, but that does not perform a non-const operation on any member variable.

Con.3: By default, pass pointers and references to consts

Reason

To avoid a called function unexpectedly changing the value. It's far easier to reason about programs when called functions don't modify state.

Example

```
void f(char* p);  // does f modify *p? (assume it does)
void g(const char* p); // g does not modify *p
```

Note

It is not inherently bad to pass a pointer or reference to non-const, but that should be done only when the called function is supposed to modify the object.

Note

Do not cast away const.

Enforcement

- Flag a function that does not modify an object passed by pointer or reference to non-const
- Flag a function that (using a cast) modifies an object passed by pointer or reference to const

Con.4: Use const to define objects with values that do not change after construction

Reason

Prevent surprises from unexpectedly changed object values.

Example

```
void f()
{
   int x = 7;
   const int y = 9;

   for (;;) {
        // ...
   }
   // ...
}
```

As x is not const, we must assume that it is modified somewhere in the loop.

Enforcement

• Flag unmodified non-const variables.

Con.5: Use constexpr for values that can be computed at compile time

Reason

Better performance, better compile-time checking, guaranteed compile-time evaluation, no possibility of race conditions.

Example

```
double x = f(2); // possible run-time evaluation const double y = f(2); // possible run-time evaluation constexpr double z = f(2); // error unless f(2) can be evaluated at compile time
```

Note

See F.4.

Enforcement

• Flag const definitions with constant expression initializers.

T: Templates and generic programming

Generic programming is programming using types and algorithms parameterized by types, values, and algorithms. In C++, generic programming is supported by the template language mechanisms.

Arguments to generic functions are characterized by sets of requirements on the argument types and values involved. In C++, these requirements are expressed by compile-time predicates called concepts.

Templates can also be used for meta-programming; that is, programs that compose code at compile time.

A central notion in generic programming is "concepts"; that is, requirements on template arguments presented as compile-time predicates. "Concepts" were standardized in C++20, although they were first made available, in slightly older syntax, in GCC 6.1.

Template use rule summary:

- T.1: Use templates to raise the level of abstraction of code
- T.2: Use templates to express algorithms that apply to many argument types
- T.3: Use templates to express containers and ranges
- T.4: Use templates to express syntax tree manipulation
- T.5: Combine generic and OO techniques to amplify their strengths, not their costs

Concept use rule summary:

- T.10: Specify concepts for all template arguments
- T.11: Whenever possible use standard concepts
- T.12: Prefer concept names over auto for local variables
- T.13: Prefer the shorthand notation for simple, single-type argument concepts
- **???**

Concept definition rule summary:

- T.20: Avoid "concepts" without meaningful semantics
- T.21: Require a complete set of operations for a concept
- T.22: Specify axioms for concepts
- T.23: Differentiate a refined concept from its more general case by adding new use patterns
- T.24: Use tag classes or traits to differentiate concepts that differ only in semantics

- T.25: Avoid complementary constraints
- T.26: Prefer to define concepts in terms of use-patterns rather than simple syntax
- T.30: Use concept negation (!C<T>) sparingly to express a minor difference
- T.31: Use concept disjunction (C1<T> || C2<T>) sparingly to express alternatives
- **???**

Template interface rule summary:

- T.40: Use function objects to pass operations to algorithms
- T.41: Require only essential properties in a template's concepts
- T.42: Use template aliases to simplify notation and hide implementation details
- T.43: Prefer using over typedef for defining aliases
- T.44: Use function templates to deduce class template argument types (where feasible)
- T.46: Require template arguments to be at least semiregular
- T.47: Avoid highly visible unconstrained templates with common names
- T.48: If your compiler does not support concepts, fake them with enable_if
- T.49: Where possible, avoid type-erasure

Template definition rule summary:

- T.60: Minimize a template's context dependencies
- T.61: Do not over-parameterize members (SCARY)
- T.62: Place non-dependent class template members in a non-templated base class
- T.64: Use specialization to provide alternative implementations of class templates
- T.65: Use tag dispatch to provide alternative implementations of functions
- T.67: Use specialization to provide alternative implementations for irregular types
- T.68: Use {} rather than () within templates to avoid ambiguities
- T.69: Inside a template, don't make an unqualified non-member function call unless you intend it to be a customization point

Template and hierarchy rule summary:

- T.80: Do not naively templatize a class hierarchy
- T.81: Do not mix hierarchies and arrays // ??? somewhere in "hierarchies"
- T.82: Linearize a hierarchy when virtual functions are undesirable
- T.83: Do not declare a member function template virtual
- T.84: Use a non-template core implementation to provide an ABI-stable interface
- T.??: ????

Variadic template rule summary:

- T.100: Use variadic templates when you need a function that takes a variable number of arguments of a variety of types
- T.101: ??? How to pass arguments to a variadic template ???
- T.102: ??? How to process arguments to a variadic template ???
- T.103: Don't use variadic templates for homogeneous argument lists
- T.??: ????

Metaprogramming rule summary:

- T.120: Use template metaprogramming only when you really need to
- T.121: Use template metaprogramming primarily to emulate concepts
- T.122: Use templates (usually template aliases) to compute types at compile time

- T.123: Use constexpr functions to compute values at compile time
- T.124: Prefer to use standard-library TMP facilities
- T.125: If you need to go beyond the standard-library TMP facilities, use an existing library
- T.??: ????

Other template rules summary:

- T.140: If an operation can be reused, give it a name
- T.141: Use an unnamed lambda if you need a simple function object in one place only
- T.142: Use template variables to simplify notation
- T.143: Don't write unintentionally non-generic code
- T.144: Don't specialize function templates
- T.150: Check that a class matches a concept using static_assert
- T??:????

T.gp: Generic programming

Generic programming is programming using types and algorithms parameterized by types, values, and algorithms.

T.1: Use templates to raise the level of abstraction of code

Reason

Generality. Reuse. Efficiency. Encourages consistent definition of user types.

Example, bad

Conceptually, the following requirements are wrong because what we want of T is more than just the very low-level concepts of "can be incremented" or "can be added":

```
template<typename T>
    requires Incrementable<T>
T sum1(vector<T>& v, T s)
{
    for (auto x : v) s += x;
    return s;
}

template<typename T>
    requires Simple_number<T>
T sum2(vector<T>& v, T s)
{
    for (auto x : v) s = s + x;
    return s;
}
```

Assuming that Incrementable does not support + and Simple_number does not support +=, we have overconstrained implementers of sum1 and sum2. And, in this case, missed an opportunity for a generalization.

Example

```
template<typename T>
    requires Arithmetic<T>
T sum(vector<T>& v, T s)
{
    for (auto x : v) s += x;
    return s;
}
```

Assuming that Arithmetic requires both + and +=, we have constrained the user of sum to provide a complete arithmetic type. That is not a minimal requirement, but it gives the implementer of algorithms much needed freedom and ensures that any Arithmetic type can be used for a wide variety of algorithms.

For additional generality and reusability, we could also use a more general Container or Range concept instead of committing to only one container, vector.

Note

If we define a template to require exactly the operations required for a single implementation of a single algorithm (e.g., requiring just += rather than also = and +) and only those, we have overconstrained maintainers. We aim to minimize requirements on template arguments, but the absolutely minimal requirements of an implementation is rarely a meaningful concept.

Note

Templates can be used to express essentially everything (they are Turing complete), but the aim of generic programming (as expressed using templates) is to efficiently generalize operations/algorithms over a set of types with similar semantic properties.

Enforcement

- Flag algorithms with "overly simple" requirements, such as direct use of specific operators without a concept.
- Do not flag the definition of the "overly simple" concepts themselves; they might simply be building blocks for more useful concepts.

T.2: Use templates to express algorithms that apply to many argument types

Reason

Generality. Minimizing the amount of source code. Interoperability. Reuse.

Example

That's the foundation of the STL. A single find algorithm easily works with any kind of input range:

```
template<typename Iter, typename Val>
    // requires Input_iterator<Iter>
    //     && Equality_comparable<Value_type<Iter>, Val>
Iter find(Iter b, Iter e, Val v)
{
    // ...
}
```

Note

Don't use a template unless you have a realistic need for more than one template argument type. Don't overabstract.

Enforcement

??? tough, probably needs a human

T.3: Use templates to express containers and ranges

Reason

Containers need an element type, and expressing that as a template argument is general, reusable, and type safe. It also avoids brittle or inefficient workarounds. Convention: That's the way the STL does it.

Example

```
template<typename T>
    // requires Regular<T>
class Vector {
    // ...
    T* elem; // points to sz Ts
    int sz;
};

Vector<double> v(10);
v[7] = 9.9;
```

Example, bad

```
class Container {
    // ...
    void* elem; // points to size elements of some type
    int sz;
};

Container c(10, sizeof(double));
((double*) c.elem)[7] = 9.9;
```

This doesn't directly express the intent of the programmer and hides the structure of the program from the type system and optimizer.

Hiding the void* behind macros simply obscures the problems and introduces new opportunities for confusion.

Exceptions: If you need an ABI-stable interface, you might have to provide a base implementation and express the (type-safe) template in terms of that. See Stable base.

Enforcement

• Flag uses of void*s and casts outside low-level implementation code

T.4: Use templates to express syntax tree manipulation

Reason

???

Example

```
???
```

Exceptions: ???

T.5: Combine generic and OO techniques to amplify their strengths, not their costs

Reason

Generic and OO techniques are complementary.

Example

Static helps dynamic: Use static polymorphism to implement dynamically polymorphic interfaces.

```
class Command {
    // pure virtual functions
};

// implementations
template</*...*/>
class ConcreteCommand : public Command {
    // implement virtuals
};
```

Example

Dynamic helps static: Offer a generic, comfortable, statically bound interface, but internally dispatch dynamically, so you offer a uniform object layout. Examples include type erasure as with std::shared_ptr's deleter (but don't overuse type erasure).

```
#include <memory>
class Object {
public:
   template<typename T>
   Object(T&& obj)
        : concept_(std::make_shared<ConcreteCommand<T>>(std::forward<T>(obj))) {}
    int get_id() const { return concept_->get_id(); }
private:
    struct Command {
        virtual ~Command() {}
        virtual int get_id() const = 0;
   };
   template<typename T>
    struct ConcreteCommand final : Command {
        ConcreteCommand(T&& obj) noexcept : object (std::forward<T>(obj)) {}
        int get_id() const final { return object_.get_id(); }
    private:
        T object_;
   };
    std::shared_ptr<Command> concept_;
};
class Bar {
public:
    int get_id() const { return 1; }
```

```
struct Foo {
public:
    int get_id() const { return 2; }
};

Object o(Bar{});
Object o2(Foo{});
```

Note

In a class template, non-virtual functions are only instantiated if they're used -- but virtual functions are instantiated every time. This can bloat code size, and might overconstrain a generic type by instantiating functionality that is never needed. Avoid this, even though the standard-library facets made this mistake.

See also

- ref ???
- ref ???
- ref ???

Enforcement

See the reference to more specific rules.

T.concepts: Concept rules

Concepts is a C++20 facility for specifying requirements for template arguments. They are crucial in the thinking about generic programming and the basis of much work on future C++ libraries (standard and other).

This section assumes concept support

Concept use rule summary:

- T.10: Specify concepts for all template arguments
- T.11: Whenever possible use standard concepts
- T.12: Prefer concept names over auto
- T.13: Prefer the shorthand notation for simple, single-type argument concepts
- **???**

Concept definition rule summary:

- T.20: Avoid "concepts" without meaningful semantics
- T.21: Require a complete set of operations for a concept
- T.22: Specify axioms for concepts
- T.23: Differentiate a refined concept from its more general case by adding new use patterns
- T.24: Use tag classes or traits to differentiate concepts that differ only in semantics
- T.25: Avoid complimentary constraints
- T.26: Prefer to define concepts in terms of use-patterns rather than simple syntax

T.con-use: Concept use

T.10: Specify concepts for all template arguments

Reason

Correctness and readability. The assumed meaning (syntax and semantics) of a template argument is fundamental to the interface of a template. A concept dramatically improves documentation and error handling for the template. Specifying concepts for template arguments is a powerful design tool.

Example

```
template<typename Iter, typename Val>
    requires input_iterator<Iter>
        && equality_comparable_with<iter_value_t<Iter>, Val>
Iter find(Iter b, Iter e, Val v)
{
        // ...
}
```

or equivalently and more succinctly:

```
template<input_iterator Iter, typename Val>
    requires equality_comparable_with<iter_value_t<Iter>, Val>
Iter find(Iter b, Iter e, Val v)
{
    // ...
}
```

Note

Plain typename (or auto) is the least constraining concept. It should be used only rarely when nothing more than "it's a type" can be assumed. This is typically only needed when (as part of template metaprogramming code) we manipulate pure expression trees, postponing type checking.

References: TC++PL4

Enforcement

Flag template type arguments without concepts

T.11: Whenever possible use standard concepts

Reason

"Standard" concepts (as provided by the GSL and the ISO standard itself) save us the work of thinking up our own concepts, are better thought out than we can manage to do in a hurry, and improve interoperability.

Note

Unless you are creating a new generic library, most of the concepts you need will already be defined by the standard library.

Example

```
template<typename T>
    // don't define this: sortable is in <iterator>
concept Ordered_container = Sequence<T> && Random_access<Iterator<T>> &&
Ordered<Value_type<T>>;

void sort(Ordered_container auto& s);
```

This Ordered_container is quite plausible, but it is very similar to the sortable concept in the standard library. Is it better? Is it right? Does it accurately reflect the standard's requirements for sort? It is better and simpler just to use sortable:

```
void sort(sortable auto& s); // better
```

Note

The set of "standard" concepts is evolving as we approach an ISO standard including concepts.

Note

Designing a useful concept is challenging.

Enforcement

Hard.

- Look for unconstrained arguments, templates that use "unusual"/non-standard concepts, templates that use "homebrew" concepts without axioms.
- Develop a concept-discovery tool (e.g., see an early experiment).

T.12: Prefer concept names over auto for local variables

Reason

auto is the weakest concept. Concept names convey more meaning than just auto.

Example

Enforcement

???

T.13: Prefer the shorthand notation for simple, single-type argument concepts

Reason

Readability. Direct expression of an idea.

Example

To say "T is sortable":

The shorter versions better match the way we speak. Note that many templates don't need to use the template keyword.

Enforcement

- Not feasible in the short term when people convert from the <typename T> and <class T> notation.
- Later, flag declarations that first introduce a typename and then constrain it with a simple, single-type-argument concept.

T.concepts.def: Concept definition rules

Defining good concepts is non-trivial. Concepts are meant to represent fundamental concepts in an application domain (hence the name "concepts"). Similarly throwing together a set of syntactic constraints to be used for the arguments for a single class or algorithm is not what concepts were designed for and will not give the full benefits of the mechanism.

Obviously, defining concepts is most useful for code that can use an implementation (e.g., C++20 or later) but defining concepts is in itself a useful design technique and help catch conceptual errors and clean up the concepts (sic!) of an implementation.

T.20: Avoid "concepts" without meaningful semantics

Reason

Concepts are meant to express semantic notions, such as "a number", "a range" of elements, and "totally ordered." Simple constraints, such as "has a + operator" and "has a > operator" cannot be meaningfully specified in isolation and should be used only as building blocks for meaningful concepts, rather than in user code.

Example, bad

```
template<typename T>
// bad; insufficient
concept Addable = requires(T a, T b) { a + b; };

template<Addable N>
auto algo(const N& a, const N& b) // use two numbers
{
    // ...
    return a + b;
}

int x = 7;
int y = 9;
auto z = algo(x, y); // z = 16

string xx = "7";
string yy = "9";
auto zz = algo(xx, yy); // zz = "79"
```

Maybe the concatenation was expected. More likely, it was an accident. Defining minus equivalently would give dramatically different sets of accepted types. This Addable violates the mathematical rule that addition is supposed to be commutative: a+b == b+a.

The ability to specify meaningful semantics is a defining characteristic of a true concept, as opposed to a syntactic constraint.

Example

```
template<typename T>
// The operators +, -, *, and / for a number are assumed to follow the usual mathematical
rules
concept Number = requires(T a, T b) { a + b; a - b; a * b; a / b; };

template<Number N>
auto algo(const N& a, const N& b)
{
    // ...
    return a + b;
}

int x = 7;
int y = 9;
auto z = algo(x, y); // z = 16

string xx = "7";
string yy = "9";
auto zz = algo(xx, yy); // error: string is not a Number
```

Note

Concepts with multiple operations have far lower chance of accidentally matching a type than a single-operation concept.

Enforcement

- Flag single-operation concepts when used outside the definition of other concepts.
- Flag uses of enable_if that appear to simulate single-operation concepts.

T.21: Require a complete set of operations for a concept

Reason

Ease of comprehension. Improved interoperability. Helps implementers and maintainers.

This is a specific variant of the general rule that a concept must make semantic sense.

Example, bad

```
template<typename T> concept Subtractable = requires(T a, T b) { a - b; };
```

This makes no semantic sense. You need at least + to make - meaningful and useful.

Examples of complete sets are

```
Arithmetic: +, -, *, /, +=, -=, *=, /=Comparable: <, >, <=, >=, ==, !=
```

Note

This rule applies whether we use direct language support for concepts or not. It is a general design rule that even applies to non-templates:

```
class Minimal {
   // ...
};
bool operator==(const Minimal&, const Minimal&);
bool operator<(const Minimal&, const Minimal&);</pre>
Minimal operator+(const Minimal&, const Minimal&);
// no other operators
void f(const Minimal& x, const Minimal& y)
{
   if (!(x == y)) \{ /* ... */ \} // OK
   if (x != y) { /* ... */ }
                                   // surprise! error
   while (!(x < y)) \{ /* ... */ \} // OK
   while (x \ge y) \{ /^* ... ^*/ \} // surprise! error
                       // OK
   x = x + y;
   x += y;
                        // surprise! error
}
```

This is minimal, but surprising and constraining for users. It could even be less efficient.

The rule supports the view that a concept should reflect a (mathematically) coherent set of operations.

```
class Convenient {
   // ...
};
bool operator==(const Convenient&, const Convenient&);
bool operator<(const Convenient&, const Convenient&);</pre>
// ... and the other comparison operators ...
Convenient operator+(const Convenient&, const Convenient&);
// ... and the other arithmetic operators ...
void f(const Convenient& x, const Convenient& y)
   if (!(x == y)) { /* ... */ }
                                  // OK
   if (x != y) \{ /* ... */ \}
                                    // OK
   while (!(x < y)) { /* ... */ } // OK
   while (x \ge y) \{ /^* ... */ \} // OK
   x = x + y; // OK
   x += y;
                  // OK
}
```

It can be a nuisance to define all operators, but not hard. Ideally, that rule should be language supported by giving you comparison operators by default.

Enforcement

• Flag classes that support "odd" subsets of a set of operators, e.g., == but not != or + but not -. Yes, std::string is "odd", but it's too late to change that.

T.22: Specify axioms for concepts

Reason

A meaningful/useful concept has a semantic meaning. Expressing these semantics in an informal, semi-formal, or formal way makes the concept comprehensible to readers and the effort to express it can catch conceptual errors. Specifying semantics is a powerful design tool.

Example

```
template<typename T>
    // The operators +, -, *, and / for a number are assumed to follow the usual mathematical
rules
    // axiom(T a, T b) { a + b == b + a; a - a == 0; a * (b + c) == a * b + a * c; /*...*/ }
    concept Number = requires(T a, T b) {
        { a + b } -> convertible_to<T>;
        { a - b } -> convertible_to<T>;
        { a * b } -> convertible_to<T>;
        { a / b / b / convertible_to<T>;
        { a / b / convertibl
```

This is an axiom in the mathematical sense: something that can be assumed without proof. In general, axioms are not provable, and when they are the proof is often beyond the capability of a compiler. An axiom might not be general, but the template writer can assume that it holds for all inputs actually used (similar to a precondition).

Note

In this context axioms are Boolean expressions. See the Palo Alto TR for examples. Currently, C++ does not support axioms (even the ISO Concepts TS), so we have to make do with comments for a longish while. Once language support is available, the // in front of the axiom can be removed

Note

The GSL concepts have well-defined semantics; see the Palo Alto TR and the Ranges TS.

Exception

Early versions of a new "concept" still under development will often just define simple sets of constraints without a well-specified semantics. Finding good semantics can take effort and time. An incomplete set of constraints can still be very useful:

```
// balancer for a generic binary tree
template<typename Node> concept Balancer = requires(Node* p) {
   add_fixup(p);
   touch(p);
   detach(p);
};
```

So a Balancer must supply at least these operations on a tree Node, but we are not yet ready to specify detailed semantics because a new kind of balanced tree might require more operations and the precise general semantics for all nodes is hard to pin down in the early stages of design.

A "concept" that is incomplete or without a well-specified semantics can still be useful. For example, it allows for some checking during initial experimentation. However, it should not be assumed to be stable. Each new use case might require such an incomplete concept to be improved.

Enforcement

• Look for the word "axiom" in concept definition comments

T.23: Differentiate a refined concept from its more general case by adding new use patterns.

Reason

Otherwise they cannot be distinguished automatically by the compiler.

Example

```
template<typename I>
// Note: input_iterator is defined in <iterator>
concept Input_iter = requires(I iter) { ++iter; };

template<typename I>
// Note: forward_iterator is defined in <iterator>
concept Fwd_iter = Input_iter<I> && requires(I iter) { iter++; };
```

The compiler can determine refinement based on the sets of required operations (here, suffix ++). This decreases the burden on implementers of these types since they do not need any special declarations to "hook into the concept". If two concepts have exactly the same requirements, they are logically equivalent (there is no refinement).

Enforcement

• Flag a concept that has exactly the same requirements as another already-seen concept (neither is more refined). To disambiguate them, see T.24.

T.24: Use tag classes or traits to differentiate concepts that differ only in semantics.

Reason

Two concepts requiring the same syntax but having different semantics leads to ambiguity unless the programmer differentiates them.

The programmer (in a library) must define is_contiguous (a trait) appropriately.

Wrapping a tag class into a concept leads to a simpler expression of this idea:

```
template<typename I> concept Contiguous = is_contiguous_v<I>;
template<typename I>
concept Contiguous_iter = RA_iter<I> && Contiguous<I>;
```

The programmer (in a library) must define is_contiguous (a trait) appropriately.

Note

Traits can be trait classes or type traits. These can be user-defined or standard-library ones. Prefer the standard-library ones.

Enforcement

- The compiler flags ambiguous use of identical concepts.
- Flag the definition of identical concepts.

T.25: Avoid complementary constraints

Reason

Clarity. Maintainability. Functions with complementary requirements expressed using negation are brittle.

Example

Initially, people will try to define functions with complementary requirements:

This is better:

The compiler will choose the unconstrained template only when C<T> is unsatisfied. If you do not want to (or cannot) define an unconstrained version of f(), then delete it.

```
template<typename T>
void f() = delete;
```

The compiler will select the overload, or emit an appropriate error.

Note

Complementary constraints are unfortunately common in enable_if code:

```
template<typename T>
enable_if<!C<T>, void> // bad
f();

template<typename T>
enable_if<C<T>, void>
f();
```

Note

Complementary requirements on one requirement is sometimes (wrongly) considered manageable. However, for two or more requirements the number of definitions needs can go up exponentially (2,4,8,16,...):

```
C1<T> && C2<T>
!C1<T> && C2<T>
!C1<T> && !C2<T>
C1<T> && !C2<T>
!C1<T> && !C2<T>
```

Now the opportunities for errors multiply.

Enforcement

• Flag pairs of functions with C<T> and !C<T> constraints

T.26: Prefer to define concepts in terms of use-patterns rather than simple syntax

Reason

The definition is more readable and corresponds directly to what a user has to write. Conversions are taken into account. You don't have to remember the names of all the type traits.

Example

You might be tempted to define a concept Equality like this:

```
template<typename T> concept Equality = has_equal<T> && has_not_equal<T>;
```

Obviously, it would be better and easier just to use the standard equality_comparable, but - just as an example - if you had to define such a concept, prefer:

```
template<typename T> concept Equality = requires(T a, T b) {
    { a == b } -> std::convertible_to<bool>;
    { a != b } -> std::convertible_to<bool>;
    // axiom { !(a == b) == (a != b) }
    // axiom { a = b; => a == b } // => means "implies"
};
```

as opposed to defining two meaningless concepts has_equal and has_not_equal just as helpers in the definition of Equality. By "meaningless" we mean that we cannot specify the semantics of has_equal in isolation.

Enforcement

???

Template interfaces

Over the years, programming with templates have suffered from a weak distinction between the interface of a template and its implementation. Before concepts, that distinction had no direct language support. However, the interface to a template is a critical concept - a contract between a user and an implementer - and should be carefully designed.

T.40: Use function objects to pass operations to algorithms

Reason

Function objects can carry more information through an interface than a "plain" pointer to function. In general, passing function objects gives better performance than passing pointers to functions.

Example

You can, of course, generalize those functions using auto or concepts. For example:

```
auto y1 = find_if(v, [](totally_ordered auto x) { return x > 7; }); // require an ordered type
auto z1 = find_if(v, [](auto x) { return x > 7; }); // hope that the type has
a >
```

Note

Lambdas generate function objects.

Note

The performance argument depends on compiler and optimizer technology.

Enforcement

- Flag pointer to function template arguments.
- Flag pointers to functions passed as arguments to a template (risk of false positives).

T.41: Require only essential properties in a template's concepts

Reason

Keep interfaces simple and stable.

Example

Consider, a sort instrumented with (oversimplified) simple debug support:

```
void sort(sortable auto& s) // sort sequence s
{
   if (debug) cerr << "enter sort( " << s << ")\n";
   // ...
   if (debug) cerr << "exit sort( " << s << ")\n";
}</pre>
```

Should this be rewritten to:

```
template<sortable S>
    requires Streamable<S>
void sort(S& s) // sort sequence s
{
    if (debug) cerr << "enter sort( " << s << ")\n";
    // ...
    if (debug) cerr << "exit sort( " << s << ")\n";
}</pre>
```

After all, there is nothing in sortable that requires iostream support. On the other hand, there is nothing in the fundamental idea of sorting that says anything about debugging.

Note

If we require every operation used to be listed among the requirements, the interface becomes unstable: Every time we change the debug facilities, the usage data gathering, testing support, error reporting, etc., the definition of the template would need change and every use of the template would have to be recompiled. This is cumbersome, and in some environments infeasible.

Conversely, if we use an operation in the implementation that is not guaranteed by concept checking, we might get a late compile-time error.

By not using concept checking for properties of a template argument that is not considered essential, we delay checking until instantiation time. We consider this a worthwhile tradeoff.

Note that using non-local, non-dependent names (such as debug and cerr) also introduces context dependencies that might lead to "mysterious" errors.

Note

It can be hard to decide which properties of a type are essential and which are not.

T.42: Use template aliases to simplify notation and hide implementation details

Reason

Improved readability. Implementation hiding. Note that template aliases replace many uses of traits to compute a type. They can also be used to wrap a trait.

Example

```
template<typename T, size_t N>
class Matrix {
    // ...
    using Iterator = typename std::vector<T>::iterator;
    // ...
};
```

This saves the user of Matrix from having to know that its elements are stored in a vector and also saves the user from repeatedly typing typename std::vector<T>::.

Example

```
template<typename T>
void user(T& c)
{
    // ...
    typename container_traits<T>::value_type x; // bad, verbose
    // ...
}

template<typename T>
using Value_type = typename container_traits<T>::value_type;
```

This saves the user of Value_type from having to know the technique used to implement value_types.

```
template<typename T>
void user2(T& c)
{
    // ...
    Value_type<T> x;
    // ...
}
```

A simple, common use could be expressed: "Wrap traits!"

Enforcement

- Flag use of typename as a disambiguator outside using declarations.
- 2??

T.43: Prefer using over typedef for defining aliases

Reason

Improved readability: With using, the new name comes first rather than being embedded somewhere in a declaration. Generality: using can be used for template aliases, whereas typedefs can't easily be templates. Uniformity: using is syntactically similar to auto.

Example

```
typedef int (*PFI)(int);  // OK, but convoluted

using PFI2 = int (*)(int);  // OK, preferred

template<typename T>
typedef int (*PFT)(T);  // error

template<typename T>
using PFT2 = int (*)(T);  // OK
```

Enforcement

• Flag uses of typedef. This will give a lot of "hits" :-(

T.44: Use function templates to deduce class template argument types (where feasible)

Reason

Writing the template argument types explicitly can be tedious and unnecessarily verbose.

```
tuple<int, string, double> t1 = {1, "Hamlet", 3.14}; // explicit type
auto t2 = make_tuple(1, "Ophelia"s, 3.14); // better; deduced type
```

Note the use of the s suffix to ensure that the string is a std::string, rather than a C-style string.

Note

Since you can trivially write a make_T function, so could the compiler. Thus, make_T functions might become redundant in the future.

Exception

Sometimes there isn't a good way of getting the template arguments deduced and sometimes, you want to specify the arguments explicitly:

```
vector<double> v = { 1, 2, 3, 7.9, 15.99 };
list<Record*> lst;
```

Note

Note that C++17 will make this rule redundant by allowing the template arguments to be deduced directly from constructor arguments: Template parameter deduction for constructors (Rev. 3). For example:

```
tuple t1 = {1, "Hamlet"s, 3.14}; // deduced: tuple<int, string, double>
```

Enforcement

Flag uses where an explicitly specialized type exactly matches the types of the arguments used.

T.46: Require template arguments to be at least semiregular

Reason

Readability. Preventing surprises and errors. Most uses support that anyway.

Example

Semiregular requires default constructible.

Enforcement

Flag types used as template arguments that are not at least semiregular.

T.47: Avoid highly visible unconstrained templates with common names

Reason

An unconstrained template argument is a perfect match for anything so such a template can be preferred over more specific types that require minor conversions. This is particularly annoying/dangerous when ADL is used. Common names make this problem more likely.

Example

```
namespace Bad {
    struct S { int m; };
    template<typename T1, typename T2>
    bool operator==(T1, T2) { cout << "Bad\n"; return true; }
}

namespace T0 {
    bool operator==(int, Bad::S) { cout << "T0\n"; return true; } // compare to int

    void test()
    {
        Bad::S bad{ 1 };
        vector<int> v(10);
        bool b = 1 == bad;
        bool b2 = v.size() == bad;
    }
}
```

This prints T0 and Bad.

Now the == in Bad was designed to cause trouble, but would you have spotted the problem in real code? The problem is that v.size() returns an unsigned integer so that a conversion is needed to call the local ==; the == in Bad requires no conversions. Realistic types, such as the standard-library iterators can be made to exhibit similar anti-social tendencies.

Note

If an unconstrained template is defined in the same namespace as a type, that unconstrained template can be found by ADL (as happened in the example). That is, it is highly visible.

Note

This rule should not be necessary, but the committee cannot agree to exclude unconstrained templates from ADL.

Unfortunately this will get many false positives; the standard library violates this widely, by putting many unconstrained templates and types into the single namespace std.

Enforcement

Flag templates defined in a namespace where concrete types are also defined (maybe not feasible until we have concepts).

T.48: If your compiler does not support concepts, fake them with enable_if

Reason

Because that's the best we can do without direct concept support. enable_if can be used to conditionally define functions and to select among a set of functions.

Example

```
template<typename T>
enable_if_t<is_integral_v<T>>
f(T v)
{
      // ...
}

// Equivalent to:
template<Integral T>
void f(T v)
{
      // ...
}
```

Beware of complementary constraints. Faking concept overloading using enable_if sometimes forces us to use that error-prone design technique.

Enforcement

???

T.49: Where possible, avoid type-erasure

Reason

Type erasure incurs an extra level of indirection by hiding type information behind a separate compilation boundary.

Example

???

Exceptions: Type erasure is sometimes appropriate, such as for std::function.

Enforcement

???

Note

T.def: Template definitions

A template definition (class or function) can contain arbitrary code, so only a comprehensive review of C++ programming techniques would cover this topic. However, this section focuses on what is specific to template implementation. In particular, it focuses on a template definition's dependence on its context.

T.60: Minimize a template's context dependencies

Reason

Eases understanding. Minimizes errors from unexpected dependencies. Eases tool creation.

Note

Templates typically appear in header files so their context dependencies are more vulnerable to #include order dependencies than functions in .cpp files.

Note

Having a template operate only on its arguments would be one way of reducing the number of dependencies to a minimum, but that would generally be unmanageable. For example, algorithms usually use other algorithms and invoke operations that do not exclusively operate on arguments. And don't get us started on macros!

See also: T.69

Enforcement

??? Tricky

T.61: Do not over-parameterize members (SCARY)

Reason

A member that does not depend on a template parameter cannot be used except for a specific template argument. This limits use and typically increases code size.

Example, bad

```
template<typename T, typename A = std::allocator<T>>
   // requires Regular<T> && Allocator<A>
class List {
public:
    struct Link { // does not depend on A
        T elem;
       Link* pre;
        Link* suc;
   };
   using iterator = Link*;
   iterator first() const { return head; }
   // ...
private:
   Link* head;
};
List<int> lst1;
List<int, My_allocator> 1st2;
```

This looks innocent enough, but now Link formally depends on the allocator (even though it doesn't use the allocator). This forces redundant instantiations that can be surprisingly costly in some real-world scenarios. Typically, the solution is to make what would have been a nested class non-local, with its own minimal set of template parameters.

```
template<typename T>
struct Link {
   T elem;
   Link* pre;
   Link* suc;
};
template<typename T, typename A = std::allocator<T>>
   // requires Regular<T> && Allocator<A>
class List2 {
public:
   using iterator = Link<T>*;
   iterator first() const { return head; }
   // ...
private:
   Link<T>* head;
};
List2<int> lst1;
List2<int, My_allocator> lst2;
```

Some people found the idea that the Link no longer was hidden inside the list scary, so we named the technique SCARY. From that academic paper: "The acronym SCARY describes assignments and initializations that are Seemingly erroneous (appearing Constrained by conflicting generic parameters), but Actually work with the Right implementation (unconstrained by the conflict due to minimized dependencies)."

Note

This also applies to lambdas that don't depend on all of the template parameters.

Enforcement

- Flag member types that do not depend on every template parameter
- Flag member functions that do not depend on every template parameter
- Flag lambdas or variable templates that do not depend on every template parameter

T.62: Place non-dependent class template members in a non-templated base class

Reason

Allow the base class members to be used without specifying template arguments and without template instantiation.

Example

```
template<typename T>
class Foo {
public:
    enum { v1, v2 };
    // ...
};
```

???

A more general version of this rule would be "If a class template member depends on only N template parameters out of M, place it in a base class with only N parameters." For N == 1, we have a choice of a base class of a class in the surrounding scope as in T.61.

??? What about constants? class statics?

Enforcement

■ Flag ???

T.64: Use specialization to provide alternative implementations of class templates

Reason

A template defines a general interface. Specialization offers a powerful mechanism for providing alternative implementations of that interface.

Example

```
??? string specialization (==)
??? representation specialization ?
```

Note

???

Enforcement

???

T.65: Use tag dispatch to provide alternative implementations of a function

Reason

- A template defines a general interface.
- Tag dispatch allows us to select implementations based on specific properties of an argument type.
- Performance.

This is a simplified version of std::copy (ignoring the possibility of non-contiguous sequences)

```
struct trivially_copyable_tag {};
struct non_trivially_copyable_tag {};
// T is not trivially copyable
template<class T> struct copy_trait { using tag = non_trivially_copyable_tag; };
// int is trivially copyable
template<> struct copy_trait<int> { using tag = trivially_copyable_tag; };
template<class Iter>
Out copy_helper(Iter first, Iter last, Iter out, trivially_copyable_tag)
    // use memmove
}
template<class Iter>
Out copy_helper(Iter first, Iter last, Iter out, non_trivially_copyable_tag)
    // use loop calling copy constructors
}
template<class Iter>
Out copy(Iter first, Iter last, Iter out)
    using tag_type = typename copy_trait<std::iter_value_t<Iter>>;
    return copy_helper(first, last, out, tag_type{})
}
void use(vector<int>& vi, vector<int>& vi2, vector<string>& vs, vector<string>& vs2)
{
    copy(vi.begin(), vi.end(), vi2.begin()); // uses memmove
    copy(vs.begin(), vs.end(), vs2.begin()); // uses a loop calling copy constructors
}
```

This is a general and powerful technique for compile-time algorithm selection.

Note

With C++20 constraints, such alternatives can be distinguished directly:

```
template<class Iter>
    requires std::is_trivially_copyable_v<std::iter_value_t<Iter>>
Out copy_helper(In, first, In last, Out out)
{
    // use memmove
}

template<class Iter>
Out copy_helper(In, first, In last, Out out)
{
    // use loop calling copy constructors
}
```

Enforcement

???

T.67: Use specialization to provide alternative implementations for irregular types

Reason

???

Example

```
???
```

Enforcement

???

T.68: Use {} rather than () within templates to avoid ambiguities

Reason

() is vulnerable to grammar ambiguities.

Enforcement

- flag () initializers
- flag function-style casts

T.69: Inside a template, don't make an unqualified non-member function call unless you intend it to be a customization point

Reason

- Provide only intended flexibility.
- Avoid vulnerability to accidental environmental changes.

Example

There are three major ways to let calling code customize a template.

```
template<class T>
    // Call a member function
void test1(T t)
{
    t.f();    // require T to provide f()
}

template<class T>
void test2(T t)
    // Call a non-member function without qualification
{
    f(t);    // require f(/*T*/) be available in caller's scope or in T's namespace
}

template<class T>
void test3(T t)
    // Invoke a "trait"
{
```

A trait is usually a type alias to compute a type, a constexpr function to compute a value, or a traditional traits template to be specialized on the user's type.

Note

If you intend to call your own helper function helper(t) with a value t that depends on a template type parameter, put it in a ::detail namespace and qualify the call as detail::helper(t);. An unqualified call becomes a customization point where any function helper in the namespace of t's type can be invoked; this can cause problems like unintentionally invoking unconstrained function templates.

Enforcement

• In a template, flag an unqualified call to a non-member function that passes a variable of dependent type when there is a non-member function of the same name in the template's namespace.

T.temp-hier: Template and hierarchy rules:

Templates are the backbone of C++'s support for generic programming and class hierarchies the backbone of its support for object-oriented programming. The two language mechanisms can be used effectively in combination, but a few design pitfalls must be avoided.

T.80: Do not naively templatize a class hierarchy

Reason

Templating a class hierarchy that has many functions, especially many virtual functions, can lead to code bloat.

Example, bad

```
Vector<int> vi;
Vector<string> vs;
```

It is probably a bad idea to define a sort as a member function of a container, but it is not unheard of and it makes a good example of what not to do.

Given this, the compiler cannot know if vector<int>::sort() is called, so it must generate code for it. Similar for vector<string>::sort(). Unless those two functions are called that's code bloat. Imagine what this would do to a class hierarchy with dozens of member functions and dozens of derived classes with many instantiations.

Note

In many cases you can provide a stable interface by not parameterizing a base; see "stable base" and OO and GP

Enforcement

• Flag virtual functions that depend on a template argument. ??? False positives

T.81: Do not mix hierarchies and arrays

Reason

An array of derived classes can implicitly "decay" to a pointer to a base class with potential disastrous results.

Example

Assume that Apple and Pear are two kinds of Fruits.

Probably, aa[0] will be a Pear (without the use of a cast!). If sizeof(Apple) != sizeof(Pear) the access to aa[1] will not be aligned to the proper start of an object in the array. We have a type violation and possibly (probably) a memory corruption. Never write such code.

Note that maul() violates the a T* points to an individual object rule.

Alternative: Use a proper (templatized) container:

```
void maul2(Fruit* p)
{
    *p = Pear{};    // put a Pear into *p
}

vector<Apple> va = { an_apple, another_apple };    // va contains Apples (obviously!)

maul2(va);    // error: cannot convert a vector<Apple> to a Fruit*
maul2(&va[0]);    // you asked for it

Apple& a0 = &va[0];    // a Pear?
```

Note that the assignment in maul2() violated the no-slicing rule.

Enforcement

Detect this horror!

T.82: Linearize a hierarchy when virtual functions are undesirable

Reason

???

Example

```
???
```

Enforcement

???

T.83: Do not declare a member function template virtual

Reason

C++ does not support that. If it did, vtbls could not be generated until link time. And in general, implementations must deal with dynamic linking.

Example, don't

```
class Shape {
    // ...
    template<class T>
    virtual bool intersect(T* p); // error: template cannot be virtual
};
```

Note

We need a rule because people keep asking about this

Alternative

Double dispatch, visitors, calculate which function to call

Enforcement

The compiler handles that.

T.84: Use a non-template core implementation to provide an ABI-stable interface

Reason

Improve stability of code. Avoid code bloat.

Example

It could be a base class:

```
template<typename T>
class List : List_base {
public:
    void put_front(const T& e) { add_front(new Link<T>{e}); } // implicit cast to Link_base
    T& front() { static_cast<Link<T>*>(first).val; } // explicit cast back to Link<T>
    // ...
};
List<int> li;
List<string> ls;
```

Now there is only one copy of the operations linking and unlinking elements of a List. The Link and List classes do nothing but type manipulation.

Instead of using a separate "base" type, another common technique is to specialize for void or void* and have the general template for T be just the safely-encapsulated casts to and from the core void implementation.

Alternative: Use a Pimpl implementation.

Enforcement

???

T.var: Variadic template rules

???

T.100: Use variadic templates when you need a function that takes a variable number of arguments of a variety of types

Reason

Variadic templates is the most general mechanism for that, and is both efficient and type-safe. Don't use C varargs.

Example

```
??? printf
```

Enforcement

• Flag uses of va_arg in user code.

T.101: ??? How to pass arguments to a variadic template ???

Reason

???

Example

??? beware of move-only and reference arguments

Enforcement

???

T.102: How to process arguments to a variadic template

Reason

???

Example

??? forwarding, type checking, references

Enforcement

???

T.103: Don't use variadic templates for homogeneous argument lists

Reason

There are more precise ways of specifying a homogeneous sequence, such as an initializer_list.

???

Enforcement

???

T.meta: Template metaprogramming (TMP)

Templates provide a general mechanism for compile-time programming.

Metaprogramming is programming where at least one input or one result is a type. Templates offer Turing-complete (modulo memory capacity) duck typing at compile time. The syntax and techniques needed are pretty horrendous.

T.120: Use template metaprogramming only when you really need to

Reason

Template metaprogramming is hard to get right, slows down compilation, and is often very hard to maintain. However, there are real-world examples where template metaprogramming provides better performance than any alternative short of expert-level assembly code. Also, there are real-world examples where template metaprogramming expresses the fundamental ideas better than run-time code. For example, if you really need AST manipulation at compile time (e.g., for optional matrix operation folding) there might be no other way in C++.

Example, bad

333

Example, bad

enable if

Instead, use concepts. But see How to emulate concepts if you don't have language support.

Example

??? good

Alternative: If the result is a value, rather than a type, use a constexpr function.

If you feel the need to hide your template metaprogramming in macros, you have probably gone too far.

T.121: Use template metaprogramming primarily to emulate concepts

Reason

Where C++20 is not available, we need to emulate them using TMP. Use cases that require concepts (e.g. overloading based on concepts) are among the most common (and simple) uses of TMP.

Example

```
template<typename Iter>
    /*requires*/ enable_if<random_access_iterator<Iter>, void>
advance(Iter p, int n) { p += n; }

template<typename Iter>
    /*requires*/ enable_if<forward_iterator<Iter>, void>
advance(Iter p, int n) { assert(n >= 0); while (n--) ++p;}
```

Note

Such code is much simpler using concepts:

```
void advance(random_access_iterator auto p, int n) { p += n; }
void advance(forward_iterator auto p, int n) { assert(n >= 0); while (n--) ++p;}
```

Enforcement

???

T.122: Use templates (usually template aliases) to compute types at compile time

Reason

Template metaprogramming is the only directly supported and half-way principled way of generating types at compile time.

"Traits" techniques are mostly replaced by template aliases to compute types and constexpr functions to compute values.

Example

```
??? big object / small object optimization
```

Enforcement

???

T.123: Use constexpr functions to compute values at compile time

Reason

A function is the most obvious and conventional way of expressing the computation of a value. Often a constexpr function implies less compile-time overhead than alternatives.

Note

"Traits" techniques are mostly replaced by template aliases to compute types and constexpr functions to compute values.

Example

```
template<typename T>
    // requires Number<T>
constexpr T pow(T v, int n) // power/exponential
{
    T res = 1;
    while (n--) res *= v;
    return res;
}

constexpr auto f7 = pow(pi, 7);
```

Enforcement

• Flag template metaprograms yielding a value. These should be replaced with constexpr functions.

T.124: Prefer to use standard-library TMP facilities

Reason

Facilities defined in the standard, such as conditional, enable_if, and tuple, are portable and can be assumed to be known.

Example

????

Enforcement

???

T.125: If you need to go beyond the standard-library TMP facilities, use an existing library

Reason

Getting advanced TMP facilities is not easy and using a library makes you part of a (hopefully supportive) community. Write your own "advanced TMP support" only if you really have to.

Example

???

Enforcement

???

Other template rules

T.140: If an operation can be reused, give it a name

See F.10

T.141: Use an unnamed lambda if you need a simple function object in one place only

See F.11

T.142?: Use template variables to simplify notation

Reason

Improved readability.

Example

```
???
```

Enforcement

???

T.143: Don't write unintentionally non-generic code

Reason

Generality. Reusability. Don't gratuitously commit to details; use the most general facilities available.

Example

Use != instead of < to compare iterators; != works for more objects because it doesn't rely on ordering.

Of course, range-for is better still where it does what you want.

Use the least-derived class that has the functionality you need.

```
class Base {
public:
    Bar f();
    Bar g();
};
class Derived1 : public Base {
public:
    Bar h();
};
class Derived2 : public Base {
public:
    Bar j();
};
// bad, unless there is a specific reason for limiting to Derived1 objects only
void my_func(Derived1& param)
    use(param.f());
    use(param.g());
}
// good, uses only Base interface so only commit to that
void my_func(Base& param)
{
    use(param.f());
    use(param.g());
}
```

Enforcement

- Flag comparison of iterators using < instead of !=.
- Flag x.size() == 0 when x.empty() or x.is_empty() is available. Emptiness works for more containers than size(), because some containers don't know their size or are conceptually of unbounded size.
- Flag functions that take a pointer or reference to a more-derived type but only use functions declared in a base type.

T.144: Don't specialize function templates

Reason

You can't partially specialize a function template per language rules. You can fully specialize a function template but you almost certainly want to overload instead -- because function template specializations don't participate in overloading, they don't act as you probably wanted. Rarely, you should actually specialize by delegating to a class template that you can specialize properly.

Example

```
???
```

Exceptions: If you do have a valid reason to specialize a function template, just write a single function template that delegates to a class template, then specialize the class template (including the ability to write partial specializations).

Enforcement

• Flag all specializations of a function template. Overload instead.

T.150: Check that a class matches a concept using static_assert

Reason

If you intend for a class to match a concept, verifying that early saves users' pain.

Example

```
class X {
public:
    X() = delete;
    X(const X&) = default;
    X(X&&) = default;
    X& operator=(const X&) = default;
    // ...
};
```

Somewhere, possibly in an implementation file, let the compiler check the desired properties of X:

Not feasible.

CPL: C-style programming

C and C++ are closely related languages. They both originate in "Classic C" from 1978 and have evolved in ISO committees since then. Many attempts have been made to keep them compatible, but neither is a subset of the other.

C rule summary:

- CPL.1: Prefer C++ to C
- CPL.2: If you must use C, use the common subset of C and C++, and compile the C code as C++
- CPL.3: If you must use C for interfaces, use C++ in the calling code using such interfaces

CPL.1: Prefer C++ to C

Reason

C++ provides better type checking and more notational support. It provides better support for high-level programming and often generates faster code.

Example

```
char ch = 7;
void* pv = &ch;
int* pi = pv;  // not C++
*pi = 999;  // overwrite sizeof(int) bytes near &ch
```

The rules for implicit casting to and from void* in C are subtle and unenforced. In particular, this example violates a rule against converting to a type with stricter alignment.

Enforcement

Use a C++ compiler.

CPL.2: If you must use C, use the common subset of C and C++, and compile the C code as C++

Reason

That subset can be compiled with both C and C++ compilers, and when compiled as C++ is better type checked than "pure C."

Example

Enforcement

- Flag if using a build mode that compiles code as C.
 - The C++ compiler will enforce that the code is valid C++ unless you use C extension options.

CPL.3: If you must use C for interfaces, use C++ in the calling code using such interfaces

Reason

C++ is more expressive than C and offers better support for many types of programming.

Example

For example, to use a 3rd party C library or C systems interface, define the low-level interface in the common subset of C and C++ for better type checking. Whenever possible encapsulate the low-level interface in an interface that follows the C++ guidelines (for better abstraction, memory safety, and resource safety) and use that C++ interface in C++ code.

Example

You can call C from C++:

```
// in C:
double sqrt(double);

// in C++:
extern "C" double sqrt(double);

sqrt(2);
```

Example

You can call C++ from C:

```
// in C:
X call_f(struct Y*, int);

// in C++:
extern "C" X call_f(Y* p, int i)
{
    return p->f(i); // possibly a virtual function call
}
```

Enforcement

None needed

SF: Source files

Distinguish between declarations (used as interfaces) and definitions (used as implementations). Use header files to represent interfaces and to emphasize logical structure.

Source file rule summary:

- SF.1: Use a .cpp suffix for code files and .h for interface files if your project doesn't already follow another convention
- SF.2: A header file must not contain object definitions or non-inline function definitions
- SF.3: Use header files for all declarations used in multiple source files
- SF.4: Include header files before other declarations in a file
- SF.5: A .cpp file must include the header file(s) that defines its interface
- SF.6: Use using namespace directives for transition, for foundation libraries (such as std), or within a local scope (only)
- SF.7: Don't write using namespace at global scope in a header file
- SF.8: Use #include guards for all header files
- SF.9: Avoid cyclic dependencies among source files
- SF.10: Avoid dependencies on implicitly #included names
- SF.11: Header files should be self-contained
- SF.12: Prefer the quoted form of #include for files relative to the including file and the angle bracket form everywhere else
- SF.13: Use portable header identifiers in #include statements
- SF.20: Use namespaces to express logical structure
- SF.21: Don't use an unnamed (anonymous) namespace in a header
- SF.22: Use an unnamed (anonymous) namespace for all internal/non-exported entities

SF.1: Use a .cpp suffix for code files and .h for interface files if your project doesn't already follow another convention

See NL.27

SF.2: A header file must not contain object definitions or non-inline function definitions

Reason

Including entities subject to the one-definition rule leads to linkage errors.

Example

```
// file.h:
namespace Foo {
    int x = 7;
    int xx() { return x+x; }
}

// file1.cpp:
#include <file.h>
// ... more ...

// file2.cpp:
#include <file.h>
// ... more ...
```

Linking file1.cpp and file2.cpp will give two linker errors.

Alternative formulation: A header file must contain only:

- #includes of other header files (possibly with include guards)
- templates
- class definitions
- function declarations
- extern declarations
- inline function definitions
- constexpr definitions
- const definitions
- using alias definitions
- **????**

Check the positive list above.

SF.3: Use header files for all declarations used in multiple source files

Reason

Maintainability. Readability.

Example, bad

```
// bar.cpp:
void bar() { cout << "bar\n"; }

// foo.cpp:
extern void bar();
void foo() { bar(); }</pre>
```

A maintainer of bar cannot find all declarations of bar if its type needs changing. The user of bar cannot know if the interface used is complete and correct. At best, error messages come (late) from the linker.

Enforcement

• Flag declarations of entities in other source files not placed in a .h.

SF.4: Include header files before other declarations in a file

Reason

Minimize context dependencies and increase readability.

Example

```
#include <vector>
#include <algorithm>
#include <string>
// ... my code here ...
```

Example, bad

```
#include <vector>
// ... my code here ...
#include <algorithm>
#include <string>
```

Note

This applies to both .h and .cpp files.

Note

There is an argument for insulating code from declarations and macros in header files by **#including** headers *after* the code we want to protect (as in the example labeled "bad"). However

- that only works for one file (at one level): Use that technique in a header included with other headers and the vulnerability reappears.
- a namespace (an "implementation namespace") can protect against many context dependencies.
- full protection and flexibility require modules.

See also:

- Working Draft, Extensions to C++ for Modules
- Modules, Componentization, and Transition

Enforcement

Easy.

SF.5: A . cpp file must include the header file(s) that defines its interface

Reason

This enables the compiler to do an early consistency check.

Example, bad

```
// foo.h:
void foo(int);
int bar(long);
int foobar(int);

// foo.cpp:
void foo(int) { /* ... */ }
int bar(double) { /* ... */ }
double foobar(int);
```

The errors will not be caught until link time for a program calling bar or foobar.

Example

```
// foo.h:
void foo(int);
int bar(long);
int foobar(int);

// foo.cpp:
#include "foo.h"

void foo(int) { /* ... */ }
int bar(double) { /* ... */ }
double foobar(int); // error: wrong return type
```

The return-type error for foobar is now caught immediately when foo.cpp is compiled. The argument-type error for bar cannot be caught until link time because of the possibility of overloading, but systematic use of .h files increases the likelihood that it is caught earlier by the programmer.

Enforcement

???

SF.6: Use using namespace directives for transition, for foundation libraries (such as std), or within a local scope (only)

Reason

using namespace can lead to name clashes, so it should be used sparingly. However, it is not always possible to qualify every name from a namespace in user code (e.g., during transition) and sometimes a namespace is so fundamental and prevalent in a code base, that consistent qualification would be verbose and distracting.

Example

```
#include <string>
#include <vector>
#include <iostream>
#include <memory>
#include <algorithm>

using namespace std;
// ...
```

Here (obviously), the standard library is used pervasively and apparently no other library is used, so requiring std:: everywhere could be distracting.

Example

The use of using namespace std; leaves the programmer open to a name clash with a name from the standard library

```
#include <cmath>
using namespace std;

int g(int x)
{
   int sqrt = 7;
   // ...
   return sqrt(x); // error
}
```

However, this is not particularly likely to lead to a resolution that is not an error and people who use using namespace std are supposed to know about std and about this risk.

Note

A .cpp file is a form of local scope. There is little difference in the opportunities for name clashes in an N-line .cpp containing a using namespace X, an N-line function containing a using namespace X, and M functions each containing a using namespace Xwith N lines of code in total.

Note

Don't write using namespace at global scope in a header file.

SF.7: Don't write using namespace at global scope in a header file

Reason

Doing so takes away an #includer's ability to effectively disambiguate and to use alternatives. It also makes #included headers order-dependent as they might have different meaning when included in different orders.

Example

```
// bad.h
#include <iostream>
using namespace std; // bad

// user.cpp
#include "bad.h"

bool copy(/*... some parameters ...*/); // some function that happens to be named copy
int main()
{
    copy(/*...*/); // now overloads local ::copy and std::copy, could be ambiguous
}
```

Note

An exception is using namespace std::literals;. This is necessary to use string literals in header files and given the rules - users are required to name their own UDLs operator""_x - they will not collide with the standard library.

Enforcement

Flag using namespace at global scope in a header file.

SF.8: Use **#incLude** guards for all header files

Reason

To avoid files being #included several times.

In order to avoid include guard collisions, do not just name the guard after the filename. Be sure to also include a key and good differentiator, such as the name of library or component the header file is part of.

Example

```
// file foobar.h:
#ifndef LIBRARY_FOOBAR_H
#define LIBRARY_FOOBAR_H
// ... declarations ...
#endif // LIBRARY_FOOBAR_H
```

Enforcement

Flag .h files without #include guards.

Note

Some implementations offer vendor extensions like #pragma once as alternative to include guards. It is not standard and it is not portable. It injects the hosting machine's filesystem semantics into your program, in addition to locking you down to a vendor. Our recommendation is to write in ISO C++: See rule P.2.

SF.9: Avoid cyclic dependencies among source files

Reason

Cycles complicate comprehension and slow down compilation. They also complicate conversion to use language-supported modules (when they become available).

Note

Eliminate cycles; don't just break them with #include guards.

Example, bad

```
// file1.h:
#include "file2.h"

// file2.h:
#include "file3.h"

// file3.h:
#include "file1.h"
```

Enforcement

Flag all cycles.

SF.10: Avoid dependencies on implicitly #incLuded names

Reason

Avoid surprises. Avoid having to change #includes if an #included header changes. Avoid accidentally becoming dependent on implementation details and logically separate entities included in a header.

Example, bad

<iostream> exposes the definition of std::string ("why?" makes for a fun trivia question), but it is not required
to do so by transitively including the entire <string> header, resulting in the popular beginner question "why
doesn't getline(cin,s); work?" or even an occasional "strings cannot be compared with ==").

The solution is to explicitly #include <string>:

Example, good

Note

Some headers exist exactly to collect a set of consistent declarations from a variety of headers. For example:

```
// basic_std_lib.h:

#include <string>
#include <map>
#include <iostream>
#include <random>
#include <vector>
```

a user can now get that set of declarations with a single #include

```
#include "basic_std_lib.h"
```

This rule against implicit inclusion is not meant to prevent such deliberate aggregation.

Enforcement

Enforcement would require some knowledge about what in a header is meant to be "exported" to users and what is there to enable implementation. No really good solution is possible until we have modules.

SF.11: Header files should be self-contained

Reason

Usability, headers should be simple to use and work when included on their own. Headers should encapsulate the functionality they provide. Avoid clients of a header having to manage that header's dependencies.

Example

```
#include "helpers.h"
// helpers.h depends on std::string and includes <string>
```

Note

Failing to follow this results in difficult to diagnose errors for clients of a header.

Note

A header should include all its dependencies. Be careful about using relative paths because C++ implementations diverge on their meaning.

A test should verify that the header file itself compiles or that a cpp file which only includes the header file compiles.

SF.12: Prefer the quoted form of **#incLude** for files relative to the including file and the angle bracket form everywhere else

Reason

The standard provides flexibility for compilers to implement the two forms of #include selected using the angle (<>) or quoted ("") syntax. Vendors take advantage of this and use different search algorithms and methods for specifying the include path.

Nevertheless, the guidance is to use the quoted form for including files that exist at a relative path to the file containing the #include statement (from within the same component or project) and to use the angle bracket form everywhere else, where possible. This encourages being clear about the locality of the file relative to files that include it, or scenarios where the different search algorithm is required. It makes it easy to understand at a glance whether a header is being included from a local relative file versus a standard library header or a header from the alternate search path (e.g. a header from another library or a common set of includes).

Example

Note

Failing to follow this results in difficult to diagnose errors due to picking up the wrong file by incorrectly specifying the scope when it is included. For example, in a typical case where the #include "" search algorithm might search for a file existing at a local relative path first, then using this form to refer to a file that is not locally relative could mean that if a file ever comes into existence at the local relative path (e.g. the including file is moved to a new location), it will now be found ahead of the previous include file and the set of includes will have been changed in an unexpected way.

Library creators should put their headers in a folder and have clients include those files using the relative path #include <some library/common.h>

A test should identify whether headers referenced via "" could be referenced with <>.

SF.13: Use portable header identifiers in #include statements

Reason

The standard does not specify how compilers uniquely locate headers from an identifier in an #include directive, nor does it specify what constitutes uniqueness. For example, whether the implementation considers the identifiers to be case-sensitive, or whether the identifiers are file system paths to a header file, and if so, how a hierarchical file system path is delimited.

To maximize the portability of #include directives across compilers, guidance is to:

- use case-sensitivity for the header identifier, matching how the header is defined by the standard, specification, implementation, or file that provides the header.
- when the header identifier is a hierarchical file path, use forward-slash / to delimit path components as this is the most widely-accepted path-delimiting character.

Example

```
// good examples
#include <vector>
#include <string>
#include "util/util.h"
// bad examples
#include <VECTOR>
                        // bad: the standard library defines a header identified as <vector>,
not <VECTOR>
                         // bad: the standard library defines a header identified as <string>,
#include <String>
not <String>
#include "Util/Util.H"
                         // bad: the header file exists on the file system as "util/util.h"
#include "util\util.h"
                         // bad: may not work if the implementation interprets `\u` as an
escape sequence, or where '\' is not a valid path separator
```

Enforcement

It is only possible to enforce on implementations where header identifiers are case-sensitive and which only support / as a file path delimiter.

SF.20: Use namespaces to express logical structure

Reason

???

Example

```
???
```

Enforcement

???

SF.21: Don't use an unnamed (anonymous) namespace in a header

Reason

It is almost always a bug to mention an unnamed namespace in a header file.

Example

```
// file foo.h:
namespace
{
    const double x = 1.234; // bad

    double foo(double y) // bad
    {
        return y + x;
    }
}

namespace Foo
{
    const double x = 1.234; // good

    inline double foo(double y) // good
    {
        return y + x;
    }
}
```

• Flag any use of an anonymous namespace in a header file.

SF.22: Use an unnamed (anonymous) namespace for all internal/nonexported entities

Reason

Nothing external can depend on an entity in a nested unnamed namespace. Consider putting every definition in an implementation source file in an unnamed namespace unless that is defining an "external/exported" entity.

Example; bad

```
static int f();
int g();
static bool h();
int k();
```

Example; good

```
namespace {
    int f();
    bool h();
}
int g();
int k();
```

Example

An API class and its members can't live in an unnamed namespace; but any "helper" class or function that is defined in an implementation source file should be at an unnamed namespace scope.

```
???
```

Enforcement

???

SL: The Standard Library

Using only the bare language, every task is tedious (in any language). Using a suitable library any task can be reasonably simple.

The standard library has steadily grown over the years. Its description in the standard is now larger than that of the language features. So, it is likely that this library section of the guidelines will eventually grow in size to equal or exceed all the rest.

<< ??? We need another level of rule numbering ??? >>

C++ Standard Library component summary:

- SL.con: Containers
- SL.str: String
- SL.io: Iostream
- SL.regex: Regex
- SL.chrono: Time
- SL.C: The C Standard Library

Standard-library rule summary:

- SL.1: Use libraries wherever possible
- SL.2: Prefer the standard library to other libraries
- SL.3: Do not add non-standard entities to namespace std
- SL.4: Use the standard library in a type-safe manner
- **???**

SL.1: Use libraries wherever possible

Reason

Save time. Don't re-invent the wheel. Don't replicate the work of others. Benefit from other people's work when they make improvements. Help other people when you make improvements.

SL.2: Prefer the standard library to other libraries

Reason

More people know the standard library. It is more likely to be stable, well-maintained, and widely available than your own code or most other libraries.

SL.3: Do not add non-standard entities to namespace std

Reason

Adding to std might change the meaning of otherwise standards conforming code. Additions to std might clash with future versions of the standard.

Example

```
namespace std { // BAD: violates standard

class My_vector {
    // ...
};

}

namespace Foo { // GOOD: user namespace is allowed

class My_vector {
    // ...
};

}
```

Enforcement

Possible, but messy and likely to cause problems with platforms.

SL.4: Use the standard library in a type-safe manner

Reason

Because, obviously, breaking this rule can lead to undefined behavior, memory corruption, and all kinds of other bad errors.

Note

This is a semi-philosophical meta-rule, which needs many supporting concrete rules. We need it as an umbrella for the more specific rules.

Summary of more specific rules:

• SL.4: Use the standard library in a type-safe manner

SL.con: Containers

Container rule summary:

- SL.con.1: Prefer using STL array or vector instead of a C array
- SL.con.2: Prefer using STL vector by default unless you have a reason to use a different container
- SL.con.3: Avoid bounds errors
- SL.con.4: don't use memset or memcpy for arguments that are not trivially-copyable

SL.con.1: Prefer using STL array or vector instead of a C array

Reason

C arrays are less safe, and have no advantages over array and vector. For a fixed-length array, use std::array, which does not degenerate to a pointer when passed to a function and does know its size. Also, like a built-in array, a stack-allocated std::array keeps its elements on the stack. For a variable-length array, use std::vector, which additionally can change its size and handles memory allocation.

Example

```
int v[SIZE];  // BAD
std::array<int, SIZE> w;  // ok
```

Example

Note

Use gsl::span for non-owning references into a container.

Note

Comparing the performance of a fixed-sized array allocated on the stack against a vector with its elements on the free store is bogus. You could just as well compare a std::array on the stack against the result of a malloc() accessed through a pointer. For most code, even the difference between stack allocation and free-store allocation doesn't matter, but the convenience and safety of vector does. People working with code for which that difference matters are quite capable of choosing between array and vector.

• Flag declaration of a C array inside a function or class that also declares an STL container (to avoid excessive noisy warnings on legacy non-STL code). To fix: At least change the C array to a std::array.

SL.con.2: Prefer using STL vector by default unless you have a reason to use a different container

Reason

vector and array are the only standard containers that offer the following advantages:

- the fastest general-purpose access (random access, including being vectorization-friendly);
- the fastest default access pattern (begin-to-end or end-to-begin is prefetcher-friendly);
- the lowest space overhead (contiguous layout has zero per-element overhead, which is cache-friendly).

Usually you need to add and remove elements from the container, so use vector by default; if you don't need to modify the container's size, use array.

Even when other containers seem more suited, such as map for O(log N) lookup performance or a list for efficient insertion in the middle, a vector will usually still perform better for containers up to a few KB in size.

Note

string should not be used as a container of individual characters. A string is a textual string; if you want a container of characters, use vector</*char_type*/> or array</*char_type*/> instead.

Exceptions

If you have a good reason to use another container, use that instead. For example:

- If vector suits your needs but you don't need the container to be variable size, use array instead.
- If you want a dictionary-style lookup container that guarantees O(K) or O(log N) lookups, the container will be larger (more than a few KB) and you perform frequent inserts so that the overhead of maintaining a sorted vector is infeasible, go ahead and use an unordered_map or map instead.

Note

To initialize a vector with a number of elements, use ()-initialization. To initialize a vector with a list of elements, use {}-initialization.

```
vector<int> v1(20); // v1 has 20 elements with the value 0 (vector<int>{}) vector<int> v2 \{20\}; // v2 has 1 element with the value 20
```

Prefer the {}-initializer syntax.

• Flag a vector whose size never changes after construction (such as because it's const or because no non-const functions are called on it). To fix: Use an array instead.

SL.con.3: Avoid bounds errors

Reason

Read or write beyond an allocated range of elements typically leads to bad errors, wrong results, crashes, and security violations.

Note

The standard-library functions that apply to ranges of elements all have (or could have) bounds-safe overloads that take span. Standard types such as vector can be modified to perform bounds-checks under the bounds profile (in a compatible way, such as by adding contracts), or used with at().

Ideally, the in-bounds guarantee should be statically enforced. For example:

- a range-for cannot loop beyond the range of the container to which it is applied
- a v.begin(), v.end() is easily determined to be bounds safe

Such loops are as fast as any unchecked/unsafe equivalent.

Often a simple pre-check can eliminate the need for checking of individual indices. For example

• for v.begin(), v.begin()+i the i can easily be checked against v.size()

Such loops can be much faster than individually checked element accesses.

Example, bad

Also, std::array<>::fill() or std::fill() or even an empty initializer are better candidates than memset().

Example, good

Example

If code is using an unmodified standard library, then there are still workarounds that enable use of std::array and std::vector in a bounds-safe manner. Code can call the .at() member function on each class, which will result in an std::out_of_range exception being thrown. Alternatively, code can call the at() free function, which will result in fail-fast (or a customized action) on a bounds violation.

Enforcement

• Issue a diagnostic for any call to a standard-library function that is not bounds-checked. ??? insert link to a list of banned functions

This rule is part of the bounds profile.

SL.con.4: don't use memset or memcpy for arguments that are not triviallycopyable

Reason

Doing so messes the semantics of the objects (e.g., by overwriting a vptr).

Note

Similarly for (w)memset, (w)memcpy, (w)memmove, and (w)memcmp

Example

```
struct base {
    virtual void update() = 0;
};

struct derived : public base {
    void update() override {}
};
```

```
void f(derived& a, derived& b) // goodbye v-tables
{
    memset(&a, 0, sizeof(derived));
    memcpy(&a, &b, sizeof(derived));
    memcmp(&a, &b, sizeof(derived));
}
```

Instead, define proper default initialization, copy, and comparison functions

Enforcement

• Flag the use of those functions for types that are not trivially copyable

TODO Notes:

- Impact on the standard library will require close coordination with WG21, if only to ensure compatibility even if never standardized.
- We are considering specifying bounds-safe overloads for stdlib (especially C stdlib) functions like memcmp and shipping them in the GSL.
- For existing stdlib functions and types like vector that are not fully bounds-checked, the goal is for these features to be bounds-checked when called from code with the bounds profile on, and unchecked when called from legacy code, possibly using contracts (concurrently being proposed by several WG21 members).

SL.str: String

Text manipulation is a huge topic. std::string doesn't cover all of it. This section primarily tries to clarify std::string's relation to char*, zstring, string_view, and gsl::span<char>. The important issue of non-ASCII character sets and encodings (e.g., wchar_t, Unicode, and UTF-8) will be covered elsewhere.

See also: regular expressions

Here, we use "sequence of characters" or "string" to refer to a sequence of characters meant to be read as text (somehow, eventually). We don't consider ???

String summary:

- SL.str.1: Use std::string to own character sequences
- SL.str.2: Use std::string_view or gsl::span<char> to refer to character sequences
- SL.str.3: Use zstring or czstring to refer to a C-style, zero-terminated, sequence of characters
- SL.str.4: Use char* to refer to a single character
- SL.str.5: Use std::byte to refer to byte values that do not necessarily represent characters
- SL.str.10: Use std::string when you need to perform locale-sensitive string operations
- SL.str.11: Use gsl::span<char> rather than std::string_view when you need to mutate a string
- SL.str.12: Use the s suffix for string literals meant to be standard-library strings

See also:

- F.24 span
- F.25 zstring

SL.str.1: Use std::string to own character sequences

Reason

string correctly handles allocation, ownership, copying, gradual expansion, and offers a variety of useful operations.

Example

```
vector<string> read_until(const string& terminator)
{
    vector<string> res;
    for (string s; cin >> s && s != terminator; ) // read a word
        res.push_back(s);
    return res;
}
```

Note how >> and != are provided for string (as examples of useful operations) and there are no explicit allocations, deallocations, or range checks (string takes care of those).

In C++17, we might use string_view as the argument, rather than const string& to allow more flexibility to callers:

```
vector<string> read_until(string_view terminator) // C++17
{
    vector<string> res;
    for (string s; cin >> s && s != terminator; ) // read a word
        res.push_back(s);
    return res;
}
```

Example, bad

Don't use C-style strings for operations that require non-trivial memory management

```
char* cat(const char* s1, const char* s2)  // beware!
    // return s1 + '.' + s2
{
    int l1 = strlen(s1);
    int l2 = strlen(s2);
    char* p = (char*) malloc(l1 + l2 + 2);
    strcpy(p, s1, l1);
    p[l1] = '.';
    strcpy(p + l1 + 1, s2, l2);
    p[l1 + l2 + 1] = 0;
    return p;
}
```

Did we get that right? Will the caller remember to free() the returned pointer? Will this code pass a security review?

Note

Do not assume that string is slower than lower-level techniques without measurement and remember that not all code is performance critical. Don't optimize prematurely

Enforcement

???

SL.str.2: Use std::string_view or gsl::span<char> to refer to character sequences

Reason

std::string_view or gsl::span<char> provides simple and (potentially) safe access to character sequences independently of how those sequences are allocated and stored.

Example

```
vector<string> read_until(string_view terminator);

void user(zstring p, const string& s, string_view ss)
{
    auto v1 = read_until(p);
    auto v2 = read_until(s);
    auto v3 = read_until(ss);
    // ...
}
```

Note

std::string_view (C++17) is read-only.

Enforcement

???

SL.str.3: Use zstring or czstring to refer to a C-style, zero-terminated, sequence of characters

Reason

Readability. Statement of intent. A plain char* can be a pointer to a single character, a pointer to an array of characters, a pointer to a C-style (zero-terminated) string, or even to a small integer. Distinguishing these alternatives prevents misunderstandings and bugs.

Example

```
void f1(const char* s); // s is probably a string
```

All we know is that it is supposed to be the nullptr or point to at least one character

```
void f1(zstring s);  // s is a C-style string or the nullptr
void f1(czstring s);  // s is a C-style string constant or the nullptr
void f1(std::byte* s);  // s is a pointer to a byte (C++17)
```

Note

Don't convert a C-style string to string unless there is a reason to.

Note

Like any other "plain pointer", a zstring should not represent ownership.

Note

There are billions of lines of C++ "out there", most use char* and const char* without documenting intent. They are used in a wide variety of ways, including to represent ownership and as generic pointers to memory (instead of void*). It is hard to separate these uses, so this guideline is hard to follow. This is one of the major sources of bugs in C and C++ programs, so it is worthwhile to follow this guideline wherever feasible.

Enforcement

- Flag uses of [] on a char*
- Flag uses of delete on a char*
- Flag uses of free() on a char*

SL.str.4: Use char to refer to a single character*

Reason

The variety of uses of char* in current code is a major source of errors.

Example, bad

```
char arr[] = {'a', 'b', 'c'};

void print(const char* p)
{
   cout << p << '\n';
}

void use()
{
   print(arr); // run-time error; potentially very bad
}</pre>
```

The array arr is not a C-style string because it is not zero-terminated.

Alternative

See zstring, string, and string_view.

Enforcement

• Flag uses of [] on a char*

SL.str.5: Use **std::byte** to refer to byte values that do not necessarily represent characters

Reason

Use of char* to represent a pointer to something that is not necessarily a character causes confusion and disables valuable optimizations.

Example

???

Note

C++17

Enforcement

???

SL.str.10: Use std::string when you need to perform locale-sensitive string operations

Reason

std::string supports standard-library locale facilities

Example

???

Note

???

Enforcement

???

SL.str.11: Use gsl::span<char> rather than std::string_view when you need to mutate a string

Reason

std::string_view is read-only.

Example

???

Note

???

Enforcement

The compiler will flag attempts to write to a string_view.

SL.str.12: Use the **s** suffix for string literals meant to be standard-library **string**s

Reason

Direct expression of an idea minimizes mistakes.

Example

???

SL.io: Iostream

iostreams is a type safe, extensible, formatted and unformatted I/O library for streaming I/O. It supports multiple (and user extensible) buffering strategies and multiple locales. It can be used for conventional I/O, reading and writing to memory (string streams), and user-defined extensions, such as streaming across networks (asio: not yet standardized).

Iostream rule summary:

- SL.io.1: Use character-level input only when you have to
- SL.io.2: When reading, always consider ill-formed input
- SL.io.3: Prefer iostreams for I/O
- SL.io.10: Unless you use printf-family functions call ios_base::sync_with_stdio(false)
- SL.io.50: Avoid endl
- **????**

SL.io.1: Use character-level input only when you have to

Reason

Unless you genuinely just deal with individual characters, using character-level input leads to the user code performing potentially error-prone and potentially inefficient composition of tokens out of characters.

Example

```
char c;
char buf[128];
int i = 0;
while (cin.get(c) && !isspace(c) && i < 128)
    buf[i++] = c;
if (i == 128) {
    // ... handle too long string ....
}</pre>
```

Better (much simpler and probably faster):

```
string s;
s.reserve(128);
cin >> s;
```

and the reserve(128) is probably not worthwhile.

???

SL.io.2: When reading, always consider ill-formed input

Reason

Errors are typically best handled as soon as possible. If input isn't validated, every function must be written to cope with bad data (and that is not practical).

Example

```
???
```

Enforcement

???

SL.io.3: Prefer iostreams for I/O

Reason

iostreams are safe, flexible, and extensible.

Example

```
// write a complex number:
complex<double> z{ 3, 4 };
cout << z << '\n';</pre>
```

complex is a user-defined type and its I/O is defined without modifying the iostream library.

Example

```
// read a file of complex numbers:
for (complex<double> z; cin >> z; )
   v.push_back(z);
```

Exception

??? performance ???

Discussion: iostreams vs. the printf() family

It is often (and often correctly) pointed out that the printf() family has two advantages compared to iostreams: flexibility of formatting and performance. This has to be weighed against iostreams advantages of extensibility to handle user-defined types, resilience against security violations, implicit memory management, and locale handling.

If you need I/O performance, you can almost always do better than printf().

gets(), scanf() using %s, and printf() using %s are security hazards (vulnerable to buffer overflow and generally error-prone). C11 defines some "optional extensions" that do extra checking of their arguments. If present in your C library, gets_s(), scanf_s(), and printf_s() might be safer alternatives, but they are still not type safe.

Enforcement

Optionally flag <cstdio> and <stdio.h>.

```
SL.io.10: Unless you use printf-family functions call ios_base::sync_with_stdio(false)
```

Reason

Synchronizing iostreams with printf-style I/O can be costly. cin and cout are by default synchronized with printf.

Example

```
int main()
{
   ios_base::sync_with_stdio(false);
   // ... use iostreams ...
}
```

Enforcement

SL.io.50: Avoid endL

Reason

The endl manipulator is mostly equivalent to '\n' and "\n"; as most commonly used it simply slows down output by doing redundant flush()s. This slowdown can be significant compared to printf-style output.

Example

Note

For cin/cout (and equivalent) interaction, there is no reason to flush; that's done automatically. For writing to a file, there is rarely a need to flush.

Note

For string streams (specifically ostringstream), the insertion of an endl is entirely equivalent to the insertion of a '\n' character, but also in this case, endl might be significantly slower.

end1 does *not* take care of producing a platform specific end-of-line sequence (like "\r\n" on Windows). So for a string stream, s << end1 just inserts a *single* character, '\n'.

Note

Apart from the (occasionally important) issue of performance, the choice between '\n' and end1 is almost completely aesthetic.

SL.regex: Regex

<regex> is the standard C++ regular expression library. It supports a variety of regular expression pattern
conventions.

SL.chrono: Time

<chrono> (defined in namespace std::chrono) provides the notions of time_point and duration together with
functions for outputting time in various units. It provides clocks for registering time_points.

SL.C: The C Standard Library

C Standard Library rule summary:

- SL.C.1: Don't use setjmp/longjmp
- **???**?
- **???**

SL.C.1: Don't use setjmp/longjmp

Reason

a longjmp ignores destructors, thus invalidating all resource-management strategies relying on RAII

Enforcement

Flag all occurrences of longjmpand setjmp

A: Architectural ideas

This section contains ideas about higher-level architectural ideas and libraries.

Architectural rule summary:

- A.1: Separate stable code from less stable code
- A.2: Express potentially reusable parts as a library
- A.4: There should be no cycles among libraries
- ???
- **???**
- **???**
- **????**
- **???**
- **???**

A.1: Separate stable code from less stable code

Isolating less stable code facilitates its unit testing, interface improvement, refactoring, and eventual deprecation.

A.2: Express potentially reusable parts as a library

Reason

Note

A library is a collection of declarations and definitions maintained, documented, and shipped together. A library could be a set of headers (a "header-only library") or a set of headers plus a set of object files. You can statically or dynamically link a library into a program, or you can #include a header-only library.

A.4: There should be no cycles among libraries

Reason

- A cycle complicates the build process.
- Cycles are hard to understand and might introduce indeterminism (unspecified behavior).

Note

A library can contain cyclic references in the definition of its components. For example:

???

However, a library should not depend on another that depends on it.

NR: Non-Rules and myths

This section contains rules and guidelines that are popular somewhere, but that we deliberately don't recommend. We know perfectly well that there have been times and places where these rules made sense, and we have used them ourselves at times. However, in the context of the styles of programming we recommend and support with the guidelines, these "non-rules" would do harm.

Even today, there can be contexts where the rules make sense. For example, lack of suitable tool support can make exceptions unsuitable in hard-real-time systems, but please don't naïvely trust "common wisdom" (e.g., unsupported statements about "efficiency"); such "wisdom" might be based on decades-old information or experiences from languages with very different properties than C++ (e.g., C or Java).

The positive arguments for alternatives to these non-rules are listed in the rules offered as "Alternatives".

Non-rule summary:

- NR.1: Don't insist that all declarations should be at the top of a function
- NR.2: Don't insist to have only a single return-statement in a function
- NR.3: Don't avoid exceptions

- NR.4: Don't insist on placing each class definition in its own source file
- NR.5: Don't use two-phase initialization
- NR.6: Don't place all cleanup actions at the end of a function and goto exit
- NR.7: Don't make all data members protected
- 2??

NR.1: Don't insist that all declarations should be at the top of a function

Reason

The "all declarations on top" rule is a legacy of old programming languages that didn't allow initialization of variables and constants after a statement. This leads to longer programs and more errors caused by uninitialized and wrongly initialized variables.

Example, bad

```
int use(int x)
{
    int i;
    char c;
    double d;

    // ... some stuff ...

    if (x < i) {
        // ...
        i = f(x, d);
    }
    if (i < x) {
        // ...
        i = g(x, c);
    }
    return i;
}</pre>
```

The larger the distance between the uninitialized variable and its use, the larger the chance of a bug. Fortunately, compilers catch many "used before set" errors. Unfortunately, compilers cannot catch all such errors and unfortunately, the bugs aren't always as simple to spot as in this small example.

Alternative

- Always initialize an object
- ES.21: Don't introduce a variable (or constant) before you need to use it

NR.2: Don't insist to have only a single return-statement in a function

Reason

The single-return rule can lead to unnecessarily convoluted code and the introduction of extra state variables. In particular, the single-return rule makes it harder to concentrate error checking at the top of a function.

Example

```
template<class T>
// requires Number<T>
string sign(T x)
{
   if (x < 0)
      return "negative";
   if (x > 0)
      return "positive";
   return "zero";
}
```

to use a single return only we would have to do something like

This is both longer and likely to be less efficient. The larger and more complicated the function is, the more painful the workarounds get. Of course many simple functions will naturally have just one return because of their simpler inherent logic.

Example

```
int index(const char* p)
{
   if (!p) return -1; // error indicator: alternatively "throw nullptr_error{}"
   // ... do a lookup to find the index for p
   return i;
}
```

If we applied the rule, we'd get something like

```
int index2(const char* p)
{
   int i;
   if (!p)
        i = -1; // error indicator
   else {
        // ... do a lookup to find the index for p
   }
   return i;
}
```

Note that we (deliberately) violated the rule against uninitialized variables because this style commonly leads to that. Also, this style is a temptation to use the goto exit non-rule.

Alternative

- Keep functions short and simple
- Feel free to use multiple return statements (and to throw exceptions).

NR.3: Don't avoid exceptions

Reason

There seem to be four main reasons given for not using exceptions:

- exceptions are inefficient
- exceptions lead to leaks and errors
- exception performance is not predictable
- the exception-handling run-time support takes up too much space

There is no way we can settle this issue to the satisfaction of everybody. After all, the discussions about exceptions have been going on for 40+ years. Some languages cannot be used without exceptions, but others do not support them. This leads to strong traditions for the use and non-use of exceptions, and to heated debates.

However, we can briefly outline why we consider exceptions the best alternative for general-purpose programming and in the context of these guidelines. Simple arguments for and against are often inconclusive. There are specialized applications where exceptions indeed can be inappropriate (e.g., hard-real-time systems without support for reliable estimates of the cost of handling an exception).

Consider the major objections to exceptions in turn

• Exceptions are inefficient: Compared to what? When comparing make sure that the same set of errors are handled and that they are handled equivalently. In particular, do not compare a program that immediately terminates on seeing an error to a program that carefully cleans up resources before logging an error. Yes, some systems have poor exception handling implementations; sometimes, such implementations force us to use other error-handling approaches, but that's not a fundamental problem with exceptions. When using an efficiency argument - in any context - be careful that you have good data that actually provides insight into the

problem under discussion.

- Exceptions lead to leaks and errors. They do not. If your program is a rat's nest of pointers without an overall strategy for resource management, you have a problem whatever you do. If your system consists of a million lines of such code, you probably will not be able to use exceptions, but that's a problem with excessive and undisciplined pointer use, rather than with exceptions. In our opinion, you need RAII to make exception-based error handling simple and safe -- simpler and safer than alternatives.
- Exception performance is not predictable. If you are in a hard-real-time system where you must guarantee completion of a task in a given time, you need tools to back up such guarantees. As far as we know such tools are not available (at least not to most programmers).
- The exception-handling run-time support takes up too much space. This can be the case in small (usually embedded) systems. However, before abandoning exceptions consider what space consistent error-handling using error-codes would require and what failure to catch an error would cost.

Many, possibly most, problems with exceptions stem from historical needs to interact with messy old code.

The fundamental arguments for the use of exceptions are

- They clearly differentiate between erroneous return and ordinary return
- They cannot be forgotten or ignored
- They can be used systematically

Remember

- Exceptions are for reporting errors (in C++; other languages can have different uses for exceptions).
- Exceptions are not for errors that can be handled locally.
- Don't try to catch every exception in every function (that's tedious, clumsy, and leads to slow code).
- Exceptions are not for errors that require instant termination of a module/system after a non-recoverable error.

Example

???

Alternative

- RAII
- Contracts/assertions: Use GSL's Expects and Ensures (until we get language support for contracts)

NR.4: Don't insist on placing each class definition in its own source file

Reason

The resulting number of files from placing each class in its own file are hard to manage and can slow down compilation. Individual classes are rarely a good logical unit of maintenance and distribution.

```
???
```

Alternative

Use namespaces containing logically cohesive sets of classes and functions.

NR.5: Don't use two-phase initialization

Reason

Splitting initialization into two leads to weaker invariants, more complicated code (having to deal with semi-constructed objects), and errors (when we didn't deal correctly with semi-constructed objects consistently).

Example, bad

```
// Old conventional style: many problems
class Picture
   int mx;
   int my;
   int * data;
public:
   // main problem: constructor does not fully construct
   Picture(int x, int y)
    {
        mx = x;
                       // also bad: assignment in constructor body
                        // rather than in member initializer
        my = y;
        data = nullptr; // also bad: constant initialization in constructor
                        // rather than in member initializer
   }
   ~Picture()
        Cleanup();
   // ...
    // bad: two-phase initialization
   bool Init()
        // invariant checks
        if (mx <= 0 || my <= 0) {
            return false;
```

```
}
        if (data) {
           return false;
        data = (int*) malloc(mx*my*sizeof(int));  // also bad: owning raw * and malloc
        return data != nullptr;
   }
   // also bad: no reason to make cleanup a separate function
   void Cleanup()
        if (data) free(data);
        data = nullptr;
   }
};
Picture picture(100, 0); // not ready-to-use picture here
// this will fail..
if (!picture.Init()) {
   puts("Error, invalid picture");
// now have an invalid picture object instance.
```

Example, good

```
class Picture
   int mx;
   int my;
   vector<int> data;
   static int check_size(int size)
   {
        // invariant check
        Expects(size > 0);
        return size;
   }
public:
   // even better would be a class for a 2D Size as one single parameter
   Picture(int x, int y)
        : mx(check_size(x))
        , my(check_size(y))
        // now we know x and y have a valid size
        , data(mx * my) // will throw std::bad_alloc on error
        // picture is ready-to-use
   }
   // compiler generated dtor does the job. (also see C.21)
```

```
// ...
};

Picture picture1(100, 100);
// picture1 is ready-to-use here...

// not a valid size for y,
// default contract violation behavior will call std::terminate then
Picture picture2(100, 0);
// not reach here...
```

Alternative

- Always establish a class invariant in a constructor.
- Don't define an object before it is needed.

NR.6: Don't place all cleanup actions at the end of a function and goto exit

Reason

goto is error-prone. This technique is a pre-exception technique for RAII-like resource and error handling.

Example, bad

```
void do_something(int n)
{
    if (n < 100) goto exit;
    // ...
    int* p = (int*) malloc(n);
    // ...
    if (some_error) goto_exit;
    // ...
exit:
    free(p);
}</pre>
```

and spot the bug.

Alternative

- Use exceptions and RAII
- for non-RAII resources, use finally.

NR.7: Don't make all data members protected

Reason

protected data is a source of errors. protected data can be manipulated from an unbounded amount of code in various places. protected data is the class hierarchy equivalent to global data.

Example

???

Alternative

Make member data public or (preferably) private

RF: References

Many coding standards, rules, and guidelines have been written for C++, and especially for specialized uses of C++. Many

- focus on lower-level issues, such as the spelling of identifiers
- are written by C++ novices
- see "stopping programmers from doing unusual things" as their primary aim
- aim at portability across many compilers (some 10 years old)
- are written to preserve decades old code bases
- aim at a single application domain
- are downright counterproductive
- are ignored (must be ignored by programmers to get their work done well)

A bad coding standard is worse than no coding standard. However an appropriate set of guidelines are much better than no standards: "Form is liberating."

Why can't we just have a language that allows all we want and disallows all we don't want ("a perfect language")? Fundamentally, because affordable languages (and their tool chains) also serve people with needs that differ from yours and serve more needs than you have today. Also, your needs change over time and a general-purpose language is needed to allow you to adapt. A language that is ideal for today would be overly restrictive tomorrow.

Coding guidelines adapt the use of a language to specific needs. Thus, there cannot be a single coding style for everybody. We expect different organizations to provide additions, typically with more restrictions and firmer style rules.

Reference sections:

- RF.rules: Coding rules
- RF.books: Books with coding guidelines
- RF.C++: C++ Programming (C++11/C++14/C++17)
- RF.web: Websites

- RS.video: Videos about "modern C++"
- RF.man: Manuals
- RF.core: Core Guidelines materials

RF.rules: Coding rules

- AUTOSAR Guidelines for the use of the C++14 language in critical and safety-related systems v17.10
- Boost Library Requirements and Guidelines. ???.
- Bloomberg: BDE C++ Coding. Has a strong emphasis on code organization and layout.
- Facebook: ???
- GCC Coding Conventions. C++03 and (reasonably) a bit backwards looking.
- Google C++ Style Guide. Geared toward C++17 and (also) older code bases. Google experts are now actively collaborating here on helping to improve these Guidelines, and hopefully to merge efforts so these can be a modern common set they could also recommend.
- JSF++: JOINT STRIKE FIGHTER AIR VEHICLE C++ CODING STANDARDS. Document Number 2RDU00001 Rev C. December 2005. For flight control software. For hard-real-time. This means that it is necessarily very restrictive ("if the program fails somebody dies"). For example, no free store allocation or deallocation is allowed to occur after the plane takes off (no memory overflow and no fragmentation allowed). No exception is allowed to be used (because there was no available tool for guaranteeing that an exception would be handled within a fixed short time). Libraries used have to have been approved for mission critical applications. Any similarities to this set of guidelines are unsurprising because Bjarne Stroustrup was an author of JSF++. Recommended, but note its very specific focus.
- MISRA C++ 2008: Guidelines for the use of the C++ language in critical systems.
- Using C++ in Mozilla Code. As the name indicates, this aims for portability across many (old) compilers. As such, it is restrictive.
- Geosoft.no: C++ Programming Style Guidelines. ???.
- Possibility.com: C++ Coding Standard. ???.
- SEI CERT: Secure C++ Coding Standard. A very nicely done set of rules (with examples and rationales) done for security-sensitive code. Many of their rules apply generally.
- High Integrity C++ Coding Standard.
- llvm. Somewhat brief, based on C++14, and (not unreasonably) adjusted to its domain.
- **???**

RF.books: Books with coding guidelines

- Meyers96 Scott Meyers: *More Effective C++*. Addison-Wesley 1996.
- Meyers97 Scott Meyers: Effective C++, Second Edition. Addison-Wesley 1997.
- Meyers01 Scott Meyers: Effective STL. Addison-Wesley 2001.
- Meyers05 Scott Meyers: *Effective C++*, *Third Edition*. Addison-Wesley 2005.
- Meyers15 Scott Meyers: Effective Modern C++. O'Reilly 2015.
- SuttAlex05 Sutter and Alexandrescu: C++ Coding Standards. Addison-Wesley 2005. More a set of meta-rules than a set of rules. Pre-C++11.
- Stroustrup05 Bjarne Stroustrup: A rationale for semantically enhanced library languages. LCSD05. October 2005.
- Stroustrup14 Stroustrup: A Tour of C++. Addison Wesley 2014. Each chapter ends with an advice section

consisting of a set of recommendations.

- Stroustrup13 Stroustrup: The C++ Programming Language (4th Edition). Addison Wesley 2013. Each chapter ends with an advice section consisting of a set of recommendations.
- Stroustrup: Style Guide for Programming: Principles and Practice using C++. Mostly low-level naming and layout rules. Primarily a teaching tool.

RF.C++: C++ Programming (C++11/C++14)

- TC++PL4: A thorough description of the C++ language and standard libraries for experienced programmers.
- Tour++: An overview of the C++ language and standard libraries for experienced programmers.
- Programming: Principles and Practice using C++: A textbook for beginners and relative novices.

RF.web: Websites

- isocpp.org
- Bjarne Stroustrup's home pages
- WG21
- Boost
- Adobe open source
- Poco libraries
- Sutter's Mill?
- **???**

RS.video: Videos about "modern C++"

- Bjarne Stroustrup: C++11 Style. 2012.
- Bjarne Stroustrup: The Essence of C++: With Examples in C++84, C++98, C++11, and C++14. 2013
- All the talks from CppCon '14
- Bjarne Stroustrup: The essence of C++ at the University of Edinburgh. 2014.
- Bjarne Stroustrup: The Evolution of C++ Past, Present and Future. CppCon 2016 keynote.
- Bjarne Stroustrup: Make Simple Tasks Simple!. CppCon 2014 keynote.
- Bjarne Stroustrup: Writing Good C++14. CppCon 2015 keynote about the Core Guidelines.
- Herb Sutter: Writing Good C++14... By Default. CppCon 2015 keynote about the Core Guidelines.
- CppCon 15
- ??? C++ Next
- ??? Meting C++
- ??? more ???

RF.man: Manuals

■ ISO C++ Standard C++11.

- ISO C++ Standard C++14.
- ISO C++ Standard C++17. Committee Draft.
- Palo Alto "Concepts" TR.
- ISO C++ Concepts TS.
- WG21 Ranges report. Draft.

RF.core: Core Guidelines materials

This section contains materials that have been useful for presenting the core guidelines and the ideas behind them:

- Our documents directory
- Stroustrup, Sutter, and Dos Reis: A brief introduction to C++'s model for type- and resource-safety. A paper with lots of examples.
- Sergey Zubkov: a Core Guidelines talk and here are the slides. In Russian. 2017.
- Neil MacIntosh: The Guideline Support Library: One Year Later. CppCon 2016.
- Bjarne Stroustrup: Writing Good C++14. CppCon 2015 keynote.
- Herb Sutter: Writing Good C++14... By Default. CppCon 2015 keynote.
- Peter Sommerlad: C++ Core Guidelines Modernize your C++ Code Base. ACCU 2017.
- Bjarne Stroustrup: No Littering!. Bay Area ACCU 2016. It gives some idea of the ambition level for the Core Guidelines.

Note that slides for CppCon presentations are available (links with the posted videos).

Contributions to this list would be most welcome.

Acknowledgements

Thanks to the many people who contributed rules, suggestions, supporting information, references, etc.:

- Peter Juhl
- Neil MacIntosh
- Axel Naumann
- Andrew Pardoe
- Gabriel Dos Reis
- Zhuang, Jiangang (Jeff)
- Sergey Zubkov

and see the contributor list on the github.

Pro: Profiles

Ideally, we would follow all of the guidelines. That would give the cleanest, most regular, least error-prone, and often the fastest code. Unfortunately, that is usually impossible because we have to fit our code into large code bases and use existing libraries. Often, such code has been written over decades and does not follow these guidelines. We must aim for gradual adoption.

Whatever strategy for gradual adoption we adopt, we need to be able to apply sets of related guidelines to address some set of problems first and leave the rest until later. A similar idea of "related guidelines" becomes important when some, but not all, guidelines are considered relevant to a code base or if a set of specialized guidelines is to be applied for a specialized application area. We call such a set of related guidelines a "profile". We aim for such a set of guidelines to be coherent so that they together help us reach a specific goal, such as "absence of range errors" or "static type safety." Each profile is designed to eliminate a class of errors. Enforcement of "random" rules in isolation is more likely to be disruptive to a code base than delivering a definite improvement.

A "profile" is a set of deterministic and portably enforceable subset of rules (i.e., restrictions) that are designed to achieve a specific guarantee. "Deterministic" means they require only local analysis and could be implemented in a compiler (though they don't need to be). "Portably enforceable" means they are like language rules, so programmers can count on different enforcement tools giving the same answer for the same code.

Code written to be warning-free using such a language profile is considered to conform to the profile. Conforming code is considered to be safe by construction with regard to the safety properties targeted by that profile. Conforming code will not be the root cause of errors for that property, although such errors might be introduced into a program by other code, libraries or the external environment. A profile might also introduce additional library types to ease conformance and encourage correct code.

Profiles summary:

Pro.type: Type safety

Pro.bounds: Bounds safety

• Pro.lifetime: Lifetime safety

In the future, we expect to define many more profiles and add more checks to existing profiles. Candidates include:

- narrowing arithmetic promotions/conversions (likely part of a separate safe-arithmetic profile)
- arithmetic cast from negative floating point to unsigned integral type (ditto)
- selected undefined behavior: Start with Gabriel Dos Reis's UB list developed for the WG21 study group
- selected unspecified behavior: Addressing portability concerns.
- const violations: Mostly done by compilers already, but we can catch inappropriate casting and underuse of const.

Enabling a profile is implementation defined; typically, it is set in the analysis tool used.

To suppress enforcement of a profile check, place a suppress annotation on a language contract. For example:

```
[[suppress(bounds)]] char* raw_find(char* p, int n, char x)  // find x in p[0]..p[n - 1]
{
    // ...
}
```

Now raw find() can scramble memory to its heart's content. Obviously, suppression should be very rare.

Pro.safety: Type-safety profile

This profile makes it easier to construct code that uses types correctly and avoids inadvertent type punning. It does so by focusing on removing the primary sources of type violations, including unsafe uses of casts and unions.

For the purposes of this section, type-safety is defined to be the property that a variable is not used in a way that doesn't obey the rules for the type of its definition. Memory accessed as a type T should not be valid memory that actually contains an object of an unrelated type U. Note that the safety is intended to be complete when combined also with Bounds safety and Lifetime safety.

An implementation of this profile shall recognize the following patterns in source code as non-conforming and issue a diagnostic.

Type safety profile summary:

- Type.1: Avoid casts:
 - 1. Don't use reinterpret_cast; A strict version of Avoid casts and prefer named casts.
 - 2. Don't use static_cast for arithmetic types; A strict version of Avoid casts and prefer named casts.
 - 3. Don't cast between pointer types where the source type and the target type are the same; A strict version of Avoid casts.
 - 4. Don't cast between pointer types when the conversion could be implicit; A strict version of Avoid casts.
- Type.2: Don't use static_cast to downcast: Use dynamic_cast instead.
- Type.3: Don't use const_cast to cast away const (i.e., at all): Don't cast away const.
- Type.4: Don't use C-style (T)expression or functional T(expression) casts: Prefer construction or named casts or T{expression}.
- Type.5: Don't use a variable before it has been initialized: always initialize.
- Type.6: Always initialize a member variable: always initialize, possibly using default constructors or default member initializers.
- Type.7: Avoid naked union: Use variant instead.
- Type.8: Avoid varargs: Don't use va_arg arguments.

Impact

With the type-safety profile you can trust that every operation is applied to a valid object. An exception can be thrown to indicate errors that cannot be detected statically (at compile time). Note that this type-safety can be complete only if we also have Bounds safety and Lifetime safety. Without those guarantees, a region of memory could be accessed independent of which object, objects, or parts of objects are stored in it.

Pro.bounds: Bounds safety profile

This profile makes it easier to construct code that operates within the bounds of allocated blocks of memory. It does so by focusing on removing the primary sources of bounds violations: pointer arithmetic and array indexing. One of the core features of this profile is to restrict pointers to only refer to single objects, not arrays.

We define bounds-safety to be the property that a program does not use an object to access memory outside of the range that was allocated for it. Bounds safety is intended to be complete only when combined with Type safety and Lifetime safety, which cover other unsafe operations that allow bounds violations.

Bounds safety profile summary:

- Bounds.1: Don't use pointer arithmetic. Use span instead: Pass pointers to single objects (only) and Keep pointer arithmetic simple.
- Bounds.2: Only index into arrays using constant expressions: Pass pointers to single objects (only) and Keep pointer arithmetic simple.
- Bounds.3: No array-to-pointer decay: Pass pointers to single objects (only) and Keep pointer arithmetic simple.
- Bounds.4: Don't use standard-library functions and types that are not bounds-checked: Use the standard library in a type-safe manner.

Impact

Bounds safety implies that access to an object - notably arrays - does not access beyond the object's memory allocation. This eliminates a large class of insidious and hard-to-find errors, including the (in)famous "buffer overflow" errors. This closes security loopholes as well as a prominent source of memory corruption (when writing out of bounds). Even if an out-of-bounds access is "just a read", it can lead to invariant violations (when the accessed isn't of the assumed type) and "mysterious values."

Pro.lifetime: Lifetime safety profile

Accessing through a pointer that doesn't point to anything is a major source of errors, and very hard to avoid in many traditional C or C++ styles of programming. For example, a pointer might be uninitialized, the nullptr, point beyond the range of an array, or to a deleted object.

See the current design specification here.

Lifetime safety profile summary:

Lifetime.1: Don't dereference a possibly invalid pointer: detect or avoid.

Impact

Once completely enforced through a combination of style rules, static analysis, and library support, this profile

- eliminates one of the major sources of nasty errors in C++
- eliminates a major source of potential security violations
- improves performance by eliminating redundant "paranoia" checks
- increases confidence in correctness of code
- avoids undefined behavior by enforcing a key C++ language rule

GSL: Guidelines support library

The GSL is a small library of facilities designed to support this set of guidelines. Without these facilities, the guidelines would have to be far more restrictive on language details.

The Core Guidelines support library is defined in namespace gsl and the names might be aliases for standard library or other well-known library names. Using the (compile-time) indirection through the gsl namespace allows for experimentation and for local variants of the support facilities.

The GSL is header only, and can be found at GSL: Guidelines support library. The support library facilities are designed to be extremely lightweight (zero-overhead) so that they impose no overhead compared to using conventional alternatives. Where desirable, they can be "instrumented" with additional functionality (e.g., checks) for tasks such as debugging.

These Guidelines use types from the standard (e.g., C++17) in addition to ones from the GSL. For example, we assume a variant type, but this is not currently in GSL. Eventually, use the one voted into C++17.

Some of the GSL types listed below might not be supported in the library you use due to technical reasons such as limitations in the current versions of C++. Therefore, please consult your GSL documentation to find out more.

For each GSL type below we state an invariant for that type. That invariant holds as long as user code only changes the state of a GSL object using the type's provided member/free functions (i.e., user code does not bypass the type's interface to change the object's value/bits by violating any other Guidelines rule).

Summary of GSL components:

GSL.view: Views

GSL.owner

■ GSL.assert: Assertions

GSL.util: Utilities

■ GSL.concept: Concepts

We plan for a "ISO C++ standard style" semi-formal specification of the GSL.

We rely on the ISO C++ Standard Library and hope for parts of the GSL to be absorbed into the standard library.

GSL.view: Views

These types allow the user to distinguish between owning and non-owning pointers and between pointers to a single object and pointers to the first element of a sequence.

These "views" are never owners.

References are never owners (see R.4). Note: References have many opportunities to outlive the objects they refer to (returning a local variable by reference, holding a reference to an element of a vector and doing push_back, binding to std::max(x, y + 1), etc). The Lifetime safety profile aims to address those things, but even so owner<T&> does not make sense and is discouraged.

The names are mostly ISO standard-library style (lower case and underscore):

- T* // The T* is not an owner, might be null; assumed to be pointing to a single element.
- T& // The T& is not an owner and can never be a "null reference"; references are always bound to objects.

The "raw-pointer" notation (e.g. int*) is assumed to have its most common meaning; that is, a pointer points to an object, but does not own it. Owners should be converted to resource handles (e.g., unique_ptr or vector<T>) or marked owner<T*>.

owner<T*> // a T* that owns the object pointed/referred to; might be nullptr.

owner is used to mark owning pointers in code that cannot be upgraded to use proper resource handles. Reasons for that include:

- Cost of conversion.
- The pointer is used with an ABI.
- The pointer is part of the implementation of a resource handle.

An owner<T> differs from a resource handle for a T by still requiring an explicit delete.

An owner<T> is assumed to refer to an object on the free store (heap).

If something is not supposed to be nullptr, say so:

- not_null<T> // T is usually a pointer type (e.g., not_null<int*> and not_null<owner<Foo*>>) that must not be nullptr. T can be any type for which ==nullptr is meaningful.
- span<T> // [p:p+n), constructor from {p, q} and {p, n}; T is the pointer type
- span_p<T> // {p, predicate} [p:q) where q is the first element for which predicate(*p) is true

A span<T> refers to zero or more mutable Ts unless T is a const type. All accesses to elements of the span, notably via operator[], are guaranteed to be bounds-checked by default.

Note: GSL's span (initially called array_view) was proposed for inclusion in the C++ standard library, and was adopted (with changes to its name and interface) except only that std::span does not provide for guaranteed bounds checking. Therefore GSL changed span's name and interface to track std::span and should be exactly the same as std::span, and the only difference should be that GSL span is fully bounds-safe by default. If bounds-safety might affect its interface, then those change proposals should be brought back via the ISO C++ committee to keep gsl::span interface-compatible with std::span. If a future evolution of std::span adds bounds checking, gsl::span can be removed.

"Pointer arithmetic" is best done within spans. A char* that points to more than one char but is not a C-style string (e.g., a pointer into an input buffer) should be represented by a span.

- zstring // a char* supposed to be a C-style string; that is, a zero-terminated sequence of char or nullptr
- czstring // a const char* supposed to be a C-style string; that is, a zero-terminated sequence of const char or nullptr

Logically, those last two aliases are not needed, but we are not always logical, and they make the distinction between a pointer to one char and a pointer to a C-style string explicit. A sequence of characters that is not assumed to be zero-terminated should be a span<char>, or if that is impossible because of ABI issues a char*, rather than a zstring.

Use not_null<zstring> for C-style strings that cannot be nullptr. ??? Do we need a name for not_null<zstring>? or is its ugliness a feature?

GSL.owner: Ownership pointers

- unique_ptr<T> // unique ownership: std::unique_ptr<T>
- shared_ptr<T> // shared ownership: std::shared_ptr<T> (a counted pointer)
- stack_array<T> // A stack-allocated array. The number of elements is determined at construction and fixed thereafter. The elements are mutable unless T is a const type.
- dyn_array<T> // ??? needed ??? A heap-allocated array. The number of elements is determined at construction and fixed thereafter. The elements are mutable unless T is a const type. Basically a span that allocates and owns its elements.

GSL.assert: Assertions

- Expects // precondition assertion. Currently placed in function bodies. Later, should be moved to declarations. // Expects(p) terminates the program unless p == true // Expects is under control of some options (enforcement, error message, alternatives to terminate)
- Ensures // postcondition assertion. Currently placed in function bodies. Later, should be moved to declarations.

These assertions are currently macros (yuck!) and must appear in function definitions (only) pending standard committee decisions on contracts and assertion syntax. See the contract proposal; using the attribute syntax, for example, Expects(p) will become [[expects: p]].

GSL.util: Utilities

- finally // finally(f) makes a final_action(f) with a destructor that invokes f
- narrow_cast // narrow_cast<T>(x) is static_cast<T>(x)
- narrow // narrow<T>(x) is static_cast<T>(x) if static_cast<T>(x) == x with no signedness promotions, or it throws narrowing_error (e.g., narrow<unsigned>(-42) throws)
- [[implicit]] // "Marker" to put on single-argument constructors to explicitly make them non-explicit.
- move_owner // p = move_owner(q) means p = q but ???
- joining_thread // a RAII style version of std::thread that joins.
- index // a type to use for all container and array indexing (currently an alias for ptrdiff_t)

GSL.concept: Concepts

These concepts (type predicates) are borrowed from Andrew Sutton's Origin library, the Range proposal, and the ISO WG21 Palo Alto TR. Many of them are very similar to what became part of the ISO C++ standard in C++20.

- String
- Number
- Boolean
- Range // in C++20, std::ranges::range
- Sortable // in C++20, std::sortable

- EqualityComparable // in C++20, std::equality comparable
- Convertible // in C++20, std::convertible to
- Common // in C++20, std::common with
- Integral // in C++20, std::integral
- SignedIntegral // in C++20, std::signed_integral
- SemiRegular // in C++20, std::semiregular
- Regular // in C++20, std::regular
- TotallyOrdered // in C++20, std::totally_ordered
- Function // in C++20, std::invocable
- RegularFunction // in C++20, std::regular_invocable
- Predicate // in C++20, std::predicate
- Relation // in C++20, std::relation
- · ...

GSL.ptr: Smart pointer concepts

- Pointer // A type with *, ->, ==, and default construction (default construction is assumed to set the singular "null" value)
- Unique_pointer // A type that matches Pointer, is movable, and is not copyable
- Shared_pointer // A type that matches Pointer, and is copyable

NL: Naming and layout suggestions

Consistent naming and layout are helpful. If for no other reason because it minimizes "my style is better than your style" arguments. However, there are many, many, different styles around and people are passionate about them (pro and con). Also, most real-world projects include code from many sources, so standardizing on a single style for all code is often impossible. After many requests for guidance from users, we present a set of rules that you might use if you have no better ideas, but the real aim is consistency, rather than any particular rule set. IDEs and tools can help (as well as hinder).

Naming and layout rules:

- NL.1: Don't say in comments what can be clearly stated in code
- NL.2: State intent in comments
- NL.3: Keep comments crisp
- NL.4: Maintain a consistent indentation style
- NL.5: Avoid encoding type information in names
- NL.7: Make the length of a name roughly proportional to the length of its scope
- NL.8: Use a consistent naming style
- NL.9: Use ALL_CAPS for macro names only
- NL.10: Prefer underscore style names
- NL.11: Make literals readable
- NL.15: Use spaces sparingly

- NL.16: Use a conventional class member declaration order
- NL.17: Use K&R-derived layout
- NL.18: Use C++-style declarator layout
- NL.19: Avoid names that are easily misread
- NL.20: Don't place two statements on the same line
- NL.21: Declare one name (only) per declaration
- NL.25: Don't use void as an argument type
- NL.26: Use conventional const notation
- NL.27: Use a .cpp suffix for code files and .h for interface files

Most of these rules are aesthetic and programmers hold strong opinions. IDEs also tend to have defaults and a range of alternatives. These rules are suggested defaults to follow unless you have reasons not to.

We have had comments to the effect that naming and layout are so personal and/or arbitrary that we should not try to "legislate" them. We are not "legislating" (see the previous paragraph). However, we have had many requests for a set of naming and layout conventions to use when there are no external constraints.

More specific and detailed rules are easier to enforce.

These rules bear a strong resemblance to the recommendations in the PPP Style Guide written in support of Stroustrup's Programming: Principles and Practice using C++.

NL.1: Don't say in comments what can be clearly stated in code

Reason

Compilers do not read comments. Comments are less precise than code. Comments are not updated as consistently as code.

Example, bad

```
auto x = m * v1 + vv; // multiply m with v1 and add the result to vv
```

Enforcement

Build an AI program that interprets colloquial English text and see if what is said could be better expressed in C++.

NL.2: State intent in comments

Reason

Code says what is done, not what is supposed to be done. Often intent can be stated more clearly and concisely than the implementation.

Example

```
void stable_sort(Sortable& c)
   // sort c in the order determined by <, keep equal elements (as defined by ==) in
   // their original relative order
{
   // ... quite a few lines of non-trivial code ...
}</pre>
```

Note

If the comment and the code disagree, both are likely to be wrong.

NL.3: Keep comments crisp

Reason

Verbosity slows down understanding and makes the code harder to read by spreading it around in the source file.

Note

Use intelligible English. I might be fluent in Danish, but most programmers are not; the maintainers of my code might not be. Avoid SMS lingo and watch your grammar, punctuation, and capitalization. Aim for professionalism, not "cool."

Enforcement

not possible.

NL.4: Maintain a consistent indentation style

Reason

Readability. Avoidance of "silly mistakes."

Example, bad

```
int i;
for (i = 0; i < max; ++i); // bug waiting to happen
if (i == j)
    return i;</pre>
```

Note

Always indenting the statement after if (...), for (...), and while (...) is usually a good idea:

```
if (i < 0) error("negative argument");
if (i < 0)
    error("negative argument");</pre>
```

Enforcement

Use a tool.

NL.5: Avoid encoding type information in names

Rationale

If names reflect types rather than functionality, it becomes hard to change the types used to provide that functionality. Also, if the type of a variable is changed, code using it will have to be modified. Minimize unintentional conversions.

Example, bad

```
void print_int(int i);
void print_string(const char*);

print_int(1);  // repetitive, manual type matching
print_string("xyzzy"); // repetitive, manual type matching
```

Example, good

Note

Names with types encoded are either verbose or cryptic.

```
printS // print a std::string
prints // print a C-style string
printi // print an int
```

Requiring techniques like Hungarian notation to encode a type has been used in untyped languages, but is generally unnecessary and actively harmful in a strongly statically-typed language like C++, because the annotations get out of date (the warts are just like comments and rot just like them) and they interfere with good use of the language (use the same name and overload resolution instead).

Note

Some styles use very general (not type-specific) prefixes to denote the general use of a variable.

```
auto p = new User();
auto p = make_unique<User>();
// note: "p" is not being used to say "raw pointer to type User,"
// just generally to say "this is an indirection"

auto cntHits = calc_total_of_hits(/*...*/);
// note: "cnt" is not being used to encode a type,
// just generally to say "this is a count of something"
```

This is not harmful and does not fall under this guideline because it does not encode type information.

Note

Some styles distinguish members from local variable, and/or from global variable.

```
struct S {
   int m_;
   S(int m) : m_{abs(m)} { }
};
```

This is not harmful and does not fall under this guideline because it does not encode type information.

Note

Like C++, some styles distinguish types from non-types. For example, by capitalizing type names, but not the names of functions and variables.

```
typename<typename T>
class HashTable {    // maps string to T
    // ...
};
HashTable<int> index;
```

This is not harmful and does not fall under this guideline because it does not encode type information.

NL.7: Make the length of a name roughly proportional to the length of its scope

Rationale: The larger the scope the greater the chance of confusion and of an unintended name clash.

Example

```
double sqrt(double x);  // return the square root of x; x must be non-negative
int length(const char* p);  // return the number of characters in a zero-terminated C-style string
int length_of_string(const char zero_terminated_array_of_char[])  // bad: verbose
int g;  // bad: global variable with a cryptic name
int open;  // bad: global variable with a short, popular name
```

The use of p for pointer and x for a floating-point variable is conventional and non-confusing in a restricted scope.

Enforcement

???

NL.8: Use a consistent naming style

Rationale: Consistence in naming and naming style increases readability.

Note

There are many styles and when you use multiple libraries, you can't follow all their different conventions. Choose a "house style", but leave "imported" libraries with their original style.

Example

ISO Standard, use lower case only and digits, separate words with underscores:

- int
- vector
- my_map

Avoid identifier names that contain double underscores __ or that start with an underscore followed by a capital letter (e.g., _Throws). Such identifiers are reserved for the C++ implementation.

Stroustrup: ISO Standard, but with upper case used for your own types and concepts:

- int
- vector
- My_map

Example

CamelCase: capitalize each word in a multi-word identifier:

- int
- vector
- МуМар
- myMap

Some conventions capitalize the first letter, some don't.

Note

Try to be consistent in your use of acronyms and lengths of identifiers:

```
int mtbf {12};
int mean_time_between_failures {12}; // make up your mind
```

Enforcement

Would be possible except for the use of libraries with varying conventions.

NL.9: Use ALL_CAPS for macro names only

Reason

To avoid confusing macros with names that obey scope and type rules.

Example

```
void f()
{
   const int SIZE{1000}; // Bad, use 'size' instead
   int v[SIZE];
}
```

Note

In particular, this avoids confusing macros with non-macro symbolic constants (see also Enum.5: Don't use ALL_CAPS for enumerators)

enum bad { BAD, WORSE, HORRIBLE }; // BAD

Enforcement

- Flag macros with lower-case letters
- Flag ALL_CAPS non-macro names

NL.10: Prefer underscore_style names

Reason

The use of underscores to separate parts of a name is the original C and C++ style and used in the C++ Standard Library.

Note

This rule is a default to use only if you have a choice. Often, you don't have a choice and must follow an established style for consistency. The need for consistency beats personal taste.

This is a recommendation for when you have no constraints or better ideas. This rule was added after many requests for guidance.

Example

Stroustrup: ISO Standard, but with upper case used for your own types and concepts:

- int
- vector
- My_map

Enforcement

Impossible.

NL.11: Make literals readable

Reason

Readability.

Example

Use digit separators to avoid long strings of digits

```
auto c = 299'792'458; // m/s2
auto q2 = 0b0000'1111'0000'0000;
auto ss_number = 123'456'7890;
```

Example

Use literal suffixes where clarification is needed

```
auto hello = "Hello!"s; // a std::string
auto world = "world"; // a C-style string
auto interval = 100ms; // using <chrono>
```

Note

Literals should not be sprinkled all over the code as "magic constants", but it is still a good idea to make them readable where they are defined. It is easy to make a typo in a long string of integers.

Enforcement

Flag long digit sequences. The trouble is to define "long"; maybe 7.

NL.15: Use spaces sparingly

Reason

Too much space makes the text larger and distracts.

Example, bad

```
#include < map >
int main(int argc, char * argv [ ])
{
    // ...
}
```

```
#include <map>
int main(int argc, char* argv[])
{
    // ...
}
```

Note

Some IDEs have their own opinions and add distracting space.

This is a recommendation for when you have no constraints or better ideas. This rule was added after many requests for guidance.

Note

We value well-placed whitespace as a significant help for readability. Just don't overdo it.

NL.16: Use a conventional class member declaration order

Reason

A conventional order of members improves readability.

When declaring a class use the following order

- types: classes, enums, and aliases (using)
- constructors, assignments, destructor
- functions
- data

Use the public before protected before private order.

This is a recommendation for when you have no constraints or better ideas. This rule was added after many requests for guidance.

Example

```
class X {
public:
    // interface
protected:
    // unchecked function for use by derived class implementations
private:
    // implementation details
};
```

Sometimes, the default order of members conflicts with a desire to separate the public interface from implementation details. In such cases, private types and functions can be placed with private data.

```
class X {
public:
    // interface
protected:
    // unchecked function for use by derived class implementations
private:
    // implementation details (types, functions, and data)
};
```

Example, bad

Avoid multiple blocks of declarations of one access (e.g., public) dispersed among blocks of declarations with different access (e.g. private).

The use of macros to declare groups of members often leads to violation of any ordering rules. However, using macros obscures what is being expressed anyway.

Enforcement

Flag departures from the suggested order. There will be a lot of old code that doesn't follow this rule.

NL.17: Use K&R-derived layout

Reason

This is the original C and C++ layout. It preserves vertical space well. It distinguishes different language constructs (such as functions and classes) well.

Note

In the context of C++, this style is often called "Stroustrup".

This is a recommendation for when you have no constraints or better ideas. This rule was added after many requests for guidance.

```
struct Cable {
    int x;
    // ...
};
double foo(int x)
    if (0 < x) {
        // ...
    switch (x) {
    case 0:
        // ...
        break;
    case amazing:
        // ...
        break;
    default:
        // ...
        break;
    }
    if (0 < x)
        ++x;
    if (x < 0)
        something();
    else
        something_else();
    return some_value;
}
```

Note the space between if and (

Note

Use separate lines for each statement, the branches of an if, and the body of a for.

Note

The { for a class and a struct is *not* on a separate line, but the { for a function is.

Note

Capitalize the names of your user-defined types to distinguish them from standards-library types.

Note

Do not capitalize function names.

Enforcement

If you want enforcement, use an IDE to reformat.

NL.18: Use C++-style declarator layout

Reason

The C-style layout emphasizes use in expressions and grammar, whereas the C++-style emphasizes types. The use in expressions argument doesn't hold for references.

Example

```
T& operator[](size_t);  // OK
T & operator[](size_t);  // just strange
T & operator[](size_t);  // undecided
```

Note

This is a recommendation for when you have no constraints or better ideas. This rule was added after many requests for guidance.

Enforcement

Impossible in the face of history.

NL.19: Avoid names that are easily misread

Reason

Readability. Not everyone has screens and printers that make it easy to distinguish all characters. We easily confuse similarly spelled and slightly misspelled words.

```
int oO01lL = 6; // bad

int splunk = 7;
int splonk = 8; // bad: splunk and splonk are easily confused
```

Enforcement

???

NL.20: Don't place two statements on the same line

Reason

Readability. It is really easy to overlook a statement when there is more on a line.

Example

```
int x = 7; char* p = 29;  // don't
int x = 7; f(x); ++x;  // don't
```

Enforcement

Easy.

NL.21: Declare one name (only) per declaration

Reason

Readability. Minimizing confusion with the declarator syntax.

Note

For details, see ES.10.

NL.25: Don't use void as an argument type

Reason

It's verbose and only needed where C compatibility matters.

Example

```
void f(void); // bad

void g(); // better
```

Note

Even Dennis Ritchie deemed void f(void) an abomination. You can make an argument for that abomination in C when function prototypes were rare so that banning:

```
int f(); f(1, 2, "weird but valid C89"); // hope that f() is defined int f(a, b, c) char* c; { /* ... */ }
```

would have caused major problems, but not in the 21st century and in C++.

NL.26: Use conventional const notation

Reason

Conventional notation is more familiar to more programmers. Consistency in large code bases.

Example

```
const int x = 7;  // OK
int const y = 9;  // bad

const int *const p = nullptr;  // OK, constant pointer to constant int
int const *const p = nullptr;  // bad, constant pointer to constant int
```

Note

We are well aware that you could claim the "bad" examples more logical than the ones marked "OK", but they also confuse more people, especially novices relying on teaching material using the far more common, conventional OK style.

As ever, remember that the aim of these naming and layout rules is consistency and that aesthetics vary immensely.

This is a recommendation for when you have no constraints or better ideas. This rule was added after many requests for guidance.

Enforcement

Flag const used as a suffix for a type.

NL.27: Use a .cpp suffix for code files and .h for interface files

Reason

It's a longstanding convention. But consistency is more important, so if your project uses something else, follow that.

Note

This convention reflects a common use pattern: Headers are more often shared with C to compile as both C++ and C, which typically uses .h, and it's easier to name all headers .h instead of having different extensions for just those headers that are intended to be shared with C. On the other hand, implementation files are rarely shared with C and so should typically be distinguished from .c files, so it's normally best to name all C++ implementation files something else (such as .cpp).

The specific names .h and .cpp are not required (just recommended as a default) and other names are in widespread use. Examples are .hh, .C, and .cxx. Use such names equivalently. In this document, we refer to .h and .cpp as a shorthand for header and implementation files, even though the actual extension might be different.

Your IDE (if you use one) might have strong opinions about suffixes.

Example

```
// foo.h:
extern int a; // a declaration
extern void foo();

// foo.cpp:
int a; // a definition
void foo() { ++a; }
```

foo.h provides the interface to foo.cpp. Global variables are best avoided.

Example, bad

```
// foo.h:
int a; // a definition
void foo() { ++a; }
```

#include <foo.h> twice in a program and you get a linker error for two one-definition-rule violations.

Enforcement

- Flag non-conventional file names.
- Check that .h and .cpp (and equivalents) follow the rules below.

FAQ: Answers to frequently asked questions

This section covers answers to frequently asked questions about these guidelines.

FAQ.1: What do these guidelines aim to achieve?

See the top of this page. This is an open-source project to maintain modern authoritative guidelines for writing C++ code using the current C++ Standard. The guidelines are designed to be modern, machine-enforceable wherever possible, and open to contributions and forking so that organizations can easily incorporate them into their own corporate coding guidelines.

FAQ.2: When and where was this work first announced?

It was announced by Bjarne Stroustrup in his CppCon 2015 opening keynote, "Writing Good C++14". See also the accompanying isocpp.org blog post, and for the rationale of the type and memory safety guidelines see Herb Sutter's follow-up CppCon 2015 talk, "Writing Good C++14 ... By Default".

FAQ.3: Who are the authors and maintainers of these guidelines?

The initial primary authors and maintainers are Bjarne Stroustrup and Herb Sutter, and the guidelines so far were developed with contributions from experts at CERN, Microsoft, Morgan Stanley, and several other organizations. At the time of their release, the guidelines are in a "0.6" state, and contributions are welcome. As Stroustrup said in his announcement: "We need help!"

FAQ.4: How can I contribute?

See CONTRIBUTING.md. We appreciate volunteer help!

FAQ.5: How can I become an editor/maintainer?

By contributing a lot first and having the consistent quality of your contributions recognized. See CONTRIBUTING.md. We appreciate volunteer help!

FAQ.6: Have these guidelines been approved by the ISO C++ standards committee? Do they represent the consensus of the committee?

No. These guidelines are outside the standard. They are intended to serve the standard, and be maintained as current guidelines about how to use the current Standard C++ effectively. We aim to keep them in sync with the standard as that is evolved by the committee.

FAQ.7: If these guidelines are not approved by the committee, why are they under github.com/isocpp?

Because isocpp is the Standard C++ Foundation; the committee's repositories are under github.com/cplusplus. Some neutral organization has to own the copyright and license to make it clear this is not being dominated by any one person or vendor. The natural entity is the Foundation, which exists to promote the use and up-to-date understanding of modern Standard C++ and the work of the committee. This follows the same pattern that isocpp.org did for the C++ FAQ, which was initially the work of Bjarne Stroustrup, Marshall Cline, and Herb Sutter and contributed to the open project in the same way.

FAQ.8: Will there be a C++98 version of these Guidelines? a C++11 version?

No. These guidelines are about how to best use modern standard C++ and write code assuming you have a modern conforming compiler.

FAQ.9: Do these guidelines propose new language features?

No. These guidelines are about how to best use modern Standard C++, and they limit themselves to recommending only those features.

FAQ.10: What version of Markdown do these guidelines use?

These coding standards are written using CommonMark, and <a> HTML anchors.

We are considering the following extensions from GitHub Flavored Markdown (GFM):

- fenced code blocks (consistently using indented vs. fenced is under discussion)
- tables (none yet but we'll likely need them, and this is a GFM extension)

Avoid other HTML tags and other extensions.

Note: We are not yet consistent with this style.

FAQ.50: What is the GSL (guidelines support library)?

The GSL is the small set of types and aliases specified in these guidelines. As of this writing, their specification herein is too sparse; we plan to add a WG21-style interface specification to ensure that different implementations agree, and to propose as a contribution for possible standardization, subject as usual to whatever the committee decides to accept/improve/alter/reject.

FAQ.51: Is github.com/Microsoft/GSL the GSL?

No. That is just a first implementation contributed by Microsoft. Other implementations by other vendors are encouraged, as are forks of and contributions to that implementation. As of this writing one week into the public project, at least one GPLv3 open-source implementation already exists. We plan to produce a WG21-style interface specification to ensure that different implementations agree.

FAQ.52: Why not supply an actual GSL implementation in/with these guidelines?

We are reluctant to bless one particular implementation because we do not want to make people think there is only one, and inadvertently stifle parallel implementations. And if these guidelines included an actual implementation, then whoever contributed it could be mistakenly seen as too influential. We prefer to follow the long-standing approach of the committee, namely to specify interfaces, not implementations. But at the same time we want at least one implementation available; we hope for many.

FAQ.53: Why weren't the GSL types proposed through Boost?

Because we want to use them immediately, and because they are temporary in that we want to retire them as soon as types that fill the same needs exist in the standard library.

FAQ.54: Has the GSL (guidelines support library) been approved by the ISO C++ standards committee?

No. The GSL exists only to supply a few types and aliases that are not currently in the standard library. If the committee decides on standardized versions (of these or other types that fill the same need) then they can be removed from the GSL.

FAQ.55: If you're using the standard types where available, why is the GSL span<char> different from the string_view in the Library Fundamentals 1 Technical Specification and C++17 Working Paper? Why not just use the committee-approved string_view?

The consensus on the taxonomy of views for the C++ Standard Library was that "view" means "read-only", and "span" means "read/write". If you only need a read-only view of characters that does not need guaranteed bounds-checking and you have C++17, use C++17 std::string_view. Otherwise, if you need a read-write view that does not need guaranteed bounds-checking and you have C++20, use C++20 std::span<char>. Otherwise, use gsl::span<char>.

FAQ.56: Is owner the same as the proposed observer_ptr?

No. owner owns, is an alias, and can be applied to any indirection type. The main intent of observer_ptr is to signify a *non*-owning pointer.

FAQ.57: Is stack_array the same as the standard array?

No. stack_array is guaranteed to be allocated on the stack. Although a std::array contains its storage directly inside itself, the array object can be put anywhere, including the heap.

FAQ.58: Is dyn_array the same as vector or the proposed dynarray?

No. dyn_array is not resizable, and is a safe way to refer to a heap-allocated fixed-size array. Unlike vector, it is intended to replace array-new[]. Unlike the dynarray that has been proposed in the committee, this does not anticipate compiler/language magic to somehow allocate it on the stack when it is a member of an object that is allocated on the stack; it simply refers to a "dynamic" or heap-based array.

FAQ.59: Is Expects the same as assert?

No. It is a placeholder for language support for contract preconditions.

FAQ.60: Is Ensures the same as assert?

No. It is a placeholder for language support for contract postconditions.

Appendix A: Libraries

This section lists recommended libraries, and explicitly recommends a few.

??? Suitable for the general guide? I think not ???

Appendix B: Modernizing code

Ideally, we follow all rules in all code. Realistically, we have to deal with a lot of old code:

- application code written before the guidelines were formulated or known
- libraries written to older/different standards
- code written under "unusual" constraints
- code that we just haven't gotten around to modernizing

If we have a million lines of new code, the idea of "just changing it all at once" is typically unrealistic. Thus, we need a way of gradually modernizing a code base.

Upgrading older code to modern style can be a daunting task. Often, the old code is both a mess (hard to understand) and working correctly (for the current range of uses). Typically, the original programmer is not around and the test cases incomplete. The fact that the code is a mess dramatically increases the effort needed to make any change and the risk of introducing errors. Often, messy old code runs unnecessarily slowly because it requires outdated compilers and cannot take advantage of modern hardware. In many cases, automated "modernizer"-style tool support would be required for major upgrade efforts.

The purpose of modernizing code is to simplify adding new functionality, to ease maintenance, and to increase performance (throughput or latency), and to better utilize modern hardware. Making code "look pretty" or "follow modern style" are not by themselves reasons for change. There are risks implied by every change and costs (including the cost of lost opportunities) implied by having an outdated code base. The cost reductions must outweigh the risks.

But how?

There is no one approach to modernizing code. How best to do it depends on the code, the pressure for updates, the backgrounds of the developers, and the available tool. Here are some (very general) ideas:

- The ideal is "just upgrade everything." That gives the most benefits for the shortest total time. In most circumstances, it is also impossible.
- We could convert a code base module for module, but any rules that affects interfaces (especially ABIs), such as use span, cannot be done on a per-module basis.
- We could convert code "bottom up" starting with the rules we estimate will give the greatest benefits and/or the least trouble in a given code base.
- We could start by focusing on the interfaces, e.g., make sure that no resources are lost and no pointer is misused. This would be a set of changes across the whole code base, but would most likely have huge benefits. Afterwards, code hidden behind those interfaces can be gradually modernized without affecting other code.

Whichever way you choose, please note that the most advantages come with the highest conformance to the guidelines. The guidelines are not a random set of unrelated rules where you can randomly pick and choose with an expectation of success.

We would dearly love to hear about experience and about tools used. Modernization can be much faster, simpler, and safer when supported with analysis tools and even code transformation tools.

Appendix C: Discussion

This section contains follow-up material on rules and sets of rules. In particular, here we present further rationale, longer examples, and discussions of alternatives.

Discussion: Define and initialize member variables in the order of member declaration

Member variables are always initialized in the order they are declared in the class definition, so write them in that order in the constructor initialization list. Writing them in a different order just makes the code confusing because it won't run in the order you see, and that can make it hard to see order-dependent bugs.

```
class Employee {
    string email, first, last;
public:
    Employee(const char* firstName, const char* lastName);
    // ...
};

Employee::Employee(const char* firstName, const char* lastName)
    : first(firstName),
        last(lastName),
        // BAD: first and last not yet constructed
        email(first + "." + last + "@acme.com")
{}
```

In this example, email will be constructed before first and last because it is declared first. That means its constructor will attempt to use first and last too soon -- not just before they are set to the desired values, but before they are constructed at all.

If the class definition and the constructor body are in separate files, the long-distance influence that the order of member variable declarations has over the constructor's correctness will be even harder to spot.

References:

[[Cline99]](#Cline99) §22.03-11, [[Dewhurst03]](#Dewhurst03) §52-53, [[Koenig97]](#Koenig97) §4, [[Lakos96]] (#Lakos96) §10.3.5, [[Meyers97]](#Meyers97) §13, [[Murray93]](#Murray93) §2.1.3, [[Sutter00]](#Sutter00) §47

Discussion: Use a factory function if you need "virtual behavior" during initialization

If your design wants virtual dispatch into a derived class from a base class constructor or destructor for functions like f and g, you need other techniques, such as a post-constructor -- a separate member function the caller must invoke to complete initialization, which can safely call f and g because in member functions virtual calls behave normally. Some techniques for this are shown in the References. Here's a non-exhaustive list of options:

- *Pass the buck*: Just document that user code must call the post-initialization function right after constructing an object.
- *Post-initialize lazily:* Do it during the first call of a member function. A Boolean flag in the base class tells whether or not post-construction has taken place yet.
- *Use virtual base class semantics:* Language rules dictate that the constructor of the most-derived class decides which base constructor will be invoked; you can use that to your advantage. (See [[Taligent94]](#Taligent94).)
- *Use a factory function*: This way, you can easily force a mandatory invocation of a post-constructor function.

Here is an example of the last option:

```
class B {
public:
   B()
        /* · · · */
        f(); // BAD: C.82: Don't call virtual functions in constructors and destructors
        /* · · · */
    }
   virtual void f() = 0;
};
class B {
protected:
   class Token {};
public:
   // constructor needs to be public so that make_shared can access it.
   // protected access level is gained by requiring a Token.
    explicit B(Token) { /* ... */ } // create an imperfectly initialized object
   virtual void f() = 0;
   template<class T>
    static shared_ptr<T> create() // interface for creating shared objects
        auto p = make_shared<T>(typename T::Token{});
```

```
p->post_initialize();
    return p;
}

protected:
    virtual void post_initialize() // called right after construction
        { /* ... */ f(); /* ... */ } // GOOD: virtual dispatch is safe
    }
};
```

This design requires the following discipline:

- Derived classes such as D must not expose a publicly callable constructor. Otherwise, D's users could create D objects that don't invoke post_initialize.
- Allocation is limited to operator new. B can, however, override new (see Items 45 and 46 in SuttAlex05).
- D must define a constructor with the same parameters that B selected. Defining several overloads of create can assuage this problem, however; and the overloads can even be templated on the argument types.

If the requirements above are met, the design guarantees that post_initialize has been called for any fully constructed B-derived object. post_initialize doesn't need to be virtual; it can, however, invoke virtual functions freely.

In summary, no post-construction technique is perfect. The worst techniques dodge the whole issue by simply asking the caller to invoke the post-constructor manually. Even the best require a different syntax for constructing objects (easy to check at compile time) and/or cooperation from derived class authors (impossible to check at compile time).

References: [[Alexandrescu01]](#Alexandrescu01) §3, [[Boost]](#Boost), [[Dewhurst03]](#Dewhurst03) §75, [[Meyers97]](#Meyers97) §46, [[Stroustrup00]](#Stroustrup00) §15.4.3, [[Taligent94]](#Taligent94)

Discussion: Make base class destructors public and virtual, or protected and non-virtual

Should destruction behave virtually? That is, should destruction through a pointer to a base class be allowed? If yes, then base's destructor must be public in order to be callable, and virtual otherwise calling it results in undefined behavior. Otherwise, it should be protected so that only derived classes can invoke it in their own destructors, and non-virtual since it doesn't need to behave virtually.

Example

The common case for a base class is that it's intended to have publicly derived classes, and so calling code is just about sure to use something like a shared_ptr<base>:

In rarer cases, such as policy classes, the class is used as a base class for convenience, not for polymorphic behavior. It is recommended to make those destructors protected and non-virtual:

Note

This simple guideline illustrates a subtle issue and reflects modern uses of inheritance and object-oriented design principles.

For a base class Base, calling code might try to destroy derived objects through pointers to Base, such as when using a unique_ptr<Base>. If Base's destructor is public and non-virtual (the default), it can be accidentally called on a pointer that actually points to a derived object, in which case the behavior of the attempted deletion is undefined. This state of affairs has led older coding standards to impose a blanket requirement that all base class destructors must be virtual. This is overkill (even if it is the common case); instead, the rule should be to make base class destructors virtual if and only if they are public.

To write a base class is to define an abstraction (see Items 35 through 37). Recall that for each member function participating in that abstraction, you need to decide:

- Whether it should behave virtually or not.
- Whether it should be publicly available to all callers using a pointer to Base or else be a hidden internal implementation detail.

As described in Item 39, for a normal member function, the choice is between allowing it to be called via a pointer to Base non-virtually (but possibly with virtual behavior if it invokes virtual functions, such as in the NVI or Template Method patterns), virtually, or not at all. The NVI pattern is a technique to avoid public virtual functions.

Destruction can be viewed as just another operation, albeit with special semantics that make non-virtual calls dangerous or wrong. For a base class destructor, therefore, the choice is between allowing it to be called via a pointer to Base virtually or not at all; "non-virtually" is not an option. Hence, a base class destructor is virtual if it can be called (i.e., is public), and non-virtual otherwise.

Note that the NVI pattern cannot be applied to the destructor because constructors and destructors cannot make deep virtual calls. (See Items 39 and 55.)

Corollary: When writing a base class, always write a destructor explicitly, because the implicitly generated one is public and non-virtual. You can always =default the implementation if the default body is fine and you're just writing the function to give it the proper visibility and virtuality.

Exception

Some component architectures (e.g., COM and CORBA) don't use a standard deletion mechanism, and foster different protocols for object disposal. Follow the local patterns and idioms, and adapt this guideline as appropriate.

Consider also this rare case:

- B is both a base class and a concrete class that can be instantiated by itself, and so the destructor must be public for B objects to be created and destroyed.
- Yet B also has no virtual functions and is not meant to be used polymorphically, and so although the destructor is public it does not need to be virtual.

Then, even though the destructor has to be public, there can be great pressure to not make it virtual because as the first virtual function it would incur all the run-time type overhead when the added functionality should never be needed.

In this rare case, you could make the destructor public and non-virtual but clearly document that further-derived objects must not be used polymorphically as B's. This is what was done with std::unary_function.

In general, however, avoid concrete base classes (see Item 35). For example, unary_function is a bundle-of-typedefs that was never intended to be instantiated standalone. It really makes no sense to give it a public destructor; a better design would be to follow this Item's advice and give it a protected non-virtual destructor.

References: [[SuttAlex05]](#SuttAlex05) Item 50, [[Cargill92]](#Cargill92) pp. 77-79, 207, [[Cline99]](#Cline99) §21.06, 21.12-13, [[Henricson97]](#Henricson97) pp. 110-114, [[Koenig97]](#Koenig97) Chapters 4, 11, [[Meyers97]] (#Meyers97) §14, [[Stroustrup00]](#Stroustrup00) §12.4.2, [[Sutter02]](#Sutter02) §27, [[Sutter04]](#Sutter04) §18

Discussion: Usage of noexcept

Discussion: Destructors, deallocation, and swap must never fail

Never allow an error to be reported from a destructor, a resource deallocation function (e.g., operator delete), or a swap function using throw. It is nearly impossible to write useful code if these operations can fail, and even if something does go wrong it nearly never makes any sense to retry. Specifically, types whose destructors might throw an exception are flatly forbidden from use with the C++ Standard Library. Most destructors are now implicitly noexcept by default.

Example

```
class Nefarious {
public:
    Nefarious() { /* code that could throw */ } // ok
    ~Nefarious() { /* code that could throw */ } // BAD, should not throw
    // ...
};
```

1. Nefarious objects are hard to use safely even as local variables:

2. Classes with Nefarious members or bases are also hard to use safely, because their destructors must invoke Nefarious' destructor, and are similarly poisoned by its bad behavior:

???

3. You can't reliably create global or static Nefarious objects either:

```
static Nefarious n; // oops, any destructor exception can't be caught
```

4. You can't reliably create arrays of Nefarious:

```
void test()
{
    std::array<Nefarious, 10> arr; // this line can std::terminate()
}
```

The behavior of arrays is undefined in the presence of destructors that throw because there is no reasonable rollback behavior that could ever be devised. Just think: What code can the compiler generate for constructing an `arr` where, if the fourth object's constructor throws, the code has to give up and in its cleanup mode tries to call the destructors of the already-constructed objects ... and one or more of those destructors throws? There is no satisfactory answer.

5. You can't use Nefarious objects in standard containers:

```
std::vector<Nefarious> vec(10); // this line can std::terminate()
```

The standard library forbids all destructors used with it from throwing. You can't store `Nefarious` objects in standard containers or use them with any other part of the standard library.

Note

These are key functions that must not fail because they are necessary for the two key operations in transactional programming: to back out work if problems are encountered during processing, and to commit work if no problems occur. If there's no way to safely back out using no-fail operations, then no-fail rollback is impossible to implement. If there's no way to safely commit state changes using a no-fail operation (notably, but not limited to, swap), then no-fail commit is impossible to implement.

Consider the following advice and requirements found in the C++ Standard:

If a destructor called during stack unwinding exits with an exception, terminate is called (15.5.1). So destructors should generally catch exceptions and not let them propagate out of the destructor. --[[C++03]] (#Cplusplus03) §15.2(3)

No destructor operation defined in the C++ Standard Library (including the destructor of any type that is used to instantiate a standard-library template) will throw an exception. --[[C++03]] (#Cplusplus03) \$17.4.4.8(3)

Deallocation functions, including specifically overloaded operator delete and operator delete[], fall into the same category, because they too are used during cleanup in general, and during exception handling in particular, to back out of partial work that needs to be undone. Besides destructors and deallocation functions, common error-safety techniques rely also on swap operations never failing -- in this case, not because they are used to implement a guaranteed rollback, but because they are used to implement a guaranteed commit. For example, here is an idiomatic implementation of operator= for a type T that performs copy construction followed by a call to a no-fail swap:

```
T& T::operator=(const T& other)
{
    auto temp = other;
    swap(temp);
    return *this;
}
```

(See also Item 56. ???)

Fortunately, when releasing a resource, the scope for failure is definitely smaller. If using exceptions as the error reporting mechanism, make sure such functions handle all exceptions and other errors that their internal processing might generate. (For exceptions, simply wrap everything sensitive that your destructor does in a try/catch(...) block.) This is particularly important because a destructor might be called in a crisis situation, such as failure to allocate a system resource (e.g., memory, files, locks, ports, windows, or other system objects).

When using exceptions as your error handling mechanism, always document this behavior by declaring these functions noexcept. (See Item 75.)

References: [[SuttAlex05]](#SuttAlex05) Item 51; [[C++03]](#Cplusplus03) §15.2(3), §17.4.4.8(3), [[Meyers96]] (#Meyers96) §11, [[Stroustrup00]](#Stroustrup00) §14.4.7, §E.2-4, [[Sutter00]](#Sutter00) §8, §16, [[Sutter02]] (#Sutter02) §18-19

Define Copy, move, and destroy consistently

Reason

Note

If you define a copy constructor, you must also define a copy assignment operator.

Note

If you define a move constructor, you must also define a move assignment operator.

Example

```
class X {
public:
    X(const X&) { /* stuff */ }

    // BAD: failed to also define a copy assignment operator

    X(x&&) noexcept { /* stuff */ }

    // BAD: failed to also define a move assignment operator

    // ...
};

X x1;
X x2 = x1; // ok
x2 = x1; // pitfall: either fails to compile, or does something suspicious
```

If you define a destructor, you should not use the compiler-generated copy or move operation; you probably need to define or suppress copy and/or move.

```
class X {
    HANDLE hnd;
    // ...
public:
    ~X() { /* custom stuff, such as closing hnd */ }
    // suspicious: no mention of copying or moving -- what happens to hnd?
};

X x1;
X x2 = x1; // pitfall: either fails to compile, or does something suspicious
x2 = x1; // pitfall: either fails to compile, or does something suspicious
```

If you define copying, and any base or member has a type that defines a move operation, you should also define a move operation.

```
class X {
    string s; // defines more efficient move operations
    // ... other data members ...
public:
    X(const X&) { /* stuff */ }
    X& operator=(const X&) { /* stuff */ }
```

```
// BAD: failed to also define a move construction and move assignment
// (why wasn't the custom "stuff" repeated here?)
};

X test()
{
    X local;
    // ...
    return local; // pitfall: will be inefficient and/or do the wrong thing
}
```

If you define any of the copy constructor, copy assignment operator, or destructor, you probably should define the others.

Note

If you need to define any of these five functions, it means you need it to do more than its default behavior -- and the five are asymmetrically interrelated. Here's how:

- If you write/disable either of the copy constructor or the copy assignment operator, you probably need to do the same for the other: If one does "special" work, probably so should the other because the two functions should have similar effects. (See Item 53, which expands on this point in isolation.)
- If you explicitly write the copying functions, you probably need to write the destructor: If the "special" work in the copy constructor is to allocate or duplicate some resource (e.g., memory, file, socket), you need to deallocate it in the destructor.
- If you explicitly write the destructor, you probably need to explicitly write or disable copying: If you have to write a non-trivial destructor, it's often because you need to manually release a resource that the object held. If so, it is likely that those resources require careful duplication, and then you need to pay attention to the way objects are copied and assigned, or disable copying completely.

In many cases, holding properly encapsulated resources using RAII "owning" objects can eliminate the need to write these operations yourself. (See Item 13.)

Prefer compiler-generated (including =default) special members; only these can be classified as "trivial", and at least one major standard library vendor heavily optimizes for classes having trivial special members. This is likely to become common practice.

Exceptions: When any of the special functions are declared only to make them non-public or virtual, but without special semantics, it doesn't imply that the others are needed. In rare cases, classes that have members of strange types (such as reference members) are an exception because they have peculiar copy semantics. In a class holding a reference, you likely need to write the copy constructor and the assignment operator, but the default destructor already does the right thing. (Note that using a reference member is almost always wrong.)

References: [[SuttAlex05]](#SuttAlex05) Item 52; [[Cline99]](#Cline99) §30.01-14, [[Koenig97]](#Koenig97) §4, [[Stroustrup00]](#Stroustrup00) §5.5, §10.4, [[SuttHysl04b]](#SuttHysl04b)

Resource management rule summary:

- Provide strong resource safety; that is, never leak anything that you think of as a resource
- Never return or throw while holding a resource not owned by a handle
- A "raw" pointer or reference is never a resource handle

- Never let a pointer outlive the object it points to
- Use templates to express containers (and other resource handles)
- Return containers by value (relying on move or copy elision for efficiency)
- If a class is a resource handle, it needs a constructor, a destructor, and copy and/or move operations
- If a class is a container, give it an initializer-list constructor

Discussion: Provide strong resource safety; that is, never leak anything that you think of as a resource

Reason

Prevent leaks. Leaks can lead to performance degradation, mysterious error, system crashes, and security violations.

Alternative formulation: Have every resource represented as an object of some class managing its lifetime.

Example

```
template<class T>
class Vector {
private:
    T* elem; // sz elements on the free store, owned by the class object
    int sz;
    // ...
};
```

This class is a resource handle. It manages the lifetime of the Ts. To do so, Vector must define or delete the set of special operations (constructors, a destructor, etc.).

Example

```
??? "odd" non-memory resource ???
```

Enforcement

The basic technique for preventing leaks is to have every resource owned by a resource handle with a suitable destructor. A checker can find "naked news". Given a list of C-style allocation functions (e.g., fopen()), a checker can also find uses that are not managed by a resource handle. In general, "naked pointers" can be viewed with suspicion, flagged, and/or analyzed. A complete list of resources cannot be generated without human input (the definition of "a resource" is necessarily too general), but a tool can be "parameterized" with a resource list.

Discussion: Never return or throw while holding a resource not owned by a handle

Reason

That would be a leak.

Example

```
void f(int i)
{
    FILE* f = fopen("a file", "r");
    ifstream is { "another file" };
    // ...
    if (i == 0) return;
    // ...
    fclose(f);
}
```

If i == 0 the file handle for a file is leaked. On the other hand, the ifstream for another file will correctly close its file (upon destruction). If you must use an explicit pointer, rather than a resource handle with specific semantics, use a unique_ptr or a shared_ptr with a custom deleter:

```
void f(int i)
{
    unique_ptr<FILE, int(*)(FILE*)> f(fopen("a file", "r"), fclose);
    // ...
    if (i == 0) return;
    // ...
}
```

Better:

```
void f(int i)
{
    ifstream input {"a file"};
    // ...
    if (i == 0) return;
    // ...
}
```

Enforcement

A checker must consider all "naked pointers" suspicious. A checker probably must rely on a human-provided list of resources. For starters, we know about the standard-library containers, string, and smart pointers. The use of span and string_view should help a lot (they are not resource handles).

Discussion: A "raw" pointer or reference is never a resource handle

Reason

To be able to distinguish owners from views.

Note

This is independent of how you "spell" pointer: T*, T&, Ptr<T> and Range<T> are not owners.

Discussion: Never let a pointer outlive the object it points to

Reason

To avoid extremely hard-to-find errors. Dereferencing such a pointer is undefined behavior and could lead to violations of the type system.

Example

```
string* bad() // really bad
{
    vector<string> v = { "This", "will", "cause", "trouble", "!" };
    // leaking a pointer into a destroyed member of a destroyed object (v)
    return &v[0];
}

void use()
{
    string* p = bad();
    vector<int> xx = {7, 8, 9};
    // undefined behavior: x might not be the string "This"
    string x = *p;
    // undefined behavior: we don't know what (if anything) is allocated a location p
    *p = "Evil!";
}
```

The strings of v are destroyed upon exit from bad() and so is v itself. The returned pointer points to unallocated memory on the free store. This memory (pointed into by p) might have been reallocated by the time *p is executed. There might be no string to read and a write through p could easily corrupt objects of unrelated types.

Enforcement

Most compilers already warn about simple cases and have the information to do more. Consider any pointer returned from a function suspect. Use containers, resource handles, and views (e.g., span known not to be resource handles) to lower the number of cases to be examined. For starters, consider every class with a destructor as resource handle.

Discussion: Use templates to express containers (and other resource handles)

Reason

To provide statically type-safe manipulation of elements.

Example

```
template<typename T> class Vector {
    // ...
    T* elem; // point to sz elements of type T
    int sz;
};
```

Discussion: Return containers by value (relying on move or copy elision for efficiency)

Reason

To simplify code and eliminate a need for explicit memory management. To bring an object into a surrounding scope, thereby extending its lifetime.

See also: F.20, the general item about "out" output values

Example

```
vector<int> get_large_vector()
{
    return ...;
}

auto v = get_large_vector(); // return by value is ok, most modern compilers will do copy elision
```

Exception

See the Exceptions in F.20.

Enforcement

Check for pointers and references returned from functions and see if they are assigned to resource handles (e.g., to a unique_ptr).

Discussion: If a class is a resource handle, it needs a constructor, a destructor, and copy and/or move operations

Reason

To provide complete control of the lifetime of the resource. To provide a coherent set of operations on the resource.

Example

```
??? Messing with pointers
```

Note

If all members are resource handles, rely on the default special operations where possible.

```
template<typename T> struct Named {
    string name;
    T value;
};
```

Now Named has a default constructor, a destructor, and efficient copy and move operations, provided T has.

Enforcement

In general, a tool cannot know if a class is a resource handle. However, if a class has some of the default operations, it should have all, and if a class has a member that is a resource handle, it should be considered as resource handle.

Discussion: If a class is a container, give it an initializer-list constructor

Reason

It is common to need an initial set of elements.

Example

```
template<typename T> class Vector {
public:
    Vector(std::initializer_list<T>);
    // ...
};

Vector<string> vs { "Nygaard", "Ritchie" };
```

Enforcement

When is a class a container? ???

Appendix D: Supporting tools

This section contains a list of tools that directly support adoption of the C++ Core Guidelines. This list is not intended to be an exhaustive list of tools that are helpful in writing good C++ code. If a tool is designed specifically to support and links to the C++ Core Guidelines it is a candidate for inclusion.

Tools: Clang-tidy

Clang-tidy has a set of rules that specifically enforce the C++ Core Guidelines. These rules are named in the pattern cppcoreguidelines-*.

Tools: CppCoreCheck

The Microsoft compiler's C++ code analysis contains a set of rules specifically aimed at enforcement of the C++ Core Guidelines.

Glossary

A relatively informal definition of terms used in the guidelines (based off the glossary in Programming: Principles and Practice using C++)

More information on many topics about C++ can be found on the Standard C++ Foundation's site.

- *ABI*: Application Binary Interface, a specification for a specific hardware platform combined with the operating system. Contrast with API.
- *abstract class*: a class that cannot be directly used to create objects; often used to define an interface to derived classes. A class is made abstract by having a pure virtual function or only protected constructors.
- *abstraction*: a description of something that selectively and deliberately ignores (hides) details (e.g., implementation details); selective ignorance.
- *address*: a value that allows us to find an object in a computer's memory.
- *algorithm*: a procedure or formula for solving a problem; a finite series of computational steps to produce a result.
- alias: an alternative way of referring to an object; often a name, pointer, or reference.

- *API*: Application Programming Interface, a set of functions that form the communication between various software components. Contrast with ABI.
- *application*: a program or a collection of programs that is considered an entity by its users.
- *approximation*: something (e.g., a value or a design) that is close to the perfect or ideal (value or design). Often an approximation is a result of trade-offs among ideals.
- *argument*: a value passed to a function or a template, in which it is accessed through a parameter.
- array: a homogeneous sequence of elements, usually numbered, e.g., [0:max).
- *assertion*: a statement inserted into a program to state (assert) that something must always be true at this point in the program.
- base class: a type that is intended to be derived from (e.g., has a non-final virtual function), and objects of the type are intended to be used only indirectly (e.g., by pointer). [In strict terms, "base class" could be defined as "something we derived from" but we are specifying in terms of the class designer's intent.] Typically a base class has one or more virtual functions.
- *bit*: the basic unit of information in a computer. A bit can have the value 0 or the value 1.
- *bug*: an error in a program.
- *byte*: the basic unit of addressing in most computers. Typically, a byte holds 8 bits.
- class: a user-defined type that can contain data members, function members, and member types.
- *code*: a program or a part of a program; ambiguously used for both source code and object code.
- *compiler*: a program that turns source code into object code.
- complexity: a hard-to-precisely-define notion or measure of the difficulty of constructing a solution to a problem
 or of the solution itself. Sometimes complexity is used to (simply) mean an estimate of the number of
 operations needed to execute an algorithm.
- *computation*: the execution of some code, usually taking some input and producing some output.
- *concept*: (1) a notion, and idea; (2) a set of requirements, usually for a template argument.
- *concrete type*: a type that is not a base class, and objects of the type are intended to be used directly (not only by pointer/indirection), its size is known, it can typically be allocated anywhere the programmer wants (e.g., stack or statically).
- *constant*: a value that cannot be changed (in a given scope); not mutable.
- *constructor*: an operation that initializes ("constructs") an object. Typically a constructor establishes an invariant and often acquires resources needed for an object to be used (which are then typically released by a destructor).
- *container*: an object that holds elements (other objects).
- *copy*: an operation that makes two objects have values that compare equal. See also move.
- *correctness*: a program or a piece of a program is correct if it meets its specification. Unfortunately, a specification can be incomplete or inconsistent, or can fail to meet users' reasonable expectations. Thus, to produce acceptable code, we sometimes have to do more than just follow the formal specification.
- *cost*: the expense (e.g., in programmer time, run time, or space) of producing a program or of executing it. Ideally, cost should be a function of complexity.
- customization point: ???
- *data*: values used in a computation.
- debugging: the act of searching for and removing errors from a program; usually far less systematic than testing.
- *declaration*: the specification of a name with its type in a program.
- definition: a declaration of an entity that supplies all information necessary to complete a program using the entity. Simplified definition: a declaration that allocates memory.
- *derived class*: a class derived from one or more base classes.
- *design*: an overall description of how a piece of software should operate to meet its specification.
- destructor: an operation that is implicitly invoked (called) when an object is destroyed (e.g., at the end of a scope). Often, it releases resources.
- encapsulation: protecting something meant to be private (e.g., implementation details) from unauthorized access.

- error: a mismatch between reasonable expectations of program behavior (often expressed as a requirement or a users' guide) and what a program actually does.
- *executable*: a program ready to be run (executed) on a computer.
- feature creep: a tendency to add excess functionality to a program "just in case."
- *file*: a container of permanent information in a computer.
- *floating-point number*: a computer's approximation of a real number, such as 7.93 and 10.78e-3.
- *function*: a named unit of code that can be invoked (called) from different parts of a program; a logical unit of computation.
- *generic programming*: a style of programming focused on the design and efficient implementation of algorithms. A generic algorithm will work for all argument types that meet its requirements. In C++, generic programming typically uses templates.
- *global variable*: technically, a named object in namespace scope.
- handle: a class that allows access to another through a member pointer or reference. See also resource, copy, move.
- *header*: a file containing declarations used to share interfaces between parts of a program.
- hiding: the act of preventing a piece of information from being directly seen or accessed. For example, a name from a nested (inner) scope can prevent that same name from an outer (enclosing) scope from being directly used.
- *ideal*: the perfect version of something we are striving for. Usually we have to make trade-offs and settle for an approximation.
- *implementation*: (1) the act of writing and testing code; (2) the code that implements a program.
- *infinite loop*: a loop where the termination condition never becomes true. See iteration.
- *infinite recursion*: a recursion that doesn't end until the machine runs out of memory to hold the calls. In reality, such recursion is never infinite but is terminated by some hardware error.
- *information hiding*: the act of separating interface and implementation, thus hiding implementation details not meant for the user's attention and providing an abstraction.
- *initialize*: giving an object its first (initial) value.
- *input*: values used by a computation (e.g., function arguments and characters typed on a keyboard).
- *integer*: a whole number, such as 42 and -99.
- *interface*: a declaration or a set of declarations specifying how a piece of code (such as a function or a class) can be called.
- *invariant*: something that must be always true at a given point (or points) of a program; typically used to describe the state (set of values) of an object or the state of a loop before entry into the repeated statement.
- *iteration*: the act of repeatedly executing a piece of code; see recursion.
- *iterator*: an object that identifies an element of a sequence.
- *ISO*: International Organization for Standardization. The C++ language is an ISO standard, ISO/IEC 14882. More information at iso.org.
- *library*: a collection of types, functions, classes, etc. implementing a set of facilities (abstractions) meant to be potentially used as part of more than one program.
- *lifetime*: the time from the initialization of an object until it becomes unusable (goes out of scope, is deleted, or the program terminates).
- *linker*: a program that combines object code files and libraries into an executable program.
- *literal*: a notation that directly specifies a value, such as 12 specifying the integer value "twelve."
- *loop*: a piece of code executed repeatedly; in C++, typically a for-statement or a while-statement.
- move: an operation that transfers a value from one object to another leaving behind a value representing "empty." See also copy.
- *move-only type*: a concrete type that is movable but not copyable.
- *mutable*: changeable; the opposite of immutable, constant, and invariable.
- object: (1) an initialized region of memory of a known type which holds a value of that type; (2) a region of

memory.

- object code: output from a compiler intended as input for a linker (for the linker to produce executable code).
- *object file*: a file containing object code.
- *object-oriented programming*: (OOP) a style of programming focused on the design and use of classes and class hierarchies.
- *operation*: something that can perform some action, such as a function and an operator.
- *output*: values produced by a computation (e.g., a function result or lines of characters written on a screen).
- *overflow*: producing a value that cannot be stored in its intended target.
- overload: defining two functions or operators with the same name but different argument (operand) types.
- *override*: defining a function in a derived class with the same name and argument types as a virtual function in the base class, thus making the function callable through the interface defined by the base class.
- *owner*: an object responsible for releasing a resource.
- *paradigm*: a somewhat pretentious term for design or programming style; often used with the (erroneous) implication that there exists a paradigm that is superior to all others.
- *parameter*: a declaration of an explicit input to a function or a template. When called, a function can access the arguments passed through the names of its parameters.
- *pointer*: (1) a value used to identify a typed object in memory; (2) a variable holding such a value.
- *post-condition*: a condition that must hold upon exit from a piece of code, such as a function or a loop.
- *pre-condition*: a condition that must hold upon entry into a piece of code, such as a function or a loop.
- *program*: code (possibly with associated data) that is sufficiently complete to be executed by a computer.
- *programming*: the art of expressing solutions to problems as code.
- programming language: a language for expressing programs.
- pseudo code: a description of a computation written in an informal notation rather than a programming language.
- *pure virtual function*: a virtual function that must be overridden in a derived class.
- *RAII*: ("Resource Acquisition Is Initialization") a basic technique for resource management based on scopes.
- *range*: a sequence of values that can be described by a start point and an end point. For example, [0:5) means the values 0, 1, 2, 3, and 4.
- *recursion*: the act of a function calling itself; see also iteration.
- reference: (1) a value describing the location of a typed value in memory; (2) a variable holding such a value.
- *regular expression*: a notation for patterns in character strings.
- regular: a semiregular type that is equality-comparable (see std::regular concept). After a copy, the copied object compares equal to the original object. A regular type behaves similarly to built-in types like int and can be compared with ==. In particular, an object of a regular type can be copied and the result of a copy is a separate object that compares equal to the original. See also semiregular type.
- requirement: (1) a description of the desired behavior of a program or part of a program; (2) a description of the assumptions a function or template makes of its arguments.
- *resource*: something that is acquired and must later be released, such as a file handle, a lock, or memory. See also handle, owner.
- rounding: conversion of a value to the mathematically nearest value of a less precise type.
- *RTTI*: Run-Time Type Information. ???
- *scope*: the region of program text (source code) in which a name can be referred to.
- semiregular: a concrete type that is copyable (including movable) and default-constructible (see std::semiregular concept). The result of a copy is an independent object with the same value as the original. A semiregular type behaves roughly like a built-in type like int, but possibly without a == operator. See also regular type.
- *sequence*: elements that can be visited in a linear order.
- *software*: a collection of pieces of code and associated data; often used interchangeably with program.
- source code: code as produced by a programmer and (in principle) readable by other programmers.

- *source file*: a file containing source code.
- *specification*: a description of what a piece of code should do.
- *standard*: an officially agreed upon definition of something, such as a programming language.
- state: a set of values.
- *STL*: the containers, iterators, and algorithms part of the standard library.
- *string*: a sequence of characters.
- style: a set of techniques for programming leading to a consistent use of language features; sometimes used in a
 very restricted sense to refer just to low-level rules for naming and appearance of code.
- *subtype*: derived type; a type that has all the properties of a type and possibly more.
- *supertype*: base type; a type that has a subset of the properties of a type.
- *system*: (1) a program or a set of programs for performing a task on a computer; (2) a shorthand for "operating system", that is, the fundamental execution environment and tools for a computer.
- *TS*: Technical Specification, A Technical Specification addresses work still under technical development, or where it is believed that there will be a future, but not immediate, possibility of agreement on an International Standard. A Technical Specification is published for immediate use, but it also provides a means to obtain feedback. The aim is that it will eventually be transformed and republished as an International Standard.
- *template*: a class or a function parameterized by one or more types or (compile-time) values; the basic C++ language construct supporting generic programming.
- *testing*: a systematic search for errors in a program.
- *trade-off*: the result of balancing several design and implementation criteria.
- truncation: loss of information in a conversion from a type into another that cannot exactly represent the value to be converted.
- type: something that defines a set of possible values and a set of operations for an object.
- uninitialized: the (undefined) state of an object before it is initialized.
- *unit*: (1) a standard measure that gives meaning to a value (e.g., km for a distance); (2) a distinguished (e.g., named) part of a larger whole.
- *use case*: a specific (typically simple) use of a program meant to test its functionality and demonstrate its purpose.
- *value*: a set of bits in memory interpreted according to a type.
- *value type*: a term some people use to mean a regular or semiregular type.
- *variable*: a named object of a given type; contains a value unless uninitialized.
- *virtual function*: a member function that can be overridden in a derived class.
- word: a basic unit of memory in a computer, often the unit used to hold an integer.

To-do: Unclassified proto-rules

This is our to-do list. Eventually, the entries will become rules or parts of rules. Alternatively, we will decide that no change is needed and delete the entry.

- No long-distance friendship
- Should physical design (what's in a file) and large-scale design (libraries, groups of libraries) be addressed?
- Namespaces
- Avoid using directives in the global scope (except for std, and other "fundamental" namespaces (e.g. experimental))

- How granular should namespaces be? All classes/functions designed to work together and released together (as defined in Sutter/Alexandrescu) or something narrower or wider?
- Should there be inline namespaces (à la std::literals::*_literals)?
- Avoid implicit conversions
- Const member functions should be thread safe ... aka, but I don't really change the variable, just assign it a value the first time it's called ... argh
- Always initialize variables, use initialization lists for member variables.
- Anyone writing a public interface which takes or returns void* should have their toes set on fire. That one has been a personal favorite of mine for a number of years.:)
- Use const-ness wherever possible: member functions, variables and (yippee) const_iterators
- Use auto
- (size) vs. {initializers} vs. {Extent{size}}
- Don't overabstract
- Never pass a pointer down the call stack
- falling through a function bottom
- Should there be guidelines to choose between polymorphisms? YES. classic (virtual functions, reference semantics) vs. Sean Parent style (value semantics, type-erased, kind of like std::function) vs. CRTP/static? YES Perhaps even vs. tag dispatch?
- should virtual calls be banned from ctors/dtors in your guidelines? YES. A lot of people ban them, even though I think it's a big strength of C++ that they are ??? -preserving (D disappointed me so much when it went the Java way). WHAT WOULD BE A GOOD EXAMPLE?
- Speaking of lambdas, what would weigh in on the decision between lambdas and (local?) classes in algorithm calls and other callback scenarios?
- And speaking of std::bind, Stephen T. Lavavej criticizes it so much I'm starting to wonder if it is indeed going to fade away in future. Should lambdas be recommended instead?
- What to do with leaks out of temporaries?: p = (s1 + s2).c_str();
- pointer/iterator invalidation leading to dangling pointers:

```
void bad()
{
    int* p = new int[700];
    int* q = &p[7];
    delete p;

    vector<int> v(700);
    int* q2 = &v[7];
    v.resize(900);

    // ... use q and q2 ...
}
```

- LSP
- private inheritance vs/and membership

- avoid static class members variables (race conditions, almost-global variables)
- Use RAII lock guards (lock_guard, unique_lock, shared_lock), never call mutex.lock and mutex.unlock directly (RAII)
- Prefer non-recursive locks (often used to work around bad reasoning, overhead)
- Join your threads! (because of std::terminate in destructor if not joined or detached ... is there a good reason to detach threads?) -- ??? could support library provide a RAII wrapper for std::thread?
- If two or more mutexes must be acquired at the same time, use std::lock (or another deadlock avoidance algorithm?)
- When using a condition_variable, always protect the condition by a mutex (atomic bool whose value is set outside of the mutex is wrong!), and use the same mutex for the condition variable itself.
- Never use atomic_compare_exchange_strong with std::atomic<user-defined-struct> (differences in padding matter, while compare_exchange_weak in a loop converges to stable padding)
- individual shared_future objects are not thread-safe: two threads cannot wait on the same shared_future object (they can wait on copies of a shared_future that refer to the same shared state)
- individual shared_ptr objects are not thread-safe: different threads can call non-const member functions on
 different shared_ptrs that refer to the same shared object, but one thread cannot call a non-const member
 function of a shared_ptr object while another thread accesses that same shared_ptr object (if you need that,
 consider atomic_shared_ptr instead)
- rules for arithmetic

Bibliography

- [Abrahams01]: D. Abrahams. Exception-Safety in Generic Components.
- [Alexandrescu01]: A. Alexandrescu. Modern C++ Design (Addison-Wesley, 2001).
- [C++03]: ISO/IEC 14882:2003(E), Programming Languages C++ (updated ISO and ANSI C++ Standard including the contents of (C++98) plus errata corrections).
- [Cargill92]: T. Cargill. C++ Programming Style (Addison-Wesley, 1992).
- [Cline99]: M. Cline, G. Lomow, and M. Girou. C++ FAQs (2ndEdition) (Addison-Wesley, 1999).
- [Dewhurst03]: S. Dewhurst. C++ Gotchas (Addison-Wesley, 2003).
- [Henricson97]: M. Henricson and E. Nyquist. Industrial Strength C++ (Prentice Hall, 1997).
- [Koenig97]: A. Koenig and B. Moo. Ruminations on C++ (Addison-Wesley, 1997).
- [Lakos96]: J. Lakos. Large-Scale C++ Software Design (Addison-Wesley, 1996).
- [Meyers96]: S. Meyers. More Effective C++ (Addison-Wesley, 1996).
- [Meyers97]: S. Meyers. Effective C++ (2nd Edition) (Addison-Wesley, 1997).
- [Meyers01]: S. Meyers. Effective STL (Addison-Wesley, 2001).
- [Meyers05]: S. Meyers. Effective C++ (3rd Edition) (Addison-Wesley, 2005).
- [Meyers15]: S. Meyers. Effective Modern C++ (O'Reilly, 2015).
- [Murray93]: R. Murray. C++ Strategies and Tactics (Addison-Wesley, 1993).
- [Stroustrup94]: B. Stroustrup. The Design and Evolution of C++ (Addison-Wesley, 1994).
- [Stroustrup00]: B. Stroustrup. The C++ Programming Language (Special 3rdEdition) (Addison-Wesley, 2000).
- [Stroustrup05]: B. Stroustrup. A rationale for semantically enhanced library languages.
- [Stroustrup13]: B. Stroustrup. The C++ Programming Language (4th Edition). Addison Wesley 2013.

- [Stroustrup14]: B. Stroustrup. A Tour of C++. Addison Wesley 2014.
- [Stroustrup15]: B. Stroustrup, Herb Sutter, and G. Dos Reis: A brief introduction to C++'s model for type- and resource-safety.
- [SuttHysl04b]: H. Sutter and J. Hyslop. Collecting Shared Objects (C/C++ Users Journal, 22(8), August 2004).
- [SuttAlex05]: H. Sutter and A. Alexandrescu. C++ Coding Standards. Addison-Wesley 2005.
- [Sutter00]: H. Sutter. Exceptional C++ (Addison-Wesley, 2000).
- [Sutter02]: H. Sutter. More Exceptional C++ (Addison-Wesley, 2002).
- [Sutter04]: H. Sutter. Exceptional C++ Style (Addison-Wesley, 2004).
- [Taligent94]: Taligent's Guide to Designing Programs (Addison-Wesley, 1994).