

Computer Networks Data Link Layer

Paolo Costa costa@cs.vu.nl

 $\verb|http://www.cs.vu.nl/\sim|costa||$

Vrije Universiteit Amsterdam

(Version May 9, 2008)

Paolo Cost

3 - Data Link Layer

1 / 55

Notes

Data Link Layer

- Physical: Describes the transmission of raw bits in terms of mechanical and electrical issues.
- Data Link: Describes how a shared communication channel can be accessed, and how a data frame can be reliably transmitted.
- Network: Describes how routing is to be done. Mostly needed in subnets
- Transport: The hardest one: generally offers connection-oriented as well as connectionless services, and varying degrees of reliability. This layer provides the actual network interface to applications.
- Application: Contains the stuff that users see: e-mail, remote logins, the Web's exchange protocol, etc.

Note


We'll just concentrate on transmission issues. Channel access is discussed in Chapter 4

Paolo Costa

03 - Data Link Layer

ntroduction

Design Issues



- Provide well-defined interface to network layer
- Handle transmission errors
- Regulate flow of data: get sender and receiver in the same pace

Paolo Cost

03 - Data Link Layer

sign Issues

Basic Services

- Network layer passes a number of bits (frame) to the data link layer.
- Data link layer is responsible for transmitting the frame to the destination machine.
- Receiving layer passes received frame to its network layer.

Basic services commonly provided:


- unacknowledged connectionless service (LANs)
- acknowledged connectionless service (Wireless systems).
- acknowledged connection-oriented service (WANs).

Question

Why are we so concerned about error-free frame transmissions?
 Can't the higher layers take care of that?
 It's not mandatory but it may improve efficiency (fine-grained recovery: frames vs. messages)

Notes			
Notes			
Notes			


Transmission



• The actual transmissions follow the path of (b) but it is easier to think in terms of two data link process communicating using a data link protocol (a)

Notes


Routing



- The network layer consists of routing
 - they are connected through point=to-point links
- The router would really its packet to be sent correctly, guaranteed, and in the order it was issued.
- It is up to the data link to make unreliable connections look perfect, or at least, fairly good

Frames

- The physical layer doesn't do much: it just pumps bits from one end to the other.
- But things may go wrong
 - ⇒ the data link layer needs a means to do retransmissions.
- The unit of retransmission is a frame (which is just a fixed number of bits).
- Problem: How can we break up a bit stream into frames?
 - naive solution: counting



(a) Without errors (b) With errors

Frames Byte Stuffing

• Byte stuffing: Mark the beginning and end of a byte frame with two special flag bytes - a special bit sequence (e.g. 01111110). If such bytes appear in the original frame, escape them:

FLAG	Header		Pa	yload fi	eld			Trailer	FLAG
				(a)					
Origi	nal charac	cters			After s	tuffing			
Α	FLAG	В	\rightarrow	А	ESC	FLAG	В		
А	ESC	В	-	А	ESC	ESC	В		
А	ESC	FLAG B		А	ESC	ESC	ESC	FLAG	В
А	ESC	ESC B		А	ESC	ESC	ESC	ESC	В

	_
	_
lotes	
	_
	_
	_
	_
	_
	_
	_
1.1	
lotes	
	_
lotes	
lotes	
Jotes	
lotes	

Frames Notes Bit Stuffing • Byte stuffing is closely tied to the use of 8-bit character ⇒ Bit stuffing: Escape the flag byte (e.g., 01111110) through an additional bit • whenever the sender's data link encounters five consecutive 1s in the data, it automatically stuffs a 0 bit (b) 0110111110<u>1</u>1111011111<u>0</u>10010 Stuffed bits (c) 011011111111111111110010 (a) frame to send (b) frame transmitted over the wire (c) reconstructed frame 03 - Data Link Layer **Error Correction and Detection** Notes • Problem: Suppose something went wrong during frame transmission. How do we actually notice that something's wrong, and can it be corrected by the receiver? Definition: The Hamming distance between two frames \vec{a} and \vec{b} is the number of bits at the same position that differ. Example 10001001 and 10110001 are at Hamming distance 3 1 0 0 0 1 0 0 1 1 0 1 1 0 0 0 1 $\oplus \leftarrow XOR$ 0 0 1 1 1 0 0 0 To detect d errors, you need a distance d + 1 code d-single bit errors cannot change a valid codeword in another • To correct d errors, you need a distance 2d+1 code • this way, even with 2d changes, the original codeword is still closer that any other codeword **Error Detection** Notes • Add a bit to a bit string such that the total number of 1-bits is even (or odd) • e.g., (even parity) 1011010 ⇒ 10110100 • (odd parity) 1011010 ⇒ 10110101 • The distance between two (legal) frames is at least d = 2. any single-bit error produces a code word with the wrong parity • We can detect a single error (i.e., k = 1 and d = 2) • remember that to detect d errors, you need a distance d+1 code **Error Correction** Notes • Consider a code with only four valid codewords: 1 0000000000 2 0000011111 3 1111100000 4 11111111111 • This code has distance 5 • The XOR between any pair of the above codeword gives at least five 1 bits ⇒ it means it can correct double errors ullet remember that to correct d errors, you need a distance 2d+1 code • E.g., if the codeword 000000111 is received, the receiver knows

Paolo Costa 03 - Data Link Layer Error Control 12 / 55

• If, however, a triple error changes 000000000 into 000000111,

that the original must have been 0000011111

the error will not be corrected properly

Error Correction

Lower Bound

- Problem: we want to design a code with m message bits and r check bits to correct all single errors
- Each of the 2^m legal messages has n illegal codewords at
 - these are obtained by systematically change each of the n bits in the n-bit codeword
- ullet Each of the 2^m legal messages require n+1 bit patterns dedicated to it
- The total number of bit pattern is 2ⁿ

 $\Rightarrow (n+1)2^m \leq 2^n$ $(m+r+1)\leq 2^r$

 \bullet Given m, it is possible to have a lower bound to the number r of check bits needed to correct single errors

Notes

Error Correction: Hamming

- The theoretical lower limit can be achieved using a method due to **Hamming** (1950)

 - Enumerate all bits in a codeword starting with bit 1 at the left
 The bits at position 2^k (k ≥ 0) are check bits, the rest (3,5,6,7,...) are filled with the m data bits
 - Every check bit is used as a parity bit for those positions to which it contributes

	b1	b2	b3	b4	b5	b6	b7	b8	b9	b10	b11
1	Х		Х		Х		Х		Х		X
2		X	Х			Х	Х			Х	X
4				Х	Χ	Х	Х				
8								Х	Х	Х	X

- Rewrite every data bit as sums of power of 2
 - \bullet e.g., 7 = 1 + 2 + 4 and 11 = 1 + 2 + 8
- A bit is checked by just those bits occurring in its expansion
 - e.g., bit 11 is checked by bit 1, 2, and 8

03 - Data Link Layer

Error Correction: Hamming

	b1	b2	b3	b4	b5	b6	b7	b8	b9	b10	b11
1	X		Χ		Χ		Χ		Χ		Х
2		X	Χ			Χ	Χ			Χ	Χ
4				X	Х	Χ	Χ				
8								X	Χ	Χ	Χ
	1	0	1	1	1	0	0	1	0	0	1

- Check bits are used to even out the number of 1 bits they contribute to

 - e.g., assume the message is 1100001
 Check bit at position 2, is used to even out the bits for positions 2, 3, 6, 7, 10, and 11
 - \Rightarrow b2 = 0 as the number of 1s is even (b3 and b11)
 - Other check bits are computed in the same way
 - The final codeword is 1011100101

Error Correction: Hamming

- If a check bit at position p is wrong upon receipt, the receiver increments a counter v with p
- The value of v will, in the end, give the position of the wrong bit, which should then be swapped. E.g.:

	b1	b2	b3	b4	b5	b6	b7	b8	b9	b10	b11
1	X		Χ		Χ		Χ		Χ		X
2		X	Χ			Χ	X			X	X
4				X	Χ	Χ	Х				
8								X	Χ	X	X
S:	1	0	1	1	1	0	0	1	0	0	1
R:	1	0	1	1	1	0	0	1	1	0	1
C:	0	0	1	1	1	0	0	0	-1	0	1
F:											

- S: string sent

R:	string received		
	•	check bits: #1 and #8 correcte	ed ⇒ bit #9 is wrong
	(v = 1 + 9)		
F:	final result after correct	tion	

-	
Notes	
Neter	
Notes	
Notes	

Error Correction: Hamming

Hamming codes can only detect single errors

• However, there is a trick to correct burst errors

 A sequence of k codewords are arranged as a matrix, one codeword per row

 Data are transmitted one column at a time

 If a burst error of length k occurs, at most 1 bit per codeword is affected • Hamming code can correct

one error per codeword ⇒ the entire block can be restored

Check bits 00110010000 1001000 1100001 1101101 1101101 10111001000 10111001001 1110101010101 a m m i 1110101010101 1101001 1101110 1100111 0100000 01101010101 01101010101 01111001111 n g 10011000000 1100011 1101111 1100100 1100101 11111000011

10101011111 11111001100 00111000101 Order of bit transmission

Error Control 17 / 55

Error Detection

- Error correcting codes are simply too expensive
 - e.g., for 10,000 bit blocks, 10 check bits are needed
 - ⇒ only use error detection combined with retransmissions
- Cyclic Redundancy Check (CRC), a.k.a. polynomial code, is based upon treating bit strings as polynomials with coefficient of 0 and 1 only
 - ullet a k-bit frame is regarded as the coefficient list for a polynomial with k terms, from x^{k-1} to x^0
 - e.g., a 6-bit block

$$M(x) = m_{k-1}x^{k-1} + \ldots + m_1x^1 + m_0x^0$$

110001
$$\Rightarrow$$
 $1\dot{x}^5 + 1\dot{x}^4 + 0\dot{x}^3 + 0\dot{x}^2 + 0\dot{x}^1 + 1\dot{x}^0$
= $x^5 + x^4 + 1$

• Polynomial arithmetic is done in modulo 2, according to the rule of algebraic field theory

03 - Data Link Layer

Polynomial Arithmetic

Addition and Subtraction

- Since the coefficients are constrained to a single bit, any math operation on CRC polynomials must map the coefficients of the result to either 0 or 1
- Addition

$$(x^3 + x) + (x + 1) = x^3 + 2x + 1 \equiv x^3 + 1$$

• note that 2x becomes zero because addition of coefficient is done modulo 2

$$2x = x + x = (1+1)x = 0x = 0$$

analogous to exclusive OR (XOR)

- Subtraction
 - works like addition (only absolute values are used)

$$(x^4 + x^2 + 1) - (x + 1) = x^4 + x^2 - x \equiv x^4 + x^2 + x$$

Polynomial Arithmetic

Multiplication and Division

- Multiplication
 - It follows the rule of traditional polynomials but, again, addition of coefficient is done module 2

$$(x^2 + x)(x + 1) = x^3 + x^2 + x^2 + 1 = x^3 + 2x^2 + 1 \equiv x^3 + 1$$

- Division
 - we can also divide polynomials mod 2 and find the quotient and remainder

$$\frac{x^3 + x^2 + x}{x+1} = (x^2 + 1) - \frac{1}{x-1}$$

or in other words:

$$(x^3 + x^2 + x) = (x^2 + 1)(x + 1) - 1$$

Notes Notes

Notes

Notes

CRC	Notes
Algorithm	
 Let's go back our problem Sender and receiver agree upon a generator polynomial G(x) both the high- and low-order bits of the generator must be 1 the frame M(x) must be longer than the generator (m > r) 	
 Idea: append a checksum to the end of the frame in such a way that the polynomial obtained is divisible (i.e., no remainder) by G(x) 	
 when the receivers gets the checksummed frame, it tries dividing it by G(x) 	
 if there is a remainder, there has been a transmission error Algorithm 	
 append r zero bits to the low order of the frame now it contains m + r bits and corresponds to x^rM(x) 	
 divide x'M(x) by G(x) subtract (mod 2) the remainder from x'M(x). The result is the checksummed frame T(x) to be transmitted 	
Paolo Costa 03 - Data Link Layer Error Control 21 / 55	
CRC	
Division Example	Notes
Check the input bit above the Check the input bit above the Frame : 1101011011 Generator: 100111 Ge	
leftmost divisor If it is 0, do nothing	
If it is 1, the divisor is XORed into (i.e., subtracted from) the input	
Move the divisor to the right by	
one bit The process is repeated until	
the divisor reaches the right-hand end of the input row	
The left bits are the remainder of the division to be appended One of the division to be appended One of the division to be appended One of the division to be appended	
to the frame	·
Paolo Costa 03 - Data Link Layer Error Control 22 / 55	
CRC	
Decoding	Notes
• If a transmission error occurs, instead of the original polynomial $T(x), T(x) + E(x)$ arrives	
 each 1 bit in E(x) corresponds to a bit that has been inverted if there are k 1 bits in E(x), k single bit errors have occurred E(x) is characterized by an initial 1, a mixture of 0s and 1s, and a final 1 	
• The receiver divided the received frame by $G(x)$, i.e., $[T(x) + E(x)]/G(x)$ and computes the remainder	
 in case of error, the remainder will be E(x)/G(x) If there is a single-bit error, E(x) = xⁱ (being i the position of the 	
wrong bit) • if $G(x)$ contains two or more terms, it will never divide $E(x) \Rightarrow$ all	
single-bit errors will be detected • the simplest error-detection system, the parity bit, is in fact a trivial	
CRC: it uses the two-bit-long divisor 11 Paolo Costa 03 - Data Link Layer Error Control 23 / 55	
CRC	Notes
Burst Error	Notes
 By carefully choosing G(x), burst errors can be correctly detected a burst error is a contiguous sequence of bits, containing wrong bits 	
• It can be shown, that a polynomial code with r check bits, will	
detect all bursts errors of length $\leq r$ • If the burst length is $r+1$, the probability of accepting an incorrect	
frame is $\frac{1}{2^{r-1}}$ • It can also be shown that for bursts longer than $r+1$ bit, such	
probability becomes $\frac{1}{2^r}$, assuming that all bit patterns are equally likely (not always true)	
probability becomes ½, assuming that all bit patterns are equally likely (not always true) ■ Certain polynomial have become standards ■ e.g., the one used in IEEE 802 (Wi-Fi) is:	

odd number of bits



- CRC is not used by the data link layer but also by applications to check the correctness of a given file
- e.g., WinZip



Paolo Cost

03 - Data Link Lave

rror Control

25 / 55

Notes

Data Link Layer Protocols

- Concentrated on design aspects and error control
 - frame size (stuffing)
 - error correction (Hamming Code)
 - error detection (CRC)
- Now: basic protocols and real-world examples

Some basic assumptions:

- We have a machine A that wants to send data to machine B
- There is always enough data for A to send
- There is a well-defined interface to the network layer, and to the physical layer
 - void from_network_layer(packet *)
 void to_network_layer(packet *)
 void from_physical_layer(packet *)
 void to_physical_layer(packet *)
- The receiver generally waits for an event to happen by calling
 - void wait_for_event(event_type *event)

Paolo Costa

03 - Data Link Layer

Basic Protocols

26 / 55

Notes

Unrestricted Simplex Protocol

```
typedef enum (false, true) boolean;
typedef unsigned int seq.nr;
typedef struct (unsigned char data[MAX_PRT];) packet;
typedef struct {
    typedef struct {
        frame_kind kind; /* what kind of a frame is it? */
        seq_nr seq; /* sequence number */
        seq_nr ack; /* acknowledgment number */
        packet info; /* the network layer packet */
    } frame;

typedef enum (false, true) {
        if reme_kind kind; /* what kind of a frame is it? */
        seq_nr ack; /* acknowledgment number */
        packet info; /* the network layer packet */
    } frame;

typedef enum (frame_arrival) event_type;

typedef enum (frame_arrival) event_type;

typedef enum (false, true) {
        typedef enum (false, true) {
            true frame arrival) event_type;

        void sender!(void) {
            frame s; packet buffer;
            to_physical_layer(sb);
        }
    }

void receiver!(void) {
    frame r; event_type event;
    wait_for_event(sevent);
    from_physical_layer(sr);
        to_network_layer(sr.info);
    }
}

longth for the first for the fir
```

Unrestricted Simplex Protocol

Question

- What are some of the underlying assumptions here? How does the flow control manifest itself?
 Underlying assumptions are error-free transmission, and sender-receiver are in pace.
- Issue: Fast senders would make receivers collapse

Question

- Would a simple delay on sender's side fix the problem?
 Not really! It's hard to predict when receiver's congestion may
 occur.
- Assuming always the worst-case behavior would be highly inefficient

osta	03 - Data Link Laver	

Notes			
NOIGS			

Notes

Simplex Stop-and-Wait

- Here the receiver provide the feedback to the sender
 - it sends a little dummy packet (acknowledgment) back to the sender
- After having sent a frame, the sender is required to wait for the ack

Paolo Cost

03 - Data Link Layer

Basic Protocols 2

29 / 55

Notes

Simplex Protocol for Noisy Channel

Question

- What are the assumptions in this case? We are assuming only error-free transmission.
- Ok, so assume that damaged frames can be detected

Question

 Idea: send the ack only upon correct receipt! Works? No, because also the ack can be lost.

Question

- Second idea: let the sender use a timer by which it simply retransmits unacknowledged frames after some time! Works? No again! Because the data link layer cannot detect duplicate transmissions.
- Let's use sequence numbers!
 - Problem: sequence number cannot go on for ever and they wast space
 - Solution: no worries, we need just two (0 & 1)
 Paolo Costa
 03 Data Link Layer

Basic Proto

ic Protocols

Simplex Protocol for Noisy Channel

Sende

- next_frame_to_send indicates which is the last message sent
- A timer is started after sending a message
- Only if the correct ack is received, the next message is sent

Paolo Costa

03 - Data Link Laver

sic Protocols

Simplex Protocol for Noisy Channel

Receive

- frame_expected enables filtering out duplicate
- Its value is increased each time a frame is delivered to the network layer
 - ⇒ only two values (0 and 1) are needed

1 2	<pre>void receiver3(void) {</pre>
3	<pre>seq_nr frame_expected; frame r, s; event_type event;</pre>
5 6 7	<pre>frame_expected = 0; while (true) {</pre>
8 9 10	<pre>wait_for_event(&event); if(event == frame_arrival) {</pre>
11 12 13	<pre>from_physical_layer(&r); if (r.seq == frame_expected) {</pre>
14 15 16	<pre>to_network_layer(&r.info); inc(frame_expected); }</pre>
17 18 19	<pre>s.ack = 1 - frame_expected; to_physical_layer(6s); }</pre>
20 21	}

aolo Costa 03 - Data Link Layer

Link Layer Basic

Notes Notes Notes

From Simplex to Duplex

- Problem: We want to allow symmetric frame transmission between two communicating parties, rather than transmission in
 - don't waste channels, so use the same channel for duplex communication.
- Solution: Just transmit frames, but distinguish between data, acknowledgments (acks), and possibly negative acks (nacks) in the frame's type field.
- Idea: If the other party is going to send data as well, it might as well send acknowledgments along with its data frames
 - ⇒ piggybacking.

What's good and bad about piggybacking? Good: save bandwidth

Bad: poor performance with irregular transmission rate.

03 - Data Link Layer

Sliding Windows


- Principle: Rather than just sending a single frame at a time, permit the sender to transmit a set of frames, called the sending window.
 - a frame is removed from the sending window iff it has been acknowledged.
 - the receiver has a receiving window containing frames it is permitted to receive.
- A damaged frame is kept in the receiving window until a correct version is received. Also, frame N is kept in the window until frame N-1 has been received.
 - if both window sizes equal one, we are dealing with the stop-and-wait protocols

Question

• Is there a relationship between window size, transmission rate, and propagation delay? If the propagation delay is high and the window size is small, transmission rate decreases dramatically because the sender while waiting for acks cannot send new messages

03 - Data Link Layer


Window Size & Sequence Number



- (a) Initially (c) After receiving frame #1.
- (b) After sending frame #1.
 (d) After receiving ack for frame #1

• How would you interpret the shaded areas? Shaded area is to-be-acknowledged (at sender) and to-be-received next (at receiver).


1-Bit Sliding Window



- tells which frame the sender is trying to send
- tells which frames the receiver is expecting
- If the received frame is the one expected, the frame is passed to the network layer
- If the received ack is the one expected, the next frame is sent

Notes		
Notes		
Notes		
Notes		

1-Bit Sliding Window Simultaneous Transmissions



The notation is (seq, ack, packet number). * means: passed to network layer

- All things go well, but behavior is a bit strange when A and B transmit simultaneously.
- We are transmitting more than once, just because the two senders are more or less out of sync.

Paolo Costa	03 - Data Link Layer	Sliding Wi

Error Control

Problem: What should the receiver do if a frame is damaged?

Go back n

Simply request retransmission of all frames starting from frame #N. If any other frames had been received in the meantime (and stored in the receiver's window), they'll just be ignored


Selective Repeat

Request just retransmission of the damaged frame, and wait until it comes in before delivering any frames after that

Paolo Costa 03 - Data Link Layer Sliding Window Protocols 38 / 55

Error Control

Example



(a) Go back n (b) Selective Repeat.

Error Control

Pros & Cons

- Go-back-N is really simple: the sender keeps a frame in its window until it is acknowledged.
 - if the window is full, the network layer is not allowed to submit new packets.
 - the receiver hardly needs to keep an account on what happens: if a frame is damaged, its successors in the receive window are ignored.
 - it is equivalent to a receive window of size 1
- Selective repeat seems to do better because frames aren't discarded, but the administration is much harder
 - it also requires large amounts of memory if the window is large
- Trade-off between bandwidth and data link layer buffer space

Notes		
Notes		
Notes		
Notes		

Costa 03 - Data Link Layer Sliding Window Protocols 40

Go-back-n (1/2)

```
#define MAX_SEQ 7 /* should be 2^n - 1 */
typedef enum (frame_arrival, cksum_err,
    timeout, network_layer_ready) event_type;
#include "protocol.h"
 static boolean between(seq_nr a, seq_nr b, seq_nr c) {
  /* Return TRUE iff a <= b < c (cyclic) */</pre>
static void send_data(
seq_nr frame_nr, seq_nr frame_expected, packet buffer[]) {
    frame s;
    s.info = buffer[frame_nr];    s.seq = frame_nr;
    s.ack = (frame_expected + MAX_SEQ) % (MAX_SEQ + 1);
    to_physical_layer(sa);    start_timer(frame_nr);
 void protocol5(void) {
   seq_nr next_frame_to_send, ack_expected, frame_expected;
   frame r;
   packet buffer(MAX_SEQ + 1);
   seq_nr nbuffered, i;
       enable_network_layer();
ack_expected = 0; next_frame_to_send = 0; frame_expected = 0;
      nbuffered = 0;
```

• enable_network_layer prevents network layer to input more frames when there are ${\tt MAX_SEQ}$ unacknowledged frames

Go-back-n (2/2)

```
while (true) {
                                                                          see Intwork_layer(shuffer(next_frame_to_send));
nbuffered = nbuffered + 1;
send_data(next_frame_to_send, frame_expected, buffer);
inc(next_frame_to_send).
                                                           sen_uasa (max_tamm_to_send);
break;
inc(next_frame_to_send);
break;
from_physical_layer(r);
if (r.seq = frame_expected) {
    to_network_layer(sr.info);
    inc(frame_expected);
    inc(frame_expected);
    while (between(ack_expected); r.ack, next_frame_to_send)) {
        nbuffered = nbuffered - l;
        stop_timer(ack_expected);
        inc(ack_expected);
        inc(ack_expected);
        break;
    case (xsum_err; break; /* just ignore bad frames */
    case (xsum_err; break; /* just ignore bad frames */
    case (xsum_err; break; /* just ignore bad frames */
        case (xsum_err; break; /* just ignore bad frames */
        case (xsum_err; break; /* just ignore bad frames */
        case (xsum_err; break; /* rouble; retransmit outstanding frames */
        next_frame_to_send, ack_expected, buffer);
        inc(next_frame_to_send, frame_expected, buffer);
        inc(next_frame_to_send);
}
8
9
10
11
12
13
14
15
16
17
18
19
20
21
22
23
24
25
26
27
28
29
30
31
                                                                   03 - Data Link Layer
```

Go-back-n

- An ack for frame n, automatically acknowledges also frames n-1,
- Note that a maximum of MAX_SEQ frames and not MAX_SEQ + 1 frames may be outstanding
 - \rightarrow packet buffer[MAX_SEQ+1]
 - → if nbuffered < MAX SEO
 - The reason is the following:

 - The sender sends frames 0 through 7
 An ack for frame 7 comes back to the sender
 The sender sends other eight frames with sequence number 0
 - Now another piggybacked ack for frame 7 comes in
- Problem: Did all eight frames belonging to the second batch arrive correctly or did all get lost?
 - the sender has no way to detect it
- Solution Restrict the maximum number of outstanding frames to MAX_SEQ

03 - Data Link Layer

Selective Repeat

- Go-back-n works well if errors are rare, but if the line is poor, it wastes a lot of bandwidth
- An alternative strategy is to allow receiver to accept and buffer the frames following a damaged or lost one
 - both sender and receiver maintain a window larger than 1
 - whenever a frame arrives, its sequence number is checked by the function between to see if it falls within the window
 - however, it must be kept within the data link layer and not passed to the network layer until all lower numbered frames are received

Notes			
Notes			
Notes			
Notes			

Selective Repeat (1/3)

```
static boolean between(seq_nr a, seq_nr b, seq_nr c) {...}

static void send_frame(frame_kind fk, seq_nr frame_nr,
seq_nr frame_expected, packet buffer[]){

frame s; s.kind = fk;

if (fk == data) s.info = buffer[frame_nr % NR_BUFS];
s.seq = frame_nr;
s.ack = (frame_expected + MAX_SEQ) % (MAX_SEQ + 1);

if (fk == nak) no_nak = false;
to_physical_layer(fs);

if (fk == data) start_timer(frame_nr % NR_BUFS);
stop_ack_timer();
{
    void protocol6(void) {
        seq_nr ack_expected, next_frame_to_send, frame_expected;
        seq_nr nbuffered, too_far; event_type event;int i; frame r;
        packet out_buf[NR_BUFS], im_buf[NR_BUFS];
        boolean arrived[NR_BUFS];
                                 enable_network_layer();
ack_expected = 0; next_frame_to_send = 0; frame_expected = 0;
too_far = Ns_BUBS; nbuffered = 0;
for (i = 0; i < NN_BUBS; i++) arrived[i] = false;
while (true) {</pre>
                                          wait_for_event(&event);
switch(event) {
                                               case network_layer_ready:
nbuffered = nbuffered + 1;
```

Example: Selective Repeat (2/3)

```
1 2 3 4 5 6 7 8 9 10 111 12 13 14 15 16 17 18 22 23 24 22 25 26 27 28 29 31
                       }

if ((r.kind -= nak) &&

if between (ack_expected, (r.ack+1) & (MAX_SEQ+1)

mext_frame_to_send))

send_frame(data, (r.ack+1) & (MAX_SEQ + 1),

frame_expected,out_buf);
                          while (between(ack_expected, r.ack, next
nbuffered = nbuffered - 1;
stop_timer(ack_expected % NR_BUFS);
inc(ack_expected);
}
```


03 - Data Link Layer

Example: Selective Repeat (3/3)

```
case cksum_err:
   if (no_nak) send_frame(nak, 0, frame_expected, out_buf);
   break;
 rase timeout:
    send_frame(data, oldest_frame, frame_expected, out_buf);
case ack_timeout:
    send_frame(ack,0,frame_expected, out_buf);
    (nbuffered < NR_BUFS) enable_network_layer();
se disable_network_layer();</pre>
```

Selective Repeat

- Frames need not be received in order,
 - we may have an undamaged frame N, while still waiting for an undamaged version of N-1.
- If the receiver delivers all frames in its window just after sending an ack for the entire window, we may have a serious problem:



- Solution: we must avoid overlapping send and receive windows
 - ⇒ the highest sequence number must be at least twice the window

03 - Data Link Layer

Data Link Protocols

http://www.csi.uottawa.ca/~elsaddik/abedweb/applets/ Applets/Sliding_Window/sliding-window/index.html

03 - Data Link Layer Sliding Window Protocols 49 / 55

Notes

Notes

Data Link Layer Protocols

Now let's take a look how point-to-point connections are supported in, for example, the Internet.

Recall:

- The data link layer is responsible for transmitting frames from sender to receiver.
- It can use only the physical layer, which supports only transmission of a bit at a time.
- The DLL has to take into account that transmission errors may
 - \Rightarrow er
- The D operat
 - \Rightarrow flo

High-Lev

• HDLC conne

- HDLC
- The co

Question

What multip

Internet

This is a prov

- We'd li ADSL)
 - th ac
- Issues
 - hc
 - hc

LE has to take this account that transmission offers may	
ror control (ACKs, NACKs, checksums, etc.) LL has to take into account that sender and receiver may e at different speeds	
ow control (windows, frame numbers, etc.)	
Costa 03 - Data Link Layer Examples 50 / 55	
vel Data Link Control	Notes
: A pretty old, but widely used protocol for point-to-point ctions. Is bit-oriented.	
Bits 8 8 8 ≥ 0 16 8 0 11 1 1 1 1 1 0 Address Control Data Checksum 0 1 1 1 1 1 1 1 0	
uses a sliding window protocol with 3-bit sequencing ontrol field is used to distinguish different kinds of frames ontains sequence numbers, acks, nacks, etc.	
do we need the address field for? Useful on line with le terminals	
Costa 03 - Data Link Layer Examples 51 / 55	
Point-to-Point Connections	Notes
what may happen when you have an Internet connection to ider:	
User's home Internet provider's office Moderns Client process using CPUP Del-up stephone line TCPRP connection using PPP Router Routing process	
ike to use the Internet protocol stack at our home (e.g.,	
e bottom line is that we'll have to transfer IP (network) packets cross our telephone line	
ow can we embed IP packets into frames ? ow can we unpacked at the other end ?	
03 - Data Link Layer Examples 52 / 55	

PPP: Point-to-Point Protocol

- PPP is the data link protocol for point-to-point connections with respect to the Internet (home-ISP and router-to-router):
 - Proper framing, i.e. the start and end of a frame can be
 - unambiguously detected.

 A separate protocol for controlling the line (setup, testing, negotiating options, and tear-down) (LCP)
 - Supports many different network layer protocols, not just IP.
 - No need for fixed network addresses.

The default frame:



Protocol Checksum

LCP / NCP / IP / (usually 2 bytes)

Control Payload

no seg. number (no reliable transmission) (up to a negotiated maximum)

Notes

PPP

Address


Connection Setup

Suppose you want to set up a true Internet connection to your provider.

- Set up a physical connection through your modem
- 2 Your PC starts sending a number of Link Control Packets (LCP) to negotiate the kind of PPP connection you want.
 - the maximum payload size in data frames
 - do authentication (e.g. ask for a password)
 - monitor the quality of the link (e.g. how many frames didn't come through).
 - compress headers (useful for slow links between fast computers)
- Then, we negotiate network layer stuff, like getting an IP address that the provider's router can use to forward packets to you.

PPP

Example



 $\bullet\,$ If an IP address is dynamically assigned, who does the assignment ? The provider

 If an IP address is dynamically assigned, Can someone else ever send you data (they don't know your address, do they?) We need to contact them first (our address is included in the reques

03 - Data Link Layer

Notes			
Notes			
Notes			