



About Keras

Getting started

Developer guides

Keras API reference

Models API

Layers API

Callbacks API

Optimizers

Metrics

Losses

Data loading

Built-in small datasets

Keras Applications

Mixed precision

Utilities

KerasTuner

Code examples

Why choose Keras?

Community & governance

Contributing to Keras

KerasTuner

Search Keras documentation...

» Keras API reference / Layers API / Convolution layers / Conv2D layer

Conv2D layer

Conv2D class

```
tf.keras.layers.Conv2D(
   filters,
   kernel_size,
   strides=(1, 1),
   padding="valid",
   data_format=None,
   dilation_rate=(1, 1),
   groups=1,
   activation=None,
   use_bias=True,
   kernel_initializer="glorot_uniform",
   bias_initializer="zeros",
   kernel_regularizer=None,
   bias_regularizer=None,
   activity_regularizer=None,
   kernel_constraint=None,
   bias_constraint=None,
    *kwargs
```

2D convolution layer (e.g. spatial convolution over images).

This layer creates a convolution kernel that is convolved with the layer input to produce a tensor of outputs. If use_bias is True, a bias vector is created and added to the outputs. Finally, if activation is not None, it is applied to the outputs as well.

When using this layer as the first layer in a model, provide the keyword argument input_shape (tuple of integers or None, does not include the sample axis), e.g. input_shape=(128, 128, 3) for 128x128 RGB pictures in data format="channels last". You can use None when a dimension has variable size.

Examples

```
# The inputs are 28x28 RGB images with `channels last` and the batch
>> # size is 4.
>>> input_shape = (4, 28, 28, 3)
>>> x = tf.random.normal(input_shape)
>> y = tf.keras.layers.Conv2D(
.. 2, 3, activation='relu', input_shape=input_shape[1:])(x)
>>> print(y.shape)
(4, 26, 26, 2)
```

```
>> # With `dilation_rate` as 2.
>>> input_shape = (4, 28, 28, 3)
>>> x = tf.random.normal(input_shape)
>>> y = tf.keras.layers.Conv2D(
.. 2, 3, activation='relu', dilation_rate=2, input_shape=input_shape[1:])(x)
   print(y.shape)
(4, 24, 24, 2)
```

```
>>> # With `padding` as "same".
>>> input_shape = (4, 28, 28, 3)
>>> x = tf.random.normal(input_shape)
>>> y = tf.keras.layers.Conv2D(
... 2, 3, activation='relu', padding="same", input_shape=input_shape[1:])(x)
>>> print(y.shape)
(4, 28, 28, 2)
```

```
>>> # With extended batch shape [4, 7]:
>>> input_shape = (4, 7, 28, 28, 3)
>>> x = tf.random.normal(input_shape)
>>> y = tf.keras.layers.Conv2D(
... 2, 3, activation='relu', input_shape=input_shape[2:])(x)
>>> print(y.shape)
(4, 7, 26, 26, 2)
```

Arguments

- **filters**: Integer, the dimensionality of the output space (i.e. the number of output filters in the convolution).
- **kernel_size**: An integer or tuple/list of 2 integers, specifying the height and width of the 2D convolution window. Can be a single integer to specify the same value for all spatial dimensions.
- **strides**: An integer or tuple/list of 2 integers, specifying the strides of the convolution along the height and width. Can be a single integer to specify the same value for all spatial dimensions. Specifying any stride value != 1 is incompatible with specifying any dilation_rate value != 1.
- **padding**: one of "valid" or "same" (case-insensitive). "valid" means no padding. "same" results in padding with zeros evenly to the left/right or up/down of the input. When padding="same" and strides=1, the output has the same size as the input.
- data_format: A string, one of channels_last (default) or channels_first. The ordering of the dimensions in the inputs. channels_last corresponds to inputs with shape (batch_size, height, width, channels) While channels_first corresponds to inputs with shape (batch_size, channels, height, width). It defaults to the image_data_format value found in your Keras config file at ~/.keras/keras.json. If you never set it, then it will be channels_last.
- dilation_rate: an integer or tuple/list of 2 integers, specifying the dilation rate to use for dilated convolution. Can be a single integer to specify the same value for all spatial dimensions.
 Currently, specifying any dilation_rate value != 1 is incompatible with specifying any stride value != 1.
- **groups**: A positive integer specifying the number of groups in which the input is split along the channel axis. Each group is convolved separately with filters / groups filters. The output is the concatenation of all the groups results along the channel axis. Input channels and filters must both be divisible by groups.
- **activation**: Activation function to use. If you don't specify anything, no activation is applied (see keras.activations).
- **use_bias**: Boolean, whether the layer uses a bias vector.
- **kernel_initializer**: Initializer for the **kernel** weights matrix (see **keras.initializers**). Defaults to 'glorot uniform'.
- bias_initializer: Initializer for the bias vector (see keras.initializers). Defaults to 'zeros'.
- **kernel_regularizer**: Regularizer function applied to the **kernel** weights matrix (see **keras.regularizers**).
- bias_regularizer: Regularizer function applied to the bias vector (see keras.regularizers).
- activity_regularizer: Regularizer function applied to the output of the layer (its "activation") (see keras.regularizers).
- **kernel_constraint**: Constraint function applied to the kernel matrix (see keras.constraints).
- bias_constraint: Constraint function applied to the bias vector (see keras.constraints).

Input shape

4+D tensor with shape: batch_shape + (channels, rows, cols) if data_format='channels_first' or 4+D tensor with shape: batch_shape + (rows, cols, channels) if data_format='channels_last'.

Output shape

4+D tensor with shape: batch_shape + (filters, new_rows, new_cols) if data_format='channels_first' or 4+D tensor with shape: batch_shape + (new_rows, new_cols, filters) if data_format='channels_last'. rows and cols values might have changed due to padding.

Returns

A tensor of rank 4+ representing activation(conv2d(inputs, kernel) + bias).

Raises

- ValueError: if padding is "causal".
- ValueError: when both strides > 1 and dilation_rate > 1.