

Sperto IN / OUT

What is sent, when, and what was checked

Two pages · 28 September 2026

Only one Sperto API is called: `api_record_device_usage.php`. It is called twice per presentation — IN when it starts, OUT when it ends. The `api_key` stays on our server; the browser never sees it.

```
POST https://net4hgc.sperto.co.in/_api/api_record_device_usage.php
Content-Type: application/json
```

1 Login — Sales ID

Staff type their Sales ID (any ID, e.g. PDPL0349). Nothing is sent to Sperto here.
The Sales ID is kept in the signed session cookie and used as `sales_manager_login` later.



2 Lead ID + device -> IN (the check)

After the Lead ID is entered and a device is picked, the server sends IN:
`{ api_key, device_id, lead_id, sales_manager_login, type: "IN",
page_url: "https://net4hgc.sperto.co.in" }`
Sperto answers success -> the presentation opens.
Sperto says error (wrong Sales ID / Lead ID) or is unreachable -> it does not open;
Sperto's message is shown on the same screen and the staff member can retry.



3 Presentation

A clock runs per project opened (Elena, Alibaug, ...). Nothing is sent meanwhile.



4 Logout -> OUT

Sent once, with the same `lead_id` / `device_id` / `sales_manager_login` and type "OUT".
`page_url` carries the minutes per project: `[ { "Elena": 3 }, { "Alibaug": 4.5 } ]`
Also sent on idle timeout / force-logout. Not sent if no presentation was started.

What was checked

The real server was run against a stand-in Sperto that accepts only certain Sales IDs and Lead IDs, so no test entries were written into the client's CRM.

	Check	Result
PASS	Login with Sales ID	Works; no call to Sperto
PASS	IN, correct Sales ID + Lead ID	Sperto success -> presentation allowed
PASS	IN request body	Exactly the 6 fields, in Sperto's format
PASS	IN, wrong Lead ID	Blocked, Sperto's message shown
PASS	IN, wrong Sales ID	Blocked, Sperto's message shown
PASS	Other Sales IDs / Lead IDs	Whatever is typed is sent — nothing hardcoded
PASS	IN without Lead ID	Refused before calling Sperto
PASS	IN without login	Refused (401)
PASS	Sperto down	Blocked with "could not reach Sperto"
PASS	OUT	Times in page_url; only the 6 fields
PASS	OUT sent once	Even if logout runs twice
PASS	API key	Never in the browser, masked (***) in logs
PASS	Unit tests / lint / build	60 of 60 tests, 0 lint errors, build OK

Where to see it live

Every call is logged by the server — the terminal locally, Vercel's Logs tab in production:

```
[device-usage] -> POST .../api_record_device_usage.php {"api_key":"****", ...}
[device-usage] <- HTTP 200 {"status":"success", ...}
```

Still open with the client

- device_id is a placeholder: Tab 1, TV 2, Kiosk 3, Laptop 4 — needs Sperto's real IDs.
- "Continue without a Lead ID" sends a WALKIN-... lead_id, which Sperto will likely reject.
- A wrong Sales ID is only caught at the IN step, not at login — Sperto gives no separate check.

Files: [server/routes/device-usage.js](#), [server/lib/sperto-device-usage.js](#), [src/lib/session.js](#), [src/components/SessionStart.jsx](#).