

Moving Therefore™

www.therefore.net
© 2024 Therefore Corporation



All rights reserved. No parts of this work may be reproduced in any form or by any means - graphic, electronic, or mechanical, including photocopying, recording, taping, or information storage and retrieval systems - without the written permission of the publisher.

Any 3rd Party Products that are referred to or shown in this document, are the property of, and may be either trademarks and/or registered trademarks of the respective owners in the USA and/or other countries. The publisher and the author make no claim to these products, trademarks or registered trademarks.

While care has been taken in the preparation of this document, the publisher and the author assume no responsibility for errors or omissions, or for damages resulting from the use of information contained in this document.

VERSION: 2024 - 01

Table of Contents

1. Introduction	4
2. Moving the Therefore™ Server.....	5
3. Moving a Primary or Backup Storage.....	6
4. Moving the Therefore™ Database	7

1. Introduction

It is sometimes necessary to move different components within a Therefore™ system. e.g. the Therefore™ Server, or Primary Storage etc. The purpose of this document is to give guidelines on how to do this.

2. Moving the Therefore™ Server

To move the Therefore™ Server perform the following steps:

1. Contact support@therefore.net to reset the license (You will need the CustomerID).
2. Stop and disable all Therefore™ services on the old server (services.msc).
3. If the Therefore™ database also needs to be moved, make a full backup and restore it on the new server.
4. Open the Therefore database and navigate to the TheServer table. Make sure the computer name and domain name are correct (Computer and Domain columns, you can leave the rest as it is). If the domain has also changed then go to the TheUser table and change the user accounts to reflect the new domain (Domain column).
5. Install Therefore™ Server on the new server.
6. Copy the contents of the Buffer, Cache, Preview, Full-Text folders from the old server to the new one.
7. Run the Configuration Wizard on the new server and make sure use either “Activate” or “Import License” during the activation (do not use Connect to DB because this will use the old license info and you’ll get an error).
8. Make sure the service accounts are the same as before.

3. Moving a Primary or Backup Storage

To move the Primary or Backup storage perform the following steps:

1. Copy the complete folder to the new location
2. Open the Therefore™ Solution Designer and under the Storage object change the path so it points to a new device
3. Restart the Therefore™ Server Service
4. Test the new location by saving a document and checking that it is successfully migrated

4. Moving the Therefore™ Database

For moving the Therefore™ database in single server environment perform the following steps:

1. Open Therefore™ Solution Designer and go to Settings and then Database. Enter in the new path and if needed the credentials to the database
2. Stop and disable Therefore™ Server Service
3. Make sure that the account that is running the Therefore™ Server Service has permissions to access new database
4. Back up the Therefore™ database and restore it on the new server
5. Start Therefore™ Server Service